typesense

⌘ K

Install Typesense

Copy Markdown

Here are a couple of available options to install and run Typesense.

Option 1: Typesense Cloud

The easiest way to run Typesense is using our managed Cloud service called Typesense Cloud .

- Sign-in with GitHub
- Pick a configuration and click on Launch. You'll have a ready-to-use cluster in a few minutes.
- Then click on "Generate API Key", which will give you the hostnames and API keys to use in your code.

Option 2: Local Machine / Self-Hosting

You can also run Typesense on your local machine or self-host it.

You'll find DEB, RPM and pre-built binaries for Linux and macOS on our downloads page.

We also publish official Docker images for Typesense on Docker hub .

Docker

Shell

```
export TYPESENSE_API_KEY=xyz

mkdir "$(pwd)"/typesense-data

docker run -p 8108:8108 \
           -v"$(pwd)"/typesense-data:/data typesense/typesense:30.1 \
           --data-dir /data \
```

typesense

⌘ K

Docker Compose

yml

```
services:
  typesense:
    image: typesense/typesense:30.1
    restart: on-failure
    ports:
      - "8108:8108"
    volumes:
      - ./typesense-data:/data
    command: '--data-dir /data --api-key=xyz --enable-cors'
```

```
mkdir "$(pwd)"/typesense-data

docker-compose up
```

Kubernetes

There are a few **community supported** contributions for deploying on Kubernetes:

- via Kubernetes Operator by sai3010
- via Kubernetes Operator by akyriako
- via Kompose

Mac via Homebrew

> **Compatibility with macOS**
>
> The macOS native binary only works with macOS Ventura (13.x) or above.
>
> For older versions of macOS, please use the Docker or Docker Compose installation method above.

```
brew install typesense/tap/typesense-server@30.1
brew services start typesense-server@30.1
```

For macOS running on Intel CPUs:

- The default API key is `xyz` and the default port is `8108`
- The config file is at `/usr/local/etc/typesense/typesense.ini`
- Logs are under `/usr/local/var/log/typesense/`
- Data dir is under `/usr/local/var/lib/typesense/`

For macOS running on Apple Silicon CPUs:

- The default API key is `xyz` and the default port is `8108`
- The config file is at `/opt/homebrew/etc/typesense/typesense.ini`
- Logs are under `/opt/homebrew/var/log/typesense/`
- Data dir is under `/opt/homebrew/var/lib/typesense/`

Mac Binary

> **Compatibility with macOS**
>
> The macOS native binary only works with macOS Ventura (13.x) or above.
>
> For older versions of macOS, please use the Docker or Docker Compose installation method above.

Apple-Silicon Intel

```
# Download Typesense
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-darwin-arm64.tar
tar -xzf typesense-server-30.1-darwin-arm64.tar.gz

# Start Typesense
export TYPESENSE_API_KEY=xyz
mkdir "$(pwd)"/typesense-data
./typesense-server --data-dir="$(pwd)"/typesense-data --api-key=$TYPESENSE_API_KEY --
```

typesense ⌘ K

DEB package on Ubuntu/Debian

x64 arm64

```
# Download & Install
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-amd64.deb
sudo apt install ./typesense-server-30.1-amd64.deb

# Start Typesense
sudo systemctl start typesense-server.service
```

- The config file is at `/etc/typesense/typesense-server.ini`
  - The admin API key is auto-generated and can be found inside the config file.
- Logs are under `/var/log/typesense/`
- Data dir is under `/var/lib/typesense/`

> **Compatibility**
>
> v26.0+ of Typesense Server requires Ubuntu 20 or later.

RPM package on CentOS/RHEL

x64 aarch64

```
# Download & Install
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-1.x86_64.rpm
sudo yum install ./typesense-server-30.1-1.x86_64.rpm

# Start Typesense
sudo systemctl start typesense-server.service
```

- The config file is at `/etc/typesense/typesense-server.ini`
  - The admin API key is auto-generated and can be found inside the config file.
- Logs are under `/var/log/typesense/`
- Data dir is under `/var/lib/typesense/`

> v26.0+ of Typesense Server requires recent versions of the Linux kernel.

Linux Binary

x64 arm64

```
# Download
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-linux-amd64.tar
tar -xzf typesense-server-30.1-linux-amd64.tar.gz

# Start Typesense
export TYPESENSE_API_KEY=xyz
mkdir "$(pwd)"/typesense-data # Use a directory like /var/lib/typesense in productio
./typesense-server --data-dir="$(pwd)"/typesense-data --api-key=$TYPESENSE_API_KEY --
```

> **Compatibility**
>
> v26.0+ of Typesense Server requires Ubuntu 20 or later or recent versions of the Linux kernel.

Windows (WSL)

Shell

```
wsl
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-amd64.deb
sudo apt install ./typesense-server-30.1-amd64.deb

# Start Typesense
sudo /usr/bin/./typesense-server --config=/etc/typesense/typesense-server.ini
```

Note: Post install, you might see the message "installed typesense-server package post-installation script subprocess returned error exit status 1". You can safely ignore this error message. Executing `apt list --installed | grep typesense` should show that installation was successful.

If you'd like Typesense to be started at startup, you can create a BAT file with the command `powershell.exe /c wsl.exe sudo /usr/bin/./typesense-server --config=/etc/typesense/typesense-server.ini` and set it to execute at startup.

By default, Typesense will start on port 8108, and the installation will generate a random API key, which you can view/change from the configuration file at `/etc/typesense/typesense-server.ini`

> **TIP**
>
> We are starting a single node here, but Typesense can also run in a clustered mode. See the High Availability section for more details.

Using a GPU (optional)

Using a GPU will be handy for generating embeddings for vector search and for voice query.

You would have to install the following additional dependencies, after which Typesense will automatically make use of any available Nvidia GPUs:

1. Install CUDA following the instructions on Nvidia's site here .

   You want to specifically install the following versions of these packages: `cuda=11.8.0-1` , `libcudnn8=8.9.2.26-1+cuda11.8` and `libcudnn8-dev=8.9.2.26-1+cuda11.8` and their dependencies.

2. Install cuDNN following the instructions here .

   You want to specifically install the `libcudnn8` and `libcudnn8-dev` packages.

3. Add the following to `/etc/profile.d/cuda-path.sh` :

   ```sh
   export PATH=/usr/local/cuda/bin${PATH:+:${PATH}}
   export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:/usr/local/cuda/lib64
   export CUDA_HOME=/usr/local/cuda
   ```

4. Install the Typesense GPU dependencies package:

   DEB RPM Linux-Binary

```
sudo apt install ./typesense-gpu-deps-30.1-amd64.deb

# arm64
curl -O https://dl.typesense.org/releases/30.1/typesense-gpu-deps-30.1-arm64.deb
sudo apt install ./typesense-gpu-deps-30.1-arm64.deb
```

Large Page Size Build

Some operating systems / runtimes running on ARM, use a larger 16K system page size than the default one we compile Typesense with (4K). For these environments, we now publish a separate "lg-pg-size" build.

Typesense-Server Typesense-GPU-Deps

```
# Linux Binary
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-linux-arm64-lg-p
tar -xzf typesense-server-30.1-linux-arm64-lg-page16.tar.gz

# DEB
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-arm64-lg-page16.
sudo apt install ./typesense-server-30.1-arm64-lg-page16.deb

# RPM
curl -O https://dl.typesense.org/releases/30.1/typesense-server-30.1-1.lg.page16.aarc
sudo yum install ./typesense-server-30.1-1.lg.page16.aarch64.rpm

# Docker
docker pull typesense/typesense:30.1-arm64-lg-page16
```

OK Health Check

You can use the `/health` API end-point to verify that the server is ready to accept requests.

Shell

You can use the `/debug` API end-point to verify the version of Typesense running. See Managing Access to Data for more information about using API keys.

Shell

```
curl -H 'X-TYPESENSE-API-KEY: xyz' http://localhost:8108/debug
{
  "state": 1,
  "version": "30.1"
}
```

⚙️ Configure Typesense

You can configure various Typesense Server settings using command line arguments. Read this reference article for more information on How To Configure Typesense Server.

Edit page

Last Updated: 8/21/2025, 1:13:21 AM

← Introduction Installing a Client →