


01 What It Is


Concrete is a vintage sampler emulation instrument modeling the playback architecture of twelve classic 1980s hardware samplers — the E-mu SP-1200, Emulator II and Emax, the Akai MPC60, the Fairlight CMI, the Synclavier II, the Kurzweil K250, the Ensoniq Mirage/EPS/ASR-10, the Linn 9000, and the Casio SK-1. Each machine is reproduced as its own pitch-shifting mechanism, storage bit depth and companding scheme, and analog filter behavior — not a single bitcrusher effect with a preset menu on top. Any pad in the trigger grid can hold its own independent sample, so a full kit and a single re-pitched sample are the same underlying structure, not two different modes.

02 Signal Path



The Capture Pass is an offline technique, not a live effect; it re-bakes a sample's working buffer in the background whenever its own controls change. Everything below it — the pitch engine, the live filter, and the amp envelope — runs fresh on every voice, every time a note plays.


03 The Panel



LCD SCREEN

Sample / Machine / Filter / Capture pages


Everything about the currently-selected sample lives here, edited with the physical Directional Pad and Data Knob to the right (there is no mouse-drag-to-adjust on the fields themselves). The Sample page shows the waveform, a moving playhead while something is playing, the filename and its embedded-vs-path-referenced status, and the Root Note / One-Shot / Loop / Coarse Tune / Fine Tune / Volume fields — all per-sample state, so a pad's own sample keeps its own settings independent of every other pad and the main sample. Machine shows the pitch engine, base rate, bit depth, quantizer mode, and amp envelope; Filter shows cutoff/resonance/env-amount/key-track; Capture shows the offline resample/drive/quantize controls plus the Save Sample embed toggle and its live payload-size readout.



PADS

4x4 trigger grid


By default all 16 pads play the one loaded sample chromatically from its root note — the classic SP-1200/MPC "tune the pad" workflow. Dragging an audio file onto any single pad (or right-clicking it for a Load.../Clear/Copy/Paste menu) gives that pad its own independent sample, completely separate from the main sample and every other pad; hitting it switches the LCD screen to show and edit that pad's own settings. A looping pad keeps playing until it is hit again, which stops it rather than starting a second overlapping copy.



MACHINE

Machine select (Custom) / 12 machines default (Custom)

Applies a whole machine's worth of the parameters below in one go — pitch engine, base rate, bit depth, companding, filter model, voice count, and amp envelope — without touching the loaded sample or its per-pad settings. "(Custom)" is a deliberate placeholder so a fresh instance isn't silently colored by whichever machine is listed first. Your host's own native program list offers the same twelve machines, kept in sync automatically.



PERFORMANCE

Cutoff 20 Hz – 20 kHz default 20 kHz

The playback-side filter's cutoff frequency. Defaults fully open — no coloration until asked for.

Resonance 0 – 1 default 0

1 is at (or just past) self-oscillation for the resonant ladder filter models; has no effect on the SK-1's One-Pole model, which can't peak or self-oscillate.



VOLUME

Sample 0 – 120% default 100%

A per-sample gain — follows whichever sample the LCD screen is currently displaying, so it always adjusts the same sample you're looking at.

Master 0 – 120% default 100%


A flat output-gain stage applied after every voice renders — host-automatable and saved with the session, unlike Sample.



EDIT

Directional Pad + Data Knob

The only way to edit anything the LCD screen shows. The Directional Pad moves which field is selected (highlighted on screen); the Data Knob changes the selected field's value. There is no mouse-drag-to-adjust on the screen's own fields.



SESSION

One-Shot / Loop

Toggle the currently-displayed sample's own sample playback mode, mirroring the LCD's own fields. One-Shot plays a sample through to its own end regardless of how long a pad is held; Loop repeats it indefinitely until the same pad is hit again.

Resample

Re-runs the Capture Pass with the current settings.

Save Sample

Toggles whether the session embeds its sample data or only references the original file path.

Clear Sample

Clears whichever sample the screen is currently showing — a pad's own sample, or the main one — never the whole kit at once.

Stop All

Immediately silences anything currently playing.