KIZAMI DJ User Manual

Japanese version: user-manual.md

This manual is written for beginner to intermediate DJs. Technical terms are explained where they first appear. Items marked "unverified" could not be confirmed from the program itself.

Contents

1. Introduction
2. Screen Overview
3. Library
4. Decks
5. Mixer
6. Beat FX
7. Recording
8. Settings
9. Supported MIDI Devices and Control Tables
10. Keyboard Shortcuts
11. Troubleshooting and Glossary

---

1. Introduction

1.1 What KIZAMI DJ can do

- Import your own music files and automatically analyze BPM (tempo), key, and beat positions.
- Play tracks on three decks (A / B / C) and blend them by adjusting volume and tone on the mixer.
- Use loops, Hot Cues (mark any position and jump to it instantly), Beat Jump (jump by beats), and SYNC (match BPM).
- Apply Beat FX (echo, reverb, and more).
- Preview the next track in headphones (CUE; requires a 4-channel output device).
- Record your mix to a WAV file.
- (Pro version) Split a track into vocals, drums, bass, and other, and change the volume of each part (4.10).
- (Pro version) Let the Auto Mixer pick the next track, join the tracks, and keep playing (4.11).
- Control everything from the keyboard or a MIDI controller.

1.2 System requirements

Item	Details
OS	Windows (parts such as the recording destination are built with Windows-only code). The list of supported versions is unverified
Window width	Because three decks sit side by side, the window must be at least 1680 px wide (it cannot be made smaller; the default is 1800 px). On a laptop with a width of about 1536 px, the whole screen does not fit
Supported track formats	MP3, AAC (M4A), FLAC, WAV, AIFF, ALAC
Headphone CUE	Requires a 4-channel output device (channels 3-4 are the headphones)
Waveform display	Requires an environment where WebGL2 works
Beat analysis (AI)	AI is used only when the Beat This! model is installed. Otherwise a simple estimator is used (see 8.1)
Required PC performance (CPU, memory, etc.)	Unverified

1.3 Launching and first-time setup

1. Launch KIZAMI DJ. "KIZAMI DJ / Starting…" appears, and after a short wait the main screen opens.
2. On the empty Library screen, press **[Add Folder]** and choose your music folder. Import and analysis start automatically (chapter 3).
3. Check the output device in Settings (the ⚙ at the top right) (8.1).
4. Drag a track row onto a deck to load it, then press PLAY (chapter 4).

If startup fails, the recovery screen appears (8.4).

License agreement on first launch

The first time you launch the app, a license agreement screen appears before the main screen. Read it and press **[Accept]**; the version of the text you agreed to is saved in the settings, and the screen will not appear on later launches. If you press **[Decline]**, the app quits (nothing is saved, so the screen appears again the next time you launch). Until you agree, neither on-screen controls nor keyboard shortcuts work. However, in this version, MIDI controller input still reaches the app while it waits for your agreement. If the text of the agreement is revised, even users who have already agreed are asked to agree again at launch.


1.4 Japanese edition (0.2.0 JP)

This edition shows every on-screen word in Japanese. The features are the same as the English edition, and the version is shown as "0.2.0 JP".

- **It installs as a separate app.** It is named "KIZAMI DJ JP", and both it and the English "KIZAMI DJ" can be installed on the same computer (with separate shortcuts).
- **The library, settings, and license are shared with the English edition.** For that reason, **do not run the two at the same time.**
- **It does not update itself.** To update the Japanese edition, run the new installer.
- **The License Agreement is authoritative in English.** The Japanese edition adds a Japanese reference translation below the English text (if the two are read differently, the English prevails).
- DJ terms (SYNC, KEYLOCK, LOOP, CUE, BPM, EQ, FX), product names, and deck names (A, B, C) stay in English.
- Even in the Japanese edition, these stay in English: the master's auto label (`MASTER (auto)`), the names and buttons of the Stems tracks (`Stems`, `Reset`, `Instrumental`, `Acapella`, `Drums`, `Rhythm`, and so on), and the mixer's auto gain (such as `Auto -5.8 dB`).
- This manual is written for the English edition's labels. Where the Japanese edition differs, a matching list is given (such as at the end of 4.11).

---

2. Screen Overview



```
┌──────┬──────────────────┬──────┬──────────────────┐
│ BEAT FX 1 / BEAT FX 2                            │
├──────────────────────────────────────────────────┤
│ Library (folders, playlists, track list)         │
└──────────────────────────────────────────────────┘
```

- If the window is short, the screen scrolls vertically.
- From the left, the order is Deck A, Mixer, Deck B, Deck C. The mixer has three channels, A / B / C (chapter 5).
- Deck A is pink, Deck B is light blue, and Deck C is purple.
- Keyboard shortcuts are disabled while Settings, the recovery screen, the startup screen, or MIDI Learn is active.

2.1 Top bar (TopBar)

Display	Meaning
Master {BPM}	BPM of the master deck
● REC	Start/stop recording (Ctrl+R). Elapsed time is shown while recording. "⚠ Dropped {x}" shows the amount of audio lost because writing could not keep up (chapter 7)
CPU bar	Time spent on audio processing (as a ratio of the buffer duration). Warning color above 70%, danger color above 90%
⚠ n	Number of underruns (audio dropouts)
CLIP / ⚠ CLIP	Lights for 1 second when the level exceeds 0 dB before the limiter
GR	Amount by which the limiter reduced the volume
MIDI Learn active [Exit]	Shown only during MIDI Learn (8.3)
⚙	Opens Settings

Below the TopBar and the red banner, an update notification bar may appear when a new version is available (2.2).

2.2 Update notification

Updates are notify-only; an update is installed only when you press **[Update]**.

Display	Meaning / action
"Version {version} is available" + **[Update]** / **[Later]**	A new version is available. **[Update]** starts the update. **[Later]** hides the notice for that version until the next launch. The supporting text shows the release notes (if there are none, "Updating will restart the app")

Display	Meaning / action
"Installing update ({version})"	The update is being installed. "The app will restart when it finishes. Please wait." is shown; wait until it finishes and the app restarts
"Could not check for or apply the update"	Checking for the update, or installing it, failed. The reason is shown in the same bar. If installing failed, the update remains available, so you can press the button again

---

3. Library

This is the screen for managing tracks. The folder/playlist tree is on the left and the track list is on the right.

3.1 Importing (folders)

- Add a music folder with the ＋ next to "Folders" in the tree, or with **[Add Folder]** on the empty Library ("Your library is empty. Add a music folder to start importing and analyzing.").
- To add just a few tracks, press ♪＋ next to "Folders" and choose audio files (you can select several). Only the chosen tracks are imported; their folder is not watched. Dragging files in from Explorer is not supported yet.
- Import starts when you add a folder, and "Importing done / total", a progress bar, and **[Cancel]** appear.
- When it finishes, "Import finished" and "Added n, skipped n, failed n" appear. If you cancel, "Import cancelled" appears.
- You cannot register a folder that is inside, or that contains, an already registered folder.
- To remove a folder, use **[Remove]** on the General tab in Settings (8.1). Removing a folder only takes it out of the Library; the track files are not deleted.

3.2 Tree

Item	Details
All Tracks (n)	Shows all tracks
Folders	Filter by each registered folder
Playlists	Always shown. Indented by playlist folder
rekordbox	Import a rekordbox XML (3.2.2)

3.2.1 Editing playlists

- Use the ＋ next to "Playlists" to create a new playlist, or 📁 to create a playlist folder. Type a name and press Enter (Esc cancels).
- When you hover over a row, ✎ (rename; F2 also works) and 🗑 (delete; Delete also works) appear. Deleting asks for confirmation. The tracks themselves are not deleted.
- Drag a playlist or folder row in the tree onto another folder row to move it inside. Dropping it on the empty area of the playlist list moves it to the top level. It cannot be moved into itself or into its own contents.
- Drag a row from the track list onto a playlist in the tree to append it to the end (the same track can be added any number of times).
- While a playlist is open in its own order, drag rows to reorder them, and use the row action to remove a track from it (the track itself is not deleted).

You can also work from the toolbar above the track list.

Control	Details
Add to playlist (selector)	Appends the tracks selected in the track list to the end of the chosen playlist. The selector initially shows "Choose…", or "(No playlists)" if there are none. It is unavailable when no track is selected or there are no playlists. Only playlists can be chosen as a destination, not playlist folders
[↑ Up] / **[↓ Down]**	Moves the selected track up/down by one. Shown only while a playlist is open. Up is disabled for the first track, Down for the last
[Remove from playlist]	Removes the selected track from the playlist (the track itself is not deleted). Shown only while a playlist is open

- Reordering (Up / Down, dragging rows) and Remove work only when the search box is empty and the playlist is open in its own order. Otherwise the three buttons are disabled and "Reordering works only with an empty search while viewing in playlist order" is shown.

3.2.2 Importing a rekordbox XML

- Under "rekordbox" in the tree, press **[Import…]** and choose an XML exported from rekordbox.
- The confirmation includes "**Overwrite existing cues and manually edited values with the XML contents**", which is off by default. When off, existing cues and manually corrected beats and keys are kept, and only missing data is added. When on, they are replaced with the contents of the XML.
- When it finishes, a notification shows the number of tracks, playlists, and cues added. If some files were not found, that count is shown too.
- For AAC tracks (such as m4a), the start offset from the export source (about 34 ms) is corrected automatically when beat positions are imported.

3.3 Search

- Type in the search box (Ctrl+F jumps to it); the search runs 150 ms after you stop typing. Enter searches immediately.
- Esc leaves the search box. It does not misfire while you are composing text with a Japanese input method.

3.4 Sorting

- Click a column header to sort by that column. Click again to reverse the order.

3.5 Columns

Column	Meaning
(Deck column)	The deck the track is loaded on (see "Reading the track list" below)
Title / Artist	Track title and artist
BPM	Track speed (beats per minute). "—" if not analyzed
Key	Musical key of the track, in Camelot notation (see "Key notation" below). "—" if not analyzed
Time	Track length
Rating	Shown as ★/☆ (5 levels). Display only; clicking does not change it

- A maximum of 1000 tracks are shown. Beyond that, "Showing the top 1000 tracks. Narrow down with search." appears.
- Click a row to select it; drag it to load it onto a deck (4.1).

3.6 Analysis and row states

When you import a track, its BPM, key, and beat positions are analyzed automatically.

Display	Meaning	What to do
⏳ (waiting for analysis / analyzing)	Waiting its turn for analysis, or being analyzed	Wait
⚠ (analysis failed) + **[Re-analyze]**	Analysis failed	Press **[Re-analyze]**
(missing)	The file was moved or deleted. The row cannot be dragged	Put it back in its original location, or register the folder again

- If you see "Automatic analysis stopped" or "{n} analyses timed out. You can still use [Re-analyze] on each track", automatic analysis has stopped. The per-track **[Re-analyze]** still works.

- Tracks that cannot be analyzed can still be loaded onto a deck and played. However, without beat analysis, SYNC, loops, and Beat Jump cannot be used (4.8).

3.7 Reading the track list

Deck column (A / B / C)

- The column to the left of the title shows which deck the track is on. Deck A is in pink text, Deck B in light blue, Deck C in purple.
- While playing, a ▶ is added (such as "▶A") and the text is bold and glowing. If the track is merely loaded and stopped, only colored text and an outline are shown.
- If the same track is on several decks, the letters of all those decks are shown.
- The row of a loaded track has a deck-colored bar at its left edge, and its title is bold.
- Tooltip: hovering shows "Playing on Deck A" or "Loaded on Deck A".

★ mark (key-compatible tracks)

- A ★ is added to tracks whose key (Camelot notation) is compatible with the track on the master deck. It marks tracks that are likely to sound good when mixed. On a ★ row, the title and key cells are shown in green.
- The "master" is the deck used as the reference for BPM and key. When the master changes, the ★ marks move accordingly.
- Hovering over the ★ shows "Compatible with the master key".

About key notation (8A, 7B, and so on)

The "8A", "7B", etc. in the Key column are **Camelot wheel** codes for the key (musical scale) of the track. DJs use them to tell which tracks mix easily.

- The number (1-12) is the position on a circle that arranges keys in fifths (the circle of fifths). Like a clock face, 12 is followed by 1.
- The letter: A is a minor key (darker sound) and B is a major key (brighter sound).
- Examples: 8A = A minor (Am), 8B = C major (C). 7A = D minor (Dm), 9A = E minor (Em).
- Keys that are neighbors on the wheel, or the same number with A/B swapped, tend to stay clean when blended and are easy to mix.

When ★ is added

A ★ is added to a track whose key has one of the following relationships with the master's key.

Condition	When the master is 8A
Same key	8A

Condition	When the master is 8A
Same number, only A/B differs (relative key)	8B
Same A/B, number ±1 (12 and 1 are neighbors)	7A, 9A

- Example: if the master is 8A, ★ is added for four keys: 8A, 8B, 7A, and 9A. If the master is 12A, they are 12A, 12B, 11A, and 1A.
- Keys that are ±1 but with a different A/B (7B, 9B, etc.) and keys 2 or more steps away do not get a ★.
- The master track itself also gets a ★, because its key is the same.

When ★ is not added

- No track is loaded on the master deck.
- The key of the master's track has not been analyzed.
- The key of that track has not been analyzed, or is not in the "1A" to "12B" format.

(Implementation: `isCompatibleKey` in `ui/src/lib/camelot.ts`)

---

4. Decks

How to use the three decks (A / B / C) on the screen. All three work the same way. However, Deck C cannot be controlled from a MIDI controller; it is operated with the mouse and keyboard only (8.3, chapter 9).

4.1 Loading a track

Method	Operation
Drag	Drag a track row from the Library onto a deck
Shortcut	Select a track in the Library, then Shift+← (Deck A) / Shift+→ (Deck B) / Shift+ ↓ (Deck C)

- An empty deck shows "No track loaded (drag one from the library, or press Shift+←)" (Shift+→ for B, Shift+ ↓ for C).
- While loading it shows "Loading…". If loading fails, the cause and a remedy are shown.
- The full waveform loads in two stages, starting from the beginning. Parts not yet loaded are shown dark.
- Files that are not found cannot be loaded.

4.2 Deck display

- Header: deck name, title, artist. The master deck shows "MASTER", and a deck that is master automatically shows "MASTER (auto)".
- Readouts: BPM, key, elapsed time, and remaining time (with a minus sign). "⏳ Analyzing" and "⚠ Analysis failed" can also appear.

4.3 Play, stop, and CUE

Button	Behavior
PLAY (▶ / ▮▮)	Play / pause
CUE	When stopped, sets a Cue point at the current position. It sounds only while held, and returns to the Cue point when released (hold style)
SYNC	Matches the master deck's BPM (4.7). Cannot be pressed without beat analysis
M	Makes this deck the master. Press again to return the master to automatic

4.4 Hot Cue

A feature for marking any position in a track and jumping straight to it. Each deck has 3 buttons on screen, numbered 1-3.

State	Operation	Behavior
Empty	Press	Records the current position
Set	Press	Plays from that position (hold style: only while held)
Set	Shift+press	Deletes it

- Hovering over a button shows its position and key.
- Internally the data still holds 8 Hot Cues, numbered 1-8. Only 1-3 are shown on screen.
- Hot Cues 4-8 have no button and no waveform mark on screen. However, any 4-8 you have already recorded are not erased. You can still record, play, and delete them from the keyboard (chapter 10) and with MIDI buttons that are already assigned.
- From the screen, MIDI Learn can newly assign only Hot Cues 1-3 (8.3). To assign 4-8 to MIDI, use the bundled mapping (chapter 9).

4.5 Loops

Plays a chosen section repeatedly. Requires beat analysis.

Operation	Details
Auto loop ½ / 1 / 2 / 4 / 8	Creates a loop of that many beats from the current position
½× / 2×	Halves / doubles the length of the current loop
IN / OUT	Set the loop start / end by hand. Pressing IN enters "waiting for OUT"
↺	Exits the loop. While "waiting for OUT", cancels Loop In
SLIP	When on, the playback position keeps advancing in the background during loops and scratches, and returns to that position when they end

4.6 Beat Jump

- ◀◀ ▶▶ move back / forward by the chosen number of beats. Choose 1 / 2 / 4 / 8 / 16 beats (default 4).
- Requires beat analysis. The keyboard Beat Jump also uses the beat count chosen on this screen.

4.7 Tempo, pitch, SYNC, and master

Terms: **tempo** is the playback speed of a track, and **pitch** is the height of the sound. Normally, changing the speed also changes the pitch.

- **TEMPO fader** (on the outer edge of the deck; left edge for A, right edge for B and C): moving it down speeds up (+), up slows down (−). Double-click to reset to 0%.
- The current value is shown in %. Each press of the range button cycles ±8% → ±16% → ±50%.
- **KEYLOCK**: keeps the pitch the same when you change the tempo.
- **BEND**: while the speed is temporarily shifted with the jog wheel (MIDI controller), "BEND +x.x%" is shown.
- **SYNC**: automatically matches the other deck's BPM. Requires beat analysis.
- **Master**: the deck used as the reference for BPM and key. Set it manually with the M button; releasing it returns it to automatic. It is also the reference for the ★ mark (3.7). Deck C can also become the master automatically when it is playing with its VOL raised (the same rule as A / B).

4.8 When there is no beat analysis

The deck shows "⚠ No beat grid analysis(SYNC, loops and Beat Jump are unavailable)". Analysis of the track has not finished or has failed. Try **[Re-analyze]** in the Library (3.6).

4.9 Waveforms

Waveform	Details
Zoomed waveform (top of screen)	8 seconds with the playback position at the center. Beat grid, loops, Cue, and Hot Cues are overlaid (Hot Cues 1-3 only; marks for 4-8 are not shown)
Full waveform (in the deck)	The whole track. Click to move to that position

- If WebGL2 is unavailable, "Cannot display the waveform (WebGL2 is unavailable)" is shown; if drawing fails, "Cannot display the waveform (drawing failed)" is shown.

4.10 Stems (Pro version only)

Splits a track into four parts (Vocals, Drums, Bass, Other) and lets you raise or lower the volume of each, per deck. This section is not shown in the Free version.

How the splitting works

- When you load a track onto a deck, it starts splitting automatically. It splits **starting near the playback position**, so you can use it at the current position within a few seconds (about 2-4 seconds in measurements). Splitting the whole track takes about 20-40 seconds for a 4-minute track (it varies with the speed of your PC and whether other decks are also splitting). When several decks split at once, they take turns using a single model in small slices, so each deck gets slower as the number of decks grows (with 3 decks at once, measurements showed about 6-7 seconds until the current position is usable, and about 50-85 seconds until the whole track is done, depending on track length). This is not a waiting queue, so it is not only the track loaded last that gets pushed back.
- Parts that have not been split yet play as **the original track**. If you jump to a different part of the track, it splits from there (this takes a few seconds).
- The strip below the waveform shows the range that has been split.
- While all knobs are at 100% and nothing is muted, the original track is played as it is (to keep the sound quality unchanged). As soon as you lower any one, playback switches to the sum of the parts (it switches smoothly over about 20 ms).
- Sounds above about 11 kHz cannot be separated and **go into Other**. Lowering Other also lowers the very top of cymbals and similar content.

Reading the panel ("Stems" in the deck)

Display / control	Details
▾ Stems / ▸ Stems	Open / collapse the panel (the status stays visible when collapsed)
Status	Waiting / Separating xx% (splitting) / Ready (everything is split) / Unavailable (cannot be used)
V / D / B / O	Volume of Vocals, Drums, Bass, Other (0-100%; double-click to return to 100%)
Rhythm (knob)	Raises or lowers Drums and Bass together (see "How to use Rhythm" below)
M	Mute that part
Reset	Everything at 100%, nothing muted
Instrumental	Mute Vocals only
Acapella	Play Vocals only
Drums	Play Drums only
Rhythm (button)	Play Drums and Bass only

- Pressing a preset returns all volumes to 100% and changes only the mutes.
- When no track is loaded, or when a track cannot be split, the knobs and buttons cannot be pressed.

How to use Rhythm

- Rhythm is a volume that applies to both Drums and Bass. Drums and Bass each play at their own volume multiplied by the Rhythm volume.
- **Heavy electronic sub-bass is hard to separate**, and much of the low end can end up in Drums or Other. In such tracks, moving Bass alone does not remove or keep the low end cleanly.
- When splitting finishes and the track turns out to be one where bass is hard to separate, "Bass is hard to separate in this track. Try Rhythm." is shown and the Rhythm frame glows. In that case, move the low end and drums together with **Rhythm** instead of Bass.
- Examples: to pull the previous track's low end and beat out during a transition, lower that track's Rhythm. To keep only the vocals, use Acapella.

Preparing in advance (Prepare stems)

- Right-click a track in the Library and press **[Prepare stems]** to split it before loading it onto a deck. Progress is shown in the TopBar, such as "Preparing stems 1/3".
- The result is saved in the cache, and the next time you load the same track the whole track becomes usable in a few seconds (about 2-6 seconds in measurements). The cache location and limit can be changed under "Stems" in 8.1.

When it cannot be used

- The status becomes "Unavailable" and the reason is shown. The **original track keeps playing as it is** in the meantime.
- "The stem model (spleeter4.onnx) was not found in the model folder": the file used for splitting cannot be found. Reinstall the app.
- "Couldn't load the stem model": the file is damaged, or a component needed to load it (a DLL) is missing. Reinstall the app.
- The model for splitting (`spleeter4.onnx`) and its component (`onnxruntime.dll`) are included in the installer. At startup they are copied automatically to the model folder (by default `%APPDATA%\KIZAMI DJ\models`), so you do not need to place them yourself (they are copied only when missing or when the size differs). If you have changed the model folder to another location, they are copied there.

Assignments

- Keyboard: the mute for each part (such as Mute Vocals) is unassigned at first. You can assign them in **Settings** → **Shortcuts** (8.2).
- MIDI: the knobs and mutes can be assigned with MIDI Learn (8.3).

What has not been verified

- How it sounds (quality of the separation, the sound of switching) has not yet been checked by human ears.
- Operating Stems from a MIDI device (such as the MixTrack Pro) has not been checked on real hardware.

4.11 Auto Mixer (Pro version only)

The Auto Mixer picks the next track, overlaps it on a bar line, and keeps the music going without anyone touching the controls. It is meant for places with no DJ, such as an unattended lounge. In the free version the screen only shows "Auto Mixer is a Pro feature (available in KIZAMI DJ Pro)" and you cannot start it.

The "Auto Mixer" bar appears in the lower part of the screen, below the mixer and above the library. Its buttons and fields sit on one line and wrap only when the window is too narrow. Use ▾ / ▸ to collapse or expand it.

How it works

- It uses **decks A and B only**, alternating between them. Deck C is not used (manual only).

- Tracks are overlapped on a bar line. The overlap is 16 bars as a base. While they overlap, the low end (the kick and so on) is handed over in a short time (about 1/4 beat) so that only one of the two tracks plays the low end.
- While it runs, the crossfader curve is fixed to Smooth (it goes back when you stop).
- It makes no network connection during use.

Starting

1. **From a playlist**: choose a playlist under "Playlist" and press **Start**. Tracks play in the order of the playlist.
2. **From the whole library**: press **Pick from the whole library**. The machine picks the next track from the whole library. The basis is "the mood fits", which here means the kick and drum rhythm match (it also looks at how close the tempos are). Tracks that have not been analyzed yet come last. If the library has no playable track, it shows "The library has no playable tracks" and does not start.

Once it is running, the bar shows the state (Playing / Mixing / Paused / Stopped), the track playing now (Now), and the next track (Next).

Controls while it runs

Button / field	What it does
Stop	Stops it
Pause / Resume	Pauses / resumes
Skip	Moves on to the next track (with a fade of about 6 seconds)
Exclude next	Leaves the next track out of this auto mix; another track is picked
Direction	Which way to pick tracks: **Auto**, **Calmer** (toward calmer tracks), **Livelier** (toward livelier tracks). Over a long run the mood drifts a little. A change takes effect from the next pick
Tempo tolerance (%)	How far apart two tracks' tempos may be. 5% at first (range 1 to 20)
Same-track gap (min)	How long to wait before playing the same track again. 120 minutes (2 hours) at first

- Tempo tolerance and the same-track gap are saved as settings, but **changing them while it runs does not take effect at once** (it applies the next time you start). Only Direction takes effect at once.
- A deck you operate by hand (on screen or with MIDI) is left alone by the Auto Mixer until the next changeover is over.

- If you load a different track onto the next deck after the next track has been chosen, the Auto Mixer does not treat that track as its own. It cancels its plan and picks the next track again.
- The inside of the app can replace the next track with one you name, but there is no button for it on the screen.

When the tempo is out of range

- In playlist order, even when the next track is outside the tempo tolerance, **the order is kept**. Only that track is joined with a long fade (about 20 seconds), and its tempo is not matched.
- Tracks with no beat information, tracks whose tempo changes, and tracks that are not 4/4 are also joined with the long fade only.
- Tracks at about double or half the tempo (such as 70 and 140 BPM) are treated as close tempos.

The "Not enough candidates" notices (loosening)

To **keep playing without stopping** when candidates run out, the rules are loosened step by step. While they are loosened, a notice appears in the bar.

Notice	Meaning
Not enough candidates: shortening the same-track gap	Picking with a shorter same-track gap
Not enough candidates: widening the tempo tolerance	Picking with a wider tempo tolerance
Not enough candidates: playing the closest available track	The last resort: picking from the tracks that can be used (you may hear the same track again)

In the last resort, the track that was played longest ago comes first (a track that has never been played comes before all others). This keeps it from going back and forth between the same two tracks when few candidates are left.

It stops when every track has been excluded.

When something goes wrong

- If a track's file is missing or cannot be read, that track is skipped and it moves on.
- If the audio device is unplugged, it pauses and tells you, and resumes when the device comes back.

What has not been verified (an honest note)

- **A listening check of about 30 minutes with nobody touching it has not been done yet** (waiting for the owner's check; DEC-047 in decision-log.md). Human ears have not yet checked, with real tracks, whether the joins sound natural, whether the kick sounds doubled, or whether the sound breaks up.
- The numeric checks were made only with synthesized four-on-the-floor tracks (kick offset at most 2.5 ms, level dip within 1.4 dB, no silence longer than 50 ms). Real tracks may not give these numbers.
- The level dip of the long fade has not been measured.
- Tracks whose bar line is off (the beats match but the first beat of the bar is shifted) cannot be detected.
- The kick pattern is built from the analyzed beat grid. It may differ from a grid you fixed by hand or one from rekordbox.
- A person has not gone through the look and feel of the screen from start to finish.
- The speed of picking from the whole library has not been measured on a large library (thousands of tracks).
- The setting "resume automatically when the app restarts" (`resumeOnRestart`) exists inside the app, but it is not shown on the screen and does nothing.
- Tracks played by the Auto Mixer also count toward play counts (also when it plays from a playlist).

Labels in the Japanese edition

English edition	Japanese edition (1.4)
Auto Mixer	オートミキサー
Stopped / Paused / Mixing / Playing	停止中 / 一時停止中 / ミックス中 / 再生中
Now / Next	現在 / 次
Stop / Pause / Resume / Skip	停止 / 一時停止 / 再開 / スキップ
Exclude next	次の曲を除外
Playlist / Start	プレイリスト / 開始
Pick from the whole library	ライブラリ全体から選ぶ
Direction (Auto / Calmer / Livelier)	曲選びの向き (おまかせ / 落ち着いた曲 / 盛り上がる曲)
Tempo tolerance (%)	テンポ許容範囲 (%)
Same-track gap (min)	同じ曲の間隔 (分)

---

5. Mixer

The mixer in the center of the screen is made up of three channels (A / B / C) and a shared section. Channel C has TRIM, EQ, FILTER, VOL, and CUE just like A / B.

5.1 Knob and fader controls

Operation	Behavior
Drag vertically	Changes the value (about 200 px for the full range)
Shift+drag	Fine adjustment
← ↑ → ↓	Change in fixed steps (finer with Shift)
Home / End	Minimum / maximum
Double-click, Delete, Backspace	Reset to the default value
Alt+click, or Enter while an EQ is focused	Toggle KILL (5.3) on/off

5.2 TRIM and auto gain

- **TRIM**: a knob that adjusts the input level (±12 dB). Use it to even out differences in recording level between tracks. Double-click for 0 dB.
- "Auto x dB" is the auto-gain correction amount. Auto gain matches the loudness of tracks to −14 LUFS (a unit of perceived loudness), and can be turned on/off in Settings (8.1). TRIM is a manual adjustment and is applied on top of the automatic correction.

5.3 EQ (HI / MID / LOW) and KILL

- **EQ**: splits the sound into highs (HI), mids (MID), and lows (LOW), and raises or lowers each. The range is −40 dB to +6 dB. Double-click for 0 dB.
- **KILL**: cuts that band completely. "KILL" is displayed. Alt+click again to restore it.

5.4 FILTER

- One knob switches between two kinds of filter. Turn it left for LPF (low-pass = cuts the highs) and right for HPF (high-pass = cuts the lows). The center is OFF.
- The display reads "LPF n%", "HPF n%", or "OFF". Double-click for OFF.

5.5 Channel fader (VOL) and meter

- The VOL fader adjusts the channel volume (shown in %). The meter beside it shows the peak level.
- The meter starts at −48 dBFS. It turns the warning color above −6 dB and the danger color above −0.3 dB (on the verge of clipping).

5.6 CUE (headphones)

- The **CUE A / CUE B / CUE C** button on each channel lets you listen to that channel in headphones (it is not sent to the main output).
- It works only with a 4-channel output device. When unavailable, the button cannot be pressed and "No headphone output (channels 3-4)" is shown.

5.7 Crossfader (X-FADER)

- Move it left and right to switch the volume between A and B. The display reads "CENTER", "A n%", or "B n%". Double-click for center.
- **Deck C does not pass through the crossfader (Thru).** Channel C shows "THRU", and C's volume does not change wherever you move the crossfader. C's volume is decided only by C's VOL fader.
- There is no assign switch for choosing between A / B / C.
- The curve (smooth / cut) can be changed in Settings (8.1).

5.8 MASTER

- The vertical fader adjusts the overall output volume. The range is 0 to +6 dB. Double-click for 0 dB. Left and right (L/R) meters are attached.
- If you turn on the master limiter in Settings, it prevents clipping (8.1). You can see whether the limiter engaged in CLIP / GR in the TopBar.

5.9 Headphones (HP LEVEL / HP MIX)

Knob	Details
HP LEVEL	Headphone volume (0-2, default 1)
HP MIX	The balance of what you hear in the headphones. Fully left is CUE only; fully right is MASTER only. The default is the center (0.5)

- When there is no headphone output, "⚠ No headphone output (channels 3-4)" is shown.

---

6. Beat FX

Effects that follow the beat of the track. There are two units, BEAT FX 1 and 2.

Item	Details
Type	ECHO / REVERB / FLANGER / FILTER

Item	Details
Beats	Choose with ◀ ▶ from 1/16, 1/8, 1/4, 1/2, 3/4, 1, 2, 4, 8, 16, 32, 64. The length of the effect's cycle
MIX	How much effect is applied (wet/dry). Default 50%, in steps of 5%
Target	Choose A / B / C / M (the whole master)
BPM display	The BPM the effect is based on
ON / OFF	Turns the effect on/off

---

7. Recording

Records the final output of the mix (the MASTER sound) to a WAV file.

Item	Details
Start / stop	● REC in the TopBar, or Ctrl+R
Save location	`KIZAMI DJ\Recordings\` in your Documents folder
File name	`YYYYMMDD-HHMMSS.wav` (example: 20261022-213045.wav). If the name already exists, `-2`, `-3` is appended so nothing is overwritten
Format	WAV (24-bit)
Display while recording	Elapsed time on the REC button
When stopped	"Recording saved" and the save location are shown

- If writing cannot keep up and audio is lost, "⚠ Dropped {x}" is shown.
- If writing fails, a red banner "Recording stopped: ..." appears and the recording up to that point stays in the file. Dismiss the banner with **[Close]**.
- Even if you have moved your Documents folder to OneDrive or elsewhere, the recording is saved in `KIZAMI DJ\Recordings\` inside that location.
- The maximum recording length and file size limit are unverified.

---

8. Settings

Open with the ⚙ at the top right. Esc closes it. There are three tabs: General, Shortcuts, and MIDI.

8.1 General tab

Output

Item	Details
Output device	The device that plays the sound. Choose from "Default device", "{name} (default)", and "{name} (not found)"
Current: ...	The device in use, its channel count, and buffer size
Auto gain (match track loudness to −14 LUFS)	Matches track loudness to −14 LUFS (on by default)
Master limiter (prevents clipping)	Prevents clipping (on by default)
Crossfader curve	Smooth (default) / Cut (a small move from either end fully opens the opposite side, and it cuts only at the end; suited to scratching)

- If the channel count is less than 4, "Headphone output requires a 4-channel device (currently Master only)" is shown.

Library folders

- A list of registered folders. Press **[Remove]** on a row, then **[Really remove]** in the confirmation, to remove it (track files are not deleted).
- Add folders with **[Add folder]**. Removing a folder only removes it from the library; your music files are not deleted.

Beat analysis

- It shows "Using Beat This! (AI beat detection)." or "Using the simple estimator." In the simple case, the reason the AI cannot be used is also shown.
- Specify the model folder with **[Choose folder]** and revert with **[Reset to default]**.

Stems (Pro version only)

Settings for the cache that stores the split parts (4.10).

Item	Details
Cache folder	Where the cache is kept. At first it is `stems-cache` inside the app's data folder

Item	Details
[Choose folder] / [Reset to default]	Choose a location / return to the original location. Even if you change it, files in the previous location are not deleted ("Files in the previous folder are not deleted. You can remove them yourself." is shown; delete them yourself if you do not need them)
Cache limit (GB)	The limit. A whole number from 1 to 200 (5 at first). Beyond the limit, the oldest items are deleted first. If you enter a value out of range, "Enter a whole number from 1 to 200" is shown and it is not saved
Used: ...	The space used and the number of tracks
[Clear cache]	Deletes the entire cache. Press **[Really clear]**, shown after the first press, to delete it. The tracks are split again the next time they are loaded

- The cache for one track (4 minutes) is about 80-90 MB. 5 GB holds about 60 tracks.

License (Pro)

After you buy KIZAMI DJ Pro, you receive a license key that starts with `KDJ1-`. Enter it, restart the app, and the Pro features (such as AI Stems) become available.

1. Open Settings with the ⚙ at the top right and find the **License** section in the General tab.
2. Paste the key into the box ("Paste your license key"). Extra spaces or line breaks around the key are fine.
3. Press **[Apply]**. If the key is accepted, the status shows "KIZAMI DJ Pro — Order …, issued …" and "Restart KIZAMI DJ to apply." appears.
4. Quit KIZAMI DJ and start it again. The app is now Pro.
5. If the key is wrong or damaged, the reason is shown and the key is not saved (a valid key you entered earlier stays as it is).
6. To remove the key, press **[Remove]** and restart. The app goes back to Free (your tracks and library are not deleted).
7. The key is checked without an internet connection. Without a key, KIZAMI DJ keeps working as the Free version.

8.2 Shortcuts tab

- Press **[Change]** on an action's row, then press the key you want to assign. Esc cancels.
- Usable keys: a single key, or Shift+key, Ctrl+key. Hot Cues allow only keys without modifiers (because Shift+key is used for deletion).
- If you choose a key that is already in use, "{combo} is already used by {name}. Swap them?" is shown. Choose **[Swap]** or **[Cancel]**.

- Each row has **[Reset]**, and there is **[Reset all to default]** for everything.
- Keys that cannot be assigned: Tab, Escape, CapsLock, NumLock, kana, a modifier key alone, combinations with Alt or Win, Shift+Ctrl together, and Ctrl+C/V/X/A/Z/Y. Numpad digits cannot be assigned to Hot Cues, and cannot be combined with Shift.
- Key labels are shown as US-keyboard engravings (for example -, =, `, ', ¥, Ro, Numpad1). They may differ from the engravings on a Japanese (JIS) layout keyboard.

8.3 MIDI tab

Settings for using a MIDI controller. For supported devices and control tables, see chapter 9. MIDI can operate only Decks A and B. Deck C does not support MIDI (operate it with the mouse and keyboard).

Devices and mappings

- A list of connected MIDI devices is shown. A device may not appear right after you connect it, so wait a moment.
- Status per device: "Connected", "Not connected", "Cannot open (another app may be using it)".
- Use the **Mapping** selector to choose the mapping used for that device. You can also choose "No mapping". Mappings not yet checked on real hardware are labeled "Untested".
- The table below shows the mapping's Action / MIDI / Type (button, knob, jog, 14-bit). The MIDI column reads type, channel, number, for example "Note ch0 #11" (note; channel 0, number 11), "CC ch0 #20" (control change; channel 0, number 20), or "14bit CC ch0 #msb/lsb".
- If a mapping has rows that cannot be read, a "⚠ ..." row appears. If the mapping itself cannot be read, "Could not read this mapping: ..." is shown.
- When the state changes, the screen shows "MIDI device connected: {name}", "MIDI device disconnected: {name}", or "Cannot open MIDI device: {name}".

MIDI Learn (assign buttons yourself)

A feature that lets you link on-screen controls to your controller's knobs and buttons yourself.

1. Press **[Start Learn]**.
2. "Click the control you want to assign (Esc to exit)" -- click a control on the screen (button, knob, etc.).
3. If the control has several actions, "Which action do you want to assign?" appears; choose one.
4. "{action}: Move a control on your controller" appears. Operate the knob or button you want to use. **[Cancel]** aborts.
5. If it is already assigned to another action, "{midi} is already assigned to {action}. Replace it?" appears ({midi} looks like "Note ch0 #11"). Choose **[Replace]** or **[Keep]**.
6. "{midi} assigned to {action}." appears, and the type (button, knob, jog, 14-bit) is shown. Choose **[Redo]** or **[Next control]**.

7. If no message arrives, "No message received." appears. Choose **[Try again]** or **[Cancel]**.
8. **Controls on Deck C cannot be chosen.** MIDI supports only the two decks A and B. Controls on C get no Learn outline, and clicking them does not proceed to assignment.
9. Because the screen shows only Hot Cues 1-3, the Hot Cues you can newly assign with Learn are also 1-3. Existing assignments for 4-8 keep working as they are.
10. During Learn, controls that can be assigned get an outline. Finish with **[Exit]** in the TopBar or with Esc.

Jog wheel (scratch and pitch bend)

- Touch the top surface of the jog wheel and turn it: scratch (the sound moves back and forth as if you were moving a record by hand). One revolution advances 1.8 seconds.
- Turn it without touching the top (the side or top surface): pitch bend (temporarily shifts the speed so you can match beats). One revolution per second gives +5%, up to ±10%. When you stop turning, it returns to 0 in about 0.1 seconds. The amount is shown as "BEND +x.x%".

8.4 Banners, notifications, and warnings: meaning and fixes

Banners (red bar at the top of the screen)

Display	Meaning	What to do
Audio output: {device} was disconnected / Reconnecting to the same device	The audio output device was unplugged	When you reconnect it, playback resumes at the same position. If it does not come back, choose another device in Settings
Output lost (an error and remedy are shown)	Output stopped	Follow the remedy shown. If it does not recover, restart KIZAMI DJ
Recording stopped: ...	Writing the recording failed	The recording up to that point remains at the path shown. Check free space and the save location. Dismiss with **[Close]**

Notifications (messages shown on screen for a few seconds)

Notifications disappear after 6 seconds (errors stay until closed). Up to 4 are shown at once.

Display	Meaning
Importing {folder} / Import finished / Import cancelled	3.1
Automatic analysis stopped / {n} analyses timed out	3.6

Display	Meaning
{saved device} not found. Playing through the default device	The previous output device was not found, so playback switched to the default device. You can choose again in Settings
Recording saved	Chapter 7
MIDI device connected / disconnected: {name}, Cannot open MIDI device: {name}	8.3. For "Cannot open", check whether another app is using it
Mapping {name} has lines that could not be read	8.3. Rows that cannot be read are not used

Recovery screen (at startup)

- "The library database is corrupted": choose the backup to restore (newest first) and press **[Restore and start]**. To quit, press **[Quit]**. If there is no backup, "No backups are available to restore." is shown.
- "KIZAMI DJ could not start": **[Start again]** or **[Quit]**.
- This screen is not closed by Esc.

Error hints (text shown on screen)

Situation	Guidance shown
The library is in use	Check that KIZAMI DJ is not already running in another window
The library is from a newer version	Open it with a newer version of KIZAMI DJ
The track file cannot be read	Check whether it was moved or deleted, whether another app is using it, and permissions
Unsupported format	Supported formats are MP3, AAC (M4A), FLAC, WAV, AIFF, and ALAC
The track is corrupted	Check that the file is not corrupted and that it plays in another player
The track is too long	Tracks that are too long cannot be loaded (the maximum length is unverified)
Out of memory	Close other apps to free up memory, then try loading again
Output device not found	Check the device connection and power, or choose a different output device in Settings
Internal error	Restart KIZAMI DJ. If the problem continues, please contact the developer

9. Supported MIDI Devices and Control Tables

9.1 Support status

Device	Status
Numark MixTrack Pro	Partly verified on real hardware (9.3)
Pioneer DJ DDJ-FLX4	**Not verified on real hardware.** The mapping was transcribed from the official MIDI message list. It may not work or may be off
Other devices	No mapping is included. Assign controls yourself with MIDI Learn (8.3)

- MIDI supports Decks A / B. **Deck C does not support MIDI.** There is no C column in the tables below, and C cannot be assigned even with MIDI Learn.
- You can change the mapping from the selector on the tab. The bundled mappings are read-only.
- On Windows, only one app can open a given MIDI port. Close other DJ software and the like.
- Even similar models (such as MixTrack Pro 3) may use different MIDI numbers. In that case, choose a mapping again on the MIDI tab, or assign controls with MIDI Learn.

9.2 DDJ-FLX4 (not verified on real hardware)

These are the actions included in the bundled mapping. In particular, "SYNC", "TEMPO", "Jog (top surface / side)", and "effect amount" were already marked unverified at the time of transcription. **Everything in the table is unverified on real hardware.**

Category	Actions
Playback	PLAY/PAUSE, CUE, SYNC
Hot Cue	Set / play 1-8, delete 1-8 (Decks A and B)
Loop	Auto loop, Loop IN / OUT, ½, ×2
Beat Jump	Back, forward
Mixer	TRIM, EQ HI / MID / LOW, FILTER, channel fader, CUE (headphones), crossfader, MASTER, headphone MIX / LEVEL
Tempo / jog	TEMPO fader (14-bit), jog (top surface / side), jog touch
Beat FX	ON (units 1 and 2), next / previous type, beats down / up, amount
Library	Browse (select a track), load to Deck A / B
LED (lighting on the device)	Playing, Cue set, SYNC on, in loop, Hot Cue set

Main numbers (MIDI notes; from the bundled mapping):

Action	Number
PLAY (A)	Channel 0, note 11
CUE	Note 12
SYNC	Note 88 (unverified)
Hot Cue 1-8	A: channel 7, B: channel 9, notes 0-7
Hot Cue delete	A: channel 8, B: channel 10
Auto loop / IN / OUT / ½ / ×2	77 / 16 / 17 / 81 / 83
Beat Jump back / forward	Channels 7 and 9, notes 32 / 33
CUE (headphones)	Note 84
Jog touch	Note 54
Beat FX ON	Channels 4 and 5, note 71
FX type next / previous	99 / 100
FX beats down / up	74 / 75
Library load	Channel 6, note 70 (A) / 71 (B)

9.3 MixTrack Pro (partly verified on real hardware)

For MIDI devices whose name contains "MixTrack Pro", the bundled mapping (USB VID_15E4 / PID_0077) is selected. Everything uses MIDI channel 0.

Action	Deck A	Deck B	Notes
Jog	CC25	CC24	600 pulses per revolution
Jog touch	Note 78	Note 77	
PLAY/PAUSE	Note 59	Note 66	
CUE	Note 51	Note 60	
SYNC	Note 64	Note 71	
Pitch fader	CC13	CC14	Top is −8%, bottom is +8%
Channel fader	CC8	CC9	
EQ HI	CC16	CC17	
EQ MID	CC18	CC19	

Action	Deck A	Deck B	Notes
EQ LOW	CC20	CC21	
Crossfader	CC10 (shared)		
MASTER GAIN	CC23 (shared)		May fluctuate around 45-47 even when untouched

Verification status on real hardware (from the developer's records):

Item	Status
Jog scratch (touch the top and turn)	Verified
Jog bend (turn without touching) and on-screen display	Verified
PLAY / CUE / SYNC	Verified
EQ, MASTER GAIN, channel fader	Verified
Direction of the pitch fader	Verified
Direction of the crossfader	Verified
Noise when the jog is spun quickly in reverse	Unverified
Feel when stopping the jog while touching it	Unverified
CUE GAIN / CUE MIX, loading tracks, loops, effects	Mapping not created (not in the bundled mapping; assign with MIDI Learn)

Note: if an old settings file (`%APPDATA%\KIZAMI DJ\mappings\mixtrack-pro.json` , one containing only the jog) remains, it is chosen before the bundled one, and SYNC, playback, and faders stop working. Delete that file, or choose "MixTrack Pro (Default)" on the MIDI tab.

---

10. Keyboard Shortcuts

These are the defaults. You can change them on the Shortcuts tab in Settings (8.2). The action names below match those shown in the app (for example "Deck A Play"). Names such as "Deck A Auto Loop" are shown in the app exactly as written.

10.1 Decks

Action	Deck A	Deck B	Deck C
Play (Deck A Play / Deck B Play / Deck C Play)	Z	M	T

Action	Deck A	Deck B	Deck C
Cue	X	N	G
Sync	C	B	V
Auto Loop (4 beats; exits the loop if in one)	S	K	Y
Beat Jump Back	A	J	F
Beat Jump Forward	D	L	H
Hot Cue 1-4	1 2 3 4	7 8 9 0	(1-3 only) - = ¥ (key codes Minus, Equal, Backslash; on a Japanese layout the physical keys differ: Equal is the ^ key and Backslash is the] key)
Hot Cue 5-8	Q W E R	U I O P	None
Hot Cue delete	Shift+the Hot Cue key	Shift+the Hot Cue key	Shift+the Hot Cue key

- The Hot Cue 4-8 keys work even though there are no buttons on screen (A / B). Deck C has 3 Hot Cues, 1-3.
- The Stems part mutes for Deck C (such as Mute Vocals) are unassigned at first (8.2).
- If, in an earlier setup, you had changed an A / B action to the same key as one of C's defaults (T, G, V, Y, F, H, etc.), that A / B action is returned to its default at startup. If this bothers you, reassign it in Settings → Shortcuts.

10.2 Library and other

Action	Key
Library Select Up / Library Select Down	↑ / ↓ (hold to repeat)
Library Load to Deck A	Shift+←
Library Load to Deck B	Shift+→
Library Load to Deck C	Shift+ ↓
Library Search	Ctrl+F
Recording Start/Stop	Ctrl+R

10.3 Rules

- Cue and Hot Cue are hold style: they sound only while the key is held and stop when released.
- While you are typing text, shortcuts do not work (except those using Ctrl).

- Ctrl+R and Ctrl+F work as KIZAMI DJ functions, not as the screen reload or the browser search.
- Nothing happens on a deck with no track loaded. For a track without beat analysis, SYNC, loops, and Beat Jump also do not work.
- The Beat Jump beat count for the keys uses the value chosen on screen (4.6).

---

11. Troubleshooting and Glossary

11.1 Troubleshooting

Symptom	What to check
No sound	(1) The output device in Settings is correct (2) PLAY is pressed on the deck (3) The VOL fader and MASTER are not pulled down (4) The crossfader is not pushed to the opposite side (5) EQ KILL is not on (6) FILTER is not turned all the way (7) No red banner (output disconnected) is shown
Cannot hear in headphones	Whether the output device is 4-channel (check the channel count in "Current: ..." in Settings). With 2 channels, CUE is unavailable. Also check HP LEVEL and HP MIX
Sound breaks up	Look at the CPU bar and ⚠ n in the TopBar. If they are high, close other apps. You can check the output device's buffer size in "Current: ..." in Settings (how to change it is unverified)
Sound is distorted	Lower MASTER and the channel VOL. Turn on the master limiter. Keep the meters from going red
SYNC, loops, and Beat Jump do not work	The track has no beat analysis (4.8). **[Re-analyze]** in the Library
Analysis never finishes / fails	See 3.6. **[Re-analyze]**. Check that the track format is supported (1.2)
Track shows " (missing)"	Put the file back in its original location, or register the folder again
Cannot load a track	See the error hints table in 8.4
MIDI device does not appear / a warning appears	(1) Cable and power (2) Wait a moment (3) Whether another app is using the MIDI port (on Windows, only one app can) (4) Choose the mapping again
Only some actions work over MIDI	Whether an old mapping file remains (note in 9.3)
Cannot start	Follow the recovery screen in 8.4

Symptom	What to check
No ★ appears	"When ★ is not added" in 3.7
Recording stopped	Chapter 7. The recording up to that point remains at the path shown in the banner
Want to report a problem	**[Open logs folder]** in Settings opens the folder with the activity logs (`kizamidj.date.log`). Only the newest 7 days are kept, and track names and file locations are not written. Attach the latest file when you report. For a detailed investigation, start with the environment variable `KIZAMIDJ_LOG=debug` to get detailed logs that include track locations (check the contents before sharing them)

11.2 Glossary

Term	Meaning
BPM	Beats per minute. The unit of a track's speed
Camelot	A notation that expresses a track's key as 1A-12B. Neighboring keys are easy to match (3.7)
Beat grid	A scale showing where the beats of a track fall. The foundation of SYNC, loops, and Beat Jump
Deck	One player that plays a track
Mixer	The device (screen) that adjusts the volume and tone of the decks and blends them
Master	The deck used as the reference for BPM and key. Or the final output
SYNC	A feature that matches the BPM (and beats) between decks
CUE	(1) A position to start a track from, or the operation of returning to it (2) The mixer's CUE button: listen to that sound in headphones
Hot Cue	A mark placed at any position. A button jumps to it instantly
Loop	Playing a section repeatedly
Beat Jump	Jumping forward or back in units of beats
Scratch	Playing by moving the sound back and forth as if moving a record by hand
Pitch bend	Temporarily shifting the speed to match the beats of two tracks by hand
KEYLOCK	Keeping the pitch unchanged when the tempo changes
TRIM	Input-stage volume. Evens out volume differences between tracks
Auto gain	A feature that automatically matches track loudness to −14 LUFS
LUFS	A unit of loudness as heard by the human ear
EQ (equalizer)	A feature that raises or lowers highs, mids, and lows individually

Term	Meaning
KILL	Cutting a band completely
FILTER	A feature that cuts the lows or highs (LPF / HPF)
LPF / HPF	Low-pass (cuts highs) / high-pass (cuts lows)
Crossfader	Switches the volume between A and B with a single horizontal fader (Deck C does not pass through it: Thru)
Limiter	A feature that automatically holds the level below a set volume to prevent clipping
Beat FX	Effects applied in time with the beat (ECHO, REVERB, FLANGER, FILTER)
MIDI	A communication standard connecting instruments and controllers to a computer
MIDI Learn	A feature for assigning a controller's knobs and buttons to on-screen controls yourself
Jog	The controller's rotating platter. Used for scratching and pitch bend
Underrun	Audio processing could not keep up, so the sound breaks up
Beat This!	The name of the AI model that estimates beats