

Advanced DOM Window

Platform Windows | intermediate | 13 min read | DeepCharts Help Center | August 24, 2026

The Advanced DOM is the standalone price ladder in DeepCharts: live market depth on both sides of price, click-to-trade order columns, a projected P&L ladder while you hold a position, and up to two volume-profile columns — all in one window.

This article maps the whole window: anatomy, every ladder column, the gear menu, and the deeply nested settings dialogs (**Chart Dom Settings** and the two profile dialogs). If you want the concept behind a DOM rather than this specific window, start with Depth of Market (DOM) Indicator; for the ladder that lives inside a chart, see DOM Trading on the Chart (Click-Trading Ladder).

What it is

A DOM (Depth of Market) shows the resting order book as a vertical price ladder: bid sizes stacked below and around the current price on one side, ask sizes on the other. The Advanced DOM window adds trading columns (click a level to work an order there), a per-level projected profit/loss column for your open position, per-level traded-volume counters, and volume profiles built from executed trades.

If the ladder idea is new to you, explore the living order book below — hover any level to see what the resting size there means.

[WIDGET: dom-ladder]

Note: Depth display depends on your data feed. With Level 1 data only the best bid/ask is available; the full ladder of resting sizes needs Level 2 depth data.

When to use it

- Working precise limit orders at chosen levels instead of clicking buttons on a panel.
- Watching how resting liquidity builds or disappears around a level (Understanding Auction Theory: Imbalance, Unfinished Auctions, Absorption explains why that matters).
- Managing an open position with a per-level projected P&L readout.
- Combining live depth with executed-volume context via the two volume-profile columns.
- Running the tape and the book together — pair it with Advanced Time And Sales (The Tape).

Quick start

1. In the main bar, open **New** → **Book** → **Adv. Dom** (the **Book** submenu also offers **Horizontal dom** and **Vertical dom** variants).
2. Pick your instrument in **Select Instrument** and confirm. Only exchanges subscribed in Symbol Manage: Subscribe Exchanges and Map Your Feed appear.
3. The window opens and the ladder starts updating live. While history downloads, the main bar may show a **DWT:** badge — that is normal (DWT = downloading data from the feed server; LDT = loading data already on disk).

[SCREENSHOT PLACEHOLDER] New menu open with the Book submenu expanded showing Adv. Dom, Horizontal dom and Vertical dom, and the Select Instrument dialog behind it dc-en-advanced-dom-01.png

Window anatomy

[SCREENSHOT PLACEHOLDER] Full Advanced DOM window on NQ with all four sections visible: title bar with logo, eraser, gear, symbol dropdown and link icons; the Broker/Account/Qty/Daily P&L header; the %V %O V T stats row; the ladder with P&L, B, Bid, Price, Ask, S and VP columns with the current-price row highlighted orange; and the footer with the A box, Qty spinner, Cancel - Flat All, Buy, Cancel, Flat, Sell and the OCO block dc-en-advanced-dom-02.png

Top to bottom:

- **Title bar** — DeepCharts logo, **eraser** icon (clears the Resettable Profile column), **gear** icon (the settings hub), the symbol dropdown (for example NQ-202609), the square **link** icon, minimize and close. Closing asks for confirmation ("Are you sure to close the window?").
- **Trading header** — **Broker**, **Account**, **Qty** (turns green with +N while you are long) and **Daily P/L**.
- **Fundamentals row** — **%V** (percent change versus the previous day), **%O** (change versus the session open), **V** (total volume) and **T** (number of trades).
- **The ladder** — the columns described below; the current-price row is highlighted orange (the **Last** marker).
- **Footer** — the **[A]** order-type box, **Qty** spinner, **Cancel - Flat All** (orange), **Buy**, **Cancel**, **Flat**, **Sell**, the OCO toggle with **Server/Client** radios and the strategy dropdown with its own gear.

The four middle/outer sections map one-to-one to the gear menu's **Show Fundamental**, **Show Trading Panel**, **Show Trading Buttons** and **Show OCO Panel** toggles — uncheck one and that section disappears.

Ladder columns

The default view shows **P&L | B | Bid | Price | Ask | S | VP**. Enabling everything (via the settings or the column-header right-click menu) yields **P&L | #B | B.PS | B | Bid | B.T | Price | A.T | Ask | S | A.PS | #A | VP | VP**.

Column	What it shows
Price	The price ladder itself. The orange row is the current price (Last marker).
Bid / Ask	Resting market-depth sizes per level (bid cells blue, ask cells purple by default), updating live.
B / S	Wide click-to-trade bands for your own orders — buy side green, sell side dark red. Your working orders appear here.
P&L	With an open position: the projected profit/loss of that position at every price level. The green 0.00 row marks your entry/breakeven level.
B.PS / A.PS	Pull/Stack columns — per-level liquidity change tracking (green = liquidity added, red = pulled). Empty until pull/stack events occur; the feature is off by default.
B.T / A.T	Per-level traded-volume counters per side (market-sold / market-bought volume).
#B / #A	Order-count columns, tied to the Offers feature (count of individual orders per level). They can stay empty on feeds that do not deliver order-level data — exact data requirement unconfirmed.
VP / VP	Two volume-profile columns: the Resettable Profile (accumulates until you clear it with the eraser icon) and the Daily Profile (from session start). Bars with numbers per level; the highest-volume level's value is highlighted red (the POC).

[SCREENSHOT PLACEHOLDER] Advanced DOM ladder zoomed to show blue bid depth cells, purple ask depth cells, a green working buy order in the B column, and the two VP columns on the right with the red-highlighted POC value
dc-en-advanced-dom-03.png

How to read it

- **Depth (Bid/Ask columns)** — the sizes update tick by tick; watch levels where size stacks or vanishes. For interpretation patterns, see Understanding Auction Theory: Imbalance, Unfinished Auctions, Absorption and Orderflow 101: Bid, Ask, Aggressor and Delta.

- **The P&L ladder** — while flat it stays empty; once you hold a position every level shows what closing there would mean. The green 0.00 row is your breakeven/entry; values above and below scale with distance.
- **The two VP columns** — executed-volume context. The Daily Profile shows the full session; the Resettable Profile shows only what traded since you last pressed the eraser icon, which makes it useful for "what happened since the news" style questions. The red-highlighted value is the level with the most traded volume (POC — see Understanding Volume Profile: POC, Value Area, HVN/LVN).
- **Markers** — the ladder highlights session levels: **Last** (orange, on by default), **High** (green, on), **Low** (red, on), **Open** (off by default), plus **Suspension** (cyan, on) and **Auction** (off). What the Suspension and Auction markers indicate exactly is **[CONFIRM: Suspension and Auction marker semantics]**.

[SCREENSHOT PLACEHOLDER] Advanced DOM while long 2 contracts — Qty field green showing +2, the P&L column filled with per-level values and the green 0.00 row at the entry level, current-price row orange below it
dc-en-advanced-dom-04.png

Trading from the DOM

- **Order type — the [A] box.** The box next to Qty selects the order type: **Automatic / Limit / Market / Conditional**. In Automatic mode the platform decides from your mouse action — right-click places a market order, left-click places a limit or stop depending on which side of price you click.
- **Working orders.** Click in the **B** column to work a buy at that level, **S** for a sell. Drag an order to move it, right-click it to delete it, double-click to edit its quantity.
- **Footer buttons.** **Buy** and **Sell** submit at the footer quantity; **Cancel** cancels working orders and **Flat** closes the position. **Cancel - Flat All** does both in one click — its exact scope (this symbol only, or all accounts/symbols) is **[CONFIRM: scope of Cancel - Flat All in the Adv DOM footer]**.
- **OCO block.** The footer's OCO toggle, **Server/Client** radios and strategy dropdown mirror the trading panel's bracket system — see OCO (One-Cancels-the-Other) Strategies and Trading Panel Reference: Every Button and Field for how server-side versus client-side brackets behave.

Warning: The B and S columns are live order-entry surfaces. A click places or works a real order for the selected account — keep the simulation account selected while you learn the ladder (Trading Accounts and Simulation).

Compact layout

When the window is narrow, the DOM re-arranges itself: the header gains **Price** and **P/L** fields, the ladder splits with price in the center and **X** columns that cancel the working order at that level, and the footer becomes an explicit order ticket (**Qty**, **Price**, **Type** dropdown showing LMT, **Buy**, **Cancel all**, **Flat**, **Sell**, plus the OCO row). What width triggers the switch is **[CONFIRM: activation rule for the compact split layout]**

[SCREENSHOT PLACEHOLDER] Narrow Advanced DOM in compact split layout showing the centered price columns, X cancel columns, and the order-ticket footer with Qty, Price and Type=LMT fields dc-en-advanced-dom-05.png

Settings reference

Everything starts at the **gear** icon: **Duplicate Dom**, **Settings Column Order**, **Settings Dom**, **Resettable Profile** ■ **Daily Profile** ■ the four **Show** toggles **Always on Top** and **Template** ■ (Load / Save As)

[SCREENSHOT PLACEHOLDER] Advanced DOM gear menu open showing Duplicate Dom, Settings Column Order, Settings Dom, Resettable Profile, Daily Profile, the four checked Show toggles, Always on Top and Template
dc-en-advanced-dom-06.png

Note: After some settings or profile changes the ladder briefly shows a Loading spinner while it rebuilds. This is normal — the same pattern as a chart rebuilding.

Settings Column Order

A simple list of the internal column ids with **Up / Down** buttons plus **Apply / OK** — reorder the ladder columns here. The full inventory: ProfitLoss, BidOffer, BidPullStack, BuyOrder, BidQty, BidFilled, PriceScale, AskFilled, AskQty, SellOrder, AskPullStack, AskOffer.

A faster alternative: right-click any column header for the quick menu — **Adjust column size**, **Adjust window to fit content**, and show/hide toggles for **Pull/Stack**, **Trades**, **Offers**, **Profit/Loss** plus the two nrofile submenus.

[SCREENSHOT PLACEHOLDER] Column-header right-click quick menu open showing Adjust column size, Adjust window to fit content, Pull/Stack, Trades, Offers, the checked Profit/Loss entry and the Resettable/Daily Profile submenus dc-en-advanced-dom-07.png

Settings Dom (Chart Dom Settings dialog)

The main dialog, organized in ten collapsible sections:

Section	Settings
GENERAL	Font size (11.00), Text format (Automatic), Background color , Number of levels to show (0), Tick grouping (1), Auto. axis margin % (20). [CONFIRM: meaning of Number of levels to show = 0 — all levels?]
BID/ASK COLUMN	Bid back color (blue), Ask back color (purple), Bid/Ask profile color (the horizontal size bars inside the depth cells), Text Color .
PULL/STACK COLUMN	Enable (off by default), Calculation Mode (Avg filter — other options unconfirmed), Show As Profile (on), Text Color , plus per-side pull/stack colors (bid pull red, bid stack green, ask pull green, ask stack red).
FILLED COLUMN	Enable (off), Auto reset (on), Bid Text , Ask Text , Highlight Bid/Ask (off), Bid/Ask Highlight colors. Exactly what Filled counts versus the Trades columns, and when Auto reset fires, is unconfirmed.
OFFERS COLUMN	Enable offers (off), Bid/Ask offer back colors , Text Color .
ORDER SETTINGS	Text Color , Buy Order (green), Sell Order (red), Buy/Sell BackGround , Buy/Sell Filled Color — the working-order colors in the B/S columns.
PRICE SCALE	Price back color , Price text color .
PL COLUMN	Enable (on), Background , Gain Text Color (green), Loss Text Color (purple) — turn the P&L ladder off here if you do not want it.
MARKER SETTINGS	Per-marker enable + color: Last (on, orange), Open (off), High (on, green), Low (on, red), Suspension (on, cyan), Auction (off, purple).
ORDER ENABLE SETTINGS	Enable stop order (on), Enable market order (on). Whether these gate ladder clicks only or also the footer buttons is unconfirmed.

[SCREENSHOT PLACEHOLDER] Chart Dom Settings dialog open with the GENERAL section expanded and the list of all ten section headers visible dc-en-advanced-dom-08.png

Resettable Profile and Daily Profile settings

Each of the two VP columns has its own full settings dialog (identical structure, nine sections): **GENERAL** (**Auto grouping** Manual/Automatic, **Auto group factory** 2, **Manual ticks** 1), **PLOT SETTINGS** (**Background** → **Show Settings**, **Show text**, **Text** → **Show Settings**, **Text format**, **Number of profile** 2), **VISUAL APPEARANCE** (**Vbp opacity** 90, **Show filled vbp** off), **POINT OF CONTROL** (**Enable** on, **Highlight** on, magenta highlight color, optional line), **VALUE AREA** (**Enable** on, **% Value Area** 70, **Highlight** on, **Outside Color** yellow — the yellow bars you see in the ladder are outside-value-area levels, optional

line), PEAK AND VALLEY (**Sensitivity** 20 plus a nested PEAK/VALLEY settings window with enable, highlight, minimum volume and line options), SUMMARY, PRICE LINE and LAST FILLED QTY (each with an Enable toggle plus colors).

The nested **Background Settings** window controls profile-bar coloring: **Method color** (Fading color), **Color calculation** (Volume), **Min. Vol. Diff. for Imbalance**, **Include zero on imbalance**, **Color only dominant side**, fixed color swatches, and a RANGE system (**Range defining** Automatic plus FIRST–FOURTH RANGE color tiers). The full option lists and what defines the four range tiers are unconfirmed — expect this area to reward experimentation on a simulation feed.

These profile concepts (POC, value area, peaks and valleys) are the same ones the Deep Profile (Volume / Delta Profile) indicator uses on charts.

[SCREENSHOT PLACEHOLDER] Resettable Profile settings dialog showing the nine section headers with GENERAL expanded, and the nested Background Settings window open on top showing Method color=Fading color and Color calculation=Volume dc-en-advanced-dom-09.png

Troubleshooting

- **Ladder shows only best bid/ask, most depth cells empty.** Your feed is Level 1. Full depth needs Level 2 data — check what your subscription includes (How to Buy a Data Feed and Get Your Credentials).
- **#B/#A columns stay empty.** These order-count columns can stay empty on feeds without order-level data even while B.T/A.T populate. Exact requirement unconfirmed.
- **Window stuck on Loading.** Settings and profile changes rebuild the ladder — give it a moment. If the main bar shows **DWT**: the platform is downloading history from the feed; if it never finishes, work through Fix: Charts Lagging or Data Delayed (Checklist).
- **Resettable Profile column looks empty or sparse.** It only accumulates since the last eraser click — that is its job. The Daily Profile column next to it carries the full session.
- **Prices frozen.** Check the feed dot in the main bar and see Fix: Live Feed Connected but Chart Is Not Moving.

Tips and common mistakes

- **Eraser vs Daily.** Press the title-bar eraser deliberately: it clears the Resettable Profile immediately. The Daily Profile is unaffected.
- Use **Duplicate Dom** to spin up a second ladder with identical settings, then switch its symbol — faster than reconfiguring from scratch.
- If a section of the window "disappeared", check the gear menu's four **Show** toggles before assuming a bug.
- Save your configured DOM as a template (**Gear** → **Template** → **Save As**) and reload it on any workspace.
- Keep **Enable stop order / Enable market order** in mind: if a ladder click refuses to place a stop or market order, these toggles are the first place to look.

Related articles

- Depth of Market (DOM) Indicator
- DOM Trading on the Chart (Click-Trading Ladder)
- Advanced Time And Sales (The Tape)
- Trading Panel Reference: Every Button and Field
- OCO (One-Cancels-the-Other) Strategies
- Understanding Volume Profile: POC, Value Area, HVN/LVN

