

Deep Pattern Builder

Indicators & Analysis / Deep Indicators | advanced | 7 min read | DeepCharts Help Center | August 24, 2026

Deep Pattern Builder is the most advanced indicator in the DeepCharts suite. It lets you construct custom trading logic out of relational conditions — comparisons like $A + B > C + D$ over candle values, volume, delta, POC references or other indicators' outputs — and then run automated backtests on that logic with the built-in simulation engine.

In practice it is two tools in one: a signal engine that plots markers or background highlights wherever your conditions are true, and a backtester that turns those signals into simulated entries with stops, targets and trailing logic.

What it is

Each condition in the builder takes up to four inputs (**A**, **B**, **C**, **D**), joins A with B and C with D using math operators, and compares the AB block against the CD block with one logical operator. Conditions can be combined with AND/OR logic, filtered by an integrated imbalance filter, visualized on the chart, wired to alerts, and fed into a simulated entry/exit model for backtesting.

[SCREENSHOT PLACEHOLDER] Chart with Deep Pattern Builder applied — signal markers plotted on candles where the custom conditions fired, with a couple of background-highlighted bars visible
dc-en-deep-pattern-builder-01.png

When to use it

- You have a repeatable idea ("close above the POC with positive delta") and want the platform to mark it on every bar, live and historically.
- You want to reference other indicators' values (for example a moving average) inside your conditions.
- You want statistical evidence: the built-in backtest simulates entries, stops and targets over historical data.
- You want alerting on multi-part logic that no single stock indicator covers.

Quick start

1. Apply the **Deep Trades** indicator to the chart first — the builder workflow depends on it (see Deep Trades).
2. Click the **Indicator** icon, search for **Deep Pattern Builder** and click **+** to add it.
3. Click the **Settings** icon next to Deep Pattern Builder.
4. Build a first condition. Example — "delta-positive close above the open": **Condition 1**: Input A = **Reference** → **Close**, Logical Operator **>**, Input C = **Reference** → **Open**. **Condition 2**: Input A = **Reference** → **Delta Volume**, Logical Operator **>**, Input C = **Constant** → **0**. Combine with **AND (Simple)**.
5. Enable **Calculate on Close** so signals evaluate only when the candle completes, without intrabar flicker.
6. Under **Plot Settings**, choose a **Plot Type** (start with **Marker**) and a **Plot Price** placement.
7. Click **Apply and Save** and check that markers appear on historical bars where the logic is true.

[SCREENSHOT PLACEHOLDER] Deep Pattern Builder settings dialog showing one enabled condition with Input A set to Reference Close, the Logical Operator dropdown, Input C set to Reference Open, and the Combine Mode selector below
dc-en-deep-pattern-builder-02.png

How to read it

A signal (marker or highlighted background) means every part of your combined logic evaluated true on that bar — nothing more. The tool plots your idea; judging the idea is what the backtest is for.

- **Markers** are placed at the **Plot Price** you chose (High = above the candle, Low = below, Current = at the close, Mid Price = wick center), colored per side via the subgraph colors.
- **Flickering signals during a live bar** mean the condition is oscillating intrabar — enable **Calculate on Close** if you only want confirmed signals.
- **Backtest report**: after running a backtest, the report shows how the simulated entries performed under your stop/target model. Iterate: adjust the conditions or risk settings, re-run, compare against previous saved reports.

Settings reference

Grouped as in the settings dialog.

Condition

Setting	What it does
Enable	Activates the condition.
Inputs A, B, C, D	Up to four input slots per condition; B and D are optional (set unused slots to Unused).
Math Operator 1	+, −, ×, / between inputs A and B.
Math Operator 2	+, −, ×, / between inputs C and D.
Logical Operator	Compares the AB block with the CD block: >, >=, =, <> (not equal), <, <=.

Input types

Input Type	What it does
Unused	Disables the input slot.
Reference	Candle components: Open, Close, High, Low, Bid Volume, Bid NT, Ask Volume, Ask NT, Total Volume, Total NT, Delta Volume, Delta NT, Low–High Ticks, Open–Close Ticks, POC Price %, POC Total Volume, POC on Shadow, Cumulative Delta Volume.
Indicator	Live values from another applied indicator — requires that indicator's Indicator ID and Subgraph ID (the specific value line to read).
Constant	A fixed numeric value you type in.

Option	What it does
Previous Bar	Pulls the input's value from the prior candle instead of the current one — enables bar-over-bar logic such as "delta rising" (A = Delta Volume > B = Delta Volume, Previous Bar).

Combine modes

Mode	What it does
OR (Simple)	Any single condition being true fires the signal.
AND (Simple)	All conditions must be true.
AND + OR (Advanced)	Nested groupings such as (Condition 1 OR Condition 2) AND (Condition 3 OR Condition 4).
Calculate on Close	Evaluates conditions only after the candle closes — no intrabar flicker.

Imbalance filter

Setting	What it does
Imbalance filter	An integrated filter whose configuration mirrors the Imbalance Tracker indicator's settings — restricts signals to bars that also meet the imbalance criteria.

Plot Settings

Setting	What it does
Plot Type	Marker (signal marker only), Background (candle background highlight), or Series & Background (both).
Days to Load	How many historical days to calculate signals for.
Plot Price	Marker placement: High (above candle), Low (below candle), Current (at close), Mid Price (wick center).
Color / Opacity	Marker or background color and background transparency.

Alert Settings

Setting	What it does
Alert selection	Alerts must be created first via Options → Add Alert ; only then do they appear in the builder's alert list for selection.

Simulation (backtesting)

Setting	What it does
Enable	Activates simulation mode.
Entry Type	Market (immediate entry), Half Bar , or Ticks from Close (limit order X ticks from the candle close).
Side	Buy or Sell .
Allow Multiple Entries	Permits concurrent positions.
Entry Expiration (Bars)	How many bars a pending entry stays valid.
Stop (Ticks)	Fixed stop-loss distance.
Trailing Stop — Enable / Trigger (Ticks) / Offset (Ticks)	Activates a trailing stop; Trigger is the profit threshold before it engages, Offset the gap it maintains behind price.
Targets	Multiple profit targets in ticks.
Move to Break Even (B/E)	Moves the stop to entry price when a target is reached.

Subgraph

Setting	What it does
Color / Color 2	Bid-side and ask-side marker colors.
Subgraph style	Marker style selection.

Running a backtest

1. Configure conditions, plot and simulation settings, then click **Apply and Save**.
2. Right-click the chart.
3. Select **Autotrading** → **Execute Backtest**.
4. Review the report. Via right-click you can also clear results, view previous backtests and save reports.

[SCREENSHOT PLACEHOLDER] Right-click context menu on the chart with Autotrading expanded and Execute Backtest highlighted, with a completed backtest report visible 

Tips and common mistakes

- **Backtest option missing on right-click?** Follow the full workflow in order: Deep Trades applied, Deep Pattern Builder added and configured, **Apply and Save** clicked — then right-click → **Autotrading** → **Execute Backtest**.
- **Alert not listed in the builder?** Alerts must exist before the builder can use them — create them first via **Options** → **Add Alert**.
- **Signals flicker intrabar?** Enable **Calculate on Close**.
- **Referencing another indicator returns nothing?** Check both the **Indicator ID** and the **Subgraph ID** — the Subgraph ID selects which value line of that indicator you read.
- **Start with one condition.** Verify each condition plots sensibly on its own before combining with AND/OR — debugging nested logic with four inputs per condition is much harder.
- **Bar-over-bar logic needs Previous Bar.** "Delta rising" is current Delta Volume > Delta Volume with **Previous Bar** enabled on the second input, not two separate conditions.

Related articles

- Deep Trades
- Imbalance Tracker
- Orderflow 101: Bid, Ask, Aggressor and Delta
- Different Types of Input Data for Indicators
- How to Change the Layout of Indicators
- Dynamic POC