File Handling

DOS Services

- 03Ch : Create File
 - Overwrite the existing file
- 03Dh : Open File
- 03Eh : Close File
- 03Fh : Read From File
- 040h : Write to File
- 42h : Move File Pointer

03Ch- Create File

Input:

- -Ah = 03ch
- DX = offset file-name
- CX = File Attribute
 - 0h Normal
 - 01h Read Only
 - 02h Hidden
 - 04h System
- Return:
 - On success AX= FileHandle
 - On Error carry will be generated

3DH Open File

- INPUT:
 - -Ah = 03dh
 - DX = offset of the ASCIZ filename.
 - AL = file access code
 - -0 =read-only,
 - 1 =write-only,
 - 2 =read/write).
- OUTPUT: AX=file handle.

03FH Read a record from a file

INPUT:

- -Ah = 03Fh
- BX = file handle
- -CX = record size
- DX = start of the buffer into which data will be read

OUTPUT:

AX=number of bytes actually read into buffer.

40H Write a record to a file (or a device).

INPUT:

- -Ah = 40h
- BX = file handle ;01=display,02=printer rest for files
- CX = record size ;no of bytes to write
- -DX = buffer

OUTPUT:

AX=number of bytes actually written.

3EH Close File

Input:

```
-AH = 3EH
```

– BX =file handle.

Separate File/Module Linking

- We have two files, IOProc.asm and GetAryElement.asm
 - IOProc.asm has GetNo and ShowNo procs.
- Public: is used in the main program(IOProc.asm) to share the variables and procs in other program(GetAryElement.asm, i.e; Public GetNo, ShowNo,PrevNo)
- Extrn: Means External is used in the sub programs (GetAryElement.asm) to access those elements which are external (present in IOProc.asm as public but Extrn as in subprorams)
 - Extrn GetNo:Proc,ShowNo:proc,PrevNo:Word)

Assembling and Linking

- Masm IOProc.asm;
 - Generates IOProc.obj
- Masm GetAryElement.asm;
 - Generates GetAryElement.obj
- Link GetAryElement IOProc;
 - Generates GetAryElement.Exe