

CONFIDENTIAL

Nomadix Nexus

NOMADIX CLOUD®

Last Updated
10 January 2025

Table of Contents

#	Section	Page
1	**PMS Integration**	5
1.1	Overview	5
1.2	PMS Module Overview	5
1.3	Logical Components	6
1.4	Integration with Nomadix Products	7
2	**Supported PMS Types**	9
2.1	Overview	9
2.2	Supported PMS Interfaces and Types	9
3	**Commercial Licensing**	10
3.1	Required Licenses	10
3.2	Oracle OHIP Licensing	11
3.3	PMS Vendor Licensing	13
4	**Configuration**	13
4.1	Prerequisites Before Any Configuration	13
4.2	Configure On-Premise PMS system using FIAS via Nomadix Gateway	13
4.3	Configure On-Premise PMS System using Marriott PMS Redirector	24
4.4	Configuring Cloud PMS	33
4.5	Configuring Cloud PMS: Oracle OPERA Cloud (OHIP)	38
4.6	Legacy MICROS Emulation (Gateway-Only Configuration)	43
5	**Nomadix Cloud PMS Module Overview**	43
5.1	Dashboard	44
5.2	Rooms	45
5.3	Events	46
5.4	Transactions	46
5.5	Settings	46
6	**Nomadix Gateway - Role in PMS Integration**	46
6.1	What the Gateway Does	46
6.2	Gateway Requirements	47
6.3	Serial Connection Option	48

#	Section	Page
7	**Integration with Nomadix Products**	48
7.1	Captive Portal	48
7.2	Cloud Telephony	51
7.3	EMS (Energy Management Solution)	53
7.4	Casting and IPTV	54
8	**Readiness and Go-Live Checklist**	55
8.1	Pre-Configuration Readiness	55
8.2	Configuration Completeness Checklist	56
8.3	Go-Live Validation Tests	57
9	**Monitoring and Operations**	58
9.1	Daily Checks	58
9.2	After PMS Maintenance or Network Outage	59
10	**Troubleshooting**	59
10.1	Quick Triage	59
10.2	PMS Link Down or Inactive	61
10.3	Product Not Responding to PMS Events	61
10.4	Event Issues	62
10.5	Escalation	63
11	**INTRODUCTION**	64
11.1	Scope and Purpose	64
11.2	Documentation Conventions	64
11.3	Technical Assistance	65
12	**OVERVIEW**	66
13	**NOMADIX CLOUD PMS MODULE OVERVIEW**	67
13.1	PMS Dashboard	68
13.2	Room Status	69
13.3	Events	70
13.4	Transactions	70
13.5	Settings	71
14	**FEATURES AND FUNCTIONALITY**	71
15	**COMMERCIAL PRODUCT LICENSES**	72
16	**SUPPORTED PMS SOFTWARE**	72
17	**PMS INTERFACE MODULE CONFIGURATION**	73
17.1	Configuration for On-site PMS Software (Using PMS Redirector) via Gateway	74

#	Section	Page
17.2	Configuration for Legacy PMS Software (Using PMS Redirector) via Gateway	78
18	**DISCLAIMER**	83
18.1	Resources	84
19	**Download this guide**	85
20	**INTRODUCTION**	85
20.1	Scope and Purpose	85
20.2	Documentation Conventions	85
20.3	Further Reading	85
21	**OHIP INTEGRATION PRESENTATION**	85
21.1	Overview	85
21.2	Oracle Hospitality Integration Platform (OHIP)	85
21.3	Commercial Licensing Model	86
22	**OHIP INTEGRATION CONFIGURATION**	88
22.1	Process Overview	88
22.2	Register Interest for the Nomadix OHIP Integration	88
22.3	Collect the Customer Environment Details	89
22.4	Approve the Customer Environment Creation	89
22.5	Approve Business Events Streaming	90
22.6	Remove the Customer Environment	91
22.7	OHIP API Fair Use Policy	91

Nomadix PMS Guide

PMS Integration

Overview

A Property Management System (PMS) is software that facilitates the main processes in a hotel related to internal and external operations. The most important functions include front-desk services, reservations, channel management, housekeeping, rate and occupancy management, and payment processing. It may also manage housekeeping and perform human resources management.

PMS integration allows third party software applications to communicate and share data to streamline processes, reduce errors and save a lot of time spent on manual data transfer. Working with the same information across different platforms and updating it in real time also enables the delivery of enhanced services.

PMS integration is a complex topic. There are hundreds of solutions on the market, ranging from legacy products designed in the 80s and still in use today, all the way to modern cloud-based platforms. While a few interconnection methods such as the Fidelio Interface Application Standard (FIAS) or the Marriott WFB/FOSSE dominated the industry for many years and were used by many PMS software, it is also not uncommon to find systems using proprietary APIs.

PMS Module Overview

For over 25 years, Nomadix has been a trusted vendor to the world's largest hospitality brands and has built a strong PMS integration experience. Initially designed to offer per room guest billing for High Speed Internet Access (HSIA), Nomadix PMS integration can be used to support several Nomadix product use cases as described further in this guide. The Nomadix PMS Module receives live data from the hotel PMS including guest check-in and check-out events, room move events, room occupancy status and guest identity and makes that data available to Nomadix products. Nomadix PMS module can also send data to the PMS system for certain use cases such as posting charges for internet usage or updating housekeeping room status in the PMS. PMS integration facilitates a 2-way communication between PMS and Nomadix products.

Key Benefits for Properties

Nomadix PMS Integration Module -

- Allows the hotel staff to offer a more personalized service to guests calling from their rooms, thanks to the display of their name and room number:
- Automatically opening optional services such as a voicemail box upon a guest check-in.
- Automatically closing services and clearing logs upon guest check-out.
- Facilitating advanced functionality such as enabling a maid to use housekeeping codes from in-room phone to update room status.
- Activates energy management routines before guests arrive, reducing waste while keeping guests comfortable

- Is a single integration point connecting the hotel PMS to all applicable Nomadix products
- Provides a more personalized experience for in-room casting experience.
- Provides ability to get guest loyalty information from PMS system to authenticate guest for internet access.
- Provides ability to charge for premium internet access.

Logical Components

The PMS Module operates across three layers. Understanding these layers helps you configure and troubleshoot correctly.

Componer	Description	Location
Hotel PMS	A **PMS application** containing the source data and capable of sending out events, including check-in/out information.	This can be -A **legacy** system deployed on a local site and requiring serial or Ethernet connection ORA modern **cloud** platform.
Nomadix Gateway (NSE)	For on-premise PMS systems: the on-site connector that facilitates 2-way interaction between PMS and Nomadix products via Nomadix Cloud. Note that Nomadix gateway is needed for Cloud hosted PMS systems as well for the purpose of licensing and management.	On-site (server room or cabinet)
Nomadix Cloud Platform including PMS Module (and events engine)	The cloud-side hub. Receives and sends events from/to the Gateway or directly from cloud PMS APIs. Provides the Dashboard, Rooms, Events, Transactions and Settings views.	Nomadix Cloud (hosted)
Events Engine	Application that parses incoming PMS events from the connectors to the telephony platform. This can either be: Delivered by Nomadix as part of the **Nomadix Cloud** platform as a chargeable option.An alternative middleware application developed by a **Partner** if preferred.	Nomadix Cloud or external
Nomadix product modules	Captive Portal, Cloud Telephony, EMS, Casting / IPTV.	Nomadix Cloud with on-site components for some products

Integration with Nomadix Products

The table below shows features facilitated by PMS integration for various Nomadix products.

Nomadix product	What PMS integration enables
Captive Portal	Guest authentication for internet access. Post charges to PMS for premium internet access.
Cloud Telephony	Guest name update on room extension (activate at check-in and clear at check-out). Guest name display.Update housekeeping room status to PMS.Clear Voicemailbox on guest check-out.
EMS	Thermostat pre-conditioning on guest check-in. Setback on guest check-out.
Casting	Customize Casting interface with personalized information at check-inClear out guest information at check-outInformation transfer on room move.
IPTV	Same lifecycle model as Casting.

The table below shows exactly what PMS data each Nomadix product uses and what integration method it applies. For more details, refer Supported PMS Integration Matrix.

Nomadix product	PMS functions used	Method
Casting	Check-in / Check-out / Room move	Events
Cloud Telephony	Check-in / Check-out / Room move / Housekeeping status update	Events, Post, and Query
Captive Portal	Guest authentication	Post and QueryEvents (optional)
EMS	Check-in / Check-out / Room move	Events
IPTV	Check-in / Check-out / Room move	Events

Supported PMS Types

Overview

The PMS Module supports a wide range of PMS systems across two main deployment categories: On-Premise and Cloud. Your configuration depends on which category the property's PMS falls into.

On-Premise PMS Systems

On-premise PMS systems are installed at the hotel and connect to the Nomadix Gateway on the local network. Two interface types are supported for on premise PMS systems:

- FIAS (Fidelio Interface Application Specification)
- Marriott PMS Redirector (MICROS/WFB/FOSSE)

Cloud PMS Systems

Cloud PMS systems can communicate directly with Nomadix Cloud. The Nomadix Gateway is still required on-site as the local edge connector for other services.

Legacy PMS Systems - Limited Interface

A group of on-premises PMS systems use MICROS emulation (versions 1700, 2000, 3700, 4700 or 8700 System Software Emulation). These provide limited integration and are configured on the Gateway only. There is no cloud-side PMS Module configuration for these systems.

The following chapters provide detailed setup and configuration information for these multiple scenarios.

Supported PMS Interfaces and Types

Over the years, Nomadix certified interoperability with a variety of PMS software. The received data can then either be used internally within the Gateway connector and/or Nomadix Cloud for the provision of Nomadix originated guest services or forwarded to a third party destination to enhance their services.

Warning

There are different levels of interoperability, depending on the data fields and APIs supported by individual PMS software. Carefully check Integration with Nomadix Products to determine which PMS functions must be supported in order to achieve desired functionality.

While only a few PMS interfaces include the check-in/out field, they tend to be the ones that still dominate the market today. Do not scope Cloud Telephony lifecycle automation, EMS occupancy control or Casting / IPTV session management for any PMS system in the limited interface group. Confirm the interface type with the customer before project scoping.

Contact Nomadix if the PMS software you are looking for is not listed in the matrix below. The tables show interface types rather than individual vendor names, as more platforms than listed comply with one of these standards, but don't always publicly advertise it.

The following PMS integration matrix shows the supported PMS systems, interfaces, along with the functions supported by Nomadix products for the corresponding PMS system.

For full PMS integration details, refer to the PMS Integration Matrix.

Commercial Licensing

The PMS Module requires licensing before it can be deployed. Licensing is tied to the Nomadix Gateway model at the property. Confirm all licenses are in place before beginning configuration.

Required Licenses

License	Type	Description
PMS Module License	One-off	Initial activation of PMS functionality on the gateway and Nomadix Cloud. One license per gateway model.
PMS Interface License	Recurring	Ongoing PMS functionality including software updates and support. Available in 1-, 3- or 5-year terms.

Notes


sEach gateway model (EG 1000, EG 3000, EG 5000 or EG 6000) has a specific part number for both the PMS Module License and the PMS Interface License. Refer to the Nomadix price book for current part numbers and pricing.For PMS systems connecting Nomadix gateway via serial connections, an optional PMS Serial Hardware Integration Kit (part number 715-5001-010) is available separately from Nomadix. It includes the DB9-to-RJ45 cable and an optical isolator for circuit protection.

Oracle OHIP Licensing

The Nomadix OHIP integration is subject to fees. Oracle operates a usage-based billing model, where it charges vendors, in this case Nomadix, for the number of calls made to the Oracle platform. Nomadix passes this cost to Managed Service Providers (MSPs) in the way of a recurring license, which in turn is passed to end-customers.

The Nomadix commercial licensing model for OHIP comprises of 4 components:

- **PMS Module License:** One-off cost for the initial activation of the PMS functionality on Nomadix Gateways + Nomadix Cloud. The charge is specific to each gateway model.
- **OHIP Module License:** One-off cost for the initial activation of the OHIP functionality on Nomadix Gateways + Nomadix Cloud. The charge is specific to each gateway model
- **PMS Interface License:** Recurring cost for the use of the PMS functionality on Nomadix Gateways + Nomadix Cloud, including software updates, as well as hardware and software support. The charge is specific to each gateway model, with options for 1-, 3- and 5-years contracts.
- **OHIP Interface License:** Recurring cost for the Oracle usage-based billing model. The charge is specific to each gateway model, with options for 1-, 3- and 5-years contracts.



Warning

sMSPs are responsible for paying the Nomadix OHIP license fees for the properties they manage. In turn, they pass this cost onto their respective customers, same as in the case of any other Nomadix license they resell.Each site requires a Nomadix Gateway acting as a local edge connector and which must be correctly licensed for the other services it is expected to deliver.The OHIP license described in this document is solely for the exchange of events between the Oracle and the Nomadix platforms. Customers must have valid licenses for the use of Oracle solutions.Excessive Usage: the OHIP license is intended for typical property activity and is subject to customers agreeing to the Fair Use Policy. Non-typical usage, determined at Nomadix' sole discretion, may incur additional usage charges. In addition, if Nomadix determines that abnormal, unreasonable or impermissible usage is occurring, additional steps such as suspension or termination of the license may occur.Oracle requires that customers purchase a mandatory OHIP Premium Remote assistance 4 hour workshop to engage with Oracle Professional Services and learn how to enable streaming. Further details can be found here (public information).

OHIP API usage and Fair Use Policy

Nomadix sets its OHIP license fees after careful estimation of API usage based on the property size and the Nomadix gateway on-site. The OHIP license tiers are designed to provide flexibility and scalability to Nomadix MSPs.

OHIP licenses are intended for typical property activity and are subject to customers agreeing to the Fair Use Policy. Non-typical usage, determined at Nomadix' sole discretion, may incur additional usage charges. In addition, if Nomadix determines that abnormal, unreasonable or impermissible usage is occurring, additional steps such as suspension or termination of the license may occur.

Warning

Oracle also requires customers to purchase a mandatory OHIP Premium Remote Assistance 4-hour workshop to enable business event streaming. This is an Oracle requirement and is not covered by Nomadix licensing. Budget for this when scoping OHIP deployments.

PMS Vendor Licensing

Some PMS vendors require their own third-party interface license before they will allow an external system to connect. This cost is separate from Nomadix licensing and is paid directly to the PMS vendor. Confirm this with the PMS vendor before scheduling a deployment.

Configuration

This section provides step-by-step configuration procedures for each supported PMS type.


Prerequisites Before Any Configuration

Confirm all of the following are in place before beginning configuration:

- This section provides step-by-step configuration procedures for each supported PMS type.
- The Nomadix Gateway is registered in Nomadix Cloud under the correct property.
- The PMS Module license is confirmed as active for the gateway model.
- The PMS is running and the PMS vendor has confirmed the interface is enabled for third-party access.
- For on-premise PMS: make sure that the PMS IP address and TCP port are known, and that the gateway can reach that address. If the PMS requires a serial connection, you must purchase the Nomadix PMS Serial Hardware Integration Kit (part number 715-5001-010)
- For Oracle OHIP: OPERA Cloud Foundation is purchased, and the Oracle Developer Portal URL has been received.

Configure On-Premise PMS system using FIAS via Nomadix Gateway

This chapter provides detailed setup and configuration information for the use of a Nomadix Gateway as a Cloud Connector to integrate with a legacy PMS software that use FIAS interface.



There are two parts to this configuration: the Gateway configuration and Nomadix Cloud configuration. Complete the Gateway steps first then proceed to the Cloud configuration steps.

The current Edge Gateway (EG) family comprises of 4 main models: the EG 1000, EG 3000, EG 5K and EG 6000, offering different maximum capacities in terms of bandwidth and concurrent number of devices.

All Nomadix Gateways are powered by the same patented suite of embedded software, called the Nomadix Service Engine™ (NSE). In addition to the native core functionality, extra features and services, such as PMS integration, are enabled through the purchase of optional software license modules.

For serial connection, an optional (sold separately by Nomadix) PMS Serial Hardware Integration Kit (part number 715-5001-010) is available and includes the necessary cable and built-in optical isolator for circuit protection to the PMS.

Step 1 - Configure the Nomadix Gateway


- Before proceeding with the steps below, Register the product by completing the Nomadix Gateway Registration Form online at the following address: https://nomadix.com/product-registration/
- Once registered, follow the gateway installation process, cabling, and initial configuration as outlined in Gateway Administration Guide.

Warning


The PMS port should only be used for serial connection to PMS using the dedicated cable. Connecting other devices can result in failure.

Step 2: Configure Gateway PMS Interface Module Configuration

1. From the Web Management Interface, click on Configuration, then PMS. The Property Management System Settings screen below appears:




2. To disable PMS services, select the PMS services disabled option.
3. Enable the FIAS PMS Redirector service by selecting its corresponding radio button.
4. Click the Configure hyperlink positioned adjacent to the active radio button.
5. Under Link Options, select TCP/IP, then supply the target PMS IP Address and TCP Port Number. Click Save.NoteFor serial (RS232) connections instead of TCP/IP, connect the optional PMS Serial Hardware Integration Kit (part number 715-5001-010) and select the serial option instead of TCP/IP.
6. The Type of PMS and Post-paid PMS Type fields are only used when configuring guest HSIA services.
7. In Miscellaneous settings, enable Syslog PMS communications if you wish to record PMS events.
8. Click on the Save button (scroll to the bottom of the screen)
9. The PMS Port Test Mode provides a utility to confirm that the PMS serial port is working, by checking both transmit and receive capabilities, as a functional equivalent of an external loopback test. To test the PMS port, click PMS Port Test Mode, then click Save.



Next, the Nomadix Gateway needs to be configured to forward PMS data either to the Nomadix Cloud.

1. From the Web Management Interface, click on AAA, the screen below appears:
2. Click Configure next to XML Interface.
3. Enable the Enable Authentication via XML User Credentials checkbox.

4. Click the User Credentials hyperlink, then define your custom XML API username and password. Click Save.
5. Navigate to Configuration > AAA > Internal Web Server tab.




6. In the Portal XML POST URL field, enter: https://nomadix.cloud/network/api/nomadix_xml
7. We recommend using port 443 and enabling “SSL Support”, however if needed “SSL Support” can be disabled and port 80 used.
8. Navigate to Configuration > Access Control and input the matching port value into the HTTP Port field.

Step 3 - Create or Confirm the Property in Nomadix Cloud


Complete these steps in Nomadix Cloud.

1. In Nomadix Cloud, go to Properties from the left-hand menu.

2. Click the + New Property.



3. Complete all required fields within the New Property modal form:



Properties
New Property
Name *
Angelica Hotel
Venue type *
Hospitality: Brand HQ / Other
Site Code *
ABCD1234
Customer Code
Customer
Sub brand
Type *
Demo
Address
Address 1
Address 2
City
State
Postcode
Country Code *
United States
Latitude
Longitude
Contact Details
Primary Contact Number
Primary Support Number
Localization Preferences
Timezone *
Locales
en
Default Locale *
en
Temperature Unit *
Fahrenheit
Distance Unit *
Imperial
Currency *
United States Dollar (USD)
Cancel
Create Property

Fields	Description
Name	The hotel or site name.
Venue Type	Select the appropriate venue type from the pull-down list.
Site Code	This can be any unique alpha-numeric identifier. It is best practice to use the same ID assigned to the property from the hotel brand. If the Gateway is going into a lab, then this can be a random number.
Type	Select the appropriate type from the pull-down list.
Country Code	Select the appropriate country code from the pull-down list.
Timezone	The time zone where the hotel is located. This is important as it affects operations scheduled to take place at a specific time.
Default Locale	Refers to the local language. Currently only English (en) is supported.
Temperature Unit	Whether the administrator prefers to display temperature information using Fahrenheit or Celsius.
Distance Unit	Whether the administrator prefers to display distance measurements in Imperial or Metric.
Currency	Select the appropriate currency from the pull-down list.


Step 4 - Deploy the Networks Module

Complete these steps if the Networks module is not already deployed.

1. From the Property dashboard, click + Deploy Product and select Networks.



2. Accept the End User License Agreement (EULA) and click Deploy.
   The Networks tile will appear on the dashboard.
3. Click the Networks tile and go to Nomadix Gateways.
4. If the gateway is not already listed, click New Gateway and enter the serial number, NSE ID and model number (found on the label on the bottom of the unit).




The Gateway is attached to this Property and can be viewed by clicking on it.


Step 5 - Set Gateway XML Connectivity

This step establishes communication between Nomadix Cloud and the Gateway.


1. From the property dashboard, click the Networks tile.
2. From the left side navigation menu, Select Nomadix Gateways and click on the gateway being configured.



3. The Gateway initially appears offline. Click on the Connectivity widget to configure the parameters.



4. Click on the pen icons to configure Connectivity for Ping, SFTP/SSH, SNMP and XML. Click Submit to save each configuration and return to the Gateway Management page.
   The XML API is the most important for the PMS integration functionality:Mandatory Fields:CommentsXML API Address:This is the public IP address of the local gateway as it would appear from Nomadix Cloud. This can be a static, public IP address for the gateway, or a WAN address with port forwarding turned on to reach the gateway.XML API Port:The port set for the XML API during the gateway configuration.XML API Username:The username setup for the XML API during the gateway configuration.XML API Password:The password setup for the XML API during the gateway configuration.




5. Click Enable XML API Endpoint then Submit.
6. If the Gateway and Nomadix Cloud are configured correctly, the XML API shows a green indicator after one to two minutes. If the indicator goes to red, there is something wrong with the XML API connection, recheck the Gateway configuration from Step 1.Once all the Connectivity parameters are configured, the activity graphs will populate.




Step 6 - Deploy and Configure the PMS Module


1. Scroll down the Properties list or use the search field in the top menu bar to find the desired site and click on it:
2. Once selected, click the + Deploy Product button.




3. Select the PMS module from the drop-down list and accept the End User License Agreement (EULA), then click the Deploy button.



4. Once done, click the PMS tile.



5. Once done, click on the Configuration button to enter the base settings:




6. Fill-in the fields and click Submit to save:

Fields:	Description
PMS Type	Select the appropriate PMS type from the pull-down list.
Name/Room Authentication Format	Specify the format of name/room authentication requests. Example: '!ti,!fn,!sn' where !ti is Title, !fn is First Name and !sn is Surname.
Nomadix Gateway	Select the Nomadix gateway from the pull-down list.
FIAS Loyalty Data Field	This allows to map hospitality brands' loyalty tiers. This field is not used for telephony PMS integration.
Loyalty Tier Mapping	Define a comma-separated list of strings that will be used to map the PMS loyalty tier to the Nomadix Cloud one. This field is not used for telephony PMS integration.
Custom Loyalty Tier Names	Indicate the loyalty unset custom name.
Hotel Code/Property ID	Specify the hotel unique code or ID.
API Basic Authentication	Enter the username/password or client ID/secret key for the PMS connectivity API authentication.
API Region	Select the appropriate region from the pull-down list.

Step 7 - Set Up Rooms (Optional)

The PMS interface determines the number of rooms based on events received from the PMS system but cannot assign floors or buildings automatically. Use this step if floor and building organisation is needed.

1. From the property dashboard, click the Rooms tile.



2. Click New Rooms.
3. Enter the Floor number, Building name (default: Main) and a room number or range. A range is entered as 100...110 for rooms 100 to 110. Separate individual rooms with commas.
4. Click Create Rooms. Repeat for all floors and buildings.

Step 8 - Test the Configuration

1. Ask the hotel front desk staff to perform a test guest check-in or check-out operation from the PMS.
2. Verify that the event is received and processed successfully by the Nomadix system.
3. On the Rooms page, confirm that the room appears with the correct occupancy status within 1 to 2 minutes after the PMS event is triggered.
4. Verify that the room tile status indicators update correctly based on the guest check-in or check-out state.
5. Click Events to verify that check-in and check-out events appear in the log.

Configure On-Premise PMS System using Marriott PMS Redirector

Use this procedure for Marriott-branded properties using the MICROS/WFB/FOSSE interface.

Warning

Marriott brand standards apply to this integration. Confirm all certification and brand requirements with the hotel brand team before configuring.

Step 1 - Configure the Nomadix Gateway

Before proceeding with the steps below, Register the product by completing the Nomadix Gateway Registration Form online at the following address: https://nomadix.com/product-registration/

Once registered, follow the gateway installation process, cabling, and initial configuration as outlined in Gateway Administration Guide.

Warning

The PMS port should only be used for serial connection to PMS using the dedicated cable. Connecting other devices can result in failure.


Step 2: Configure Gateway Marriott PMS Interface Module Configuration

1. From the Web Management Interface, click on Configuration, then PMS. The Property Management System Settings screen appears.
2. To disable PMS services, select the PMS services disabled option.

3. Enable the Marriott PMS Redirector service by selecting its corresponding radio button.
4. Click the Configure hyperlink positioned adjacent to the active radio button.
5. Under the interface connection options, provide the hardware serial parameters. NoteFor properties utilizing direct serial connections over older infrastructure, connect the dedicated USB-to-RS232 connection cable (part #715-4001-001) or the optional PMS Serial Hardware Integration Kit (part #715-5001-010) and verify that the interface is set to standard serial tracking.
6. Enter the unique system serial number inside the configuration parameters field and click Save.

Set up the local edge system to securely route its incoming data streams toward the Nomadix cloud platform.

1. From the Web Management Interface, click on AAA, the screen below appears:
2. Click Configure next to XML Interface.
3. Enable the Enable Authentication via XML User Credentials checkbox.
4. Click the User Credentials hyperlink, then define your custom XML API username and password. Click Save.
5. Navigate to Configuration > AAA > Internal Web Server tab.




6. In the Portal XML POST URL field, enter: https://nomadix.cloud/network/api/nomadix_xml
7. We recommend using port 443 and enabling “SSL Support”, however if needed “SSL Support” can be disabled and port 80 used.
8. Navigate to Configuration > Access Control and input the matching port value into the HTTP Port field.

Step 3 - Create or Confirm the Property in Nomadix Cloud

Complete these steps in Nomadix Cloud.

1. In Nomadix Cloud, go to Properties from the left-hand menu.
2. Click the + New Property.




3. Complete all required fields within the New Property modal form:

Fields	Description
Name	The hotel or site name.
Venue Type	Select the appropriate venue type from the pull-down list.
Site Code	This can be any unique alpha-numeric identifier. It is best practice to use the same ID assigned to the property from the hotel brand. If the Gateway is going into a lab, then this can be a random number.
Type	Select the appropriate type from the pull-down list.
Country Code	Select the appropriate country code from the pull-down list.
Timezone	The time zone where the hotel is located. This is important as it affects operations scheduled to take place at a specific time.
Default Locale	Refers to the local language. Currently only English (en) is supported.
Temperature Unit	Whether the administrator prefers to display temperature information using Fahrenheit or Celsius.
Distance Unit	Whether the administrator prefers to display distance measurements in Imperial or Metric.
Currency	Select the appropriate currency from the pull-down list.


Step 4 - Deploy the Networks Module

Complete these steps if the Networks module is not already deployed.

1. From the Property dashboard, click + Deploy Product and select Networks.



2. Accept the End User License Agreement (EULA) and click Deploy.
   The Networks tile will appear on the dashboard.
3. Click the Networks tile and go to Nomadix Gateways.
4. If the gateway is not already listed, click New Gateway and enter the serial number, NSE ID and model number (found on the label on the bottom of the unit).




The Gateway is attached to this Property and can be viewed by clicking on it.


Step 5 - Set Gateway XML Connectivity

This step establishes communication between Nomadix Cloud and the Gateway.


1. From the property dashboard, click the Networks tile.
2. From the left side navigation menu, Select Nomadix Gateways and click on the gateway being configured.



3. The Gateway initially appears offline. Click on the Connectivity widget to configure the parameters.



4. Click on the pen icons to configure Connectivity for Ping, SFTP/SSH, SNMP and XML. Click Submit to save each configuration and return to the Gateway Management page.
   The XML API is the most important for the PMS integration functionality:Mandatory Fields:CommentsXML API Address:This is the public IP address of the local gateway as it would appear from Nomadix Cloud. This can be a static, public IP address for the gateway, or a WAN address with port forwarding turned on to reach the gateway.XML API Port:The port set for the XML API during the gateway configuration.XML API Username:The username setup for the XML API during the gateway configuration.XML API Password:The password setup for the XML API during the gateway configuration.




5. Click Enable XML API Endpoint then Submit.
6. Click Enable XML API Endpoint then Submit.
7. If the Gateway and Nomadix Cloud are configured correctly, the XML API shows a green indicator after one to two minutes. If the indicator goes to red, there is something wrong with the XML API connection, recheck the Gateway configuration from Step 1.Once all the Connectivity parameters are configured, the activity graphs will populate.




Step 6 - Deploy and Configure the PMS Module


1. Scroll down the Properties list or use the search field in the top menu bar to find the desired site and click on it:
2. Once selected, click the + Deploy Product button.




3. Select the PMS module from the drop-down list and accept the End User License Agreement (EULA), then click the Deploy button.



4. Once done, click the PMS tile.



5. Once done, click on the Configuration button to enter the base settings:




6. Fill-in the fields and click Submit to save:

Fields:	Description
PMS Type	Select the Marriott PMS via Nomadix Gateway from the pull-down list.
Name/Room Authentication Format	Specify the format of name/room authentication requests. Example: '!ti,!fn,!sn' where !ti is Title, !fn is First Name and !sn is Surname.
Nomadix Gateway	Select the Nomadix gateway from the pull-down list.
Loyalty Data Field	This allows to map hospitality brands' loyalty tiers. This field is not used for telephony PMS integration.
Loyalty Tier Mapping	Define a comma-separated list of strings that will be used to map the PMS loyalty tier to the Nomadix Cloud one. This field is not used for telephony PMS integration.
Custom Loyalty Tier Names	Indicate the loyalty unset custom name.
Hotel Code/Property ID	Specify the hotel unique code or ID.
API Basic Authentication	Enter the username/password or client ID/secret key for the PMS connectivity API authentication.
API Region	Select the appropriate region from the pull-down list.

Step 7 - Set Up Rooms (Optional)

The PMS interface determines the number of rooms based on events received from the PMS system but cannot assign floors or buildings automatically. Use this step if floor and building organisation is needed.

1. From the property dashboard, click the Rooms tile.



2. Click New Rooms.
3. Enter the Floor number, Building name (default: Main) and a room number or range. A range is entered as 100...110 for rooms 100 to 110. Separate individual rooms with commas.
4. Click Create Rooms. Repeat for all floors and buildings.


Configuring Cloud PMS

Cloud-to-cloud integrations are simpler than on-premise configurations. The Gateway does not require PMS Module interface configuration. However since gateway is needed as local edge connector, add the gateway and Complete basic configuration for gateway by following Gateway administration guide.


Step 1 - Create or Confirm the Property in Nomadix Cloud

Complete these steps in Nomadix Cloud.

1. In Nomadix Cloud, go to Properties from the left-hand menu.
2. Click the + New Property.



3. Complete all required fields within the New Property modal form:



Properties
New Property
Name *
Angelica Hotel
Venue type *
Hospitality: Brand HQ / Other
Site Code *
ABCD1234
Customer Code
Customer
Sub brand
Type *
Demo
Address
Address 1
Address 2
City
State
Postcode
Country Code *
United States
Latitude
Longitude
Contact Details
Primary Contact Number
Primary Support Number
Localization Preferences
Timezone *
Locales
en
Default Locale *
en
Temperature Unit *
Fahrenheit
Distance Unit *
Imperial
Currency *
United States Dollar (USD)
Cancel
Create Property

Fields	Description
Name	The hotel or site name.
Venue Type	Select the appropriate venue type from the pull-down list.
Site Code	This can be any unique alpha-numeric identifier. It is best practice to use the same ID assigned to the property from the hotel brand. If the Gateway is going into a lab, then this can be a random number.
Type	Select the appropriate type from the pull-down list.
Country Code	Select the appropriate country code from the pull-down list.
Timezone	The time zone where the hotel is located. This is important as it affects operations scheduled to take place at a specific time.
Default Locale	Refers to the local language. Currently only English (en) is supported.
Temperature Unit	Whether the administrator prefers to display temperature information using Fahrenheit or Celsius.
Distance Unit	Whether the administrator prefers to display distance measurements in Imperial or Metric.
Currency	Select the appropriate currency from the pull-down list.


Step 2 - Deploy the Networks Module

Complete these steps if the Networks module is not already deployed.

1. From the Property dashboard, click + Deploy Product and select Networks.



2. Accept the End User License Agreement (EULA) and click Deploy.
   The Networks tile will appear on the dashboard.
3. Click the Networks tile and go to Nomadix Gateways.
4. If the gateway is not already listed, click New Gateway and enter the serial number, NSE ID and model number (found on the label on the bottom of the unit).



The Gateway is attached to this Property and can be viewed by clicking on it.

Step 3 - Deploy and Configure the PMS Module

1. Scroll down the Properties list or use the search field in the top menu bar to find the desired site and click on it:
2. Once selected, click the + Deploy Product button.




3. Select the PMS module from the drop-down list and accept the End User License Agreement (EULA), then click the Deploy button.



4. Once done, click the PMS tile.



5. Once done, click on the Configuration button to enter the base settings:




6. Fill-in the fields and click Submit to save:Fields:DescriptionPMS TypeSelect the appropriate PMS Type from the pull-down list.Name/Room Authentication FormatSpecify the format of name/room authentication requests. Example: '!ti,!fn,!sn' where !ti is Title, !fn is First Name and !sn is Surname.Nomadix GatewaySelect the Nomadix gateway from the pull-down list.Loyalty Data FieldThis allows to map hospitality brands' loyalty tiers. This field is not used for telephony PMS integration.Loyalty Tier MappingDefine a comma-separated list of strings that will be used to map the PMS loyalty tier to the Nomadix Cloud one. This field is not used for telephony PMS integration.Custom Loyalty Tier NamesIndicate the loyalty unset custom name.Hotel Code/Property IDSpecify the hotel unique code or ID.API Basic AuthenticationEnter the username/password or client ID/secret key for the PMS connectivity API authentication.API RegionSelect the appropriate region from the pull-down list.

Step 4 - Set Up Rooms (Optional)

The PMS interface determines the number of rooms based on events received from the PMS system but cannot assign floors or buildings automatically. Use this step if floor and building organisation is needed.

1. From the property dashboard, click the Rooms tile.



2. Click New Rooms.
3. Enter the Floor number, Building name (default: Main) and a room number or range. A range is entered as 100...110 for rooms 100 to 110. Separate individual rooms with commas.
4. Click Create Rooms. Repeat for all floors and buildings.

Step 5 - Test the Configuration

1. Ask the hotel front desk staff to perform a test guest check-in or check-out operation from the PMS.
2. Verify that the event is received and processed successfully by the Nomadix system.
3. On the Rooms page, confirm that the room appears with the correct occupancy status within 1 to 2 minutes after the PMS event is triggered.
4. Verify that the room tile status indicators update correctly based on the guest check-in or check-out state.
5. Click Events to verify that check-in and check-out events appear in the log.

Notes

sIf housekeeping is supported by PMS, additional fields will appear that need to be configured. Housekeeping section is covered here in Housekeeping Events in the guide.If the cloud PMS system you are working with is not listed in the PMS Type drop-down, contact Nomadix. New vendor integrations are regularly added.


Configuring Cloud PMS: Oracle OPERA Cloud (OHIP)

Oracle Hospitality's OPERA Cloud is the leading Property Management System in the World. Interconnectivity is achieved via the Oracle Hospitality Integration Platform (OHIP). Validated connectors to OHIP are offered via the Oracle Cloud Marketplace.

As a member of the Oracle partner network, Nomadix offers a validated OHIP integration advertised on the Oracle Cloud Marketplace, which enables the exchange of events for 2-way interactions between OHIP and Nomadix Gateways + Nomadix Cloud. Once the link is established, it can be used with several Nomadix Products, including Captive Portal, Cloud Telephony, Energy Management, and more.

The Nomadix commercial licensing model for OHIP comprises of 4 components. Refer to Commercial Licensingin this guide for more details.

Nomadix sets its OHIP license fees after careful estimation of API usage based on the property size and the Nomadix gateway on-site. The OHIP license tiers are designed to provide flexibility and scalability to Nomadix MSPs based on a fair use policy. Refer to Commercial Licensing in this guide for more details.




The Nomadix OHIP integration is subject to fees. Oracle operates a usage-based billing model, where it charges vendors, in this case Nomadix, for the number of calls made to the Oracle platform. Nomadix passes this cost to Managed Service Providers (MSPs) in the way of a recurring license, which in turn is passed to end-customers.

This configuration requires four steps involving the MSP, Nomadix, and Oracle. You must complete these steps in order.

Warning

Do not attempt to skip steps or complete them out of order. The environment cannot be used until customer approval is received in Step 3 and streaming must be approved separately in Step 4.


OHIP configuration must be completed in the correct order. The deployment includes four main steps.




Step 1: Register Interest for the Nomadix OHIP Integration

As a member of the Oracle partner network, Nomadix offers a validated OHIP integration advertised on the Oracle Cloud Marketplace. The first step of the process is to register interest via this site.

- Go to the Oracle Hospitality Marketplace (here) and search for Nomadix.
- Click on Nomadix Cloud and then click on the Get App button.
- Log into your Oracle account or create one.
- Fill-in the form to register interest for the integration.
- This notifies both Oracle and Nomadix of a project requirement.









Step 2: Collect the Customer Environment Details

Please **collect the following information** from the customer and **send it to** support@Nomadix.com:

- **Production Status:** Many hotels run non-production OPERA Cloud environments as well as their production environment(s). Customers must determine whether the OPERA Cloud environment in use is a production or non-production instance.
- **Region:** The region where the customer's OPERA Cloud setup is running.
- **Tenant / Chain Code:** The customer's tenant code used to target the right tenant, especially in OPERA Cloud environments that host multiple tenants.
- **Hotel ID:** The hotel's OPERA internal ID for the tenant.
- **Enterprise ID:** The unique identifier for the enterprise. This can be found in the environment details of the customer in the OPERA Cloud Identity Management portal.

Warning

The next steps cannot be completed without the above details.Customers can find the requested information via the OHIP Customer Portal.

Step 3: Approve the Customer Environment Creation

Customers require unique environments for integrations between OHIP and partner applications. As a member of the Oracle partner network, Nomadix is responsible for setting-up environments (accounts) for all customers requiring OHIP integrations, which can only be done once the key details indicated in the earlier step have been provided by customers. Environments then only become live once customers approve them.

Warning

sCustomers must have purchased and be using OPERA Cloud Foundation before Nomadix can create environments.Customers do not have permissions to create or edit environments in Oracle Developer or Partner Portal, as Oracle intends for partners like Nomadix, to create and manage the customers' environments.

Notes

sCustomers have access to the OHIP Customer Portal to view environments and to manage partner connection requests.The guide Getting Started for Hoteliers (for Oracle Hospitality OPERA Cloud Foundation Users with Oracle Hospitality Shared Security Domain) can be found here (public information).

- Nomadix creates the environment using the key details provided by the customer.
- Upon completion, customers' administrators receive a connection request for approval. The environment remains in a pending state until acceptance. Follow the below steps to approve the request:
- From the Developer Portal, click Environments at the top of the page.
- Click Partner Connections to display the list.

- Search for the partner connection that is pending approval, here Nomadix.
- Search for and select the properties to assign to the partner connection.
- Click Next.
- Review the Summary and click Approve. The status of the partner connection request should change to Approved in both the Customer and Partner Portals.
- An email notification confirming the approval of the connection request is sent.
- The customer's environment is ready for use within 5 minutes of approval and can start calling OHIP APIs and streaming events.

Notes

sCustomers can reject connection requests and revoke access to previously approved ones.Nomadix Cloud tracks OHIP API usage for each customer.

Step 4: Approve Business Events Streaming

Nomadix products and services provide real-time and on-demand features through the OHIP integration, provided they can consume business events from the OHIP interface. These are updates to the state of a resource, for example a reservation. Rather than Getting it repeatedly, subscribing to the update reservation event informs the system when this or other reservations are changed. Oracle Hospitality systems emit business events in multiple scenarios, such as when a guest checks-in or checks-out. Each business event contains the following information:

- **Resource:** This is the resource that has received the event, for example a reservation.
- **Event:** The name of the event, for example an update to a reservation.
- **Old Value:** This is the old value for the field.
- **New Value:** This is the new value for the field.

Oracle recommends **enabling streaming** to receive business events due to several limitations of the polling mechanism. In addition, streaming is required to receive real-time information about events such as check-in. Polling mechanisms can be used for less critical events.

Warning

Streaming is enabled at chain level, not at hotel level, so it only needs activation once.Oracle requires that customers purchase a mandatory OHIP Premium Remote assistance 4 hour workshop to engage with Oracle Professional Services and learn how to enable streaming. Further details can be found here (public information).Customers can only approve the streaming of business events for hotels to which they have access in the Developer Portal.

When integrated applications such as Nomadix Cloud consume business event data from OPERA Cloud, they can choose which ones they receive. These are the events to which the applications subscribe. Environment owners are required to approve business event subscription requests. Follow the below steps to approve them:

- Log into the Developer Portal.
- Display the list of the partners requesting to consume business events.

- Display the list of business events a partner is consuming and check from which hotels and environments the partner is consuming these events.
- Approve the business event consumption for one or many hotels within the environment.

Step 5: Removing the Customer Environment when no longer needed

Once the OHIP integration with Nomadix products is no longer required, the customer environment should be removed from the Oracle Partner Portal. This can only be done by Oracle partners.

Warning

Customers do not have permissions to remove environments in Oracle Developer or Partner Portal, as Oracle intends for the partners, here Nomadix, to remove the customers' environments.When an environment is removed, it will cease sending any events to which Nomadix Cloud had subscribed via the streaming API.The environment can be added back using the same enterprise ID and chain code that were previously used to create it, but it will be subject to a new customer approval.Customers have access to the OHIP Customer Portal to view environments.

Send a request for the environment to be removed to support@Nomadix.com

Legacy MICROS Emulation (Gateway-Only Configuration)

PMS systems using MICROS emulation (see Supported PMS Integration Matrix) are configured on the Gateway only. There is no cloud-side PMS Module configuration for these systems. They provide guest validation capability only.

Gateway Configuration

1. Log in to the Gateway Web UI.
2. Go to Configuration then PMS.
3. Select the appropriate MICROS emulation type (1700, 2000, 3700, 4700 or 8700).
4. Enter the PMS IP address and port number.
5. Click Save.

Warning

Legacy MICROS emulation deployments support guest authentication only. Cloud Telephony lifecycle automation, EMS, Casting and IPTV are not supported. Inform the customer before scoping.

Nomadix Cloud PMS Module Overview

Once the PMS Module is configured and running, Nomadix Cloud provides various functions for day-to-day monitoring and management. Access these from the left-hand menu after clicking the PMS tile on the property dashboard.

Dashboard

The PMS dashboard can be used to monitor the current status of the PMS interface and the activity on the PMS link in the last 24 hours:

Item	What it shows
PMS Status	This shows if the XML API connection between the gateway and the cloud is working and how long it has been up for.
Check-in	Number of check-in events received in the last 24 hours.
Check-out	Number of check-out events received in the last 24 hours.
Transactions	The number of PMS API transactions during the previous 24 hours. These are the REST API calls from other Nomadix Cloud modules such as Telephony, Captive Portal etc.
Events	Number of PMS messages received in the last 24 hours.
Rooms	A circular occupancy graph showing the total number of currently checked-in rooms.

Rooms

The Rooms view shows the current occupancy status of every room at the property.

Item	What it shows
Total	Total number of rooms configured for the property.
Occupied	Currently checked-in rooms. Click this tile to filter the view to occupied rooms only.
Vacant	Currently empty rooms. Click to filter.
Floors	Filter rooms by building or floor.
Room tile	Each room appears as a tile. A green border and corner indicate the room is checked in. Clicking a room shows the checked-in guest name (guest-based mode only).

Events

The Events page shows every PMS message received by the system. Use this view to confirm that check-in, check-out and room move events are arriving correctly from the PMS. This is the primary diagnostic tool for PMS connectivity issues.

Transactions

The Transactions page shows the internal calls made by other Nomadix product modules against the PMS data. For example, this is where you see Cloud Telephony querying guest check-in status. Use this view to confirm that product modules are consuming PMS data correctly.

Settings

The Settings page shows the current PMS Module configuration. Click Edit to return to the configuration form and make changes. Settings are described in detail in Configuration section .

Nomadix Gateway - Role in PMS Integration

The Nomadix Gateway is required for all on-premise and Cloud PMS deployments. Understanding its role helps you configure it correctly and troubleshoot issues when they arise.

What the Gateway Does

Gateway function	Description
On-site PMS connector	For on-premise FIAS and Marriott redirectors both systems maintain connection to the PMS and receives check-in, check-out and room move events as they occur.
Event relay to Nomadix Cloud	Forwards PMS events from the on-site PMS to Nomadix Cloud for distribution to product modules. Also sends messages to PMS e.g. posting charges, housekeeping status etc.
Local edge connector	For cloud PMS systems: the Gateway still acts as the on-site network and service delivery point even though PMS connectivity is handled cloud-to-cloud.

Gateway Requirements

Requirement	Details
Model	EG 1000, EG 3000, EG 5K or EG 6000. Each model requires the corresponding PMS Module License part number.
Firmware	Current recommended firmware version. Check with Nomadix support for the current version before deployment.
Internet access	The Gateway must be able to reach Nomadix Cloud. Outbound HTTPS (port 443) must be permitted.
PMS reachability (on-premise)	The Gateway must be able to reach the PMS IP address on the PMS TCP port. Confirm with the hotel IT team that no firewall rule blocks this traffic.
Public IP or port forwarding	Required for the XML API. Nomadix Cloud needs to reach the Gateway on the configured XML API port. This can be a static public IP or port forwarding from the WAN address.
PMS Module License	The PMS Module License must be active on the gateway before the PMS Module can be deployed in Nomadix Cloud.

Serial Connection Option

Some on-premise PMS systems connect to the Gateway via serial (RS232) rather than TCP/IP. For these deployments, the optional PMS Serial Hardware Integration Kit (part number 715-5001-010) is available from Nomadix separately. It includes the DB9-to-RJ45 cable and a built-in optical isolator for circuit protection.

Integration with Nomadix Products


Once the PMS Module is configured and receives events from the PMS, it automatically provides data to connected Nomadix product modules. Similarly, Nomadix products can query PMS or post data via Nomadix cloud to the PMS system. This section describes how each product uses PMS data and what to verify to confirm the integration is working.

Captive Portal


The PMS Module enables the Captive Portal to authenticate guests using their room number and their surname. When a guest connects to the hotel Wi-Fi, the Captive Portal validates their input against the live PMS room occupancy data.

The PMS integration can also support posting guest internet access charges to the PMS, depending on the PMS platform capabilities and configuration.

If it is intended to use the Property Management System (PMS) as an authentication method for the Captive Portal, it is then necessary to deploy the **Nomadix Cloud PMS** module.



Deploy and Configure PMS Module for your property as descibed earlier in this guide. If it is intended to offer tiered services, Loyalty Tier Mapping and Loyalty Tier Names must be provided:



Warning

The Tier names are automatically pulled from this page when configuring PMS Authentication as explained later in Captive Portal Administration Guide.

PMS event / data	Captive Portal behavior
Room occupied (check-in)	Room is eligible for authentication. Guests can connect using their room number and name.
Room vacant (check-out)	Authentication for that room is rejected automatically.

Cloud Telephony

Cloud Telephony uses PMS events to automate the phone lifecycle for each guest room. This feature associates the guest's name with the in-room extension upon check-in. This helps the front desk staff identify and address the guest with name when the guest calls front desk / other internal extensions. The extension, name association is removed upon check-out. In addition, on check-out, the voicemail box for the given guest room extension is cleared out.

PMS event	Cloud Telephony behaviour
Check-in	Phone extension is mapped to Guest name/room (guest-based mode).
Room move	Extension remapped to the new room. Old room extension reverts to vacant.
Housekeeping code dialed by staff	Staff dial a predefined code from the in-room phone. Cloud Telephony writes the room status update back to the PMS. This is a bidirectional flow.
Check-out	Unmap phone extension and clear voicemail.

Warning

Test the check-out voicemail clearing step explicitly before go-live. If voicemail is not cleared, the next guest may be able to access the previous guest's messages.

Housekeeping Events

The Housekeeping Events functionality is an optional add-on module for the Nomadix Cloud Telephony platform. It is specifically designed to address the Hospitality requirement to allow cleaning staff to update the readiness status of a room in real time via its phone.

The service is initially configured through Nomadix Cloud's intuitive web browser interface. After this step, housekeeping personnel just need to dial predefined codes that are automatically transmitted to the Property Management System (PMS), for example to set a room as ready to be checked-in.

- The service is delivered via an integration with the Nomadix Cloud platform, so requires System Administrators to have accounts with Editor permissions for that application
- The housekeeping codes being configured should not already be in use by the Nomadix Telephony Platform to avoid conflict.
- The Cloud Telephony Domain must already be up and running before configuring the codes on PMS Module
- The system administrator should know the Room Status supported by PMS system and make sure configuration page has a placeholder to match all desired Room Statuses to a code.
- The housekeeping codes should be communicated to the housekeeping staff by the hotel.

Configuration for Housekeeping Codes

Upon successful login, locate your Telephony Deployment: Click on Cloud Telephony and select Configuration from left hand side menu to bring up the configuration screen.

If your PMS vendor is Nomadix, the following housekeeping status events are preconfigured and can be used: Note that housekeeping codes for Nomadix Cloud Telephony vendor are fixed. If your PMS requires additional status fields, please contact Nomadix support.

Dial Code	Status
*31	Room Clean
*32	Room dirty
*33	Room Out of Service
*34	Room In Service
*35	Room inspected

For non-Nomadix Telephony platforms, housekeeping codes can be configured manually using the Configuration section under Cloud Telephony on Nomadix Cloud.


Additional configuration may be required on the telephony platform to configure dial codes, dial translations, and audio prompts associated with housekeeping events.

Use the Housekeeping Codes

The use of the functionality by cleaning staff is straightforward. From the in-room phone, dial one of the predefined codes as highlighted in table above.

Check Housekeeping Events

To check housekeeping events communication, in Nomadix Cloud navigate to Products-> PMS, select the relevant Deployment and go to the Transactions screen in the left-hand menu:



EMS (Energy Management Solution)

EMS uses PMS check-in and check-out events to control in-room thermostats. The room is pre-conditioned to a comfortable temperature before the guest arrives and set back to an energy-saving mode when the guest checks out. No additional configuration is required for EMS module to use PMS integration.

PMS event	EMS behaviour
Check-in received	Thermostat pre-conditioning begins. The room reaches the target comfort temperature before the guest arrives.
Check-out received	Thermostat setback to energy-saving mode.
Room vacant	Minimum temperature maintained per the property energy policy.

Casting and IPTV

Casting allows guests to mirror content from personal devices to the in-room television, connecting without leaving personal credentials on the device. IPTV follows the same PMS lifecycle model.

PMS event	Casting / IPTV behaviour
Check-in	Casting session activated for the room. Guest can connect immediately.
Room move	Session transferred to the new room. Old room session cleared.
Check-out	Session cleared. The next guest starts with a completely clean session.

Warning

Always test check-out session clearing before go-live. If sessions are not cleared, the next guest may see or access the previous guest's connected devices or content preferences.

Readiness and Go-Live Checklist

Use these checklists to confirm readiness before beginning configuration and before enabling any guest-facing features.

Pre-Configuration Readiness

Item	Confirmed
Nomadix Gateway registered in Nomadix Cloud under the correct property	
PMS Module license active for the gateway model	
PMS Interface license active (recurring)	
For OHIP: OHIP Module and Interface licenses active	
For OHIP: OPERA Cloud Foundation confirmed active	
For OHIP: Oracle OHIP Premium Remote Assistance workshop ordered or completed	
PMS vendor has confirmed third-party interface access is enabled	
For on-premise FIAS: PMS IP address and TCP port confirmed and reachable from Gateway	
Gateway firmware is current (confirm with Nomadix support)	
Gateway has outbound internet access (HTTPS port 443)	
Gateway public IP or port forwarding for XML API confirmed	
Support contacts confirmed: hotel IT, PMS vendor and Nomadix	

Configuration Completeness Checklist

Item	Where to verify	Confirmed
Property created in Nomadix Cloud with correct name, site code and timezone	Nomadix Cloud then Properties	
Networks module deployed and gateway visible under property	Property dashboard then Networks	
XML API connectivity indicator is green	Networks then Gateway then Connectivity	
PMS module deployed	Property dashboard - PMS tile visible	
PMS type selected and configuration saved	PMS tile then Settings	
Physical serial connection made between PMS and Gateway	On-site physical inspection of hardware ports	
Housekeeping	Property dashboard then Housekeeping tile	
Corresponding configuration Telephony	Property dashboard then Telephony tile	
For FIAS: Gateway PMS Redirector enabled with correct IP and port	Gateway Web UI then Configuration then PMS	
Rooms configured (floors and buildings)	PMS tile then Rooms	

Go-Live Validation Tests

Run these tests before enabling any guest-facing feature. All tests must pass.

Test	How to run	Pass condition
PMS Dashboard active	Open PMS Dashboard	Status shows active/connected. Event count is not zero.
Check-in event received	Ask front desk to check in a test guest	Check-in event appears in Events view within 60 seconds.
Check-out event received	Ask front desk to check out the test guest	Check-out event in Events view. Room reverts to vacant in Rooms view.
Product module responds to check-in	Observe the relevant product (telephony, Casting, EMS)	Product activates for the checked-in room within expected time.
Service clears at check-out	Observe product behaviour after test check-out	Product deactivates. Session cleared. No data from previous guest visible.

All the following must be true before enabling guest-facing features:

- PMS Dashboard shows active status with non-zero event counts.
- Check-in and check-out events confirmed flowing via test.
- Room occupancy in Nomadix Cloud matches actual property occupancy.
- All in-scope product services respond appropriately.
- Front desk has been briefed and has a fallback procedure for reported issues.
- MSP day-2 support plan is in place with named contacts.

Monitoring and Operations

After go-live, monitor the PMS Module regularly to catch issues before they affect guests.

Daily Checks

Check	Where	Pass condition
PMS Dashboard status is active	PMS tile then Dashboard	Status shows active/connected. No error indicators.
Event count is non-zero (during occupied hours)	PMS tile then Dashboard	Events are arriving from the PMS. If the property has guests and no events have arrived in 24 hours, investigate.
Room occupancy is plausible	PMS tile then Rooms	Occupied room count is consistent with expected occupancy levels.
No persistent transaction errors (weekly check)	PMS tile then Transactions	All recent transactions show success status.

After PMS Maintenance or Network Outage

If the PMS is restarted, updated or the Gateway loses connectivity, events emitted during the outage may have been lost. When this happens:


1. Check the PMS Dashboard status and confirm the link has re-established.
2. Review the Events view for a gap in event timestamps. Any gap indicates missed events.
3. Request a PMS database sync from the front desk to re-sync room occupancy state.
4. Manually verify the Rooms view matches actual front desk occupancy.

Troubleshooting

Use this section when a reported issue involves the PMS Module. Start with the quick triage guide to identify where the problem lies before taking action.

Quick Triage

Work through the layers from bottom to top. Do not escalate to any vendor until the layers below their component are confirmed clear.


Always diagnose from Layer 1 upward –
do not contact any vendor until the layers below are confirmed clear.
Layer 5 – Destination service
Telephony, EMS, Casting, Captive Portal
Layer 4 – Nomadix Cloud
Dashboard events, module consumption, Transactions log
Layer 3 – PMS data
Record accuracy, event emission, room identifier, folio state
Layer 2 – PMS interface
PMS Redirector active, API credentials valid, streaming approved (OHIP)
Layer 1 – Network
Gateway to PMS reachability, TCP port, firewall, DNS
Diagnose upwards
← START HERE

Symptom	First check	Section
PMS Dashboard shows inactive or red status	Gateway connection to PMS (on-premise)Gateway connection to Noamdix Cloud (on-premise)API credentials (cloud/OHIP)	PMS Link Down or Inactive
Events not coming from the PMS system	Vendor needs to enable events streaming. This will vary by the PMS vendor. Check authentication token / API credentials.	Event Issues
Unable to post data to the PMS system	Authentication issue	Check that the API credentials, enterprise ID, hotel chain code etc match with what is configured on PMS configuration. (Varies by PMS)
Product not responding to check-in or check-out	Events are arriving; product module configuration and room mapping	Product Not Responding to PMS Events

PMS Link Down or Inactive

For on Premise systems –

- Verify that the PMS configuration on the gateway is correct
- Appropriate PMS redirector should be selected.
- PMS TCP IP and port should be correct.
- In case of serial connections, PMS should be connected to gateway via serial cable.
- Verify that Nomadix Cloud configuration to reach gateway is correct
- Gateway XML API configuration should be correct in Nomadix Cloud.
- The configured IP address and port should be reachable publicly.
- XML API indicator should be green in Nomadix Cloud.

For Cloud based systems, the inactive status indicates that no events have been received in the last one hour from the PMS system. Refer to Event Issues section Reference source not found. to troubleshoot further. Additionally, check that the API credentials, enterprise ID, hotel chain code etc match with what is configured on PMS configuration. (Varies by PMS)

After restoring the link, always perform a test check-in to confirm events are flowing before closing the issue.

Product Not Responding to PMS Events

If events are confirmed in the Events view but a product (Telephony, EMS, Casting) is not responding:

1. Open the product module in Nomadix Cloud and check that the product specific PMS configuration is complete, if applicable (e.g. Housekeeping events for Cloud telephony).
2. Check the room mapping: confirm the room identifier in the product module exactly matches the room number in the PMS Module.
3. Check the Transactions view for error entries related to the product module.
4. If errors are present, review the product guide for the specific module.
5. Verify the event data and work with the PMS vendor to get the correct data.

Event Issues

Symptom	Likely cause	Action
Events missing for specific hotel	Streaming not enabled or approved for that hotel within the chain. This process will vary for different PMS vendors.	Confirm streaming is approved in Oracle Developer Portal.
Token mismatch	If Nomadix webhook requires a token to be sent in the event, make sure the token value is correct.	
OHIP Environment stuck in pending state	Customer administrator has not approved the connection	Ask the hotel Oracle administrator to approve the Nomadix partner connection in the Developer Portal.

Escalation

Before escalating to any vendor, collect the following:

- Property name and Nomadix Cloud property ID
- Gateway serial number and model
- PMS vendor, version and interface type
- Description of the symptom (what was expected, what happened and when it started)
- Screenshot of the PMS Dashboard showing current status
- Screenshot of the Events view (or showing the absence of events)
- Screenshot of the Transactions view if a product issue is involved
- Confirmation from the PMS administrator that the PMS interface is active and PMS records are correct

Issue type	Escalate to
Gateway connectivity, XML API or Nomadix Cloud issues	Nomadix Support: support@nomadix.com
PMS interface not active or sending events	PMS vendor support
OHIP environment or streaming issues	Nomadix Support first then Oracle if an environment-level issue is confirmed

PMS Interface Module Guide

INTRODUCTION

Scope and Purpose

Thank you for choosing Nomadix products. This Guide covers the overview of PMS Interface module that integrates with various Nom

adix products. This guide will not cover the configuration of the other modules that use the PMS interface. Refer to the respective guides of these modules for product specific configuration and feature details.

The Property Management system module is an integral part of the Nomadix products in a hospitality setting and allows for a live connection between an on-site hotel Property Management System (PMS) or a Cloud PMS and the Nomadix products. The connection is facilitated via Nomadix gateway.

It will process guest check-in/check-out and folio information for use with other hospitality products such as:

- Telephony
- Casting
- Captive Portal

Documentation Conventions

{{snippet.Documentation Conventions}}

Technical Assistance

Further information is available via:

- The Nomadix Partner Portal https://portal.nomadix.com/ (requires account creation)
- The Nomadix public website https://www.nomadix.com/

Vendor technical support can be obtained here:

Support Email:	Support Call:
Americas:Europe:MEA: Asia Pacific:Japan:	support@nomadix.comsupport_europe@nomadix.com support_mea@nomadix.com support_singapore@nomadix.com support_japan@nomadix.com

OVERVIEW


A Property Management System (PMS) is software that facilitates the main processes in a hotel related to internal and external operations. The most important functions include front-desk services, reservations, channel management, housekeeping, rate and occupancy management, and payment processing. It may also manage housekeeping and perform human resources management.

The Nomadix Cloud Property Management System (PMS) module is the central PMS connection point for various Nomadix Cloud submodules that require PMS connectivity. PMS Interface module is not a stand-alone product but is an add-on that works with various products in Nomadix portfolio to provide advanced features and seamless integration with Property Management Systems.

The main benefits of an integration between a hotel PMS and a telephony platform include:

- Allowing the hotel staff to offer a more personalized service to guests calling from their rooms thanks to the display of their name and room number.
- Automatically opening optional services such as a voicemail box upon a guest check-in.
- Automatically closing services and clearing logs upon guest check-out.
- Facilitating advanced functionality such as managing wake-up calls or enabling a maid to use housekeeping codes from a phone to update a room status.
- Posting Room charges for HSIA usage.
- Managing billing information for chargeable guest calls

The PMS Interface module supports integration with various On-Premises PMS systems as well as with modern Cloud based systems. Please refer Supported PMS Software for a complete list of PMS Interfaces supported.



The logical components include:

- A **PMS application** containing the source data and capable of sending out events, including check-in/out information. This can either be:
- Asystem deployed on a local site and requiring serial or Ethernet connection.
- A modernplatform.
- A **Nomadix connector**, tested and validated with a large selection of PMS vendors to receive their events. This can either be:
- Awith serial or Ethernet connection (typically an EG 1000 model).
- Theplatform.

NOMADIX CLOUD PMS MODULE OVERVIEW


The PMS systems that are either cloud based or that support integration with FIAS via gateway can be viewed in and configured from Nomadix cloud.

This section explains main elements of the PMS module dashboard for day-to-day operations. It covers the functions available from the side menu including:

- PMS dashboard
- Rooms
- Events
- Transactions
- Settings

PMS Dashboard


The PMS dashboard can be used to monitor the current status of the PMS interface and the activity on the PMS link in the last 24 hours:



Element:	Description:
Check-in	The number of check-ins in the previous 24 hours.
Check-out	The number of check-outs in the last 24 hours.
PMS Status	This shows if the XML API connection between the gateway and the cloud is working and how long it has been up for.
Transactions	The number of PMS API transactions during the previous 24 hours. These are the REST API calls from other Nomadix Cloud modules such as Telephony.
Events	This shows how many FIA PMS commands have come from the gateway in the last 24 hours.
Rooms	The circular graph shows the total number of rooms currently checked in.

Room Status


The **Rooms status** from the left-hand menu will show the current status of all the rooms in the property and the current occupancy:



Element:	Description:
Total	The total number of rooms for the property.
Occupied	Checked in rooms. Click on this tile and it will display just the check-in rooms.
Vacant	Empty rooms. Click this tile and it will show just the checked-out rooms.
Floors	Clicking this tile allows you to choose what building or floor to display.
Rooms	Each room is show as a tile. The green border and corner indicate the room is checked in. Clicking the room will show the name of the checked in guest (if the PMS module is set to display guest information)


Events

The **Events** page will show all the PMS transactions that are processed by the PMS link to the Cloud for troubleshooting. It shows the raw FIAS messages as received by the system.



Transactions


The **Transactions** page displays the information going across the internal PMS API used by other Nomadix Cloud modules such as Angie or Telephony. Transactions can be used for troubleshooting issues such as displaying a guest bill. Refer to the guides for the other Nomadix Cloud modules for API troubleshooting recommendations.



Settings

This page allows you to revisit the settings that were configured for the PMS link.

- Click the **Edit** button to return to the settings page as described in section 4.5 - Configure the PMS Module.



FEATURES AND FUNCTIONALITY

The PMS Integration Module supports a wide range of platforms – as shown in diagram above. Initially designed to offer per room guest billing for High-Speed Internet Access (HSIA), some of these connectors can be used to support telephony use cases – subject to compatibility between the different systems in use at a particular property.

At present, PMS integration features as supported by various products are listed in the table below –

Nomadix Product	Functionality	
Casting	Check-In/Check-Out/Room move	Post and Query
Cloud Telephony	Check-In/Check-Out/Room move/Post housekeeping status	Post and Query
Captive Portal	Post Room charges	Post and Query
Gateway	Query Room/Guest Info	Query
IPTV	Check-In/Check-Out/Room move	Post and Query
Hotel Portal	Post Room Charges	Post and Query

COMMERCIAL PRODUCT LICENSES

In order to enable PMS integration with Nomadix products, PMS Interface Module license must be purchased along with an EG Gateway license. Please note that each Gateway model has a corresponding PMS interface module license part number along with required Support and warranty licenses.

Warning

Crexendo partners should refer Hospitality Services Add-On for Crexendo / NetSapiens Cloud Telephony Guide for details.

SUPPORTED PMS SOFTWARE

Over the years, Nomadix certified interoperability with a variety of PMS software. The received data can then either be used internally within the Gateway connector and/or Nomadix Cloud for the provision of Nomadix originated guest services or forwarded to a third-party destination – such as the NetSapiens telephony platform – to enhance their services.

Warning

Crexendo partners should refer Hospitality Services Add-On for Crexendo / NetSapiens Cloud Telephony Guide for details.Carefully check the tables here after and contact Nomadix if the PMS software you are looking for is not listed. The tables show interface types rather than individual vendor names, as more platforms than listed comply with one of these standards, but don't always publicly advertise it.While only a few PMS interfaces include the check-in/out field, they tend to be the ones that still dominate the market today.

The tables here after detail the legacy PMS interfaces supported by the Nomadix EG series Gateways connectors, as well as the Cloud PMS interfaces supported by Nomadix Cloud. The headers' definitions are:

- **PMS Type:** the selectable PMS via the Nomadix Gateway or Nomadix Cloud user interface under *Configuration -> PMS*
- **Check-In/Out:** the known interface can send check-in/out messages and the Nomadix Gateway or Nomadix Cloud can inform external systems of these events – required for telephony integration
- **Lookup:** the Nomadix Gateway or Nomadix Cloud can perform a guest name and room number lookup and can inform external systems that they match
- **POST:** the Nomadix Gateway or Nomadix Cloud can trigger a POST to this PMS Type


PMS INTERFACE MODULE CONFIGURATION

There are 2 types of PMS integrations that Nomadix PMS Interface Module supports. The PMS interface is supported via a serial connection or over TCP/IP, either to a local or cloud PMS The configuration of module will depend on the type of PMS in context.

Warning

For serial connection, an optional (sold separately by Nomadix) PMS Serial Hardware Integration Kit (part number 715-5001-010) is available and includes the necessary cable and built-in optical isolator for circuit protection to the PMS.Some PMS vendors may require a license of their own to enable interconnection with 3rd party systems and might even charge for Professional Services to set it up. These potential costs are not covered by Nomadix and should be checked ahead of a project.

The rest of this chapter is organized based on different configuration options which in turn is dependent on the PMS and the supported interface type.



Configuration for On-site PMS Software (Using PMS Redirector) via Gateway

This procedure assumes you have a Nomadix Gateway that has been configured with the most recent firmware, a PMS module license has been purchased for the gateway, and the gateway has access to the Internet. The Nomadix gateway communicates with the PMS via the PMS redirector feature and then the gateway uses the XML API features to communicate with the Nomadix Cloud. For more information on the XML API and PMS features of the gateway, refer to the Gateway Administration Guide.

Follow the steps below to configure Nomadix PMS Interface module for On-Premises PMS systems.

Nomadix Gateway Configuration

It is first necessary to configure the connection between the Nomadix Gateway and the PMS software before data can then be redirected to an Events Engine how.

1. In the gateway webUI, go to **Configuration** → **AAA**.
2. Under the **Options** tab, click the Configure button next to “XML Interface” to expand the XML setting.
3. Ensure the **Enable Authentication via XML User Credentials** is checked.
4. Click the link to **User Credentials** to go to the **Login Name and Password** screen (which can also be reached from **System** → **Login**).
5. Set the login name and password for the XML User and click **Save**.
6. Return to **Configuration** → **AAA** and select the **Internal Web Server** tab.
7. In the **Portal XML POST URL insert** field add *https://nomadix.cloud/network/api/nomadix_xml* and then enter the **Portal XML Post Port** number you intend to use to communicate with the Nomadix Cloud XML API (which we will configure later in the Cloud).
8. Go to **Configuration** → **Access Control** and insert the XML Post Port number you entered in Step 7 into the **HTTP Port** field.
9. Go to **Configuration** → **PMS** and click the appropriate radio button to enable the **FIAS PMS Redirector** or **Marriott PMS Redirector**.
10. Select the **Configure** link next to the radio button to open the PMS configuration screen.

11. Select the **TCP/IP** option and insert the IP address and TCP port number for the hotel PMS system the gateway will be connecting to then click **Save**. No other PMS settings need to be changed.
12. Go back to the Property Management System Settings page and click **Save**.

Nomadix Cloud Configuration

Once the gateway is configured, there are a series of steps required in the Nomadix Cloud to enable PMS connectivity.

This series of procedures assumes that:

- The partner has been setup on the Nomadix Cloud
- The partner's gateways have been imported into the Nomadix Cloud
- The partner has been enabled to deploy the PMS module.

1. At the organization top level, select **Properties** from the menu on the left-hand side.
2. While on the list of properties, click the **+ New Property** button in the upper right-hand corner.
3. Complete the fields in the **New Property** form. Note that the following fields are mandatory:Name – The hotel name.Site Code - This can be any unique alpha-numeric identifier. It is recommended to use the ID assigned to the property from the hotel brand.Timezone – The time zone where the hotel is located.Default Locale – Refers to the local language. Currently only English (en) is supported.Temperature Unit – Whether the local property prefers Fahrenheit or CelsiusDistance Unit – Whether the local property prefers Imperial or Metric measurement.
4. With all fields completed, the form should look like the following.
5. Click **Create Property** to complete the process.

To enable the features for the property, the Networks module must be deployed to the site.

1. From the Properties list, select the property to go to the dashboard for the hotel, which will be shown as empty with no features deployed.
2. Click the **+Deploy Product** button on the right hand side.
3. From the **Product Deployment** page, select **Networks** from the drop-down and click the checkbox to **accept the End User License Agreement (EULA).**
4. Click the **Deploy** button.
5. You will see the property with the Networks module deployed.
6. If the Networks module is not already populated with a gateway, then click the **Networks** tile and select **Nomadix Gateways** from the menu on the left had side.
7. Click **+ New Gateway** and fill in the serial number, NSE ID and model number of the gateway. (The information is located on the label on the bottom of the gateway.)
8. You will now see a list of the gateways for the property.

Similar to the Networks module, the PMS module must be deployed to the property before it can be configured.

1. From the property dashboard, click the **+ Deploy Product** button.
2. Select MPS from the drop-down menu.
3. Click the checkbox to accept the EULA and then click **Deploy**. The PMS module tile will now appear in the Deployments area.

Before configuring the PMS module, the XML connectivity from the Nomadix Cloud to the gateway must be established.

1. From the property dashboard, click the **Networks** tile.
2. From the left-hand menu, select **Nomadix Gateways.**
3. Select the gateway from the list of gateways at the property and you will see the gateway detail page for the unit. (Note that the PMS feature must show as enabled in the “Features” area.)
4. Click XML API tile in the **Connectivity** section in the upper right of the screen.
5. Complete the form as follows:XML API Address – This is the public IP address of the local gateway as it would appear from the Nomadix Cloud. This can be a static, public IP address for the gateway, or a WAN address with port forwarding turned on to reach the gateway.XML API Port – The IP address set for the XML API during the gateway configuration (see Section 3 Nomadix Gateway Configuration).XML API Username – The username set up for the XML API during gateway configuration.XML API Password – The password set up for the XML API during gateway configuration.
6. Turn On the toogle for **Enable API Endpoint** to turn on the XML API connection to the Noamdix Cloud.
7. Click **Submit** to save the configuration and exit back to the gateway status page.
8. If the gateway and Nomadix Cloud have been configured correctly the XML API will show a green indicator after one to two minutes.
9. If the indicator goes to red, it indicates there is something wrong with the XML API connection. Recheck the gateway setting from Section 3 Nomadix Gateway Configuration.

To enable the PMS connection, the PMS module must be configured. Follow these steps:

1. When you click on the **PMS** tile from the property dashboard, it will show that the PMS module has not yet been configured.
2. Click the **Configuration** button to open the PMS Settings page.PMS Type – Currently there is only one option which is FIAS via Nomadix Gateway.Mode of operation – This provides two options:Guest-based PMS - which means the PMS integration will process data for rooms as well as guests. Guest personal data will be stored for the duration of their stay and erased on check-out.Room-based PMS - which the PMS integration will only process data based on rooms and will not have visibility of guest personal data. This option is suitable when you do not require guest data and wish to ensure strict privacy.The Nomadix Gateway drop down will list the gateways associated with the property. Select the gateway that has been configured with PMS interface set up earlier.
3. Once you have set the options for your site, click **Submit** to complete the configuration of the Interface.

This section is optional. The PMS interface can determine the number of rooms set up for the hotel during its first database sync, but it will not be able to determine which floors or buildings are associated with which room. If this is useful for the property, the Rooms tile can be used to configure the rooms for the property.

1. From the hotel dashboard, click the **Rooms** tile.
2. From the Rooms page, select **+ New Rooms**.
3. This opens the New Rooms dialog.Floor - The floor the room is located on.Building – If there are multiple buildings in the hotel complex you can set the name of the building. Default is Main.Rooms – You can enter a single room, or a range of rooms or a list of rooms. A range of rooms is entered as starting...ending, so to create rooms

100 to 110 you would enter 100..110. You can also enter a list of rooms separated by commas.

4. Once you have set up the rooms for your floor/building, click **Create Rooms** and the rooms will be created in the database.NoteRooms can only be deleted one at a time, so ensure you have entered correct information for large numbers of rooms.
5. Repeat step 3 for all floors/buildings in the hotel.
6. The rooms list will now show all the configured rooms in the property.
7. Click the **Edit** icon to the right of the room to edit the settings for each individual room.

Assuming the PMS settings on the gateway and the Nomadix Cloud PMS module have all been set correctly, you should now see the PMS module dashboard (more details in the next section).


To test the PMS module:

1. Request that the front desk staff trigger a PMS database sync. The PMS dashboard should show a banner indicating that a sync operation is underway.
   A database sync could take anywhere from 10 to 20 minutes depending on the size of the property. (Very large properties may take even longer.)
2. Assuming the sync completes successfully, request front desk staff to trigger several check-in and check-out operations on some test rooms.
3. On the Rooms page, you should see the room status update. The green border and corner indicate the room is checked in. Room status can sometimes take a few seconds to update depending on internal queuing in the gateway. If the status does not update in 1 to 2 minutes the room update may have failed.
4. Click **Events** on the left hand side to see the raw FIAS traffic to verify it is working as expected. Consult the Oracle Hospitality FIAS documentation for the format of the messages.

Warning

The following instructions assume a PMS is live, licensed for third party integration by its vendor and reachable by the Nomadix Gateway – either via IP or using the optional DB9 to RJ45 serial cable.

From the Web Management Interface, click on **Configuration** → **PMS**. The Property Management System Settings screen below appears:



Configuration for Legacy PMS Software (Using PMS Redirector) via Gateway

This section describes the configuration for integration with Legacy PMS software systems that do not use FIAS Interface. The integration for such systems will be configured directly on the gateway and there will be no cloud configuration.


It is first necessary to configure the connection between the Nomadix Gateway and the PMS software before data can then be redirected to an Events Engine how.

1. In the gateway webUI, go to **Configuration** → **AAA**.
2. Go to **Configuration** → **PMS** and click the radio button to enable the **FIAS PMS Redirector**.
3. Select the **Configure** link next to the radio button to open the PMS confgiuration screen.
4. Select the **TCP/IP** option and insert the *IP address* and *TCP port number* for the hotel PMS system the gateway will be connecting to then click **Save**. No other PMS settings need to be changed.
5. Go back to the Property Management System Settings page and click **Save**.

Configuration for Cloud PMS software

The setup of a direct Cloud-to-Cloud interface is simpler. Once a Property and its PMS module are deployed in Nomadix Cloud (Follow the steps from **Create a new property** to **Deploy the PMS module**), proceed as follows –


Select the vendor from the pull-down menu on the **Settings** page in the left menu:



Warning

If the Cloud PMS software you require is not listed, please contact Nomadix. We are regularly working with new vendors and adding support for their interfaces.

A few **parameters** – which can vary depending on the vendor – are required to connect and authenticate with the PMS instance to start collecting their events:



Once done, click **Submit** to save your configuration.

PMS Interoperability Matrix

Supported PMS interfaces that are compatible with Nomadix Products

The matrix outlines the supported integration methods and interface functions. It highlights the depth of event exchange, billing interaction and service automation for each PMS type.*

PMS	Interface Type	Cloud/On Premise	Nomadix Product	Functions Supported
Opera On-Prem	FIAS	On-Premise	Gateway, EMS, Cloud Telephony, Casting, Captive Portal, Hotel Portal	Full Interface and all commands:Checkin/out/move,Get Guest VIP Status,Guest Messaging,Housekeeping,Guest Folio information,POST charges,InRoom Checkout (All messaging interface supports)
Opera Cloud	Cloud /On-Premise			
Oasis	On-Premise			
Sihot				
Shiji				
RMS				
Infor HMS				
Agilysis	FIAS (using COMTROL - ROW 19)	On-Premise		
SkyTouch	SkyTouch	Cloud /On-Premise		
Front2Go	Front2Go	Cloud	EMS, Cloud Telephony	
StaynTouch	StaynTouch	Cloud	EMS, Cloud Telephony, Casting, Captive Portal	
Opera OHIP	OHIP	Cloud		
HotelKey	HotelKey	Cloud		

Hilton OnQ	Micros (1700/2000/3700/4700/8700 System Software Emulation)	On-Premise	Gateway, Captive Portal, Hotel Portal	Guest Validation and POST Charges
Galaxy				
Springer-Miller Systems				
Encore				
COMTROL (Used to bridge to different PMS systems)	FIAS / Micros (1700/2000/3700/4700/8700 System Software Emulation)			
Hotel Info Sys (HIS)	MICROS/WFB/FOSSE			
Igets.net				
Innquest				
LanMark				
LIBICA				
Logistics				
Maestro				
Marriott	Gateway, EMS, Cloud Telephony, Casting, Captive Portal, Hotel Portal	Full Interface and All Commands:Check-in/Check Out/MoveGet Guest VIP StatusGuest MessagingHousekeepingGuest Folio InformationPOST Charges,In-Room Check out(All MessagingInterface Support)		

Megasys Hospitality Systems	Micros (1700/2000/3700/4700/8700 System Software Emulation)	Gateway, Captive Portal, Hotel Portal	Guest Validation and POST Charges	
MSI				
NH Hotels	NH			
NiteVision	Micros (1700/2000/3700/4700/8700 System Software Emulation)			
Protel				
Protocol Technologies				
Ramesys ImagInn PMS				
Xeta Virtual XL				
MEWS PMS	Mews Open API/Connector API	Cloud	Gateway, Captive Portal, Hotel Portal	Check-in/Check OutMove Guest ValidationPOST Charges

DISCLAIMER

The information regarding the PMS interfaces and products in this Nomadix PMS Interoperability Matrix (“Guide”) are subject to change without notice. All information in this Guide is believed to be accurate but are presented as-is, and without warranty of any kind, express or implied.

Installation and use of the product is subject to the current Nomadix End User License Agreement, which can be found at https://nomadix.com.

When installing the product, use all recommended safety precautions including in regard to working with electricity and working at heights. Failure to do so can result in injury or death, and damage to property.

Nomadix, Inc. reserves the right to improve this Guide, its contents, and any products described herein at any time without prior notification. The information in this document has been reviewed for accuracy, clarity, and completeness. If you find any errors or have any comments, please forward them to: marketing@nomadix.com.

PDF Downloads

Resources

Step-by-step resources for IT teams and installers to correctly deploy and manage Nomadix PMS.

Latest product guide

PMS Integration Configuration Guide for Oracle Hospitality Integration Platform (OHIP)

PMS Interoperability Matrix v1.1

PMS Integration Configuration Guide for Oracle Hospitality Integration Platform (OHIP)

Download this guide

INTRODUCTION

Scope and Purpose

Thank you for your interest in Nomadix products. The aim of this document is to cover the requirements and configuration steps for a connection between the Oracle Hospitality Integration Platform (OHIP) and Nomadix Cloud.

Documentation Conventions

{{snippet.Documentation Conventions}}

Further Reading

We recommend that you familiarize yourself with the Nomadix Cloud Administration Guide, available on the Nomadix Partner Portal (requires an account). Please consult the vendor documentation for complete instructions on the Oracle part of the implementation.


OHIP INTEGRATION PRESENTATION

Overview


{{snippet.PMS Product Overview}}

Oracle Hospitality Integration Platform (OHIP)

Oracle Hospitality's OPERA Cloud is the leading Property Management System in the World. Interconnectivity is achieved via the Oracle Hospitality Integration Platform (OHIP). Validated connectors to OHIP are offered via the Oracle Cloud Marketplace.



As a member of the Oracle partner network, Nomadix offers a validated OHIP integration advertised on the Oracle Cloud Marketplace, which enables the exchange of events for 2-way interactions between OHIP and Nomadix Gateways + Nomadix Cloud. Once the link is established, it can be used with several Nomadix Products, including Captive Portal, Cloud Telephony, Energy Management, and more.



The Nomadix OHIP integration is subject to fees. Oracle operates a usage-based billing model, where it charges vendors – in this case Nomadix – for the number of calls made to the Oracle platform. Nomadix passes this cost to Managed Service Providers (MSPs) in the way of a recurring license, which in turn is passed to end- customers.


Commercial Licensing Model

The Nomadix commercial licensing model for OHIP comprises of 4 components:

- PMS Module License: One-off cost for the initial activation of the PMS functionality on Nomadix Gateways + Nomadix Cloud. The charge is specific to each gateway model.
- OHIP Module License: One-off cost for the initial activation of the OHIP functionality on Nomadix Gateways + Nomadix Cloud. The charge is specific to each gateway model
- PMS Interface License: Recurring cost for the use of the PMS functionality on Nomadix Gateways + Nomadix Cloud – including software updates, as well as

hardware and software support. The charge is specific to each gateway model, with options for 1-, 3- and 5-years contracts.

- OHIP Interface License: Recurring cost for the Oracle usage-based billing model. The charge is specific to each gateway model, with options for 1-, 3- and 5-years contracts.



Please note the following:

Warning

MSPs are responsible for paying the Nomadix OHIP license fees for the properties they manage. In turn, they pass this cost onto their respective customers – same as in the case of any other Nomadix license they resell.Each site requires a Nomadix Gateway acting as a local edge connector and which must be correctly licensed for the other services it is expected to deliver.The OHIP license described in this document is solely for the exchange of events between the Oracle and the Nomadix platforms. Customers must have valid licenses for the use of Oracle solutions.Excessive Usage: the OHIP license is intended for typical property activity and is subject to customers agreeing to the Fair Use Policy. Non-typical usage, determined at Nomadix' sole discretion, may incur additional usage charges. In addition, if Nomadix determines that abnormal, unreasonable or impermissible usage is occurring, additional steps such as suspension or termination of the license may occur.Oracle requires that customers purchase a mandatory OHIP Premium Remote assistance 4 hour workshop to engage with Oracle Professional Services and learn how to enable streaming. Further details can be found here (public information).

OHIP INTEGRATION CONFIGURATION

Process Overview


A OHIP integration with Nomadix Cloud requires several actions to be completed by a combination of the customer, the managed service partner (MSP) and Nomadix. The following instructions are written assuming the MSP will coordinate the overall deployment on behalf of the customer and in close relationship with Nomadix.

Warning

This document focuses on the OHIP integration configuration. Please refer to the respective Oracle and Nomadix documentation for the setup and configuration of OPERA, Nomadix Cloud and Nomadix Gateways.It is assumed by this point the customer has acquired the appropriate licenses and completed the appropriate product setups both for Nomadix and Oracle.Customers must have purchased and be using OPERA Cloud Foundation.

Upon provisioning of or migration to Oracle Hospitality OPERA Cloud Foundation, the customer receives an email advising of the Oracle Hospitality Developer Portal URL. This portal can be used for viewing environments, finding details about environment variables such as Enterprise ID etc, and for managing environment connection requests. Oracle Hospitality OPERA Cloud Foundation includes access to the Oracle Hospitality Integration Platform.


To enable the OHIP integration with Nomadix Cloud, please follow the 4 logical steps below in this order, and as described in the next sections of this guide:



Register Interest for the Nomadix OHIP Integration

As a member of the Oracle partner network, Nomadix offers a validated OHIP integration advertised on the Oracle Cloud Marketplace. The first step of the process is to register interest via this site.

- Go to the Oracle Hospitality Marketplace (here) and search for Nomadix.
- Click on Nomadix Cloud and then click on the Get App button.
- Log into your Oracle account or create one.
- Fill-in the form to register interest for the integration.
- This notifies both Oracle and Nomadix of a project requirement.



Collect the Customer Environment Details

- Please **collect the following information** from the customer and **send it to** support@Nomadix.com:
- : Many hotels run non-production OPERA Cloud environments as well as their production environment(s). Customers must determine whether the OPERA Cloud environment in use is a production or non-production instance.
- : The region in which the customer's OPERA Cloud environment is running.
- : The customer's tenant code used to target the right tenant, especially in OPERA Cloud environments that host multiple tenants.
- : The hotel's OPERA internal ID for the tenant.
- : The unique identifier for the enterprise. This can be found in the environment details of the customer in the OPERA Cloud Identity Management portal.

Warning

The next steps cannot be completed without the above details.Customers can find the requested information by logging into the OHIP Customer Portal.

Approve the Customer Environment Creation

Customers require unique environments for integrations between OHIP and partner applications. As a member of the Oracle partner network, Nomadix is responsible for setting-up environments (accounts) for all customers requiring OHIP integrations – which can only be done once the key details indicated in the earlier step have been provided by customers. Environments then only become live once customers approve them.

Warning

Customers must have purchased and be using OPERA Cloud Foundation before Nomadix can create environments.Customers do not have permissions to create or edit environments in Oracle Developer or Partner Portal, as Oracle intends for the partners – here Nomadix – to create and manage the customers' environments.

- Nomadix creates the environment using the key details provided by the customer.
- Upon completion, customers' administrators receive a connection request for approval. The environment remains in a pending state until acceptance. Follow the below steps to approve the request:
- From the Developer Portal, click Environments at the top of the page.
- Click Partner Connections to display the list.
- Search for the partner connection that is pending approval – here Nomadix.
- Search for and select the properties you wish to assign to the partner connection.
- Click Next.
- Review the Summary and click Approve. The status of the partner connection request should change to Approved in both the Customer and Partner Portals.
- An email notification confirming the approval of the connection request is sent to Nomadix.
- The customer's environment is ready for use within 5 minutes of approval and can start calling OHIP APIs and streaming events.

Warning

Customers can reject connection requests and revoke access to previously approved ones.

Approve Business Events Streaming

Nomadix products and services provide real-time and on-demand features through the OHIP integration, provided they can **consume business events** from the OHIP interface. These are updates to the state of a resource, for example a reservation. Rather than GETting it repeatedly, subscribing to the update reservation event informs the system when this or other reservations are changed. Oracle Hospitality systems emit business events in multiple scenarios, such as when a guest checks-in or checks-out. Each business event contains the following information:

- **Resource**: This is the resource that has received the event, for example a reservation.
- **Event**: The name of the event, for example an update to a reservation.
- **Old Value**: This is the old value for the field.
- **New Value**: This is the new value for the field.

Oracle recommends enabling streaming to receive business events due to several limitations of the polling mechanism. In addition, streaming is required to receive real-time information about events such as check-in. Polling mechanisms can be used for less critical events.

Warning

Streaming is enabled at chain level, not at hotel level, so it only needs activation once.Oracle requires that customers purchase a mandatory OHIP Premium Remote assistance 4 hour workshop to engage with Oracle Professional Services and learn how to enable streaming. Further details can be found here (public information).Customers can only approve the streaming of business events for hotels to which they have access in the Developer Portal.

When integrated applications such as Nomadix Cloud consume business event data from OPERA Cloud, they can choose which ones they receive. These are the events to which the applications subscribe. Environment owners are required to approve business event subscription requests. Follow the below steps to approve them:

- Log into the Developer Portal.
- Display the list of the partners requesting to consume business events.
- Display the list of business events a partner is consuming and check from which hotels and environments the partner is consuming these events.
- Approve the business event consumption for one or many hotels within the environment.

Remove the Customer Environment

Once the OHIP integration with Nomadix products is no longer required, the customer environment should be removed from the Oracle Partner Portal. This can only be done by Oracle partners.

Warning

Customers do not have permissions to remove environments in Oracle Developer or Partner Portal, as Oracle intends for the partners – here Nomadix – to remove the customers' environments.When an environment is removed, it will cease sending any events to which Nomadix Cloud had subscribed via the streaming API.The environment can be added back using the same enterprise ID and chain code that were previously used to create it, but it will be subject to a new customer approval.

- Send a request for the environment to be removed to support@Nomadix.com.

OHIP API Fair Use Policy

Nomadix set its OHIP license fees after careful estimation of API usage based on the property size and the Nomadix gateway on-site. The OHIP license tiers are designed to provide flexibility and scalability to Nomadix MSPs.

OHIP licenses are intended for typical property activity and are subject to customers agreeing to the Fair Use Policy. Non-typical usage, determined at Nomadix' sole discretion, may incur additional usage charges. In addition, if Nomadix determines that abnormal, unreasonable or impermissible usage is occurring, additional steps such as suspension or termination of the license may occur.