
IP Addressing Table

COH: City Operations Hub | Subnet: 3.1.0.0/23 | Mask: 255.255.254.0				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
COH	COH (Router)	3.1.0.1	255.255.254.0	
COH	COH-PC1	(DHCP assigned)	255.255.254.0	3.1.0.1 (DHCP assigned)
COH	COH-PC2	(DHCP assigned)	255.255.254.0	3.1.0.1 (DHCP assigned)
COH	COH-Printer	3.1.0.6	255.255.254.0	3.1.0.1
COH	DHCP-Server	3.1.0.2	255.255.254.0	3.1.0.1
COH	DNS-Server	3.1.0.3	255.255.254.0	3.1.0.1
COH	Web-Server	3.1.0.4	255.255.254.0	3.1.0.1
COH	Email-Server	3.1.0.5	255.255.254.0	3.1.0.1
TMC: Traffic Management Center | Subnet: 3.1.2.0/23 | Mask: 255.255.254.0				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
TMC	TMC (Router)	3.1.2.1	255.255.254.0	
TMC	TMC-PC1	(DHCP assigned)	255.255.254.0	3.1.2.1 (DHCP assigned)
TMC	TMC-PC2	(DHCP assigned)	255.255.254.0	3.1.2.1 (DHCP assigned)
TMC	TMC-Printer	3.1.2.3	255.255.254.0	3.1.2.1
TMC	TMC-Email-Server	3.1.2.2	255.255.254.0	3.1.2.1
PUN: Public Utilities Node | Subnet: 3.1.4.0/24 | Mask: 255.255.255.0				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
PUN	PUN (Router)	3.1.4.1	255.255.255.0	
PUN	PUN-PC1	(DHCP assigned)	255.255.255.0	3.1.4.1 (DHCP assigned)
PUN	PUN-PC2	(DHCP assigned)	255.255.255.0	3.1.4.1 (DHCP assigned)
PUN	PUN-Printer	3.1.4.2	255.255.255.0	3.1.4.1

EDU: Emergency Dispatch Unit | Subnet: 3.1.5.0/24 | Mask: 255.255.255.0				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
EDU	EDU (Router)	3.1.5.1	255.255.255.0	
EDU	EDU-PC1	(DHCP assigned)	255.255.255.0	3.1.5.1 (DHCP assigned)
EDU	EDU-PC2	(DHCP assigned)	255.255.255.0	3.1.5.1 (DHCP assigned)
EDU	EDU-Printer	3.1.5.2	255.255.255.0	3.1.5.1
EMP: Environmental Monitoring Post | Subnet: 3.1.6.0/25 | Mask: 255.255.255.128				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
EMP	EMP (Router)	3.1.6.1	255.255.255.128	
EMP	EMP-PC1	(DHCP assigned)	255.255.255.128	3.1.6.1 (DHCP assigned)
EMP	EMP-PC2	(DHCP assigned)	255.255.255.128	3.1.6.1 (DHCP assigned)
EMP	EMP-Printer	3.1.6.2	255.255.255.128	3.1.6.1
RFS — Remote Field Station | Subnet: 3.1.6.128/26 | Mask: 255.255.255.192				
Unit	**Device**	**IP Address**	**Subnet Mask**	**Default Gateway**
RFS	RFS (Router)	3.1.6.129	255.255.255.192	
RFS	RFS-PC1	3.1.6.130	255.255.255.192	3.1.6.129
RFS	RFS-PC2	3.1.6.131	255.255.255.192	3.1.6.129
RFS	RFS-Printer	3.1.6.132	255.255.255.192	3.1.6.129

VLSM Tree

Subnet Name / Unit	Required Hosts	Hosts + 2 (Net/Bcast)	IP Block Size (2^n)	Host Bits (n)	Network Bits (Prefix)
COH	501	503	512	9	/23
TMC	301	303	512	9	/23
PUN	221	223	256	8	/24
EDU	181	183	256	8	/24
EMP	91	93	128	7	/25
RFS	51	53	64	6	/26
(Switch1)	3	5	8	3	/29
WAN 1	2	4	4	2	/30
WAN 2	2	4	4	2	/30
WAN 3	2	4	4	2	/30
WAN 4	2	4	4	2	/30
WAN 5	2	4	4	2	/30


3.1.0.0 / 16
3.1.0.0 / 23 (COH)
3.1.2.0 / 23 (TMC)
3.1.4.0 / 23
3.1.6.0 / 23
3.1.4.0 / 24 (PUN)
3.1.5.0 / 24 (EDU)
3.1.6.0 / 25 (EMP)
3.1.6.128 / 25
3.1.6.128 / 26 (RFS)
3.1.6.192 / 26
3.1.6.192 / 29 (Switch)
3.1.6.200 / 29
3.1.6.208 / 29
3.1.6.216 / 29
3.1.6.200 / 30 (WAN 1)
3.1.6.204 / 30 (WAN 2)
3.1.6.208 / 30 (WAN 3)
3.1.6.212 / 30 (WAN 4)
3.1.6.216 / 30 (WAN 5)

Router Interface Configuration

COH:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname COH_Router
COH_Router(config)#interface Fa0/0
COH_Router(config-if)#ip address 3.1.0.1 255.255.254.0
COH_Router(config-if)#ip helper-address 3.1.0.2
COH_Router(config-if)#no shutdown

COH_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

COH_Router(config-if)#int s0/0/0
COH_Router(config-if)#ip address 3.1.6.201 255.255.255.252
COH_Router(config-if)#clock rate 64000
COH_Router(config-if)#no shut
COH_Router(config-if)#exit
COH_Router(config)#int s0/0/0
COH_Router(config-if)#
COH_Router#
%SYS-5-CONFIG_I: Configured from console by console

COH_Router#en
COH_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
COH_Router(config)#int s0/0/0
COH_Router(config-if)#ip address 3.1.6.201 255.255.255.252
COH_Router(config-if)#clock rate 64000
COH_Router(config-if)#no shut
COH_Router(config-if)#exit
COH_Router(config)#exit
COH_Router#
%SYS-5-CONFIG_I: Configured from console by console
en
COH_Router#en
COH_Router#conf t
```

```
Enter configuration commands, one per line.  End with CNTL/Z.
COH_Router(config)#int s0/0/1
COH_Router(config-if)#ip address 3.1.6.205 255.255.255.252
COH_Router(config-if)#clock rate 64000
COH_Router(config-if)#no shut

COH_Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up

COH_Router(config-if)#exit
COH_Router(config)#exit
COH_Router#
%SYS-5-CONFIG_I: Configured from console by console

COH_Router#en
COH_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
COH_Router(config)#int s0/1/0
COH_Router(config-if)# ip address 3.1.6.209 255.255.255.252
COH_Router(config-if)#clock rate 64000
COH_Router(config-if)#no shut

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
COH_Router(config-if)#exit
COH_Router(config)#exit
COH_Router#
%SYS-5-CONFIG_I: Configured from console by console

COH_Router#
```

TMC:

```
Router>
Router>en
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname TMC_Router
TMC_Router(config)#int fa0/1
TMC_Router(config-if)#ip address 3.1.2.1 255.255.254.0
TMC_Router(config-if)#no shut

TMC_Router(config-if)#
```

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

TMC_Router(config-if)#en
% Ambiguous command: "en"
TMC_Router(config)#exit
TMC_Router#
%SYS-5-CONFIG_I: Configured from console by console

TMC_Router#en
TMC_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
TMC_Router(config)#int fa0/0
TMC_Router(config-if)#ip address 3.1.6.193 255.255.255.248
TMC_Router(config-if)#no shut

TMC_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

TMC_Router(config-if)#exit
TMC_Router(config)#int s0/0/0
TMC_Router(config-if)#ip address 3.1.6.202 255.255.255.252
TMC_Router(config-if)#no shut
TMC_Router(config-if)#

PUN:

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname PUN_Router
PUN_Router(config)#int fa0/0
PUN_Router(config-if)#ip address 3.1.4.1 255.255.255.0
PUN_Router(config-if)#no shut

PUN_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

PUN_Router(config-if)#exit

```
PUN_Router(config)#int fa0/1
PUN_Router(config-if)#ip address 3.1.6.194 255.255.255.248
PUN_Router(config-if)#no shut

PUN_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

PUN_Router(config-if)#exit
PUN_Router(config)#int s0/0/0
PUN_Router(config-if)#ip address 3.1.6.213 255.255.255.252
PUN_Router(config-if)#clock rate 64000
PUN_Router(config-if)#no shut
PUN_Router(config-if)#exit
PUN_Router(config)#
```

EDU:

```
Router>en
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname EDU_Router
EDU_Router(config)#int fa0/0
EDU_Router(config-if)#ip address 3.1.5.1 255.255.255.0
EDU_Router(config-if)#no shut
EDU_Router(config-if)#exit
EDU_Router(config)#

EDU_Router(config)#int s0/0/0
EDU_Router(config-if)# ip address 3.1.6.206 255.255.255.252
EDU_Router(config-if)#no shut
EDU_Router(config-if)#exit

EDU_Router(config)#int s0/0/1
EDU_Router(config-if)#ip address 3.1.6.214 255.255.255.252
EDU_Router(config-if)#no shut

EDU_Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
```

EMP:

```
Router>en
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname EMP_Router
EMP_Router(config)#int fa0/0
EMP_Router(config-if)#ip address 3.1.6.1 255.255.255.128
EMP_Router(config-if)#no shut

EMP_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

EMP_Router(config-if)#exit
EMP_Router(config)#int fa0/1
EMP_Router(config-if)#ip address 3.1.6.195 255.255.255.248
EMP_Router(config-if)#no shut
EMP_Router(config-if)#exit
EMP_Router(config)#int s0/0/0
EMP_Router(config-if)#ip address 3.1.6.210 255.255.255.252
EMP_Router(config-if)#no shut

EMP_Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

EMP_Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

EMP_Router(config-if)#exit
EMP_Router(config)#int s0/0/1
EMP_Router(config-if)#ip address 3.1.6.217 255.255.255.252
EMP_Router(config-if)#clock rate 64000
EMP_Router(config-if)#no shut
EMP_Router(config-if)#exit
```

RFS:

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname RFS_Router
RFS_Router(config)#int fa0/0
RFS_Router(config-if)#ip address 3.1.6.129 255.255.255.192
RFS_Router(config-if)#no shut
RFS_Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
RFS_Router(config-if)#exit

RFS_Router(config)#int s0/0/0
RFS_Router(config-if)#ip address 3.1.6.218 255.255.255.252
RFS_Router(config-if)#no shut
RFS_Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
RFS_Router(config-if)#exit
RFS_Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
```

DHCP Configuration

COH:

```
COH_Router>en
COH_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
COH_Router(config)# interface fastethernet 0/0
COH_Router(config-if)# ip helper-address 3.1.0.2
COH_Router(config-if)# end
```

TMC:

```
TMC_Router>en
TMC_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
TMC_Router(config)#ip dhcp excluded-address 3.1.2.1 3.1.2.94
TMC_Router(config)#ip dhcp pool TMC_POOL
TMC_Router(dhcp-config)#network 3.1.2.0 255.255.254.0
TMC_Router(dhcp-config)#default-router 3.1.2.1
TMC_Router(dhcp-config)#dns-server 3.1.0.3
TMC_Router(dhcp-config)#exit
TMC_Router(config)#
```

PUN:

```
PUN_Router>en
PUN_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
PUN_Router(config)#ip dhcp excluded-address 3.1.4.1 3.1.4.34
PUN_Router(config)#ip dhcp pool PUN_POOL
PUN_Router(dhcp-config)#network 3.1.4.0 255.255.255.0
PUN_Router(dhcp-config)#default-router 3.1.4.1
PUN_Router(dhcp-config)#dns-server 3.1.0.3
PUN_Router(dhcp-config)#exit
PUN_Router(config)#
```

EDU:

```
EDU_Router>en
EDU_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
EDU_Router(config)#ip dhcp excluded-address 3.1.5.1 3.1.5.2
EDU_Router(config)#ip dhcp pool EDU_POOL
```

```
EDU_Router(dhcp-config)#network 3.1.5.0 255.255.255.0
EDU_Router(dhcp-config)#default-router 3.1.5.1
EDU_Router(dhcp-config)#dns-server 3.1.0.3
EDU_Router(dhcp-config)#exit
EDU_Router(config)#
```

EMP:

```
EMP_Router>en
EMP_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
EMP_Router(config)#ip dhcp excluded-address 3.1.6.1 3.1.6.2
EMP_Router(config)#ip dhcp pool EMP_POOL
EMP_Router(dhcp-config)#network 3.1.6.0 255.255.255.128
EMP_Router(dhcp-config)#default-router 3.1.6.1
EMP_Router(dhcp-config)#dns-server 3.1.0.3
EMP_Router(dhcp-config)#exit
EMP_Router(config)#
```

Routing Design

COH:

```
COH_Router>en
COH_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
COH_Router(config)#router rip
COH_Router(config-router)#version 2
COH_Router(config-router)#no auto-summary
COH_Router(config-router)#network 3.1.0.0
COH_Router(config-router)#network 3.1.2.0
COH_Router(config-router)#network 3.1.6.0
COH_Router(config-router)#passive-interface serial 0/0/1
COH_Router(config-router)#redistribute static
COH_Router(config-router)#exit
COH_Router(config)#ip route 3.1.5.0 255.255.255.0 3.1.6.206
COH_Router(config)#ip route 3.1.6.0 255.255.255.128 3.1.6.210
COH_Router(config)#ip route 3.1.6.128 255.255.255.192 3.1.6.210
COH_Router(config)#ip route 3.1.6.216 255.255.255.252 3.1.6.210
COH_Router(config)#
COH_Router(config)#
```

TMC:

```
TMC_Router>en
TMC_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
TMC_Router(config)#router rip
TMC_Router(config-router)#version 2
TMC_Router(config-router)#no auto-summary
TMC_Router(config-router)#network 3.1.2.0
TMC_Router(config-router)#network 3.1.6.192
TMC_Router(config-router)#network 3.1.6.200
TMC_Router(config-router)#exit
TMC_Router(config)#ip route 3.1.0.0 255.255.254.0 3.1.6.194 150
TMC_Router(config)#
```

PUN:

```
PUN_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
PUN_Router(config)#router rip
PUN_Router(config-router)#version 2
PUN_Router(config-router)#no auto-summary
PUN_Router(config-router)#network 3.1.4.0
PUN_Router(config-router)#network 3.1.6.212
PUN_Router(config-router)#network 3.1.6.192
PUN_Router(config-router)#exit
PUN_Router(config)#
```

EDU:

```
EDU_Router>en
EDU_Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
EDU_Router(config)#router rip
EDU_Router(config-router)#version 2
EDU_Router(config-router)#no auto-summary
EDU_Router(config-router)#network 3.1.5.0
EDU_Router(config-router)#network 3.1.6.204
EDU_Router(config-router)#network 3.1.6.212
EDU_Router(config-router)#passive-interface s0/0/0
EDU_Router(config-router)#exit
EDU_Router(config)#
```

EMP:

```
EMP_Router>en
EMP_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
EMP_Router(config)#ip route 3.1.0.0 255.255.254.0 3.1.6.193
EMP_Router(config)#ip route 3.1.2.0 255.255.254.0 3.1.6.193
EMP_Router(config)#ip route 3.1.4.0 255.255.255.0 3.1.6.193
EMP_Router(config)#ip route 3.1.5.0 255.255.255.0 3.1.6.193
EMP_Router(config)#ip route 3.1.6.128 255.255.255.192 3.1.6.218
EMP_Router(config)#ip route 3.1.6.200 255.255.255.252 3.1.6.193
EMP_Router(config)#ip route 3.1.6.204 255.255.255.252 3.1.6.193
EMP_Router(config)#ip route 3.1.6.212 255.255.255.252 3.1.6.193
EMP_Router(config)#exit
EMP_Router#
```


RFS:


```
RFS_Router>en
RFS_Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
RFS_Router(config)#ip route 3.1.0.0 255.255.254.0 s0/0/0
RFS_Router(config)#ip route 3.1.2.0 255.255.254.0 s0/0/0
RFS_Router(config)#ip route 3.1.4.0 255.255.255.0 s0/0/0
RFS_Router(config)#ip route 3.1.5.0 255.255.255.0 serial 0/0/0
RFS_Router(config)#
RFS_Router(config)#ip route 3.1.6.0 255.255.255.128 serial 0/0/0
RFS_Router(config)#ip route 3.1.6.192 255.255.255.248 serial 0/0/0
RFS_Router(config)#ip route 3.1.6.200 255.255.255.252 serial 0/0/0
RFS_Router(config)#ip route 3.1.6.204 255.255.255.252 serial 0/0/0
RFS_Router(config)#ip route 3.1.6.208 255.255.255.252 serial 0/0/0
RFS_Router(config)#ip route 3.1.6.212 255.255.255.252 serial 0/0/0
RFS_Router(config)#exit
RFS_Router#
```


Assumptions:


- In COH, server IPs are assigned sequentially
  Router=3.1.0.1
  DHCP=3.1.0.2
  DNS=3.1.0.3
  Web=3.1.0.4
  Mail=3.1.0.5
  Printer=3.1.0.6
  COH DHCP pool starts at 3.1.0.7 after excluding 6 static devices
- EDU excluded range = 3.1.5.1 to 3.1.5.2 for Router + printer
- EMP excluded range = 3.1.6.1 to 3.1.6.2 for Router + printer
- Max users COH = 504 as 512 -2 (network, broadcast)= 510, 510 -6 (static devices)
- TMC mail server IP = 3.1.2.2
  TMC printer IP = 3.1.2.3
- RFS PC1 IP = 3.1.6.130
  RFS PC2 IP = 3.1.6.131
  RFS printer IP = 3.1.6.132
- Email username used: group1903, password: 123
  One email account per mail server (group1903@coh.city and group1903@tmc.city)
  COH-PC1 outgoing = mail.tmc.city to enable cross-domain sending
  TMC-PC1 outgoing = mail.coh.city to enable cross-domain sending
  Only one PC per unit was email configured, as the requirement doesn't specify multiple PCs
- Recursive static routing: question mentioned “EMP must use a recursive static route to reach the COH network, pointing to TMC as the intermediate hop”, but didn't mention how to reach the other routers, so we configured the route to the other routers from EMP in the same way as EMP-COH


Server Configuration Screenshots:






DNS-Server
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IPv4 Address
3.1.0.3
Subnet Mask
255.255.254.0
Default Gateway
3.1.0.1
DNS Server
3.1.0.3
IPv6 Configuration
Automatic
Static
IPv6 Address
Link Local Address
FE80::230:F2FF:FEBE:526A
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password



DNS-Server
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
DNS
DNS Service
On
Off
Resource Records
Name
Type
A Record
Address
Add
Save
Remove
No.
Name
Type
Detail
0
mail.coh.city
A Record
3.1.0.5
1
mail.tmc.city
A Record
3.1.2.2
2
www.metropolis.city
A Record
3.1.0.4



Web-Server
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
X
IP Configuration
DHCP
Static
IPv4 Address
3.1.0.4
Subnet Mask
255.255.254.0
Default Gateway
3.1.0.1
DNS Server
3.1.0.3
IPv6 Configuration
Automatic
Static
IPv6 Address
/
Link Local Address
FE80::230:A3FF:FE2A:1C72
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password



Web-Server
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
File Name:
index.html
<html>
<body>
<h1>Smart City Operations - Online.</h1>
</body>
</html>



EDU-PC2
Physical
Config
Desktop
Programming
Attributes
Web Browser
X
<
>
URL
http://www.metropolis.city
Go
Stop
Smart City Operations - Online.



RFS-PC2
Physical
Config
Desktop
Programming
Attributes
Web Browser
X
<
>
URL
http://www.metropolis.city
Go
Stop
Smart City Operations - Online.



Email-Server
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
X
IP Configuration
DHCP
Static
IPv4 Address
3.1.0.5
Subnet Mask
255.255.254.0
Default Gateway
3.1.0.1
DNS Server
3.1.0.3
IPv6 Configuration
Automatic
Static
IPv6 Address
/
Link Local Address
FE80::206:2AFF:FE0D:AC39
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password


Email-Server
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
EMAIL
SMTP Service
ON
OFF
POP3 Service
ON
OFF
Domain Name:
coh.city
Set
User Setup
User
Password
group1903


COH-PC1
Physical
Config
Desktop
Programming
Attributes
Configure Mail
X
User Information
Your Name:
COH user
Email Address
group1903@coh.city
Server Information
Incoming Mail Server
3.1.0.5
Outgoing Mail Server
3.1.2.2
Logon Information
User Name:
group1903
Password:
Save
Remove
Clear
Reset


TMC-Email-Server
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
EMAIL
SMTP Service
ON
OFF
POP3 Service
ON
OFF
Domain Name:
tmc.city
Set
User Setup
User
Password
group1903


TMC-Email-Server
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
X
IP Configuration
DHCP
Static
IPv4 Address
3.1.2.2
Subnet Mask
255.255.254.0
Default Gateway
3.1.2.1
DNS Server
3.1.0.3
IPv6 Configuration
Automatic
Static
IPv6 Address
/
Link Local Address
FE80::2D0:BAFF:FEB2:4138
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password


TMC-PC1
Physical
Config
Desktop
Programming
Attributes
Configure Mail
X
User Information
Your Name:
TMC User
Email Address
group1903@tmc.city
Server Information
Incoming Mail Server
3.1.2.2
Outgoing Mail Server
3.1.0.5
Logon Information
User Name:
group1903
Password:
Save
Remove
Clear
Reset