Novell Teaming

1.0 www.novell.com

September, 2007

INSTALLATION AND CONFIGURATION GUIDE



Novell®

Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the Novell International Trade Services Web page (http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2007 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc., has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the Novell Legal Patents Web page (http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc. 404 Wyman Street, Suite 500 Waltham, MA 02451 U.S.A. www.novell.com

Online Documentation: To access the latest online documentation for this and other Novell products, see the Novell Documentation Web page (http://www.novell.com/documentation).

Novell Trademarks

For Novell trademarks, see the Novell Trademark and Service Mark list (http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

	Abo	ut This Guide	٧
1	Insta	alling Teaming	1
	1.1	Prerequisites	. 1
	1.2	Steps for Installing Teaming	
	1.3	Database Planning	
	1.4	File System Planning	
	1.5	Integrating with iChain	
	1.6	Editing the Installer (.xml) File	
	1.7	Running the Installer	
	1.8	Starting and Stopping Teaming	
	1.9	Memory Guidelines	
	1.10	Security Guidelines	
	1.11	Document Support.	
	1.12	Installing the Lucene Index Server	
	1.12	1.12.1 Install a Standalone Lucene Index Server for a New Teaming Application	
		1.12.2 Install a Standalone Lucene Index Server for an Existing Teaming Application	
	1.13	Load-Balancing and Clustering Teaming	
2	Conf	figuring Teaming	21
	2.1	Log in as Liferay Site Manager	21
		2.1.1 To Log In Using the Administrator Account:	
		2.1.2 Using the ICEcore Administration Portlet	
	2.2	Log in as JBoss Site Manager	23
	2.3	Initial Logon	23
	2.4	Adding Users	24
		2.4.1 Basic User Management	
		2.4.2 User Management with LDAP/eDirectory	
		2.4.3 The ICEcore LDAP Configuration Form	
	٥.	2.4.4 Secure LDAP/eDirectory Setup	
	2.5	Mail Setup	
	2.6	Adjust Access Control for the Site	
		2.6.1 Default Role Definitions	
		2.6.2 To Change a Default Role Definition: 2.6.3 Edit Default Team Workspace Access Rights	
	2.7	Create Your Initial Workspaces	
	2.1	2.7.1 Create an Administration Team Workspace	
		2.7.2 Set the Administration Team Access Rights	
		2.7.3 Using the Root Team Workspace	
	2.8	Invite Users to the Site	
	2.9	Set Up E-mail for a Workspace	45
	2.10	Mirrored Folders Configuration	
A	The	sample-installer.xml File	47
	IΔ2r	ning (=ineearl/	57

About This Guide

This guide covers the installation and initial configuration of Novell Teaming. Novell Teaming is implemented using ICEcore technology. The term "ICEcore" appears in the GUI (Graphical User Interface) and in many file/directory names and refers to the application technology that enables the Novell Teaming software. In this manual, the term "Teaming" applies to all versions of the Teaming software unless otherwise noted.

Audience

This guide is intended for Teaming administrators.

Contents of this Manual

This manual provides information about the following:

- Installing Teaming
- Configuring Teaming
- Controlling Access

Conventions

This manual uses the following conventions:

A greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol ([®], [™], etc.) denotes a Novell trademark. An asterisk (*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux or UNIX, should use forward slashes as required by your software.

What you see	What it means
Click the Add toolbar item.	References to toolbar items, links, menu items, and
Click the Getting Started link.	buttons are presented in <i>italic</i> font.
Click the Add Document menu item.	
Click Close.	
Type status, then press Enter.	Text that you must type and file names are
Open the ManagerGuide.pdf file.	presented in Courier font.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to www.novell.com/documentation/feedback.html and enter your comments there.

Documentation Updates

For the most recent version of the Teaming Installation and Configuration Guide and other documentation, visit the Novell Web site (http://www.novell.com/documentation/team_plus_conf).

Additional Documentation

You may find more information in the Teaming documentation, which is accessible from links within Teaming:

- Teaming Help system
- Teaming Quick Start Guide
- Teaming User Guide
- Teaming Admin Guide

The Teaming online documents may be found from within the Teaming Help system. To access the Teaming Help system, after logging in (described later in this manual), click the *Help* link.

In the Teaming Help system, click the *Getting Started Manuals* link to access copies of the online documents listed above.

Installing Teaming

This chapter describes how to initially install and configure Teaming:

- Section 1.1, "Prerequisites," on page 1
- Section 1.2, "Steps for Installing Teaming," on page 2
- Section 1.3, "Database Planning," on page 3
- Section 1.4, "File System Planning," on page 6
- Section 1.5, "Integrating with iChain," on page 6
- Section 1.6, "Editing the Installer (.xml) File," on page 8
- Section 1.7, "Running the Installer," on page 9
- Section 1.8, "Starting and Stopping Teaming," on page 11
- Section 1.9, "Memory Guidelines," on page 12
- Section 1.10, "Security Guidelines," on page 13
- Section 1.11, "Document Support," on page 15
- Section 1.12, "Installing the Lucene Index Server," on page 17
- Section 1.13, "Load-Balancing and Clustering Teaming," on page 19

1.1 Prerequisites

You need a few things before you install Teaming:

- 1. Computer:
 - Linux systems need to have a minimum open file limit of 4096.

For SLES, check /etc/security/limits.conf:

hard nofile 65535 soft nofile 4096

- Minimum 2Ghz processor
- Multi-CPU systems preferred
- Minimum 2GB RAM

NOTE: You may potentially run with less RAM for specific development and testing configurations without simultaneous users, lots of database traffic, etc.

See "Memory Guidelines" on page 12 for details.

- 2. Sun JDK 1.5.0 011 or higher installed (Java 1.6 is not yet supported).
- 3. A Database Server:
 - MySQL 5.0.37 (or higher) Server and Client for Linux or MySQL 5.0.26 (or higher) Server and Client for Windows

NOTE: MySQL 5.1 is not yet supported.

• SQL Server for Windows (2000 or 2005)

See "Database Planning" on page 3 for details.

How much disk do you need?

This depends on how much data you plan to put into the system. See sections "Database Planning" on page 3 and "File System Planning" on page 6.

The software takes about 250 MB.

1.2 Steps for Installing Teaming

The following sequence shows the steps you want to follow to install Teaming:

- **1** Install JDK (Sun JDK 1.5.0_011 or higher).
- **2** Set JAVA HOME environment variable.

For example:


- ◆ On Linux: export JAVA HOME=/usr/java/jdk 1.5.0 11
- ◆ On Windows: JAVA HOME=C:\Program Files\Java\jdk1.5.0 11
- **3** Install and Configure the Database Server.
- **4** Download the appropriate Teaming kit.
- **5** Edit the installer.xml file (see Editing the Installer (.xml) File).

NOTE: If you are doing an upgrade, use your existing license-key.xml and installer.xml files by placing them in the same directory as the installer program. If you are doing a new installation, copy the sample-installer.xml file to installer.xml and edit that file. The license-key.xml file required to install the product is provided with the software kit (but is not included in kit).

- **6** If you want to run the indexing service in Teaming on a different machine from Teaming, you have to Install the Lucene Index Server on the other machine.
- **7** Run the installer (on Linux, do a chmod +x installer-(liferay|jboss).linux to make the installer executable).

The installer is named one of the following according to your operating system and portal server:

- installer-liferay.exe
- installer-liferay.linux
- installer-jboss.exe
- installer-jboss.linux
- **8** Start and Stop Teaming.



1.3 Database Planning

Teaming and Liferay use separate dedicated databases within your database server.

A set of SQL configuration scripts are used to initialize the databases (creating the necessary tables, etc.).

Teaming's default database for Linux and Windows is MySQL. It also supports SQL Server on Windows, and Oracle on Linux and Windows.

Teaming's database requirements are relatively modest. The bulk of the data uploaded to Teaming is stored in a file repository (see File System Planning - the database is primarily used for storing metadata and descriptive text.

Because the amount of data stored in the database is highly sensitive to the usage patterns of Teaming (which are highly variable) there is no reliable formula for determining disk space usage, but the following can be used as a guideline:

- numberAttachments x averageAttachmentSize = totalAttachmentSpace
- totalAttachmentSpace * .04 = sqlDataSpace
- sqlDataSpace x 5 = sqlStorageSapce

MySQL

 MySQL 5.0.37 (or higher) Server and Client for Linux or MySQL 5.0.26 (or higher) Server and Client for Windows are required with "innodb support" enabled

NOTE: MySQL 5.1 is not yet supported.

- Specify root for the administrator password (or make commensurate changes in the Teaming installer.xml file)
- Set the default character set to UTF-8 by selecting "Best support for Multilingualism" in the Windows Configuration window, or edit the my.cnf configuration file to the following:

```
[mysqld]
character_set_server = utf8
[client]
default character set = utf8
```

NOTE: This file is located in /etc/my.cnf for Linux and in c:\my.cnf for Windows.

Microsoft SQL Server

- You can use SQL Server 2000 or SQL Server 2005
- Make sure to select SQL Server and Windows for authentication (the default is Windows only)
- Set the administrator password to "sa" (or make commensurate changes in the Teaming installer.xml file)

Oracle Database

• Supported versions: Oracle 9, Oracle 10.

NOTE: Oracle's default database name is "orcl". We use this name in our examples. If you have chosen a different name, replace "orcl" with your database name.

- Teaming is a Unicode-enabled application and requires you to set up the Oracle Database Character Set to support Unicode character encodings. The recommended value is AL32UTF8.
- To check your database character set execute the following command with SQL*Plus: select value from SYS.NLS_DATABASE_PARAMETERS where PARAMETER = 'NLS_CHARACTERSET';
- Before you install the Teaming application software, use the "Create Initial Database Scripts" option of the installer to obtain the two database creation scripts for oracle (one for the portal and one for Teaming).
 - a. Copy these scripts to a directory where you have access to the SQL*Plus utility and your database.
 - b. Edit the supplied database scripts to set the passwords for the users (these are defined in the top few lines of each script).
 - c. Use the SQL*Plus utility with the SYSTEM account to run the scripts:

```
sqlplus SYSTEM/systemPassword
sqlplus SYSTEM/systemPassword @create-database-oracle.sql
sqlplus> quit
```

- d. Edit the installer.xml file to use the Oracle_Default configuration and change the JDBC URLs to reflect the database and username/passwords you have chosen.
- e. Install the Teaming software using the UPDATE option (not the FULL INSTALL option). This installs the software, but does not run the database creation scripts, which you have already run separately.

Non-Local Database Setup

When installing the Teaming software for the first time (the "FULL INSTALL" option) one of the steps involves creating two databases: one for the portal and one for the Teaming application.

If you have granted the database user specified in the configuration the privileges needed to create a database, the installer creates the databases during the installation process.

For example, in MySql you can first create the databases and grant full access to the database user specified in the installer.

If this is done, the installer can create the rest of the database schema without further intervention: create database lportal;

```
grant all on lportal.* to dbuser@host identified by 'dbpassword'; create database sitescape; grant all on sitescape.* to dbuser@host identified by 'dbpassword';
```

However, there may be a number of reasons why this is not desirable.

If your database server administration doesn't allow this for security reasons, or if you have a special database setup, the installer can initially be run to extract the schema setup files and place them on the disk for you to examine or forward to the database administrator.

Once the schema is in place and the database user has been given the appropriate access rights for full database access, the installer can be run with the UPDATE option, which installs the software but doesn't create the databases.

The following are a list of "generic" database rights that are needed for normal operation of Teaming:

```
DELETE, INSERT, SELECT, UPDATE,
ALTER TABLE, CREATE TABLE, CREATE VIEW, DROP,
CREATE INDEX, DROP INDEX, DRI
```

The first four are obvious. The rest are related to schema changes that may be invoked during upgrades or configuration changes.

NOTE: "DRI" refers to Microsoft SQLServer foreign key constraints.

The initial database creation scripts may CREATE/DROP USERs, but that is the only time users are defined.

Port 80/443 configuration on Linux

The default installation of Teaming uses the Tomcat web server. Although the Tomcat server is part of the Apache project, it is not the same thing as the Apache web server. Tomcat is written in Java and can not do some of the special privilege behaviors that Apache can.

In particular, Linux does not allow non-root processes from allocating TCP/IP ports less than 1024. For this reason the default configuration for Tomcat (and Teaming) uses ports 8080 for http and 8443 for https (SSL). Unfortunately this requires specifying the port number in the browser's URL for Teaming (e.g., http://icecore.mycompany.com:8080).

WARNING: While running Tomcat as "root" solves this problem, it creates many (far worse) problems. Do not do this!

If you want Teaming to be available on the default http/https ports, use an operating system feature called "kernal space port forwarding". The <code>iptables</code> command is used to map requests from port 80 to port 8080 (or whatever port you specify). For example:

```
iptables -t nat -A OUTPUT -d localhost -p tcp --dport 80 -j
REDIRECT --to-ports 8080

iptables -t nat -A OUTPUT -d yourHostname -p tcp --dport 80 -j
REDIRECT --to-ports 8080

iptables -t nat -A PREROUTING -d yourHostname -p tcp --dport 80 -j
REDIRECT --to-ports 8080

iptables -t nat -A OUTPUT -d localhost -p tcp --dport 443 -j
REDIRECT --to-ports 8443

iptables -t nat -A OUTPUT -d yourHostname -p tcp --dport 443 -j
REDIRECT --to-ports 8443

iptables -t nat -A PREROUTING -d yourHostname -p tcp --dport 443 -j
REDIRECT --to-ports 8443
```

If you install Teaming as the "root" user, it will ask if you want to use iptables to set up this mapping. See the iptables man page for more information about port forwarding.

1.4 File System Planning

Teaming software and configuration files are stored in a tree shared with Liferay, Tomcat, etc. There are some temporary files also located here, but mainly locks, etc.

Teaming data is stored in the database (see "Database Planning" on page 3) and on the file system. The file system usage is divided up into several functional areas:

- filerepository This is where all attachment files are located, so it tends to be a large consumer of disk space. The tree is roughly organized by site, binder (folder/workspace), and entry.
- archiveStore Only activated in the Enterprise version of Teaming, this is where previous versions of files are stored. The files are stored here to meet compliance and archival goals.
- cachefilestore This tree holds information derived from the attachments, such as thumbnails, scaled images, text, and HTML renderings. Depending on the nature of the attachments this tree consumes somewhat less space than the file repository (but it can, conceivably, store more).
- lucene This tree holds the search index for the data. It tends to be a fraction of the space consumed by the file repository, but it is also sensitive to the type of information stored.
- Other trees These are other trees that you cannot configure which typically consume a small amount of space (relatively speaking).
 - rss Caches of RSS feeds for folders
 - temp Temporary files

1.5 Integrating with iChain

NOTE: This feature is only available in the Enterprise version.

Liferay/Teaming contains support for iChain-based single sign-on (SSO).

When running in this mode, the iChain server performs user authentication tasks and passes a token representing the authenticated user's login name to Liferay/Teaming in each request to indicate who made the request.

Liferay/Teaming must be configured with the same LDAP that the iChain is using so that it can obtain and copy the user information into the portal.

However, this configuration differs from the regular portal/LDAP integration in that no password checking is performed against the LDAP when logging into the portal (because credential checking is only performed by the iChain server). This technique is safe only under the assumption that ALL accesses to the portal are routed through the iChain proxy. The SSO configuration sets up a "valve" that only permits access from the local server and the iChain proxy server.

To set up an iChain proxy, the following steps must be taken:

- **1** Assure that the iChain proxy's port number matches the Teaming/Liferay port number. For example, if you have configured Teaming to run on port 8080, the iChain proxy must also use port 8080. If you change ports through the proxy, some Teaming features do not work properly.
- **2** Edit the SSO section in the installer.xml file and set the SSO enable="true", set the Logoff URL to the log-off URL provided by the iChain proxy server, and set the IP address of the iChain proxy server.
- **3** Install the software or, if you have already installed Teaming, stop the running server and use the installer's "Apply Settings only" option.
- **4** After enabling the iChain SSO, you need to log into Liferay using a direct login URL: http://localhost:8080/c/portal/login and log in as admin. Since the SSO configuration removes the "Sign In" link, you must type the URL manually.
- **5** If you have not already done this, use Liferay's *Admin* portlet to enable LDAP-based authentication. This setup is necessary since Liferay has to copy user data from the LDAP into the portal database upon user login.
- **6** To prevent users from logging into the portal directly through the portal's login form, remove or rename the following file from Teaming's liferay-portal-tomcat directory: webapps/ROOT/html/portal/login.jsp

You may also need to remove:

```
work/Catalina/localhost/ /org/apache/jsp/html/portal/login jsp.*
```

7 Liferay/Teaming is now ready to be put behind the proxy. Consult your iChain documentation on how to do this.

NOTE: To enable iChain integration-related debug log messages, modify Liferay's portal-log4j-ext.xml to add the following category:

```
<category name="com.sitescape.team.liferay.security.auth">
  <priority value="DEBUG" />
  </category>
```

Use it only for testing or troubleshooting purpose. It is not recommended to have debug logging enabled on a production system.

1.6 Editing the Installer (.xml) File

The installer.xml file provides the Teaming installer with detailed configuration information regarding network, memory, database, file system, e-mail, presence, and other settings. Edit this file with your specific data.

The "sample-installer.xml" file is included in the kit and should be used as a template for the installer.xml file. If you are doing an upgrade, use your existing installer.xml file by placing it in the same directory as the installer program. If you are doing a new installation, copy the sample-installer.xml file to installer.xml and edit that file.

For a quick installation edit the following sections:

- 1 Change the Host name in the Network section. Change the port number to 80 and the securePort to 443 if this is a dedicated server.
- **2** Consider changing the JavaVirtualMachine setting in the Memory section if you have a large installation.
- 3 Use the default file system configuration. This stores the files in /home/icecoredata
- **4** The default database configuration is MySQL, with the default MySQL passwords.
- 5 Use the default Lucene configuration (unless you are installing a standalone Lucene Index Server.
- **6** Modify the Email section with your SMTP and POP/IMAP servers.
- 7 If you are using Conferencing, change the settings in the Presence configuration.

To view the sample-installer.xml file, see Appendix A, "The sample-installer.xml File," on page 47.

1.7 Running the Installer

The following procedure shows you how to run the installer.

1 Run the installer (on Linux, do a chmod +x - (liferay|jboss).linux to make the installer executable).

The installer is named one of the following according to your operating system and portal server:

- ◆ installer-liferay.exe
- ◆ installer-liferay.linux
- installer-jboss.exe
- installer-jboss.linux
- **2** Answer Yes to the license agreement:

```
Have you read and agree with the license? : yes
```

3 Enter the type of install you are performing:

WARNING: A full install erases the existing databases for an existing Teaming application (use the UPDATE installation for existing Teaming applications).

```
Enter the type of installation:

1. ICEcore Enterprise with Liferay/JBoss - FULL INSTALL
2. ICEcore Enterprise with Liferay/JBoss - UPDATE
3. ICEcore Enterprise Lucene Server
4. Apply settings only (Use with care)
5. Create Initial Database setup scripts for DBA
6. Exit (no changes)

Installation type [1]: 1
```

1. **FULL INSTALL** - This option installs the Teaming application software and creates the initial portal and Teaming databases.

The software is installed in the following dedicated directory: /opt/icecore

- **2. UPDATE** This option installs the Teaming application software and uses the existing portal and Teaming databases. Schema updates are applied as necessary.
- 3. Lucene Server This is an advanced configuration option that allows you to locate the Lucene Index Server on a different system than your Teaming application server. See Section 1.12, "Installing the Lucene Index Server," on page 17 for details on configuring your systems to use this option.

4. Apply Settings - The installation program uses configuration information in the installer.xml file to write a number of application configuration files. Most changes to the configuration do not require a reinstallation of the software, but just an update of the settings. Use this option to update those files without reinstalling the software.

NOTE: The *Apply settings only* option can potentially corrupt your existing system (USE WITH CARE).

- 5. Create Initial Database Scripts By default the software installation process creates the database schemas needed for operation of the software. If your database server administration does not allow this, use this option to extract the schema setup files for review and execution by your database administrator (DBA). This option installs no software or makes any changes to the application configuration.
- **4** Review the installation messages and enter Y to continue the install or N to cancel: Enter Y to continue, enter N to cancel installation [Y]: Y
- **5** The install process asks you if want to create the Teaming databases at this time; select 1 to create the databases or 2 to skip this step:

```
About to create the databases for ICEcore:

1: Create the databases now.

2: The databases were created by my DBA, don't create them now.

(1/2) [1]: 1

Creating jboss database for SQLServer ...
```

1.8 Starting and Stopping Teaming

Starting Teaming/Liferay

NOTE: These are Liferay only instructions.

On Windows:

C:\yourinstall\liferay-portal-tomcat-5.5-jdk5-4.3.0\bin\startup.bat

On Linux:

/yourinstall/liferay-portal-tomcat-5.5-jdk5-4.3.0/bin/icecore start

NOTE: While this is dependent on your system configuration, it can take upwards of 60 seconds before Teaming/Liferay starts accepting web transactions. Initial transactions also tend to be slower as various caches load into RAM. These delays are amplified somewhat when working with a new installation or updated software as the JSPs are recompiled as they are referenced.

In Windows, startup is complete when the Tomcat window displays:

INFO:Server Startup in #### ms

Setting up Teaming to start on system startup

On Windows:

- 1 C:\yourinstall\liferay-portal-tomcat-5.5-jdk5-4.3.0\bin\service.bat
 install icecore
- **2** Use the Services Control Panel to configure the service to your needs.
 - **2a** Select Control Panel > Administration Tools > Services.
 - **2b** Right-click on the *ApacheTomcat icecore* service and select *Properties*.
 - **2c** Change the *Startup Type* to *Automatic* and click *OK*.

On Linux, from the root account:

- 1 cp /yourinstall/liferay-portal-tomcat-5.5-jdk5-4.3.0/bin/icecore /etc/ init.d
- 2 chkconfig --add icecore

Log Files/Monitoring

On Windows:

A Tomcat window appears when you issue the startup.bat command. Messages (good and bad) appear here.

On Linux:

Unlike Windows, the Tomcat process starts as a background process and no window appears. To monitor the messages in real time:

tail -f /yourinstall/liferay-portal-tomcat-5.5-jdk5-4.3.0/logs/catalina.out

Stopping Teaming

On Windows:

C:\yourinstall\liferay-portal-tomcat-5.5-jdk5-4.3.0\bin\shutdown.bat

On Linux:

/yourinstall/liferay-portal-tomcat-5.5-jdk5-4.3.0/bin/icecore stop

1.9 Memory Guidelines

Teaming is a Java/J2EE application and therefore executes within a "Java Virtual Machine" (JVM). The JVM exists as a process on your system and all of the Teaming and portal software run within it. Consequently the amount of memory available to the JVM process is a critical aspect of overall Teaming performance.

The key JVM memory setting is the "Java Heap Size", which roughly corresponds to the amount of memory available to the Java applications (such as Teaming).

The installer.xml file's Memory section allows you to determine how much physical memory to devote to the Java Virtual Machine.

The default configuration assumes that the JVM uses 1g (one gigabyte) of memory. It is possible to run Teaming with less than 1GB of assigned memory, but this is only applicable to very small test configurations, and is not suitable for production use. (In such a test configuration, 512MB is the minimum amount of memory required to produce a functioning Teaming application.)

A general rule of thumb is that no more than 75% of the available physical memory should be allocated to the JVM. This means that you need to account for other processes (including the operating system itself) that use memory. Databases, in particular, tend to be memory-intensive, so take special care when co-locating a database server with the Teaming application server.

WARNING: A JVM on a 32-bit system should never be configured to take more than 1.5GB (1500MB) of memory. Larger memory allocations require 64-bit servers.

Teaming memory usage is driven by a number of factors:

- 1. Number of sessions (users logged in)
- 2. Number of active/concurrent sessions
- 3. Teaming internal database caches
- 4. Lucene index cache

Items #1 and #2 do not represent a significant amount of memory.

Item #2 generally correlates to heavier CPU utilization (as this number increases the need for clustered configurations becomes more important).

Item #3 can be a significant fraction of memory use (these are separate from any caching or memory use by the database server itself, which may or may not be on the same server). Internal tuning settings have been set to handle a wide range of deployment sizes.

Item #4 can also be a significant consumer of memory. Large data stores (particularly with large files or a high number of files) can create a very large index. Installations with this type of demand should consider separating the Lucene Index Server to a dedicated standalone server for optimum performance (see Section 1.12, "Installing the Lucene Index Server," on page 17).

1.10 Security Guidelines

This section contains security guidelines for the following:

Role-Based Access Control

Teaming controls all access to folders and entries using role-based access controls. See Section 2.6, "Adjust Access Control for the Site," on page 31 to learn more about the default roles and access settings.

NOTE: Please keep in mind that Teaming is intended to be used primarily for the sharing of information, so many default access rights lean towards allowing at least universal read access.

Inbound Email

You can configure Teaming to read e-mail and "post" those e-mail messages as entries in a folder. Because e-mail is inherently insecure there is no way to be sure that the sender is who they claim. Teaming marks the entries posted by e-mail to alert users about their origin.

Web Services are enabled by default

The default Teaming installation allows authenticated access via web services. If you are not using web services, you can disable them by setting enable="false" in the Network/WebServices section of the installer.xml file.

RSS feed URLs

Because RSS readers are outside of the authentication system, the URL provided by Teaming for an RSS feed embeds some authentication information about the user. This means that the RSS URL must be protected and not shared between users.

For this reason RSS is not recommended for use on highly sensitive data.

To disable RSS feeds, modify the RSS section of your installer.xml file to: enable="false" either during the initial installation or use the installer's Apply Settings only option to disable it at any time after installation.

LDAP (directory service) Proxy User

You can configure Teaming (and the portal) to utilize information in the LDAP directory service to provide basic user account information (and group memberships). Access to the LDAP server is done via a configuration page that requires specifying a username and password to LDAP directory. This user should be created in the LDAP directory service with the minimum number of privileges needed to perform the job.

In particular, all LDAP synchronization activities are one-way, so the proxy user only requires READ access to the directory.

Mirrored Folder Proxy User

See Section 2.10, "Mirrored Folders Configuration," on page 46 for more information about the mirrored folder feature of the Enterprise version of Teaming.

You can configure Teaming to use server directories (either the local file system or via file sharing) as repositories for Teaming folders. Because the Teaming application server is accessing those directories, the user id that the application server runs as acts as a proxy user for all file system access (i.e., the file system only sees one user accessing the files on behalf of all Teaming users who have access to the Teaming folder). This proxy user should be used to configure any local file system access (or shared file access) appropriately.

If you configure a mirrored folder to a WebDAV or Microsoft Sharepoint directory, the resource driver is configured to use a proxy username and password. The same access control practices should be applied to these resources as with the file system resource driver.

• Password Storage in the Server File System

A number of application accounts and passwords are stored in the file system. These files should be protected against unauthorized access on the server.

The installer.xml file contains a majority of the account and password information. You should protect this file accordingly. The installation "Apply Setting" phase uses this information to create and/or update a number of configuration files within the application software directory tree.

These files are outlined below:

 Database user ids and passwords for the portal and Teaming software are stored in XML files are stored in:

```
conf/Catalina/localhost/ssf.xml (Teaming)
conf/Catalina/localhost/ROOT.xml (Liferay Portal)
all/deploy/portal-mysql5-ds.xml (JBoss Portal)
all/deploy/portal-sqlserver-ds.xml (JBoss Portal)
```

• Mirrored folder resource drivers to WebDAV/Sharepoint shares store the proxy user and passwords in:

```
WEB-INF/classes/config/ssf.properties
```

• The email access (both inbound and outbound) may contain usernames and passwords for authentication (e.g., authenticated SMTP). These are stored in:

```
conf/Catalina/localhost/ssf.xml (ICEcore)
conf/Catalina/localhost/ROOT.xml (Liferay Portal)
```

Some application accounts and passwords are stored in the database. These are protected by application access controls, but are available if access to the database is obtained through other means:

- LDAP proxy user and password.
- Database access is unencrypted by default

Depending on your local security guidelines, you may want to encrypt the database connections between the Teaming and Portal software and their respective databases. Please note that SSL encrypted data between the applications and database servers imposes a performance penalty due to the increased overhead of encrypting/decrypting the retrieved data.

Support for this is highly dependent on the database client drivers and JDBC connector support and how you are configuring your client and server certificates. You should check with the database vendors on how to set up SSL connections on both the client and server sides of the connection. At minimum you need to update the JDBC URLs in the Database section of the installer.xml file (e.g., for MySQL you might add

"useSSL=true&requireSSL=true" to the options part of the URL).

LDAP Directory access is unencrypted by default

See Section 2.4.4, "Secure LDAP/eDirectory Setup," on page 29 for information about configuring Teaming to use SSL when communicating with the LDAP directory.

• File System Repositories contains unencrypted data

See Section 1.4, "File System Planning," on page 6 for details about how Teaming uses the local file system for data storage. These directories contain uploaded information in various formats (both native file formats and potentially a number of rendered formats (e.g., cached HTML versions of files, thumbnails, RSS feeds, etc.) as well as archived data.

These files are managed exclusively by the Teaming application software and the file system protections should be set to protect those directories from unauthorized access.

1.11 Document Support

When a file is uploaded into Teaming it is processed in a number of ways:

- 1. Textual content is extracted and sent to the search engine. For some file types (e.g., word processing documents) the textual content is obvious. For others, such as graphics files, there may be little or no textual content beyond basic metadata.
- 2. If possible, a thumbnail (and scaled image somewhat larger than a thumbnail) of the file is created. The thumbnail of a multi-page document shows the first page.
- 3. If possible, an browser-only renderable (HTML) version of the file is created. This allows people who do not have the ability to open the file with its native application to get an idea of what is in the file. The rendering is on a "best effort" basis and the level of detail and fidelity of the rendering varies greatly.

The Open and Enterprise versions of Teaming vary greatly in their ability to perform the above tasks

The Open version uses OpenOffice to provide access to common Microsoft and OpenOffice document formats, and that is about it.

The Enterprise version uses a licensed technology from the Stellent* company (now part of Oracle*) which provides processing capabilities to a wide spectrum of file types (over 200).

Editing Support

There are two ways of editing files stored in Teaming:

- 1. Download the file to your desktop. Edit the file. Upload the file to the entry (as an attachment). A new version of the attachment is created reflecting your changes. It is possible to manually "lock" the entry if you want to prevent other people from modifying any of the attached files.
- 2. Certain file types provide an [Edit] button which allows for "edit in place". When available, clicking on the [Edit] button will launch a small Java applet which, in turn, launches the associated edit program for the file. The program accesses the file stored in Teaming through WebDAV and is subject to the individual file locking protocols that WebDAV provides. Saving the file (or exiting the application) creates a new version of the attachment no interaction with the browser is needed.

Because the "edit in place" option requires the WebDAV URL support by the application, which is not universally supported by the operating systems, Teaming must be configured to know which applications are "WebDAV-aware."

The following table shows the planned default configuration of file/document support in Teaming.

		HTML	View	Thumbs:	ails	Appli	cation	Edit via	Sear	ch
Ezt	Description	Open	Ent		nt	Vindows	Linex	WebDAY		
doc	MS Word	?	X	-	X	winword	ooffice	X	X	X
xls	MS Excel	?	Х		X	excel	ooffice	X	×	Х
ppt	MS Powerpoint	?	X		Х	powerpnt	ooffice	X	X	Х
ods	OO Calc	Х	X		Х	soffice	ooffice	X	×	X
odq	OO Draw	X	X		X	soffice	ooffice	X	X	X
odp	OO Impress	X	X		Х	soffice	ooffice	X	X	Х
odf	OO Math	X	X		X	soffice	ooffice	X	X	X
odt	OO Writer	X	X		X	soffice	ooffice	X	X	×
SXW	OO Text	?	X		X	soffice	ooffice	X	×	X
docx	MS Word 2007		X		X	winword	0000	V		X
xlsx	MS Excel 2007		X		X	excel		Ÿ		X
pptx	MS Powerpoint 2007	-	X		X	powerpnt		Ÿ		X
123	Lotus 1-2-3	-	×		X	ролегри			-	X
avi	Windows Multimedia		X		X					X
bmp	Bitmap Graphic		X		X					X
cdr	Corel Draw		X		X					X
ogm	Computer Graphics Metafile	-	×		X				-	X
dsf	Micrographix Designer		X		X					X
dwg	AutoCAD Drawing Format		×		X					X
dxf	AutoCAD Exchange Format		X		X					X
gif	Graphics		- "		X				-	X
hpgl	HP Graphics Language		Х		X				-	X
htm	HTML		X		X				-	X
html	HTML		×		X			-	-	X
	Graphics		^		X					X
jpg lue	Lotus WordPro		Х		X					X
lwp mdb	MS Access		x		X					x
mov	QuickTime Movie		x		X					x
mp3	Audio		x		X					X
	Movie		x		X					X
mpeg	Movie		x		X					X
mpg			×		X					X
mpp	MS Project Adobe Portable Document		X		X					X
pdf		-	^							
png	Graphics MC Decreasion		o.		X					Х
pps	MS Powerpoint	-	X		X	powerpnt				Х
ps	Postscript		X		X			-		X
psd	Adobe Photoshop		X		X			-		X
qt	QuickTime Movie		X		X					X
rm	Real Movie		X		X		441			X
rtf	Rich Text Format		X		X	winword	ooffice			X
tif	Graphics		X		Х				-	Х
tiff	Graphics		X		Х					Х
txt	Text		X		X	winword	ooffice		X	X
vsd	MS Visio		X		Х					Χ
wav	Windows Wave Audio		X		Х					Х
wk1	Lotus Worksheet		X		Х					Х
wk3	Lotus Worksheet		X		X					Χ
wk4	Lotus Worksheet		X		Х					X
wpd	WordPerfect		X		Х					Х
xbm	X-Windows Bitmap		X		Х					Х
xml	XML		X		Х					Х
xpm	X-Windows Pixmap		X		Х					Х
zip	Compressed files (PKZIP)		Х		Х					X

1.12 Installing the Lucene Index Server

The following procedures show you how to install the Lucene Index Server on a different machine from Teaming (the Lucene Index Server is included in a full install of Teaming on the Teaming Server):

- Section 1.12.1, "Install a Standalone Lucene Index Server for a New Teaming Application," on page 17
- Section 1.12.2, "Install a Standalone Lucene Index Server for an Existing Teaming Application," on page 18

NOTE: You need to install JDK (Sun JDK 1.5.0_011 or higher) before installing the Lucene Index Server.

1.12.1 Install a Standalone Lucene Index Server for a New Teaming Application

1 On the standalone machine, edit the Installer.xml file (see "The sample-installer.xml File" on page 47):

- 1a In the Lucene section, set luceneLocation="server"
- **1b** If necessary, edit the default rmi port: lucene.rmi.port="1099"
- **2** Run the installer on the standalone machine and choose the option for: ICEcore Enterprise Lucene Server (see Section 1.7, "Running the Installer," on page 9).
- **3** Start the server at the end of the installation:
 - 3a Change directories to lucene-server-installation-dir
 - **3b** Run the rmiregistry-startup script in the bin directory
 - **3c** Run the indexserver-startup script in the bin directory
- **4** On the Teaming server, edit the Installer.xml file:
 - **4a** In the Lucene section set luceneLocation="server"
 - **4b** Set lucene.index.hostname to the hostname of the machine on which you installed the Lucene Index Server (in steps 1-3).
- **5** Run the normal installation of Teaming (see Section 1.7, "Running the Installer," on page 9).

1.12.2 Install a Standalone Lucene Index Server for an Existing Teaming Application

1 On the standalone machine, edit the Installer.xml file (see "The sample-installer.xml File" on page 47):

- 1a In the Lucene section set luceneLocation="server"
- **1b** If necessary, edit the default rmi port: lucene.rmi.port="1099"
- **2** Run the installer on the standalone machine and choose the option for: ICEcore Enterprise Lucene Server (see Section 1.7, "Running the Installer," on page 9).
- **3** Shutdown Teaming on the Teaming server (see Section 1.8, "Starting and Stopping Teaming," on page 11).
- **4** On the standalone machine, check the lucene-server.properties file and find the setting for index.root.dir (you can edit this setting to change the location of the root directory).
- **5** Create a "liferay.com" subdirectory in the <index.root.dir> directory.
- **6** On the Teaming server, look at the ssf.properties file and find the data.root.dir setting.
- 7 Copy all the files from the <data.root.dir>/lucene/liferay.com directory on the Teaming server to the <index.root.dir>/liferay.com directory you just created on the standalone machine.

IMPORTANT: If you are using ftp, make sure to copy in binary mode.

- **8** For Unix systems, make sure permissions are set so that the Teaming user has full access to these files and the liferay.com directory.
- **9** Start the server at the end of the installation (if not started already):
 - 9a Change directories to lucene-server-installation-dir
 - **9b** Run the rmiregistry-startup script in the bin directory
 - **9c** Run the indexserver-startup script in the bin directory
- **10** Restart Teaming (see Section 1.8, "Starting and Stopping Teaming," on page 11).

1.13 Load-Balancing and Clustering Teaming

NOTE: In this release, Teaming does not support session replication across nodes in a cluster.

To set up a scalable, clustered Teaming configuration, use the following steps as a guideline:

1 Set up a shared file storage that is accessible to all nodes.

Teaming's Simple File Repository is safe for use in a clustered environment with shared storage that is accessible to all nodes. Setting up shared storage is a platform-specific task.

2 Install and configure the Lucene Index Server.

See "Installing the Lucene Index Server" on page 17 for how to place the Lucene Index Server on a dedicated server system. All cluster nodes will shared this index server.

- **3** Make sure that the time is the same on all nodes in the cluster. Using synchronized time services for your cluster is highly advised.
- **4** Install the Teaming/portal bundle kit on each cluster node.

IMPORTANT: Since all the nodes share the same database server, it is important not to execute the database-initialization SQL scripts more than once (e.g., use the installer's UPDATE option rather than the FULL INSTALL on all but the first cluster node).

Each node in the cluster should be able to use the same installer.xml file. This assures that cluster nodes are configured uniformly.

The following settings must be uniform across the cluster:

- Configure the database connection settings on each node to use the same database.
- Set the file system settings to all point to the same shared file storage server.
- Set the Network settings (e.g., name, port, etc.) to the name of the LOAD BALANCER system.
- In the Lucene section, set luceneLocation="server" and set lucene.index.hostname to the hostname of the machine on which you installed the Lucene Index Server.
- **5** Set the portal up to work in a clustered environment.

For Liferay, follow the instructions at wiki.liferay.com (http://wiki.liferay.com/index.php/Clustering). If you are interested, Liferay provides additional high availability information at wiki.liferay.com (http://wiki.liferay.com/index.php/High_Availability_Guide).

For the JBoss portal, since Teaming is bundled with the High Availability edition of the JBoss portal, the default out-of-box configuration is already cluster-ready.

6 Configure the Load Balancer.

There are a variety of load balancing solutions that work with J2EE deployments. The following example configuration uses the balancer module built into the newer Apache (version 2.2.4), and is based on a widely-used sticky session technique. We do not support session sharing/replication among Tomcat instances.

6a Edit Tomcat's server.xml.

Add jvmRoute="jvm<n>" to the <Engine name="Catalina" ...> element, where <n> should be an integer unique to each Tomcat instance. For example, assuming you have two Tomcat instances in a cluster, the Catalina engine element should look like the following in each server.xml respectively (jvm<n> is the name of the worker as declared in the load-balancer):

```
<Engine name="Catalina" defaultHost="localhost" jvmRoute="jvm1">
<Engine name="Catalina" defaultHost="localhost" jvmRoute="jvm2">
```

- **6b** Edit Apache's httpd.conf file (in the <apache installation>/conf directory).
 - 1. Uncomment the following three lines:

```
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_ajp_module modules/mod_proxy_ajp.so
LoadModule proxy balancer module modules/mod proxy balancer.so
```

2. Append the following section to the end of the file:

```
<Location /balancer-manager>
SetHandler balancer-manager
Order deny,allow
Deny from all
Allow from 127.0.0.1
</Location>
<Proxy balancer://aspenCluster>
BalancerMember ajp://<tomcat host name 1>:8009 route=jvm1
BalancerMember ajp://<tomcat host name 2>:8009 route=jvm2
</Proxy>
<Location />
ProxyPass balancer://aspenCluster/ stickysession=JSESSIONID
</Location>
```

NOTE: In the above, you will have to substitute the real tomcat host names for <tomcat host name 1> and <tomcat host name 2> respectively. If you have more than two Tomcat instances in the cluster, make an additional line for each.

- 7 Configure Hibernate to use the cluster-safe second-level cache. For this, you need to modify the cache settings in /ssf/WEB-INF/classes/config/ehcache-hibernate.xml for each node in the cluster.
 - **7a** First, uncomment the following section to enable distributed cache:

```
<!--<cacheManagerPeerProviderFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerProviderFactory"
properties="peerDiscovery=automatic,multicastGroupAddress=232.0.0.1,mu
lticastGroupPort=4446,timeToLive=1" />
<cacheManagerPeerListenerFactory
class="net.sf.ehcache.distribution.RMICacheManagerPeerListenerFactory"
/>-->
```

7b Also, uncomment the following section in each cache definition, including the default cache:

```
<!--<cacheEventListenerFactory
class="net.sf.ehcache.distribution.RMICacheReplicatorFactory" />
<bootstrapCacheLoaderFactory
class="net.sf.ehcache.distribution.RMIBootstrapCacheLoaderFactory" />-->
```

8 Start the Lucene Index Server first, and then start the application cluster nodes.

Configuring Teaming

2

Before using Teaming, you need to perform initial configuration tasks to set up Teaming so that all default features are operable. The following sections are covered in this chapter:

- Section 2.1, "Log in as Liferay Site Manager," on page 21
- Section 2.2, "Log in as JBoss Site Manager," on page 23
- Section 2.3, "Initial Logon," on page 23
- Section 2.4, "Adding Users," on page 24
- Section 2.5, "Mail Setup," on page 30
- Section 2.6, "Adjust Access Control for the Site," on page 31
- Section 2.7, "Create Your Initial Workspaces," on page 39
- Section 2.8, "Invite Users to the Site," on page 44
- Section 2.9, "Set Up E-mail for a Workspace," on page 45
- Section 2.10, "Mirrored Folders Configuration," on page 46

2.1 Log in as Liferay Site Manager

You need to log in using an administrator account in order to set up Teaming for your users.

2.1.1 To Log In Using the Administrator Account:

1 Type the Teaming URL for your company into the browser window: http://<yourCompany.com>/portal/portal/default

The Sign In page appears.

2 In the *Login* field, type:

Admin

3 In the *Password* field, type: Admin

4 Click Login.

The Teaming Home Page appears. You are now logged in as administrator.

The Liferay portal management links are in the upper-right corner of the page below the *Welcome Mary Admin!* text. This is the name associated with the default administration account (*administrator*). When the name appears in the upper-right corner, you are logged into the system. (You can change the name "Mary Admin" by modifying the user profile for the *administration* account.)

When you begin managing Teaming, there are only two management levels: site managers (who manage the server machine) and portal managers.

By default, *administrator* is the only member of the Administrators group for the Liferay portal Administrators group. Members of the Administrators group have the right to perform portal management tasks. If you choose, you can add other members to this group, so that they can help manage the portal.


2.1.2 Using the ICEcore Administration Portlet

The ICEcore Administration portlet is designed to provide you with a maximum amount of flexibility when managing resources for your teams.

Access the Teaming management options via the *ICEcore Administration* portlet.

To Add the ICEcore Administration Portlet to Your Home Page:

- 1 Click *Add Content* in the upper-right corner.
- **2** In the portlet access frame that appears in the upper-left corner, click *ICEcore* to view the available ICEcore portlets that you can add.



3 Click the *Add* button next to *ICEcore Administration* to add this portlet to your Home Page.

The *ICEcore Administration* options provides you with access to all the administration tasks controlled by the Teaming software.

NOTE: Because Teaming is embedded within Liferay, a portion of user management is delegated to the Liferay. For example, Liferay is responsible for all user authentications using the *Enterprise Admin* portlet.

2.2 Log in as JBoss Site Manager

You need to log in using an administrator account in order to set up Teaming for your users.

- 1 Type the Teaming URL for your company into the browser window: http://<yourCompany.com>/portal/portal/default
- **2** Click the *Admin* link in the top bar.
- 3 Click Portal Definitions.
- **4** Click *local./ssf.ss administration*.
- **5** Scroll to the bottom of the screen.
- 6 Type in the Instance Name (no spaces): ICEcoreAdmin
- **7** Type a window name into the *Window Name* field under *Content Definition* before clicking *Add*.

NOTE: The recommended window naming convention for ICEcore side is <portlet name>-window. So, for instance, to create a window from the ss_administration-instance, name it ss_administration-window, etc.

- **8** Click *Add*. (You are now in the Portlet Instances).
- **9** Click *Dashboard* in the top bar.
- **10** Click *Configure Dashboard*.
- **11** Select *ICEcoreAdmin* and click *Add to Page Layout*.
- **12** Click *Dashboard* in the top bar.

NOTE: You now see *ICEcoreAdmin* on the Dashboard.

2.3 Initial Logon

After installing Teaming/Liferay you need to log in. The Teaming installation creates one system administrator account and a default format for users.

- 1. Access your installation with a browser via the following URL: http://yourhost.name.here:8080
- 2. At the login screen enter: admin
- 3. Enter the following Password: admin This brings up the initial Liferay portal window.
- 4. To add more portlets, click on the "*Add Content*" link in the upper-right-hand corner. This brings up a panel of portlets along the left-hand margin:
 - Expand the *ICEcore* section to add more Teaming features, such as the *ICEcore Administration* portlet.
 - Expand the *Admin* section to add useful Liferay features such as the *Admin* and *Enterprise Admin* portlets.

The portlets are placed in the narrow column on the left side. To move a portlet to the wider right column, mouse down on the title and drag it over the right-hand column and release when you see a blue bar with arrows on each side appear.

2.4 Adding Users

There are two methods of managing users:

- 1. Basic User Management create and manage individual accounts manually
- 2. LDAP/eDirectory synchronize user account management to a corporate directory

Regardless of which method you choose it is important to realize that because Teaming is embedded within Liferay, a portion of user management is delegated to the Liferay. For example, Liferay is responsible for all user authentications.

The section includes the following topics:

- Section 2.4.1, "Basic User Management," on page 24
- Section 2.4.2, "User Management with LDAP/eDirectory," on page 25
- Section 2.4.3, "The ICEcore LDAP Configuration Form," on page 27
- Section 2.4.4, "Secure LDAP/eDirectory Setup," on page 29

2.4.1 Basic User Management

This capability comes "out of the box" with the product - no additional setup is required.

1 Using the Liferay *Enterprise Admin* portlet, click on the *Users* tab.

Liferay has two portlets, *Enterprise Admin* and *Admin*. Both have *Users* tabs, but they do very different things. Make sure you are using the correct portlet. This brings up a list of current Liferay accounts. You can refer to the Liferay documentation (http://www.liferay.com/web/guest/documentation) for more advanced management.

- 2 Click Add.
- **3** Fill in the following fields: *First*, *Last Name*, assign a *User ID*, specify the e-mail address, and then click *Save*.

NOTE: Do not use any forbidden characters $(/ \ ?"<>; |)$ in a user's names.

- **4** Liferay shows an extended form.
- **5** Click Save.
- **6** Click on the *Password* tab, type in the password, and then click *Save*.
- **7** Repeat these steps to add additional users.

The account is now ready for use, but not fully created. The administrator and other users cannot see the new user until after the user logs in for the first time. Once the new user logs in, Teaming creates their user workspace, including a blog, calendar, and file area.

2.4.2 User Management with LDAP/eDirectory

If you want to use a corporate directory as the master reference for user accounts you need to configure both Liferay and Teaming in a similar manner. The Teaming LDAP configuration pages are designed to look and work in a similar fashion to Liferay, easing this task significantly. You can refer to the Liferay documentation (http://www.liferay.com/web/guest/documentation) for more detailed information.


1 Using the Liferay *Enterprise Admin* portlet, click on the *Settings* tab (you may need to click on the >> tab to see the *Settings* tab).



2 Click on the *Authentication* tab.



3 Click on the *LDAP* tab.



- **4** Fill out the form with the values needed to map to your corporate directory:
 - **4a** For the search filter use uid=@screen_name@ or cn=@screen_name@, depending on your site conventions.

ſ	search filter that will be used to test the validity of a user. The tokens @company_id@, @email_address@, a @ are replaced at runtime with the correct values.					
	(cn=@screen_name@)					
L						

4b Liferay checks passwords against LDAP by either doing a comparison between the user typed password and the password stored in the LDAP server or by binding to the LDAP server using the user typed password.


This behavior is controlled by the property ldap.auth.method in the portal.properties file (bind or password-compare).

- Set this value to bind (recommended) if you do not want to worry about encryption strategies.
- When you set this value to password-compare, use the Encryption Algorithm drop-down list to specify which algorithm should be used to encrypt the user typed password before conducting password comparison (a blank value means no encryption, MD5 and SHA specify two different algorithms).



4c Under *If the user...* add: password=givenName or password=sn.

NOTE: We recommend picking one of these passwords (the Liferay default password=userPassword does not always appear to work).



4d Under *Export Settings*, we recommend deselecting the *Export Enabled* option.



5 Click Save.

2.4.3 The ICEcore LDAP Configuration Form

This form is similar to the Liferay form but includes additional information on scheduling synchronization of all users and, optionally, groups.

1 Using the ICEcore Administration portlet, click on "Configure LDAP."



- **2** Fill out the form using the corresponding values that were used to configure Liferay. (See below for details on this form).
- **3** Click *Apply*.


NOTE: Users do not show up in the user list until after they have logged in for the first time.

Connection settings:



- URL: ldap://host:port/dc=foo,dc=bar, for example: ldap:// 192.168.3.3:389/dc=sleepy,dc=com
- Principal: LDAP principal (user) to authenticate access with, for example: cn=admin,o=itdepartment
- Credentials: Above principal's password or authenticating token

Users settings:



• Ldap attribute that identifies the user, for example: uid or cn

NOTE: For the LDAP attribute that identifies the user, "cn" may be a better choice than "uid" for many sites.

- Attribute mapping This is how you map the LDAP attribute names of the user record to the Teaming internal identifiers. Syntax is: TeamingId=ldapAttName, for example:
 - ◆ lastName=sn
 - ◆ name=uid
 - ◆ TeamingIds: lastName, firstName, name, description, email, Address, phone
- Select Synchronize user profiles (recommended)
- Select Register LDAP user profiles automatically (recommended)
- Select others as appropriate

Groups settings:



- Select Register LDAP group profiles automatically (recommended)
- Select Synchronize group membership (recommended)

2.4.4 Secure LDAP/eDirectory Setup

To connect to a secure LDAP server, you need to import the server's certificate into Teaming's keystore. If the LDAP server is ldap.company.com, and it's running on the usual ldaps port (636), then you can follow these steps using the command line interface:

NOTE: An administrator who understands the "openssl" tool should perform this procedure.

- 1 Make sure you have openssl available.
- 2 Type: openss1 s client -connect ldap.company.com:636
- **3** Copy everything from the '---BEGIN CERTIFICATE---' to the '---END CERTIFICATE---' lines (inclusive) into a file, say cert.ldap (the name does not matter).
- **4** Type:

keytool -import -alias ldap.company.com -keystore /sitescape-team-0.1.0/liferay-portal-tomcat-5.5-jdk5-4.3.0/conf/.keystore -file cert.ldap

NOTE: The path to the keystore depends on your install path.

5 Restart Tomcat.

NOTE: This technique only works for real certificates. If the LDAP server is using a self-signed certificate, you also need to get the certificate for the "fake" CA and add it to the cacerts file on the Teaming machine. The code at http://blogs.sun.com/andreas/entry/no_more_unable_to_find to get the other certificate appears to be a good example.

6 Make sure you use ldaps://ldap.company.com:636 as the LDAP URL, rather than the default ldap://ldap.company.com:389 (note protocol and port number changes).

2.5 Mail Setup

Teaming e-mail integration is divided into two primary functions:

- 1. Notification e-mail messages generated by Teaming to inform people of events (e.g., new entries, changes) occurring within Teaming.
- 2. Posting the processing of e-mail messages sent to Teaming with the intent of having the e-mail content added to a particular folder (as a new entry or reply).

System Configuration

As part of installing and configuring Teaming, the system administrator must supply information related to the address and access to the mail system. E-mail integration is not required and you can configure the level of integration.

The installer.xml file contains sections on e-mail configuration for both notification (Outbound) and posting (Inbound).

Outbound configuration requires the basic information for generating SMTP mail messages: server, port, and optional authentication information.

Teaming posting works by the system accessing a single e-mail account (sometimes referred to as the "posting account"). Using your e-mail system, multiple e-mail addresses (aliases) can be mapped to this account. Teaming periodically reads e-mail sent to this account and forwards the messages to individual folders (more on this below).

Create the account using your normal e-mail system management tools. You can configure the posting account to use either POP3 or IMAP. Teaming needs a host, port, e-mail account id, and password for the posting feature to work.

Setting up Incoming Mail schedule

In the *ICEcore Administration* portlet, click on the *Configure site incoming email schedule* link. This brings up a form that instructs Teaming when to check the posting e-mail account. You may choose to poll at specific times during the day or at some regular frequency.

The right-hand side of the setup page lists any aliases and the folder that is using that alias. You set up the alias address to folder mapping within the folders themselves (see next section).

Associating an E-mail Address with a Folder

If you enable incoming e-mail the final step that you need to take is to associate a particular e-mail alias address with a folder. When this is done, e-mail sent to that address is "read" by the folder and turned into entries (or replies).

- 1. Navigate to the folder you want to receive e-mail and click on the *Manage this folder* menu item, then select *Email settings*.
- 2. Enter the e-mail alias address you want to associate with this folder. Click on the *Apply* button to save the address.

You can optionally set up the notification schedule for this folder at the same time (see next section).

Establishing a Notification Schedule for a Folder

You can configure each folder to send out e-mail messages highlighting activity within the folder.

- 1. Navigate to the folder you want to send e-mail for and click on the *Manage this folder* menu item, then select *Email settings*.
- 2. Enable outgoing mail and select the type of schedule you want for notification. You can configure the schedule for specific times of the day or a regular frequency. You also need to specify who is to receive the e-mail. This can be a combination of users, groups, and arbitrary e-mail addresses.
- 3. Click *Apply* to save the schedule.

2.6 Adjust Access Control for the Site

One of your first tasks as a site manager is to set the access roles to control how different users can view and participate in the site workspaces according to what access role they are assigned. All Access Roles are assigned to users in individual workspaces or folders, except for the Site Administration access role, which grants access to the whole site. There are specific Role Definitions that you can edit to accomplish this. See the default Role Definitions below.

Key Ideas to Keep in Mind:

- Understand the default access control settings and the philosophy behind them (quick team formation, open communications, etc.)
- Determine the values and needs of your organization and adjust the access control settings accordingly
- The best way to delegate administrative tasks is to create groups and use the access-control tools to delegate folder and workspace administration accordingly

2.6.1 Default Role Definitions

The following are the default Role Definitions, which should more than enough to configure your site, though your site administrator can add new Role Definitions if required.

Workspace and Folder Administrator

Assigns every access right, but *Site Administration*, to users for the specific workspaces and folders that the administer.

• Participant

Assigns the following default access rights to users for any workspaces or folders in which they are participants:

- Add Comments
- Create Entries
- Delete His or Her Own Entries
- Modify His or Her Own Entries
- Read Entries
- Site Administrator

Has every access right selected by default. These rights apply to every workspace and folder.

• Team Member

Assigns the following default access rights to users for any workspaces or folders in which they are team members:

- Add Comments
- Add Folders
- Add Workspaces
- Create Entries
- Delete Entries
- Delete His or Her Own Entries
- Generate Reports
- Manage Community Tags
- Modify Entries
- Modify His or Her Own Entries
- Read Entries

• Visitor

Assigns the following default access rights to users for workspaces or folders to which they are only assigned as visitors:


- Add Comments
- Read Entries
- Workspace Creator

This Role Definition is a special definition assigned to All Users at the Top Team Workspace to give every user the right to create a new Team Workspace. The Site Administrator can edit the Top Team Workspace access rights so that only specific users can add Team Workspaces, see Section 2.6.3, "Edit Default Team Workspace Access Rights," on page 34.

2.6.2 To Change a Default Role Definition:

For example, you may choose to prevent visitors from adding comments in the site.

1 In the *ICEcore Administration* portlet, click *Configure Role Definitions*.



The Configure Roles page appears.



2 Click Visitor.



3 Under *Visitor*, deselect the *Add Comments* option, and then click *Apply*.

▼ Visitor
✓ Add comments
Add folders
Add workspaces
Change access control
Create entries
Delete entries
Delete his or her own entries
Design entries
Design workflows
Generate reports
Manage community tags
Modify entries
Modify his or her own entries
Modify, move, delete or re-index folders and workspaces
✓ Read entries
Site administration
Apply

4 Click *Close* to return to your Home Page.

Visitors to your site can now view entries, but can no longer add comments.

2.6.3 Edit Default Team Workspace Access Rights

Every workspace and folder has their own access rights. Access rights are the assignment of the Role Definitions to groups and individuals for a workspace or folder. When you create a new workspace, it starts off with the default access rights according to the type of workspace you created: Global, Personal, or Team.


NOTE: A personal workspace is created when a user signs into Teaming for the first time.

The Site Administrator can edit these default settings, for example, you might want to edit the Top Team Workspace access rights so that only specific users or groups can add Team Workspaces.


First you want to create a *Team Creator* group to be in charge of Team Workspace creation, and then you want to remove the *Workspace Creator* Role Definition from *All Users* and assign it to the *Team Creator* group in the Top Team Workspace access rights. The site administrator can add new users to the *Team Creator* group at any time.

Create the Team Creator Group:


1 In the *ICEcore Administration* portlet, click *Manage Groups*.



2 In the *Manage Groups* window, click *Add a New Group*.



3 Enter the new group's name, title, description, and then click *Add*.




The new group appears on the page.

4 Under *Select a Group to Modify or Delete*, click the *Team Creator (Team Creator)* group.



5 Add users to the group and click *Apply*.



6 Click Close.


NOTE: See the Online Help or Teaming User Guide for details on adding users to groups.

Grant the Team Creator Group Sole Team Workspace Creation Rights:

1 Click Team Workspace.



2 Select the *Manage* > *Access Control* menu item.



The *Configure Access Control* page appears. This page allows you to assign the Role Definitions to specific groups and users from the workspaces and folders. The current page controls the access rights for the Top Team Workspace area.

3 Click *Add a Group* in the *Access Rights* table.



4 Start typing Team Creator in the *Add a Group* dialog that appears and select *Team Creator* from the drop-down list that appears.



The Team Creator groups appears in the Access Rights table.

5 Deselect the *Workspace Creator* option for the *All Users* group and select the same right for the *Team Creator* group.



6 Click Save Changes.



7 Click Close.

You have now created a specific group to control the creation of Team Workspaces. This is an example of how you use Role Definitions and access rights to configure your site. You want to map out the access issues for your site so you can edit the default Role Definitions and default access rights for your workspaces prior to granting all your users access to the site.

2.7 Create Your Initial Workspaces

There are three types of workspaces in Teaming: Global Workspaces (company wide), Personal Workspaces (individual), and Team Workspaces (smaller teams). Once a new workspace is created, every sub-workspace and sub-folder inherits its access rights from the parent workspace by default. The workspace or folder administrator can de-select this option for any individual sub-workspace and sub-folder (on the *Access Control* page for the individual workspace or folder).

Planning the initial content for your site is an important step in regards to how your users learn and use the site. Without some content, users are lost. However, too much content (especially empty containers and a complex structure) might cause users to have trouble mapping to the real work they have to do. So, before letting end users into the installation, the Global Workspace should have enough content to engage them, but not so much as to overwhelm them. Also, we have seen time and again that a workspace hierarchy and set of dedicated applications are best developed in parallel with users using the product and providing feedback about what best serves their needs.

The best approach is to plan out a tight minimal set of content in the Global Workspace to provide the end users with a functional site that they can quickly navigate and start using.

Creating Teams

The team creation process can be simplified with some up front planning:

- Although, by default, anyone can create a team (unless you edit the default access rights, see Section 2.6.3, "Edit Default Team Workspace Access Rights," on page 34) the process is a lot easier if a site administrator creates group names for teams before team creation occurs.
- Thinking through how you want to architect group names is a useful up front task.
- Access control is greatly simplified and enhanced by utilizing well-planned group names for your site.

2.7.1 Create an Administration Team Workspace

NOTE: You should create an *Administration* group first to simplify the process for editing your administration access rights. You can then add this group to the administration team and set the access rights to this group. In the future, you can add or delete users from this administration group and not worry about editing the administration team's access rights for individual members since they are assigned correctly to the group. Assume the admin group now exists.


1 From your Home Page, click *Team Workspaces*.



2 Click Add a Team Workspace.



3 Type in a *Workspace Title* for the new workspace.



4 Select the team members (add the admin group, which we will also use for setting access rights so that you only have to control membership to this group to control administrative access rights and administration workspace membership).



NOTE: See the Online Help or the Teaming User Guide for details on selecting users.


5 Select all the initial *Workspace Folders* you want to create in this workspace.

Standard templates	
Discussion	A Discussion folder is useful for creating a forum where users are likely to both create and reply to entries.
☑ Blog	A blog folder is a forum where entire entries are displayed in reverse chronological order, based on when they were created. Blogs typically provide information on a particular topic from an individual or small group of authors. Optionally, the blog folder can be configured so that a larger group can make comments on the entries posted by the original author.
✓ Calendar	A calendar folder is a place to post group events or display other types of entries by date.
Guestbook	A guestbook folder is a simple place that individuals can "sign," indicating that they have visited a user's Personal Workspace. Visitors may also leave comments about the entries created in that personal workspace. Comments are displayed in reverse chronological order. A picture of the individual signing the guestbook is displayed with the comment. The guestbook is useful for expanding users' social networks.
File folder	A file folder is a place to put files. Comments or entire discussions can be posted about individual files. Additionally, the files can be automatically locked, edited-in-place, then unlocked, creating a new version of the file. A file folder can emulate a WebDAV server. This allows a user to add and delete files via any WebDAV client, such as the MS Windows File Manager.
Milestone folder	A milestone folder is used to roll up or summarize activity in one or more Task folders.
Photo album	A photo album allows the user to add and view thumbnails of files in a graphical format such as .JPG and .PNG.
Survey folder	A survey folder can hold a series of surveys. Each survey is made up of a series of questions. The results of the survey are summarized and can be viewed within the folder.
▼ Task folder	A task folder contains a series of task entries. The folder also displays a summary of task priority and status.
✓ Wiki	A wiki is a collaborative folder containing linked web pages that can be edited by anyone with appropriate access. It is useful for creating and making available information created by a group of authors.

6 Click OK.

2.7.2 Set the Administration Team Access Rights


1 From the *ICEcore Administration Team* workspace, select the *Manage > Access Control* menu item.



2 In the Access Rights table, click *Add a Group*.



3 Start typing in admin, and select *admin* from the drop-down list that appears.



4 For the *admin* group, select the *Workspace and Folder Administrator*, *Participant*, and *Team Member* roles.



- **5** Click Save Changes.
- 6 Click Close.

2.7.3 Using the Root Team Workspace

You can set any workspace to be a "root" team workspace, which allows anyone with the correct access rights to add workspaces under the "root" workspace. A "root" team workspace has the *Add a team workspace* button available to anyone with the appropriate access rights.


An administrator can set a workspace to be a "root" team workspace temporarily, while the sub-workspaces your company needs to set up are added, or permanently so that users can create additional workspaces under the "root" team workspace on a continuous bases. How you configure a specific area depends on what the workspaces are used for how much control you want the users to have over the layout of the site.

Configuring a Workspace to be a Root Team Workspace:

1 From the *ICEcore Administration Team* workspace, select the *Manage* > *Configure* menu item.



2 Select the *Team workspace root* option and click *Apply*.



NOTE: When choosing for a workspace, you can select the default "Workspace" definition. If you want to track project tasks and milestones based on task completion, you can select the

"Project management workspace" definition. Finally, when choosing for a team workspace, select "Team workspace root" for workspaces that you want to display the *Add a team workspace* button. If your team workspace is organizational in nature and not intended to have team workspaces as its subworkspaces, select the "Team workspace" definition (which omits the button for team creation).

3 Click Close.

The Add a team workspace button is now available in the *ICEcore Administration Team* workspace.



NOTE: Since only members (administrators) of the admin group have access to this workspace, you can make it a permanent Team workspace root, so any administrator can create sub-workspaces under this one.

2.8 Invite Users to the Site


Most end users require some minimal guidance before entering the site. They need to be invited (there is no automatic way to do this, unless you invite them during team creation (Teaming is designed to be team-centric). The invitation should contain the URL to the site. Also, you may want to include the Teaming Quick Start Guide and Teaming User Guide in the e-mail invitation.

Your organization may want to run some training sessions before having people enter the site. As another option, the administrators may want to customize the getting-started information available on the static web page off the *Welcome* portlet.

2.9 Set Up E-mail for a Workspace

To set up notifications in a workspace, enable them on one of the top level folders in your workspace first. Once this is done, e-mail notifications are enabled on all sub-folders. For postings, you need to configure the workspace with a valid e-mail alias. See your e-mail administrator to get a valid e-mail alias address for your workspace.

1 From your workspace, select the top level folder for which you want to enable e-mail.




2 Select the *Manage* > *Email Settings* menu item.



3 Type in the e-mail alias you received from your e-mail administrator in the *Receiving Email From* field.

This enables the folder to receive e-mail posts.

4 Configure the e-mail *Notification Schedule* and add the users, groups, and any individual e-mail addresses you want to receive e-mail notifications, and then click *Apply*.



NOTE: See the Online Help and the Teaming User Guide for more details.

2.10 Mirrored Folders Configuration

NOTE: Mirrored Folders are available in the Enterprise Edition only.

A mirrored folder is an Teaming folder that uses a server file system directory as its file storage area instead of the normal Teaming repository. Typically the directory is a "file share", accessed via normal file sharing mechanisms. Teaming attempts to keep its knowledge about the folder contents in sync with whatever is in the directory.

Because of the way mirrored folders are configured they are intended to be used to bring common, relatively static, file shares into the Teaming environment -- they are not appropriate for individual file shares. Teaming can then be used to add additional metadata around these files, including Teaming-specific access controls.

The server directories that are to be made available to Teaming must be specified in the server configuration files. The <code>installer.xml</code> has a section devoted to specifying mirrored folder resource drivers. These drivers then make the files in the specified directory available to the Teaming folder(s). It is important to note that access to the directories is done by the Teaming process, and the user id that Teaming is running as acts as a proxy for all Teaming users.

To Create a Mirrored Folder:

1 Add a "MirroredFolder" section to the installer.xml file. This creates a Mirrored Folder Resource Driver. (You may want to use one of the disabled samples as a template.)

Remember to set the "enabled" attribute to "true" and specify a unique id and title, the path to the directory to share, and the users and/or groups that can utilize this resource. To prevent accidental modifications to the file share, set the "readonly" attribute to "true".

After updating your installer.xml file, you need to run the Teaming installer with the "Apply settings" option, and then restart Teaming to create the resource drivers.

- **2** Log into Teaming as one of the users you specified in the mirrored folder resource driver (or as a member of one of the specified groups).
- **3** In Teaming create a folder of type *File folder*.
- **4** Within the folder, select the *Manage* > *Modify this folder* menu item.
- **5** Select the *Mirror external folders* option.
- **6** Select the mirrored folder resource driver that you created in step 1.
- **7** Optionally, you can specify a subdirectory within the resource driver's root directory structure that you want this folder to mirror.
- **8** Click *OK* to make the folder a mirrored folder.

NOTE: Once you make a folder a mirrored folder, it can not be reverted back to a regular folder, and the information you provided (i.e., resource driver name and path) can not be subsequently changed.

9 Perform initial synchronization/loading by selecting the *Manage this folder > Synchronize* menu item from the folder listing.

NOTE: For the current release of Teaming only synchronous/manual synchronization is supported.

The sample-installer.xml File



The sample-installer.xml file is shown below:

```
-->
<!--
                                                              -->
              ICEcore Installation Configuration File
<!--
                                                              -->
<ICEcoreConfig version="4">
      <Environment>
          <!-- The path to JAVA HOME -->
             <JDK JAVA HOME="" type="Sun" />
             <!-- What userid to run as (Linux-only)
             <!-- Also what userId and groupId to use as
                                                            -->
             <!-- owners of the data directories.
             <Ids userId="" groupId=""/>
      </Environment>
    <!--
                                                                  -->
    <!--
                          Network Settings
                                                                  -->
    <!--
    <!-- The host name or IP address of the server must be
                                                                  -->
    <!-- specified here. The default, localhost, is only
    <!-- appropriate for test configurations with no remote
                                                                  -->
    <!-- access.
                                                                  -->
    <!--
                                                                  -->
    <!-- If you have a dedicated server, setting the port
    <!-- to "80" and/or securePort to "443" will avoid having
                                                                  -->
    <!-- to specify a port number in browser URLs.
                                                                  -->
    <!--
                                                                  -->
    <!-- NOTE: On Linux/UNIX based systems, it's very dangerous
                                                                  -->
   <!-- to run this server on any port number less than 1024,
                                                                  -->
   <!-- since that would require the web server to run as the
                                                                  -->
    <!-- root user. If you must run on a port lower than 1024,
    <!-- please see the ICEcore documentation referring to port
                                                                  -->
    <!-- forwarding via iptables.
                                                                  -->
    <!--
                                                                  -->
    <!--
                                                                  -->
    <!-- A default certificate is supplied for SSL connections.
                                                                  -->
   <!-- You should replace this with your certificate.
                                                                  -->
    <!-- This can be placed in the conf/.keystore file or
                                                                  -->
    <!-- change the keystoreFile attribute to point to the
                                                                  -->
    <!-- certificate.
                                                                  -->
```

```
<Network>
   <Host name="localhost"</pre>
         port="8080"
         securePort="8443"
         shutdownPort="8005"
         ajpPort="8009"
          keystoreFile=""
    <WebServices enable="true" />
</Network>
<!--
                                                               -->
<!--
                                                               -->
                 Memory (RAM) Settings
<!--
<!-- ICEcore requires a minimum of 512m to operate.
                                                               -->
<!-- lg is recommended for basic production.
                                                               -->
                                                               -->
<!-- Generally do not allocate more than 75% of available
<!-- physical memory.
                                                               -->
<!--
                                                               -->
<!-- Specify amounts as Nm for N megabytes (e.g., 1500m) or -->
<!-- Ng for N gigabytes (e.g., 3g)
                                                               -->
<!--
                                                               -->
<Memory>
    <JavaVirtualMachine mx="1q" />
</Memory>
<!--
                                                               -->
<!--
                 File System Configuration
                                                               -->
<!--
                                                               -->
                                                               -->
<!-- Modify the configName to your desired configuration
<!-- in the FileSystem element below. You must set the
                                                              -->
<!-- configName to the exact configuration in the file:
                                                              -->
<!-- basic - Simple one-directory setup
                                                              -->
        advanced - Advanced multiple-directory setup
<!--
<!--
                                                               -->
<!-- WARNING! Changing a directory path does NOT relocate
                                                               -->
                                                               -->
<!-- data after the product has been installed. You must
<!-- coordinate any changes here with appropriate file system -->
<!-- modifications (including directory protections and
                                                               -->
                                                               -->
<!-- ownership where applicable).
<!--
                                                               -->
<FileSystem configName="basic">
 <!-- The basic configuration only requires that you -->
 <!-- specify a root directory for the data and -->
 <!-- we'll take care of the rest.
                                                       -->
  <Config id="basic">
   <RootDirectory path="/home/icecoredata" />
  </Config>
```

```
<!-- The advanced configuration requires that you
                                                      -->
  <!-- specify individual directory locations.
                                                      -->
  <!-- Add path attributes for those directories you
                                                      -->
  <!-- want to locate elsewhere.
  <Config id="advanced">
    <RootDirectory path="/home/icecoredata" />
    <FileRepositories />
    <ArchiveStore />
   <CacheStore />
    <LuceneIndex
  </Config>
  <!-- The liferay data dirs configuration allows you to
  <!-- change the directories that liferay uses for
                                                            -->
  <!-- it's internal data directories. If you want to
                                                            -->
  <!-- change these, change the use attribute from "default" -->
  <!-- to "custom". NOTE: If you change these after you have -->
  <!-- already started using liferay, you'll need to copy -->
  <!-- all the data from the default dirs to the new dirs
                                                            -->
  <!-- BEFORE you restart the server!
                                                            -->
  <LiferayDataDirs use="default">
    <RootDirectory path="/home/icecoredata/liferay" />
    <DocumentLibraryRoot dir="documentlibrary/root" />
    <DocumentVersionLibrary dir="documentlibrary/vroot" />
    <JackRabbit dir="jackrabbit" />
    <AutoDeploy dir="deploy" />
    <Lucene dir="lucene" />
  </LiferayDataDirs>
</FileSystem>
<!--
                                                              -->
<!--
                                                              -->
                 Database Configuration
                                                               -->
<!--
<!-- Modify the configName to your desired configuration
                                                              -->
<!-- in the Datatabase element below. You must set the
                                                              -->
                                                              -->
<!-- configName to the exact configuration in the file:
<!--
      MySQL_Default - For MySQL
                                                              -->
<!--
        SQLServer Default - For Microsoft SQL Server
                                                              -->
<!--
                                                              -->
<!-- Change the Resources for the configuration you chose
                                                               -->
<!-- (the defaults are pretty good for a simple configuration
                                                              -->
<!-- with the database running locally, but you'll probably
                                                               -->
                                                               -->
<!-- have different passwords!).
<Database configName="MySQL Default">
    <!--
                                                               -->
    <!--
                         MySQL_Default
                                                               -->
    <!--
                                                               -->
```

```
<Config id="MySQL Default" type="MySql">
           <Resource for="liferay"
               driverClassName="com.mysql.jdbc.Driver"
               url="jdbc:mysql://localhost:3306/
lportal?useUnicode=true&characterEncoding=UTF-8"
               username="root"
               password="root"
            />
           <Resource for="jboss"</pre>
               driverClassName="com.mysql.jdbc.Driver"
               url="jdbc:mysql://localhost:3306/
jbossportal?useUnicode=true&characterEncoding=UTF-8"
               username="root"
               password="root"
           />
           <Resource for="icecore"
               driverClassName="com.mysql.jdbc.Driver"
               url="jdbc:mysql://localhost:3306/
sitescape?useUnicode=true&characterEncoding=UTF-8"
               username="root"
               password="root"
           />
       </Config>
       <!--
                                                                   -->
        <!--
                                                                   -->
                         SQLServer Default
        <!--
       <Config id="SQLServer_Default" type="SQLServer">
           <Resource for="liferay"
               driverClassName="net.sourceforge.jtds.jdbc.Driver"
               url="jdbc:jtds:sqlserver://localhost/
lportal; SelectMethod=cursor"
               username="sa"
               password="sa"
            />
           <Resource for="jboss"
                driverClassName="net.sourceforge.jtds.jdbc.Driver"
               url="jdbc:jtds:sqlserver://localhost/
jbossportal; SelectMethod=cursor"
               username="sa"
               password="sa"
           <Resource for="icecore"
               driverClassName="net.sourceforge.jtds.jdbc.Driver"
               url="jdbc:jtds:sqlserver://localhost/
sitescape; SelectMethod=cursor"
               username="sa"
               password="sa"
            />
        </Config>
```

```
<!--
                                                               -->
    <!--
                         Oracle Default
                                                               -->
    <!--
                                                               -->
    <Config id="Oracle Default" type="Oracle">
       <Resource for="liferay"</pre>
            driverClassName="oracle.jdbc.driver.OracleDriver"
            url="jdbc:oracle:thin:@//localhost:1521/orcl"
            username="lportal"
            password="pw"
         />
        <Resource for="icecore"
            driverClassName="oracle.jdbc.driver.OracleDriver"
            url="jdbc:oracle:thin:@//localhost:1521/orcl"
            username="sitescape"
            password="pw"
         />
    </Config>
</Database>
<!--
                                                               -->
<!--
                                                               -->
                  Lucene Configuration Settings
<!--
                                                               -->
<!--
                                                               -->
       The Lucene index can be run "local" (within
<!--
                                                               -->
<!--
       the context of this application) or "server"
                                                               -->
<!--
       (run as it's own server). Additionally it
                                                               -->
<!--
       can be run as it's own server on this system
                                                               -->
<!--
                                                               -->
       or on a remote system.
                                                               -->
<!--
                                                               -->
<!--
       Note: The rmi port need only be set if running
<!--
       in server mode. (And then, only if the default
                                                               -->
<!--
         port cannot be used.
                                                              -->
<Lucene luceneLocation="local">
    <Resource
        lucene.index.hostname="localhost"
                lucene.flush.threshhold="100"
                lucene.max.booleans="10000"
                lucene.max.merge.docs="1000"
                lucene.merge.factor="10"
                lucene.rmi.port="1099"
    />
</Lucene>
```

```
< ! --
                                                               -->
<!--
                  RSS Configuration Settings
                                                               -->
<!--
                                                               -->
<!-- RSS feeds are inherently insecure as they do not
<!-- use the standard authentication mechanism. If you
                                                               -->
<!-- do not want to have users create RSS subscriptions
                                                               -->
<!-- set the enable property to "false"
                                                                -->
<!--
                                                                -->
<!-- If you have RSS feeds enabled you can tune the maximum
                                                               -->
<!-- number of days to keep in the feed and the the maximum
                                                                -->
<!-- number of days to keep updating a feed when there are
                                                                -->
                                                                -->
<!-- no clients reading it.
<!--
                                                                -->
  <RSS enable="true">
         <Feed max.elapseddays="31" max.inactivedays="7" />
  </RSS>
<!--
                                                                -->
<!--
                  Email Configuration Settings
                                                                -->
<!--
                                                                -->
<!-- Edit the Outbound and Inbound settings as required.
                                                                -->
< ! --
                                                                -->
<!--
                                                                -->
                                                                -->
<!-- For inbound mail (postings) you need to specify either
<!-- pop3 or imap (or pop3s/imaps for SSL connections to
<!-- mail servers), and fill out the settings for which one
                                                               -->
<!-- you choose. These settings are not used until you
                                                               -->
                                                                -->
<!-- enable incoming email within the product. If you do
<!-- not plan on using inbound email, you can ignore these
                                                                -->
<!-- settings.
                                                                -->
<!--
                                                                -->
<!--
                                                                -->
<EmailSettings>
    <Outbound>
        <Resource
           mail.transport.protocol="smtp"
            mail.smtp.host="mailhost.yourcompany.com"
            mail.smtp.user="icecore@yourcompany.com"
           mail.smtp.password=""
            mail.smtp.auth="false"
            mail.smtp.port="25"
            mail.smtps.host="mailhost.yourcompany.com"
            mail.smtps.user="icecore@yourcompany.com"
            mail.smtps.password=""
            mail.smtps.auth="false"
            mail.smtps.port="465"
        />
     </Outbound>
```

```
<Inbound>
        <Resource
            mail.store.protocol="pop3"
            mail.pop3.host="localhost"
            mail.pop3.auth="true"
            mail.pop3.user="popEmailUserId"
            mail.pop3.password="passwordHere"
            mail.pop3.port="110"
            mail.pop3s.host="localhost"
            mail.pop3s.auth="true"
            mail.pop3s.user="popEmailUserId"
            mail.pop3s.password="passwordHere"
            mail.pop3s.port="995"
            mail.imap.host="localhost"
            mail.imap.auth="true"
            mail.imap.user="imapEmailUserId"
            mail.imap.password="passwordHere"
            mail.imap.port="143"
            mail.imaps.host="localhost"
            mail.imaps.auth="true"
            mail.imaps.user="imapEmailUserId"
            mail.imaps.password="passwordHere"
            mail.imaps.port="993"
            mail.transport.protocol="smtp"
            mail.smtp.host="localhost"
            mail.smtp.auth="false"
            mail.smtp.user="icecore@yourcompany.com"
            mail.smtp.password=""
            mail.smtp.port="25"
            mail.smtps.host="localhost"
            mail.smtps.auth="false"
            mail.smtps.user="icecore@yourcompany.com"
            mail.smtps.password=""
            mail.smtps.port="465"
        />
   </Inbound>
</EmailSettings>
```

```
< ! --
                                                                   -->
   <!--
                     Presence Configuration Settings
                                                                   -->
   <!--
                                                                   -->
   < ! --
   <!-- Use thse settings to link your Teaming and Zon
                                                                   -->
   <!-- servers together. Leave the presence.service.enable
                                                                   -->
   <!-- setting at at false if you do not use the conferencing
                                                                   -->
   <!-- realtime (Zon) software.
                                                                   -->
   <!--
                                                                   -->
   <!-- The values to fill in this section are obtained when
                                                                   -->
   <!-- Zon has been installed and configured. If you don't
                                                                   -->
   <!-- know them now, you can update this configuration later
                                                                   -->
   <!-- and apply the settings.
                                                                   -->
   <!--
                                                                   -->
   <!-- The jabber.server is IP or host of the Zon XML Router
                                                                   -->
   <!--
                                                                   -->
   <!-- The default Zon admin.id is admin, and default password
                                                                   -->
                                                                   -->
   <!-- is also admin. Change the admin.passwd to match the
   <!-- Zon administrator password you have set.
                                                                   -->
   <!--
                                                                   -->
   <!-- The jabber.domain is the host name of the XML router
                                                                   -->
   <!--
                                                                   -->
   <!-- The community.id is the name of the community you
                                                                   -->
   <!-- created with the Zon console.
                                                                   -->
                                                                   -->
   <!--
   <!-- Change the hostname part of the zon.url to the ip or
   <!-- host of the Zon Web Portal (don't change the port or
                                                                   -->
   <!-- the rest the URL).
                                                                   -->
   <!--
                                                                   -->
   <Presence>
       <Resource
           presence.service.enable="false"
           presence.service.jabber.server="zon-server.yourcompany.com"
           presence.broker.admin.id="admin"
           presence.broker.admin.passwd="admin"
           presence.broker.jabber.domain="newzon"
           presence.broker.default.community.id="yourcommunity"
           presence.broker.zon.url="http://zon-server.yourcompany.com:8000/
imidio_api/"
        />
   </Presence>
```

```
<!--
                Mirrored Folders Configuration Settings
                                                                   -->
    <!--
                                                                   -->
    <!-- Mirrored folders are local/shared directories that
                                                                   -->
    <!-- are exposed within ICEcore. The directories must be
                                                                   -->
    <!-- configured here first before they are available to
                                                                   -->
    <!-- the folder configuration interface within ICEcore (see
                                                                   -->
   <!-- Modify a Folder).
                                                                   -->
   <!--
                                                                    -->
   <!-- For security reasons the set of people who can map
                                                                   -->
    <!-- ICEcore folders to these shared directories is limited
                                                                    -->
   <!-- Specify the specific ICEcore users or groups that are
                                                                   -->
    <!-- allowed to map each folder.
                                                                   -->
    <!--
                                                                   -->
    <!-- Each mirrored folder configuration must have a unique
                                                                   -->
   <!-- id (use a-z,0-9), and a title to be used in the user
                                                                   -->
   <!-- interface. Set enabled to true to make the mirrored
                                                                   -->
    <!-- folder configuration active. The examples below show
                                                                   -->
   <!-- how to set up both file system and Sharepoint mirrors.
                                                                   -->
   <!--
                                                                   -->
   <!-- By default the mirrored folder is set to readonly.
                                                                   -->
    <!-- This means that ICEcore users can access the files, but -->
   <!-- cannot modify them. Set the readonly attribute to false -->
   <!-- to allow read/write access to the folder (based on both -->
    <!-- this server's access to the directory and the ICEcore
                                                                    -->
    <!-- user's access).
                                                                    -->
    <!--
                                                                   -->
      <MirroredFolders>
             <MirroredFolder enabled="false" type="file"</pre>
                             id="fs1" title="Shared Files 1"
                             rootPath="k:/somedir" readonly="true">
                    <AllowedUsers idList="administrator,u1,u2,u3" />
                    <AllowedGroups idList="g1,g2,g3" />
             </MirroredFolder>
             <MirroredFolder enabled="false" type="file"</pre>
                             id="fs2" title="Shared Files 2"
                             rootPath="/sharedFiles/someDirectory"
readonly="true">
                    <AllowedUsers idList="administrator,u1,u2,u3" />
                    <AllowedGroups idList="g1,g2,g3" />
             </MirroredFolder>
             <MirroredFolder enabled="false" type="sharepoint"</pre>
                             id="sp1" title="Sharepoint 1"
                             rootPath="/Shared Documents/cool-dir"
readonly="true">
                 <WebDAVContext hostUrl="http://hostname" user="accessId"</pre>
password="pass" />
                    <AllowedUsers idList="administrator,u1,u2,u3" />
                    <AllowedGroups idList="g1,g2,g3" />
             </MirroredFolder>
```

```
<!--
                                                                  -->
   <!--
                       iChain Single Sign-On Support
                                                                  -->
   <!--
                                                                  -->
   <!--
   <!-- To use iChain SSO, set the enable attribute to true.
                                                                  -->
   <!-- Set the Logoff URL to the address used to trigger an
                                                                  -->
   <!-- iChain logoff. Also set the ip address of the iChain
                                                                  -->
   <!-- proxy server. Only transactions from that address and \longrightarrow
   <!-- localhost will be allowed.
                                                                  -->
                                                                  -->
   <!--
   <SSO>
       <iChain type="1" enable="false">
           <Logoff url="http://something" />
           <Proxy ipaddr="ipaddr" />
       </iChain>
   </sso>
   <!--
                                                                  -->
   <!--
                       Custom Configuration Settings
                                                                  -->
   <!--
                                                                  -->
   <!-- Custom properties set here will be placed in the
                                                                  -->
                                                                  -->
   <!-- ssf-ext.properties file.
   <!--
                                                                  -->
   <CustomProperties>
       <Resource
       />
   </CustomProperties>
</ICEcoreConfig>
```

Teaming Glossary

Items that include an "(a)" are more relevant for Teaming site administrators.

access control

The tool that determines who has the right to perform which tasks in which places. See also role-based access control.

accessibility mode

An optimized user interface that facilitates use by assistive devices, such as readers.

accessory

A section located at the top of a workspace or folder page that provides a summary view, most likely of the information contained within the item. For example, an accessory can show all of the entries within a folder authored by someone designated as a subject-matter expert.

advanced search

Extra search tools that allow you to specify more specific criteria (such as the author of an item or restricting the search to a portion of the workspace tree).

alias

See e-mail alias.

attachment

A file attached to an entry.

author

The person who created an entry.

blog

A folder contain a chronological listing of journal entries.

blog archive

A feature of blog folders that allow you to see entries authored in a specific month.

buddy list

A list of people whose presence you want to check and whom you contact frequently.

calendar

A folder containing entries for scheduled appointments.

clipboard

A tool that gathers people's names. Later, when using a tool that requires names, you can take them from your clipboard.

comment

A reply to an entry.

community tag

A keyword tag applied to an item by the owner of a workspace or folder. Other users of the workspace or folder can perform searches based on community tags.

configuration (a)

A set of tools that alter the way item content is presented. There are many types of configuration, ranging from setting allowable views for an item, selecting a color scheme, creating custom entries, and creating workflow processes.

default view

The configuration of the information you see when you first view a workspace or folder. Some items may be configured to allow alternate views, which you can select.

definition (a)

A set of elements for both the form and view of a workspace, folder, or entry.

designer (a)

A tool used to create definitions or workflow processes.

discussion

A folder whose entries are discussion topics and comments about those topics.

e-mail alias

An alternative e-mail address for an e-mail account. To enable e-mail posting into a folder, you must provide an e-mail alias for the one account used to post into all folders in your Teaming installation. Consult with your Teaming site administrator for further assistance; site administrators, consult with the IT person responsible for creating e-mail accounts to create new aliases.

e-mail notification

An e-mail message that Teaming sends indicating new or changed entries in a folder (and subfolders).

entry

An item in a folder.

favorites panel

A tool used to save links to workspaces and folders most important to you, providing a method of accessing these places quickly.

file folder

A folder whose entries are configured to highlight an attached file and to facilitate file management.

filter

A setting that limits a folder listing to only the entries that match the filter's search criteria. For example, you can create a filter that shows only the contents of a folder authored by you or that were created past a certain date.

folder

A container for entries and other folders. Each folder has a type, such as blog, wiki, or calendar, that determines its appearance and features.

form (a)

An HTML form used to create a workspace, folder, or entry.

global workspace

workspace that, by default, allows everyone to participate.

guestbook

A folder or accessory whose entries indicate who has visited the place.

help mode

A dimmed page and information icons ("i"). When you click on an information icon, Teaming presents a panel of information about that section of the page.

inherit (a)

A process by which a workspace or folder automatically uses configuration settings from its parent.

instant message (IM)

A quick communication between teammates using the Zon messaging software.

Liferay (a)

The portal software within which Teaming runs by default.

meeting

An online communication by teammates using the Zon messaging software. Zon provides tools that assist with online meetings, such as people designated as running the meeting, a way for participants to "raise their hands," and a whiteboard.

milestone

A folder that, by default, summarizes the status of tasks in a task folder as they relate to meeting project milestones.

navigator

A set of tools that you can use to go anyplace within Teaming you want to go. The tools include "My workspace," "Favorites," viewing your teams, search, Help, and a workspace tree.

owner

The person who created the workspace, folder, or entry.

parallel workflow process (a)

A set of state transitions that happen at the same time as other state transitions. A state in the main thread initiates the parallel process, and a state later in the main thread can wait for the completion of the parallel thread.

parent (a)

A workspace or folder that contains another workspace or folder. The item contained within the parent is sometimes called its child.

participant

An access role that, generally, by default, allows people to author entries in a folder.

permalink

A web address (URL) for an Teaming workspace, folder, or entry that you can copy, paste, and send to a teammate so that they may access a page directly by specifying the address to their web browser.

personal tag

A keyword tag that you apply to an item, and that only you can see and use.

personal workspace

A workspace that serves as a person's homepage in Teaming, including contact information, pictures, a personal blog, and more.

photo gallery

A folder whose entries are pictures.

portal page

A web page that can run various application in sections of its page. For example, Google and Yahoo use portal pages. Sections within a portal page may display the local time, the local weather, your favorite stock quotes, and more.

portlet

A section on a portal page. Teaming runs in portlets.

presence

The state of being connected to a communications service and available for communication. Presence information is indicated by status icons (Online, Away,

project-management workspace

A workspace configured to facilitate the tracking of tasks and completion of complex project work.

role-based access control

A mechanism that controls access by assigning people and groups to roles, and the roles determine the rights assigned to those people. See the online Help for a list of Teaming default role definitions.

site administrator

The person or people who have the right to perform any task anyplace in the Teaming installation.

state

See workflow state.

subscription

A way to track new or changed items in Teaming.

tag

A keyword that anyone can apply to a workspace, folder, or entry to make it easier to find. See also personal tag and community tag.

task

A folder that, by default, contains entries that track progress with completing an assignment.

team

An access role that, by default, allows people to participate in a workspace or folder, to do some minor administrative tasks, and to communicate easily with each other.

team workspace

A workspace that restricts participation to only teammates.

template (a)

A set of default configuration settings used to create a new workspace or folder. A template includes at least one definition, access control, a possible hierarchy of defined items, and possibly more.

view

A presentation of an item's content. For example, you can view a discussion folder in either a list or table format. By default, most folders use one view (calendar folders use a calendar view, blog folders use a blog view, and so on.)

visitor

An access role that, by default, allows people to read entries and make comments on them (but not create new entries).

WebDAV

The Web Distributed Authoring and Versioning protocol. If your system provides a tool that uses this protocol, it allows you to manage Teaming file-folder entries using the WebDAV window.

wiki

A folder whose entries are authored by all participants.

workflow

An online representation of a business process (for example, document review, paid timeoff requests, document sign off, and so on). An entry can have an associated workflow process, which places the entry into various workflow states.

workflow state

A status label for an entry in a workflow process. A state determines who has the right to work with an entry (including who may see it), who needs to be notified, who needs to perform the next task, and which subsequent states are possible.

workspace

A container for folders and other workspaces.

workspace tree

A tool that allows you to navigate the hierarchy of workspaces, subworkspaces, folders, and subfolders within Teaming.