About

<u>News</u> <u>RSS</u>

**Screenshots** 

Live CD/USB

**Downloads** 

**Server Edition** 

**DRBL-winroll** 

**Testimonials** 

<u>Partners</u>

FAQ/Q&A

<u>Forum</u>

Mailing Lists

**Developers** 

Contributors **Related links** 

Google™ Custom

Local communities

Introducing the

Screen image simulated.

Starting at

**\$149**99

Shop Now

Featuring the Intel®

inside'

1,341,130 Visitors 29 Mar 2013 - 23 Oct 2013

Atom™processor.

Dell Venue 7 and 8.

Related LiveCD

**Lecture Materials** 

**Related Articles** 

CD/USB key vendors

## Clonezilla

The Free and Open Source Software for Disk Imaging and Cloning

## **Customized script with PXE**

## In this example: Use customized script with a PXE version of Clonezilla live

1. To put your customized script with a PXE version of Clonezilla live

[Back to 'Clonezilla Live Doc'

. To put your customized script with a PXE version of Clonezilla live ^TOP^

In this example, we assume (1) The IP address of your PXE server is 192.168.120.254, (2) the customized script (custom-ocs-2) is put on your PXE server's tftpd root dir (E.g. On DRBL server, the path is /tftpboot /nbi\_img/. It might be different in your case if you are not use DRBL server as a PXE server).

Therefor your pxelinux.cfg/default file is like:

label Clonezilla Live

MENU DEFAULT # MENU HIDE

MENU LABEL Clonezilla Live

# MENU PASSWD

kernel vmlinuz1

append initrd=initrd1.img boot=live union=aufs config noswap noprompt vga=788 ip=frommedia fetch=tftp://192.168.120.254/filesystem.squashfs ocs\_prerun="busybox tftp -g -r custom-ocs-2 -l /tmp/custom-ocs-2 192.168.120.254" ocs\_live\_run="bash /tmp/custom-ocs-2" keyboard-layouts=NONE ocs\_live\_batch="no" locales="en\_US.UTF-8" nolocales

**TEXT HELP** 

Boot Clonezilla live via network

**ENDTEXT** 

//NOTE// Remember to check the boot parameters on the Clonezilla live iso/zip file. It might change.

The content of custom-ocs-2 can be like:

#!/bin/bash

. /usr/share/drbl/sbin/drbl-conf-functions

. /usr/share/drbl/sbin/ocs-functions

. /etc/ocs/ocs-live.conf

# Load language file

ask and load lang set en US.UTF-8

# 1. Mount the clonezilla image home.

# Types: local\_dev, ssh\_server, samba\_server, nfs\_server

prep-ocsroot -t nfs\_server

# 2. Restore the image

if mountpoint /home/partimag/ &>/dev/null; then ocs-sr -1 en\_US.UTF-8 -c -p choose restoredisk ask\_user ask\_user

else

[ "\$BOOTUP" = "color" ] && \$SETCOLOR FAILURE

echo "Fail to find the Clonezilla image home /home/partimag!"

echo "Program terminated!"

[ "\$BOOTUP" = "color" ] && \$SETCOLOR NORMAL

//NOTE// Remember to add shebang line (#!/bin/bash) in your script to avoid a "Exec format error" issue.

For more boot parameters, please refer to this doc.

[Back to 'Clonezilla Live Doc']







advice for your life. And everything in it.

Get professional advice from fully licensed insurance advisors.

Learn More 🗲

