Download from finelybook www.finelybook.com

Managing the GPU RAM

By default TensorFlow automatically grabs all the RAM in all available GPUs the first time you run a graph, so you will not be able to start a second TensorFlow program while the first one is still running. If you try, you will get the following error:

```
E [...]/cuda_driver.cc:965] failed to allocate 3.66G (3928915968 bytes) from
device: CUDA_ERROR_OUT_OF_MEMORY
```

One solution is to run each process on different GPU cards. To do this, the simplest option is to set the CUDA_VISIBLE_DEVICES environment variable so that each process only sees the appropriate GPU cards. For example, you could start two programs like this:

- \$ CUDA_VISIBLE_DEVICES=0,1 python3 program_1.py
 # and in another terminal:
 \$ CUDA_VISIBLE_DEVICES=3,2 python3 program_2.py
- Program #1 will only see GPU cards 0 and 1 (numbered 0 and 1, respectively), and program #2 will only see GPU cards 2 and 3 (numbered 1 and 0, respectively). Every-




Figure 12-3. Each program gets two GPUs for itself

thing will work fine (see Figure 12-3).

Another option is to tell TensorFlow to grab only a fraction of the memory. For example, to make TensorFlow grab only 40% of each GPU's memory, you must create a ConfigProto object, set its gpu_options.per_process_gpu_memory_fraction option to 0.4, and create the session using this configuration:

```
config = tf.ConfigProto()
config.gpu_options.per_process_gpu_memory_fraction = 0.4
session = tf.Session(config=config)
```

Now two programs like this one can run in parallel using the same GPU cards (but not three, since $3 \times 0.4 > 1$). See Figure 12-4.

Program #1
Program #2

GPU #0
GPU #1
GPU #2
GPU #3

Figure 12-4. Each program gets all four GPUs, but with only 40% of the RAM each

If you run the nvidia-smi command while both programs are running, you should see that each process holds roughly 40% of the total RAM of each card:

\$ nvidia-smi []					
ĺ	Process	es:			GPU Memory
- [GPU	PID	Туре	Process nam	e Usage
	======	======	=====		=======================================
	0	5231	C	python	1677MiB
	0	5262	C	python	1677MiB
	1	5231	C	python	1677MiB
	1	5262	C	python	1677MiB
[]					

Yet another option is to tell TensorFlow to grab memory only when it needs it. To do this you must set config.gpu_options.allow_growth to True. However, TensorFlow never releases memory once it has grabbed it (to avoid memory fragmentation) so you may still run out of memory after a while. It may be harder to guarantee a deterministic behavior using this option, so in general you probably want to stick with one of the previous options.

Okay, now you have a working GPU-enabled TensorFlow installation. Let's see how to use it!

Placing Operations on Devices

The TensorFlow whitepaper¹ presents a friendly dynamic placer algorithm that automagically distributes operations across all available devices, taking into account things like the measured computation time in previous runs of the graph, estimations of the size of the input and output tensors to each operation, the amount of RAM available in each device, communication delay when transferring data in and out of

^{1 &}quot;TensorFlow: Large-Scale Machine Learning on Heterogeneous Distributed Systems," Google Research (2015).