ioctl_fat: manipulating the FAT filesystem

systutorials.com/docs/linux/man/2-ioctl fat/

<u>Linux Man Pages</u> » <u>Linux Man Pages Session 2</u>

ioctl_fat (2) - Linux Man Pages

```
Index of ioctl_fat man page
```

Read ioctl_fat man page on Linux: \$ man 2 ioctl_fat

NAME

ioctl fat - manipulating the FAT filesystem

SYNOPSIS

DESCRIPTION

The <u>ioctl(2)</u> system call can be used to read and write metadata of FAT filesystems that are not accessible using other system calls.

Reading and setting file attributes

Files and directories in the FAT filesystem possess an attribute bit mask that can be read with **FAT_IOCTL_GET_ATTRIBUTES** and written with **FAT_IOCTL_SET_ATTRIBUTES**. The *fd* argument contains a file descriptor for a file or directory. It is sufficient to create the file descriptor by calling **open**(2) with the **O_RDONLY** flag.

The attr argument contains a pointer to a bit mask. The bits of the bit mask are:

ATTR RO

This bit specifies that the file or directory is read-only.

ATTR HIDDEN

This bit specifies that the file or directory is hidden.

ATTR SYS

This bit specifies that the file is a system file.

ATTR VOLUME

This bit specifies that the file is a volume label. This attribute is read-only.

ATTR_DIR

This bit specifies that this is a directory. This attribute is read-only.

ATTR_ARCH

This bit indicates that this file or directory should be archived. It is set when a file is created or modified. It is reset by an archiving system.

The zero value ATTR_NONE can be used to indicate that no attribute bit is set.

Reading the volume label

FAT filesystems are identified by a volume label. The volume label can be read with **FAT_IOCTL_GET_VOLUME_ID**.

The *fd* argument can be a file descriptor for any file or directory of the filesystem. It is sufficient to create the file descriptor by calling **open**(2) with the **O_RDONLY** flag.

The *id* argument is a pointer to the field that will be filled with the volume ID. Typically the volume label is displayed to the user as a group of two 16-bit fields:

```
printf("Volume ID %4x-%4x\n", id >> 16, id & 0xFFFF);
```

Reading short file names of a directory

A file or directory on a FAT filesystem always has a short filename consisting of up to 8 capital letters, optionally followed by a period and up to 3 capital letters for the file extension. If the actual filename does not fit into this scheme, it is stored as a long filename of up to 255 UTF-16 characters.

The short filenames in a directory can be read with **VFAT_IOCTL_READDIR_SHORT**. **VFAT_IOCTL_READDIR_BOTH** reads both the short and the long filenames.

The *fd* argument must be a file descriptor for a directory. It is sufficient to create the file descriptor by calling **open**(2) with the **O_RDONLY** flag. The file descriptor can be used only once to iterate over the directory entries by calling **ioctl**(2) repeatedly.

The *entry* argument is a two-element array of the following structures:

The first entry in the array is for the short filename. The second entry is for the long filename.

The *d* ino and *d* off fields are filled only for long filenames. The *d* ino field holds the inode

number of the directory. The *d_off* field holds the offset of the file entry in the directory. As these values are not available for short filenames, the user code should simply ignore them.

The field *d_reclen* contains the length of the filename in the field *d_name*. To keep backward compatibility, a length of 0 for the short filename signals that the end of the directory has been reached. However, the preferred method for detecting the end of the directory is to test the **ioctl()** return value. If no long filename exists, field *d_reclen* is set to 0 and *d_name* is a character string of length 0 for the long filename.

RETURN VALUE

On error, -1 is returned, and errno is set to indicate the error.

For VFAT_IOCTL_READDIR_BOTH and VFAT_IOCTL_READDIR_SHORT a return value of 1 signals that a new directory entry has been read and a return value of 0 signals that the end of the directory has been reached.

ERRORS

ENOENT

This error is returned by VFAT_IOCTL_READDIR_BOTH and

VFAT_IOCTL_READDIR_SHORT if the file descriptor *fd* refers to a removed, but still open directory.

ENOTDIR

This error is returned by VFAT_IOCTL_READDIR_BOTH and

VFAT_IOCTL_READDIR_SHORT if the file descriptor fd does not refer to a directory.

ENOTTY

The file descriptor fd does not refer to an object in a FAT filesystem.

For further error values, see **ioctl**(2).

VERSIONS

VFAT_IOCTL_READDIR_BOTH and **VFAT_IOCTL_READDIR_SHORT** first appeared in Linux 2.0.

FAT_IOCTL_GET_ATTRIBUTES and **FAT_IOCTL_SET_ATTRIBUTES** first appeared in Linux 2.6.12.

FAT IOCTL GET VOLUME ID was introduced in version 3.11 of the Linux kernel.

CONFORMING TO

This API is Linux-specific.

EXAMPLE

Toggling the archive flag

The following program demonstrates the usage of **ioctl()** to manipulate file attributes. The program reads and displays the archive attribute of a file. After inverting the value of the attribute, the program reads and displays the attribute again.

The following was recorded when applying the program for the file /mnt/user/foo:

```
# ./toggle_fat_archive_flag /mnt/user/foo
Archive flag is set
Toggling archive flag
Archive flag is not set
```

Program source (toggle_fat archive flag.c)

```
#include <fcntl.h>
#include <<u>linux/msdos_fs.h</u>>
#include <stdint.h>
#include <stdio.h>
#include <<u>stdlib.h</u>>
#include <<u>sys/ioctl.h</u>>
#include <<u>unistd.h</u>>
 * Read file attributes of a file on a FAT filesystem.
 * Output the state of the archive flag.
static uint32_t
readattr(int fd)
    uint32_t attr;
    int ret;
    ret = ioctl(fd, FAT_IOCTL_GET_ATTRIBUTES, &attr);
    if (ret == -1) {
        perror("ioctl");
        exit(EXIT_FAILURE);
    }
    if (attr & ATTR_ARCH)
        printf("Archive flag is set\n");
        printf("Archive flag is not set\n");
    return attr;
}
int
main(int argc, char *argv[])
    uint32_t attr;
    int fd;
    int ret;
    if (argc != 2) {
        printf("Usage: %s FILENAME\n", argv[0]);
```

```
exit(EXIT_FAILURE);
}
fd = open(argv[1], 0_RDONLY);
if (fd == -1) {
    perror("open");
    exit(EXIT_FAILURE);
}
 * Read and display the FAT file attributes.
attr = readattr(fd);
* Invert archive attribute.
printf("Toggling archive flag\n");
attr ^= ATTR_ARCH;
 * Write the changed FAT file attributes.
ret = ioctl(fd, FAT_IOCTL_SET_ATTRIBUTES, &attr);
if (ret == -1) {
    perror("ioctl");
    exit(EXIT_FAILURE);
}
 * Read and display the FAT file attributes.
readattr(fd);
close(fd);
exit(EXIT_SUCCESS);
```

Reading the volume label

}

The following program demonstrates the use of **<u>ioctl</u>**(2) to display the volume label of a FAT filesystem.

The following output was recorded when applying the program for directory /mnt/user.

```
$ ./display_fat_volume_id /mnt/user
Volume ID 6443-6241
```

Program source (display fat volume id.c)

```
#include <fcntl.h>
#include <<u>linux/msdos_fs.h</u>>
#include <stdint.h>
#include <stdio.h>
#include <stdlib.h>
#include <sys/ioctl.h>
#include <unistd.h>
int
main(int argc, char *argv[])
    uint32_t id;
    int fd;
    int ret;
    if (argc != 2) {
        printf("Usage: %s FILENAME\n", argv[0]);
        exit(EXIT_FAILURE);
    }
    fd = open(argv[1], O_RDONLY);
    if (fd == -1) {
        perror("open");
        exit(EXIT_FAILURE);
    }
     * Read volume ID.
    ret = ioctl(fd, FAT_IOCTL_GET_VOLUME_ID, &id);
    if (ret == -1) {
        perror("ioctl");
        exit(EXIT_FAILURE);
    }
     * Format the output as two groups of 16 bits each.
    printf("Volume ID %4x-%4x\n", id >> 16, id & 0xFFFF);
    close(fd);
    exit(EXIT_SUCCESS);
}
```

Listing a directory

The following program demonstrates the use of <u>ioctl(2)</u> to list a directory. The following was recorded when applying the program to the directory /mnt/user.

```
$ ./fat_dir /mnt/user
46 -> ''
46. -> ''
ALONGF~1.TXT -> 'a long filename.txt'
UPPER.TXT -> ''
LOWER.TXT -> 'lower.txt'
```

```
#include <<u>fcntl.h</u>>
#include <<u>linux/msdos_fs.h</u>>
#include <stdio.h>
#include <<u>stdlib.h</u>>
#include <sys/ioctl.h>
#include <<u>unistd.h</u>>
int
main(int argc, char *argv[])
    struct __fat_dirent entry[2];
    int fd;
    int ret;
    if (argc != 2) {
        printf("Usage: %s DIRECTORY\n", argv[0]);
        exit(EXIT_FAILURE);
    }
     * Open file descriptor for the directory.
    fd = open(argv[1], O_RDONLY | O_DIRECTORY);
    if (fd == -1) {
        perror("open");
        exit(EXIT_FAILURE);
    }
    for (;;) {
        /*
         * Read next directory entry.
        ret = ioctl( fd, VFAT_IOCTL_READDIR_BOTH, entry);
        /*
         * If an error occurs, the return value is -1.
         * If the end of the directory list has been reached,
         * the return value is 0.
         * For backward compatibility the end of the directory
         * list is also signaled by d_reclen == 0.
         */
        if (ret < 1)
            break;
         * Write both the short name and the long name.
        printf("%s -> '%s'\n", entry[0].d_name, entry[1].d_name);
    }
    if (ret == -1) {
        perror("VFAT_IOCTL_READDIR_BOTH");
        exit(EXIT_FAILURE);
```

```
/*
 * Close the file descriptor.
 */
close(fd);

exit(EXIT_SUCCESS);
}
```

SEE ALSO

ioctl(2)

COLOPHON

This page is part of release 3.81 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at http://www.kernel.org/doc/man-pages/.

Linux man pages generated by: SysTutorials

Linux Man Pages Copyright Respective Owners. Site Copyright © <u>SysTutorials</u>. All Rights Reserved.