



Point number no 1. If ASA3 and ASA4 are not accessible and you encounter the error shown below, please follow the steps provided.

ASA3 and ASA4 Error





Solution

Right Click on the Taskbar of the RDP Machine and Click Task Manager.



Go to the User Option and Right Click on the Disconnected Student User and Click Sign Off.



Click on Signout user and ASA3 and ASA will work Perfectly.

>

NSGT (48)

3.6%

425.2 MB

0.1 MB/s

0 Mbps

>

student (35)

Disconnected

0%

322.4 MB

0 MB/s

0 Mbps

>

student (56)

0.8%

1,233.9 MB

0.1 MB/s

0.1 Mbps

Task Manager

If you sign out a user, the user's unsaved data might be lost.

Do you want to continue?

Sign out user

Cancel

Point number no 2.

To clear the config of ASA3 and ASA4.

First go to the system execution space with command

Changeto context system

Then go to Global Config mode with the command

Configure terminal


Then run command

Clear configure all

Note: There is no need to change the mode of ASA3 and ASA4 in Racks 1, 2, and 3, as the ASA mode is already set to Multiple Context mode in these racks. However, in Rack 4, you need to change the *ASA mode to multiple*. And no need to perform the above command to *clear the config in Rack 4* But on Rack 1 Rack2 and Rack 3 you need to perform.

Point number no 3.

If the syslog server is not opening from the management pc and showing you errors like below.



Solution

Open the Command Prompt as administrator in Management PC and Run the below command.

"C:\Program Files (x86)\Syslogd\Syslogd_Manager.exe"


And Come to Kiwisyslog and double click to open.

Point number no 4.

How to Open the NGIPS and Attacker PC in Rack 1 Rack 2 and Rack 3.


- Login into the Eveng with URL <http://150.1.7.20> or you will find this Eveng Url in the Bookmark of the firefox in RDP Machine.
- Username is **admin** and Password is **eve** to login the Eveng.

Once you logged in the Top right side you will find a device named Firepower in between SW1 and R13 that is your Ngips. Click that.




Once you are logged in, look at the bottom-left corner of the Firepower interface. You will find the Attacker PC there. Click on it.

Login username is **root** and password is **toor**



After you access the attacker PC. Click on the Terminal and Run hping3 command.




Note:- Before running hping3 command Kindly verify whether eth0 of the attacker pc has an IP address or not with **command ifconfig**. If ip is not there assign the ip as per workbook and then run hping3 command.

Point number no 5.


With Respect to WSA Use either management pc firefox or RDP machine firefox to access. If it is not accessible from either the machine firefox. Follow the steps below.

Open the Firefox on either machine that is management pc or rdp machine.

Type about:config



Then, search for `tls` and scroll down until you find the option `security.tls.version.enable-deprecated`. Its value will be set to `false` by default. Change the value to `true`, as shown in the figure below. Once this is done, the WSA should be accessible.



Point number no 6.

When you are integrating the WSA with AD if you face the issue with respect to the Clock Skew.

Open the WSA CLI from Secure CRT.

Step 1:- Type ntpconfig and press enter

Step 2:- Type Delete and press enter

Step 3:- Type 1 and press enter

Step 4:- Press enter and You will be in wsa.cisco.com as wsa hostname

Step 5:- Type commit

Again You need to add the NTP server

Step 1:- Type ntpconfig and press enter

Step 2:- Type New and press enter

Step 3:- Type 150.1.7.200 and press enter

Step 4:- Press enter and You will be in wsa.cisco.com as wsa hostname

Step 5:- Type commit

The above setting is shown in the picture below.

To delete the NTP in WSA.

```
wsa.cisco.com> ntpconfig
Currently configured NTP servers:
1. 150.1.7.200

Choose the operation you want to perform:
- NEW - Add a server.
- DELETE - Remove a server.
[]> DELETE
Enter the number of the NTP server you wish to remove.
[]> 1
Currently configured NTP servers:
No servers currently configured.

Choose the operation you want to perform:
- NEW - Add a server.
[]> press enter
wsa.cisco.com> commit
Please enter some comments describing your changes:
[]>
Changes committed: Wed Sep 09 09:35:03 2026 GMT
wsa.cisco.com>
```

To add the NTP in WSA.

```
wsa.cisco.com> ntpconfig
Currently configured NTP servers:
No servers currently configured.

Choose the operation you want to perform:
- NEW - Add a server.
[]> NEW
Please enter the fully qualified hostname or IP address of your NTP server.
[]> 150.1.7.200
Currently configured NTP servers:
1. 150.1.7.200

Choose the operation you want to perform:
- NEW - Add a server.
- DELETE - Remove a server.
[]> press enter
wsa.cisco.com> commit
Please enter some comments describing your changes:
[]>
Changes committed: Wed Sep 09 09:37:03 2026 GMT
wsa.cisco.com> █
```

Point number no 7.

How to verify the 4.5 that is Tacacs task.

- Use normal putty to take the ssh to 150.1.7.231 which will be there in management pc or in RDP machine.

