WinDbg Cheat Sheet

BOTH UM KM

Help & Expressions

`.help`	List debugger meta-commands
`.hh command`	Open command documentation
`!help`	List extension commands
`? expr`	Evaluate a MASM expression
`?? expr`	Evaluate a C++ expression
`.formats expr`	Show common numeric formats
`? poi(address)`	Dereference a pointer with MASM
`?? sizeof(TYPE)`	Return a typed object's size

Execution Control

`g [address]`	Continue, optionally until address
`p [count]`	Step over calls
`t [count]`	Step into instructions
`gu`	Run until the current function returns
`pa address`	Run until address, stepping over calls
`pt`	Run until a return instruction
`ph [count]`	Run until the next branch
`Ctrl+Break`	Break a running live target

Registers & Frames

`r`	Display registers
`r reg`	Display one register
`r reg=value`	Change a register on a live target
`.frame n`	Select stack frame **n**
`.frame /r n`	Select frame & display registers
`dv`	Locals (needs private symbols)

Number Prefixes (MASM)

`0x`	Hexadecimal (default)
`0n`	Decimal
`0t`	Octal
`0y`	Binary
`n [radix]`	Display or set radix to **8**, **10**, or **16**

Target & Processor

`vertarget`	Display target version & session details
`!sysinfo -?`	List system information options
`!cpuinfo [n]`	CPU information for one or all processors
`~n s`	Select processor **n**
`2k`	Display processor 2's stack
`!running -it`	Running threads & stacks on all CPUs
`!prcb [n]`	Processor control block summary
`!irql [n]`	Saved IRQL for a processor
`!pcr [n]`	Legacy PCR summary, may be inaccurate
`!idt`	Interrupt descriptor table

Processes & Threads

`!process 0 0`	List all active processes
`!process -1 0`	Display the current target process
`!process EPROCESS 0x6`	Threads, waits, & stacks for a process
`!thread ETHREAD`	Thread summary, waits, & stack
`!thread -t TID`	Find a thread by system TID
`.process /p /r EPROCESS`	Set implicit process, decode its transition PTEs, & reload UM symbols
`.thread /p /r ETHREAD`	Set thread/process context (live /p /r options)

Objects & Handles

`!object address`	Object name, type, & reference counts
`!object \`	Object Manager root directory
`!handle HANDLE 0x3 EPROCESS`	Handle & referenced object in a process
`!token TOKEN`	Security token contents
`!fileobj FILE_OBJECT`	File-object details

Breakpoints

`bl`	List breakpoints
`bp address`	Set a resolved software breakpoint
`bu module!symbol`	Set an unresolved symbolic breakpoint
`bm module!pattern`	Set breakpoints on matching symbols
`ba r size address`	Break on read or write. Size is **1**, **2**, or **4** on x86, plus **8** on x64
`ba w size address`	Break on write. Size is **1**, **2**, or **4** on x86, plus **8** on x64
`ba e 1 address`	Break on execution
`bc n`	Clear breakpoint **n**
`bc *`	Clear all breakpoints
`bd n`	Disable breakpoint **n**
`be n`	Enable breakpoint **n**

Stacks & Disassembly

`k`	Display a stack trace
`kb`	Stack with first three parameters
`kp`	Full parameters (needs full symbols)
`kv`	Verbose stack with frame information
`kn`	Stack with frame numbers
`u address Lcount`	Disassemble forward
`ub address`	Disassemble backward
`uu address`	Continue disassembly past memory read errors
`uf module!function`	Disassemble a complete function
`a address`	Assemble 32-bit x86 instructions into memory

Logging

`.logopen file`	Start logging debugger output
`.logappend file`	Append to an existing log
`.logclose`	Close the active log
`.echo text`	Print text to output & log

Scheduler & Synchronization

`!ready`	Threads waiting in ready queues
`!running`	Current & next thread per active CPU
`!dpcs`	Queued DPCs for each processor
`!timer`	Kernel timer queues
`!locks`	Held executive resource locks
`!qlocks`	Queued spin-lock state
`!stacks 2`	Kernel thread stacks with full details
`!findthreads -i IRP`	Find threads associated with an IRP
`!findthreads -d DEVOBJ`	Find threads associated with a device

Structures

`dt nt!_EPROCESS addr`	Executive process object
`dt nt!_ETHREAD addr`	Executive thread object
`dt nt!_KTHREAD addr`	Dispatcher & scheduler thread state
`dt nt!_KPRCB addr`	Per-processor kernel state
`dt nt!_DRIVER_OBJECT addr`	Loaded driver object
`dt nt!_DEVICE_OBJECT addr`	Device stack object
`dt nt!_IRP addr`	I/O request packet
`dt nt!_IO_STACK_LOCATION addr`	One IRP stack location
`dt nt!_OBJECT_HEADER addr`	Object Manager header

KM Symbols

`lm k`	List KM modules
`!lmi module`	Detailed module & symbol status
`.reload /f driver.sys`	Force symbols for one driver
`sxe ld:driver.sys`	Break when a driver loads
`bu driver!function`	Breakpoint that survives deferred load

Symbols & Modules

`.sympath`	Display the symbol search path
`.symfix C:\Symbols`	Configure Microsoft symbols & cache
`.reload module`	Refresh module & defer symbol loading
`.reload /f module`	Force symbols for one module
`ld module`	Load symbols for one module
`lm`	List known modules & symbol status
`lm l`	Only modules with symbols loaded
`lm e`	Only modules with symbol problems
`lm m pattern`	Filter by module name
`ln address`	Find the nearest symbol
`x module!pattern`	Search symbol names
`x /t module!pattern`	Include symbol type when available

Memory & Types

`db addr Lcount`	Bytes
`db /c n addr`	Display **n** byte columns
`dw addr Lcount`	2-byte words
`dW addr Lcount`	2-byte words with ASCII
`dd addr Lcount`	4-byte double words
`dq addr Lcount`	8-byte quad words
`dc addr Lcount`	4-byte values with ASCII
`df addr Lcount`	4-byte floating-point values
`dD addr Lcount`	8-byte floating-point values
`dp addr Lcount`	Pointer-sized values
`da addr`	ANSI string
`du addr`	Unicode string
`dds addr Lcount`	4-byte values with symbols
`dqs addr Lcount`	8-byte values with symbols
`dps addr Lcount`	Pointer-sized values with symbols
`s -b range bytes`	Search for bytes
`s -w range value`	Search for a 2-byte value
`s -d range value`	Search for a 4-byte value
`s -q range value`	Search for an 8-byte value
`s -a range "text"`	Search for ANSI text
`s -u range "text"`	Search for Unicode text
`dt module!_TYPE addr`	Interpret memory as a type
`dt TYPE addr field`	Display selected fields
`dt -r1 TYPE addr`	Expand one nested level
`dx expression`	Evaluate a typed data-model expression

Drivers & Devices

`!drvobj \Driver\Name`	Driver object summary
`!drvobj \Driver\Name 7`	Include devices & dispatch routines
`!devobj DEVOBJ`	Device object & attached devices
`!devstack DEVOBJ`	Device stack containing the object
`!devnode DEVNODE`	Plug & Play device-node state
`!object \Driver`	Enumerate named driver objects
`!object \Device`	Enumerate named device objects

I/O

`!irp IRP`	IRP state & I/O stack locations
`!irpfind`	Scan pool for allocated IRPs, can be slow
`!ioctldecode IOCTL`	Decode an I/O control code
`!fileobj FILE_OBJECT`	File object state & name
`!devhandles DEVOBJ`	Open handles for a device, private symbols required for full output

Context Rules

`Kernel virtual address`	Normally accessible from every process context
`User virtual address`	Translated through the implicit process
`Register context`	Selected by processor, `.thread`, `.trap`, or `.cxr`
`g`	Clears temporary register contexts when execution resumes

UM Context

`.attach PID`	Attach to a process
`.restart`	Restart a process launched by the debugger
`.detach`	Detach while leaving the process running
`qd`	Detach & quit the debugger
`|`	List debugged processes
`|n s`	Select debugger process **n**
`~`	List threads in the current process
`~.`	Display the current thread
`~n s`	Select debugger thread **n**
`~~[TID]s`	Select a thread by system TID
`~* k`	Display every thread's stack
`!runaway 7`	Thread UM, KM & elapsed times
`!findstack symbol 1`	Threads & frames containing a symbol

Exceptions & Event Filters

`!analyze -v`	Analyze the current exception
`!analyze -hang`	Analyze a suspected hang
`.exr -1`	Display the most recent exception record
`.ecxr`	Select the stored exception context
`.cxr address`	Select a saved context record
`sx`	List exception & event filters
`sxe code`	Break when the event first occurs
`sxd code`	Break only when unhandled
`sxn code`	Notify without breaking
`sxi code`	Ignore the event

UM Memory & State

`!address address`	Virtual memory region information
`!vprot address`	Virtual memory protection
`!dh address`	Portable executable headers
`!heap`	List process heaps
`!heap -x address`	Find the heap block containing address
`!dlls`	Loaded modules from the loader lists
`!gle`	Current thread's last-error value
`!error code`	Decode a Windows error code
`!exchain`	x86 structured exception chain

UM Structures

`!peb`	Current process environment block
`!teb`	Current thread environment block
`!handle handle 0xf`	Detailed handle information

Virtual Memory & Pool

`!vm`	System virtual-memory summary
`!memusage`	Physical page usage summary
`!address address`	Kernel virtual-address region
`!pte VA`	PDE & PTE mapping a virtual address
`!vtop PFN VA`	Translate VA with a directory-base PFN
`!vad VAD-Root`	Display a process VAD tree
`!sysptes`	System PTE information
`!pool address`	Pool allocation containing address
`!poolfind Tag 0`	Scan nonpaged pool for tag, can be slow
`!poolfind Tag 1`	Scan paged pool for tag, can be slow
`!poolused`	Pool usage grouped by tag

Bug Checks & Exceptions

`!analyze -v`	Verbose exception or bug-check analysis
`.bugcheck`	Bug-check code & four parameters
`.exr -1`	Most recent exception record
`.trap address`	Select a trap-frame register context
`.cxr address`	Select a context-record register context
`r cr2`	Faulting linear address on x86 or x64
`!pte @cr2`	Inspect the faulting address translation
`!verifier`	Driver Verifier state & statistics
`!deadlock`	Verifier deadlock-detection data
`!blackboxpnp`	Captured PnP black-box data when present
`!blackboxntfs`	Captured NTFS black-box data when present

Local -kl has no execution, breakpoints, registers or k stacks. Memory reads can see changing state.