The Python/C API

Version 3.12.0

Guido van Rossum and the Python development team

octobre 26, 2023

Python Software Foundation Email: docs@python.org

Table des matières

1	Intro	oduction Coding standards	3		
	1.2	Include Files	4		
	1.3	Useful macros	4		
	1.4	Objects, Types and Reference Counts	7		
		1.4.1 Compteurs de références	7		
		1.4.2 Types	10		
	1.5	Exceptions	10		
	1.6	Embarquer Python	12		
	1.7	Debugging Builds	13		
2	Stab	ilité de l'API C	15		
	2.1	Unstable C API	15		
	2.2	ABI stable	16		
		2.2.1 Limited C API	16		
		2.2.2 Stable ABI	16		
		2.2.3 Porté de l'API restreinte et performance	16		
		2.2.4 Inconvénients de l'API restreinte	17		
	2.3	Considérations relatives aux plateformes	17		
	2.4	Contenu de l'API restreinte	17		
		The Very High Level Layer 3.			
3	The	Very High Level Layer	35		
3		Very High Level Layer rence Counting	35 41		
	Refe				
4	Refe	rence Counting	41		
4	Refe	rence Counting ion des exceptions Printing and clearing	41 45		
4	Gest 5.1 5.2 5.3	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings	41 45 46 46 49		
4	Gest 5.1 5.2 5.3 5.4	rence Counting ion des exceptions Printing and clearing	41 45 46 46 49 50		
4	Gest 5.1 5.2 5.3 5.4 5.5	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux	41 45 46 46 49 50 52		
4	Gest 5.1 5.2 5.3 5.4 5.5 5.6	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux Exception Classes	41 45 46 46 49 50 52 53		
4	Gest 5.1 5.2 5.3 5.4 5.5 5.6 5.7	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux Exception Classes Objets exception	41 45 46 46 49 50 52 53		
4	Gest 5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux Exception Classes Objets exception Objets exception Unicode	41 45 46 46 49 50 52 53 54		
4	Refer 5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8 5.9	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux Exception Classes Objets exception Objets exception Unicode Contrôle de la récursion	41 45 46 46 49 50 52 53 54 55 56		
4	Gest 5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8	rence Counting ion des exceptions Printing and clearing Lever des exceptions Issuing warnings Querying the error indicator Traitement des signaux Exception Classes Objets exception Objets exception Unicode	41 45 46 46 49 50 52 53 54		

6	Utilit	raires 59						
	6.1							
	6.2	System Functions						
	6.3	Process Control						
	6.4	Importer des modules						
	6.5	Data marshalling support						
	6.6	Analyse des arguments et construction des valeurs						
		6.6.1 Analyse des arguments						
		6.6.2 Construction des valeurs						
	6.7	Conversion et formatage de chaînes						
	6.8	Réflexion						
	6.9	Codec registry and support functions						
	0.7	6.9.1 Codec lookup API						
		6.9.2 Registry API for Unicode encoding error handlers						
	6.10	Support for Perf Maps						
	0.10	Support for Ferr Maps						
7	Couc	he d'abstraction des objets						
	7.1	Protocole Objet						
	7.2	Call Protocol						
		7.2.1 The <i>tp_call</i> Protocol						
		7.2.2 The Vectorcall Protocol						
		7.2.3 Object Calling API						
		7.2.4 Call Support API						
	7.3	Number Protocol						
	7.4	Sequence Protocol						
	7.5	Protocole de correspondance						
	7.6	Protocole d'itération						
	7.7	Protocole tampon						
		7.7.1 La structure <i>buffer</i>						
		7.7.2 Buffer request types						
		7.7.3 Complex arrays						
		7.7.4 Fonctions relatives aux tampons						
	7.8	Ancien Protocole Tampon						
8	Couc	the des objets concrets						
	8.1	Objets fondamentaux						
		8.1.1 Objets type						
		8.1.2 L'objet None						
	8.2	Objets numériques						
		8.2.1 Objets <i>Integer</i>						
		8.2.2 Les objets booléens						
		8.2.3 Objets représentant les nombres à virgule flottante						
		8.2.4 Objets représentant des nombres complexes						
	8.3	Objets séquences						
		8.3.1 Objets <i>bytes</i>						
		8.3.2 Objets tableau d'octets						
		8.3.3 Objets Unicode et Codecs						
		8.3.4 Tuple Objects						
		8.3.5 Struct Sequence Objects						
		8.3.6 List Objects						
	8.4	Objets conteneurs						
		8.4.1 Objets dictionnaires						
		8.4.2 Set Objects						
	8.5	Objets fonctions						
		y and the second						

		8.5.1	Objets fonction	50
		8.5.2	Instance Method Objects	52
		8.5.3	Objets méthode	52
		8.5.4	Objets Cellules	53
		8.5.5	Objets code	
		8.5.6	Extra information	
	8.6		objets	
	0.0	8.6.1	Objets fichiers	
		8.6.2	Module Objects	
		8.6.3	Itérateurs	
		8.6.4	Les descripteurs	
		8.6.5	Slice Objects	
			·	
		8.6.6	Objets de type MemoryView	
		8.6.7	Objets à références faibles	
		8.6.8	Capsules	
		8.6.9	Objets décrivant les <i>frames</i>	
		8.6.10	Objets générateur	
		8.6.11	Objets coroutines	
		8.6.12	Context Variables Objects	
		8.6.13	Objets DateTime	76
		8.6.14	Objects for Type Hinting	79
9	Initia			81
	9.1		Python Initialization	
	9.2	Global o	configuration variables	82
	9.3	Initializi	ing and finalizing the interpreter	85
	9.4	Process-	-wide parameters	86
	9.5	Thread	State and the Global Interpreter Lock	89
		9.5.1	Releasing the GIL from extension code	90
		9.5.2	Non-Python created threads	
		9.5.3	Cautions about fork()	
		9.5.4	High-level API	
		9.5.5	Low-level API	
	9.6		erpreter support	
	7.0	9.6.1	A Per-Interpreter GIL	
		9.6.2	Bugs and caveats	
	9.7		ronous Notifications	
	9.7		g and Tracing	
	9.0			
				02
	9.10			02
		9.10.1		03
		9.10.2	Thread Local Storage (TLS) API	04
10	Drutho	m Initial	lization Configuration	Λ5
10	•		9	05
		Example		05
				06
		PyStatus		07
		•	8	808
			\mathcal{I}	209
		•	6	10
				19
			8	21
	10.9	Python	Configuration	21
	10.10	Python 1	Path Configuration	21

	10.11 Py_RunMain()	223
11	Memory Management	225
	11.1 Aperçu 11.2 Allocator Domains	
	11.3 Raw Memory Interface	
	11.4 Memory Interface	
	11.5 Object allocators	
	11.6 Default Memory Allocators	
	11.7 Customize Memory Allocators	230
	11.8 Debug hooks on the Python memory allocators	231
	11.9 The pymalloc allocator	233
	11.9.1 Customize pymalloc Arena Allocator	
	11.10 tracemalloc C API	
	11.11 Exemples	234
12	Implémentation d'objets	235
	12.1 Allouer des objets dans le tas	
	12.2 Common Object Structures	
	12.2.1 Base object types and macros	
	12.2.2 Implementing functions and methods	
	12.2.3 Accessing attributes of extension types	
	12.3 Objets type	
	12.3.1 Quick Reference	
	12.3.3 PyObject Slots	
	12.3.4 PyVarObject Slots	
	12.3.5 PyTypeObject Slots	
	12.3.6 Static Types	
	12.3.7 Heap Types	
	12.4 Number Object Structures	
	12.5 Mapping Object Structures	
	12.6 Sequence Object Structures	273
	12.7 Buffer Object Structures	274
	12.8 Async Object Structures	275
	12.9 Slot Type typedefs	
	12.10 Exemples	
	12.11 Supporting Cyclic Garbage Collection	
	12.11.1 Controlling the Garbage Collector State	
	12.11.2 Querying Garbage Collector State	282
13	Version des API et ABI	285
A	Glossaire	287
D	À propos de ces documents	301
D	B.1 Contributeurs de la documentation Python	301
C	Histoire et licence	303
		303
		304
		304
	C.2.2 LICENCE D'UTILISATION BEOPEN.COM POUR PYTHON 2.0	305

Index			325
D Cop	pyright		323
	C.3.19	Audioop	321
	C.3.18	Ensemble de tests C14N du W3C	
	C.3.17	libmpdec	320
	C.3.16	cfuhash	319
	C.3.15	zlib	318
	C.3.14	libffi	318
	C.3.13	expat	
	C.3.12	OpenSSL	
	C.3.11	strtod et dtoa	
	C.3.10	SipHash24	
	C.3.9	Select kqueue	
	C.3.8	test_epoll	
	C.3.7	Appel de procédures distantes en XML (RPC, pour Remote Procedure Call)	
	C.3.6	Les fonctions UUencode et UUdecode	
	C.3.5	Traçage d'exécution	
	C.3.4	Gestion de témoin (cookie)	
	C.3.2 C.3.3	Interfaces de connexion asynchrones	
	C.3.1 C.3.2	Interfaces de connexion (sockets)	
C.3	C.3.1	s et remerciements pour les logiciels tiers	
C.3	Licence	PYTHON 3.12.0	
	C.2.5	LICENCE BSD ZERO-CLAUSE POUR LE CODE DANS LA DOCUMENTATION DE	207
	C.2.4	LICENCE D'UTILISATION CWI POUR PYTHON 0.9.0 à 1.2	307
	0.2.0	LICENCE D'UTILISATION CNRI POUR PYTHON 1.6.1	
	C.2.3	LICENCE DITTH ICATION CADIDOLID DVTHOM 1.6.1	206

C'est la documentation de l'API utilisée par les développeurs C et C++ écrivant des modules d'extension ou intégrant Python. Elle va de pair avec extending-index, qui décrit les principes généraux de l'écriture d'extensions, mais ne rentre pas dans les détails de chaque fonction de l'API.

Table des matières 1

2 Table des matières

CHAPITRE 1

Introduction

The Application Programmer's Interface to Python gives C and C++ programmers access to the Python interpreter at a variety of levels. The API is equally usable from C++, but for brevity it is generally referred to as the Python/C API. There are two fundamentally different reasons for using the Python/C API. The first reason is to write *extension modules* for specific purposes; these are C modules that extend the Python interpreter. This is probably the most common use. The second reason is to use Python as a component in a larger application; this technique is generally referred to as *embedding* Python in an application.

Writing an extension module is a relatively well-understood process, where a "cookbook" approach works well. There are several tools that automate the process to some extent. While people have embedded Python in other applications since its early existence, the process of embedding Python is less straightforward than writing an extension.

Many API functions are useful independent of whether you're embedding or extending Python; moreover, most applications that embed Python will need to provide a custom extension as well, so it's probably a good idea to become familiar with writing an extension before attempting to embed Python in a real application.

1.1 Coding standards

If you're writing C code for inclusion in CPython, you **must** follow the guidelines and standards defined in **PEP 7**. These guidelines apply regardless of the version of Python you are contributing to. Following these conventions is not necessary for your own third party extension modules, unless you eventually expect to contribute them to Python.

1.2 Include Files

All function, type and macro definitions needed to use the Python/C API are included in your code by the following line:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

This implies inclusion of the following standard headers: <stdio.h>, <string.h>, <errno.h>, imits.h>, <assert.h> and <stdlib.h> (if available).

Note: Python pouvant définir certaines définitions pré-processeur qui affectent les têtes standard sur certains systèmes, vous *devez* inclure Python.h avant les en-têtes standards.

It is recommended to always define PY_SSIZE_T_CLEAN before including Python.h. See *Analyse des arguments et construction des valeurs* for a description of this macro.

All user visible names defined by Python.h (except those defined by the included standard headers) have one of the prefixes Py or Py. Names beginning with Py are for internal use by the Python implementation and should not be used by extension writers. Structure member names do not have a reserved prefix.

Note: User code should never define names that begin with Py or _Py. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

The header files are typically installed with Python. On Unix, these are located in the directories prefix/include/pythonversion/ and $exec_prefix/include/pythonversion/$, where prefix and $exec_prefix$ are defined by the corresponding parameters to Python's **configure** script and *version* is '%d.%d' % sys. $version_info[:2]$. On Windows, the headers are installed in prefix/include, where prefix is the installation directory specified to the installer.

To include the headers, place both directories (if different) on your compiler's search path for includes. Do *not* place the parent directories on the search path and then use #include <pythonX.Y/Python.h>; this will break on multi-platform builds since the platform independent headers under prefix include the platform specific headers from exec_prefix.

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be extern "C". As a result, there is no need to do anything special to use the API from C++.

1.3 Useful macros

Several useful macros are defined in the Python header files. Many are defined closer to where they are useful (e.g. PV_RETURN_NONE). Others of a more general utility are defined here. This is not necessarily a complete listing.

PyMODINIT_FUNC

Declare an extension module PyInit initialization function. The function return type is PyObject*. The macro declares any special linkage declarations required by the platform, and for C++ declares the function as extern "C".

The initialization function must be named PyInit_name, where name is the name of the module, and should be the only non-static item defined in the module file. Example:

```
static struct PyModuleDef spam_module = {
    PyModuleDef_HEAD_INIT,
    .m_name = "spam",
    ...
};

PyMODINIT_FUNC
PyInit_spam(void)
{
    return PyModule_Create(&spam_module);
}
```

$Py_ABS(x)$

Return the absolute value of x.

Nouveau dans la version 3.3.

Py_ALWAYS_INLINE

Ask the compiler to always inline a static inline function. The compiler can ignore it and decides to not inline the function.

It can be used to inline performance critical static inline functions when building Python in debug mode with function inlining disabled. For example, MSC disables function inlining when building in debug mode.

Marking blindly a static inline function with Py_ALWAYS_INLINE can result in worse performances (due to increased code size for example). The compiler is usually smarter than the developer for the cost/benefit analysis.

If Python is built in debug mode (if the Py_DEBUG macro is defined), the Py_ALWAYS_INLINE macro does nothing.

It must be specified before the function return type. Usage:

```
static inline Py_ALWAYS_INLINE int random(void) { return 4; }
```

Nouveau dans la version 3.11.

$Py_CHARMASK(c)$

Argument must be a character or an integer in the range [-128, 127] or [0, 255]. This macro returns c cast to an unsigned char.

Py DEPRECATED (version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

Exemple:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

Modifié dans la version 3.8 : MSVC support was added.

Py_GETENV(s)

Like getenv(s), but returns NULL if -E was passed on the command line (see *PyConfig.use_environment*).

$Py_MAX(x, y)$

Return the maximum value between x and y.

Nouveau dans la version 3.3.

Py_MEMBER_SIZE (type, member)

Return the size of a structure (type) member in bytes.

Nouveau dans la version 3.6.

1.3. Useful macros 5

$Py_MIN(x, y)$

Return the minimum value between x and y.

Nouveau dans la version 3.3.

Py_NO_INLINE

Disable inlining on a function. For example, it reduces the C stack consumption: useful on LTO+PGO builds which heavily inline code (see bpo-33720).

Usage:

```
Py_NO_INLINE static int random(void) { return 4; }
```

Nouveau dans la version 3.11.

Py_STRINGIFY(X)

Convert x to a C string. E.g. Py_STRINGIFY (123) returns "123".

Nouveau dans la version 3.4.

Py UNREACHABLE ()

Use this when you have a code path that cannot be reached by design. For example, in the default: clause in a switch statement for which all possible values are covered in case statements. Use this in places where you might be tempted to put an assert (0) or abort () call.

In release mode, the macro helps the compiler to optimize the code, and avoids a warning about unreachable code. For example, the macro is implemented with __builtin_unreachable() on GCC in release mode.

A use for Py_UNREACHABLE() is following a call a function that never returns but that is not declared Py_NO_RETURN.

If a code path is very unlikely code but can be reached under exceptional case, this macro must not be used. For example, under low memory condition or if a system call returns a value out of the expected range. In this case, it's better to report the error to the caller. If the error cannot be reported to caller, $Py_FatalError()$ can be used. Nouveau dans la version 3.7.

Py_UNUSED (arg)

Use this for unused arguments in a function definition to silence compiler warnings. Example: int func(int a, int Py_UNUSED(b)) { return a; }.

Nouveau dans la version 3.4.

PyDoc_STRVAR (name, str)

Creates a variable with name name that can be used in docstrings. If Python is built without docstrings, the value will be empty.

Use PyDoc_STRVAR for docstrings to support building Python without docstrings, as specified in PEP 7.

Exemple:

PyDoc_STR (str)

Creates a docstring for the given input string or an empty string if docstrings are disabled.

Use *PyDoc_STR* in specifying docstrings to support building Python without docstrings, as specified in **PEP 7**. Exemple :

1.4 Objects, Types and Reference Counts

Most Python/C API functions have one or more arguments as well as a return value of type PyObject*. This type is a pointer to an opaque data type representing an arbitrary Python object. Since all Python object types are treated the same way by the Python language in most situations (e.g., assignments, scope rules, and argument passing), it is only fitting that they should be represented by a single C type. Almost all Python objects live on the heap: you never declare an automatic or static variable of type PyObject, only pointer variables of type PyObject* can be declared. The sole exception are the type objects; since these must never be deallocated, they are typically static PyTypeObject objects.

All Python objects (even Python integers) have a *type* and a *reference count*. An object's type determines what kind of object it is (e.g., an integer, a list, or a user-defined function; there are many more as explained in types). For each of the well-known types there is a macro to check whether an object is of that type; for instance, PyList_Check (a) is true if (and only if) the object pointed to by *a* is a Python list.

1.4.1 Compteurs de références

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a *strong reference* to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When the last *strong reference* to an object is released (i.e. its reference count becomes zero), the object is deallocated. If it contains references to other objects, those references are released. Those other objects may be deallocated in turn, if there are no more references to them, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is "don't do that.")

Reference counts are always manipulated explicitly. The normal way is to use the macro $Py_INCREF()$ to take a new reference to an object (i.e. increment its reference count by one), and $Py_DECREF()$ to release that reference (i.e. decrement the reference count by one). The $Py_DECREF()$ macro is considerably more complex than the incref one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of releasing references for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming $sizeof(Py_ssize_t) >= sizeof(void*)$). Thus, the reference count increment is a simple operation.

It is not necessary to hold a *strong reference* (i.e. increment the reference count) for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to take a new *strong reference* (i.e. increment the reference count) temporarily. An important situation where this arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without taking a new reference. Some other operation might conceivably remove the object from the list, releasing that reference, and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a

code path which allows control to flow back to the user from a Py_DECREF (), so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with PyObject_, PyNumber_, PySequence_ or PyMapping_). These operations always create a new *strong reference* (i.e. increment the reference count) of the object they return. This leaves the caller with the responsibility to call Py_DECREF() when they are done with the result; this soon becomes second nature.

Reference Count Details

The reference count behavior of functions in the Python/C API is best explained in terms of *ownership of references*. Ownership pertains to references, never to objects (objects are not owned: they are always shared). "Owning a reference" means being responsible for calling Py_DECREF on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually releasing it by calling $Py_DECREF()$ or $Py_XDECREF()$ when it's no longer needed----or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a *new* reference. When no ownership is transferred, the caller is said to *borrow* the reference. Nothing needs to be done for a *borrowed reference*.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are <code>PyList_SetItem()</code> and <code>PyTuple_SetItem()</code>, which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple (1, 2, "three") could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here, $PyLong_FromLong$ () returns a new reference which is immediately stolen by $PyTuple_SetItem$ (). When you want to keep using an object although the reference to it will be stolen, use Py_INCREF () to grab another reference before calling the reference-stealing function.

Incidentally, $PyTuple_SetItem()$ is the *only* way to set tuple items; $PySequence_SetItem()$ and $PyObject_SetItem()$ refuse to do this since tuples are an immutable data type. You should only use $PyTuple_SetItem()$ for tuples that you are creating yourself.

Equivalent code for populating a list can be written using PyList_New() and PyList_SetItem().

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function, $Py_BuildValue()$, that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

It is much more common to use PyObject_SetItem() and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding references

is much saner, since you don't have to take a new reference just so you can give that reference away ("have it be stolen"). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
   Py_ssize_t i, n;
   n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {</pre>
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {</pre>
            Py_DECREF (index);
            return -1;
        Py_DECREF (index);
    }
    return 0;
```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the only reference to the object. Therefore, the generic functions that return object references, like <code>PyObject_GetItem()</code> and <code>PySequence_GetItem()</code>, always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only --- the plumage (the type of the object passed as an argument to the function) doesn't enter into it! Thus, if you extract an item from a list using $PyList_GetItem()$, you don't own the reference --- but if you obtain the same item from the same list using $PySequence_GetItem()$ (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using $PyList_GetItem()$, and once using $PySequence_GetItem()$.

```
long
sum_list(PyObject *list)
   Py_ssize_t i, n;
   long total = 0, value;
   PyObject *item;
   n = PyList_Size(list);
   if (n < 0)
        return -1; /* Not a list */
    for (i = 0; i < n; i++) {</pre>
        item = PyList_GetItem(list, i); /* Can't fail */
        if (!PyLong_Check(item)) continue; /* Skip non-integers */
        value = PyLong_AsLong(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
        total += value;
    }
```

(suite sur la page suivante)

(suite de la page précédente)

```
return total;
}
```

```
sum_sequence(PyObject *sequence)
    Py_ssize_t i, n;
    long total = 0, value;
   PyObject *item;
    n = PySequence_Length(sequence);
    if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {</pre>
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {
            value = PyLong_AsLong(item);
            Py_DECREF (item);
            if (value == -1 && PyErr_Occurred())
                 /* Integer too big to fit in a C long, bail out */
                return -1;
            total += value;
        }
        else {
            Py_DECREF(item); /* Discard reference ownership */
    return total;
```

1.4.2 Types

There are few other data types that play a significant role in the Python/C API; most are simple C types such as int, long, double and char*. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

type Py_ssize_t

Part of the Stable ABI. A signed integral type such that $sizeof(Py_size_t) == sizeof(size_t)$. C99 doesn't define such a thing directly (size_t is an unsigned integral type). See PEP 353 for details. $PY_SSIZE_T_MAX$ is the largest positive value of type Py_size_t .

1.5 Exceptions

The Python programmer only needs to deal with exceptions if specific error handling is required; unhandled exceptions are automatically propagated to the caller, then to the caller's caller, and so on, until they reach the top-level interpreter, where they are reported to the user accompanied by a stack traceback.

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented

otherwise, this indicator is either NULL or -1, depending on the function's return type. A few functions return a Boolean true/false result, with false indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with $PyErr_Occurred()$. These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function $PyErr_Occurred()$ can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and NULL otherwise. There are a number of functions to set the exception state: $PyErr_SetString()$ is the most common (though not the most general) function to set the exception state, and $PyErr_Clear()$ clears the exception state.

The full exception state consists of three objects (all of which can be NULL): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of $sys.exc_info()$; however, they are not the same: the Python objects represent the last exception being handled by a Python try ... except statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to $sys.exc_info()$ and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function <code>sys.exc_info()</code>, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns, and return an error indicator, but it should *not* set another exception --- that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the <code>sum_sequence()</code> example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
int
incr_item(PyObject *dict, PyObject *key)
{
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
    int rv = -1; /* Return value initialized to -1 (failure) */

    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;

        /* Clear the error and use zero: */
        PyErr_Clear();
```

(suite sur la page suivante)

1.5. Exceptions 11

(suite de la page précédente)

```
item = PyLong_FromLong(OL);
       if (item == NULL)
           goto error;
   const_one = PyLong_FromLong(1L);
   if (const_one == NULL)
       goto error;
   incremented_item = PyNumber_Add(item, const_one);
   if (incremented_item == NULL)
       goto error;
   if (PyObject_SetItem(dict, key, incremented_item) < 0)</pre>
       goto error;
   rv = 0; /* Success */
   /* Continue with cleanup code */
error:
  /* Cleanup code, shared by success and failure path */
   /* Use Py_XDECREF() to ignore NULL references */
  Py_XDECREF (item);
  Py_XDECREF (const_one);
  Py_XDECREF(incremented_item);
   return rv; /* -1 for error, 0 for success */
```

This example represents an endorsed use of the goto statement in C! It illustrates the use of $PyErr_ExceptionMatches()$ and $PyErr_Clear()$ to handle specific exceptions, and the use of $Py_XDECREF()$ to dispose of owned references that may be NULL (note the 'X' in the name; $Py_DECREF()$ would crash when confronted with a NULL reference). It is important that the variables used to hold owned references are initialized to NULL for this to work; likewise, the proposed return value is initialized to -1 (failure) and only set to success after the final call made is successful.

1.6 Embarquer Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is $Py_Initialize()$. This initializes the table of loaded modules, and creates the fundamental modules builtins, __main__, and sys. It also initializes the module search path (sys.path).

Py_Initialize() does not set the "script argument list" (sys.argv). If this variable is needed by Python code that will be executed later, setting PyConfig.argv and PyConfig.parse_argv must be set: see Python Initialization Configuration.

On most systems (in particular, on Unix and Windows, although the details are slightly different), $Py_Initialize()$ calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named lib/pythonX. Y relative to the parent directory where the executable named python is found on the shell command search path (the environment variable PATH).

For instance, if the Python executable is found in /usr/local/bin/python, it will assume that the libraries are in /

usr/local/lib/pythonX. Y. (In fact, this particular path is also the "fallback" location, used when no executable file named python is found along PATH.) The user can override this behavior by setting the environment variable PYTHONHOME, or insert additional directories in front of the standard path by setting PYTHONPATH.

The embedding application can steer the search by calling $Py_SetProgramName(file)$ before calling $Py_Initialize()$. Note that PYTHONHOME still overrides this and PYTHONPATH is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of $Py_GetPath()$, $Py_GetPrefix()$, $Py_GetExecPrefix()$, and $Py_GetProgramFullPath()$ (all defined in Modules/getpath.c).

Sometimes, it is desirable to "uninitialize" Python. For instance, the application may want to start over (make another call to $Py_Initialize()$) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling $Py_FinalizeEx()$. The function $Py_IsInitialized()$ returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that $Py_FinalizeEx()$ does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

1.7 Debugging Builds

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file Misc/SpecialBuilds.txt in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently used builds will be described in the remainder of this section.

Compiling the interpreter with the Py_DEBUG macro defined produces what is generally meant by a debug build of Python. Py_DEBUG is enabled in the Unix build by adding --with-pydebug to the ./configure command. It is also implied by the presence of the not-Python-specific _DEBUG macro. When Py_DEBUG is enabled in the Unix build, compiler optimization is disabled.

In addition to the reference count debugging described below, extra checks are performed, see Python Debug Build.

Defining Py_TRACE_REFS enables reference tracing (see the configure --with-trace-refs option). When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every PyObject. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.)

Please refer to Misc/SpecialBuilds.txt in the Python source distribution for more detailed information.

Stabilité de l'API C

Unless documented otherwise, Python's C API is covered by the Backwards Compatibility Policy, **PEP 387**. Most changes to it are source-compatible (typically by only adding new API). Changing existing API or removing API is only done after a deprecation period or to fix serious issues.

L'interface binaire de CPython (ABI) est entièrement compatible au sein d'une version mineure (à condition que la compilation soit toujours faite de même manière, comme indiqué dans *Considérations relatives aux plateformes* ci-dessous). Ainsi le code compilé pour Python 3.10.0 fonctionnera avec Python 3.10.8 et inversement, mais il devra être compilé séparément pour 3.9.x et 3.10.x.

There are two tiers of C API with different stability expectations :

- *Unstable API*, may change in minor versions without a deprecation period. It is marked by the PyUnstable prefix in names.
- *Limited API*, is compatible across several minor releases. When *Py_LIMITED_API* is defined, only this subset is exposed from *Python.h*.

These are discussed in more detail below.

Names prefixed by an underscore, such as _Py_InternalState, are private API that can change without notice even in patch releases. If you need to use this API, consider reaching out to CPython developers to discuss adding public API for your use case.

2.1 Unstable C API

Any API named with the PyUnstable prefix exposes CPython implementation details, and may change in every minor release (e.g. from 3.9 to 3.10) without any deprecation warnings. However, it will not change in a bugfix release (e.g. from 3.10.0 to 3.10.1).

It is generally intended for specialized, low-level tools like debuggers.

Projects that use this API are expected to follow CPython development and spend extra effort adjusting to changes.

2.2 ABI stable

For simplicity, this document talks about *extensions*, but the Limited API and Stable ABI work the same way for all uses of the API – for example, embedding Python.

2.2.1 Limited C API

Python 3.2 introduced the *Limited API*, a subset of Python's C API. Extensions that only use the Limited API can be compiled once and work with multiple versions of Python. Contents of the Limited API are *listed below*.

Py_LIMITED_API

Définissez cette macro avant d'inclure Python. h pour n'inclure que l'API restreinte et indiquer sa version.

Define Py_LIMITED_API to the value of PY_VERSION_HEX corresponding to the lowest Python version your extension supports. The extension will work without recompilation with all Python 3 releases from the specified one onward, and can use Limited API introduced up to that version.

Il est recommandé de renseigner une version mineure minimale (par exemple 0x030A0000 pour Python 3.10) plutôt que d'utiliser directement la macro PY_VERSION_HEX pour ne pas dépendre de la version de Python utilisée lors de la compilation.

Vous pouvez aussi définir Py_LIMITED_API à 3. Cette valeur est équivalente à 0x03020000 correspondant à Python 3.2, la première version à supporter l'API restreinte.

2.2.2 Stable ABI

To enable this, Python provides a Stable ABI: a set of symbols that will remain compatible across Python 3.x versions.

The Stable ABI contains symbols exposed in the *Limited API*, but also other ones – for example, functions necessary to support older versions of the Limited API.

Sur Windows les extensions qui utilisent l'ABI stable doivent être liées avec python3.dll et non pas avec une bibliothèque spécifique à une version comme python39.dll.

Sur certaines plateformes Python essaiera de charger une bibliothèque partagée dont le nom contient abi3 (par exemple mymodule.abi3.so). Il ne vérifie pas si ces extensions respectent l'ABI stable. L'utilisateur (ou ses outils d'administration) doit s'assurer que les extensions compilées avec une version donnée de l'API restreinte, par exemple 3.10+, ne sont pas utilisées avec des versions plus anciennes de Python.

Toutes les fonctions de l'ABI stable sont présentes dans la bibliothèque dynamique de Python en tant que fonction, et pas uniquement comme macro. Elles peuvent donc être utilisées avec des langages qui n'utilisent pas le pré-processeur C.

2.2.3 Porté de l'API restreinte et performance

L'objectif de l'API restreinte est de permettre l'ensemble des opérations possibles avec l'API C étendue, mais peut avoir un impact sur les performances.

Par exemple la fonction <code>PyList_GetItem()</code> est disponible, mais la macro « dangereuse » <code>PyList_GET_ITEM()</code> ne l'est pas. Cette macro peut être plus rapide car elle dépend de détails d'implémentation spécifique à l'objet <code>list</code>.

Si Py_LIMITED_API n'est pas défini certaines fonctions de l'API C seront remplacées par des macros ou une version en-ligne. Définir Py_LIMITED_API désactive cette optimisation, permettant de se garantir contre les évolutions des structures de données utilisées par Python, et peut réduire les performances.

En omettant la définition de Py_LIMITED_API il est possible de compiler une extension utilisant l'API restreinte avec une version spécifique de l'ABI. Les performances seront meilleures pour cette version de Python, mais la compatibilité

sera réduite. Compiler en définissant Py_LIMITED_API produira une extension qui peut être utilisée quand une variante spécifique à une version n'est pas disponible — par exemple pour une version alpha de Python.

2.2.4 Inconvénients de l'API restreinte

Note that compiling with Py_LIMITED_API is *not* a complete guarantee that code conforms to the *Limited API* or the *Stable ABI*. Py_LIMITED_API only covers definitions, but an API also includes other issues, such as expected semantics.

Une des limitations est que Py_LIMITED_API ne protège pas contre l'appel d'une fonction avec des arguments qui sont invalides pour une version de Python plus ancienne. Par exemple considérons une fonction qui accepte NULL comme argument à partir de 3.9. NULL permet maintenant d'utiliser le comportement par défaut, mais Python 3.8 essayera d'accéder à l'objet pointé et dé-référencera NULL, causant un crash. Des problèmes similaires peuvent se produire avec les attributs des structures.

Un autre problème est que certains attributs ne sont pas encore cachés lorsque Py_LIMITED_API est défini, même s'ils ne font pas partie de l'API restreinte.

Pour ces raisons il est recommandé de tester une extension avec *l'ensemble des versions mineures* supportées de Python, et généralement de la compiler avec la plus *ancienne* de ces versions.

Il est aussi recommandé de vérifier la documentation de toutes les API utilisées pour vérifier qu'elles fassent bien partie de l'API restreinte. Même lorsque Py_LIMITED_API est défini quelques fonctions privées peuvent être exposées aux utilisateurs pour des raisons techniques, ou par erreur.

Notez aussi que l'API restreinte n'est pas forcément stable : compiler avec Python 3.8 en définissant Py_LIMITED_API garanti que l'extension fonctionnera avec Python 3.12, mais pas qu'elle pourra *être compilée* avec Python 3.12. En particulier certaines parties de l'API restreinte peuvent être dépréciées et retirées tant que l'ABI stable n'est pas modifiée.

2.3 Considérations relatives aux plateformes

ABI stability depends not only on Python, but also on the compiler used, lower-level libraries and compiler options. For the purposes of the *Stable ABI*, these details define a "platform". They usually depend on the OS type and processor architecture

Les distributeurs de Python doivent s'assurer que toutes les versions de Python pour une plateforme donnée sont compilées de manière à ne pas rompre la compatibilité de l'ABI stable. C'est le cas des versions produites pour Windows et macOS de python.org et de la plupart des distributions tierces.

2.4 Contenu de l'API restreinte

Currently, the *Limited API* includes the following items :

```
— PY_VECTORCALL_ARGUMENTS_OFFSET
— PyAIter_Check()
— PyArg_Parse()
— PyArg_ParseTuple()
— PyArg_ParseTupleAndKeywords()
— PyArg_UnpackTuple()
— PyArg_VaParse()
— PyArg_VaParseTupleAndKeywords()
— PyArg_ValidateKeywordArguments()
```

```
— PyBaseObject_Type
— PyBool_FromLong()
- PyBool Type
— PyBuffer_FillContiguousStrides()
— PyBuffer_FillInfo()
- PyBuffer FromContiguous()
— PyBuffer GetPointer()
— PyBuffer_IsContiguous()
— PyBuffer_Release()
— PyBuffer_SizeFromFormat()
— PyBuffer_ToContiguous()
— PyByteArrayIter_Type
— PyByteArray_AsString()
— PyByteArray_Concat()
— PyByteArray_FromObject()
— PyByteArray_FromStringAndSize()
- PyByteArray_Resize()
- PvBvteArrav Size()
— PyByteArray_Type
— PyBytesIter_Type
— PyBytes_AsString()
— PyBytes_AsStringAndSize()
— PyBytes_Concat()
- PyBytes ConcatAndDel()
— PyBytes_DecodeEscape()
- PyBytes FromFormat()
— PyBytes_FromFormatV()
- PyBytes_FromObject()
— PyBytes_FromString()
— PyBytes_FromStringAndSize()
— PyBytes_Repr()
— PyBytes_Size()
- PyBytes_Type
- PyCFunction
- PvCFunctionWithKeywords
— PyCFunction_Call()
- PyCFunction GetFlags()
— PyCFunction_GetFunction()
— PyCFunction_GetSelf()
— PyCFunction_New()
- PyCFunction NewEx()
- PyCFunction_Type
- PyCMethod New()
— PyCallIter_New()
— PyCallIter_Type
— PyCallable_Check()
- PyCapsule_Destructor
— PyCapsule_GetContext()
— PyCapsule_GetDestructor()
— PyCapsule_GetName()
— PyCapsule_GetPointer()
— PyCapsule_Import()
— PyCapsule_IsValid()
- PyCapsule New()
```

```
— PyCapsule_SetContext()
— PyCapsule_SetDestructor()
- PyCapsule SetName()
— PyCapsule_SetPointer()
— PyCapsule_Type
— PyClassMethodDescr Type
— PyCodec BackslashReplaceErrors()
- PyCodec Decode()
— PyCodec_Decoder()
— PyCodec_Encode()
— PyCodec_Encoder()
— PyCodec_IgnoreErrors()
— PyCodec_IncrementalDecoder()
— PyCodec_IncrementalEncoder()
— PyCodec_KnownEncoding()
— PyCodec_LookupError()
— PyCodec_NameReplaceErrors()
- PvCodec Register()
— PyCodec_RegisterError()
— PyCodec_ReplaceErrors()
— PyCodec_StreamReader()
- PyCodec StreamWriter()
— PyCodec_StrictErrors()
— PyCodec_Unregister()
— PyCodec_XMLCharRefReplaceErrors()
- PyComplex FromDoubles()
— PyComplex_ImagAsDouble()
— PyComplex_RealAsDouble()
— PyComplex_Type
— PyDescr_NewClassMethod()
- PyDescr_NewGetSet()
— PyDescr_NewMember()
— PyDescr_NewMethod()
— PyDictItems_Type
— PyDictIterItem_Type
— PyDictIterKey_Type
- PyDictIterValue Type
— PyDictKeys_Type
— PyDictProxy_New()
— PyDictProxy_Type
— PyDictRevIterItem_Type
— PyDictRevIterKey_Type
— PyDictRevIterValue_Type
— PyDictValues_Type
— PyDict_Clear()
— PyDict_Contains()
— PyDict_Copy()
— PyDict_DelItem()
— PyDict_DelItemString()
— PyDict_GetItem()
— PyDict_GetItemString()
— PyDict GetItemWithError()
— PyDict_Items()
- PyDict Keys()
```

```
— PyDict_Merge()
— PyDict_MergeFromSeq2()
- PyDict New()
— PyDict_Next()
— PyDict_SetItem()
- PyDict SetItemString()
- PyDict Size()
- PyDict_Type
— PyDict_Update()
— PyDict_Values()
— PyEllipsis_Type
— PyEnum_Type
— PyErr_BadArgument()
— PyErr_BadInternalCall()
— PyErr_CheckSignals()
— PyErr_Clear()
— PyErr_Display()
- PyErr DisplayException()
— PyErr_ExceptionMatches()
- PyErr Fetch()
— PyErr_Format()
— PyErr FormatV()
— PyErr_GetExcInfo()
— PyErr GetHandledException()
— PyErr GetRaisedException()
— PyErr_GivenExceptionMatches()
— PyErr_NewException()
— PyErr_NewExceptionWithDoc()
— PyErr_NoMemory()
— PyErr_NormalizeException()
— PyErr_Occurred()
— PyErr_Print()
— PyErr_PrintEx()
— PyErr_ProgramText()
— PyErr ResourceWarning()
— PyErr_Restore()
— PyErr SetExcFromWindowsErr()
— PyErr_SetExcFromWindowsErrWithFilename()
— PyErr SetExcFromWindowsErrWithFilenameObject()
- PyErr_SetExcFromWindowsErrWithFilenameObjects()
- PyErr SetExcInfo()
— PyErr SetFromErrno()
— PyErr SetFromErrnoWithFilename()
— PyErr_SetFromErrnoWithFilenameObject()
— PyErr_SetFromErrnoWithFilenameObjects()
— PyErr_SetFromWindowsErr()
— PyErr_SetFromWindowsErrWithFilename()
— PyErr_SetHandledException()
— PyErr_SetImportError()
— PyErr_SetImportErrorSubclass()
— PyErr_SetInterrupt()
— PyErr SetInterruptEx()
— PyErr_SetNone()
- PyErr SetObject()
```

— PyErr_SetRaisedException() — PyErr_SetString() — PyErr SyntaxLocation() — PyErr_SyntaxLocationEx() — PyErr_WarnEx() — PyErr WarnExplicit() — PyErr WarnFormat() - PyErr WriteUnraisable() — PyEval_AcquireLock() — PyEval_AcquireThread() — PyEval_CallFunction() — PyEval_CallMethod() — PyEval_CallObjectWithKeywords() — PyEval_EvalCode() — PyEval_EvalCodeEx() — PyEval_EvalFrame() — PyEval_EvalFrameEx() - PyEval GetBuiltins() — PyEval_GetFrame() — PyEval_GetFuncDesc() — PyEval_GetFuncName() - PyEval GetGlobals() — PyEval_GetLocals() — PyEval_InitThreads() — PyEval_ReleaseLock() — PyEval_ReleaseThread() — PyEval_RestoreThread() — PyEval_SaveThread() — PyEval_ThreadsInitialized() — PyExc_ArithmeticError — PyExc_AssertionError — PyExc_AttributeError - PyExc_BaseException — PyExc_BaseExceptionGroup — PvExc BlockingIOError — PyExc_BrokenPipeError - PyExc BufferError — PyExc_BytesWarning — PyExc_ChildProcessError — PyExc_ConnectionAbortedError — PyExc ConnectionError — PyExc ConnectionRefusedError — PyExc_ConnectionResetError - PyExc_DeprecationWarning — PyExc_EOFError — PyExc_EncodingWarning - PyExc_EnvironmentError - PyExc_Exception — PyExc_FileExistsError — PyExc_FileNotFoundError — PyExc_FloatingPointError - PyExc FutureWarning — PyExc_GeneratorExit

- PyExc IOError

- PyExc_ImportError
- PyExc_ImportWarning
- PyExc_IndentationError
- PyExc_IndexError
- PyExc_InterruptedError
- PyExc_IsADirectoryError
- PyExc KeyError
- PyExc_KeyboardInterrupt
- PyExc_LookupError
- PyExc_MemoryError
- PyExc_ModuleNotFoundError
- PyExc_NameError
- PyExc_NotADirectoryError
- PyExc_NotImplementedError
- PyExc_OSError
- PyExc_OverflowError
- PyExc_PendingDeprecationWarning
- PyExc_PermissionError
- PyExc_ProcessLookupError
- PyExc_RecursionError
- PyExc_ReferenceError
- PyExc_ResourceWarning
- PyExc_RuntimeError
- PyExc_RuntimeWarning
- PyExc_StopAsyncIteration
- PyExc_StopIteration
- PyExc_SyntaxError
- PyExc_SyntaxWarning
- PyExc_SystemError
- PyExc_SystemExit
- PyExc_TabError
- PyExc_TimeoutError
- PyExc_TypeError
- PyExc_UnboundLocalError
- PyExc_UnicodeDecodeError
- PyExc_UnicodeEncodeError
- PyExc_UnicodeError
- PyExc_UnicodeTranslateError
- PyExc_UnicodeWarning
- PyExc_UserWarning
- PyExc ValueError
- PyExc_Warning
- PyExc_WindowsError
- PyExc_ZeroDivisionError
- PyExceptionClass_Name()
- PyException_GetArgs()
- PyException_GetCause()
- PyException_GetContext()
- PyException_GetTraceback()
- PyException_SetArgs()
- PyException_SetCause()
- PyException_SetContext()
- PyException_SetTraceback()
- PyFile FromFd()

```
- PyFile GetLine()
- PyFile_WriteObject()
- PyFile WriteString()
— PyFilter_Type
- PyFloat_AsDouble()
- PyFloat FromDouble()
- PyFloat FromString()
— PyFloat_GetInfo()
— PyFloat_GetMax()
— PyFloat_GetMin()
- PyFloat_Type
- PyFrameObject
— PyFrame_GetCode()
— PyFrame_GetLineNumber()
— PyFrozenSet_New()
— PyFrozenSet_Type
— PyGC_Collect()
- PvGC Disable()
— PyGC_Enable()
— PyGC IsEnabled()
— PyGILState_Ensure()
— PyGILState_GetThisThreadState()
— PyGILState_Release()
- PyGILState STATE
— PyGetSetDef
— PyGetSetDescr_Type
— PyImport_AddModule()
— PyImport_AddModuleObject()
— PyImport_AppendInittab()
— PyImport_ExecCodeModule()
— PyImport_ExecCodeModuleEx()
— PyImport_ExecCodeModuleObject()
— PyImport_ExecCodeModuleWithPathnames()
— PyImport_GetImporter()
— PyImport GetMagicNumber()
— PyImport_GetMagicTag()
- PyImport GetModule()
— PyImport_GetModuleDict()
— PyImport_Import()
— PyImport_ImportFrozenModule()
— PyImport ImportFrozenModuleObject()
— PyImport ImportModule()
— PyImport_ImportModuleLevel()
— PyImport_ImportModuleLevelObject()
— PyImport_ImportModuleNoBlock()
— PyImport_ReloadModule()
— PyIndex_Check()
- PyInterpreterState
— PyInterpreterState_Clear()
— PyInterpreterState_Delete()
— PyInterpreterState_Get()
- PyInterpreterState GetDict()
— PyInterpreterState_GetID()
- PyInterpreterState New()
```

```
— PyIter_Check()
— PyIter_Next()
- PyIter Send()
— PyListIter_Type
— PyListRevIter_Type
- PyList Append()
- PyList AsTuple()
— PyList_GetItem()
— PyList_GetSlice()
— PyList_Insert()
— PyList_New()
- PyList_Reverse()
— PyList_SetItem()
— PyList_SetSlice()
— PyList_Size()
— PyList_Sort()
- PyList_Type
- PvLongObject
— PyLongRangeIter_Type
- PyLong AsDouble()
— PyLong_AsLong()
— PyLong_AsLongAndOverflow()
— PyLong_AsLongLong()
— PyLong AsLongLongAndOverflow()
— PyLong_AsSize_t()
- PyLong_AsSsize_t()
— PyLong_AsUnsignedLong()
— PyLong_AsUnsignedLongLong()
— PyLong_AsUnsignedLongLongMask()
— PyLong_AsUnsignedLongMask()
— PyLong_AsVoidPtr()
— PyLong_FromDouble()
— PyLong_FromLong()
— PyLong_FromLongLong()
- PyLong FromSize t()
— PyLong_FromSsize_t()
- PyLong FromString()
— PyLong_FromUnsignedLong()
— PyLong_FromUnsignedLongLong()
— PyLong_FromVoidPtr()
— PyLong GetInfo()
— PyLong_Type
- PyMap_Type
— PyMapping_Check()
— PyMapping_GetItemString()
— PyMapping_HasKey()
— PyMapping_HasKeyString()
— PyMapping_Items()
— PyMapping_Keys()
— PyMapping_Length()
— PyMapping_SetItemString()
— PyMapping_Size()
— PyMapping_Values()
- PyMem Calloc()
```

- PyMem Free() — PyMem_Malloc() - PyMem Realloc() — PyMemberDef — PyMemberDescr_Type - PyMember GetOne() - PyMember SetOne() — PyMemoryView FromBuffer() — PyMemoryView FromMemory() — PyMemoryView_FromObject() — PyMemoryView_GetContiguous() — PyMemoryView_Type — PyMethodDef — PyMethodDescr_Type — PyModuleDef — PyModuleDef_Base — PyModuleDef_Init() - PyModuleDef Type — PyModule_AddFunctions() - PyModule AddIntConstant() - PyModule_AddObject() - PyModule AddObjectRef() — PyModule_AddStringConstant() — PyModule_AddType() — PyModule_Create2() - PyModule ExecDef() — PyModule_FromDefAndSpec2() — PyModule_GetDef() — PyModule_GetDict() — PyModule_GetFilename() — PyModule_GetFilenameObject() — PyModule_GetName() — PyModule_GetNameObject() — PyModule_GetState() - PyModule New() — PyModule_NewObject() - PyModule SetDocString() — PyModule_Type - PyNumber_Absolute() — PyNumber_Add() - PyNumber And() — PyNumber_AsSsize_t() - PyNumber Check() — PyNumber_Divmod() — PyNumber_Float() — PyNumber_FloorDivide() — PyNumber_InPlaceAdd() — PyNumber_InPlaceAnd() — PyNumber_InPlaceFloorDivide() — PyNumber_InPlaceLshift() — PyNumber_InPlaceMatrixMultiply() — PyNumber_InPlaceMultiply() — PyNumber_InPlaceOr() — PyNumber InPlacePower()

```
— PyNumber_InPlaceRemainder()
— PyNumber_InPlaceRshift()
- PyNumber InPlaceSubtract()
— PyNumber_InPlaceTrueDivide()
— PyNumber_InPlaceXor()
— PyNumber Index()
- PyNumber Invert()
— PyNumber_Long()
— PyNumber_Lshift()
— PyNumber_MatrixMultiply()
— PyNumber_Multiply()
— PyNumber_Negative()
— PyNumber_Or()
- PyNumber_Positive()
— PyNumber_Power()
— PyNumber_Remainder()
— PyNumber_Rshift()
- PyNumber Subtract()
— PyNumber_ToBase()
— PyNumber TrueDivide()
— PyNumber_Xor()
- PyOS AfterFork()
— PyOS_AfterFork_Child()
- PyOS AfterFork Parent()
— PyOS_BeforeFork()
- PyOS_CheckStack()
— PyOS_FSPath()
- PyOS_InputHook
— PyOS_InterruptOccurred()
— PyOS_double_to_string()
- PyOS_getsig()
— PyOS_mystricmp()
— PyOS_mystrnicmp()
— PyOS_setsig()
- PyOS_sighandler_t
— PyOS_snprintf()
- PyOS string to double()
— PyOS_strtol()
— PyOS_strtoul()
— PyOS_vsnprintf()
- PyObject
- PyObject.ob_refcnt
- PyObject.ob_type
— PyObject_ASCII()
— PyObject_AsCharBuffer()
- PyObject_AsFileDescriptor()
— PyObject_AsReadBuffer()
— PyObject_AsWriteBuffer()
— PyObject_Bytes()
— PyObject_Call()
— PyObject_CallFunction()
— PyObject_CallFunctionObjArgs()
— PyObject_CallMethod()
- PyObject CallMethodObjArgs()
```

```
— PyObject_CallNoArgs()
- PyObject_CallObject()
- PyObject Calloc()
— PyObject_CheckBuffer()
— PyObject CheckReadBuffer()
— PyObject ClearWeakRefs()
- PyObject CopyData()
- PyObject DelItem()
— PyObject_DelItemString()
— PyObject_Dir()
— PyObject_Format()
— PyObject_Free()
- PyObject_GC_Del()
— PyObject_GC_IsFinalized()
— PyObject_GC_IsTracked()
— PyObject_GC_Track()
— PyObject_GC_UnTrack()
- PvObject GenericGetAttr()
— PyObject_GenericGetDict()
- PyObject GenericSetAttr()
— PyObject_GenericSetDict()
- PyObject GetAIter()
— PyObject_GetAttr()
— PyObject GetAttrString()
— PyObject_GetBuffer()
- PyObject GetItem()
— PyObject_GetIter()
— PyObject_GetTypeData()
— PyObject_HasAttr()
— PyObject_HasAttrString()
— PyObject_Hash()
— PyObject_HashNotImplemented()
- PyObject_Init()
— PyObject_InitVar()
- PvObject IsInstance()
- PyObject_IsSubclass()
- PyObject IsTrue()
— PyObject_Length()
- PyObject Malloc()
— PyObject_Not()
- PyObject Realloc()
- PyObject Repr()
— PyObject RichCompare()
— PyObject_RichCompareBool()
— PyObject_SelfIter()
— PyObject_SetAttr()
— PyObject_SetAttrString()
— PyObject_SetItem()
— PyObject_Size()
— PyObject_Str()
— PyObject_Type()
— PyObject_Vectorcall()
- PyObject VectorcallMethod()
```

- PyProperty Type

— PyRangeIter_Type - PyRange_Type - PyReversed Type — PySeqIter_New() — PySeqIter_Type - PySequence Check() - PySequence Concat() — PySequence_Contains() — PySequence_Count() — PySequence_DelItem() — PySequence_DelSlice() — PySequence_Fast() — PySequence_GetItem() — PySequence_GetSlice() — PySequence_In() — PySequence_InPlaceConcat() - PySequence_InPlaceRepeat() - PvSequence Index() - PySequence_Length() - PySequence List() - PySequence_Repeat () — PySequence_SetItem() — PySequence_SetSlice() - PySequence Size() - PySequence_Tuple() — PySetIter_Type — PySet_Add() — PySet_Clear() - PySet_Contains() — PySet_Discard() — PySet_New() — PySet_Pop() — PySet_Size() — PySet_Type - PvSlice AdjustIndices() — PySlice_GetIndices() - PySlice GetIndicesEx() — PySlice_New() - PySlice_Type — PySlice_Unpack() - PyState AddModule() - PyState FindModule() - PyState RemoveModule() — PyStructSequence_Desc - PyStructSequence_Field — PyStructSequence_GetItem() — PyStructSequence_New() — PyStructSequence_NewType() — PyStructSequence_SetItem() — PyStructSequence_UnnamedField — PySuper_Type - PySys AddWarnOption() — PySys_AddWarnOptionUnicode()

- PySys AddXOption()

```
— PvSvs FormatStderr()
— PySys_FormatStdout()
- PySys GetObject()
— PySys_GetXOptions()
- PySys HasWarnOptions()
- PySys ResetWarnOptions()
- PySys SetArgv()
— PySys_SetArgvEx()
- PySys_SetObject()
— PySys_SetPath()
— PySys_WriteStderr()
- PySys_WriteStdout()
- PyThreadState
— PyThreadState_Clear()
— PyThreadState_Delete()
— PyThreadState_Get()
— PyThreadState_GetDict()
- PyThreadState GetFrame()
— PyThreadState_GetID()
— PyThreadState GetInterpreter()
— PyThreadState_New()
- PyThreadState SetAsyncExc()
— PyThreadState_Swap()
— PyThread GetInfo()
- PyThread ReInitTLS()
— PyThread_acquire_lock()
— PyThread_acquire_lock_timed()
— PyThread_allocate_lock()
— PyThread_create_key()
— PyThread_delete_key()
— PyThread_delete_key_value()
— PyThread_exit_thread()
— PyThread_free_lock()
— PyThread_get_key_value()
— PyThread_get_stacksize()
— PyThread_get_thread_ident()
- PyThread get thread native id()
— PyThread_init_thread()
— PyThread_release_lock()
— PyThread_set_key_value()
— PyThread set stacksize()
— PyThread_start_new_thread()
— PyThread_tss_alloc()
— PyThread_tss_create()
— PyThread_tss_delete()
— PyThread_tss_free()
— PyThread_tss_get()
— PyThread_tss_is_created()
— PyThread_tss_set()
— PyTraceBack_Here()
— PyTraceBack_Print()
- PyTraceBack_Type
— PyTupleIter_Type
- PyTuple GetItem()
```

```
- PyTuple GetSlice()
— PyTuple_New()
- PyTuple Pack()
— PyTuple_SetItem()
— PyTuple_Size()
- PyTuple Type
- PyTypeObject
— PyType_ClearCache()
— PyType_FromMetaclass()
— PyType_FromModuleAndSpec()
— PyType_FromSpec()
— PyType_FromSpecWithBases()
— PyType_GenericAlloc()
— PyType_GenericNew()
— PyType_GetFlags()
— PyType_GetModule()
— PyType_GetModuleState()
- PyType GetName()
— PyType_GetQualName()
- PyType GetSlot()
— PyType_GetTypeDataSize()
— PyType_IsSubtype()
— PyType_Modified()
— PyType_Ready()
- PyType_Slot
— PyType_Spec
— PyType_Type
— PyUnicodeDecodeError_Create()
— PyUnicodeDecodeError_GetEncoding()
— PyUnicodeDecodeError_GetEnd()
— PyUnicodeDecodeError_GetObject()
— PyUnicodeDecodeError_GetReason()
— PyUnicodeDecodeError_GetStart()
— PyUnicodeDecodeError_SetEnd()
- PyUnicodeDecodeError SetReason()
— PyUnicodeDecodeError_SetStart()
— PyUnicodeEncodeError GetEncoding()
— PyUnicodeEncodeError_GetEnd()
— PyUnicodeEncodeError_GetObject()
— PyUnicodeEncodeError_GetReason()
— PyUnicodeEncodeError GetStart()
— PyUnicodeEncodeError SetEnd()
- PyUnicodeEncodeError SetReason()
— PyUnicodeEncodeError_SetStart()
— PyUnicodeIter_Type
— PyUnicodeTranslateError_GetEnd()
— PyUnicodeTranslateError_GetObject()
— PyUnicodeTranslateError_GetReason()
— PyUnicodeTranslateError_GetStart()
— PyUnicodeTranslateError_SetEnd()
— PyUnicodeTranslateError_SetReason()
— PyUnicodeTranslateError SetStart()
— PyUnicode_Append()
- PyUnicode AppendAndDel()
```

- PyUnicode AsASCIIString() — PyUnicode_AsCharmapString() - PyUnicode AsDecodedObject() — PyUnicode_AsDecodedUnicode() - PyUnicode AsEncodedObject() - PyUnicode AsEncodedString() - PyUnicode AsEncodedUnicode() — PyUnicode AsLatin1String() - PyUnicode AsMBCSString() — PyUnicode_AsRawUnicodeEscapeString() - PyUnicode_AsUCS4() - PyUnicode_AsUCS4Copy() — PyUnicode_AsUTF16String() — PyUnicode_AsUTF32String() — PyUnicode_AsUTF8AndSize() — PyUnicode_AsUTF8String() — PyUnicode_AsUnicodeEscapeString() - PyUnicode AsWideChar() — PyUnicode_AsWideCharString() — PyUnicode BuildEncodingMap() — PyUnicode_Compare() — PyUnicode CompareWithASCIIString() — PyUnicode_Concat() - PyUnicode Contains() - PyUnicode Count() - PyUnicode Decode() - PyUnicode_DecodeASCII() — PyUnicode_DecodeCharmap() — PyUnicode_DecodeCodePageStateful() — PyUnicode_DecodeFSDefault() - PyUnicode_DecodeFSDefaultAndSize() — PyUnicode_DecodeLatin1() — PyUnicode_DecodeLocale() — PyUnicode_DecodeLocaleAndSize() - PyUnicode DecodeMBCS() — PyUnicode_DecodeMBCSStateful() - PyUnicode DecodeRawUnicodeEscape() - PyUnicode_DecodeUTF16() - PyUnicode DecodeUTF16Stateful() — PyUnicode_DecodeUTF32() - PyUnicode DecodeUTF32Stateful() - PyUnicode DecodeUTF7() - PyUnicode DecodeUTF7Stateful() — PyUnicode_DecodeUTF8() - PyUnicode_DecodeUTF8Stateful() — PyUnicode_DecodeUnicodeEscape() — PyUnicode_EncodeCodePage() — PyUnicode_EncodeFSDefault() — PyUnicode_EncodeLocale() - PyUnicode_FSConverter() — PyUnicode_FSDecoder() — PyUnicode_Find() — PyUnicode FindChar() - PyUnicode Format()

```
— PyUnicode_FromEncodedObject()
— PyUnicode_FromFormat()
— PyUnicode FromFormatV()
— PyUnicode_FromObject()
— PyUnicode FromOrdinal()
- PyUnicode FromString()
— PyUnicode FromStringAndSize()
— PyUnicode_FromWideChar()
— PyUnicode_GetDefaultEncoding()
— PyUnicode_GetLength()
— PyUnicode_InternFromString()
— PyUnicode_InternInPlace()
- PyUnicode_IsIdentifier()
— PyUnicode_Join()
— PyUnicode_Partition()
— PyUnicode_RPartition()
— PyUnicode_RSplit()
- PyUnicode ReadChar()
- PyUnicode_Replace()
— PyUnicode_Resize()
— PyUnicode_RichCompare()
— PyUnicode_Split()
- PyUnicode_Splitlines()
- PyUnicode Substring()
- PyUnicode_Tailmatch()
- PyUnicode_Translate()
— PyUnicode_Type
— PyUnicode_WriteChar()
- PyVarObject
— PyVarObject.ob_base
- PyVarObject.ob_size
— PyVectorcall_Call()
- PyVectorcall_NARGS()
— PyWeakReference
— PyWeakref_GetObject()
— PyWeakref_NewProxy()
— PyWeakref NewRef()
— PyWrapperDescr_Type
— PyWrapper_New()
- PyZip_Type
— Py AddPendingCall()
- Py AtExit()
- Py_BEGIN_ALLOW_THREADS
- Py_BLOCK_THREADS
— Py_BuildValue()
— Py_BytesMain()
— Py_CompileString()
— Py_DecRef()
— Py_DecodeLocale()
- Py_END_ALLOW_THREADS
— Py_EncodeLocale()
— Py_EndInterpreter()
— Py_EnterRecursiveCall()
- Py_Exit()
```

```
— Py_FatalError()
— Py_FileSystemDefaultEncodeErrors
— Py_FileSystemDefaultEncoding
— Py_Finalize()
— Py_FinalizeEx()
- Py_GenericAlias()
- Py GenericAliasType
— Py_GetBuildInfo()
— Py_GetCompiler()
— Py_GetCopyright()
— Py_GetExecPrefix()
— Py_GetPath()
— Py_GetPlatform()
— Py_GetPrefix()
— Py_GetProgramFullPath()
— Py_GetProgramName()
— Py_GetPythonHome()
— Py_GetRecursionLimit()
— Py_GetVersion()
- Py_HasFileSystemDefaultEncoding
— Py_IncRef()
— Py_Initialize()
— Py_InitializeEx()
— Py_Is()
— Py_IsFalse()
— Py_IsInitialized()
— Py_IsNone()
— Py_IsTrue()
- Py_LeaveRecursiveCall()
— Py_Main()
— Py_MakePendingCalls()
— Py_NewInterpreter()
— Py_NewRef()
— Py_ReprEnter()
- Py_ReprLeave()
— Py_SetPath()
— Py SetProgramName()
— Py_SetPythonHome()
— Py_SetRecursionLimit()
— Py_UCS4
- Py UNBLOCK THREADS
— Py_UTF8Mode
— Py_VaBuildValue()
- Py_Version
— Py_XNewRef()
— Py_buffer
- Py_intptr_t
- Py_ssize_t
- Py_uintptr_t
— allocfunc
- binaryfunc
- descraetfunc
— descrsetfunc
```

— destructor

- getattrfunc
- getattrofunc
- getbufferproc
- getiterfunc
- getter
- hashfunc
- initproc
- inquiry
- iternextfunc
- lenfunc
- newfunc
- objobjargproc
- objobjproc
- releasebufferproc
- reprfunc
- richcmpfunc
- setattrfunc
- setattrofunc
- setter
- ssizeargfunc
- ssizeobjargproc
- ssizessizeargfunc
- ssizessizeobjargproc
- symtable
- ternaryfunc
- traverseproc
- unaryfunc
- vectorcallfunc
- visitproc

The Very High Level Layer

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are Py_eval_input , Py_file_input , and Py_single_input . These are described following the functions which accept them as parameters.

Note also that several of these functions take FILE* parameters. One particular issue which needs to be handled carefully is that the FILE structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that FILE* parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

int **Py_Main** (int argc, wchar_t **argv)

Part of the Stable ABI. The main program for the standard interpreter. This is made available for programs which embed Python. The argc and argv parameters should be prepared exactly as those which are passed to a C program's main () function (converted to wchar_t according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled SystemExit is raised, this function will not return 1, but exit the process, as long as PyConfig.inspect is zero.

int Py_BytesMain (int argc, char **argv)

Part of the Stable ABI *since version 3.8.* Similar to *Py_Main()* but *argv* is an array of bytes strings. Nouveau dans la version 3.8.

int **PyRun_AnyFile** (FILE *fp, const char *filename)

This is a simplified interface to $PyRun_AnyFileExFlags()$ below, leaving *closeit* set to 0 and *flags* set to NULL.

int PyRun_AnyFileFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

This is a simplified interface to PyRun_AnyFileExFlags() below, leaving the *closeit* argument set to 0.

int PyRun_AnyFileEx (FILE *fp, const char *filename, int closeit)

This is a simplified interface to PyRun_AnyFileExFlags () below, leaving the flags argument set to NULL.

int PyRun_AnyFileExFlags (FILE *fp, const char *filename, int closeit, PyCompilerFlags *flags)

If fp refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of $PyRun_InteractiveLoop()$, otherwise return the result of $PyRun_SimpleFile()$. filename is decoded from the filesystem encoding (sys.getfilesystemencoding()). If filename is NULL, this function uses "???" as the filename. If closeit is true, the file is closed before $PyRun_SimpleFileExFlags()$ returns.

int PyRun_SimpleString (const char *command)

This is a simplified interface to PyRun_SimpleStringFlags() below, leaving the PyCompilerFlags* argument set to NULL.

int PyRun_SimpleStringFlags (const char *command, PyCompilerFlags *flags)

Executes the Python source code from *command* in the __main__ module according to the *flags* argument. If __main__ does not already exist, it is created. Returns 0 on success or -1 if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled SystemExit is raised, this function will not return -1, but exit the process, as long as PyConfig.inspect is zero.

int PyRun_SimpleFile (FILE *fp, const char *filename)

This is a simplified interface to PyRun_SimpleFileExFlags() below, leaving closeit set to 0 and flags set to NULL.

int PyRun_SimpleFileEx (FILE *fp, const char *filename, int closeit)

This is a simplified interface to PyRun_SimpleFileExFlags() below, leaving flags set to NULL.

int PyRun SimpleFileExFlags (FILE *fp, const char *filename, int closeit, PyCompilerFlags *flags)

Similar to PyRun_SimpleStringFlags(), but the Python source code is read from fp instead of an inmemory string. filename should be the name of the file, it is decoded from filesystem encoding and error handler. If closeit is true, the file is closed before PyRun_SimpleFileExFlags() returns.

Note: On Windows, fp should be opened as binary mode (e.g. fopen (filename, "rb")). Otherwise, Python may not handle script file with LF line ending correctly.

int **PyRun_InteractiveOne** (FILE *fp, const char *filename)

This is a simplified interface to PyRun_InteractiveOneFlags() below, leaving flags set to NULL.

int PyRun_InteractiveOneFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the *filesystem encoding and error handler*.

Returns 0 when the input was executed successfully, -1 if there was an exception, or an error code from the errorde.h include file distributed as part of Python if there was a parse error. (Note that errorde.h is not included by Python.h, so must be included specifically if needed.)

int **PyRun_InteractiveLoop** (FILE *fp, const char *filename)

This is a simplified interface to PyRun_InteractiveLoopFlags() below, leaving flags set to NULL.

int PyRun_InteractiveLoopFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the *filesystem encoding and error handler*. Returns 0 at EOF or a negative number upon failure.

int (*PyOS InputHook)(void)

Part of the Stable ABI. Can be set to point to a function with the prototype int func (void). The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the Modules/_tkinter.c in the Python source code.

Modifié dans la version 3.12 : This function is only called from the *main interpreter*.

char *(*PyOS_ReadlineFunctionPointer)(FILE*, FILE*, const char*)

Can be set to point to a function with the prototype char *func(FILE *stdin, FILE *stdout, char *prompt), overriding the default function used to read a single line of input at the interpreter's prompt. The function is expected to output the string *prompt* if it's not NULL, and then read a line of input from the provided standard input file, returning the resulting string. For example, The readline module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by PyMem_RawMalloc() or PyMem_RawRealloc(), or NULL if an error occurred.

Modifié dans la version 3.4 : The result must be allocated by $PyMem_RawMalloc()$ or $PyMem_RawRealloc()$, instead of being allocated by $PyMem_Malloc()$ or $PyMem_Realloc()$.

Modifié dans la version 3.12 : This function is only called from the *main interpreter*.

PyObject *PyRun_String (const char *str, int start, PyObject *globals, PyObject *locals)

Return value : New reference. This is a simplified interface to *PyRun_StringFlags()* below, leaving *flags* set to NULL.

PyObject *PyRun_StringFlags (const char *str, int start, PyObject *globals, PyObject *locals, PyCompilerFlags *flags)

Return value: New reference. Execute Python source code from str in the context specified by the objects globals and locals with the compiler flags specified by flags. globals must be a dictionary; locals can be any object that implements the mapping protocol. The parameter start specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or NULL if an exception was raised.

- PyObject *PyRun_File (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals)

 Return value: New reference. This is a simplified interface to PyRun_FileExFlags() below, leaving closeit set to 0 and flags set to NULL.
- PyObject *PyRun_FileEx (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, int closeit)

 Return value: New reference. This is a simplified interface to PyRun_FileExFlags() below, leaving flags set to NULL.
- PyObject *PyRun_FileFlags (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, PyCompilerFlags *flags)

Return value: New reference. This is a simplified interface to PyRun_FileExFlags() below, leaving closeit set to 0.

PyObject *PyRun_FileExFlags (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, int closeit, PyCompilerFlags *flags)

Return value: New reference. Similar to PyRun_StringFlags(), but the Python source code is read from fp instead of an in-memory string. filename should be the name of the file, it is decoded from the filesystem encoding and error handler. If closeit is true, the file is closed before PyRun_FileExFlags() returns.

PyObject ***Py_CompileString** (const char *str, const char *filename, int start)

Return value: New reference. Part of the Stable ABI. This is a simplified interface to Py_CompileStringFlags() below, leaving flags set to NULL.

- PyObject *Py_CompileStringFlags (const char *str, const char *filename, int start, PyCompilerFlags *flags)

 Return value: New reference. This is a simplified interface to Py_CompileStringExFlags () below, with optimize set to -1.
- PyObject *Py_CompileStringObject (const char *str, PyObject *filename, int start, PyCompilerFlags *flags, int optimize)

Return value: New reference. Parse and compile the Python source code in str, returning the resulting code object. The start token is given by start; this can be used to constrain the code which can be compiled and should be Py_eval_input , Py_file_input , or Py_single_input . The filename specified by filename is used to construct the code object and may appear in tracebacks or SyntaxError exception messages. This returns NULL if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of -1 selects the optimization level of the interpreter as given by -0 options. Explicit levels are 0 (no optimization; ___debug___ is true), 1 (asserts are removed, ___debug___ is false) or 2 (docstrings are removed too).

Nouveau dans la version 3.4.

PyObject *Py_CompileStringExFlags (const char *str, const char *filename, int start, PyCompilerFlags *flags, int optimize)

Return value: New reference. Like Py_CompileStringObject(), but filename is a byte string decoded from the filesystem encoding and error handler.

Nouveau dans la version 3.2.

PyObject *PyEval_EvalCode (PyObject *co, PyObject *globals, PyObject *locals)

Return value : New reference. Part of the Stable ABI. This is a simplified interface to *PyEval_EvalCodeEx()*, with just the code object, and global and local variables. The other arguments are set to NULL.

PyObject *PyEval_EvalCodeEx (PyObject *co, PyObject *globals, PyObject *locals, PyObject *const *args, int argcount, PyObject *const *kws, int kwcount, PyObject *const *defs, int defcount, PyObject *kwdefs, PyObject *closure)

Return value: New reference. Part of the Stable ABI. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for keyword-only arguments and a closure tuple of cells.

PyObject *PyEval EvalFrame (PyFrameObject *f)

Return value: New reference. Part of the Stable ABI. Evaluate an execution frame. This is a simplified interface to $PyEval_EvalFrameEx()$, for backward compatibility.

PyObject *PyEval_EvalFrameEx (PyFrameObject *f, int throwflag)

Return value: New reference. Part of the Stable ABI. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame f is executed, interpreting bytecode and executing calls as needed. The additional throwflag parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the throw () methods of generator objects.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

int PyEval_MergeCompilerFlags (PyCompilerFlags *cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

int Py_eval_input

The start symbol from the Python grammar for isolated expressions; for use with Py_CompileString().

int Py_file_input

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with $Py_CompileString()$. This is the symbol to use when compiling arbitrarily long Python source code.

int Py_single_input

The start symbol from the Python grammar for a single statement; for use with Py_CompileString(). This is the symbol used for the interactive interpreter loop.

struct PyCompilerFlags

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as int flags, and in cases where code is being executed, it is passed as PyCompilerFlags *flags. In this case, from __future__ import can modify flags.

Whenever PyCompilerFlags *flags is NULL, cf_flags is treated as equal to 0, and any modification due to from __future__ import is discarded.

int cf_flags

Compiler flags.

int cf_feature_version

cf_feature_version is the minor Python version. It should be initialized to PY_MINOR_VERSION.

The field is ignored by default, it is used if and only if PyCF_ONLY_AST flag is set in cf_flags.

Modifié dans la version 3.8 : Added *cf_feature_version* field.

int CO_FUTURE_DIVISION

This bit can be set in *flags* to cause division operator / to be interpreted as "true division" according to PEP 238.

CHAPITRE 4

Reference Counting

The functions and macros in this section are used for managing reference counts of Python objects.

```
Py_ssize_t Py_REFCNT (PyObject *o)
```

Get the reference count of the Python object o.

Note that the returned value may not actually reflect how many references to the object are actually held. For example, some objects are "immortal" and have a very high refcount that does not reflect the actual number of references. Consequently, do not rely on the returned value to be accurate, other than a value of 0 or 1.

Use the Py_SET_REFCNT () function to set an object reference count.

Modifié dans la version 3.11 : The parameter type is no longer const PyObject*.

Modifié dans la version 3.10 : Py_REFCNT () is changed to the inline static function.

```
void Py_SET_REFCNT (PyObject *o, Py_ssize_t refcnt)
```

Set the object o reference counter to refent.

Note that this function has no effect on immortal objects.

Nouveau dans la version 3.9.

Modifié dans la version 3.12 : Immortal objects are not modified.

void Py_INCREF (PyObject *o)

Indicate taking a new *strong reference* to object o, indicating it is in use and should not be destroyed.

Cette fonction est souvent utilisée pour convertir une *référence empruntée* en une *référence forte sur place*. La fonction $Py_NewRef()$ peut être utilisée pour créer une nouvelle *référence forte*.

When done using the object, release it by calling Py_DECREF ().

L'objet ne doit pas être NULL, la fonction $Py_XINCREF$ () doit être utilisée s'il est possible qu'il soit NULL.

Do not expect this function to actually modify o in any way. For at least some objects, this function has no effect.

Modifié dans la version 3.12 : Immortal objects are not modified.

void Py_XINCREF (PyObject *o)

Similar to Py_INCREF(), but the object o can be NULL, in which case this has no effect.

Voir aussi Py_XNewRef().

PyObject *Py_NewRef (PyObject *o)

Part of the Stable ABI since version 3.10. Create a new strong reference to an object : call Py_INCREF () on o and return the object o.

When the *strong reference* is no longer needed, Py_DECREF () should be called on it to release the reference.

L'objet o ne doit pas être NULL et la fonction Py_XNewRef () doit être utilisée si o peut être NULL.

Par exemple:

```
Py_INCREF(obj);
self->attr = obj;
```

peut s'écrire :

```
self->attr = Py_NewRef(obj);
```

Voir aussi Py_INCREF().

Nouveau dans la version 3.10.

PyObject *Py_XNewRef (PyObject *o)

Part of the Stable ABI since version 3.10. Semblable à Py_NewRef() mais l'objet o peut être NULL.

Cette fonction renvoie NULL si l'objet o est NULL.

Nouveau dans la version 3.10.

void Py_DECREF (PyObject *o)

Release a *strong reference* to object o, indicating the reference is no longer used.

Once the last *strong reference* is released (i.e. the object's reference count reaches 0), the object's type's deallocation function (which must not be NULL) is invoked.

Cette fonction est généralement utilisée pour supprimer une référence forte avant qu'elle ne soit plus accessible.

L'objet en argument ne doit pas être NULL. Py_XDECREF () doit être utilisée si l'objet peut être NULL.

Do not expect this function to actually modify o in any way. For at least some objects, this function has no effect.

Avertissement : The deallocation function can cause arbitrary Python code to be invoked (e.g. when a class instance with a $_del_$ () method is deallocated). While exceptions in such code are not propagated, the executed code has free access to all Python global variables. This means that any object that is reachable from a global variable should be in a consistent state before Py_DECREF () is invoked. For example, code to delete an object from a list should copy a reference to the deleted object in a temporary variable, update the list data structure, and then call Py_DECREF () for the temporary variable.

Modifié dans la version 3.12 : Immortal objects are not modified.

void Py XDECREF (PyObject *o)

Similar to $Py_DECREF()$, but the object o can be NULL, in which case this has no effect. The same warning from $Py_DECREF()$ applies here as well.

```
void Py_CLEAR (PyObject *o)
```

Release a *strong reference* for object o. The object may be NULL, in which case the macro has no effect; otherwise the effect is the same as for $Py_DECREF()$, except that the argument is also set to NULL. The warning for $Py_DECREF()$ does not apply with respect to the object passed because the macro carefully uses a temporary variable and sets the argument to NULL before releasing the reference.

It is a good idea to use this macro whenever releasing a reference to an object that might be traversed during garbage collection.

Modifié dans la version 3.12 : The macro argument is now only evaluated once. If the argument has side effects, these are no longer duplicated.

```
void Py_IncRef (PyObject *o)
```

Part of the Stable ABI. Indicate taking a new strong reference to object o. A function version of Py_XINCREF(). It can be used for runtime dynamic embedding of Python.

```
void Py_DecRef (PyObject *o)
```

Part of the Stable ABI. Release a strong reference to object o. A function version of Py_XDECREF(). It can be used for runtime dynamic embedding of Python.

Py_SETREF (dst, src)

Macro safely releasing a strong reference to object dst and setting dst to src.

As in case of Py_CLEAR(), "the obvious" code can be deadly:

```
Py_DECREF(dst);
dst = src;
```

The safe way is:

```
Py_SETREF(dst, src);
```

That arranges to set *dst* to *src*_before_ releasing the reference to the old value of *dst*, so that any code triggered as a side-effect of *dst* getting torn down no longer believes *dst* points to a valid object.

Nouveau dans la version 3.6.

Modifié dans la version 3.12 : The macro arguments are now only evaluated once. If an argument has side effects, these are no longer duplicated.

Py_XSETREF (dst, src)

Variant of Py_SETREF macro that uses Py_XDECREF() instead of Py_DECREF().

Nouveau dans la version 3.6.

Modifié dans la version 3.12 : The macro arguments are now only evaluated once. If an argument has side effects, these are no longer duplicated.

CHAPITRE 5

Gestion des exceptions

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX errno variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually NULL if they are supposed to return a pointer, or -1 if they return an integer (exception: the PyArg_* functions return 1 for success and 0 for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be <code>NULL</code> if non-set (although some combinations are forbidden, for example you can't have a non-<code>NULL</code> traceback if the exception type is <code>NULL</code>).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

Note: The error indicator is **not** the result of sys.exc_info(). The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

5.1 Printing and clearing

```
void PyErr_Clear()
```

Part of the Stable ABI. Clear the error indicator. If the error indicator is not set, there is no effect.

```
void PyErr_PrintEx (int set_sys_last_vars)
```

Part of the Stable ABI. Print a standard traceback to sys.stderr and clear the error indicator. Unless the error is a SystemExit, in that case no traceback is printed and the Python process will exit with the error code specified by the SystemExit instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If set_sys_last_vars is nonzero, the variable sys.last_exc is set to the printed exception. For backwards compatibility, the deprecated variables sys.last_type, sys.last_value and sys.last_traceback are also set to the type, value and traceback of this exception, respectively.

Modifié dans la version 3.12 : The setting of sys.last_exc was added.

```
void PyErr_Print()
```

Part of the Stable ABI. Alias for PyErr_PrintEx (1).

```
void PyErr_WriteUnraisable (PyObject *obj)
```

Part of the Stable ABI. Call sys.unraisablehook () using the current exception and obj argument.

This utility function prints a warning message to sys.stderr when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an __del__() method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

An exception must be set when calling this function.

```
void PyErr_DisplayException (PyObject *exc)
```

Part of the Stable ABI since version 3.12. Print the standard traceback display of exc to sys.stderr, including chained exceptions and notes.

Nouveau dans la version 3.12.

5.2 Lever des exceptions

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a NULL pointer for use in a return statement.

```
void PyErr_SetString (PyObject *type, const char *message)
```

Part of the Stable ABI. This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. $PyExc_RuntimeError$. You need not create a new *strong reference* to it (e.g. with $Py_INCREF()$). The second argument is an error message; it is decoded from 'utf-8'.

```
void PyErr_SetObject (PyObject *type, PyObject *value)
```

Part of the Stable ABI. This function is similar to $PyErr_SetString()$ but lets you specify an arbitrary Python object for the "value" of the exception.

```
PyObject *PyErr_Format (PyObject *exception, const char *format, ...)
```

Return value: Always NULL. Part of the Stable ABI. This function sets the error indicator and returns NULL. exception should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in PyUnicode_FromFormat(). format is an ASCII-encoded string.

PyObject *PyErr_FormatV (PyObject *exception, const char *format, va_list vargs)

Return value: Always NULL. Part of the Stable ABI since version 3.5. Same as PyErr_Format(), but taking a va_list argument rather than a variable number of arguments.

Nouveau dans la version 3.5.

void PyErr_SetNone (PyObject *type)

Part of the Stable ABI. This is a shorthand for PyErr_SetObject (type, Py_None).

int PyErr_BadArgument()

Part of the Stable ABI. This is a shorthand for PyErr_SetString(PyExc_TypeError, message), where message indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

PyObject *PyErr_NoMemory()

Return value: Always NULL. Part of the Stable ABI. This is a shorthand for PyErr_SetNone(PyExc_MemoryError); it returns NULL so an object allocation function can write return PyErr_NoMemory(); when it runs out of memory.

PyObject *PyErr_SetFromErrno (PyObject *type)

Return value: Always NULL. Part of the Stable ABI. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable errno. It constructs a tuple object whose first item is the integer errno value and whose second item is the corresponding error message (gotten from strerror()), and then calls PyErr_SetObject(type, object). On Unix, when the errno value is EINTR, indicating an interrupted system call, this calls PyErr_CheckSignals(), and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write return PyErr_SetFromErrno(type); when the system call returns an error.

PyObject *PyErr_SetFromErrnoWithFilenameObject (PyObject *type, PyObject *filenameObject)

Return value: Always NULL. Part of the Stable ABI. Similar to PyErr_SetFromErrno(), with the additional behavior that if filenameObject is not NULL, it is passed to the constructor of type as a third parameter. In the case of OSError exception, this is used to define the filename attribute of the exception instance.

PyObject *PyErr_SetFromErrnoWithFilenameObjects (PyObject *type, PyObject *filenameObject, PyObject *filenameObject2)

Return value: Always NULL. Part of the Stable ABI since version 3.7. Similar to PyErr_SetFromErrnoWithFilenameObject(), but takes a second filename object, for raising errors when a function that takes two filenames fails.

Nouveau dans la version 3.4.

PyObject *PyErr_SetFromErrnoWithFilename (PyObject *type, const char *filename)

Return value: Always NULL. Part of the Stable ABI. Similar to PyErr_SetFromErrnoWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding and error handler.

PyObject *PyErr_SetFromWindowsErr (int ierr)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. This is a convenience function to raise WindowsError. If called with ierr of 0, the error code returned by a call to GetLastError() is used instead. It calls the Win32 function FormatMessage() to retrieve the Windows description of error code given by ierr or GetLastError(), then it constructs a tuple object whose first item is the ierr value and whose second item is the corresponding error message (gotten from FormatMessage()), and then calls PyErr_SetObject(PyExc_WindowsError, object). This function always returns NULL.

Disponibilité: Windows.

PyObject *PyErr_SetExcFromWindowsErr (PyObject *type, int ierr)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr_SetFromWindowsErr(), with an additional parameter specifying the exception type to be raised. Disponibilité: Windows.

PyObject *PyErr_SetFromWindowsErrWithFilename (int ierr, const char *filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr_SetFromWindowsErr(), with the additional behavior that if filename is not NULL, it is decoded from the filesystem encoding (os.fsdecode()) and passed to the constructor of OSError as a third parameter to be used to define the filename attribute of the exception instance.

Disponibilité: Windows.

PyObject *PyErr_SetExcFromWindowsErrWithFilenameObject (PyObject *type, int ierr, PyObject *filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to $PyErr_SetExcFromWindowsErr()$, with the additional behavior that if filename is not NULL, it is passed to the constructor of OSError as a third parameter to be used to define the filename attribute of the exception instance.

Disponibilité: Windows.

PyObject *PyErr_SetExcFromWindowsErrWithFilenameObjects (PyObject *type, int ierr, PyObject *filename, PyObject *filename2)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr_SetExcFromWindowsErrWithFilenameObject(), but accepts a second filename object.

Disponibilité: Windows.

Nouveau dans la version 3.4.

PyObject *PyErr_SetExcFromWindowsErrWithFilename (PyObject *type, int ierr, const char *filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to $PyErr_SetFromWindowsErrWithFilename()$, with an additional parameter specifying the exception type to be raised.

Disponibilité: Windows.

PyObject *PyErr_SetImportError (PyObject *msg, PyObject *name, PyObject *path)

Return value: Always NULL. Part of the Stable ABI since version 3.7. This is a convenience function to raise ImportError. msg will be set as the exception's message string. name and path, both of which can be NULL, will be set as the ImportError's respective name and path attributes.

Nouveau dans la version 3.3.

PyObject *PyErr_SetImportErrorSubclass (PyObject *exception, PyObject *msg, PyObject *name, PyObject *path)

Return value: Always NULL. Part of the Stable ABI since version 3.6. Much like PyErr_SetImportError() but this function allows for specifying a subclass of ImportError to raise.

Nouveau dans la version 3.6.

void PyErr_SyntaxLocationObject (PyObject *filename, int lineno, int col_offset)

Set file, line, and offset information for the current exception. If the current exception is not a SyntaxError, then it sets additional attributes, which make the exception printing subsystem think the exception is a SyntaxError. Nouveau dans la version 3.4.

void PyErr_SyntaxLocationEx (const char *filename, int lineno, int col_offset)

Part of the Stable ABI since version 3.7. Like PyErr_SyntaxLocationObject(), but filename is a byte string decoded from the filesystem encoding and error handler.

Nouveau dans la version 3.2.

void PyErr_SyntaxLocation (const char *filename, int lineno)

Part of the Stable ABI. Like PyErr_SyntaxLocationEx(), but the col_offset parameter is omitted.

void PyErr_BadInternalCall()

Part of the Stable ABI. This is a shorthand for PyErr_SetString (PyExc_SystemError, message), where message indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python warnings module. They normally print a warning message to *sys.stderr*; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example, P_{Y} DECREF () owned references and return an error value).

```
int PyErr_WarnEx (PyObject *category, const char *message, Py_ssize_t stack_level)
```

Part of the Stable ABI. Issue a warning message. The *category* argument is a warning category (see below) or NULL; the *message* argument is a UTF-8 encoded string. *stack_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack_level* of 1 is the function calling PyErr_WarnEx(), 2 is the function above that, and so forth.

Warning categories must be subclasses of PyExc_Warning; PyExc_Warning is a subclass of PyExc_Exception; the default warning category is PyExc_RuntimeWarning. The standard Python warning categories are available as global variables whose names are enumerated at *Standard Warning Categories*.

For information about warning control, see the documentation for the warnings module and the -W option in the command line documentation. There is no C API for warning control.

```
int PyErr_WarnExplicitObject (PyObject *category, PyObject *message, PyObject *filename, int lineno, PyObject *module, PyObject *registry)
```

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function warnings.warn_explicit(); see there for more information. The *module* and *registry* arguments may be set to NULL to get the default effect described there.

Nouveau dans la version 3.4.

int **PyErr_WarnExplicit** (*PyObject* *category, const char *message, const char *filename, int lineno, const char *module, *PyObject* *registry)

Part of the Stable ABI. Similar to PyErr_WarnExplicitObject() except that message and module are UTF-8 encoded strings, and filename is decoded from the filesystem encoding and error handler.

```
int PyErr_WarnFormat (PyObject *category, Py_ssize_t stack_level, const char *format, ...)
```

Part of the Stable ABI. Function similar to PyErr_WarnEx(), but use PyUnicode_FromFormat() to format the warning message. format is an ASCII-encoded string.

Nouveau dans la version 3.2.

```
int PyErr_ResourceWarning (PyObject *source, Py_ssize_t stack_level, const char *format, ...)
```

Part of the Stable ABI since version 3.6. Function similar to <code>PyErr_WarnFormat()</code>, but category is <code>ResourceWarning</code> and it passes source to <code>warnings.WarningMessage()</code>.

Nouveau dans la version 3.6.

5.4 Querying the error indicator

PyObject *PyErr_Occurred()

Return value: Borrowed reference. Part of the Stable ABI. Test whether the error indicator is set. If set, return the exception type (the first argument to the last call to one of the PyErr_Set* functions or to PyErr_Restore()). If not set, return NULL. You do not own a reference to the return value, so you do not need to Py_DECREF() it. The caller must hold the GIL.

Note: Do not compare the return value to a specific exception; use <code>PyErr_ExceptionMatches()</code> instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

int PyErr_ExceptionMatches (PyObject *exc)

Part of the Stable ABI. Equivalent to PyErr_GivenExceptionMatches (PyErr_Occurred(), exc). This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

```
int PyErr GivenExceptionMatches (PyObject *given, PyObject *exc)
```

Part of the Stable ABI. Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

PyObject *PyErr_GetRaisedException (void)

Return value : New reference. Part of the Stable ABI *since version 3.12.* Return the exception currently being raised, clearing the error indicator at the same time.

This function is used by code that needs to catch exceptions, or code that needs to save and restore the error indicator temporarily.

For example:

```
{
    PyObject *exc = PyErr_GetRaisedException();

    /* ... code that might produce other errors ... */
    PyErr_SetRaisedException(exc);
}
```

Voir aussi:

PyErr_GetHandledException(), to save the exception currently being handled.

Nouveau dans la version 3.12.

```
void PyErr_SetRaisedException (PyObject *exc)
```

Part of the Stable ABI since version 3.12. Set exc as the exception currently being raised, clearing the existing exception if one is set.

Avertissement : This call steals a reference to *exc*, which must be a valid exception.

Nouveau dans la version 3.12.

```
void PyErr_Fetch (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)
```

Part of the Stable ABI. Obsolète depuis la version 3.12: Use PyErr_GetRaisedException () instead.

Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to NULL. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be NULL even when the type object is not.

Note: This function is normally only used by legacy code that needs to catch exceptions or save and restore the error indicator temporarily.

For example:

```
{
    PyObject *type, *value, *traceback;
    PyErr_Fetch(&type, &value, &traceback);

    /* ... code that might produce other errors ... */
    PyErr_Restore(type, value, traceback);
}
```

void PyErr_Restore (PyObject *type, PyObject *value, PyObject *traceback)

Part of the Stable ABI. Obsolète depuis la version 3.12: Use PyErr_SetRaisedException() instead.

Set the error indicator from the three objects, *type*, *value*, and *traceback*, clearing the existing exception if one is set. If the objects are NULL, the error indicator is cleared. Do not pass a NULL type and non-NULL value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

Note: This function is normally only used by legacy code that needs to save and restore the error indicator temporarily. Use $PyErr_Fetch()$ to save the current error indicator.

```
void PyErr_NormalizeException (PyObject **exc, PyObject **val, PyObject **tb)
```

Part of the Stable ABI. Obsolète depuis la version 3.12: Use <code>PyErr_GetRaisedException()</code> instead, to avoid any possible de-normalization.

Under certain circumstances, the values returned by <code>PyErr_Fetch()</code> below can be "unnormalized", meaning that <code>*exc</code> is a class object but <code>*val</code> is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

Note: This function *does not* implicitly set the __traceback__ attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
   PyException_SetTraceback(val, tb);
}
```

PyObject *PyErr_GetHandledException (void)

Part of the Stable ABI since version 3.11. Retrieve the active exception instance, as would be returned by sys. exception (). This refers to an exception that was already caught, not to an exception that was freshly raised. Returns a new reference to the exception or NULL. Does not modify the interpreter's exception state.

Note: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr_SetHandledException()</code> to restore or clear the exception state.

Nouveau dans la version 3.11.

void PyErr_SetHandledException (PyObject *exc)

Part of the Stable ABI since version 3.11. Set the active exception, as known from sys.exception(). This refers to an exception that was already caught, not to an exception that was freshly raised. To clear the exception state, pass NULL.

Note: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr_GetHandledException()</code> to get the exception state.

Nouveau dans la version 3.11.

```
void PyErr_GetExcInfo (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)
```

Part of the Stable ABI since version 3.7. Retrieve the old-style representation of the exception info, as known from sys.exc_info(). This refers to an exception that was already caught, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be NULL. Does not modify the exception info state. This function is kept for backwards compatibility. Prefer using PyErr_GetHandledException().

Note: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use $PyErr_SetExcInfo()$ to restore or clear the exception state.

Nouveau dans la version 3.3.

```
void PyErr_SetExcInfo (PyObject *type, PyObject *value, PyObject *traceback)
```

Part of the Stable ABI since version 3.7. Set the exception info, as known from sys.exc_info(). This refers to an exception that was already caught, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass NULL for all three arguments. This function is kept for backwards compatibility. Prefer using PyErr_SetHandledException().

Note: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr_GetExcInfo()</code> to read the exception state.

Nouveau dans la version 3.3.

Modifié dans la version 3.11: The type and traceback arguments are no longer used and can be NULL. The interpreter now derives them from the exception instance (the value argument). The function still steals references of all three arguments.

5.5 Traitement des signaux

int PyErr_CheckSignals()

Part of the Stable ABI. This function interacts with Python's signal handling.

If the function is called from the main thread and under the main Python interpreter, it checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the signal module is supported, this can invoke a signal handler written in Python.

The function attempts to handle all pending signals, and then returns 0. However, if a Python signal handler raises an exception, the error indicator is set and the function returns -1 immediately (such that other pending signals may not have been handled yet: they will be on the next <code>PyErr_CheckSignals()</code> invocation).

If the function is called from a non-main thread, or under a non-main Python interpreter, it does nothing and returns 0.

This function can be called by long-running C code that wants to be interruptible by user requests (such as by pressing Ctrl-C).

Note: The default Python signal handler for SIGINT raises the KeyboardInterrupt exception.

void PyErr_SetInterrupt()

Part of the Stable ABI. Simulate the effect of a SIGINT signal arriving. This is equivalent to PyErr_SetInterruptEx(SIGINT).

Note: This function is async-signal-safe. It can be called without the *GIL* and from a C signal handler.

int PyErr_SetInterruptEx (int signum)

Part of the Stable ABI since version 3.10. Simulate the effect of a signal arriving. The next time PyErr_CheckSignals () is called, the Python signal handler for the given signal number will be called.

This function can be called by C code that sets up its own signal handling and wants Python signal handlers to be invoked as expected when an interruption is requested (for example when the user presses Ctrl-C to interrupt an operation).

If the given signal isn't handled by Python (it was set to signal.SIG_DFL or signal.SIG_IGN), it will be ignored.

If signum is outside of the allowed range of signal numbers, -1 is returned. Otherwise, 0 is returned. The error indicator is never changed by this function.

Note: This function is async-signal-safe. It can be called without the *GIL* and from a C signal handler.

Nouveau dans la version 3.10.

int PySignal_SetWakeupFd (int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. fd must be non-blocking. It returns the previous such file descriptor.

The value -1 disables the feature; this is the initial state. This is equivalent to signal.set_wakeup_fd() in Python, but without any error checking. fd should be a valid file descriptor. The function should only be called from the main thread.

Modifié dans la version 3.5 : On Windows, the function now also supports socket handles.

5.6 Exception Classes

PyObject *PyErr_NewException (const char *name, PyObject *base, PyObject *dict)

Return value: New reference. Part of the Stable ABI. This utility function creates and returns a new exception class. The name argument must be the name of the new exception, a C string of the form module.classname. The base and dict arguments are normally NULL. This creates a class object derived from Exception (accessible in C as PyExc_Exception).

The __module__ attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

PyObject *PyErr_NewExceptionWithDoc (const char *name, const char *doc, PyObject *base, PyObject *dict)

Return value: New reference. Part of the Stable ABI. Same as PyErr_NewException(), except that the new exception class can easily be given a docstring: If doc is non-NULL, it will be used as the docstring for the exception class.

Nouveau dans la version 3.2.

5.7 Objets exception

```
PyObject *PyException_GetTraceback (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI. Return the traceback associated with the exception as a new reference, as accessible from Python through __traceback__. If there is no traceback associated, this returns NULL.

```
int PyException_SetTraceback (PyObject *ex, PyObject *tb)
```

Part of the Stable ABI. Set the traceback associated with the exception to tb. Use Py_None to clear it.

```
PyObject *PyException_GetContext (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI. Return the context (another exception instance during whose handling ex was raised) associated with the exception as a new reference, as accessible from Python through __context__. If there is no context associated, this returns NULL.

```
void PyException_SetContext (PyObject *ex, PyObject *ctx)
```

Part of the Stable ABI. Set the context associated with the exception to *ctx*. Use NULL to clear it. There is no type check to make sure that *ctx* is an exception instance. This steals a reference to *ctx*.

```
PyObject *PyException_GetCause (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI. Return the cause (either an exception instance, or None, set by raise ... from ...) associated with the exception as a new reference, as accessible from Python through __cause__.

```
void PyException SetCause (PyObject *ex, PyObject *cause)
```

Part of the Stable ABI. Set the cause associated with the exception to *cause*. Use NULL to clear it. There is no type check to make sure that *cause* is either an exception instance or None. This steals a reference to *cause*.

```
__suppress_context__ is implicitly set to True by this function.
```

```
PyObject *PyException_GetArgs (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI since version 3.12. Return args of exception ex.

```
void PyException_SetArgs (PyObject *ex, PyObject *args)
```

Part of the Stable ABI since version 3.12. Set args of exception ex to args.

PyObject *PyUnstable_Exc_PrepReraiseStar (PyObject *orig, PyObject *excs)

This is *Unstable API*. It may change without warning in minor releases.

Implement part of the interpreter's implementation of except*. *orig* is the original exception that was caught, and *excs* is the list of the exceptions that need to be raised. This list contains the unhandled part of *orig*, if any, as well as the exceptions that were raised from the except* clauses (so they have a different traceback from *orig*) and those that were reraised (and have the same traceback as *orig*). Return the ExceptionGroup that needs to be reraised in the end, or None if there is nothing to reraise.

Nouveau dans la version 3.12.

5.8 Objets exception Unicode

```
The following functions are used to create and modify Unicode exceptions from C.
PyObject *PyUnicodeDecodeError Create (const char *encoding, const char *object, Py ssize t length,
                                               Py_ssize_t start, Py_ssize_t end, const char *reason)
     Return value: New reference. Part of the Stable ABI. Create a UnicodeDecodeError object with the attributes
     encoding, object, length, start, end and reason. encoding and reason are UTF-8 encoded strings.
PyObject *PyUnicodeDecodeError_GetEncoding (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetEncoding (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the encoding attribute of the given exception object.
PyObject *PyUnicodeDecodeError_GetObject (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetObject (PyObject *exc)
PyObject *PyUnicodeTranslateError_GetObject (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the object attribute of the given exception object.
int PyUnicodeDecodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeEncodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeTranslateError_GetStart (PyObject *exc, Py_ssize_t *start)
     Part of the Stable ABI. Get the start attribute of the given exception object and place it into *start. start must not
     be NULL. Return 0 on success. -1 on failure.
int PyUnicodeDecodeError SetStart (PyObject *exc, Py ssize t start)
int PyUnicodeEncodeError_SetStart (PyObject *exc, Py_ssize_t start)
int PyUnicodeTranslateError_SetStart (PyObject *exc, Py_ssize_t start)
     Part of the Stable ABI. Set the start attribute of the given exception object to start. Return 0 on success, -1 on
     failure.
int PyUnicodeDecodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeEncodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeTranslateError_GetEnd (PyObject *exc, Py_ssize_t *end)
     Part of the Stable ABI. Get the end attribute of the given exception object and place it into *end. end must not be
     NULL. Return 0 on success, -1 on failure.
int PyUnicodeDecodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeEncodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeTranslateError SetEnd (PyObject *exc, Py ssize t end)
     Part of the Stable ABI. Set the end attribute of the given exception object to end. Return 0 on success, -1 on failure.
PyObject *PyUnicodeDecodeError GetReason (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetReason (PyObject *exc)
PyObject *PyUnicodeTranslateError_GetReason (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the reason attribute of the given exception object.
int PyUnicodeDecodeError_SetReason (PyObject *exc, const char *reason)
int PyUnicodeError_SetReason (PyObject *exc, const char *reason)
int PyUnicodeTranslateError_SetReason (PyObject *exc, const char *reason)
     Part of the Stable ABI. Set the reason attribute of the given exception object to reason. Return 0 on success, -1 on
     failure.
```

5.9 Contrôle de la récursion

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically). They are also not needed for *tp_call* implementations because the *call protocol* takes care of recursion handling.

int Py_EnterRecursiveCall (const char *where)

Part of the Stable ABI since version 3.9. Marks a point where a recursive C-level call is about to be performed.

If $USE_STACKCHECK$ is defined, this function checks if the OS stack overflowed using $PyOS_CheckStack$ (). In this is the case, it sets a MemoryError and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a RecursionError is set and a nonzero value is returned. Otherwise, zero is returned.

where should be a UTF-8 encoded string such as " in instance check" to be concatenated to the RecursionError message caused by the recursion depth limit.

Modifié dans la version 3.9: This function is now also available in the *limited API*.

void Py LeaveRecursiveCall (void)

Part of the Stable ABI since version 3.9. Ends a Py_EnterRecursiveCall(). Must be called once for each successful invocation of Py_EnterRecursiveCall().

Modifié dans la version 3.9 : This function is now also available in the *limited API*.

Properly implementing tp_repr for container types requires special recursion handling. In addition to protecting the stack, tp_repr also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to reprlib.recursive_repr().

int Py_ReprEnter (PyObject *object)

Part of the Stable ABI. Called at the beginning of the tp_repr implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the tp_repr implementation should return a string object indicating a cycle. As examples, dict objects return $\{\ldots\}$ and list objects return $[\ldots]$.

The function will return a negative integer if the recursion limit is reached. In that case the tp_repr implementation should typically return NULL.

Otherwise, the function returns zero and the tp_repr implementation can continue normally.

void Py_ReprLeave (PyObject *object)

Part of the Stable ABI. Ends a Py_ReprEnter(). Must be called once for each invocation of Py_ReprEnter() that returns zero.

5.10 Exceptions standards

All standard Python exceptions are available as global variables whose names are $PyExc_$ followed by the Python exception name. These have the type PyObject*; they are all class objects. For completeness, here are all the variables:

Nom C	Nom Python	Notes
PyExc_BaseException	BaseException	1
PyExc_Exception	Exception	page 57, 1
PyExc_ArithmeticError	ArithmeticError	page 57, 1
PyExc_AssertionError	AssertionError	
PyExc_AttributeError	AttributeError	

suite sur la page suivante

Tableau 1 - suite de la page précédente

Nom C	Nom Python	Notes
PyExc_BlockingIOError	BlockingIOError	
PyExc_BrokenPipeError	BrokenPipeError	
PyExc_BufferError	BufferError	
PyExc_ChildProcessError	ChildProcessError	
PyExc_ConnectionAbortedEr	r6pnnectionAbortedError	
PyExc_ConnectionError	ConnectionError	
PyExc_ConnectionRefusedEr	r@pnnectionRefusedError	
PyExc_ConnectionResetErrorConnectionResetError		
PyExc_EOFError	EOFError	
PyExc_FileExistsError	FileExistsError	
PyExc_FloatingPointError	FileNotFoundError	
PyExc_FloatingPointError	FloatingPointError	
PyExc_GeneratorExit	GeneratorExit	
PyExc_ImportError	ImportError	
PyExc_IndentationError	IndentationError	
PyExc_IndexError	IndexError	
PyExc_InterruptedError	InterruptedError	
PyExc_IsADirectoryError	IsADirectoryError	
PyExc_KeyError	KeyError	
PyExc_KeyboardInterrupt	KeyboardInterrupt	
PyExc_LookupError	LookupError	page 57, 1
PyExc_MemoryError	MemoryError	
PyExc_ModuleNotFoundError	ModuleNotFoundError	
PyExc_NameError	NameError	
PyExc_NotADirectoryError	NotADirectoryError	
PyExc_NotImplementedError	NotImplementedError	
PyExc_OSError	OSError	page 57, 1
PyExc_OverflowError	OverflowError	
PyExc_PermissionError	PermissionError	
PyExc_ProcessLookupError	ProcessLookupError	
PyExc_ReferenceError	RecursionError	
PyExc_ReferenceError	ReferenceError	
PyExc_RuntimeError	RuntimeError	
PyExc_StopAsyncIteration	StopAsyncIteration	
PyExc_StopIteration	StopIteration	
PyExc_SyntaxError	SyntaxError	
PyExc_SystemError	SystemError	
PyExc_SystemExit	SystemExit	
PyExc_TabError	TabError	
PyExc_ImportError	TimeoutError	
PyExc_TypeError	TypeError	
PyExc_UnboundLocalError	UnboundLocalError	
PyExc_UnicodeDecodeError	UnicodeDecodeError	
PyExc_UnicodeEncodeError	UnicodeEncodeError	
PyExc_UnicodeError	UnicodeError	
PyExc_UnicodeTranslateErr		
PyExc_ValueError	ValueError	
PyExc_ZeroDivisionError	ZeroDivisionError	

^{1.} C'est la classe de base pour les autres exceptions standards.

Nouveau dans la version 3.3 : PyExc_BlockingIOError, PyExc_BrokenPipeError, PyExc_ChildProcessError, PyExc_ConnectionError, PyExc_ConnectionAbortedError, PyExc_ConnectionRefusedError, PyExc_ConnectionResetError, PyExc_FileExistsError, PyExc_FileNotFoundError, PyExc_InterruptedError, PyExc_IsADirectoryError, PyExc_NotADirectoryError, PyExc_PermissionError, PyExc_ProcessLookupError and PyExc_TimeoutError were introduced following PEP 3151.

Nouveau dans la version 3.5: PyExc_StopAsyncIteration et PyExc_RecursionError.

Nouveau dans la version 3.6: PyExc_ModuleNotFoundError.

These are compatibility aliases to PyExc_OSError:

Nom C	Notes
PyExc_EnvironmentError	
PyExc_IOError	
PyExc_WindowsError	2

Modifié dans la version 3.3 : These aliases used to be separate exception types.

Notes:

5.11 Standard Warning Categories

All standard Python warning categories are available as global variables whose names are $PyExc_followed$ by the Python exception name. These have the type PyObject*; they are all class objects. For completeness, here are all the variables:

Nom C	Nom Python	Notes
PyExc_Warning	Warning	3
PyExc_BytesWarning	BytesWarning	
PyExc_DeprecationWarning	DeprecationWarning	
PyExc_FutureWarning	FutureWarning	
PyExc_ImportWarning	ImportWarning	
PyExc_PendingDeprecationWarning	PendingDeprecationWarning	
PyExc_ResourceWarning	ResourceWarning	
PyExc_RuntimeWarning	RuntimeWarning	
PyExc_SyntaxWarning	SyntaxWarning	
PyExc_UnicodeWarning	UnicodeWarning	
PyExc_UserWarning	UserWarning	

Nouveau dans la version 3.2: PyExc_ResourceWarning.

Notes:

^{2.} Only defined on Windows; protect code that uses this by testing that the preprocessor macro MS_WINDOWS is defined.

^{3.} C'est la classe de base pour les autres catégories de warning.

CHAPITRE 6

Utilitaires

Les fonctions de ce chapitre sont utilitaires, certaines aident à rendre le code en C plus portable, d'autres à utiliser des modules Python depuis du C, analyser des arguments de fonctions, ou encore construire des valeurs Python à partir de valeurs C.

6.1 Operating System Utilities

PyObject *PyOS_FSPath (PyObject *path)

Return value: New reference. Part of the Stable ABI since version 3.6. Return the file system representation for path. If the object is a str or bytes object, then a new strong reference is returned. If the object implements the os.PathLike interface, then __fspath__() is returned as long as it is a str or bytes object. Otherwise TypeError is raised and NULL is returned.

Nouveau dans la version 3.6.

int Py_FdIsInteractive (FILE *fp, const char *filename)

Return true (nonzero) if the standard I/O file fp with name filename is deemed interactive. This is the case for files for which <code>isatty(fileno(fp))</code> is true. If the <code>PyConfig.interactive</code> is non-zero, this function also returns true if the filename pointer is <code>NULL</code> or if the name is equal to one of the strings '<stdin>' or '???'. This function must not be called before Python is initialized.

void PyOS_BeforeFork()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to prepare some internal state before a process fork. This should be called before calling fork() or any similar function that clones the current process. Only available on systems where fork() is defined.

Avertissement: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for $PyOS_BeforeFork$ ().

Nouveau dans la version 3.7.

void PyOS_AfterFork_Parent()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to update some internal state after a process fork. This should be called from the parent process after calling fork() or any similar function that clones the current process, regardless of whether process cloning was successful. Only available on systems where fork() is defined.

Avertissement: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for $PyOS_AfterFork_Parent$ ().

Nouveau dans la version 3.7.

void PyOS_AfterFork_Child()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to update internal interpreter state after a process fork. This must be called from the child process after calling fork(), or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where fork() is defined.

Avertissement: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for $PyOS_AfterFork_Child$ ().

Nouveau dans la version 3.7.

Voir aussi:

os.register_at_fork() allows registering custom Python functions to be called by PyOS_BeforeFork(), PyOS_AfterFork_Parent() and PyOS_AfterFork_Child().

void PyOS_AfterFork()

Part of the Stable ABI on platforms with fork(). Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

Obsolète depuis la version 3.7: This function is superseded by PyOS AfterFork Child().

int PyOS_CheckStack()

Part of the Stable ABI on platforms with USE_STACKCHECK since version 3.7. Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when USE_STACKCHECK is defined (currently on certain versions of Windows using the Microsoft Visual C++ compiler). USE_STACKCHECK will be defined automatically; you should never change the definition in your own code.

PyOS_sighandler_t PyOS_getsig (int i)

Part of the Stable ABI. Return the current signal handler for signal i. This is a thin wrapper around either signation() or signal(). Do not call those functions directly! PyOS_sighandler_t is a typedef alias for void (*)(int).

PyOS_sighandler_t PyOS_setsig (int i, PyOS_sighandler_t h)

Part of the Stable ABI. Set the signal handler for signal i to be h; return the old signal handler. This is a thin wrapper around either signation () or signal (). Do not call those functions directly! PyOS_sighandler_t is a typedef alias for void (*) (int).

wchar_t *Py_DecodeLocale (const char *arg, size_t *size)

Part of the Stable ABI since version 3.7.

Avertissement: This function should not be called directly: use the <code>PyConfig</code> API with the <code>PyConfig_SetBytesString()</code> function which ensures that <code>Python</code> is preinitialized.

This function must not be called before *Python is preinitialized* and so that the LC_CTYPE locale is properly configured : see the *Py_PreInitialize()* function.

Decode a byte string from the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, undecodable bytes are decoded as characters in range U+DC80..U+DCFF; and if a byte sequence can be decoded as a surrogate character, the bytes are escaped using the surrogateescape error handler instead of decoding them.

Return a pointer to a newly allocated wide character string, use <code>PyMem_RawFree()</code> to free the memory. If size is not <code>NULL</code>, write the number of wide characters excluding the null character into <code>*size</code>

Return NULL on decoding error or memory allocation error. If size is not NULL, *size is set to (size_t)-1 on memory error or set to (size_t)-2 on decoding error.

The filesystem encoding and error handler are selected by PyConfig_Read(): see filesystem_encoding and filesystem_errors members of PyConfig.

Decoding errors should never happen, unless there is a bug in the C library.

Use the Py_EncodeLocale() function to encode the character string back to a byte string.

Voir aussi:

 $\begin{tabular}{lll} The & {\it PyUnicode_DecodeFSDefaultAndSize()} & and & {\it PyUnicode_DecodeLocaleAndSize()} \\ functions. \end{tabular}$

Nouveau dans la version 3.5.

Modifié dans la version 3.7 : The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Modifié dans la version 3.8 : The function now uses the UTF-8 encoding on Windows if PyPreConfig. legacy_windows_fs_encoding is zero;

char *Py_EncodeLocale (const wchar_t *text, size_t *error_pos)

Part of the Stable ABI since version 3.7. Encode a wide character string to the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Return a pointer to a newly allocated byte string, use PyMem_Free() to free the memory. Return NULL on encoding error or memory allocation error.

If error_pos is not NULL, *error_pos is set to (size_t)-1 on success, or set to the index of the invalid character on encoding error.

The filesystem encoding and error handler are selected by $PyConfig_Read()$: see filesystem_encoding and filesystem_errors members of $PyConfig_Read()$.

Use the Py DecodeLocale () function to decode the bytes string back to a wide character string.

Avertissement : This function must not be called before *Python is preinitialized* and so that the LC_CTYPE locale is properly configured : see the *Py_PreInitialize()* function.

Voir aussi:

The PyUnicode_EncodeFSDefault() and PyUnicode_EncodeLocale() functions.

Nouveau dans la version 3.5.

Modifié dans la version 3.7: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Modifié dans la version 3.8 : The function now uses the UTF-8 encoding on Windows if PyPreConfig. legacy_windows_fs_encoding is zero.

6.2 System Functions

These are utility functions that make functionality from the sys module accessible to C code. They all work with the current interpreter thread's sys module's dict, which is contained in the internal thread state structure.

PyObject *PySys_GetObject (const char *name)

Return value : Borrowed reference. Part of the Stable ABI. Return the object *name* from the sys module or NULL if it does not exist, without setting an exception.

int PySys_SetObject (const char *name, PyObject *v)

Part of the Stable ABI. Set *name* in the sys module to v unless v is NULL, in which case *name* is deleted from the sys module. Returns 0 on success, -1 on error.

void PySys_ResetWarnOptions()

Part of the Stable ABI. Reset sys.warnoptions to an empty list. This function may be called prior to Py_Initialize().

void PySys_AddWarnOption (const wchar_t *s)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.warnoptions should be used instead, see Python Initialization Configuration.

Append s to sys.warnoptions. This function must be called prior to $Py_Initialize()$ in order to affect the warnings filter list.

Obsolète depuis la version 3.11.

void PySys_AddWarnOptionUnicode (PyObject *unicode)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.warnoptions should be used instead, see Python Initialization Configuration.

Append unicode to sys.warnoptions.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of warnings in $Py_Initialize()$ to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

Obsolète depuis la version 3.11.

void PySys SetPath (const wchar t *path)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig. module_search_paths and PyConfig.module_search_paths_set should be used instead, see Python Initialization Configuration.

Set sys.path to a list object of paths found in *path* which should be a list of paths separated with the platform's search path delimiter (: on Unix, ; on Windows).

Obsolète depuis la version 3.11.

void PySys_WriteStdout (const char *format, ...)

Part of the Stable ABI. Write the output string described by format to sys.stdout. No exceptions are raised, even if truncation occurs (see below).

format should limit the total size of the formatted output string to 1000 bytes or less -- after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted "%s" formats should occur; these should be limited using "%.<N>s" where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for "%f", which can print hundreds of digits for very large numbers.

If a problem occurs, or sys. stdout is unset, the formatted message is written to the real (C level) stdout.

void PySys_WriteStderr (const char *format, ...)

Part of the Stable ABI. As PySys_WriteStdout(), but write to sys.stderr or stderr instead.

void PySys_FormatStdout (const char *format, ...)

Part of the Stable ABI. Function similar to PySys_WriteStdout() but format the message using PyUnicode_FromFormatV() and don't truncate the message to an arbitrary length.

Nouveau dans la version 3.2.

void PySys_FormatStderr (const char *format, ...)

Part of the Stable ABI. As PySys_FormatStdout(), but write to sys.stderr or stderr instead. Nouveau dans la version 3.2.

void PySys_AddXOption (const wchar_t *s)

Part of the Stable ABI since version 3.7. This API is kept for backward compatibility: setting PyConfig. xoptions should be used instead, see Python Initialization Configuration.

Parse s as a set of -X options and add them to the current options mapping as returned by $PySys_GetXOptions()$. This function may be called prior to $Py_Initialize()$.

Nouveau dans la version 3.2.

Obsolète depuis la version 3.11.

PyObject *PySys_GetXOptions()

Return value: Borrowed reference. Part of the Stable ABI since version 3.7. Return the current dictionary of -X options, similarly to sys._xoptions. On error, NULL is returned and an exception is set.

Nouveau dans la version 3.2.

int PySys_Audit (const char *event, const char *format, ...)

Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure. If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from N, the same format characters as used in $Py_BuildValue()$ are available. If the built value is not a tuple, it will be added into a single-element tuple. (The N format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

Note that # format characters should always be treated as Py_ssize_t , regardless of whether $PY_SSIZE_T_CLEAN$ was defined.

sys.audit() performs the same function from Python code.

Nouveau dans la version 3.8.

Modifié dans la version 3.8.2 : Require Py_ssize_t for # format characters. Previously, an unavoidable deprecation warning was raised.

int PySys_AddAuditHook (Py_AuditHookFunction hook, void *userData)

Append the callable *hook* to the list of active auditing hooks. Return zero on success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

This function is safe to call before $Py_Initialize()$. When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from Exception (other errors will not be silenced).

The hook function is of type int (*) (const char *event, PyObject *args, void *userData), where args is guaranteed to be a PyTupleObject. The hook function is always called with the GIL held by the Python interpreter that raised the event.

See PEP 578 for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

Déclenche un événement d'audit sys. addaudithook sans arguments.

Nouveau dans la version 3.8.

6.3 Process Control

void Py_FatalError (const char *message)

Part of the Stable ABI. Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function abort () is called which will attempt to produce a core file.

The Py_FatalError() function is replaced with a macro which logs automatically the name of the current function, unless the Py_LIMITED_API macro is defined.

Modifié dans la version 3.9 : Log the function name automatically.

void Py Exit (int status)

Part of the Stable ABI. Exit the current process. This calls $Py_FinalizeEx()$ and then calls the standard C library function exit (status). If $Py_FinalizeEx()$ indicates an error, the exit status is set to 120.

Modifié dans la version 3.6 : Errors from finalization no longer ignored.

int Py_AtExit (void (*func)())

Part of the Stable ABI. Register a cleanup function to be called by $Py_FinalizeEx()$. The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful, $Py_AtExit()$ returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

6.4 Importer des modules

PyObject *PyImport ImportModule (const char *name)

Return value: New reference. Part of the Stable ABI. This is a simplified interface to PyImport_ImportModuleEx() below, leaving the globals and locals arguments set to NULL and level set to 0. When the name argument contains a dot (when it specifies a submodule of a package), the fromlist argument is set to the list ['*'] so that the return value is the named module rather than the top-level package containing it as would otherwise be the case. (Unfortunately, this has an additional side effect when name in fact specifies a subpackage instead of a submodule: the submodules specified in the package's __all___ variable are loaded.) Return a new reference to the imported module, or NULL with an exception set on failure. A failing import of a module doesn't leave the module in sys.modules.

This function always uses absolute imports.

PyObject *PyImport_ImportModuleNoBlock (const char *name)

Return value: New reference. Part of the Stable ABI. This function is a deprecated alias of PyImport_ImportModule().

Modifié dans la version 3.3 : This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

PyObject *PyImport_ImportModuleEx (const char *name, PyObject *globals, PyObject *locals, PyObject *fromlist)

Return value : New reference. Import a module. This is best described by referring to the built-in Python function __import__().

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for __import__ (), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with PyImport_ImportModule().

PyObject *PyImport_ImportModuleLevelObject (PyObject *name, PyObject *globals, PyObject *locals, PyObject *fromlist, int level)

Return value: New reference. Part of the Stable ABI since version 3.7. Import a module. This is best described by referring to the built-in Python function __import__(), as the standard __import__() function calls this function directly.

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for __import__ (), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Nouveau dans la version 3.3.

PyObject *PyImport_ImportModuleLevel (const char *name, PyObject *globals, PyObject *locals, PyObject *fromlist, int level)

Return value: New reference. Part of the Stable ABI. Similar to PyImport_ImportModuleLevelObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

Modifié dans la version 3.3 : Negative values for *level* are no longer accepted.

PyObject *PyImport_Import (PyObject *name)

Return value: New reference. Part of the Stable ABI. This is a higher-level interface that calls the current "import hook function" (with an explicit level of 0, meaning absolute import). It invokes the __import__() function from the __builtins__ of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

This function always uses absolute imports.

PyObject *PyImport_ReloadModule (PyObject *m)

Return value : New reference. Part of the Stable ABI. Reload a module. Return a new reference to the reloaded module, or NULL with an exception set on failure (the module still exists in this case).

PyObject *PyImport_AddModuleObject (PyObject *name)

Return value: Borrowed reference. Part of the Stable ABI since version 3.7. Return the module object corresponding to a module name. The name argument may be of the form package.module. First check the modules dictionary if there's one there, and if not, create a new one and insert it in the modules dictionary. Return NULL with an exception set on failure.

Note: This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use <code>PyImport_ImportModule()</code> or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

Nouveau dans la version 3.3.

PyObject *PyImport_AddModule (const char *name)

Return value: Borrowed reference. Part of the Stable ABI. Similar to PyImport_AddModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

PyObject *PyImport_ExecCodeModule (const char *name, PyObject *co)

Return value: New reference. Part of the Stable ABI. Given a module name (possibly of the form package. module) and a code object read from a Python bytecode file or obtained from the built-in function compile(), load the module. Return a new reference to the module object, or NULL with an exception set if an error occurred. name is removed from sys.modules in error cases, even if name was already in sys.modules on entry to PyImport_ExecCodeModule(). Leaving incompletely initialized modules in sys.modules is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's __spec__ and __loader__ will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's __loader__ (if set) and to an instance of SourceFileLoader otherwise. The module's __file__ attribute will be set to the code object's co_filename. If applicable, __cached__ will also be set.

This function will reload the module if it was already imported. See <code>PyImport_ReloadModule()</code> for the intended way to reload a module.

If *name* points to a dotted name of the form package.module, any package structures not already created will still not be created.

 $\textbf{See also} \ \textit{PyImport_ExecCodeModuleEx()} \ \ \textbf{and} \ \ \textit{PyImport_ExecCodeModuleWithPathnames()}.$

Modifié dans la version 3.12: The setting of __cached__ and __loader__ is deprecated. See ModuleSpec for alternatives.

PyObject *PyImport_ExecCodeModuleEx (const char *name, PyObject *co, const char *pathname)

Return value: New reference. Part of the Stable ABI. Like PyImport_ExecCodeModule(), but the __file__ attribute of the module object is set to pathname if it is non-NULL.

See also PyImport ExecCodeModuleWithPathnames ().

PyObject *PyImport_ExecCodeModuleObject (PyObject *name, PyObject *co, PyObject *pathname, PyObject *co, PyObject *pathname)

Return value: New reference. Part of the Stable ABI since version 3.7. Like PyImport_ExecCodeModuleEx(), but the __cached__ attribute of the module object is set to cpathname if it is non-NULL. Of the three functions, this is the preferred one to use.

Nouveau dans la version 3.3.

Modifié dans la version 3.12: Setting __cached__ is deprecated. See ModuleSpec for alternatives.

PyObject *PyImport_ExecCodeModuleWithPathnames (const char *name, PyObject *co, const char *pathname, const char *cpathname)

Return value: New reference. Part of the Stable ABI. Like PyImport_ExecCodeModuleObject(), but name, pathname and cpathname are UTF-8 encoded strings. Attempts are also made to figure out what the value for pathname should be from cpathname if the former is set to NULL.

Nouveau dans la version 3.2.

Modifié dans la version 3.3 : Uses imp.source_from_cache() in calculating the source path if only the bytecode path is provided.

Modifié dans la version 3.12 : No longer uses the removed imp module.

long PyImport_GetMagicNumber()

Part of the Stable ABI. Return the magic number for Python bytecode files (a.k.a. .pyc file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns -1 on error.

Modifié dans la version 3.3 : Return value of −1 upon failure.

const char *PyImport_GetMagicTag()

Part of the Stable ABI. Return the magic tag string for PEP 3147 format Python bytecode file names. Keep in mind that the value at sys.implementation.cache_tag is authoritative and should be used instead of this function.

Nouveau dans la version 3.2.

PyObject *PyImport_GetModuleDict()

Return value: Borrowed reference. Part of the Stable ABI. Return the dictionary used for the module administration (a.k.a. sys.modules). Note that this is a per-interpreter variable.

PyObject *PyImport_GetModule (PyObject *name)

Return value : New reference. Part of the Stable ABI *since version 3.8.* Return the already imported module with the given name. If the module has not been imported yet then returns NULL but does not set an error. Returns NULL and sets an error if the lookup failed.

Nouveau dans la version 3.7.

PyObject *PyImport_GetImporter (PyObject *path)

Return value: New reference. Part of the Stable ABI. Return a finder object for a sys.path/pkg.__path_item path, possibly by fetching it from the sys.path_importer_cache dict. If it wasn't yet cached, traverse sys.path_hooks until a hook is found that can handle the path item. Return None if no hook could; this tells our caller that the path based finder could not find a finder for this path item. Cache the result in sys.path_importer_cache. Return a new reference to the finder object.

int PyImport_ImportFrozenModuleObject (PyObject *name)

Part of the Stable ABI since version 3.7. Load a frozen module named name. Return 1 for success, 0 if the module is not found, and -1 with an exception set if the initialization failed. To access the imported module on a successful load, use <code>PyImport_ImportModule()</code>. (Note the misnomer --- this function would reload the module if it was already imported.)

Nouveau dans la version 3.3.

Modifié dans la version 3.4 : The ___file__ attribute is no longer set on the module.

int PyImport_ImportFrozenModule (const char *name)

Part of the Stable ABI. Similar to PyImport_ImportFrozenModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

struct frozen

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see Tools/freeze/ in the Python source distribution). Its definition, found in Include/import.h, is:

```
struct _frozen {
   const char *name;
   const unsigned char *code;
   int size;
   bool is_package;
};
```

Modifié dans la version 3.11: The new is_package field indicates whether the module is a package or not. This replaces setting the size field to a negative value.

const struct _frozen *PyImport_FrozenModules

This pointer is initialized to point to an array of _frozen records, terminated by one whose members are all NULL or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

int PyImport_AppendInittab (const char *name, PyObject *(*initfunc)(void))

Part of the Stable ABI. Add a single module to the existing table of built-in modules. This is a convenience wrapper around <code>PyImport_ExtendInittab()</code>, returning -1 if the table could not be extended. The new module can be imported by the name <code>name</code>, and uses the function <code>initfunc</code> as the initialization function called on the first attempted import. This should be called before <code>Py_Initialize()</code>.

struct _inittab

Structure describing a single entry in the list of built-in modules. Programs which embed Python may use an array of these structures in conjunction with <code>PyImport_ExtendInittab()</code> to provide additional built-in modules. The structure consists of two members:

const char *name

The module name, as an ASCII encoded string.

int PyImport_ExtendInittab (struct _inittab *newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains NULL for the *name* field; failure to provide the sentinel value can result in a memory fault. Returns 0 on success or -1 if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This must be called before *Py_Initialize()*.

If Python is initialized multiple times, PyImport_AppendInittab() or PyImport ExtendInittab() must be called before each Python initialization.

6.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the marshal module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports two versions of the data format: version 0 is the historical version, version 1 shares interned strings in the file, and upon unmarshalling. Version 2 uses a binary format for floating point numbers. Py_MARSHAL_VERSION indicates the current file format (currently 2).

void PyMarshal_WriteLongToFile (long value, FILE *file, int version)

Marshal a long integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native long type. *version* indicates the file format.

This function can fail, in which case it sets the error indicator. Use PyErr_Occurred() to check for that.

void PyMarshal_WriteObjectToFile (PyObject *value, FILE *file, int version)

Marshal a Python object, value, to file. version indicates the file format.

This function can fail, in which case it sets the error indicator. Use PyErr_Occurred() to check for that.

PyObject *PyMarshal_WriteObjectToString (PyObject *value, int version)

Return value: New reference. Return a bytes object containing the marshalled representation of value. version indicates the file format.

The following functions allow marshalled values to be read back in.

long PyMarshal_ReadLongFromFile (FILE *file)

Return a C long from the data stream in a FILE* opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of long.

On error, sets the appropriate exception (EOFError) and returns -1.

int PyMarshal_ReadShortFromFile (FILE *file)

Return a C short from the data stream in a FILE* opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of short.

On error, sets the appropriate exception (EOFError) and returns -1.

PyObject *PyMarshal_ReadObjectFromFile (FILE *file)

Return value: New reference. Return a Python object from the data stream in a FILE* opened for reading. On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject *PyMarshal_ReadLastObjectFromFile (FILE *file)

Return value: New reference. Return a Python object from the data stream in a FILE* opened for reading. Unlike PyMarshal_ReadObjectFromFile(), this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject *PyMarshal_ReadObjectFromString (const char *data, Py_ssize_t len)

Return value: New reference. Return a Python object from the data stream in a byte buffer containing len bytes pointed to by data.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

6.6 Analyse des arguments et construction des valeurs

Ces fonctions sont utiles pour créer vos propres fonctions et méthodes d'extensions. Des informations supplémentaires et des exemples sont disponibles ici : extending-index.

Dans Les trois premières de ces fonctions décrites, <code>PyArg_ParseTuple()</code>, <code>PyArg_ParseTupleAndKeywords()</code>, et <code>PyArg_Parse()</code>, toutes utilisent des chaînes de format qui sont utilisées pour indiquer à la fonction les arguments attendus. Les chaînes de format utilise la même syntaxe pour chacune de ces fonctions.

6.6.1 Analyse des arguments

Une chaîne de format se compose de zéro ou plusieurs "unités de format". Une unité de format décrit un objet Python, elle est généralement composée d'un seul caractère ou d'une séquence d'unités de format entre parenthèses. À quelques exceptions près, une unité de format qui n'est pas une séquence entre parenthèses correspond normalement à un argument d'une seule adresse pour ces fonctions. Dans la description qui suit, la forme entre guillemets est l'unité de format, l'entrée entre parenthèses est le type d'objet Python qui correspond à l'unité de format, et l'entrée entre crochets est le type de la variable C (ou des variables) dont l'adresse doit être donnée.

Chaînes et tampons

Ces formats permettent d'accéder à un objet sous forme d'un fragment de mémoire contiguë. Il n'est pas nécessaire d'allouer la mémoire pour l'*unicode* ou le *bytes* renvoyé.

Sauf indication contraire, les tampons ne se terminent pas par NUL.

There are three ways strings and buffers can be converted to C:

- Formats such as y* and s* fill a Py_buffer structure. This locks the underlying buffer so that the caller can subsequently use the buffer even inside a Py_BEGIN_ALLOW_THREADS block without the risk of mutable data being resized or destroyed. As a result, **you have to call** PyBuffer_Release() after you have finished processing the data (or in any early abort case).
- The es, es#, et and et# formats allocate the result buffer. **You have to call** <code>PyMem_Free()</code> after you have finished processing the data (or in any early abort case).
- Other formats take a str or a read-only bytes-like object, such as bytes, and provide a const char * pointer to its buffer. In this case the buffer is "borrowed": it is managed by the corresponding Python object, and shares the lifetime of this object. You won't have to release any memory yourself.
 - To ensure that the underlying buffer may be safely borrowed, the object's <code>PyBufferProcs.bf_releasebuffer</code> field must be <code>NULL</code>. This disallows common mutable objects such as <code>bytearray</code>, but also some read-only objects such as <code>memoryview</code> of <code>bytes</code>.
 - Besides this bf_releasebuffer requirement, there is no check to verify whether the input object is immutable (e.g. whether it would honor a request for a writable buffer, or whether another thread can mutate the data).

Note: For all # variants of formats (s#, y#, etc.), the macro PY_SSIZE_T_CLEAN must be defined before including Python.h. On Python 3.9 and older, the type of the length argument is Py_ssize_t if the PY_SSIZE_T_CLEAN macro is defined, or int otherwise.

s (str) [const char *] Convertit un objet Unicode en un pointeur vers une chaîne de caractères. S'il s'agit d'un pointeur vers une chaîne de caractères déjà existante, il est stocké dans la variable de type pointeur vers un caractère dont vous avez donné l'adresse. Une chaîne de caractères en C se termine par NULL. La chaîne de caractères Python ne doit donc pas contenir de caractère dont le code est null. Si elle en contient, une exception ValueError est levée. Si la conversion échoue, une UnicodeError est levée.

Note: Ce format n'accepte pas les *objets compatibles avec une chaîne d'octets*. Si vous voulez accepter les chemins du système de fichiers et les convertir vers des chaînes de caractères C, il est préférable d'utiliser le format O& avec <code>PyUnicode_FSConverter()</code> en tant que *converter*.

Modifié dans la version 3.5 : Auparavant, une TypeError était levée quand la chaîne de caractères Python contenait des codes NULL.

- s* (str ou bytes-like object) [Py_buffer] Ce format accepte les objets Unicode et les bytes-like object. Cela remplit une structure Py_buffer qui est fournie par l'appelant. Dans ce cas, la chaîne de caractères C qui en résulte peut contenir des octets NULL. Les objets Unicode sont convertis en chaînes de caractères C en utilisant l'encodage 'utf-8'.
- s# (str, read-only bytes-like object) [const char *, Py_ssize_t] Like s*, except that it provides a borrowed buffer. The result is stored into two C variables, the first one a pointer to a C string, the second one its length. The string may contain embedded null bytes. Unicode objects are converted to C strings using 'utf-8' encoding.
- z (strou None) [const char *] Like s, but the Python object may also be None, in which case the C pointer is set to NULL.
- z* (str, bytes-like object ou None) [Py_buffer] Comme s*, mais l'objet Python peut aussi être None, auquel cas le membre buf, dont la structure est Py_buffer est fixée à NULL.
- z# (str, read-only bytes-like object or None) [const char *, Py_ssize_t] Like s#, but the Python object may also be None, in which case the C pointer is set to NULL.
- y (lecture seule *objet compatible avec une chaîne d'octets*) [constante char *] This format converts a bytes-like object to a C pointer to a *borrowed* character string; it does not accept Unicode objects. The bytes buffer must not contain embedded null bytes; if it does, a ValueError exception is raised.
 - Modifié dans la version 3.5 : Auparavant, TypeError était levée lorsque des octets *null* étaient rencontrés dans le tampon d'octets.
- y* (bytes-like object) [Py_buffer] This variant on s* doesn't accept Unicode objects, only bytes-like objects. This is the recommended way to accept binary data.
- y# (read-only bytes-like object) [const char *, Py_ssize_t] Cette variante de s# n'accepte pas les objets Unicode, uniquement des objets assimilés à des octets.
- **S (bytes)** [PyBytesObject *] Requires that the Python object is a bytes object, without attempting any conversion. Raises TypeError if the object is not a bytes object. The C variable may also be declared as PyObject*.
- Y (bytearray) [PyByteArrayObject *] Requires that the Python object is a bytearray object, without attempting any conversion. Raises TypeError if the object is not a bytearray object. The C variable may also be declared as PyObject*.
- **U**(str)[PyObject *] Requires that the Python object is a Unicode object, without attempting any conversion. Raises TypeError if the object is not a Unicode object. The C variable may also be declared as PyObject*.
- **w*** (**lecture-écriture** *bytes-like object*) [**Py_buffer**] This format accepts any object which implements the readwrite buffer interface. It fills a *Py_buffer* structure provided by the caller. The buffer may contain embedded null bytes. The caller have to call *PyBuffer_Release()* when it is done with the buffer.
- **es** (**str**) [const char *encoding, char **buffer] This variant on s is used for encoding Unicode into a character buffer. It only works for encoded data without embedded NUL bytes.
 - This format requires two arguments. The first is only used as input, and must be a const char* which points to the name of an encoding as a NUL-terminated string, or NULL, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char**; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument.
 - $PyArg_ParseTuple()$ will allocate a buffer of the needed size, copy the encoded data into this buffer and adjust *buffer to reference the newly allocated storage. The caller is responsible for calling $PyMem_Free()$ to free the allocated buffer after use.

- et (str, bytes or bytearray) [const char *encoding, char **buffer] Same as es except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.
- es#(str)[const char *encoding, char **buffer, Py_ssize_t *buffer_length] This variant on s# is used for encoding Unicode into a character buffer. Unlike the es format, this variant allows input data which contains NUL characters.

It requires three arguments. The first is only used as input, and must be a const char* which points to the name of an encoding as a NUL-terminated string, or NULL, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char**; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument. The third argument must be a pointer to an integer; the referenced integer will be set to the number of bytes in the output buffer.

Il existe deux modes de fonctionnement :

If *buffer points a NULL pointer, the function will allocate a buffer of the needed size, copy the encoded data into this buffer and set *buffer to reference the newly allocated storage. The caller is responsible for calling <code>PyMem_Free()</code> to free the allocated buffer after usage.

If *buffer points to a non-NULL pointer (an already allocated buffer), $PyArg_ParseTuple()$ will use this location as the buffer and interpret the initial value of *buffer_length as the buffer size. It will then copy the encoded data into the buffer and NUL-terminate it. If the buffer is not large enough, a ValueError will be set. Dans les deux cas, *buffer_length est la longueur des données encodées, sans l'octet NUL de fin.

et# (str, bytes or bytearray) [const char *encoding, char **buffer, Py_ssize_t *buffer_length]

Same as es# except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

Modifié dans la version 3.12 : u, u#, Z, and Z# are removed because they used a legacy Py_UNICODE* representation.

Les nombres

- **b** (int) [unsigned char] Convert a nonnegative Python integer to an unsigned tiny int, stored in a C unsigned char.
- **B(int)[unsigned char]** Convert a Python integer to a tiny int without overflow checking, stored in a C unsigned char.
- h (int) [short int] Convert a Python integer to a C short int.
- H (int) [unsigned short int] Convert a Python integer to a C unsigned short int, without overflow checking.
- i (int) [int] Convert a Python integer to a plain C int.
- I (int) [unsigned int] Convert a Python integer to a C unsigned int, without overflow checking.
- 1 (int) [long int] Convert a Python integer to a C long int.
- k (int) [unsigned long] Convert a Python integer to a C unsigned long without overflow checking.
- L(int)[long long] Convert a Python integer to a C long long.
- K (int) [unsigned long long] Convert a Python integer to a C unsigned long long without overflow checking.
- n (int) [Py_ssize_t] Convertit un entier Python en un Py_ssize_t.
- c (bytes ou bytearray de longueur 1) [char] Convert a Python byte, represented as a bytes or bytearray object of length 1, to a C char.
 - Modifié dans la version 3.3 : Allow bytearray objects.
- C (str de longueur 1) [int] Convert a Python character, represented as a str object of length 1, to a C int.
- **f (float)** [float] Convert a Python floating point number to a C float.
- d (float) [double] Convert a Python floating point number to a C double.
- D (complex) [Py_complex] Convertit un nombre complexe Python vers une structure Py_complex C.

Autres objets

- O (objet) [PyObject *] Store a Python object (without any conversion) in a C object pointer. The C program thus receives the actual object that was passed. A new *strong reference* to the object is not created (i.e. its reference count is not increased). The pointer stored is not NULL.
- O! (objet) [typeobject, PyObject *] Store a Python object in a C object pointer. This is similar to 0, but takes two C arguments: the first is the address of a Python type object, the second is the address of the C variable (of type PyObject*) into which the object pointer is stored. If the Python object does not have the required type, TypeError is raised.
- **O&** (objet) [converter, anything] Convert a Python object to a C variable through a converter function. This takes two arguments: the first is a function, the second is the address of a C variable (of arbitrary type), converted to void*. The converter function in turn is called as follows:

```
status = converter(object, address);
```

where *object* is the Python object to be converted and *address* is the void* argument that was passed to the PyArg_Parse* function. The returned *status* should be 1 for a successful conversion and 0 if the conversion has failed. When the conversion fails, the *converter* function should raise an exception and leave the content of *address* unmodified.

If the *converter* returns Py_CLEANUP_SUPPORTED, it may get called a second time if the argument parsing eventually fails, giving the converter a chance to release any memory that it had already allocated. In this second call, the *object* parameter will be NULL; *address* will have the same value as in the original call.

Modifié dans la version 3.1 : Py_CLEANUP_SUPPORTED à été ajouté.

p (bool) [int] Tests the value passed in for truth (a boolean predicate) and converts the result to its equivalent C true/false integer value. Sets the int to 1 if the expression was true and 0 if it was false. This accepts any valid Python value. See truth for more information about how Python tests values for truth.

Nouveau dans la version 3.3.

(items) (tuple) [matching-items] L'objet doit être une séquence Python dont la longueur est le nombre d'unités de formats dans articles. Les arguments C doivent correspondre à chaque unité de format particulière dans articles. Les unités de formats pour les séquences peuvent être imbriquées.

It is possible to pass "long" integers (integers whose value exceeds the platform's LONG_MAX) however no proper range checking is done --- the most significant bits are silently truncated when the receiving field is too small to receive the value (actually, the semantics are inherited from downcasts in C --- your mileage may vary).

Quelques autres caractères ont un sens dans une chaîne de format. On ne doit pas les trouvées dans des parenthèses imbriquées. Ce sont :

- Indicates that the remaining arguments in the Python argument list are optional. The C variables corresponding to optional arguments should be initialized to their default value --- when an optional argument is not specified, <code>PyArg_ParseTuple()</code> does not touch the contents of the corresponding C variable(s).
- \$ PyArg_ParseTupleAndKeywords() only: Indicates that the remaining arguments in the Python argument list are keyword-only. Currently, all keyword-only arguments must also be optional arguments, so | must always be specified before \$ in the format string.

Nouveau dans la version 3.3.

- : The list of format units ends here; the string after the colon is used as the function name in error messages (the "associated value" of the exception that PyArg_ParseTuple() raises).
- ; La liste des unités de format s'arrête ici ; la chaîne après le point-virgule est utilise comme message d'erreur *au lieu* du message d'erreur par défaut. : et ; sont mutuellement exclusifs.

Note that any Python object references which are provided to the caller are *borrowed* references; do not release them (i.e. do not decrement their reference count)!

Les arguments additionnels qui sont donnés à ces fonctions doivent être des adresses de variables dont le type est déterminé par la chaîne de format. Elles sont utilisées pour stocker les valeurs du *n*-uplet d'entrée. Il y a quelques cas, comme décrit précédemment dans le liste des unités de formats, où ces paramètres sont utilisés comme valeurs d'entrée. Dans ce cas, ils devraient correspondre à ce qui est spécifié pour l'unité de format correspondante.

For the conversion to succeed, the *arg* object must match the format and the format must be exhausted. On success, the PyArg_Parse* functions return true, otherwise they return false and raise an appropriate exception. When the PyArg_Parse* functions fail due to conversion failure in one of the format units, the variables at the addresses corresponding to that and the following format units are left untouched.

Fonction de l'API

```
int PyArg_ParseTuple (PyObject *args, const char *format, ...)
```

Part of the Stable ABI. Parse the parameters of a function that takes only positional parameters into local variables. Returns true on success; on failure, it returns false and raises the appropriate exception.

```
int PyArg_VaParse (PyObject *args, const char *format, va_list vargs)
```

Part of the Stable ABI. Identical to $PyArg_ParseTuple()$, except that it accepts a va_list rather than a variable number of arguments.

```
int PyArg_ParseTupleAndKeywords (PyObject *args, PyObject *kw, const char *format, char *keywords[], ...)
```

Part of the Stable ABI. Parse the parameters of a function that takes both positional and keyword parameters into local variables. The *keywords* argument is a NULL-terminated array of keyword parameter names. Empty names denote *positional-only parameters*. Returns true on success; on failure, it returns false and raises the appropriate exception.

Modifié dans la version 3.6 : Added support for *positional-only parameters*.

int PyArg_VaParseTupleAndKeywords (*PyObject* *args, *PyObject* *kw, const char *format, char *keywords[], va list vargs)

Part of the Stable ABI. Identical to $PyArg_ParseTupleAndKeywords()$, except that it accepts a va_list rather than a variable number of arguments.

int PyArg_ValidateKeywordArguments (PyObject*)

Part of the Stable ABI. Ensure that the keys in the keywords argument dictionary are strings. This is only needed if PyArg_ParseTupleAndKeywords () is not used, since the latter already does this check.

Nouveau dans la version 3.2.

```
int PyArg_Parse (PyObject *args, const char *format, ...)
```

Part of the Stable ABI. Function used to deconstruct the argument lists of "old-style" functions --- these are functions which use the METH_OLDARGS parameter parsing method, which has been removed in Python 3. This is not recommended for use in parameter parsing in new code, and most code in the standard interpreter has been modified to no longer use this for that purpose. It does remain a convenient way to decompose other tuples, however, and may continue to be used for that purpose.

```
int PyArq_UnpackTuple (PyObject *args, const char *name, Py_ssize_t min, Py_ssize_t max, ...)
```

Part of the Stable ABI. A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as METH_VARARGS in function or method tables. The tuple containing the actual parameters should be passed as args; it must actually be a tuple. The length of the tuple must be at least min and no more than max; min and max may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a PyObject* variable; these will be filled in with the values from args; they will contain borrowed references. The variables which correspond to optional parameters not given by args will not be filled in; these should be initialized by the caller. This function returns true on success and false if args is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

This is an example of the use of this function, taken from the sources for the _weakref helper module for weak references:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

The call to $PyArg_UnpackTuple()$ in this example is entirely equivalent to this call to $PyArg_ParseTuple()$:

```
PyArg_ParseTuple(args, "0|0:ref", &object, &callback)
```

6.6.2 Construction des valeurs

```
PyObject *Py_BuildValue (const char *format, ...)
```

Return value: New reference. Part of the Stable ABI. Create a new value based on a format string similar to those accepted by the PyArg_Parse* family of functions and a sequence of values. Returns the value or NULL in the case of an error; an exception will be raised if NULL is returned.

 $Py_BuildValue()$ does not always build a tuple. It builds a tuple only if its format string contains two or more format units. If the format string is empty, it returns None; if it contains exactly one format unit, it returns whatever object is described by that format unit. To force it to return a tuple of size 0 or one, parenthesize the format string. When memory buffers are passed as parameters to supply data to build objects, as for the s and s# formats, the required data is copied. Buffers provided by the caller are never referenced by the objects created by $Py_BuildValue()$. In other words, if your code invokes malloc() and passes the allocated memory to $Py_BuildValue()$, your code is responsible for calling free() for that memory once $Py_BuildValue()$ returns.

In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that the format unit will return; and the entry in [square] brackets is the type of the C value(s) to be passed.

The characters space, tab, colon and comma are ignored in format strings (but not within format units such as s#). This can be used to make long format strings a tad more readable.

- s (strou None) [const char *] Convert a null-terminated C string to a Python str object using 'utf-8' encoding. If the C string pointer is NULL, None is used.
- **s#** (**str or None**) [**const char ***, **Py_ssize_t**] Convert a C string and its length to a Python str object using 'utf-8' encoding. If the C string pointer is NULL, the length is ignored and None is returned.
- y (bytes) [const char *] This converts a C string to a Python bytes object. If the C string pointer is NULL, None is returned.
- y# (bytes) [const char *, Py_ssize_t] This converts a C string and its lengths to a Python object. If the C string pointer is NULL, None is returned.
- z (strou None) [const char *] Same as s.
- **z#** (str or None) [const char *, Py_ssize_t] Same as s#.
- u (str) [const wchar_t *] Convert a null-terminated wchar_t buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is NULL, None is returned.

u# (str) [const wchar_t *, Py_ssize_t] Convert a Unicode (UTF-16 or UCS-4) data buffer and its length to a Python Unicode object. If the Unicode buffer pointer is NULL, the length is ignored and None is returned.

U(strou None) [const char *] Same as s.

U# (str or None) [const char *, Py_ssize_t] Same as s#.

i (int) [int] Convert a plain C int to a Python integer object.

b (int) [char] Convert a plain C char to a Python integer object.

h (int) [short int] Convert a plain C short int to a Python integer object.

1 (int) [long int] Convert a Clong int to a Python integer object.

B(int)[unsigned char] Convert a Cunsigned char to a Python integer object.

H (int) [unsigned short int] Convert a C unsigned short int to a Python integer object.

I (int) [unsigned int] Convert a C unsigned int to a Python integer object.

k (int) [unsigned long] Convert a C unsigned long to a Python integer object.

L(int)[long long] Convert a Clong long to a Python integer object.

K (int) [unsigned long long] Convert a C unsigned long long to a Python integer object.

n (int) [Py_ssize_t] Convert a C Py_ssize_t to a Python integer.

c (bytes de taille 1) [char] Convert a C int representing a byte to a Python bytes object of length 1.

C (str de longueur 1) [int] Convert a C int representing a character to Python str object of length 1.

d (float) [double] Convert a C double to a Python floating point number.

f (**float**) [**float**] Convert a C float to a Python floating point number.

D (complex) [Py_complex *] Convert a C Py_complex structure to a Python complex number.

O (objet) [PyObject *] Pass a Python object untouched but create a new *strong reference* to it (i.e. its reference count is incremented by one). If the object passed in is a NULL pointer, it is assumed that this was caused because the call producing the argument found an error and set an exception. Therefore, <code>Py_BuildValue()</code> will return <code>NULL</code> but won't raise an exception. If no exception has been raised yet, <code>SystemError</code> is set.

S (objet) [PyObject *] Same as O.

N (objet) [PyObject *] Same as O, except it doesn't create a new *strong reference*. Useful when the object is created by a call to an object constructor in the argument list.

O& (**objet**) [converter, anything] Convert anything to a Python object through a converter function. The function is called with anything (which should be compatible with void*) as its argument and should return a "new" Python object, or NULL if an error occurred.

(items) (tuple) [matching-items] Convert a sequence of C values to a Python tuple with the same number of items.

[items] (list) [matching-items] Convert a sequence of C values to a Python list with the same number of items.

{items} (dict) [matching-items] Convert a sequence of C values to a Python dictionary. Each pair of consecutive C values adds one item to the dictionary, serving as key and value, respectively.

If there is an error in the format string, the SystemError exception is set and NULL returned.

PyObject *Py_VaBuildValue (const char *format, va_list vargs)

Return value: New reference. Part of the Stable ABI. Identical to Py_BuildValue(), except that it accepts a valist rather than a variable number of arguments.

6.7 Conversion et formatage de chaînes

Fonctions de conversion pour les nombres et pour la sortie des chaînes formatées.

```
int PyOS snprintf (char *str, size t size, const char *format, ...)
```

Part of the Stable ABI. Output not more than size bytes to str according to the format string format and the extra arguments. See the Unix man page snprintf(3).

```
int PyOS_vsnprintf (char *str, size_t size, const char *format, va_list va)
```

Part of the Stable ABI. Output not more than size bytes to str according to the format string format and the variable argument list va. Unix man page vsnprintf(3).

PyOS_snprintf() and PyOS_vsnprintf() wrap the Standard C library functions snprintf() and vsnprintf(). Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

The wrappers ensure that str[size-1] is always '\0' upon return. They never write more than size bytes (including the trailing '\0') into str. Both functions require that str != NULL, size > 0, format != NULL and $size < INT_MAX$. Note that this means there is no equivalent to the C99 n = snprintf(NULL, 0, ...) which would determine the necessary buffer size.

The return value (rv) for these functions should be interpreted as follows:

- When 0 <= rv < size, the output conversion was successful and rv characters were written to str (excluding the trailing '\0' byte at str[rv]).
- When rv >= size, the output conversion was truncated and a buffer with rv + 1 bytes would have been needed to succeed. str[size-1] is '\0' in this case.
- When rv < 0, "something bad happened." str[size-1] is '\0' in this case too, but the rest of *str* is undefined. The exact cause of the error depends on the underlying platform.

The following functions provide locale-independent string to number conversions.

```
double PyOS_string_to_double (const char *s, char **endptr, PyObject *overflow_exception)
```

Part of the Stable ABI. Convert a string s to a double, raising a Python exception on failure. The set of accepted strings corresponds to the set of strings accepted by Python's float () constructor, except that s must not have leading or trailing whitespace. The conversion is independent of the current locale.

If endptr is NULL, convert the whole string. Raise ValueError and return -1.0 if the string is not a valid representation of a floating-point number.

If endptr is not NULL, convert as much of the string as possible and set *endptr to point to the first unconverted character. If no initial segment of the string is the valid representation of a floating-point number, set *endptr to point to the beginning of the string, raise ValueError, and return -1.0.

If s represents a value that is too large to store in a float (for example, "1e500" is such a string on many platforms) then if overflow_exception is NULL return Py_HUGE_VAL (with an appropriate sign) and don't set any exception. Otherwise, overflow_exception must point to a Python exception object; raise that exception and return -1.0. In both cases, set *endptr to point to the first character after the converted value.

If any other error occurs during the conversion (for example an out-of-memory error), set the appropriate Python exception and return -1.0.

Nouveau dans la version 3.1.

char *PyOS double to string (double val, char format_code, int precision, int flags, int *ptype)

Part of the Stable ABI. Convert a double val to a string using supplied format_code, precision, and flags.

 $format_code$ must be one of 'e', 'E', 'f', 'F', 'g', 'G' or 'r'. For 'r', the supplied precision must be 0 and is ignored. The 'r' format code specifies the standard repr() format.

flags can be zero or more of the values Py_DTSF_SIGN, Py_DTSF_ADD_DOT_0, or Py_DTSF_ALT, or-ed together:

- Py_DTSF_SIGN means to always precede the returned string with a sign character, even if val is non-negative.
- Py_DTSF_ADD_DOT_0 means to ensure that the returned string will not look like an integer.

— Py_DTSF_ALT means to apply "alternate" formatting rules. See the documentation for the PyOS_snprintf() '#' specifier for details.

If *ptype* is non-NULL, then the value it points to will be set to one of Py_DTST_FINITE, Py_DTST_INFINITE, or Py_DTST_NAN, signifying that *val* is a finite number, an infinite number, or not a number, respectively.

The return value is a pointer to *buffer* with the converted string or NULL if the conversion failed. The caller is responsible for freeing the returned string by calling <code>PyMem_Free()</code>.

Nouveau dans la version 3.1.

int PyOS_stricmp (const char *s1, const char *s2)

Case insensitive comparison of strings. The function works almost identically to stromp () except that it ignores the case.

```
int PyOS_strnicmp (const char *s1, const char *s2, Py_ssize_t size)
```

Case insensitive comparison of strings. The function works almost identically to strncmp () except that it ignores the case.

6.8 Réflexion

PyObject *PyEval_GetBuiltins (void)

Return value : Borrowed reference. Part of the Stable ABI. Renvoie un dictionnaire des fonctions natives de la frame en cours d'exécution, ou si aucune frame n'est exécutée, les fonctions natives du thread indiqué par le thread state.

PyObject *PyEval_GetLocals (void)

Return value : Borrowed reference. Part of the Stable ABI. Return a dictionary of the local variables in the current execution frame, or NULL if no frame is currently executing.

PyObject *PyEval_GetGlobals (void)

Return value : Borrowed reference. Part of the Stable ABI. Return a dictionary of the global variables in the current execution frame, or NULL if no frame is currently executing.

PyFrameObject *PyEval_GetFrame (void)

Return value : Borrowed reference. Part of the Stable ABI. Return the current thread state's frame, which is NULL if no frame is currently executing.

See also PyThreadState_GetFrame().

const char *PyEval GetFuncName (PyObject *func)

Part of the Stable ABI. Renvoie le nom de func s'il s'agit d'une fonction, d'une classe ou d'un objet d'instance, sinon le nom du type de func

const char *PyEval_GetFuncDesc (PyObject *func)

Part of the Stable ABI. Renvoie une description en chaîne de caractères, en fonction du type de func. Les valeurs renvoyées peuvent être " () " pour les fonction et les méthodes, \" constructor\", \" instance\", \" object\". Concaténé avec le résultat de PyEval_GetFuncName (), le résultat sera une description de func

6.8. Réflexion 77

6.9 Codec registry and support functions

int PyCodec_Register (PyObject *search_function)

Part of the Stable ABI. Register a new codec search function.

As side effect, this tries to load the encodings package, if not yet done, to make sure that it is always first in the list of search functions.

int PyCodec_Unregister (PyObject *search_function)

Part of the Stable ABI since version 3.10. Unregister a codec search function and clear the registry's cache. If the search function is not registered, do nothing. Return 0 on success. Raise an exception and return -1 on error. Nouveau dans la version 3.10.

int PyCodec_KnownEncoding (const char *encoding)

Part of the Stable ABI. Return 1 or 0 depending on whether there is a registered codec for the given *encoding*. This function always succeeds.

PyObject *PyCodec_Encode (PyObject *object, const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Generic codec based encoding API.

object is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

PyObject *PyCodec_Decode (PyObject *object, const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Generic codec based decoding API.

object is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

6.9.1 Codec lookup API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a KeyError is set and NULL returned.

PyObject *PyCodec_Encoder (const char *encoding)

Return value: New reference. Part of the Stable ABI. Get an encoder function for the given encoding.

PyObject *PyCodec Decoder (const char *encoding)

Return value: New reference. Part of the Stable ABI. Get a decoder function for the given encoding.

PyObject *PyCodec_IncrementalEncoder (const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Get an IncrementalEncoder object for the given encoding.

PyObject *PyCodec_IncrementalDecoder (const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Get an IncrementalDecoder object for the given encoding.

PyObject *PyCodec_StreamReader (const char *encoding, PyObject *stream, const char *errors)

Return value: New reference. Part of the Stable ABI. Get a StreamReader factory function for the given encoding.

PyObject *PyCodec_StreamWriter (const char *encoding, PyObject *stream, const char *errors)

Return value: New reference. Part of the Stable ABI. Get a StreamWriter factory function for the given encoding.

6.9.2 Registry API for Unicode encoding error handlers

int PyCodec_RegisterError (const char *name, PyObject *error)

Part of the Stable ABI. Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of UnicodeEncodeError, UnicodeDecodeError or UnicodeTranslateError that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Objets exception Unicode* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

Return 0 on success, -1 on error.

PyObject *PyCodec_LookupError (const char *name)

Return value : New reference. Part of the Stable ABI. Lookup the error handling callback function registered under *name.* As a special case NULL can be passed, in which case the error handling callback for "strict" will be returned.

PyObject *PyCodec_StrictErrors (PyObject *exc)

Return value: Always NULL. Part of the Stable ABI. Raise exc as an exception.

PyObject *PyCodec_IgnoreErrors (PyObject *exc)

Return value: New reference. Part of the Stable ABI. Ignore the unicode error, skipping the faulty input.

PyObject *PyCodec_ReplaceErrors (PyObject *exc)

Return value: New reference. Part of the Stable ABI. Replace the unicode encode error with? or U+FFFD.

PyObject *PyCodec_XMLCharRefReplaceErrors (PyObject *exc)

Return value: New reference. Part of the Stable ABI. Replace the unicode encode error with XML character references.

PyObject *PyCodec_BackslashReplaceErrors (PyObject *exc)

Return value: New reference. Part of the Stable ABI. Replace the unicode encode error with backslash escapes ($\xspace x$, $\astrue u$ and $\astrue U$).

PyObject *PyCodec_NameReplaceErrors (PyObject *exc)

Return value: New reference. Part of the Stable ABI since version 3.7. Replace the unicode encode error with $N\{...\}$ escapes.

Nouveau dans la version 3.5.

6.10 Support for Perf Maps

On supported platforms (as of this writing, only Linux), the runtime can take advantage of *perf map files* to make Python functions visible to an external profiling tool (such as perf). A running process may create a file in the /tmp directory, which contains entries that can map a section of executable code to a name. This interface is described in the documentation of the Linux Perf tool.

In Python, these helper APIs can be used by libraries and features that rely on generating machine code on the fly.

Note that holding the Global Interpreter Lock (GIL) is not required for these APIs.

int PyUnstable_PerfMapState_Init (void)

This is *Unstable API*. It may change without warning in minor releases.

Open the /tmp/perf-\$pid.map file, unless it's already opened, and create a lock to ensure thread-safe writes to the file (provided the writes are done through <code>PyUnstable_WritePerfMapEntry()</code>). Normally, there's no need to call this explicitly; just use <code>PyUnstable_WritePerfMapEntry()</code> and it will initialize the state on first call.

Returns 0 on success, -1 on failure to create/open the perf map file, or -2 on failure to create a lock. Check errno for more information about the cause of a failure.

This is *Unstable API*. It may change without warning in minor releases.

Write one single entry to the /tmp/perf-pid.map file. This function is thread safe. Here is what an example entry looks like:

Will call PyUnstable_PerfMapState_Init() before writing the entry, if the perf map file is not already opened. Returns 0 on success, or the same error codes as PyUnstable_PerfMapState_Init() on failure.

void PyUnstable_PerfMapState_Fini (void)

This is *Unstable API*. It may change without warning in minor releases.

Close the perf map file opened by <code>PyUnstable_PerfMapState_Init()</code>. This is called by the runtime itself during interpreter shut-down. In general, there shouldn't be a reason to explicitly call this, except to handle specific scenarios such as forking.

Couche d'abstraction des objets

Dans ce chapitre, les fonctions s'appliquent à des objets Python sans tenir compte de leur type, ou des classes d'objets au sens large (par exemple, tous les types numériques, ou tous les types de séquence). Quand ils sont utilisés sur des types d'objets qui ne correspondent pas, ils lèveront une exception Python.

Il n'est pas possible d'utiliser ces fonctions sur des objets qui n'ont pas été correctement initialisés, comme un objet liste qui a été créé avec <code>PyList_New()</code> mais dont les éléments n'ont pas encore été mis à une valeur non-NULL.

7.1 Protocole Objet

PyObject *Py_NotImplemented

Le singleton Not Implemented, utilisé pour signaler qu'une opération n'est pas implémentée pour la combinaison de types en question.

Py_RETURN_NOTIMPLEMENTED

Properly handle returning Py_NotImplemented from within a C function (that is, create a new *strong reference* to NotImplemented and return it).

int PyObject_Print (PyObject *o, FILE *fp, int flags)

Print an object o, on file fp. Returns -1 on error. The flags argument is used to enable certain printing options. The only option currently supported is Py_PRINT_RAW; if given, the str() of the object is written instead of the repr().

int PyObject_HasAttr (PyObject *o, PyObject *attr_name)

Part of the Stable ABI. Renvoie 1 si *o* a l'attribut *attr_name*, et 0 sinon. Ceci est équivalent à l'expression Python hasattr(o, attr_name). Cette fonction réussit toujours.

Note: Exceptions that occur when this calls __getattr__() and __getattribute__() methods are silently ignored. For proper error handling, use PyObject_GetAttr() instead.

int PyObject_HasAttrString (*PyObject* *o, const char *attr_name)

Part of the Stable ABI. This is the same as PyObject_HasAttr(), but attr_name is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

Note: Exceptions that occur when this calls $__getattr__()$ and $__getattribute__()$ methods or while creating the temporary str object are silently ignored. For proper error handling, use $PyObject_GetAttrString()$ instead.

PyObject *PyObject_GetAttr (PyObject *o, PyObject *attr_name)

Return value : New reference. Part of the Stable ABI. Retrieve an attribute named *attr_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression o .attr name.

PyObject *PyObject_GetAttrString (PyObject *o, const char *attr_name)

Return value: New reference. Part of the Stable ABI. This is the same as PyObject_GetAttr(), but attr_name is specified as a const_char* UTF-8 encoded bytes string, rather than a PyObject*.

PyObject *PyObject_GenericGetAttr(PyObject *o, PyObject *name)

Return value: New reference. Part of the Stable ABI. Accesseur d'attribut générique destiné à être mis dans le slot tp_getattro d'un objet type. Recherche un descripteur dans le dictionnaire de classes du MRO de l'objet ainsi qu'un attribut dans le __dict__ de l'objet (si présent). Comme défini dans descriptors, les descripteurs de données sont prioritaires sur les attributs d'instance, contrairement aux autres descripteurs. Sinon, une AttributeError est levée.

int PyObject_SetAttr (PyObject *o, PyObject *attr_name, PyObject *v)

Part of the Stable ABI. Définit la valeur de l'attribut nommé $attr_name$, pour l'objet o, à la valeur v. Lève une exception et renvoie -1 en cas d'échec; renvoie 0 en cas de succès. Ceci est équivalent à l'instruction Python $o.attr_name = v$.

If v is NULL, the attribute is deleted. This behaviour is deprecated in favour of using $PyObject_DelAttr()$, but there are currently no plans to remove it.

int PyObject_SetAttrString (PyObject *o, const char *attr_name, PyObject *v)

Part of the Stable ABI. This is the same as PyObject_SetAttr(), but attr_name is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

If v is NULL, the attribute is deleted, but this feature is deprecated in favour of using $PyObject_DelAttrString()$.

int PyObject_GenericSetAttr (PyObject *o, PyObject *name, PyObject *value)

Part of the Stable ABI. Accesseur et suppresseur générique d'attributs qui est fait pour être mis dans le tp_setattro d'un objet type. Il cherche un descripteur de données dans le dictionnaire de classes dans le MRO de l'objet et, si ce descripteur est trouvé, c'est lui qui est utilisé de préférence pour la suppression et la définition de l'attribut dans le dictionnaire d'instance. Sinon, l'attribut est défini ou supprimé dans le __dict__ de l'objet (si présent). En cas de succès, 0 est renvoyé, sinon une AttributeError est levée et -1 est renvoyé.

int PyObject_DelAttr(PyObject *o, PyObject *attr_name)

Supprime l'attribut nommé $attr_name$, pour l'objet o. Renvoie -1 en cas d'échec. Ceci est l'équivalent de l'expression Python del o.attr_name.

int PyObject_DelAttrString (PyObject *o, const char *attr_name)

This is the same as $PyObject_DelAttr()$, but $attr_name$ is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

PyObject *PyObject_GenericGetDict (PyObject *o, void *context)

Return value : New reference. Part of the Stable ABI since version 3.10. Une implémentation générique de l'accesseur d'un descripteur d'un ___dict___. Crée le dictionnaire si nécessaire.

This function may also be called to get the <u>__dict__</u> of the object o. Pass NULL for *context* when calling it. Since this function may need to allocate memory for the dictionary, it may be more efficient to call <code>PyObject_GetAttr()</code> when accessing an attribute on the object.

On failure, returns NULL with an exception set.

Nouveau dans la version 3.3.

int PyObject_GenericSetDict (PyObject *o, PyObject *value, void *context)

Part of the Stable ABI since version 3.7. Une implémentation générique du mutateur d'un descripteur de __dict__. Cette implémentation n'autorise pas la suppression du dictionnaire.

Nouveau dans la version 3.3.

PyObject **_PyObject_GetDictPtr(PyObject *obj)

Return a pointer to __dict__ of the object *obj*. If there is no __dict__, return NULL without setting an exception.

This function may need to allocate memory for the dictionary, so it may be more efficient to call $PyObject_GetAttr()$ when accessing an attribute on the object.

PyObject *PyObject RichCompare (PyObject *o1, PyObject *o2, int opid)

Return value: New reference. Part of the Stable ABI. Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py_LT , Py_LE , Py_EQ , Py_NE , Py_GT , or Py_GE , corresponding to <, <=, ==, !=, >, or >= respectively. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid. Returns the value of the comparison on success, or NULL on failure.

int PyObject_RichCompareBool (PyObject *o1, PyObject *o2, int opid)

Part of the Stable ABI. Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py_LT , Py_LE , Py_EQ , Py_NE , Py_GT , or Py_GE , corresponding to <, <=, ==, !=, >, or >= respectively. Returns -1 on error, 0 if the result is false, 1 otherwise. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid.

Note: If ol and o2 are the same object, $PyObject_RichCompareBool()$ will always return 1 for Py_EQ and 0 for Py_NE .

PyObject *PyObject Format (PyObject *obj, PyObject *format spec)

Part of the Stable ABI. Format obj using format_spec. This is equivalent to the Python expression format (obj, format_spec).

format_spec may be NULL. In this case the call is equivalent to format (obj). Returns the formatted string on success, NULL on failure.

PyObject *PyObject_Repr (PyObject *o)

Return value: New reference. Part of the Stable ABI. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression repr (o). Called by the repr() built-in function.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

PyObject *PyObject_ASCII (PyObject *o)

Return value : New reference. Part of the Stable ABI. Comme $PyObject_Repr()$, calcule une représentation en chaîne de caractères de l'objet o, mais échappe les caractères non ASCII dans la chaîne de caractères renvoyée par $PyObject_Repr()$ avec' \x , \u ou \U . Cela génère une chaîne de caractères similaire à celle renvoyée par $PyObject_Repr()$ en Python 2. Appelée par la fonction native ascii().

PyObject *PyObject_Str (PyObject *o)

Return value: New reference. Part of the Stable ABI. Compute a string representation of object o. Returns the string

representation on success, NULL on failure. This is the equivalent of the Python expression str(0). Called by the str() built-in function and, therefore, by the print() function.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

PyObject *PyObject_Bytes (PyObject *o)

Return value: New reference. Part of the Stable ABI. Compute a bytes representation of object o. NULL is returned on failure and a bytes object on success. This is equivalent to the Python expression bytes (o), when o is not an integer. Unlike bytes (o), a TypeError is raised when o is an integer instead of a zero-initialized bytes object.

int PyObject_IsSubclass (PyObject *derived, PyObject *cls)

Part of the Stable ABI. Renvoie 1 si la classe derived est identique à ou dérivée de la classe cls, renvoie 0 sinon. En cas d'erreur, renvoie -1.

Si *cls* est un *n*-uplet, la vérification est menée sur chaque entrée de *cls*. Le résultat sera 1 quand au moins une des vérifications renvoie 1, sinon ce sera 0.

Si *cls* a une méthode __subclasscheck__(), elle est appelée pour déterminer le statut de la sous-classe comme décrit dans PEP 3119. Sinon, *derived* est une sous-classe de *cls* si c'est une sous-classe directe ou indirecte, c'est-à-dire contenue dans cls.__mro__.

Normally only class objects, i.e. instances of type or a derived class, are considered classes. However, objects can override this by having a __bases__ attribute (which must be a tuple of base classes).

int PyObject_IsInstance (PyObject *inst, PyObject *cls)

Part of the Stable ABI. Renvoie 1 si inst est une instance de la classe cls ou une sous-classe de cls, ou 0 sinon. En cas d'erreur, renvoie -1 et initialise une exception.

Si *cls* est un *n*-uplet, la vérification est menée sur chaque entrée de *cls*. Le résultat sera 1 quand au moins une des vérifications renvoie 1, sinon ce sera 0.

Si *cls* a une méthode __subclasscheck__(), elle sera appelée pour déterminer le statut de la sous-classe comme décrit dans PEP 3119. Sinon, *inst* est une instance *cls* si sa classe est une sous-classe de *cls*.

An instance inst can override what is considered its class by having a __class__ attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a __bases__ attribute (which must be a tuple of base classes).

Py_hash_t PyObject_Hash (PyObject *o)

Part of the Stable ABI. Compute and return the hash value of an object o. On failure, return -1. This is the equivalent of the Python expression hash (o).

Modifié dans la version 3.2 : The return type is now Py_hash_t. This is a signed integer the same size as Py_ssize_t .

Py_hash_t PyObject_HashNotImplemented (PyObject *o)

Part of the Stable ABI. Set a TypeError indicating that type (0) is not hashable and return -1. This function receives special treatment when stored in a tp_hash slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

int PyObject_IsTrue (PyObject *o)

Part of the Stable ABI. Returns 1 if the object o is considered to be true, and 0 otherwise. This is equivalent to the Python expression not not o. On failure, return -1.

int PyObject_Not (PyObject *o)

Part of the Stable ABI. Returns 0 if the object o is considered to be true, and 1 otherwise. This is equivalent to the Python expression not o. On failure, return -1.

PyObject *PyObject Type (PyObject *o)

Return value: New reference. Part of the Stable ABI. When o is non-NULL, returns a type object corresponding to the object type of object o. On failure, raises SystemError and returns NULL. This is equivalent to the Python expression type (o). This function creates a new *strong reference* to the return value. There's really no reason to

use this function instead of the $Py_TYPE()$ function, which returns a pointer of type PyTypeObject*, except when a new *strong reference* is needed.

int PyObject_TypeCheck (PyObject *o, PyTypeObject *type)

Return non-zero if the object o is of type type or a subtype of type, and 0 otherwise. Both parameters must be non-NULL.

Py_ssize_t PyObject_Size (PyObject *o)

Py_ssize_t PyObject_Length (PyObject *o)

Part of the Stable ABI. Return the length of object o. If the object o provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression len(o).

Py_ssize_t PyObject_LengthHint (PyObject *0, Py_ssize_t defaultvalue)

Return an estimated length for the object o. First try to return its actual length, then an estimate using $_length_hint__()$, and finally return the default value. On error return -1. This is the equivalent to the Python expression operator.length_hint(o, defaultvalue).

Nouveau dans la version 3.4.

PyObject *PyObject_GetItem (PyObject *o, PyObject *key)

Return value: New reference. Part of the Stable ABI. Return element of o corresponding to the object key or NULL on failure. This is the equivalent of the Python expression o[key].

int PyObject_SetItem (PyObject *o, PyObject *key, PyObject *v)

Part of the Stable ABI. Map the object key to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[key] = v. This function *does not* steal a reference to v.

int PyObject_DelItem (PyObject *o, PyObject *key)

Part of the Stable ABI. Remove the mapping for the object key from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key].

PyObject *PyObject_Dir (PyObject *o)

Return value: New reference. Part of the Stable ABI. This is equivalent to the Python expression dir (0), returning a (possibly empty) list of strings appropriate for the object argument, or NULL if there was an error. If the argument is NULL, this is like the Python dir (), returning the names of the current locals; in this case, if no execution frame is active then NULL is returned but PyErr_Occurred() will return false.

PyObject *PyObject_GetIter (PyObject *o)

Return value: New reference. Part of the Stable ABI. This is equivalent to the Python expression iter(0). It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises TypeError and returns NULL if the object cannot be iterated.

PyObject *PyObject_GetAIter (PyObject *o)

Return value: New reference. Part of the Stable ABI since version 3.10. This is the equivalent to the Python expression aiter(o). Takes an AsyncIterable object and returns an AsyncIterator for it. This is typically a new iterator but if the argument is an AsyncIterator, this returns itself. Raises TypeError and returns NULL if the object cannot be iterated.

Nouveau dans la version 3.10.

void *PyObject_GetTypeData (PyObject *o, PyTypeObject *cls)

Part of the Stable ABI since version 3.12. Get a pointer to subclass-specific data reserved for cls.

The object o must be an instance of cls, and cls must have been created using negative $PyType_Spec.$ basicsize. Python does not check this.

On error, set an exception and return NULL.

Nouveau dans la version 3.12.

Py_ssize_t PyType_GetTypeDataSize (PyTypeObject *cls)

Part of the Stable ABI since version 3.12. Return the size of the instance memory space reserved for cls, i.e. the size of the memory PyObject GetTypeData() returns.

This may be larger than requested using $-PyType_Spec.basicsize$; it is safe to use this larger size (e.g. with memset ()).

The type *cls* **must** have been created using negative *PyType_Spec.basicsize*. Python does not check this. On error, set an exception and return a negative value.

Nouveau dans la version 3.12.

void *PyObject_GetItemData (PyObject *o)

Get a pointer to per-item data for a class with Py TPFLAGS ITEMS AT END.

On error, set an exception and return NULL. TypeError is raised if o does not have $Py_TPFLAGS_ITEMS_AT_END$ set.

Nouveau dans la version 3.12.

7.2 Call Protocol

CPython supports two different calling protocols : *tp_call* and vectorcall.

7.2.1 The tp_call Protocol

Instances of classes that set tp_call are callable. The signature of the slot is :

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

A call is made using a tuple for the positional arguments and a dict for the keyword arguments, similarly to callable (*args, **kwargs) in Python code. *args* must be non-NULL (use an empty tuple if there are no arguments) but *kwargs* may be *NULL* if there are no keyword arguments.

This convention is not only used by tp_call : tp_new and tp_init also pass arguments this way.

To call an object, use PyObject_Call () or another call API.

7.2.2 The Vectorcall Protocol

Nouveau dans la version 3.9.

The vectorcall protocol was introduced in PEP 590 as an additional protocol for making calls more efficient.

As rule of thumb, CPython will prefer the vectorcall for internal calls if the callable supports it. However, this is not a hard rule. Additionally, some third-party extensions use tp_call directly (rather than using $PyObject_Call$ ()). Therefore, a class supporting vectorcall must also implement tp_call . Moreover, the callable must behave the same regardless of which protocol is used. The recommended way to achieve this is by setting tp_call to $PyVectorcall_Call$ (). This bears repeating:

Avertissement : A class supporting vectorcall **must** also implement tp_call with the same semantics.

Modifié dans la version 3.12 : The $Py_TPFLAGS_HAVE_VECTORCALL$ flag is now removed from a class when the class's $__call__$ () method is reassigned. (This internally sets tp_call only, and thus may make it behave differently than the vectorcall function.) In earlier Python versions, vectorcall should only be used with immutable or static types.

A class should not implement vectorcall if that would be slower than *tp_call*. For example, if the callee needs to convert the arguments to an args tuple and kwargs dict anyway, then there is no point in implementing vectorcall.

Classes can implement the vectorcall protocol by enabling the $Py_TPFLAGS_HAVE_VECTORCALL$ flag and setting $tp_vectorcall_offset$ to the offset inside the object structure where a *vectorcallfunc* appears. This is a pointer to a function with the following signature :

typedef *PyObject* *(*vectorcallfunc)(*PyObject* *callable, *PyObject* *const *args, size_t nargsf, *PyObject* *kwnames)

Part of the Stable ABI since version 3.12.

- *callable* is the object being called.
- *args* is a C array consisting of the positional arguments followed by the values of the keyword arguments.

 This can be *NULL* if there are no arguments.
- *nargsf* is the number of positional arguments plus possibly the *PY_VECTORCALL_ARGUMENTS_OFFSET* flag. To get the actual number of positional arguments from *nargsf*, use *PyVectorcall_NARGS()*.
- *kwnames* is a tuple containing the names of the keyword arguments; in other words, the keys of the kwargs dict. These names must be strings (instances of str or a subclass) and they must be unique. If there are no keyword arguments, then *kwnames* can instead be *NULL*.

PY_VECTORCALL_ARGUMENTS_OFFSET

Part of the Stable ABI since version 3.12. If this flag is set in a vectorcall nargsf argument, the callee is allowed to temporarily change args[-1]. In other words, args points to argument 1 (not 0) in the allocated vector. The callee must restore the value of args[-1] before returning.

For PyObject_VectorcallMethod(), this flag means instead that args[0] may be changed.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use $PY_VECTORCALL_ARGUMENTS_OFFSET$. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) very efficiently.

Nouveau dans la version 3.8.

To call an object that implements vectorcall, use a *call API* function as with any other callable. <code>PyObject_Vectorcall()</code> will usually be most efficient.

Note: In CPython 3.8, the vectorcall API and related functions were available provisionally under names with a leading underscore: _PyObject_Vectorcall, _Py_TPFLAGS_HAVE_VECTORCALL, _PyObject_VectorcallMethod, _PyVectorcall_Function, _PyObject_CallOneArg, _PyObject_CallMethodNoArgs, _PyObject_CallMethodOneArg. Additionally, PyObject_VectorcallDict was available as _PyObject_FastCallDict. The old names are still defined as aliases of the new, non-underscored names.

Contrôle de la récursion

When using tp_call , callees do not need to worry about recursion: CPython uses $Py_EnterRecursiveCall$ () and $Py_LeaveRecursiveCall$ () for calls made using tp_call .

For efficiency, this is not the case for calls done using vectorcall: the callee should use *Py_EnterRecursiveCall* and *Py_LeaveRecursiveCall* if needed.

7.2. Call Protocol 87

Vectorcall Support API

Py_ssize_t PyVectorcall_NARGS (size_t nargsf)

Part of the Stable ABI since version 3.12. Given a vectorcall nargsf argument, return the actual number of arguments. Currently equivalent to:

```
(Py_ssize_t) (nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET)
```

However, the function PyVectorcall_NARGS should be used to allow for future extensions.

Nouveau dans la version 3.8.

vectorcallfunc PyVectorcall_Function (PyObject *op)

If op does not support the vectorcall protocol (either because the type does not or because the specific instance does not), return NULL. Otherwise, return the vectorcall function pointer stored in op. This function never raises an exception.

This is mostly useful to check whether or not op supports vectorcall, which can be done by checking PyVectorcall_Function(op) != NULL.

Nouveau dans la version 3.9.

PyObject *PyVectorcall_Call (PyObject *callable, PyObject *tuple, PyObject *dict)

Part of the Stable ABI since version 3.12. Call callable's vectorcallfunc with positional and keyword arguments given in a tuple and dict, respectively.

This is a specialized function, intended to be put in the tp_call slot or be used in an implementation of tp_call . It does not check the $Py_TPFLAGS_HAVE_VECTORCALL$ flag and it does not fall back to tp_call . Nouveau dans la version 3.8.

7.2.3 Object Calling API

Various functions are available for calling a Python object. Each converts its arguments to a convention supported by the called object – either *tp_call* or vectorcall. In order to do as little conversion as possible, pick one that best fits the format of data you have available.

The following table summarizes the available functions; please see individual documentation for details.

Fonction	callable	args	kwargs
PyObject_Call()	PyObject *	tuple	dict/NULL
PyObject_CallNoArgs()	PyObject *		
PyObject_CallOneArg()	PyObject *	1 object	
PyObject_CallObject()	PyObject *	tuple/NULL	
PyObject_CallFunction()	PyObject *	format	
PyObject_CallMethod()	obj + char*	format	
<pre>PyObject_CallFunctionObjArgs()</pre>	PyObject *	variadic	
PyObject_CallMethodObjArgs()	obj + name	variadic	
PyObject_CallMethodNoArgs()	obj + name		
PyObject_CallMethodOneArg()	obj + name	1 object	
PyObject_Vectorcall()	PyObject *	vectorcall	vectorcall
PyObject_VectorcallDict()	PyObject *	vectorcall	dict/NULL
PyObject_VectorcallMethod()	arg + name	vectorcall	vectorcall

PyObject *PyObject_Call (PyObject *callable, PyObject *args, PyObject *kwargs)

Return value : New reference. Part of the Stable ABI. Appelle un objet Python appelable callable, avec des arguments donnés par le n-uplet args, et des arguments nommés donnés par le dictionnaire kwargs.

args must not be *NULL*; use an empty tuple if no arguments are needed. If no named arguments are needed, *kwargs* can be *NULL*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python : callable (*args, **kwargs).

PyObject *PyObject_CallNoArgs (PyObject *callable)

Part of the Stable ABI since version 3.10. Call a callable Python object callable without any arguments. It is the most efficient way to call a callable Python object without any argument.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

PyObject *PyObject_CallOneArg (PyObject *callable, PyObject *arg)

Call a callable Python object *callable* with exactly 1 positional argument *arg* and no keyword arguments.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

PyObject *PyObject_CallObject (PyObject *callable, PyObject *args)

Return value: New reference. Part of the Stable ABI. Call a callable Python object callable, with arguments given by the tuple args. If no arguments are needed, then args can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python : callable (*args).

PyObject *PyObject_CallFunction (PyObject *callable, const char *format, ...)

Return value: New reference. Part of the Stable ABI. Call a callable Python object callable, with a variable number of C arguments. The C arguments are described using a Py_BuildValue() style format string. The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python : callable (*args).

Note that if you only pass PyObject* args, PyObject_CallFunctionObjArgs () is a faster alternative.

Modifié dans la version 3.4 : The type of *format* was changed from char *.

PyObject *PyObject CallMethod (PyObject *obj, const char *name, const char *format, ...)

Return value: New reference. Part of the Stable ABI. Call the method named name of object obj with a variable number of C arguments. The C arguments are described by a Py_BuildValue() format string that should produce a tuple.

The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: obj.name(arg1, arg2, ...).

Note that if you only pass PyObject* args, PyObject_CallMethodObjArgs() is a faster alternative.

Modifié dans la version 3.4: The types of *name* and *format* were changed from char *.

PyObject *PyObject_CallFunctionObjArgs (PyObject *callable, ...)

Return value : New reference. Part of the Stable ABI. Call a callable Python object *callable*, with a variable number of *PyObject** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (arg1, arg2, ...).

PyObject *PyObject_CallMethodObjArgs (PyObject *obj, PyObject *name, ...)

Return value: New reference. Part of the Stable ABI. Call a method of the Python object obj, where the name of the method is given as a Python string object in name. It is called with a variable number of PyObject* arguments. The arguments are provided as a variable number of parameters followed by NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

7.2. Call Protocol 89

PyObject *PyObject_CallMethodNoArgs (PyObject *obj, PyObject *name)

Call a method of the Python object *obj* without arguments, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

PyObject *PyObject CallMethodOneArg (PyObject *obj, PyObject *name, PyObject *arg)

Call a method of the Python object *obj* with a single positional argument *arg*, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

PyObject *PyObject_Vectorcall (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwnames)

Part of the Stable ABI since version 3.12. Call a callable Python object *callable*. The arguments are the same as for vectorcall func. If *callable* supports vectorcall, this directly calls the vectorcall function stored in *callable*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

PyObject *PyObject_VectorcallDict (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwdict)

Call *callable* with positional arguments passed exactly as in the *vectorcall* protocol, but with keyword arguments passed as a dictionary *kwdict*. The *args* array contains only the positional arguments.

Regardless of which protocol is used internally, a conversion of arguments needs to be done. Therefore, this function should only be used if the caller already has a dictionary ready to use for the keyword arguments, but not a tuple for the positional arguments.

Nouveau dans la version 3.9.

PyObject *PyObject_VectorcallMethod (PyObject *name, PyObject *const *args, size_t nargsf, PyObject *kwnames)

Part of the Stable ABI since version 3.12. Call a method using the vectorcall calling convention. The name of the method is given as a Python string name. The object whose method is called is args[0], and the args array starting at args[1] represents the arguments of the call. There must be at least one positional argument. nargsf is the number of positional arguments including args[0], plus $PY_VECTORCALL_ARGUMENTS_OFFSET$ if the value of args[0] may temporarily be changed. Keyword arguments can be passed just like in $PyObject_Vectorcall()$.

If the object has the $Py_TPFLAGS_METHOD_DESCRIPTOR$ feature, this will call the unbound method object with the full args vector as arguments.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

7.2.4 Call Support API

int PyCallable Check (PyObject *o)

Part of the Stable ABI. Détermine si l'objet o est appelable. Renvoie 1 si c'est le cas, et 0 sinon. Cette fonction réussit toujours.

7.3 Number Protocol

int PyNumber_Check (PyObject *o)

Part of the Stable ABI. Returns 1 if the object o provides numeric protocols, and false otherwise. This function always succeeds.

Modifié dans la version 3.8 : Returns 1 if o is an index integer.

PyObject *PyNumber_Add (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of adding o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 + o2.

PyObject *PyNumber Subtract (PyObject *o1, PyObject *o2)

Return value : New reference. Part of the Stable ABI. Returns the result of subtracting o2 from o1, or NULL on failure. This is the equivalent of the Python expression o1 - o2.

PyObject *PyNumber_Multiply (PyObject *o1, PyObject *o2)

Return value : New reference. Part of the Stable ABI. Returns the result of multiplying o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 * o2.

PyObject *PyNumber_MatrixMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI since version 3.7. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 @ o2. Nouveau dans la version 3.5.

PyObject *PyNumber_FloorDivide (PyObject *o1, PyObject *o2)

Return value : New reference. Part of the Stable ABI. Return the floor of o1 divided by o2, or NULL on failure. This is the equivalent of the Python expression o1 // o2.

PvObject *PyNumber TrueDivide (PvObject *o1, PvObject *o2)

Return value: New reference. Part of the Stable ABI. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. This is the equivalent of the Python expression o1 / o2.

PyObject *PyNumber_Remainder (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the remainder of dividing o1 by o2, or NULL on failure. This is the equivalent of the Python expression o1 % o2.

PyObject *PyNumber_Divmod (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. See the built-in function divmod(). Returns NULL on failure. This is the equivalent of the Python expression divmod(o1, o2).

PyObject *PyNumber_Power (PyObject *o1, PyObject *o2, PyObject *o3)

Return value: New reference. Part of the Stable ABI. See the built-in function pow(). Returns NULL on failure. This is the equivalent of the Python expression pow(o1, o2, o3), where o3 is optional. If o3 is to be ignored, pass Py_None in its place (passing NULL for o3 would cause an illegal memory access).

PyObject *PyNumber_Negative (PyObject *o)

Return value: New reference. Part of the Stable ABI. Returns the negation of o on success, or NULL on failure. This is the equivalent of the Python expression $-\circ$.

PyObject *PyNumber_Positive (PyObject *o)

Return value : New reference. Part of the Stable ABI. Returns *o* on success, or NULL on failure. This is the equivalent of the Python expression +0.

7.3. Number Protocol 91

PyObject *PyNumber_Absolute (PyObject *o)

Return value : New reference. Part of the Stable ABI. Returns the absolute value of o, or NULL on failure. This is the equivalent of the Python expression abs (o).

PyObject *PyNumber_Invert (PyObject *o)

Return value: New reference. Part of the Stable ABI. Returns the bitwise negation of o on success, or NULL on failure. This is the equivalent of the Python expression $\sim \circ$.

PyObject *PyNumber Lshift (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of left shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 << o2.

PyObject *PyNumber_Rshift (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of right shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 >> o2.

PyObject *PyNumber_And (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. This is the equivalent of the Python expression o1 & o2.

PyObject *PyNumber_Xor (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 oo o2.

PyObject *PyNumber_Or (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 | o2.

PyObject *PyNumber_InPlaceAdd (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of adding o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 += o2.

PyObject *PyNumber_InPlaceSubtract (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of subtracting o2 from o1, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 -= o2.

PyObject *PyNumber_InPlaceMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of multiplying o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 *= o2.

PyObject *PyNumber_InPlaceMatrixMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI since version 3.7. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 @= o2.

Nouveau dans la version 3.5.

PyObject *PyNumber_InPlaceFloorDivide (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the mathematical floor of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 //= o2.

PyObject *PyNumber InPlaceTrueDivide (PyObject *o1, PyObject *o2)

Return value : New reference. Part of the Stable ABI. Return a reasonable approximation for the mathematical value of *o1* divided by *o2*, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating

point value when passed two integers. The operation is done *in-place* when *o1* supports it. This is the equivalent of the Python statement 01 /= 02.

PyObject *PyNumber_InPlaceRemainder (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the remainder of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 %= o2.

PyObject *PyNumber_InPlacePower (PyObject *o1, PyObject *o2, PyObject *o3)

Return value: New reference. Part of the Stable ABI. See the built-in function pow(). Returns NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 **= o2 when o3 is Py_None , or an in-place variant of pow(o1, o2, o3) otherwise. If o3 is to be ignored, pass Py_None in its place (passing NULL for o3 would cause an illegal memory access).

PyObject *PyNumber_InPlaceLshift (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of left shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 <<= o2.

PyObject *PyNumber_InPlaceRshift (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the result of right shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 >>= o2.

PyObject *PyNumber_InPlaceAnd (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 &= o2.

PyObject *PyNumber_InPlaceXor (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement $o1 ^= o2$.

PyObject *PyNumber_InPlaceOr (PyObject *o1, PyObject *o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 = o2.

PyObject *PyNumber_Long (PyObject *o)

Return value: New reference. Part of the Stable ABI. Returns the o converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression int (0).

PyObject *PyNumber Float (PyObject *o)

Return value: New reference. Part of the Stable ABI. Returns the o converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression float (o).

PyObject *PyNumber Index (PyObject *o)

Return value : New reference. Part of the Stable ABI. Returns the *o* converted to a Python int on success or NULL with a TypeError exception raised on failure.

Modifié dans la version 3.10: The result always has exact type int. Previously, the result could have been an instance of a subclass of int.

PyObject *PyNumber_ToBase (PyObject *n, int base)

Return value: New reference. Part of the Stable ABI. Returns the integer n converted to base base as a string. The base argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of '0b', '0o', or '0x', respectively. If n is not a Python int, it is converted with $PyNumber_Index()$ first.

7.3. Number Protocol 93

Py_ssize_t PyNumber_AsSsize_t (PyObject *o, PyObject *exc)

Part of the Stable ABI. Returns o converted to a Py_ssize_t value if o can be interpreted as an integer. If the call fails, an exception is raised and -1 is returned.

If o can be converted to a Python int but the attempt to convert to a Py_ssize_t value would raise an OverflowError, then the exc argument is the type of exception that will be raised (usually IndexError or OverflowError). If exc is NULL, then the exception is cleared and the value is clipped to PY_SSIZE_T_MIN for a negative integer or PY SSIZE T MAX for a positive integer.

int PyIndex_Check (PyObject *o)

Part of the Stable ABI since version 3.8. Returns 1 if o is an index integer (has the nb_index slot of the tp_as_number structure filled in), and 0 otherwise. This function always succeeds.

7.4 Sequence Protocol

int PySequence_Check (PyObject *o)

Part of the Stable ABI. Return 1 if the object provides the sequence protocol, and 0 otherwise. Note that it returns 1 for Python classes with a __getitem__() method, unless they are dict subclasses, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

```
Py ssize t PySequence Size (PyObject *o)
```

```
Py_ssize_t PySequence_Length (PyObject *o)
```

Part of the Stable ABI. Returns the number of objects in sequence o on success, and -1 on failure. This is equivalent to the Python expression len (0).

```
PyObject *PySequence Concat (PyObject *o1, PyObject *o2)
```

Return value: New reference. Part of the Stable ABI. Return the concatenation of o1 and o2 on success, and NULL on failure. This is the equivalent of the Python expression o1 + o2.

```
PyObject *PySequence_Repeat (PyObject *o, Py_ssize_t count)
```

Return value: New reference. Part of the Stable ABI. Return the result of repeating sequence object o count times, or NULL on failure. This is the equivalent of the Python expression o * count.

```
PyObject *PySequence_InPlaceConcat (PyObject *o1, PyObject *o2)
```

Return value: New reference. Part of the Stable ABI. Return the concatenation of o1 and o2 on success, and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python expression o1 += o2.

```
PyObject *PySequence_InPlaceRepeat (PyObject *o, Py_ssize_t count)
```

Return value: New reference. Part of the Stable ABI. Return the result of repeating sequence object o count times, or NULL on failure. The operation is done *in-place* when o supports it. This is the equivalent of the Python expression o *= count.

```
PyObject *PySequence_GetItem (PyObject *o, Py_ssize_t i)
```

Return value : New reference. Part of the Stable ABI. Return the *i*th element of o, or NULL on failure. This is the equivalent of the Python expression o[i].

```
PyObject *PySequence_GetSlice (PyObject *o, Py_ssize_t i1, Py_ssize_t i2)
```

Return value: New reference. Part of the Stable ABI. Return the slice of sequence object o between i1 and i2, or NULL on failure. This is the equivalent of the Python expression o[i1:i2].

```
int PySequence_SetItem (PyObject *o, Py_ssize_t i, PyObject *v)
```

Part of the Stable ABI. Assign object v to the ith element of o. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[i] = v. This function *does not* steal a reference to v.

If v is NULL, the element is deleted, but this feature is deprecated in favour of using $PySequence_DelItem()$.

int PySequence DelItem (PyObject *o, Py ssize ti)

Part of the Stable ABI. Delete the *i*th element of object o. Returns -1 on failure. This is the equivalent of the Python statement del o[i].

int **PySequence_SetSlice** (*PyObject* *o, *Py_ssize_t* i1, *Py_ssize_t* i2, *PyObject* *v)

Part of the Stable ABI. Assign the sequence object v to the slice in sequence object o from il to il. This is the equivalent of the Python statement o[il:il] = v.

int PySequence_DelSlice (PyObject *o, Py_ssize_t i1, Py_ssize_t i2)

Part of the Stable ABI. Delete the slice in sequence object o from il to i2. Returns -1 on failure. This is the equivalent of the Python statement del o[i1:i2].

Py_ssize_t PySequence_Count (PyObject *o, PyObject *value)

Part of the Stable ABI. Return the number of occurrences of value in o, that is, return the number of keys for which o [key] == value. On failure, return -1. This is equivalent to the Python expression o.count (value).

int PySequence_Contains (PyObject *o, PyObject *value)

Part of the Stable ABI. Determine if o contains *value*. If an item in o is equal to *value*, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression value in o.

Py_ssize_t PySequence_Index (PyObject *o, PyObject *value)

Part of the Stable ABI. Return the first index *i* for which o[i] = value. On error, return -1. This is equivalent to the Python expression o.index(value).

PyObject *PySequence_List (PyObject *o)

Return value : New reference. Part of the Stable ABI. Return a list object with the same contents as the sequence or iterable *o*, or NULL on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression list (0).

PyObject *PySequence_Tuple (PyObject *o)

Return value: New reference. Part of the Stable ABI. Return a tuple object with the same contents as the sequence or iterable o, or NULL on failure. If o is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression tuple (\circ).

PyObject *PySequence_Fast (PyObject *o, const char *m)

Return value: New reference. Part of the Stable ABI. Return the sequence or iterable o as an object usable by the other PySequence_Fast* family of functions. If the object is not a sequence or iterable, raises TypeError with m as the message text. Returns NULL on failure.

The PySequence_Fast* functions are thus named because they assume o is a PyTupleObject or a PyListObject and access the data fields of o directly.

As a CPython implementation detail, if o is already a sequence or list, it will be returned.

Py_ssize_t PySequence_Fast_GET_SIZE (PyObject *o)

Returns the length of o, assuming that o was returned by $PySequence_Fast$ () and that o is not NULL. The size can also be retrieved by calling $PySequence_Size$ () on o, but $PySequence_Fast_GET_SIZE$ () is faster because it can assume o is a list or tuple.

PyObject *PySequence_Fast_GET_ITEM (PyObject *o, Py_ssize_t i)

Return value : Borrowed reference. Return the *i*th element of o, assuming that o was returned by $PySequence_Fast()$, o is not NULL, and that i is within bounds.

PyObject **PySequence_Fast_ITEMS (PyObject *o)

Return the underlying array of PyObject pointers. Assumes that o was returned by $PySequence_Fast()$ and o is not NULL.

Note, if a list gets resized, the reallocation may relocate the items array. So, only use the underlying array pointer in contexts where the sequence cannot change.

```
PyObject *PySequence_ITEM (PyObject *o, Py_ssize_t i)
```

Return value: New reference. Return the ith element of o or NULL on failure. Faster form of PySequence_GetItem() but without checking that PySequence_Check() on o is true and without adjustment for negative indices.

7.5 Protocole de correspondance

Voir aussi PyObject_GetItem(), PyObject_SetItem() et PyObject_DelItem().

int PyMapping_Check (PyObject *o)

Part of the Stable ABI. Return 1 if the object provides the mapping protocol or supports slicing, and 0 otherwise. Note that it returns 1 for Python classes with a __getitem__() method, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

```
Py_ssize_t PyMapping_Size (PyObject *o)
```

```
Py_ssize_t PyMapping_Length (PyObject *o)
```

Part of the Stable ABI. Renvoie le nombre de clefs dans l'objet o et -1 en cas d'échec. C'est l'équivalent de l'expression Python len (o).

```
PyObject *PyMapping_GetItemString (PyObject *o, const char *key)
```

Return value: New reference. Part of the Stable ABI. This is the same as PyObject_GetItem(), but key is specified as a const_char* UTF-8 encoded bytes string, rather than a PyObject*.

```
int PyMapping_SetItemString (PyObject *o, const char *key, PyObject *v)
```

Part of the Stable ABI. This is the same as PyObject_SetItem(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

```
int PyMapping DelItem (PyObject *o, PyObject *key)
```

This is an alias of PyObject_DelItem().

```
int PyMapping_DelItemString (PyObject *o, const char *key)
```

This is the same as PyObject_DelItem(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

```
int PyMapping_HasKey (PyObject *o, PyObject *key)
```

Part of the Stable ABI. Renvoie 1 si l'objet de correspondance possède une clef key et 0 sinon. C'est l'équivalent de l'expression Python key in o. Cette fonction ne provoque jamais d'erreur.

Note: Exceptions which occur when this calls $__{getitem}$ () method are silently ignored. For proper error handling, use $PyObject_GetItem$ () instead.

int **PyMapping_HasKeyString** (*PyObject* *o, const char *key)

Part of the Stable ABI. This is the same as PyMapping_HasKey(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

Note: Exceptions that occur when this calls __getitem__() method or while creating the temporary str object are silently ignored. For proper error handling, use <code>PyMapping_GetItemString()</code> instead.

PyObject *PyMapping_Keys (PyObject *o)

Return value: New reference. Part of the Stable ABI. Renvoie la liste des clefs dans l'objet o. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7 : Auparavant, la fonction renvoyait une liste ou un *n*-uplet.

```
PyObject *PyMapping_Values (PyObject *o)
```

Return value : New reference. Part of the Stable ABI. Renvoie la liste des valeurs dans l'objet o. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7 : Auparavant, la fonction renvoyait une liste ou un *n*-uplet.

```
PyObject *PyMapping_Items (PyObject *o)
```

Return value : New reference. Part of the Stable ABI. Renvoie la liste des éléments dans l'objet o, où chaque élément est un n-uplet contenant une paire clef-valeur. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7 : Auparavant, la fonction renvoyait une liste ou un *n*-uplet.

7.6 Protocole d'itération

Il existe deux fonctions dédiées à l'interaction avec les itérateurs.

```
int PyIter_Check (PyObject *o)
```

Part of the Stable ABI since version 3.8. Return non-zero if the object o can be safely passed to $PyIter_Next()$, and 0 otherwise. This function always succeeds.

```
int PyAIter_Check (PyObject *o)
```

Part of the Stable ABI *since version 3.10.* Return non-zero if the object *o* provides the AsyncIterator protocol, and 0 otherwise. This function always succeeds.

Nouveau dans la version 3.10.

```
PyObject *PyIter_Next (PyObject *o)
```

Return value: New reference. Part of the Stable ABI. Return the next value from the iterator o. The object must be an iterator according to PyIter_Check() (it is up to the caller to check this). If there are no remaining values, returns NULL with no exception set. If an error occurs while retrieving the item, returns NULL and passes along the exception.

Pour écrire une boucle itérant un itérateur, le code C devrait ressembler à :

```
PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while ((item = PyIter_Next(iterator))) {
    /* do something with item */
    ...
    /* release reference when done */
    Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
```

(suite sur la page suivante)

(suite de la page précédente)

```
else {
    /* continue doing useful work */
}
```

type PySendResult

The enum value used to represent different results of PyIter_Send().

Nouveau dans la version 3.10.

PySendResult PyIter_Send (PyObject *iter, PyObject *arg, PyObject **presult)

Part of the Stable ABI since version 3.10. Sends the arg value into the iterator iter. Returns:

- PYGEN_RETURN if iterator returns. Return value is returned via *presult*.
- PYGEN_NEXT if iterator yields. Yielded value is returned via *presult*.
- PYGEN_ERROR if iterator has raised and exception. presult is set to NULL.

Nouveau dans la version 3.10.

7.7 Protocole tampon

Certains objets Python enveloppent l'accès à un tableau de mémoire sous-jacente (nommée zone tampon ou simplement tampon, *buffer* en anglais). Les objets natifs bytes et bytearray en sont des exemples, ainsi que quelques types d'extension comme array. Les bibliothèques tierces peuvent définir leurs propres types à des fins spéciales, telles que le traitement d'image ou l'analyse numérique.

Alors que chacun de ces types a sa propre sémantique, ils partagent la caractéristique commune d'être soutenus par un tampon de mémoire important. Il est donc souhaitable, dans certains cas, d'accéder à cette mémoire directement sans l'étape intermédiaire de copie.

Python fournit une telle facilité au niveau du C sous la forme de protocole tampon. Ce protocole comporte deux aspects :

- du côté producteur, un type peut exporter une "interface tampon" qui permet aux objets de ce type d'exposer des informations concernant leur tampon sous-jacent. Cette interface est décrite dans la section Buffer Object Structures:
- du côté consommateur, plusieurs moyens sont disponibles pour obtenir un pointeur vers les données sous-jacentes brutes d'un objet (par exemple un paramètre de méthode).

Des objets simples tels que bytes et bytearray exposent leur tampon sous-jacent dans un format orienté octet. D'autres formes sont possibles; par exemple, les éléments exposés par un array array peuvent être des valeurs multi-octets.

An example consumer of the buffer interface is the write () method of file objects: any object that can export a series of bytes through the buffer interface can be written to a file. While write() only needs read-only access to the internal contents of the object passed to it, other methods such as readinto() need write access to the contents of their argument. The buffer interface allows objects to selectively allow or reject exporting of read-write and read-only buffers.

Un consommateur de l'interface tampon peut acquérir un tampon sur un objet cible de deux manières :

```
— appelez PyObject_GetBuffer() avec les paramètres appropriés;
```

— appelez <code>PyArg_ParseTuple()</code> (ou l'un de ses fonctions sœurs) avec l'un des y*, w* ou s* format codes.

Dans les deux cas, <code>PyBuffer_Release()</code> doit être appelée quand le tampon n'est plus nécessaire. Ne pas le faire peut conduire à divers problèmes tels que des fuites de ressources.

7.7.1 La structure buffer

Les structures tampons (ou simplement les "tampons", *buffers* en anglais) sont utiles pour exposer les données binaires d'un autre objet au programmeur Python. Elles peuvent également être utilisées comme un mécanisme de découpage sans copie. En utilisant leur capacité à référencer un bloc de mémoire, il est possible d'exposer toutes les données au programmeur Python assez facilement. La mémoire peut être un grand tableau constant dans une extension C, il peut s'agir d'un bloc brut de mémoire à manipuler avant de passer à une bibliothèque de système d'exploitation ou être utilisé pour transmettre des données structurées dans son format natif en mémoire.

Contrairement à la plupart des types de données exposés par l'interpréteur Python, les tampons ne sont pas de simples pointeurs vers PyObject mais plutôt des structures C simples. Cela leur permet d'être créés et copiés très simplement. lorsque vous avez besoin d'une enveloppe générique (wrapper en anglais) pour un tampon, un objet memoryview peut être créé.

For short instructions how to write an exporting object, see *Buffer Object Structures*. For obtaining a buffer, see *PyObject_GetBuffer()*.

type Py_buffer

Part of the Stable ABI (including all members) since version 3.11.

void *buf

A pointer to the start of the logical structure described by the buffer fields. This can be any location within the underlying physical memory block of the exporter. For example, with negative strides the value may point to the end of the memory block.

For *contiguous* arrays, the value points to the beginning of the memory block.

PyObject *obj

A new reference to the exporting object. The reference is owned by the consumer and automatically released (i.e. reference count decremented) and set to NULL by <code>PyBuffer_Release()</code>. The field is the equivalent of the return value of any standard C-API function.

As a special case, for *temporary* buffers that are wrapped by *PyMemoryView_FromBuffer()* or *PyBuffer_FillInfo()* this field is NULL. In general, exporting objects MUST NOT use this scheme.

Py ssize t len

product (shape) * itemsize. For contiguous arrays, this is the length of the underlying memory block. For non-contiguous arrays, it is the length that the logical structure would have if it were copied to a contiguous representation.

Accessing ((char *)buf)[0] up to ((char *)buf)[len-1] is only valid if the buffer has been obtained by a request that guarantees contiguity. In most cases such a request will be PyBUF_SIMPLE or PyBUF WRITABLE.

int readonly

An indicator of whether the buffer is read-only. This field is controlled by the PyBUF_WRITABLE flag.

Py_ssize_t itemsize

Item size in bytes of a single element. Same as the value of struct.calcsize() called on non-NULL format values.

Important exception: If a consumer requests a buffer without the <code>PyBUF_FORMAT</code> flag, <code>format</code> will be set to <code>NULL</code>, but <code>itemsize</code> still has the value for the original format.

If shape is present, the equality product (shape) * itemsize == len still holds and the consumer can use itemsize to navigate the buffer.

If shape is NULL as a result of a $PyBUF_SIMPLE$ or a $PyBUF_WRITABLE$ request, the consumer must disregard itemsize and assume itemsize == 1.

const char *format

A *NUL* terminated string in struct module style syntax describing the contents of a single item. If this is NULL, "B" (unsigned bytes) is assumed.

This field is controlled by the PyBUF_FORMAT flag.

int ndim

The number of dimensions the memory represents as an n-dimensional array. If it is 0, buf points to a single item representing a scalar. In this case, shape, strides and suboffsets MUST be NULL. The maximum number of dimensions is given by PyBUF MAX NDIM.

Py_ssize_t *shape

An array of Py_ssize_t of length ndim indicating the shape of the memory as an n-dimensional array. Note that shape [0] * ... * shape [ndim-1] * itemsize MUST be equal to <math>len.

Shape values are restricted to shape[n] >= 0. The case shape[n] == 0 requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

Py ssize t*strides

An array of Py_ssize_t of length ndim giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case $strides[n] \le 0$. See *complex arrays* for further information.

The strides array is read-only for the consumer.

Py_ssize_t *suboffsets

An array of Py_ssize_t of length ndim. If suboffsets[n] >= 0, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after dereferencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be NULL (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

void *internal

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

Constants:

PyBUF_MAX_NDIM

The maximum number of dimensions the memory represents. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to PyBUF_MAX_NDIM dimensions. Currently set to 64.

7.7.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via PyObject_GetBuffer(). Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the *flags* argument to specify the exact buffer type it can handle.

All Py_buffer fields are unambiguously defined by the request type.

request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values : obj, buf, len, itemsize, ndim.

readonly, format

PyBUF_WRITABLE

Controls the readonly field. If set, the exporter MUST provide a writable buffer or else report failure. Otherwise, the exporter MAY provide either a read-only or writable buffer, but the choice MUST be consistent for all consumers.

PyBUF_FORMAT

Controls the format field. If set, this field MUST be filled in correctly. Otherwise, this field MUST be NULL.

PyBUF_WRITABLE can be I'd to any of the flags in the next section. Since PyBUF_SIMPLE is defined as 0, PyBUF_WRITABLE can be used as a stand-alone flag to request a simple writable buffer.

PyBUF_FORMAT can be I'd to any of the flags except PyBUF_SIMPLE. The latter already implies format B (unsigned bytes).

shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

Request	shape	strides	suboffsets
PyBUF_INDIRECT	oui	oui	si nécessaire
PyBUF_STRIDES	oui	oui	NULL
PyBUF_ND	oui	NULL	NULL
PyBUF_SIMPLE	NULL	NULL	NULL

contiguity requests

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

Request	shape	strides	suboffsets	contig
PyBUF_C_CONTIGUOUS	oui	oui	NULL	С
PyBUF_F_CONTIGUOUS	oui	oui	NULL	F
PyBUF_ANY_CONTIGUOUS	oui	oui	NULL	C or F
PyBUF_ND	oui	NULL	NULL	С

compound requests

All possible requests are fully defined by some combination of the flags in the previous section. For convenience, the buffer protocol provides frequently used combinations as single flags.

In the following table U stands for undefined contiguity. The consumer would have to call $PyBuffer_IsContiguous$ () to determine contiguity.

Request	shape	strides	suboffsets	contig	lecture seule	format
PyBUF_FULL	oui	oui	si nécessaire	U	0	oui
PyBUF_FULL_RO	oui	oui	si nécessaire	U	0 ou 1	oui
PyBUF_RECORDS	oui	oui	NULL	U	0	oui
PyBUF_RECORDS_RO	oui	oui	NULL	U	0 ou 1	oui
PyBUF_STRIDED	oui	oui	NULL	U	0	NULL
PyBUF_STRIDED_RO	oui	oui	NULL	U	0 ou 1	NULL
PyBUF_CONTIG	oui	NULL	NULL	С	0	NULL
PyBUF_CONTIG_RO	oui	NULL	NULL	С	0 ou 1	NULL

7.7.3 Complex arrays

NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by itemsize, ndim, shape and strides.

If ndim == 0, the memory location pointed to by buf is interpreted as a scalar of size itemsize. In that case, both shape and strides are NULL.

If strides is NULL, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, buf can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
       the bounds of the allocated memory:
           char *mem: start of the physical memory block
           memlen: length of the physical memory block
           offset: (char *)buf - mem
    11 11 11
   if offset % itemsize:
       return False
    if offset < 0 or offset+itemsize > memlen:
       return False
    if any(v % itemsize for v in strides):
       return False
   if ndim <= 0:
       return ndim == 0 and not shape and not strides
   if 0 in shape:
       return True
   imin = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] <= 0)</pre>
   imax = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] > 0)
    return 0 <= offset+imin and offset+imax+itemsize <= memlen</pre>
```

PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array char v[2][2][3] can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: char (*v[2])[2][3]. In suboffsets representation, those two pointers can be embedded at the start of buf, pointing to two char x[2][3] arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-NULL strides and suboffsets:

7.7.4 Fonctions relatives aux tampons

int PyObject_CheckBuffer (PyObject *obj)

Part of the Stable ABI since version 3.11. Return 1 if obj supports the buffer interface otherwise 0. When 1 is returned, it doesn't guarantee that PyObject_GetBuffer() will succeed. This function always succeeds.

```
int PyObject_GetBuffer (PyObject *exporter, Py_buffer *view, int flags)
```

Part of the Stable ABI since version 3.11. Send a request to exporter to fill in view as specified by flags. If the exporter cannot provide a buffer of the exact type, it MUST raise BufferError, set view->obj to NULL and return -1.

On success, fill in *view*, set view->obj to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, view->obj MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to $PyObject_GetBuffer()$ must be paired with calls to $PyBuffer_Release()$, similar to malloc() and free(). Thus, after the consumer is done with the buffer, $PyBuffer_Release()$ must be called exactly once.

```
void PyBuffer_Release (Py_buffer *view)
```

Part of the Stable ABI since version 3.11. Release the buffer view and release the strong reference (i.e. decrement the reference count) to the view's supporting object, view->obj. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via PyObject_GetBuffer().

Py_ssize_t PyBuffer_SizeFromFormat (const char *format)

Part of the Stable ABI since version 3.11. Return the implied itemsize from format. On error, raise an exception and return -1.

Nouveau dans la version 3.9.

int PyBuffer_IsContiguous (const *Py_buffer* *view, char order)

Part of the Stable ABI since version 3.11. Return 1 if the memory defined by the view is C-style (order is 'C') or Fortran-style (order is 'F') contiguous or either one (order is 'A'). Return 0 otherwise. This function always succeeds.

```
void *PyBuffer_GetPointer (const Py_buffer *view, const Py_ssize_t *indices)
```

Part of the Stable ABI since version 3.11. Get the memory area pointed to by the indices inside the given view. indices must point to an array of view->ndim indices.

```
int PyBuffer_FromContiguous (const Py_buffer *view, const void *buf, Py_ssize_t len, char fort)
```

Part of the Stable ABI since version 3.11. Copy contiguous len bytes from buf to view. fort can be 'C' or 'F' (for C-style or Fortran-style ordering). 0 is returned on success, -1 on error.

int PyBuffer_ToContiquous (void *buf, const Py_buffer *src, Py_ssize_t len, char order)

Part of the Stable ABI since version 3.11. Copy len bytes from src to its contiguous representation in buf. order can be 'C' or 'F' or 'A' (for C-style or Fortran-style ordering or either one). 0 is returned on success, -1 on error. This function fails if len!= src->len.

int PyObject_CopyData (PyObject *dest, PyObject *src)

Part of the Stable ABI since version 3.11. Copy data from src to dest buffer. Can convert between C-style and or Fortran-style buffers.

0 is returned on success, -1 on error.

void **PyBuffer_FillContiguousStrides** (int ndims, *Py_ssize_t* *shape, *Py_ssize_t* *strides, int itemsize, char order)

Part of the Stable ABI since version 3.11. Fill the strides array with byte-strides of a contiguous (C-style if order is 'C' or Fortran-style if order is 'F') array of the given shape with the given number of bytes per element.

int PyBuffer_FillInfo (Py_buffer *view, PyObject *exporter, void *buf, Py_ssize_t len, int readonly, int flags)

Part of the Stable ABI since version 3.11. Handle buffer requests for an exporter that wants to expose buf of size len with writability set according to readonly. buf is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and *PyBUF_WRITABLE* is set in *flags*.

On success, set view->obj to a new reference to *exporter* and return 0. Otherwise, raise BufferError, set view->obj to NULL and return -1;

If this function is used as part of a *getbufferproc*, *exporter* MUST be set to the exporting object and *flags* must be passed unmodified. Otherwise, *exporter* MUST be NULL.

7.8 Ancien Protocole Tampon

Obsolète depuis la version 3.0.

Ces fonctions faisaient partie de l'API de l'ancien protocole de tampons dans Python 2. Dans Python 3, ce protocole n'existe plus, mais les fonctions sont toujours exposées pour simplifier le portage de code Python 2.x. Elles se comportent comme une abstraction de compatibilité du *nouveau protocole de tampons*, mais sans vous donner de contrôle sur la durée de vie des ressources acquises lorsqu'un tampon est exporté.

Il est donc recommandé d'appeler $PyObject_GetBuffer()$ (ou les codes y* ou w* à la famille de fonctions $PyArg_ParseTuple()$) pour obtenir une vue d'un tampon sur un objet, et $PyBuffer_Release()$ lorsque la vue peut être libérée.

int PyObject_AsCharBuffer (PyObject *obj, const char **buffer, Py_ssize_t *buffer_len)

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire en lecture seule utilisable en tant qu'entrée basée sur des caractères. L'argument *obj* doit prendre en charge l'interface de tampon de caractère à segment unique. En cas de succès, retourne 0, définit *buffer* à l'emplacement de la mémoire et *buffer_len* à la longueur de la mémoire tampon. Retourne -1 et affecte une exception TypeError en cas d'erreur.

int PyObject_AsReadBuffer (PyObject *obj, const void **buffer, Py_ssize_t *buffer_len)

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire en lecture seule contenant des données arbitraires. L'argument *obj* doit prendre en charge l'interface de tampon lisible à segment unique. En cas de succès, retourne 0, définit *buffer* à l'emplacement de la mémoire et *buffer_len* à la longueur de la mémoire tampon. Renvoie -1 et affecte l'exception TypeError en cas d'erreur.

int PyObject CheckReadBuffer (PyObject *o)

Part of the Stable ABI. Retourne 1 si *o* prend en charge l'interface de mémoire tampon lisible à segment unique. Sinon, renvoie 0. Cette fonction réussit toujours.

Notez que cette fonction tente d'obtenir et de libérer une mémoire tampon, et les exceptions qui se produisent lors de l'appel des fonctions correspondantes seront supprimées. Pour que les erreurs vous soient signalées, utilisez <code>PyObject_GetBuffer()</code> à la place.

int PyObject_AsWriteBuffer (PyObject *obj, void **buffer, Py_ssize_t *buffer_len)

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire accessible en écriture. L'argument obj doit prendre en charge l'interface de mémoire tampon de caractère à segment unique. En cas de succès, retourne 0, définit buffer à l'emplacement de la mémoire et buffer_len à la longueur de la mémoire tampon. Renvoie -1 et affecte l'exception TypeError en cas d'erreur.

Couche des objets concrets

Les fonctions de ce chapitre sont spécifiques à certains types d'objets Python. Leur donner un objet du mauvais type n'est pas une bonne idée, si vous recevez un objet d'un programme Python, et que vous n'êtes pas sûr qu'il soit du bon type, vous devez vérifier son type en premier. Par exemple, pour vérifier qu'un objet est un dictionnaire, utilisez PyDict_Check(). Ce chapitre est organisé comme un arbre généalogique de types d'objets Python.

Avertissement : Tandis que les fonctions décrites dans ce chapitre vérifient avec soin le type des objets qui leur sont passés, beaucoup d'entre elles ne vérifient pas que NULL est passé au lieu d'un objet valide. Autoriser NULL à être passé peut provoquer des violations d'accès à la mémoire et ainsi terminer immédiatement l'interpréteur.

8.1 Objets fondamentaux

Cette section décrit les objets de type Python et l'objet singleton None.

8.1.1 Objets type

type PyTypeObject

Part of the Limited API (as an opaque struct). The C structure of the objects used to describe built-in types.

PyTypeObject PyType_Type

Part of the Stable ABI. This is the type object for type objects; it is the same object as type in the Python layer.

int PyType_Check (PyObject *o)

Return non-zero if the object *o* is a type object, including instances of types derived from the standard type object. Return 0 in all other cases. This function always succeeds.

int PyType_CheckExact (*PyObject* *o)

Return non-zero if the object o is a type object, but not a subtype of the standard type object. Return 0 in all other cases. This function always succeeds.

unsigned int PyType_ClearCache()

Part of the Stable ABI. Clear the internal lookup cache. Return the current version tag.

unsigned long PyType_GetFlags (PyTypeObject *type)

Part of the Stable ABI. Return the tp_flags member of type. This function is primarily meant for use with $Py_LIMITED_API$; the individual flag bits are guaranteed to be stable across Python releases, but access to tp_flags itself is not part of the *limited API*.

Nouveau dans la version 3.2.

Modifié dans la version 3.4: The return type is now unsigned long rather than long.

PyObject *PyType_GetDict (PyTypeObject *type)

Return the type object's internal namespace, which is otherwise only exposed via a read-only proxy (cls. __dict__). This is a replacement for accessing tp_dict directly. The returned dictionary must be treated as read-only.

This function is meant for specific embedding and language-binding cases, where direct access to the dict is necessary and indirect access (e.g. via the proxy or $PyObject_GetAttr()$) isn't adequate.

Extension modules should continue to use tp_dict, directly or indirectly, when setting up their own types.

Nouveau dans la version 3.12.

void PyType_Modified (PyTypeObject *type)

Part of the Stable ABI. Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

int PyType_AddWatcher (PyType_WatchCallback callback)

Register *callback* as a type watcher. Return a non-negative integer ID which must be passed to future calls to $PyType_Watch()$. In case of error (e.g. no more watcher IDs available), return -1 and set an exception.

Nouveau dans la version 3.12.

int PyType_ClearWatcher (int watcher_id)

Clear watcher identified by *watcher_id* (previously returned from *PyType_AddWatcher()*). Return 0 on success, -1 on error (e.g. if *watcher_id* was never registered.)

An extension should never call $PyType_ClearWatcher$ with a watcher_id that was not returned to it by a previous call to $PyType_AddWatcher()$.

Nouveau dans la version 3.12.

int PyType_Watch (int watcher_id, PyObject *type)

Mark *type* as watched. The callback granted *watcher_id* by *PyType_AddWatcher()* will be called whenever *PyType_Modified()* reports a change to *type*. (The callback may be called only once for a series of consecutive modifications to *type*, if _PyType_Lookup() is not called on *type* between the modifications; this is an implementation detail and subject to change.)

An extension should never call PyType_Watch with a watcher_id that was not returned to it by a previous call to PyType_AddWatcher().

Nouveau dans la version 3.12.

typedef int (*PyType_WatchCallback)(PyObject *type)

Type of a type-watcher callback function.

The callback must not modify type or cause $PyType_Modified()$ to be called on type or any type in its MRO; violating this rule could cause infinite recursion.

Nouveau dans la version 3.12.

int **PyType_HasFeature** (*PyTypeObject* *o, int feature)

Return non-zero if the type object o sets the feature feature. Type features are denoted by single bit flags.

int PyType_IS_GC (PyTypeObject *o)

Return true if the type object includes support for the cycle detector; this tests the type flag $Py_TPFLAGS_HAVE_GC$.

int PyType_IsSubtype (PyTypeObject *a, PyTypeObject *b)

Part of the Stable ABI. Return true if a is a subtype of b.

This function only checks for actual subtypes, which means that $__subclasscheck__$ () is not called on b. Call $PyObject_IsSubclass()$ to do the same check that issubclass() would do.

PyObject *PyType_GenericAlloc (PyTypeObject *type, Py_ssize_t nitems)

Return value: New reference. Part of the Stable ABI. Generic handler for the tp_alloc slot of a type object. Use Python's default memory allocation mechanism to allocate a new instance and initialize all its contents to NULL.

PyObject *PyType_GenericNew (PyTypeObject *type, PyObject *args, PyObject *kwds)

Return value: New reference. Part of the Stable ABI. Generic handler for the tp_new slot of a type object. Create a new instance using the type's tp alloc slot.

int PyType_Ready (*PyTypeObject* *type)

Part of the Stable ABI. Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return 0 on success, or return -1 and sets an exception on error.

Note: If some of the base classes implements the GC protocol and the provided type does not include the $Py_TPFLAGS_HAVE_GC$ in its flags, then the GC protocol will be automatically implemented from its parents. On the contrary, if the type being created does include $Py_TPFLAGS_HAVE_GC$ in its flags then it **must** implement the GC protocol itself by at least implementing the $tp_traverse$ handle.

PyObject *PyType_GetName (PyTypeObject *type)

Return value : New reference. Part of the Stable ABI *since version 3.11.* Return the type's name. Equivalent to getting the type's __name__ attribute.

Nouveau dans la version 3.11.

PyObject *PyType_GetQualName (PyTypeObject *type)

Return value : New reference. Part of the Stable ABI *since version 3.11.* Return the type's qualified name. Equivalent to getting the type's __qualname__ attribute.

Nouveau dans la version 3.11.

void *PyType_GetSlot (PyTypeObject *type, int slot)

Part of the Stable ABI since version 3.4. Return the function pointer stored in the given slot. If the result is NULL, this indicates that either the slot is NULL, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See PyType_Slot.slot for possible values of the *slot* argument.

Nouveau dans la version 3.4.

Modifié dans la version 3.10: PyType_GetSlot () can now accept all types. Previously, it was limited to heap types.

PyObject *PyType_GetModule (PyTypeObject *type)

Part of the Stable ABI since version 3.10. Return the module object associated with the given type when the type was created using PyType_FromModuleAndSpec().

If no module is associated with the given type, sets TypeError and returns NULL.

This function is usually used to get the module in which a method is defined. Note that in such a method, PyType_GetModule(Py_TYPE(self)) may not return the intended result. Py_TYPE(self) may be a *subclass* of the intended class, and subclasses are not necessarily defined in the same module as their superclass.

See PyCMethod to get the class that defines the method. See PyType_GetModuleByDef() for cases when PyCMethod cannot be used.

Nouveau dans la version 3.9.

void *PyType_GetModuleState (PyTypeObject *type)

Part of the Stable ABI *since version 3.10*. Return the state of the module object associated with the given type. This is a shortcut for calling *PyModule_GetState()* on the result of *PyType_GetModule()*.

If no module is associated with the given type, sets TypeError and returns NULL.

If the type has an associated module but its state is NULL, returns NULL without setting an exception.

Nouveau dans la version 3.9.

PyObject *PyType_GetModuleByDef (PyTypeObject *type, struct PyModuleDef *def)

Find the first superclass whose module was created from the given PyModuleDef def, and return that module.

If no module is found, raises a TypeError and returns NULL.

This function is intended to be used together with $PyModule_GetState()$ to get module state from slot methods (such as tp_init or nb_add) and other places where a method's defining class cannot be passed using the PyCMethod calling convention.

Nouveau dans la version 3.11.

int PyUnstable_Type_AssignVersionTag (PyTypeObject *type)

This is *Unstable API*. It may change without warning in minor releases.

Attempt to assign a version tag to the given type.

Returns 1 if the type already had a valid version tag or a new one was assigned, or 0 if a new tag could not be assigned.

Nouveau dans la version 3.12.

Creating Heap-Allocated Types

The following functions and structs are used to create *heap types*.

PyObject *PyType_FromMetaclass (PyTypeObject *metaclass, PyObject *module, PyType_Spec *spec, PyObject *bases)

Part of the Stable ABI since version 3.12. Create and return a heap type from the spec (see Py TPFLAGS HEAPTYPE).

The metaclass *metaclass* is used to construct the resulting type object. When *metaclass* is NULL, the metaclass is derived from *bases* (or *Py_tp_base[s]* slots if *bases* is NULL, see below).

Metaclasses that override tp_new are not supported, except if tp_new is NULL. (For backwards compatibility, other PyType_From* functions allow such metaclasses. They ignore tp_new , which may result in incomplete initialization. This is deprecated and in Python 3.14+ such metaclasses will not be supported.)

The *bases* argument can be used to specify base classes; it can either be only one class or a tuple of classes. If *bases* is NULL, the Py_tp_bases slot is used instead. If that also is NULL, the Py_tp_base slot is used instead. If that also is NULL, the new type derives from object.

The *module* argument can be used to record the module in which the new class is defined. It must be a module object or NULL. If not NULL, the module is associated with the new type and can later be retrieved with $PyType_GetModule()$. The associated module is not inherited by subclasses; it must be specified for each class individually.

This function calls PyType_Ready () on the new type.

Note that this function does *not* fully match the behavior of calling type () or using the class statement. With user-provided base types or metaclasses, prefer *calling* type (or the metaclass) over PyType_From* functions. Specifically:

- __new__() is not called on the new class (and it must be set to type.__new__).
 __init__() is not called on the new class.
 __init_subclass__() is not called on any bases.
 __set_name__() is not called on new descriptors.
- Nouveau dans la version 3.12.

PyObject *PyType_FromModuleAndSpec (PyObject *module, PyType_Spec *spec, PyObject *bases)

Return value: New reference. Part of the Stable ABI since version 3.10. Equivalent to PyType_FromMetaclass(NULL, module, spec, bases).

Nouveau dans la version 3.9.

Modifié dans la version 3.10 : The function now accepts a single class as the *bases* argument and NULL as the tp_doc slot.

Modifié dans la version 3.12 : The function now finds and uses a metaclass corresponding to the provided base classes. Previously, only type instances were returned.

The tp_new of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides tp_new is deprecated and in Python 3.14+ it will be no longer allowed.

PyObject *PyType_FromSpecWithBases (PyType_Spec *spec, PyObject *bases)

Return value: New reference. Part of the Stable ABI since version 3.3. Equivalent to PyType_FromMetaclass(NULL, NULL, spec, bases).

Nouveau dans la version 3.3.

Modifié dans la version 3.12 : The function now finds and uses a metaclass corresponding to the provided base classes. Previously, only type instances were returned.

The tp_new of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides tp_new is deprecated and in Python 3.14+ it will be no longer allowed.

PyObject *PyType_FromSpec (PyType_Spec *spec)

Return value: New reference. Part of the Stable ABI. Equivalent to PyType_FromMetaclass (NULL, NULL, spec, NULL).

Modifié dans la version 3.12 : The function now finds and uses a metaclass corresponding to the base classes provided in $Py_tp_base[s]$ slots. Previously, only type instances were returned.

The tp_new of the metaclass is *ignored*. which may result in incomplete initialization. Creating classes whose metaclass overrides tp_new is deprecated and in Python 3.14+ it will be no longer allowed.

type PyType_Spec

Part of the Stable ABI (including all members). Structure defining a type's behavior.

const char *name

Name of the type, used to set PyTypeObject.tp name.

int basicsize

If positive, specifies the size of the instance in bytes. It is used to set $PyTypeObject.tp_basicsize$. If zero, specifies that $tp_basicsize$ should be inherited.

If negative, the absolute value specifies how much space instances of the class need *in addition* to the superclass. Use <code>PyObject_GetTypeData()</code> to get a pointer to subclass-specific memory reserved this way.

Modifié dans la version 3.12 : Previously, this field could not be negative.

int itemsize

Size of one element of a variable-size type, in bytes. Used to set <code>PyTypeObject.tp_itemsize</code>. See <code>tp_itemsize</code> documentation for caveats.

If zero, $tp_itemsize$ is inherited. Extending arbitrary variable-sized classes is dangerous, since some types use a fixed offset for variable-sized memory, which can then overlap fixed-sized memory used by a subclass. To help prevent mistakes, inheriting itemsize is only possible in the following situations:

— The base is not variable-sized (its tp_itemsize).

- The requested PyType_Spec.basicsize is positive, suggesting that the memory layout of the base class is known.
- The requested PyType_Spec.basicsize is zero, suggesting that the subclass does not access the instance's memory directly.
- With the Py TPFLAGS ITEMS AT END flag.

unsigned int flags

Type flags, used to set PyTypeObject.tp_flags.

If the Py_TPFLAGS_HEAPTYPE flag is not set, PyType_FromSpecWithBases() sets it automatically.

PyType_Slot *slots

Array of PyType_Slot structures. Terminated by the special slot value {0, NULL}.

Each slot ID should be specified at most once.

type PyType_Slot

Part of the Stable ABI (including all members). Structure defining optional functionality of a type, containing a slot ID and a value pointer.

int **slot**

A slot ID.

Slot IDs are named like the field names of the structures <code>PyTypeObject</code>, <code>PyNumberMethods</code>, <code>PySequenceMethods</code>, <code>PyMappingMethods</code> and <code>PyAsyncMethods</code> with an added <code>Py_prefix</code>. For example, use:

- Py_tp_dealloc to set PyTypeObject.tp_dealloc
- Py nb add to set PyNumberMethods.nb add
- Py_sq_length to set PySequenceMethods.sq_length

The following "offset" fields cannot be set using PyType_Slot:

- tp_weaklistoffset (use Py_TPFLAGS_MANAGED_WEAKREF instead if possible)
- tp_dictoffset (use Py_TPFLAGS_MANAGED_DICT instead if possible)
- tp_vectorcall_offset (use "__vectorcalloffset__" in PyMember-Def)

If it is not possible to switch to a MANAGED flag (for example, for vectorcall or to support Python older than 3.12), specify the offset in Py_tp_members. See PyMemberDef documentation for details.

The following fields cannot be set at all when creating a heap type:

- tp_vectorcall (use tp_new and/or tp_init)
- Internal fields: tp_dict, tp_mro, tp_cache, tp_subclasses, and tp_weaklist.

Setting Py_tp_bases or Py_tp_base may be problematic on some platforms. To avoid issues, use the *bases* argument of PyType_FromSpecWithBases() instead.

Modifié dans la version 3.9 : Slots in *PyBufferProcs* may be set in the unlimited API.

Modifié dans la version $3.11: bf_getbuffer$ and $bf_releasebuffer$ are now available under the limited API.

void *pfunc

The desired value of the slot. In most cases, this is a pointer to a function.

Slots other than Py_tp_doc may not be NULL.

8.1.2 L'objet None

Note that the PyTypeObject for None is not directly exposed in the Python/C API. Since None is a singleton, testing for object identity (using == in C) is sufficient. There is no PyNone_Check () function for the same reason.

PyObject *Py_None

The Python None object, denoting lack of value. This object has no methods and is immortal.

Modifié dans la version 3.12 : Py None is immortal.

Py RETURN NONE

Return Py_None from a function.

8.2 Objets numériques

8.2.1 Objets Integer

All integers are implemented as "long" integer objects of arbitrary size.

On error, most PyLong_As* APIs return (return type) -1 which cannot be distinguished from a number. Use PyErr_Occurred() to disambiguate.

type PyLongObject

Part of the Limited API (as an opaque struct). This subtype of PyObject represents a Python integer object.

PyTypeObject PyLong_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python integer type. This is the same object as int in the Python layer.

int PyLong_Check (*PyObject* *p)

Return true if its argument is a PyLongObject or a subtype of PyLongObject. This function always succeeds.

int PyLong_CheckExact (PyObject *p)

Return true if its argument is a PyLongObject, but not a subtype of PyLongObject. This function always succeeds.

PyObject *PyLong_FromLong (long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from v, or NULL on failure.

The current implementation keeps an array of integer objects for all integers between -5 and 256. When you create an int in that range you actually just get back a reference to the existing object.

PyObject *PyLong_FromUnsignedLong (unsigned long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C unsigned long, or NULL on failure.

PyObject *PyLong_FromSsize_t (Py_ssize_t v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C Py_ssize_t, or NULL on failure.

PyObject *PyLong_FromSize_t (size_t v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C size_t, or NULL on failure.

PyObject *PyLong_FromLongLong (long long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C long long, or NULL on failure.

PyObject *PyLong_FromUnsignedLongLong (unsigned long long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C unsigned long long, or NULL on failure.

PyObject *PyLong_FromDouble (double v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from the integer part of v, or NULL on failure.

PyObject *PyLong_FromString (const char *str, char **pend, int base)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject based on the string value in str, which is interpreted according to the radix in base, or NULL on failure. If pend is non-NULL, *pend will point to the end of str on success or to the first character that could not be processed on error. If base is 0, str is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a ValueError. If base is not 0, it must be between 2 and 36, inclusive. Leading and trailing whitespace and single underscores after a base specifier and between digits are ignored. If there are no digits or str is not NULL-terminated following the digits and trailing whitespace, ValueError will be raised.

Voir aussi:

Python methods int.to_bytes() and int.from_bytes() to convert a PyLongObject to/from an array of bytes in base 256. You can call those from C using PyObject_CallMethod().

PyObject *PyLong_FromUnicodeObject (PyObject *u, int base)

Return value : New reference. Convert a sequence of Unicode digits in the string *u* to a Python integer value. Nouveau dans la version 3.3.

PyObject *PyLong_FromVoidPtr (void *p)

Return value: New reference. Part of the Stable ABI. Create a Python integer from the pointer p. The pointer value can be retrieved from the resulting value using $PyLong_AsVoidPtr()$.

long PyLong_AsLong (PyObject *obj)

Part of the Stable ABI. Return a Clong representation of obj. If obj is not an instance of PyLongObject, first call its __index__() method (if present) to convert it to a PyLongObject.

Raise OverflowError if the value of *obj* is out of range for a long.

Returns -1 on error. Use PyErr_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use __index__() if available.

Modifié dans la version 3.10 : This function will no longer use __int__().

long PyLong_AsLongAndOverflow (PyObject *obj, int *overflow)

Part of the Stable ABI. Return a Clong representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than LONG_MAX or less than LONG_MIN, set **overflow* to 1 or -1, respectively, and return -1; otherwise, set **overflow* to 0. If any other exception occurs set **overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use __index__() if available.

Modifié dans la version 3.10 : This function will no longer use __int__().

long long PyLong_AsLongLong (PyObject *obj)

Part of the Stable ABI. Return a C long long representation of obj. If obj is not an instance of PyLongObject, first call its __index__() method (if present) to convert it to a PyLongObject.

Raise OverflowError if the value of *obj* is out of range for a long long.

Returns -1 on error. Use PyErr_Occurred () to disambiguate.

```
Modifié dans la version 3.8 : Use __index__() if available.
```

Modifié dans la version 3.10 : This function will no longer use ___int___().

long long PyLong_AsLongLongAndOverflow (PyObject *obj, int *overflow)

Part of the Stable ABI. Return a Clong long representation of obj. If obj is not an instance of PyLongObject, first call its __index__() method (if present) to convert it to a PyLongObject.

If the value of *obj* is greater than LLONG_MAX or less than LLONG_MIN, set **overflow* to 1 or -1, respectively, and return -1; otherwise, set **overflow* to 0. If any other exception occurs set **overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr_Occurred () to disambiguate.

Nouveau dans la version 3.2.

Modifié dans la version 3.8 : Use __index__() if available.

Modifié dans la version 3.10 : This function will no longer use __int__().

Py_ssize_t PyLong_AsSsize_t (PyObject *pylong)

Part of the Stable ABI. Return a C Py_ssize_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a *Py_ssize_t*.

Returns -1 on error. Use PyErr_Occurred() to disambiguate.

unsigned long PyLong_AsUnsignedLong (PyObject *pylong)

Part of the Stable ABI. Return a C unsigned long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a unsigned long.

Returns (unsigned long) -1 on error. Use PyErr_Occurred() to disambiguate.

size_t PyLong_AsSize_t (*PyObject* *pylong)

Part of the Stable ABI. Return a C size_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a size t.

Returns (size_t) -1 on error. Use PyErr_Occurred() to disambiguate.

unsigned long long PyLong_AsUnsignedLongLong (PyObject *pylong)

Part of the Stable ABI. Return a C unsigned long long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for an unsigned long long.

Returns (unsigned long long) -1 on error. Use PyErr_Occurred() to disambiguate.

 $Modifi\'e \ dans \ la \ version \ 3.1: A \ negative \ pylong \ now \ raises \ {\tt OverflowError}, \ not \ {\tt TypeError}.$

unsigned long PyLong AsUnsignedLongMask (PyObject *obj)

Part of the Stable ABI. Return a C unsigned long representation of obj. If obj is not an instance of PyLongObject, first call its __index__() method (if present) to convert it to a PyLongObject.

If the value of *obj* is out of range for an unsigned long, return the reduction of that value modulo ULONG_MAX + 1.

Returns (unsigned long) -1 on error. Use PyErr_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use __index__ () if available.

Modifié dans la version 3.10 : This function will no longer use int ().

unsigned long long PyLong_AsUnsignedLongLongMask (PyObject *obj)

Part of the Stable ABI. Return a C unsigned long long representation of obj. If obj is not an instance of PyLongObject, first call its __index__() method (if present) to convert it to a PyLongObject.

If the value of obj is out of range for an unsigned long long, return the reduction of that value modulo ULLONG MAX + 1.

Returns (unsigned long long) -1 on error. Use PyErr_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use __index__() if available.

Modifié dans la version 3.10 : This function will no longer use int ().

double PyLong_AsDouble (*PyObject* *pylong)

Part of the Stable ABI. Return a C double representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a double.

Returns -1.0 on error. Use PyErr_Occurred() to disambiguate.

void *PyLong_AsVoidPtr (PyObject *pylong)

Part of the Stable ABI. Convert a Python integer pylong to a C void pointer. If pylong cannot be converted, an OverflowError will be raised. This is only assured to produce a usable void pointer for values created with PyLong FromVoidPtr().

Returns NULL on error. Use PyErr_Occurred () to disambiguate.

int PyUnstable_Long_IsCompact (const PyLongObject *op)

This is *Unstable API*. It may change without warning in minor releases.

Return 1 if op is compact, 0 otherwise.

This function makes it possible for performance-critical code to implement a "fast path" for small integers. For compact values use $PyUnstable_Long_CompactValue()$; for others fall back to a $PyLong_As*$ function or calling int.to_bytes().

The speedup is expected to be negligible for most users.

Exactly what values are considered compact is an implementation detail and is subject to change.

Py_ssize_t PyUnstable_Long_CompactValue (const PyLongObject *op)

This is *Unstable API*. It may change without warning in minor releases.

If op is compact, as determined by PyUnstable Long IsCompact(), return its value.

Otherwise, the return value is undefined.

8.2.2 Les objets booléens

Booleans in Python are implemented as a subclass of integers. There are only two booleans, Py_False and Py_True. As such, the normal creation and deletion functions don't apply to booleans. The following macros are available, however.

PyTypeObject PyBool_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python boolean type; it is the same object as bool in the Python layer.

int PyBool_Check (PyObject *o)

Renvoie vrai si *o* est de type PyBook_Type. Cette fonction réussit systématiquement.

PyObject *Py False

The Python False object. This object has no methods and is immortal.

Modifié dans la version 3.12 : Py_False is immortal.

PyObject *Py_True

The Python True object. This object has no methods and is immortal.

Modifié dans la version 3.12 : Py_True is immortal.

Py RETURN FALSE

Return Py_False from a function.

Py_RETURN_TRUE

Return Py True from a function.

PyObject *PyBool_FromLong (long v)

Return value: New reference. Part of the Stable ABI. Return Py_True or Py_False, depending on the truth value of v.

8.2.3 Objets représentant les nombres à virgule flottante

type PyFloatObject

Ce sous-type de l'objet PyObject représente un nombre à virgule flottante en Python.

PyTypeObject PyFloat_Type

Part of the Stable ABI. Cette instance de l'objet PyTypeObject représente le type nombre à virgule flottante en Python. C'est le même objet que la classe float de la couche Python.

int PyFloat_Check (PyObject *p)

Return true if its argument is a PyFloatObject or a subtype of PyFloatObject. This function always succeeds.

int PyFloat_CheckExact (PyObject *p)

Return true if its argument is a PyFloatObject, but not a subtype of PyFloatObject. This function always succeeds.

PyObject *PyFloat_FromString (PyObject *str)

Return value : New reference. Part of the Stable ABI. Create a *PyFloatObject* object based on the string value in *str*, or NULL on failure.

PyObject *PyFloat_FromDouble (double v)

Return value: New reference. Part of the Stable ABI. Create a PyFloatObject object from v, or NULL on failure.

double PyFloat_AsDouble (*PyObject* *pyfloat)

Part of the Stable ABI. Return a C double representation of the contents of pyfloat. If pyfloat is not a Python floating point object but has a __float__() method, this method will first be called to convert pyfloat into a float. If __float__() is not defined then it falls back to __index__(). This method returns -1.0 upon failure, so one should call PyErr Occurred() to check for errors.

Modifié dans la version 3.8 : Use __index__() if available.

double PyFloat_AS_DOUBLE (PyObject *pyfloat)

Return a C double representation of the contents of *pyfloat*, but without error checking.

PyObject *PyFloat_GetInfo (void)

Return value: New reference. Part of the Stable ABI. Renvoie une instance structseq qui contient les informations sur la précision et les valeurs minimales et maximales pour un nombre à virgule flottante. C'est une enveloppe autour du fichier d'entête float.h.

```
double PyFloat GetMax()
```

Part of the Stable ABI. Return the maximum representable finite float DBL_MAX as C double.

```
double PyFloat_GetMin()
```

Part of the Stable ABI. Return the minimum normalized positive float DBL MIN as C double.

Pack and Unpack functions

The pack and unpack functions provide an efficient platform-independent way to store floating-point values as byte strings. The Pack routines produce a bytes string from a C double, and the Unpack routines produce a C double from such a bytes string. The suffix (2, 4 or 8) specifies the number of bytes in the bytes string.

On platforms that appear to use IEEE 754 formats these functions work by copying bits. On other platforms, the 2-byte format is identical to the IEEE 754 binary16 half-precision format, the 4-byte format (32-bit) is identical to the IEEE 754 binary32 single precision format, and the 8-byte format to the IEEE 754 binary64 double precision format, although the packing of INFs and NaNs (if such things exist on the platform) isn't handled correctly, and attempting to unpack a bytes string containing an IEEE INF or NaN will raise an exception.

On non-IEEE platforms with more precision, or larger dynamic range, than IEEE 754 supports, not all values can be packed; on non-IEEE platforms with less precision, or smaller dynamic range, not all values can be unpacked. What happens in such cases is partly accidental (alas).

Nouveau dans la version 3.11.

Pack functions

The pack routines write 2, 4 or 8 bytes, starting at p. le is an int argument, non-zero if you want the bytes string in little-endian format (exponent last, at p+1, p+3, or p+6 p+7), zero if you want big-endian format (exponent first, at p). The PY_BIG_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: 0 if all is OK, -1 if error (and an exception is set, most likely OverflowError).

There are two problems on non-IEEE platforms:

- What this does is undefined if x is a NaN or infinity.
- -0.0 and +0.0 produce the same bytes string.

int PyFloat_Pack2 (double x, unsigned char *p, int le)

Pack a C double as the IEEE 754 binary16 half-precision format.

int PyFloat_Pack4 (double x, unsigned char *p, int le)

Pack a C double as the IEEE 754 binary32 single precision format.

int PyFloat_Pack8 (double x, unsigned char *p, int le)

Pack a C double as the IEEE 754 binary64 double precision format.

Unpack functions

The unpack routines read 2, 4 or 8 bytes, starting at p. le is an int argument, non-zero if the bytes string is in little-endian format (exponent last, at p+1, p+3 or p+6 and p+7), zero if big-endian (exponent first, at p). The PY_BIG_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: The unpacked double. On error, this is -1.0 and $PyErr_Occurred()$ is true (and an exception is set, most likely OverflowError).

Note that on a non-IEEE platform this will refuse to unpack a bytes string that represents a NaN or infinity.

```
double PyFloat_Unpack2 (const unsigned char *p, int le)
```

Unpack the IEEE 754 binary16 half-precision format as a C double.

```
double PyFloat_Unpack4 (const unsigned char *p, int le)
```

Unpack the IEEE 754 binary32 single precision format as a C double.

```
double PyFloat_Unpack8 (const unsigned char *p, int le)
```

Unpack the IEEE 754 binary64 double precision format as a C double.

8.2.4 Objets représentant des nombres complexes

Les nombres complexes Python sont implémentés comme deux types distincts, lorsqu'ils sont vus de l'API C : l'un est l'objet Python tel qu'il est vu par les programmes Python, et l'autre est une structure C qui représente la valeur exacte du nombre complexe. L'API fournit des fonctions pour travailler avec ces deux représentations.

Nombres complexes en tant que structures C

Les fonctions qui acceptent ces structures comme paramètres et les renvoient comme résultats le font en fonction de leur *valeur* au lieu de les dé-référencer en utilisant des pointeurs. C'est constant dans toute l'API.

type Py_complex

Structure C représentant la valeur d'un nombre complexe Python. La majorité des fonctions qui traitent des nombres complexes utilisent cette structure en entrée ou en sortie, selon le cas. Elle est définie par :

```
typedef struct {
   double real;
   double imag;
} Py_complex;
```

```
Py_complex _Py_c_sum (Py_complex left, Py_complex right)
```

Renvoie la somme de deux nombres complexes, sous la forme d'un Py_complex en C.

```
Py_complex _Py_c_diff (Py_complex left, Py_complex right)
```

Renvoie la différence de deux nombres complexes, sous la forme d'un Py_complex en C.

```
Py_complex _Py_c_neg (Py_complex num)
```

Return the negation of the complex number *num*, using the C Py_complex representation.

```
Py_complex _Py_c_prod (Py_complex left, Py_complex right)
```

Renvoie le produit de deux nombres complexes, sous la forme d'un Py_complex en C.

```
Py_complex _Py_c_quot (Py_complex dividend, Py_complex divisor)
```

Renvoie le quotient de deux nombres complexes, sous la forme d'un Py_complex en C.

If divisor is null, this method returns zero and sets errno to EDOM.

Py_complex **_Py_c_pow** (*Py_complex* num, *Py_complex* exp)

Renvoie *num* à la puissance *exp*, sous la forme d'un *Py_complex* en C.

If *num* is null and *exp* is not a positive real number, this method returns zero and sets errno to EDOM.

Nombres complexes en tant qu'objets Python

type PyComplexObject

Ce sous-type de l'objet PyObject représente un nombre complexe en Python.

PyTypeObject PyComplex_Type

Part of the Stable ABI. Cette instance de PyTypeObject représente le type nombre complexe Python. C'est le même objet que la classe complex de la couche Python.

int PyComplex_Check (PyObject *p)

Return true if its argument is a PyComplexObject or a subtype of PyComplexObject. This function always succeeds.

int PyComplex_CheckExact (PyObject *p)

Return true if its argument is a PyComplexObject, but not a subtype of PyComplexObject. This function always succeeds.

PyObject *PyComplex_FromCComplex (Py_complex v)

Return value : New reference. Crée un nouveau nombre complexe à partir de la valeur d'un Py_complex en C.

PyObject *PyComplex_FromDoubles (double real, double imag)

Return value : New reference. Part of the Stable ABI. Renvoie un nouveau PyComplexObject à partir de real et de imag.

double PyComplex_RealAsDouble (PyObject *op)

Part of the Stable ABI. Return the real part of op as a C double.

double PyComplex_ImagAsDouble (PyObject *op)

Part of the Stable ABI. Return the imaginary part of op as a C double.

Py_complex PyComplex_AsCComplex (PyObject *op)

Renvoie la valeur du nombre complexe op sous la forme d'un Py_complex en C.

If op is not a Python complex number object but has a __complex__() method, this method will first be called to convert op to a Python complex number object. If __complex__() is not defined then it falls back to __float__(). If __float__() is not defined then it falls back to __index__(). Upon failure, this method returns -1.0 as a real value.

Modifié dans la version 3.8 : Use __index__() if available.

8.3 Objets séquences

Les opérations génériques sur les objets séquences ont été discutées dans le chapitre précédent. Cette section traite des genres spécifiques d'objets séquences qui sont intrinsèques au langage Python.

8.3.1 Objets bytes

These functions raise TypeError when expecting a bytes parameter and called with a non-bytes parameter.

type PyBytesObject

This subtype of PyObject represents a Python bytes object.

PyTypeObject PyBytes_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python bytes type; it is the same object as bytes in the Python layer.

int PyBytes_Check (PyObject *o)

Return true if the object o is a bytes object or an instance of a subtype of the bytes type. This function always succeeds.

int PyBytes_CheckExact (PyObject *o)

Return true if the object o is a bytes object, but not an instance of a subtype of the bytes type. This function always succeeds.

PyObject *PyBytes_FromString (const char *v)

Return value : New reference. Part of the Stable ABI. Return a new bytes object with a copy of the string *v* as value on success, and NULL on failure. The parameter *v* must not be NULL; it will not be checked.

PyObject *PyBytes_FromStringAndSize (const char *v, Py_ssize_t len)

Return value: New reference. Part of the Stable ABI. Return a new bytes object with a copy of the string v as value and length len on success, and NULL on failure. If v is NULL, the contents of the bytes object are uninitialized.

PyObject *PyBytes_FromFormat (const char *format, ...)

Return value: New reference. Part of the Stable ABI. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format string. The following format characters are allowed:

Caractères de format	Туре	Comment
%%	n/a	The literal % character.
%C	int	A single byte, represented as a C int.
%d	int	Equivalent to printf("%d").
%u	unsigned int	Equivalent to printf("%u").
%ld	long	Equivalent to printf("%ld").
%lu	unsigned long	Equivalent to printf("%lu").1
%zd	Py_ssize_t	Equivalent to printf("%zd").1
%zu	size_t	Equivalent to printf("%zu").1
%i	int	Equivalent to printf("%i").1
%X	int	Equivalent to printf("%x").1
%S	const char*	A null-terminated C character array.
%p	const void*	The hex representation of a C pointer. Mostly equivalent to
		printf("%p") except that it is guaranteed to start with
		the literal 0x regardless of what the platform's printf
		yields.

An unrecognized format character causes all the rest of the format string to be copied as-is to the result object, and any extra arguments discarded.

^{1.} For integer specifiers (d, u, ld, lu, zd, zu, i, x): the 0-conversion flag has effect even when a precision is given.

PyObject *PyBytes_FromFormatV (const char *format, va_list vargs)

Return value : New reference. Part of the Stable ABI. Identical to *PyBytes_FromFormat()* except that it takes exactly two arguments.

PyObject *PyBytes_FromObject (PyObject *o)

Return value: New reference. Part of the Stable ABI. Return the bytes representation of object o that implements the buffer protocol.

Py_ssize_t PyBytes_Size (PyObject *o)

Part of the Stable ABI. Return the length of the bytes in bytes object o.

Py_ssize_t PyBytes_GET_SIZE (PyObject *o)

Similar to PyBytes_Size(), but without error checking.

char *PyBytes_AsString (PyObject *o)

Part of the Stable ABI. Return a pointer to the contents of o. The pointer refers to the internal buffer of o, which consists of len(o) + 1 bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using PyBytes_FromStringAndSize(NULL, size). It must not be deallocated. If o is not a bytes object at all, $PyBytes_AsString()$ returns NULL and raises TypeError.

char *PyBytes_AS_STRING (PyObject *string)

Similar to PyBytes_AsString(), but without error checking.

int **PyBytes_AsStringAndSize** (*PyObject* *obj, char **buffer, *Py_ssize_t* *length)

Part of the Stable ABI. Return the null-terminated contents of the object obj through the output variables buffer and length.

If *length* is NULL, the bytes object may not contain embedded null bytes; if it does, the function returns -1 and a ValueError is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using PyBytes_FromStringAndSize(NULL, size). It must not be deallocated. If *obj* is not a bytes object at all, *PyBytes_AsStringAndSize()* returns -1 and raises TypeError.

Modifié dans la version 3.5 : Previously, TypeError was raised when embedded null bytes were encountered in the bytes object.

void PyBytes_Concat (PyObject **bytes, PyObject *newpart)

Part of the Stable ABI. Create a new bytes object in *bytes containing the contents of newpart appended to bytes; the caller will own the new reference. The reference to the old value of bytes will be stolen. If the new object cannot be created, the old reference to bytes will still be discarded and the value of *bytes will be set to NULL; the appropriate exception will be set.

void PyBytes_ConcatAndDel (PyObject **bytes, PyObject *newpart)

Part of the Stable ABI. Create a new bytes object in *bytes containing the contents of newpart appended to bytes. This version releases the strong reference to newpart (i.e. decrements its reference count).

```
int _PyBytes_Resize (PyObject **bytes, Py_ssize_t newsize)
```

A way to resize a bytes object even though it is "immutable". Only use this to build up a brand new bytes object; don't use this if the bytes may already be known in other parts of the code. It is an error to call this function if the refcount on the input bytes object is not one. Pass the address of an existing bytes object as an Ivalue (it may be written into), and the new size desired. On success, *bytes holds the resized bytes object and 0 is returned; the address in *bytes may differ from its input value. If the reallocation fails, the original bytes object at *bytes is deallocated, *bytes is set to NULL, MemoryError is set, and -1 is returned.

8.3.2 Objets tableau d'octets

type PyByteArrayObject

Ce sous-type de PyObject représente un objet bytearray Python.

PyTypeObject PyByteArray_Type

Part of the Stable ABI. Cette instance de PyTypeObject représente le type Python bytearray, c'est le même que bytearray côté Python.

Macros de vérification de type

int PyByteArray_Check (PyObject *o)

Renvoie vrai si l'objet o est un bytearray ou une instance d'un sous-type du type bytearray. Cette méthode réussit toujours.

int PyByteArray_CheckExact (PyObject *o)

Renvoie vrai si l'objet *o* est un bytearray, mais pas une instance d'un sous-type du type bytearray. Cette méthode réussit toujours.

Fonctions directes sur l'API

PyObject *PyByteArray_FromObject (PyObject *o)

Return value : New reference. Part of the Stable ABI. Renvoie un nouvel objet bytearray depuis n'importe quel objet, o, qui implémente le protocole buffer.

PyObject *PyByteArray_FromStringAndSize (const char *string, Py_ssize_t len)

Return value: New reference. Part of the Stable ABI. Crée un nouvel objet bytearray à partir d'un objet string et de sa longueur, len. En cas d'échec, NULL est renvoyé.

PyObject *PyByteArray_Concat (PyObject *a, PyObject *b)

Return value: New reference. Part of the Stable ABI. Concatène les bytearrays a et b et renvoie un nouveau bytearray avec le résultat.

Py_ssize_t **PyByteArray_Size** (*PyObject* *bytearray)

Part of the Stable ABI. Renvoie la taille de bytearray après vérification de la présence d'un pointeur NULL.

char *PyByteArray_AsString (PyObject *bytearray)

Part of the Stable ABI. Renvoie le contenu de bytearray sous forme d'un tableau de caractères, en vérifiant que ce n'est pas un pointeur NULL. Le tableau renvoyé a toujours un caractère null rajouté.

```
int PyByteArray_Resize (PyObject *bytearray, Py_ssize_t len)
```

Part of the Stable ABI. Redimensionne le tampon interne de bytearray à la taille len.

Macros

Ces macros sont taillées pour la vitesse d'exécution et ne vérifient pas les pointeurs.

char *PyByteArray_AS_STRING (*PyObject* *bytearray)

Similar to PyByteArray_AsString(), but without error checking.

Py_ssize_t PyByteArray_GET_SIZE (PyObject *bytearray)

Similar to PyByteArray_Size(), but without error checking.

8.3.3 Objets Unicode et Codecs

Objets Unicode

Depuis l'implémentation de **PEP 393** dans Python 3.3, les objets Unicode utilisent une variété de représentations internes, pour permettre de gérer l'intervalle complet des caractères Unicode en restant efficace en termes de mémoire. Il y a des cas spéciaux pour les chaînes où tous les points de code sont inférieurs à 128, 256, ou 65536; sinon, les points de code doivent être inférieurs à 1114112 (qui est l'intervalle Unicode complet).

UTF-8 representation is created on demand and cached in the Unicode object.

Note: The *Py_UNICODE* representation has been removed since Python 3.12 with deprecated APIs. See **PEP 623** for more information.

Type Unicode

Voici les types d'objets Unicode utilisés pour l'implémentation Unicode en Python :

type Py_UCS4

type Py_UCS2

type Py_UCS1

Part of the Stable ABI. Voici les typedefs pour les types entiers non signés suffisamment large pour contenir des caractères de 32 bits, 16 bits et 8 bits, respectivement. Pour traiter des caractères uniques, utilisez Py_UCS4. Nouveau dans la version 3.3.

type Py_UNICODE

This is a typedef of wchar t, which is a 16-bit type or 32-bit type depending on the platform.

Modifié dans la version 3.3 : Dans les versions précédentes, ceci était un type 16-bit ou un type 32-bit selon que vous choisissiez une version Unicode *narrow* ou *wide* de Python à la compilation.

type PyASCIIObject

type PyCompactUnicodeObject

type PyUnicodeObject

These subtypes of *PyObject* represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return *PyObject* pointers.

Nouveau dans la version 3.3.

PyTypeObject PyUnicode Type

Part of the Stable ABI. This instance of *PyTypeObject* represents the Python Unicode type. It is exposed to Python code as str.

The following APIs are C macros and static inlined functions for fast checks and access to internal read-only data of Unicode objects :

int PyUnicode_Check (PyObject *o)

Return true if the object o is a Unicode object or an instance of a Unicode subtype. This function always succeeds.

int PyUnicode_CheckExact (PyObject *o)

Return true if the object o is a Unicode object, but not an instance of a subtype. This function always succeeds.

int PyUnicode_READY (PyObject *o)

Returns 0. This API is kept only for backward compatibility.

Nouveau dans la version 3.3.

Obsolète depuis la version 3.10 : This API does nothing since Python 3.12.

```
Py_ssize_t PyUnicode_GET_LENGTH (PyObject *o)
```

Return the length of the Unicode string, in code points. *o* has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

```
Py_UCS1 *PyUnicode_1BYTE_DATA (PyObject *o)
```

```
Py_UCS2 *PyUnicode_2BYTE_DATA (PyObject *o)
```

```
Py_UCS4 *PyUnicode_4BYTE_DATA (PyObject *o)
```

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use PyUnicode KIND() to select the right function.

Nouveau dans la version 3.3.

```
PyUnicode_1BYTE_KIND
```

PyUnicode_2BYTE_KIND

PyUnicode_4BYTE_KIND

Return values of the PyUnicode_KIND() macro.

Nouveau dans la version 3.3.

Modifié dans la version 3.12: PyUnicode WCHAR KIND has been removed.

```
int PyUnicode_KIND (PyObject *o)
```

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. o has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

```
void *PyUnicode DATA (PyObject *o)
```

Return a void pointer to the raw Unicode buffer. o has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

```
void PyUnicode_WRITE (int kind, void *data, Py_ssize_t index, Py_UCS4 value)
```

Write into a canonical representation *data* (as obtained with *PyUnicode_DATA()*). This function performs no sanity checks, and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

Nouveau dans la version 3.3.

Py_UCS4 PyUnicode_READ (int kind, void *data, Py_ssize_t index)

Read a code point from a canonical representation *data* (as obtained with *PyUnicode_DATA()*). No checks or ready calls are performed.

Nouveau dans la version 3.3.

```
Py_UCS4 PyUnicode_READ_CHAR (PyObject *o, Py_ssize_t index)
```

Read a character from a Unicode object o, which must be in the "canonical" representation. This is less efficient than $PyUnicode_READ()$ if you do multiple consecutive reads.

Nouveau dans la version 3.3.

Py_UCS4 PyUnicode_MAX_CHAR_VALUE (PyObject *o)

Return the maximum code point that is suitable for creating another string based on o, which must be in the "canonical" representation. This is always an approximation but more efficient than iterating over the string.

Nouveau dans la version 3.3.

int PyUnicode_IsIdentifier (PyObject *o)

Part of the Stable ABI. Return 1 if the string is a valid identifier according to the language definition, section identifiers. Return 0 otherwise.

Modifié dans la version 3.9: The function does not call Py_FatalError() anymore if the string is not ready.

Unicode Character Properties

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

```
int Py_UNICODE_ISSPACE (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a whitespace character.

```
int Py_UNICODE_ISLOWER (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a lowercase character.

```
int Py_UNICODE_ISUPPER (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is an uppercase character.

```
int Py_UNICODE_ISTITLE (Py_UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is a titlecase character.

```
int Py_UNICODE_ISLINEBREAK (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a linebreak character.

```
int Py UNICODE ISDECIMAL (Py UCS4 ch)
```

Return 1 or 0 depending on whether ch is a decimal character.

```
int Py_UNICODE_ISDIGIT (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a digit character.

```
int Py_UNICODE_ISNUMERIC (Py_UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is a numeric character.

```
int Py_UNICODE_ISALPHA (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is an alphabetic character.

```
int Py_UNICODE_ISALNUM (Py_UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is an alphanumeric character.

```
int Py_UNICODE_ISPRINTABLE (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a printable character. Nonprintable characters are those characters defined in the Unicode character database as "Other" or "Separator", excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when repr() is invoked on a string. It has no bearing on the handling of strings written to sys.stdout or sys.stdout.)

These APIs can be used for fast direct character conversions:

```
Py_UCS4 Py_UNICODE_TOLOWER (Py_UCS4 ch)
```

Return the character *ch* converted to lower case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

Py_UCS4 Py_UNICODE_TOUPPER (Py_UCS4 ch)

Return the character ch converted to upper case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

Py_UCS4 Py_UNICODE_TOTITLE (Py_UCS4 ch)

Return the character *ch* converted to title case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

```
int Py_UNICODE_TODECIMAL (Py_UCS4 ch)
```

Return the character ch converted to a decimal positive integer. Return -1 if this is not possible. This function does not raise exceptions.

```
int Py_UNICODE_TODIGIT (Py_UCS4 ch)
```

Return the character ch converted to a single digit integer. Return -1 if this is not possible. This function does not raise exceptions.

```
double Py_UNICODE_TONUMERIC (Py_UCS4 ch)
```

Return the character ch converted to a double. Return -1.0 if this is not possible. This function does not raise exceptions.

These APIs can be used to work with surrogates:

```
int Py_UNICODE_IS_SURROGATE (Py_UCS4 ch)
```

Check if ch is a surrogate (0xD800 <= ch <= 0xDFFF).

```
int Py_UNICODE_IS_HIGH_SURROGATE (Py_UCS4 ch)
```

Check if ch is a high surrogate (0xD800 <= ch <= 0xDBFF).

```
int Py_UNICODE_IS_LOW_SURROGATE (Py_UCS4 ch)
```

Check if ch is a low surrogate (0xDC00 <= ch <= 0xDFFF).

```
Py_UCS4 Py_UNICODE_JOIN_SURROGATES (Py_UCS4 high, Py_UCS4 low)
```

Join two surrogate characters and return a single Py_UCS4 value. high and low are respectively the leading and trailing surrogates in a surrogate pair. high must be in the range [0xD800; 0xDBFF] and low must be in the range [0xDC00; 0xDFFF].

Creating and accessing Unicode strings

To create Unicode objects and access their basic sequence properties, use these APIs:

```
PyObject *PyUnicode_New (Py_ssize_t size, Py_UCS4 maxchar)
```

Return value : New reference. Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable. Nouveau dans la version 3.3.

PyObject *PyUnicode_FromKindAndData (int kind, const void *buffer, Py_ssize_t size)

Return value: New reference. Create a new Unicode object with the given kind (possible values are PyUnicode_1BYTE_KIND etc., as returned by PyUnicode_KIND()). The buffer must point to an array of size units of 1, 2 or 4 bytes per character, as given by the kind.

If necessary, the input *buffer* is copied and transformed into the canonical representation. For example, if the *buffer* is a UCS4 string (*PyUnicode_4BYTE_KIND*) and it consists only of codepoints in the UCS1 range, it will be transformed into UCS1 (*PyUnicode_1BYTE_KIND*).

Nouveau dans la version 3.3.

PyObject *PyUnicode_FromStringAndSize (const char *u, Py_ssize_t size)

Return value: New reference. Part of the Stable ABI. Create a Unicode object from the char buffer u. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. The return value might be a shared object, i.e. modification of the data is not allowed.

This function raises SystemError when:

- -- size < 0,
- u is NULL and size > 0

Modifié dans la version 3.12: u == NULL with size > 0 is not allowed anymore.

PyObject *PyUnicode_FromString (const char *u)

Return value: New reference. Part of the Stable ABI. Create a Unicode object from a UTF-8 encoded null-terminated char buffer u.

PyObject *PyUnicode_FromFormat (const char *format, ...)

Return value: New reference. Part of the Stable ABI. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format ASCII-encoded string.

A conversion specifier contains two or more characters and has the following components, which must occur in this order:

- 1. The '%' character, which marks the start of the specifier.
- 2. Conversion flags (optional), which affect the result of some conversion types.
- 3. Minimum field width (optional). If specified as an '*' (asterisk), the actual width is given in the next argument, which must be of type int, and the object to convert comes after the minimum field width and optional precision.
- 4. Precision (optional), given as a '.' (dot) followed by the precision. If specified as '*' (an asterisk), the actual precision is given in the next argument, which must be of type int, and the value to convert comes after the precision.
- 5. Length modifier (optional).
- 6. Conversion type.

The conversion flag characters are:

Flag	Meaning
0	The conversion will be zero padded for numeric values.
_	The converted value is left adjusted (overrides the 0 flag if both are given).

The length modifiers for following integer conversions (d, i, o, u, x, or X) specify the type of the argument (int by default):

Modifier	Types
1	long or unsigned long
11	long long or unsigned long long
j	intmax_t or uintmax_t
Z	size_t or ssize_t
t	ptrdiff_t

The length modifier 1 for following conversions s or V specify that the type of the argument is const wchar_t*. The conversion specifiers are :

Conver-	Туре	Comment
sion		
Speci-		
fier		
ે	n/a	The literal % character.
d, i	Specified by the length modifier	The decimal representation of a signed C integer.
u	Specified by the length modifier	The decimal representation of an unsigned C integer.
0	Specified by the length modifier	The octal representation of an unsigned C integer.
Х	Specified by the length modifier	The hexadecimal representation of an unsigned C integer (lowercase).
X	Specified by the length modifier	The hexadecimal representation of an unsigned C integer (uppercase).
С	int	A single character.
S	const char* or	A null-terminated C character array.
	const wchar_t*	
р	const void*	The hex representation of a C pointer. Mostly equivalent to
		printf("%p") except that it is guaranteed to start with the li-
		teral 0x regardless of what the platform's printf yields.
А	PyObject*	The result of calling ascii().
U	PyObject*	A Unicode object.
V	PyObject*,	A Unicode object (which may be NULL) and a null-terminated C charac-
	const char* or	ter array as a second parameter (which will be used, if the first parameter
	const wchar_t*	is NULL).
S	PyObject*	The result of calling PyObject_Str().
R	PyObject*	The result of calling PyObject_Repr().

Note: The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes or wchar_t items (if the length modifier 1 is used) for "%s" and "%V" (if the PyObject* argument is NULL), and a number of characters for "%A", "%U", "%S", "%R" and "%V" (if the PyObject* argument is not NULL).

Note: Unlike to C printf() the 0 flag has effect even when a precision is given for integer conversions (d, i, u, o, x, or X).

Modifié dans la version 3.2 : Support for "%lld" and "%llu" added.

Modifié dans la version 3.3 : Support for "%li", "%lli" and "%zi" added.

Modifié dans la version 3.4 : Support width and precision formatter for "%s", "%A", "%U", "%V", "%S", "%R" added.

Modifié dans la version 3.12 : Support for conversion specifiers \circ and X. Support for length modifiers j and t. Length modifiers are now applied to all integer conversions. Length modifier 1 is now applied to conversion specifiers s and V. Support for variable width and precision s. Support for flag s.

An unrecognized format character now sets a SystemError. In previous versions it caused all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

PyObject *PyUnicode_FromFormatV (const char *format, va_list vargs)

Return value: New reference. Part of the Stable ABI. Identical to PyUnicode_FromFormat () except that it takes exactly two arguments.

PyObject *PyUnicode_FromObject (PyObject *obj)

Return value: New reference. Part of the Stable ABI. Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If obj is already a true Unicode object (not a subtype), return a new strong reference to the object.

Objects other than Unicode or its subtypes will cause a TypeError.

PyObject *PyUnicode_FromEncodedObject (PyObject *obj, const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Decode an encoded object obj to a Unicode object.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be NULL to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a TypeError to be set.

The API returns NULL if there was an error. The caller is responsible for decref'ing the returned objects.

Py_ssize_t PyUnicode_GetLength (PyObject *unicode)

Part of the Stable ABI *since version 3.7*. Return the length of the Unicode object, in code points. Nouveau dans la version 3.3.

```
Py_ssize_t PyUnicode_CopyCharacters (PyObject *to, Py_ssize_t to_start, PyObject *from, Py_ssize_t from_start, Py_ssize_t how_many)
```

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to memcpy () if possible. Returns -1 and sets an exception on error, otherwise returns the number of copied characters.

Nouveau dans la version 3.3.

Py_ssize_t PyUnicode_Fill (PyObject *unicode, Py_ssize_t start, Py_ssize_t length, Py_UCS4 fill_char)

Fill a string with a character: write fill_char into unicode[start:start+length].

Fail if *fill_char* is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return -1 and raise an exception on error.

Nouveau dans la version 3.3.

int PyUnicode_WriteChar (PyObject *unicode, Py_ssize_t index, Py_UCS4 character)

Part of the Stable ABI since version 3.7. Write a character to a string. The string must have been created through PyUnicode_New(). Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that it its reference count is one).

Nouveau dans la version 3.3.

Py_UCS4 PyUnicode_ReadChar (PyObject *unicode, Py_ssize_t index)

Part of the Stable ABI since version 3.7. Read a character from a string. This function checks that unicode is a Unicode object and the index is not out of bounds, in contrast to PyUnicode_READ_CHAR(), which performs no error checking.

Nouveau dans la version 3.3.

PyObject *PyUnicode_Substring (PyObject *str, Py_ssize_t start, Py_ssize_t end)

Return value: New reference. Part of the Stable ABI since version 3.7. Return a substring of str, from character index start (included) to character index end (excluded). Negative indices are not supported.

Nouveau dans la version 3.3.

Py_UCS4 *PyUnicode_AsuCS4 (PyObject *u, Py_UCS4 *buffer, Py_ssize_t buflen, int copy_null)

Part of the Stable ABI since version 3.7. Copy the string u into a UCS4 buffer, including a null character, if $copy_null$ is set. Returns NULL and sets an exception on error (in particular, a SystemError if buflen is smaller than the length of u). buffer is returned on success.

Nouveau dans la version 3.3.

Py_UCS4 *PyUnicode_AsUCS4Copy (PyObject *u)

Part of the Stable ABI since version 3.7. Copy the string u into a new UCS4 buffer that is allocated using $PyMem_Malloc()$. If this fails, NULL is returned with a MemoryError set. The returned buffer always has an extra null code point appended.

Nouveau dans la version 3.3.

Locale Encoding

The current locale encoding can be used to decode text from the operating system.

PyObject *PyUnicode DecodeLocaleAndSize (const char *str, Py ssize t len, const char *errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The decoder uses "strict" error handler if errors is NULL. str must end with a null character but cannot contain embedded null characters.

Use PyUnicode_DecodeFSDefaultAndSize() to decode a string from the filesystem encoding and error handler.

This function ignores the Python UTF-8 Mode.

Voir aussi:

The Py_DecodeLocale() function.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, <code>Py_DecodeLocale()</code> was used for the surrogateescape, and the current locale encoding was used for strict.

PyObject *PyUnicode_DecodeLocale (const char *str, const char *errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Similar to PyUnicode_DecodeLocaleAndSize(), but compute the string length using strlen().

Nouveau dans la version 3.3.

PyObject *PyUnicode_EncodeLocale (PyObject *unicode, const char *errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The encoder uses "strict" error handler if errors is NULL. Return a bytes object. unicode cannot contain embedded null characters.

Use PyUnicode_EncodeFSDefault () to encode a string to the filesystem encoding and error handler.

This function ignores the Python UTF-8 Mode.

Voir aussi :

The Py_EncodeLocale() function.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, <code>Py_EncodeLocale()</code> was used for the surrogateescape, and the current locale encoding was used for strict.

File System Encoding

Functions encoding to and decoding from the filesystem encoding and error handler (PEP 383 and PEP 529).

To encode file names to bytes during argument parsing, the "O&" converter should be used, passing PyUnicode_FSConverter() as the conversion function:

int PyUnicode_FSConverter (*PyObject* *obj, void *result)

Part of the Stable ABI. ParseTuple converter: encode str objects -- obtained directly or through the os. PathLike interface -- to bytes using <code>PyUnicode_EncodeFSDefault()</code>; bytes objects are output as-is. result must be a <code>PyBytesObject*</code> which must be released when it is no longer used.

Nouveau dans la version 3.1.

Modifié dans la version 3.6 : Accepte un path-like object.

To decode file names to str during argument parsing, the "O&" converter should be used, passing $PyUnicode_FSDecoder()$ as the conversion function:

int PyUnicode_FSDecoder (PyObject *obj, void *result)

Part of the Stable ABI. ParseTuple converter: decode bytes objects -- obtained either directly or indirectly through the os.PathLike interface -- to str using PyUnicode_DecodeFSDefaultAndSize(); str objects are output as-is. result must be a PyUnicodeObject* which must be released when it is no longer used. Nouveau dans la version 3.2.

Modifié dans la version 3.6 : Accepte un path-like object.

PyObject *PyUnicode DecodeFSDefaultAndSize (const char *s, Py ssize t size)

Return value: New reference. Part of the Stable ABI. Decode a string from the filesystem encoding and error handler. If you need to decode a string from the current locale encoding, use PyUnicode_DecodeLocaleAndSize().

Voir aussi:

The Py_DecodeLocale() function.

Modifié dans la version 3.6 : The *filesystem error handler* is now used.

PyObject *PyUnicode DecodeFSDefault (const char *s)

Return value: New reference. Part of the Stable ABI. Decode a null-terminated string from the filesystem encoding and error handler.

If the string length is known, use PyUnicode DecodeFSDefaultAndSize().

Modifié dans la version 3.6 : The *filesystem error handler* is now used.

PyObject *PyUnicode_EncodeFSDefault (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object to the filesystem encoding and error handler, and return bytes. Note that the resulting bytes object can contain null bytes.

If you need to encode a string to the current locale encoding, use PyUnicode_EncodeLocale().

Voir aussi:

The Py_EncodeLocale() function.

Nouveau dans la version 3.2.

Modifié dans la version 3.6 : The *filesystem error handler* is now used.

wchar_t Support

wchar_t support for platforms which support it:

```
PyObject *PyUnicode_FromWideChar (const wchar_t *w, Py_ssize_t size)
```

Return value: New reference. Part of the Stable ABI. Create a Unicode object from the wchar_t buffer w of the given size. Passing -1 as the size indicates that the function must itself compute the length, using wcslen. Return NULL on failure.

```
Py_ssize_t PyUnicode_AsWideChar (PyObject *unicode, wchar_t *w, Py_ssize_t size)
```

Part of the Stable ABI. Copy the Unicode object contents into the wchar_t buffer w. At most size wchar_t characters are copied (excluding a possibly trailing null termination character). Return the number of wchar_t characters copied or -1 in case of an error. Note that the resulting wchar_t* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the wchar_t* string is null-terminated in case this is required by the application. Also, note that the wchar_t* string might contain null characters, which would cause the string to be truncated when used with most C functions.

```
wchar_t *PyUnicode_AsWideCharString (PyObject *unicode, Py_ssize_t *size)
```

Part of the Stable ABI since version 3.7. Convert the Unicode object to a wide character string. The output string always ends with a null character. If size is not NULL, write the number of wide characters (excluding the trailing null termination character) into *size. Note that the resulting wchar_t string might contain null characters, which would cause the string to be truncated when used with most C functions. If size is NULL and the wchar_t* string contains null characters a ValueError is raised.

Returns a buffer allocated by <code>PyMem_New</code> (use <code>PyMem_Free()</code> to free it) on success. On error, returns <code>NULL</code> and *size is undefined. Raises a <code>MemoryError</code> if memory allocation is failed.

Nouveau dans la version 3.2.

Modifié dans la version 3.7 : Raises a ValueError if size is NULL and the wchar_t* string contains null characters.

Built-in Codecs

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in str() string object constructor.

Setting encoding to NULL causes the default encoding to be used which is UTF-8. The file system calls should use <code>PyUnicode_FSConverter()</code> for encoding file names. This uses the *filesystem encoding and error handler* internally.

Error handling is set by errors which may also be set to NULL meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is "strict" (ValueError is raised).

The codecs all use a similar interface. Only deviations from the following generic ones are documented for simplicity.

Generic Codecs

These are the generic codec APIs:

PyObject *PyUnicode_Decode (const char *s, Py_ssize_t size, const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Create a Unicode object by decoding size bytes of the encoded string s. encoding and errors have the same meaning as the parameters of the same name in the str() built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_AsEncodedString (PyObject *unicode, const char *encoding, const char *errors)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object and return the result as Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

UTF-8 Codecs

These are the UTF-8 codec APIs:

PyObject *PyUnicode_DecodeUTF8 (const char *s, Py_ssize_t size, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_DecodeUTF8Stateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode_DecodeUTF8(). If consumed is not NULL, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

PyObject *PyUnicode_AsUTF8String (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

```
const char *PyUnicode_AsUTF8AndSize (PyObject *unicode, Py_ssize_t *size)
```

Part of the Stable ABI since version 3.10. Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in size. The size argument can be NULL; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in size), regardless of whether there are any other null code points.

In the case of an error, \mathtt{NULL} is returned with an exception set and no size is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer. The buffer is deallocated and pointers to it become invalid when the Unicode object is garbage collected.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The return type is now const char * rather of char *.

Modifié dans la version 3.10 : This function is a part of the *limited API*.

const char *PyUnicode_AsUTF8 (PyObject *unicode)

As PyUnicode_AsUTF8AndSize(), but does not store the size.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The return type is now const char * rather of char *.

UTF-32 Codecs

These are the UTF-32 codec APIs:

PyObject *PyUnicode_DecodeUTF32 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)

Return value : New reference. Part of the Stable ABI. Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If *byteorder is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *byteorder is -1 or 1, any byte order mark is copied to the output.

After completion, *byteorder is set to the current byte order at the end of input data.

If byteorder is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeUTF32Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode_DecodeUTF32(). If consumed is not NULL, PyUnicode_DecodeUTF32Stateful() will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

```
PyObject *PyUnicode_AsUTF32String (PyObject *unicode)
```

Return value: New reference. Part of the Stable ABI. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

UTF-16 Codecs

These are the UTF-16 codec APIs:

```
PyObject *PyUnicode_DecodeUTF16 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)
```

Return value : New reference. Part of the Stable ABI. Decode *size* bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If *byteorder is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *byteorder is -1 or 1, any byte order mark is copied to the output (where it will result in either a \ufeff or a \ufeff e character).

After completion, *byteorder is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeUTF16Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode_DecodeUTF16(). If consumed is not NULL, PyUnicode_DecodeUTF16Stateful() will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

PyObject *PyUnicode_AsUTF16String (PyObject *unicode)

Return value : New reference. Part of the Stable ABI. Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

UTF-7 Codecs

These are the UTF-7 codec APIs:

PyObject *PyUnicode_DecodeUTF7 (const char *s, *Py_ssize_t* size, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_DecodeUTF7Stateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode_DecodeUTF7(). If consumed is not NULL, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

Unicode-Escape Codecs

These are the "Unicode Escape" codec APIs:

PyObject *PyUnicode_DecodeUnicodeEscape (const char *s, Py_ssize_t size, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_AsUnicodeEscapeString (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

Raw-Unicode-Escape Codecs

These are the "Raw Unicode Escape" codec APIs:

PyObject *PyUnicode_DecodeRawUnicodeEscape (const char *s, Py_ssize_t size, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *s.* Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_AsRawUnicodeEscapeString (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

Latin-1 Codecs

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

PyObject *PyUnicode_DecodeLatin1 (const char *s, Py_ssize_t size, const char *errors)

Return value: New reference. Part of the Stable ABI. Create a Unicode object by decoding size bytes of the Latin-1 encoded string s. Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_AsLatin1String (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

ASCII Codecs

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

PyObject *PyUnicode_DecodeASCII (const char *s, Py_ssize_t size, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the ASCII encoded string *s.* Return NULL if an exception was raised by the codec.

PyObject *PyUnicode_AsASCIIString (PyObject *unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

Character Map Codecs

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the <code>encodings</code> package). The codec uses mappings to encode and decode characters. The mapping objects provided must support the <code>__getitem__()</code> mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

PyObject *PyUnicode_DecodeCharmap (const char *data, Py_ssize_t size, PyObject *mapping, const char *errors)

Return value : New reference. Part of the Stable ABI. Create a Unicode object by decoding *size* bytes of the encoded string *s* using the given *mapping* object. Return NULL if an exception was raised by the codec.

If mapping is NULL, Latin-1 decoding will be applied. Else mapping must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes -- ones which cause a LookupError, as well as ones which get mapped to None, 0xFFFE or '\ullffe', are treated as undefined mappings and cause an error.

PyObject *PyUnicode_AsCharmapString (PyObject *unicode, PyObject *mapping)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using the given mapping object and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec. The mapping object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a LookupError) as well as mapped to None are treated as "undefined mapping" and cause an error.

The following codec API is special in that maps Unicode to Unicode.

PyObject *PyUnicode_Translate (PyObject *str, PyObject *table, const char *errors)

Return value : New reference. Part of the Stable ABI. Translate a string by applying a character mapping table to it and return the resulting Unicode object. Return NULL if an exception was raised by the codec.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the __getitem__() interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is.

errors has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

MBCS codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

```
PyObject *PyUnicode_DecodeMBCS (const char *s, Py_ssize_t size, const char *errors)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Create a Unicode object by decoding size bytes of the MBCS encoded string s. Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeMBCSStateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. If consumed is NULL, behave like PyUnicode_DecodeMBCS(). If consumed is not NULL, PyUnicode_DecodeMBCSStateful() will not decode trailing lead byte and the number of bytes that have been decoded will be stored in consumed.

```
PyObject *PyUnicode AsMBCSString (PyObject *unicode)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_EncodeCodePage (int code_page, PyObject *unicode, const char *errors)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Encode the Unicode object using the specified code page and return a Python bytes object. Return NULL if an exception was raised by the codec. Use CP_ACP code page to get the MBCS encoder.

Nouveau dans la version 3.3.

Methods & Slots

Methods and Slot Functions

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or −1 if an exception occurs.

```
PyObject *PyUnicode_Concat (PyObject *left, PyObject *right)
```

Return value: New reference. Part of the Stable ABI. Concat two strings giving a new Unicode string.

```
PyObject *PyUnicode Split (PyObject *s, PyObject *sep, Py ssize t maxsplit)
```

Return value: New reference. Part of the Stable ABI. Split a string giving a list of Unicode strings. If sep is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most maxsplit splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

PyObject *PyUnicode_Splitlines (PyObject *s, int keepend)

Return value: New reference. Part of the Stable ABI. Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If keepend is 0, the line break characters are not included in the resulting strings.

PyObject ***PyUnicode_Join** (*PyObject* *separator, *PyObject* *seq)

Return value: New reference. Part of the Stable ABI. Join a sequence of strings using the given separator and return the resulting Unicode string.

- Py_ssize_t PyUnicode_Tailmatch (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end, int direction)

 Part of the Stable ABI. Return 1 if substr matches str[start:end] at the given tail end (direction == -1 means to do a prefix match, direction == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.
- Py_ssize_t PyUnicode_Find (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end, int direction)

Part of the Stable ABI. Return the first position of substr in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Py_ssize_t PyUnicode_FindChar (PyObject *str, Py_UCS4 ch, Py_ssize_t start, Py_ssize_t end, int direction)

Part of the Stable ABI since version 3.7. Return the first position of the character ch in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: start and end are now adjusted to behave like str[start:end].

Py_ssize_t PyUnicode_Count (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end)

Part of the Stable ABI. Return the number of non-overlapping occurrences of substr in str[start:end]. Return -1 if an error occurred.

PyObject *PyUnicode Replace (PyObject *str, PyObject *substr, PyObject *replstr, Py_ssize_t maxcount)

Return value: New reference. Part of the Stable ABI. Replace at most maxcount occurrences of substr in str with replstr and return the resulting Unicode object. maxcount == -1 means replace all occurrences.

int PyUnicode_Compare (PyObject *left, PyObject *right)

Part of the Stable ABI. Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively. This function returns -1 upon failure, so one should call *PyErr_Occurred()* to check for errors.

int PyUnicode_CompareWithASCIIString (PyObject *uni, const char *string)

Part of the Stable ABI. Compare a Unicode object, uni, with string and return −1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

PyObject *PyUnicode_RichCompare (PyObject *left, PyObject *right, int op)

Return value: New reference. Part of the Stable ABI. Rich compare two Unicode strings and return one of the following:

- NULL in case an exception was raised
- Py_True or Py_False for successful comparisons
- Py_NotImplemented in case the type combination is unknown

Possible values for op are Py_GT, Py_GE, Py_EQ, Py_NE, Py_LT, and Py_LE.

PyObject *PyUnicode_Format (PyObject *format, PyObject *args)

Return value: New reference. Part of the Stable ABI. Return a new string object from format and args; this is analogous to format % args.

int PyUnicode_Contains (*PyObject* *container, *PyObject* *element)

Part of the Stable ABI. Check whether *element* is contained in *container* and return true or false accordingly. *element* has to coerce to a one element Unicode string. –1 is returned if there was an error.

void PyUnicode_InternInPlace (PyObject **string)

Part of the Stable ABI. Intern the argument *string in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as *string, it sets *string to it (releasing the reference to the old string object and creating a new strong reference to the interned string object), otherwise it leaves *string alone and interns it (creating a new strong reference). (Clarification: even though there is a lot of talk about references, think of this function as reference-neutral; you own the object after the call if and only if you owned it before the call.)

PyObject *PyUnicode_InternFromString (const char *v)

Return value: New reference. Part of the Stable ABI. A combination of PyUnicode_FromString() and PyUnicode_InternInPlace(), returning either a new Unicode string object that has been interned, or a new ("owned") reference to an earlier interned string object with the same value.

8.3.4 Tuple Objects

type PyTupleObject

This subtype of PyObject represents a Python tuple object.

PyTypeObject PyTuple_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python tuple type; it is the same object as tuple in the Python layer.

int PyTuple_Check (*PyObject* *p)

Return true if p is a tuple object or an instance of a subtype of the tuple type. This function always succeeds.

int PyTuple_CheckExact (PyObject *p)

Return true if p is a tuple object, but not an instance of a subtype of the tuple type. This function always succeeds.

PyObject *PyTuple New (Py ssize t len)

Return value: New reference. Part of the Stable ABI. Return a new tuple object of size len, or NULL on failure.

```
PyObject *PyTuple_Pack (Py_ssize_t n, ...)
```

Return value: New reference. Part of the Stable ABI. Return a new tuple object of size n, or NULL on failure. The tuple values are initialized to the subsequent n C arguments pointing to Python objects. PyTuple_Pack (2, a, b) is equivalent to Py_BuildValue("(00)", a, b).

```
Py_ssize_t PyTuple_Size (PyObject *p)
```

Part of the Stable ABI. Take a pointer to a tuple object, and return the size of that tuple.

```
Py_ssize_t PyTuple_GET_SIZE (PyObject *p)
```

Return the size of the tuple p, which must be non-NULL and point to a tuple; no error checking is performed.

```
PyObject *PyTuple_GetItem (PyObject *p, Py_ssize_t pos)
```

Return value : Borrowed reference. Part of the Stable ABI. Return the object at position *pos* in the tuple pointed to by *p.* If *pos* is negative or out of bounds, return NULL and set an IndexError exception.

```
PyObject *PyTuple_GET_ITEM (PyObject *p, Py_ssize_t pos)
```

Return value: Borrowed reference. Like PyTuple_GetItem(), but does no checking of its arguments.

PyObject *PyTuple_GetSlice (PyObject *p, Py_ssize_t low, Py_ssize_t high)

Return value: New reference. Part of the Stable ABI. Return the slice of the tuple pointed to by p between low and high, or NULL on failure. This is the equivalent of the Python expression p[low:high]. Indexing from the end of the tuple is not supported.

```
int PyTuple_SetItem (PyObject *p, Py_ssize_t pos, PyObject *o)
```

Part of the Stable ABI. Insert a reference to object *o* at position *pos* of the tuple pointed to by *p*. Return 0 on success. If *pos* is out of bounds, return -1 and set an IndexError exception.

Note: This function "steals" a reference to *o* and discards a reference to an item already in the tuple at the affected position.

```
void PyTuple_SET_ITEM (PyObject *p, Py_ssize_t pos, PyObject *o)
```

Like PyTuple_SetItem(), but does no error checking, and should only be used to fill in brand new tuples.

Note: This function "steals" a reference to o, and, unlike PyTuple_SetItem(), does not discard a reference to any item that is being replaced; any reference in the tuple at position pos will be leaked.

```
int _PyTuple_Resize (PyObject **p, Py_ssize_t newsize)
```

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns 0 on success. Client code should never assume that the resulting value of *p will be the same as before calling this function. If the object referenced by *p is replaced, the original *p is destroyed. On failure, returns -1 and sets *p to NULL, and raises MemoryError or SystemError.

8.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of namedtuple() objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

```
PyTypeObject *PyStructSequence_NewType (PyStructSequence_Desc *desc)
```

Return value: New reference. Part of the Stable ABI. Create a new struct sequence type from the data in desc, described below. Instances of the resulting type can be created with PyStructSequence_New().

```
void PyStructSequence_InitType (PyTypeObject *type, PyStructSequence_Desc *desc)
```

Initializes a struct sequence type type from desc in place.

```
int PyStructSequence_InitType2 (PyTypeObject *type, PyStructSequence_Desc *desc)
```

The same as PyStructSequence_InitType, but returns 0 on success and -1 on failure.

Nouveau dans la version 3.4.

type PyStructSequence_Desc

Part of the Stable ABI (including all members). Contains the meta information of a struct sequence type to create. const char *name

Name of the struct sequence type.

const char *doc

Pointer to docstring for the type or NULL to omit.

```
PyStructSequence_Field *fields
```

Pointer to NULL-terminated array with field names of the new type.

int n_in_sequence

Number of fields visible to the Python side (if used as tuple).

type PyStructSequence_Field

Part of the Stable ABI (including all members). Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as PyObject*. The index in the fields array of the PyStructSequence Desc determines which field of the struct sequence is described.

const char *name

Name for the field or NULL to end the list of named fields, set to <code>PyStructSequence_UnnamedField</code> to leave unnamed.

const char *doc

Field docstring or NULL to omit.

const char *const PyStructSequence_UnnamedField

Part of the Stable ABI since version 3.11. Special value for a field name to leave it unnamed.

Modifié dans la version 3.9 : The type was changed from char *.

PyObject *PyStructSequence_New (PyTypeObject *type)

Return value: New reference. Part of the Stable ABI. Creates an instance of type, which must have been created with PyStructSequence_NewType().

PyObject *PyStructSequence_GetItem (PyObject *p, Py_ssize_t pos)

Return value : Borrowed reference. Part of the Stable ABI. Return the object at position *pos* in the struct sequence pointed to by *p*. No bounds checking is performed.

PyObject *PyStructSequence_GET_ITEM (PyObject *p, Py_ssize_t pos)

Return value: Borrowed reference. Macro equivalent of PyStructSequence_GetItem().

void PyStructSequence_SetItem (PyObject *p, Py_ssize_t pos, PyObject *o)

Part of the Stable ABI. Sets the field at index pos of the struct sequence p to value o. Like $PyTuple_SET_ITEM()$, this should only be used to fill in brand new instances.

Note: This function "steals" a reference to o.

void PyStructSequence_SET_ITEM (PyObject *p, Py_ssize_t *pos, PyObject *o)

Similar to $PyStructSequence_SetItem()$, but implemented as a static inlined function.

Note: This function "steals" a reference to o.

8.3.6 List Objects

type PyListObject

This subtype of PyObject represents a Python list object.

PyTypeObject PyList_Type

Part of the Stable ABI. This instance of *PyTypeObject* represents the Python list type. This is the same object as list in the Python layer.

int PyList_Check (*PyObject* *p)

Return true if p is a list object or an instance of a subtype of the list type. This function always succeeds.

int PyList_CheckExact (PyObject *p)

Return true if p is a list object, but not an instance of a subtype of the list type. This function always succeeds.

PyObject *PyList_New (Py_ssize_t len)

Return value: New reference. Part of the Stable ABI. Return a new list of length len on success, or NULL on failure.

Note: If *len* is greater than zero, the returned list object's items are set to NULL. Thus you cannot use abstract API functions such as *PySequence_SetItem()* or expose the object to Python code before setting all items to a real object with *PyList_SetItem()*.

Py_ssize_t PyList_Size (PyObject *list)

Part of the Stable ABI. Return the length of the list object in list; this is equivalent to len(list) on a list object.

```
Py_ssize_t PyList_GET_SIZE (PyObject *list)
```

Similar to PyList Size (), but without error checking.

```
PyObject *PyList_GetItem (PyObject *list, Py_ssize_t index)
```

Return value: Borrowed reference. Part of the Stable ABI. Return the object at position index in the list pointed to by list. The position must be non-negative; indexing from the end of the list is not supported. If index is out of bounds (<0 or >=len(list)), return NULL and set an IndexError exception.

```
PyObject *PyList_GET_ITEM (PyObject *list, Py_ssize_t i)
```

Return value: Borrowed reference. Similar to PyList_GetItem(), but without error checking.

```
int PyList_SetItem (PyObject *list, Py_ssize_t index, PyObject *item)
```

Part of the Stable ABI. Set the item at index index in list to item. Return 0 on success. If index is out of bounds, return -1 and set an IndexError exception.

Note: This function "steals" a reference to *item* and discards a reference to an item already in the list at the affected position.

```
void PyList_SET_ITEM (PyObject *list, Py_ssize_t i, PyObject *o)
```

Macro form of PyList_SetItem() without error checking. This is normally only used to fill in new lists where there is no previous content.

Note: This macro "steals" a reference to *item*, and, unlike *PyList_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in *list* at position *i* will be leaked.

```
int PyList_Insert (PyObject *list, Py_ssize_t index, PyObject *item)
```

Part of the Stable ABI. Insert the item into list list in front of index index. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.insert(index, item).

```
int PyList Append (PyObject *list, PyObject *item)
```

Part of the Stable ABI. Append the object item at the end of list list. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.append(item).

```
PyObject *PyList_GetSlice (PyObject *list, Py_ssize_t low, Py_ssize_t high)
```

Return value: New reference. Part of the Stable ABI. Return a list of the objects in list containing the objects between low and high. Return NULL and set an exception if unsuccessful. Analogous to list[low:high]. Indexing from the end of the list is not supported.

```
int PyList_SetSlice (PyObject *list, Py_ssize_t low, Py_ssize_t high, PyObject *itemlist)
```

Part of the Stable ABI. Set the slice of *list* between *low* and *high* to the contents of *itemlist*. Analogous to list [low:high] = itemlist. The *itemlist* may be NULL, indicating the assignment of an empty list (slice deletion). Return 0 on success, -1 on failure. Indexing from the end of the list is not supported.

int PyList_Sort (PyObject *list)

Part of the Stable ABI. Sort the items of *list* in place. Return 0 on success, -1 on failure. This is equivalent to list.sort().

int PyList_Reverse (PyObject *list)

Part of the Stable ABI. Reverse the items of *list* in place. Return 0 on success, -1 on failure. This is the equivalent of list.reverse().

PyObject *PyList_AsTuple (PyObject *list)

Return value: New reference. Part of the Stable ABI. Return a new tuple object containing the contents of list; equivalent to tuple (list).

8.4 Objets conteneurs

8.4.1 Objets dictionnaires

type PyDictObject

This subtype of PyObject represents a Python dictionary object.

PyTypeObject PyDict_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python dictionary type. This is the same object as dict in the Python layer.

int PyDict_Check (PyObject *p)

Return true if p is a dict object or an instance of a subtype of the dict type. This function always succeeds.

int PyDict_CheckExact (PyObject *p)

Return true if p is a dict object, but not an instance of a subtype of the dict type. This function always succeeds.

PyObject *PyDict_New()

Return value: New reference. Part of the Stable ABI. Return a new empty dictionary, or NULL on failure.

PyObject *PyDictProxy_New (PyObject *mapping)

Return value: New reference. Part of the Stable ABI. Return a types. MappingProxyType object for a mapping which enforces read-only behavior. This is normally used to create a view to prevent modification of the dictionary for non-dynamic class types.

void PyDict_Clear (PyObject *p)

Part of the Stable ABI. Empty an existing dictionary of all key-value pairs.

int PyDict_Contains (PyObject *p, PyObject *key)

Part of the Stable ABI. Determine if dictionary p contains key. If an item in p is matches key, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression key in p.

PyObject *PyDict_Copy (PyObject *p)

Return value: New reference. Part of the Stable ABI. Return a new dictionary that contains the same key-value pairs as p.

int PyDict_SetItem (PyObject *p, PyObject *key, PyObject *val)

Part of the Stable ABI. Insert val into the dictionary p with a key of key. key must be hashable; if it isn't, TypeError will be raised. Return 0 on success or -1 on failure. This function does not steal a reference to val.

int PyDict_SetItemString (PyObject *p, const char *key, PyObject *val)

Part of the Stable ABI. This is the same as PyDict_SetItem(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

int PyDict_DelItem (PyObject *p, PyObject *key)

Part of the Stable ABI. Remove the entry in dictionary p with key key. key must be hashable; if it isn't, TypeError is raised. If key is not in the dictionary, KeyError is raised. Return 0 on success or -1 on failure.

int PyDict_DelItemString (PyObject *p, const char *key)

Part of the Stable ABI. This is the same as PyDict_DelItem(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

PyObject *PyDict_GetItem (PyObject *p, PyObject *key)

Return value : Borrowed reference. Part of the Stable ABI. Return the object from dictionary *p* which has a key *key*. Return NULL if the key *key* is not present, but *without* setting an exception.

Note: Exceptions that occur while this calls __hash__() and __eq__() methods are silently ignored. Prefer the PyDict_GetItemWithError() function instead.

Modifié dans la version 3.10 : Calling this API without *GIL* held had been allowed for historical reason. It is no longer allowed.

PyObject *PyDict_GetItemWithError (PyObject *p, PyObject *key)

Return value: Borrowed reference. Part of the Stable ABI. Variant of PyDict_GetItem() that does not suppress exceptions. Return NULL with an exception set if an exception occurred. Return NULL without an exception set if the key wasn't present.

PyObject *PyDict_GetItemString (PyObject *p, const char *key)

Return value: Borrowed reference. Part of the Stable ABI. This is the same as PyDict_GetItem(), but key is specified as a const char* UTF-8 encoded bytes string, rather than a PyObject*.

Note: Exceptions that occur while this calls __hash__() and __eq__() methods or while creating the temporary str object are silently ignored. Prefer using the <code>PyDict_GetItemWithError()</code> function with your own <code>PyUnicode_FromString()</code> key instead.

PyObject *PyDict_SetDefault (PyObject *p, PyObject *key, PyObject *defaultobj)

Return value: Borrowed reference. This is the same as the Python-level dict.setdefault(). If present, it returns the value corresponding to key from the dictionary p. If the key is not in the dict, it is inserted with value defaultobj and defaultobj is returned. This function evaluates the hash function of key only once, instead of evaluating it independently for the lookup and the insertion.

Nouveau dans la version 3.4.

PyObject *PyDict_Items (PyObject *p)

Return value : New reference. Part of the Stable ABI. Return a *PyListObject* containing all the items from the dictionary.

PyObject *PyDict_Keys (PyObject *p)

Return value: New reference. Part of the Stable ABI. Return a PyListObject containing all the keys from the dictionary.

PyObject *PyDict_Values (PyObject *p)

Return value : New reference. Part of the Stable ABI. Return a *PyListObject* containing all the values from the dictionary *p*.

```
Py_ssize_t PyDict_Size (PyObject *p)
```

Part of the Stable ABI. Return the number of items in the dictionary. This is equivalent to len (p) on a dictionary.

```
int PyDict_Next (PyObject *p, Py_ssize_t *ppos, PyObject **pkey, PyObject **pvalue)
```

Part of the Stable ABI. Iterate over all key-value pairs in the dictionary p. The Py_ssize_t referred to by ppos must be initialized to 0 prior to the first call to this function to start the iteration; the function returns true for each pair in the dictionary, and false once all pairs have been reported. The parameters pkey and pvalue should either point to PyObject* variables that will be filled in with each key and value, respectively, or may be NULL. Any references returned through them are borrowed. ppos should not be altered during iteration. Its value represents offsets within the internal dictionary structure, and since the structure is sparse, the offsets are not consecutive.

Par exemple:

```
PyObject *key, *value;
Py_ssize_t pos = 0;
while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

The dictionary p should not be mutated during iteration. It is safe to modify the values of the keys as you iterate over the dictionary, but only so long as the set of keys does not change. For example :

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}</pre>
```

int PyDict_Merge (PyObject *a, PyObject *b, int override)

Part of the Stable ABI. Iterate over mapping object b adding key-value pairs to dictionary a. b may be a dictionary, or any object supporting $PyMapping_Keys$ () and $PyObject_GetItem$ (). If override is true, existing pairs in a will be replaced if a matching key is found in b, otherwise pairs will only be added if there is not a matching key in a. Return 0 on success or -1 if an exception was raised.

```
int PyDict_Update (PyObject *a, PyObject *b)
```

Part of the Stable ABI. This is the same as PyDict_Merge (a, b, 1) in C, and is similar to a .update (b) in Python except that $PyDict_Update()$ doesn't fall back to the iterating over a sequence of key value pairs if the second argument has no "keys" attribute. Return 0 on success or -1 if an exception was raised.

int PyDict_MergeFromSeq2 (PyObject *a, PyObject *seq2, int override)

Part of the Stable ABI. Update or merge into dictionary a, from the key-value pairs in seq2. seq2 must be an iterable object producing iterable objects of length 2, viewed as key-value pairs. In case of duplicate keys, the last wins if *override* is true, else the first wins. Return 0 on success or -1 if an exception was raised. Equivalent Python (except for the return value):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
        a[key] = value
```

int PyDict_AddWatcher (PyDict_WatchCallback callback)

Register *callback* as a dictionary watcher. Return a non-negative integer id which must be passed to future calls to $PyDict_Watch$ (). In case of error (e.g. no more watcher IDs available), return -1 and set an exception.

Nouveau dans la version 3.12.

int PyDict_ClearWatcher (int watcher_id)

Clear watcher identified by watcher_id previously returned from PyDict_AddWatcher(). Return 0 on success, -1 on error (e.g. if the given watcher_id was never registered.)

Nouveau dans la version 3.12.

int **PyDict_Watch** (int watcher_id, *PyObject* *dict)

Mark dictionary *dict* as watched. The callback granted *watcher_id* by *PyDict_AddWatcher()* will be called when *dict* is modified or deallocated. Return 0 on success or -1 on error.

Nouveau dans la version 3.12.

int PyDict_Unwatch (int watcher_id, PyObject *dict)

Mark dictionary *dict* as no longer watched. The callback granted *watcher_id* by *PyDict_AddWatcher()* will no longer be called when *dict* is modified or deallocated. The dict must previously have been watched by this watcher. Return 0 on success or -1 on error.

Nouveau dans la version 3.12.

type PyDict_WatchEvent

```
Enumeration of possible dictionary watcher events: PyDict_EVENT_ADDED, PyDict_EVENT_MODIFIED, PyDict_EVENT_DELETED, PyDict_EVENT_CLONED, PyDict_EVENT_CLEARED, or PyDict_EVENT_DEALLOCATED.
```

Nouveau dans la version 3.12.

typedef int (*PyDict_WatchCallback)(PyDict_WatchEvent event, PyObject *dict, PyObject *key, PyObject *new value)

Type of a dict watcher callback function.

If event is PyDict_EVENT_CLEARED or PyDict_EVENT_DEALLOCATED, both key and new_value will be NULL. If event is PyDict_EVENT_ADDED or PyDict_EVENT_MODIFIED, new_value will be the new value for key. If event is PyDict_EVENT_DELETED, key is being deleted from the dictionary and new_value will be NULL.

PyDict_EVENT_CLONED occurs when *dict* was previously empty and another dict is merged into it. To maintain efficiency of this operation, per-key PyDict_EVENT_ADDED events are not issued in this case; instead a single PyDict_EVENT_CLONED is issued, and *key* will be the source dictionary.

The callback may inspect but must not modify *dict*; doing so could have unpredictable effects, including infinite recursion. Do not trigger Python code execution in the callback, as it could modify the dict as a side effect.

If *event* is PyDict_EVENT_DEALLOCATED, taking a new reference in the callback to the about-to-be-destroyed dictionary will resurrect it and prevent it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

Callbacks occur before the notified modification to dict takes place, so the prior state of dict can be inspected.

If the callback sets an exception, it must return -1; this exception will be printed as an unraisable exception using $PyErr_WriteUnraisable()$. Otherwise it should return 0.

There may already be a pending exception set on entry to the callback. In this case, the callback should return 0 with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Nouveau dans la version 3.12.

8.4.2 Set Objects

This section details the public API for set and frozenset objects. Any functionality not listed below is best accessed using either the abstract object protocol (including PyObject_CallMethod(), PyObject_RichCompareBool(), PyObject_Hash(), PyObject_Repr(), PyObject_IsTrue(), PyObject_Print(), and PyObject_GetIter()) or the abstract number protocol (including PyNumber_And(), PyNumber_Subtract(), PyNumber_Or(), PyNumber_Xor(), PyNumber_InPlaceAnd(), PyNumber_InPlaceSubtract(), PyNumber_InPlaceOr(), and PyNumber_InPlaceXor()).

type PySetObject

This subtype of *PyObject* is used to hold the internal data for both set and frozenset objects. It is like a *PyDictObject* in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and all are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

PyTypeObject PySet Type

Part of the Stable ABI. This is an instance of PyTypeObject representing the Python set type.

PyTypeObject PyFrozenSet_Type

Part of the Stable ABI. This is an instance of PyTypeObject representing the Python frozenset type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

```
int PySet_Check (PyObject *p)
```

Return true if p is a set object or an instance of a subtype. This function always succeeds.

```
int PyFrozenSet_Check (PyObject *p)
```

Return true if p is a frozenset object or an instance of a subtype. This function always succeeds.

```
int PyAnySet_Check (PyObject *p)
```

Return true if p is a set object, a frozenset object, or an instance of a subtype. This function always succeeds.

```
int PySet_CheckExact (PyObject *p)
```

Return true if *p* is a set object but not an instance of a subtype. This function always succeeds.

Nouveau dans la version 3.10.

```
int PyAnySet CheckExact (PyObject *p)
```

Return true if p is a set object or a frozenset object but not an instance of a subtype. This function always succeeds.

```
int PyFrozenSet CheckExact (PyObject *p)
```

Return true if p is a frozenset object but not an instance of a subtype. This function always succeeds.

PyObject *PySet_New (PyObject *iterable)

Return value: New reference. Part of the Stable ABI. Return a new set containing objects returned by the iterable. The iterable may be NULL to create a new empty set. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable. The constructor is also useful for copying a set (c=set (s)).

PyObject *PyFrozenSet_New (PyObject *iterable)

Return value: New reference. Part of the Stable ABI. Return a new frozenset containing objects returned by the iterable. The iterable may be NULL to create a new empty frozenset. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable.

The following functions and macros are available for instances of set or frozenset or instances of their subtypes.

Py_ssize_t PySet_Size (PyObject *anyset)

Part of the Stable ABI. Return the length of a set or frozenset object. Equivalent to len(anyset). Raises a SystemError if anyset is not a set, frozenset, or an instance of a subtype.

Py_ssize_t PySet_GET_SIZE (PyObject *anyset)

Macro form of PySet_Size () without error checking.

int PySet_Contains (PyObject *anyset, PyObject *key)

Part of the Stable ABI. Return 1 if found, 0 if not found, and -1 if an error is encountered. Unlike the Python __contains__ () method, this function does not automatically convert unhashable sets into temporary frozensets. Raise a TypeError if the key is unhashable. Raise SystemError if anyset is not a set, frozenset, or an instance of a subtype.

int PySet_Add (PyObject *set, PyObject *key)

Part of the Stable ABI. Add key to a set instance. Also works with frozenset instances (like PyTuple_SetItem() it can be used to fill in the values of brand new frozensets before they are exposed to other code). Return 0 on success or -1 on failure. Raise a TypeError if the key is unhashable. Raise a MemoryError if there is no room to grow. Raise a SystemError if set is not an instance of set or its subtype.

The following functions are available for instances of set or its subtypes but not for instances of frozenset or its subtypes.

int PySet_Discard (PyObject *set, PyObject *key)

Part of the Stable ABI. Return 1 if found and removed, 0 if not found (no action taken), and -1 if an error is encountered. Does not raise KeyError for missing keys. Raise a TypeError if the key is unhashable. Unlike the Python discard() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise SystemError if set is not an instance of set or its subtype.

PyObject *PySet Pop (PyObject *set)

Return value: New reference. Part of the Stable ABI. Return a new reference to an arbitrary object in the set, and removes the object from the set. Return NULL on failure. Raise KeyError if the set is empty. Raise a SystemError if set is not an instance of set or its subtype.

int PySet_Clear (PyObject *set)

Part of the Stable ABI. Empty an existing set of all elements. Return 0 on success. Return -1 and raise SystemError if set is not an instance of set or its subtype.

8.5 Objets fonctions

8.5.1 Objets fonction

Certaines fonctions sont spécifiques aux fonctions Python.

type PyFunctionObject

La structure C utilisée pour les fonctions.

PyTypeObject PyFunction_Type

C'est une instance de *PyTypeObject* et représente le type fonction en Python. Il est exposé aux développeurs comme types. FunctionType.

int PyFunction_Check (PyObject *o)

Renvoie vrai si o est un objet de type fonction (a comme type $PyFunction_Type$). Le paramètre ne doit pas être NULL. Cette fonction réussit toujours.

PyObject *PyFunction_New (PyObject *code, PyObject *globals)

Return value : New reference. Renvoie une nouvelle fonction associée avec l'objet code. globals doit être un dictionnaire avec les variables globales accessibles à la fonction.

La docstring et le nom de la fonction sont récupérés à partir de l'objet code. __module__ est récupéré à partir de globals. Les arguments par défaut, les annotations et la fermeture sont mis à NULL. __qualname__ est mis à la même valeur que celle du champ co_qualname de l'objet code.

PyObject *PyFunction_NewWithQualName (PyObject *code, PyObject *globals, PyObject *qualname)

Return value: New reference. Comme PyFunction_New(), mais accepte aussi une valeur à utiliser pour l'attribut __qualname__ de l'objet fonction. qualname doit être un objet Unicode ou NULL; s'il est NULL, l'attribut __qualname__ de l'objet fonction prend la valeur de l'attribut co_qualname de l'objet code.

Nouveau dans la version 3.3.

PyObject *PyFunction_GetCode (PyObject *op)

Return value: Borrowed reference. Renvoie l'objet code associé avec l'objet de la fonction op.

PyObject *PyFunction_GetGlobals (PyObject *op)

Return value : Borrowed reference. Renvoie le dictionnaire global associé avec l'objet de la fonction op.

PyObject *PyFunction_GetModule (PyObject *op)

Return value : Borrowed reference. Renvoie un borrowed reference à l'attribut __module__ de l'objet fonction op. Il peut être NULL.

C'est typiquement une chaîne de caractère contenant le nom du module, mais il peut être changé par du code Python pour n'importe quel autre objet.

PyObject *PyFunction_GetDefaults (PyObject *op)

Return value : Borrowed reference. Renvoie les valeurs par défaut de l'argument de l'objet de la fonction op. Cela peut être un tuple d'arguments ou NULL.

int PyFunction_SetDefaults (PyObject *op, PyObject *defaults)

Définir les valeurs par défaut de l'argument pour l'objet de la fonction *op. defaults* doit être Py_None ou un tuple. Lève SystemError et renvoie -1 en cas de d'échec.

void PyFunction_SetVectorcall (PyFunctionObject *func, vectorcallfunc vectorcall)

Set the vectorcall field of a given function object func.

Warning: extensions using this API must preserve the behavior of the unaltered (default) vectorcall function! Nouveau dans la version 3.12.

PyObject *PyFunction_GetClosure (PyObject *op)

Return value : Borrowed reference. Renvoie la fermeture associée avec l'objet de la fonction *op*. Cela peut être NULL ou un tuple d'objets cellule.

int PyFunction_SetClosure (PyObject *op, PyObject *closure)

Définir la fermeture associée avec l'objet de la fonction *op. closure* doit être Py_None ou un tuple d'objets cellule. Lève SystemError et renvoie -1 en cas de d'échec.

PyObject *PyFunction_GetAnnotations (PyObject *op)

Return value : Borrowed reference. Renvoie les annotations de l'objet de la fonction op. Cela peut être un dictionnaire mutable ou NULL.

int PyFunction_SetAnnotations (PyObject *op, PyObject *annotations)

Définir les annotations pour l'objet de la fonction op. annotations doit être un dictionnaire ou Py_None.

Lève SystemError et renvoie -1 en cas de d'échec.

int PyFunction_AddWatcher (PyFunction_WatchCallback callback)

Register *callback* as a function watcher for the current interpreter. Return an ID which may be passed to $PyFunction_ClearWatcher()$. In case of error (e.g. no more watcher IDs available), return -1 and set an exception.

Nouveau dans la version 3.12.

int PyFunction_ClearWatcher (int watcher_id)

Clear watcher identified by *watcher_id* previously returned from *PyFunction_AddWatcher()* for the current interpreter. Return 0 on success, or -1 and set an exception on error (e.g. if the given *watcher_id* was never registered.)

Nouveau dans la version 3.12.

type PyFunction WatchEvent

```
Enumeration of possible function watcher events: - PyFunction_EVENT_CREATE - PyFunction_EVENT_DESTROY - PyFunction_EVENT_MODIFY_CODE - PyFunction_EVENT_MODIFY_DEFAULTS - PyFunction_EVENT_MODIFY_KWDEFAULTS Nouveau dans la version 3.12.
```

$typedef int (*{\tt PyFunction_WatchCallback}) (PyFunction_WatchEvent \ event, PyFunctionObject \ *func, PyObject \ *new_value)$

Type of a function watcher callback function.

If event is PyFunction_EVENT_CREATE or PyFunction_EVENT_DESTROY then new_value will be NULL. Otherwise, new_value will hold a borrowed reference to the new value that is about to be stored in func for the attribute that is being modified.

The callback may inspect but must not modify *func*; doing so could have unpredictable effects, including infinite recursion.

If event is PyFunction_EVENT_CREATE, then the callback is invoked after func has been fully initialized. Otherwise, the callback is invoked before the modification to func takes place, so the prior state of func can be inspected. The runtime is permitted to optimize away the creation of function objects when possible. In such cases no event will be emitted. Although this creates the possibility of an observable difference of runtime behavior depending on optimization decisions, it does not change the semantics of the Python code being executed.

If event is PyFunction_EVENT_DESTROY, Taking a reference in the callback to the about-to-be-destroyed function will resurrect it, preventing it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

If the callback sets an exception, it must return -1; this exception will be printed as an unraisable exception using $PyErr_WriteUnraisable()$. Otherwise it should return 0.

There may already be a pending exception set on entry to the callback. In this case, the callback should return 0 with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Nouveau dans la version 3.12.

8.5.2 Instance Method Objects

An instance method is a wrapper for a PyCFunction and the new way to bind a PyCFunction to a class object. It replaces the former call PyMethod_New(func, NULL, class).

PyTypeObject PyInstanceMethod_Type

This instance of PyTypeObject represents the Python instance method type. It is not exposed to Python programs.

int PyInstanceMethod_Check (PyObject *o)

Return true if o is an instance method object (has type $PyInstanceMethod_Type$). The parameter must not be NULL. This function always succeeds.

PyObject *PyInstanceMethod_New (PyObject *func)

Return value : New reference. Return a new instance method object, with *func* being any callable object. *func* is the function that will be called when the instance method is called.

PyObject *PyInstanceMethod_Function (PyObject *im)

Return value: Borrowed reference. Return the function object associated with the instance method im.

PyObject *PyInstanceMethod_GET_FUNCTION (PyObject *im)

Return value : Borrowed reference. Macro version of *PyInstanceMethod_Function()* which avoids error checking.

8.5.3 Objets méthode

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

PyTypeObject PyMethod_Type

This instance of PyTypeObject represents the Python method type. This is exposed to Python programs as types. MethodType.

int PyMethod_Check (PyObject *o)

Return true if o is a method object (has type $PyMethod_Type$). The parameter must not be NULL. This function always succeeds.

PyObject *PyMethod_New (PyObject *func, PyObject *self)

Return value : New reference. Return a new method object, with *func* being any callable object and *self* the instance the method should be bound. *func* is the function that will be called when the method is called. *self* must not be NULL.

PyObject *PyMethod_Function (PyObject *meth)

Return value: Borrowed reference. Return the function object associated with the method meth.

PyObject *PyMethod_GET_FUNCTION (PyObject *meth)

Return value: Borrowed reference. Macro version of PyMethod_Function() which avoids error checking.

PyObject *PyMethod_Self (PyObject *meth)

Return value: Borrowed reference. Return the instance associated with the method meth.

PyObject *PyMethod_GET_SELF (PyObject *meth)

Return value: Borrowed reference. Macro version of PyMethod_Self() which avoids error checking.

8.5.4 Objets Cellules

Les objets "Cellules" (*cell* en anglais) sont utilisés pour implémenter des variables référencées dans de multiples environnements. Pour chacune de ces variables, un objet cellule est créé pour stocker sa valeur; les variables locales de chaque pile d'exécution qui référence cette valeur contiennent une référence sur les cellules des autres environnements qui utilisent aussi cette variable. Quand la valeur est accédée, la valeur de la cellule est utilisée, au lei de celle de l'objet cellule proprement dit. Ce dé-référencement de l'objet cellule requiert l'intervention du *bytecode* généré; il n'est pas automatiquement dé-référencé quand il est accédé. Il est plausible que les objets cellules ne soit utilisés ailleurs.

type PyCellObject

Structure C utilisée pour les objets cellules.

PyTypeObject PyCell_Type

Type objet correspondant aux objets cellules.

```
int PyCell_Check (PyObject *ob)
```

Return true if *ob* is a cell object; *ob* must not be NULL. This function always succeeds.

```
PyObject *PyCell_New (PyObject *ob)
```

Return value : New reference. Create and return a new cell object containing the value *ob*. The parameter may be NULL.

```
PyObject *PyCell_Get (PyObject *cell)
```

Return value : New reference. Renvoie le contenu de la cellule cell.

```
PyObject *PyCell_GET (PyObject *cell)
```

Return value : Borrowed reference. Return the contents of the cell *cell*, but without checking that *cell* is non-NULL and a cell object.

```
int PyCell_Set (PyObject *cell, PyObject *value)
```

Set the contents of the cell object *cell* to *value*. This releases the reference to any current content of the cell. *value* may be NULL. *cell* must be non-NULL; if it is not a cell object, -1 will be returned. On success, 0 will be returned.

```
void PyCell_SET (PyObject *cell, PyObject *value)
```

Sets the value of the cell object *cell* to *value*. No reference counts are adjusted, and no checks are made for safety; *cell* must be non-NULL and must be a cell object.

8.5.5 Objets code

Les objets *Code* sont spécifiques à l'implémentation bas niveau de CPython. Chacun d'eux représente une partie de code exécutable, qui n'a pas encore été lié dans une fonction.

type PyCodeObject

La structure C utilisée pour décrire les objets *Code*. Les attributs de cette structure sont sujets à changer à tout moment.

PyTypeObject PyCode_Type

C'est une instance de PyTypeObject représentant le type Python code.

```
int PyCode_Check (PyObject *co)
```

Return true if co is a code object. This function always succeeds.

```
int PyCode_GetNumFree (PyCodeObject *co)
```

Renvoie le nombre de variables libres dans co.

PyCodeObject *PyUnstable_Code_New (int argcount, int kwonlyargcount, int nlocals, int stacksize, int flags,

PyObject *code, PyObject *consts, PyObject *names, PyObject *varnames, PyObject *freevars, PyObject *cellvars, PyObject *filename, PyObject *name, PyObject *qualname, int firstlineno, PyObject *linetable, PyObject *exceptiontable)

This is *Unstable API*. It may change without warning in minor releases.

Return a new code object. If you need a dummy code object to create a frame, use PyCode_NewEmpty() instead.

Since the definition of the bytecode changes often, calling PyUnstable_Code_New() directly can bind you to a precise Python version.

The many arguments of this function are inter-dependent in complex ways, meaning that subtle changes to values are likely to result in incorrect execution or VM crashes. Use this function only with extreme care.

Modifié dans la version 3.11 : Added qualname and exceptiontable parameters.

Modifié dans la version 3.12 : Renamed from PyCode_New as part of *Unstable C API*. The old name is deprecated, but will remain available until the signature changes again.

PyCodeObject *PyUnstable_Code_NewWithPosOnlyArgs (int argcount, int posonlyargcount, int

kwonlyargcount, int nlocals, int stacksize, int flags, PyObject *code, PyObject *consts, PyObject
*names, PyObject *varnames, PyObject *freevars, PyObject *cellvars, PyObject *filename, PyObject
*name, PyObject *qualname, int firstlineno, PyObject *linetable, PyObject *exceptiontable)

This is *Unstable API*. It may change without warning in minor releases.

Similar to PyUnstable_Code_New(), but with an extra "posonlyargcount" for positional-only arguments. The same caveats that apply to PyUnstable_Code_New also apply to this function.

Nouveau dans la version 3.8 : as PyCode_NewWithPosOnlyArgs

Modifié dans la version 3.11 : Added qualname and exceptiontable parameters.

 $\label{lem:modified} \begin{tabular}{l} Modified dans la version $3.12:$ Renamed to $\tt PyUnstable_Code_NewWithPosOnlyArgs.$ The old name is deprecated, but will remain available until the signature changes again. \end{tabular}$

PyCodeObject *PyCode_NewEmpty (const char *filename, const char *funcname, int firstlineno)

Return value : New reference. Return a new empty code object with the specified filename, function name, and first line number. The resulting code object will raise an Exception if executed.

int PyCode_Addr2Line (PyCodeObject *co, int byte_offset)

Return the line number of the instruction that occurs on or before byte_offset and ends after it. If you just need the line number of a frame, use PyFrame_GetLineNumber() instead.

For efficiently iterating over the line numbers in a code object, use the API described in PEP 626.

int PyCode_Addr2Location (*PyObject* *co, int byte_offset, int *start_line, int *start_column, int *end_line, int *end_column)

Sets the passed int pointers to the source code line and column numbers for the instruction at byte_offset. Sets the value to 0 when information is not available for any particular element.

Returns 1 if the function succeeds and 0 otherwise.

Nouveau dans la version 3.11.

PyObject *PyCode_GetCode (PyCodeObject *co)

Equivalent to the Python code <code>getattr(co, 'co_code')</code>. Returns a strong reference to a <code>PyBytesObject</code> representing the bytecode in a code object. On error, <code>NULL</code> is returned and an exception is raised.

This PyBytesObject may be created on-demand by the interpreter and does not necessarily represent the bytecode actually executed by CPython. The primary use case for this function is debuggers and profilers.

Nouveau dans la version 3.11.

PyObject *PyCode_GetVarnames (PyCodeObject *co)

Equivalent to the Python code getattr(co, 'co_varnames'). Returns a new reference to a PyTupleObject containing the names of the local variables. On error, NULL is returned and an exception is raised.

Nouveau dans la version 3.11.

PyObject *PyCode_GetCellvars (PyCodeObject *co)

Equivalent to the Python code <code>getattr(co, 'co_cellvars')</code>. Returns a new reference to a <code>PyTupleObject</code> containing the names of the local variables that are referenced by nested functions. On error, <code>NULL</code> is returned and an exception is raised.

Nouveau dans la version 3.11.

PyObject *PyCode_GetFreevars (PyCodeObject *co)

Equivalent to the Python code <code>getattr(co, 'co_freevars')</code>. Returns a new reference to a <code>PyTupleObject</code> containing the names of the free variables. On error, <code>NULL</code> is returned and an exception is raised.

Nouveau dans la version 3.11.

int PyCode_AddWatcher (PyCode_WatchCallback callback)

Register *callback* as a code object watcher for the current interpreter. Return an ID which may be passed to <code>PyCode_ClearWatcher()</code>. In case of error (e.g. no more watcher IDs available), return -1 and set an exception.

Nouveau dans la version 3.12.

int PyCode_ClearWatcher (int watcher_id)

Clear watcher identified by *watcher_id* previously returned from *PyCode_AddWatcher()* for the current interpreter. Return 0 on success, or -1 and set an exception on error (e.g. if the given *watcher_id* was never registered.) Nouveau dans la version 3.12.

type PyCodeEvent

Enumeration of possible code object watcher events : - PY_CODE_EVENT_CREATE - PY_CODE_EVENT_DESTROY

Nouveau dans la version 3.12.

typedef int (*PyCode_WatchCallback)(PyCodeEvent event, PyCodeObject *co)

Type of a code object watcher callback function.

If *event* is PY_CODE_EVENT_CREATE, then the callback is invoked after *co* has been fully initialized. Otherwise, the callback is invoked before the destruction of *co* takes place, so the prior state of *co* can be inspected.

If event is PY_CODE_EVENT_DESTROY, taking a reference in the callback to the about-to-be-destroyed code object will resurrect it and prevent it from being freed at this time. When the resurrected object is destroyed later, any watcher callbacks active at that time will be called again.

Users of this API should not rely on internal runtime implementation details. Such details may include, but are not limited to, the exact order and timing of creation and destruction of code objects. While changes in these details may result in differences observable by watchers (including whether a callback is invoked or not), it does not change the semantics of the Python code being executed.

If the callback sets an exception, it must return -1; this exception will be printed as an unraisable exception using $PyErr_WriteUnraisable()$. Otherwise it should return 0.

There may already be a pending exception set on entry to the callback. In this case, the callback should return 0 with the same exception still set. This means the callback may not call any other API that can set an exception unless it saves and clears the exception state first, and restores it before returning.

Nouveau dans la version 3.12.

8.5.6 Extra information

To support low-level extensions to frame evaluation, such as external just-in-time compilers, it is possible to attach arbitrary extra data to code objects.

These functions are part of the unstable C API tier: this functionality is a CPython implementation detail, and the API may change without deprecation warnings.

Py_ssize_t PyUnstable_Eval_RequestCodeExtraIndex (freefunc free)

This is *Unstable API*. It may change without warning in minor releases.

Return a new an opaque index value used to adding data to code objects.

You generally call this function once (per interpreter) and use the result with PyCode_GetExtra and PyCode_SetExtra to manipulate data on individual code objects.

If *free* is not NULL: when a code object is deallocated, *free* will be called on non-NULL data stored under the new index. Use Py_DecRef() when storing PyObject.

Nouveau dans la version 3.6 : as _PyEval_RequestCodeExtraIndex

Modifié dans la version 3.12 : Renamed to PyUnstable_Eval_RequestCodeExtraIndex. The old private name is deprecated, but will be available until the API changes.

int PyUnstable_Code_GetExtra (PyObject *code, Py_ssize_t index, void **extra)

This is *Unstable API*. It may change without warning in minor releases.

Set extra to the extra data stored under the given index. Return 0 on success. Set an exception and return -1 on failure.

If no data was set under the index, set *extra* to NULL and return 0 without setting an exception.

Nouveau dans la version 3.6 : as _PyCode_GetExtra

Modifié dans la version 3.12 : Renamed to PyUnstable_Code_GetExtra. The old private name is deprecated, but will be available until the API changes.

int PyUnstable_Code_SetExtra (PyObject *code, Py_ssize_t index, void *extra)

This is *Unstable API*. It may change without warning in minor releases.

Set the extra data stored under the given index to extra. Return 0 on success. Set an exception and return -1 on failure.

Nouveau dans la version 3.6 : as _PyCode_SetExtra

Modifié dans la version 3.12 : Renamed to PyUnstable_Code_SetExtra. The old private name is deprecated, but will be available until the API changes.

8.6 Autres objets

8.6.1 Objets fichiers

These APIs are a minimal emulation of the Python 2 C API for built-in file objects, which used to rely on the buffered I/O (FILE*) support from the C standard library. In Python 3, files and streams use the new $i \circ$ module, which defines several layers over the low-level unbuffered I/O of the operating system. The functions described below are convenience C wrappers over these new APIs, and meant mostly for internal error reporting in the interpreter; third-party code is advised to access the $i \circ$ APIs instead.

PyObject *PyFile_FromFd (int fd, const char *name, const char *mode, int buffering, const char *encoding, const char *errors, const char *newline, int closefd)

Return value: New reference. Part of the Stable ABI. Create a Python file object from the file descriptor of an already opened file fd. The arguments name, encoding, errors and newline can be NULL to use the defaults; buffering can be -1 to use the default. name is ignored and kept for backward compatibility. Return NULL on failure. For a more comprehensive description of the arguments, please refer to the io.open() function documentation.

Avertissement : Étant donné que les flux de données Python possèdent leur propre couche de tampon, les mélanger avec des descripteurs de fichiers du niveau du système d'exploitation peut produire des erreurs (comme par exemple un ordre des données inattendu).

Modifié dans la version 3.2 : ignore l'attribut name

int PyObject_AsFileDescriptor(PyObject *p)

Part of the Stable ABI. Return the file descriptor associated with p as an int. If the object is an integer, its value is returned. If not, the object's fileno() method is called if it exists; the method must return an integer, which is returned as the file descriptor value. Sets an exception and returns -1 on failure.

PyObject *PyFile_GetLine (PyObject *p, int n)

Return value: New reference. Part of the Stable ABI. Cette fonction, équivalente à p.readline ([n]), lit une ligne de l'objet p. p peut être un objet fichier ou n'importe quel objet qui possède une méthode readline (). Si n vaut 0, une seule ligne est lue, indépendamment de la taille de la ligne. Si n est plus grand que 0, un maximum de n octets seront lus en provenance du fichier; une ligne partielle peut être renvoyée. Dans les deux cas, une chaîne de caractères vide est renvoyée si la fin du fichier est atteinte immédiatement. Cependant, si n est plus petit que 0, une ligne est lue indépendamment de sa taille, mais EOFError est levée si la fin du fichier est atteinte immédiatement.

int PyFile_SetOpenCodeHook (Py_OpenCodeHookFunction handler)

Overrides the normal behavior of io.open_code () to pass its parameter through the provided handler.

The handler is a function of type PyObject *(*) (PyObject *path, void *userData), where path is guaranteed to be PyUnicodeObject.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

As this hook is intentionally used during import, avoid importing new modules during its execution unless they are known to be frozen or available in sys.modules.

Once a hook has been set, it cannot be removed or replaced, and later calls to PyFile_SetOpenCodeHook() will fail. On failure, the function returns -1 and sets an exception if the interpreter has been initialized.

This function is safe to call before Py_Initialize().

Raises an auditing event setopencodehook with no arguments.

Nouveau dans la version 3.8.

int PyFile_WriteObject (PyObject *obj, PyObject *p, int flags)

Part of the Stable ABI. Write object obj to file object p. The only supported flag for flags is Py_PRINT_RAW;

if given, the str() of the object is written instead of the repr(). Return 0 on success or -1 on failure; the appropriate exception will be set.

int PyFile_WriteString (const char *s, PyObject *p)

Part of the Stable ABI. Écrit la chaîne de caractères s dans l'objet fichier p. Retourne 0 en cas de succès ou -1 en cas d'échec; l'exception appropriée sera mise en place.

8.6.2 Module Objects

PyTypeObject PyModule_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python module type. This is exposed to Python programs as types. ModuleType.

int PyModule_Check (PyObject *p)

Return true if p is a module object, or a subtype of a module object. This function always succeeds.

int PyModule_CheckExact (PyObject *p)

Return true if p is a module object, but not a subtype of PyModule_Type. This function always succeeds.

PyObject *PyModule_NewObject (PyObject *name)

Return value: New reference. Part of the Stable ABI since version 3.7. Return a new module object with the __name__ attribute set to name. The module's __name__, __doc__, __package__, and __loader__ attributes are filled in (all but __name__ are set to None); the caller is responsible for providing a __file__ attribute.

Nouveau dans la version 3.3.

Modifié dans la version 3.4: __package__ and __loader__ are set to None.

PyObject *PyModule_New (const char *name)

Return value: New reference. Part of the Stable ABI. Similar to PyModule_NewObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

PyObject *PyModule_GetDict (PyObject *module)

Return value: Borrowed reference. Part of the Stable ABI. Return the dictionary object that implements module's namespace; this object is the same as the __dict__ attribute of the module object. If module is not a module object (or a subtype of a module object), SystemError is raised and NULL is returned.

It is recommended extensions use other PyModule_* and PyObject_* functions rather than directly manipulate a module's __dict_.

PyObject *PyModule_GetNameObject (PyObject *module)

Return value: New reference. Part of the Stable ABI since version 3.7. Return module's __name__ value. If the module does not provide one, or if it is not a string, SystemError is raised and NULL is returned.

Nouveau dans la version 3.3.

const char *PyModule_GetName (PyObject *module)

Part of the Stable ABI. Similar to PyModule_GetNameObject () but return the name encoded to 'utf-8'.

void *PyModule_GetState (PyObject *module)

Part of the Stable ABI. Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or NULL. See *PyModuleDef.m_size*.

PyModuleDef *PyModule_GetDef (PyObject *module)

Part of the Stable ABI. Return a pointer to the PyModuleDef struct from which the module was created, or NULL if the module wasn't created from a definition.

PyObject *PyModule_GetFilenameObject (PyObject *module)

Return value: New reference. Part of the Stable ABI. Return the name of the file from which module was loaded using module's ___file__ attribute. If this is not defined, or if it is not a unicode string, raise SystemError and return NULL; otherwise return a reference to a Unicode object.

Nouveau dans la version 3.2.

const char *PyModule_GetFilename (PyObject *module)

Part of the Stable ABI. Similar to PyModule_GetFilenameObject() but return the filename encoded to 'utf-8'.

Obsolète depuis la version 3.2 : PyModule_GetFilename() raises UnicodeEncodeError on unencodable filenames, use PyModule_GetFilenameObject() instead.

Initializing C modules

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using <code>PyImport_AppendInittab()</code>). See building or extending-with-embedding for details.

The initialization function can either pass a module definition instance to <code>PyModule_Create()</code>, and return the resulting module object, or request "multi-phase initialization" by returning the definition struct itself.

type PyModuleDef

Part of the Stable ABI (including all members). The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

PyModuleDef_Base m_base

Always initialize this member to PyModuleDef_HEAD_INIT.

const char *m_name

Name for the new module.

const char *m_doc

Docstring for the module; usually a docstring variable created with PyDoc STRVAR is used.

Py_ssize_t m_size

Module state may be kept in a per-module memory area that can be retrieved with $PyModule_GetState()$, rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on m_size on module creation, and freed when the module object is deallocated, after the m_free function has been called, if present.

Setting m_size to -1 means that the module does not support sub-interpreters, because it has global state. Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state. Non-negative m_size is required for multi-phase initialization.

See PEP 3121 for more details.

PyMethodDef *m_methods

A pointer to a table of module-level functions, described by <code>PyMethodDef</code> values. Can be <code>NULL</code> if no functions are present.

```
PyModuleDef_Slot *m_slots
```

An array of slot definitions for multi-phase initialization, terminated by a $\{0, \text{NULL}\}\$ entry. When using single-phase initialization, m_slots must be NULL.

Modifié dans la version 3.5 : Prior to version 3.5, this member was always set to NULL, and was defined as :

inquiry m_reload

traverseproc m traverse

A traversal function to call during GC traversal of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (Py_mod_exec function). More precisely, this function is not called if m_size is greater than 0 and the module state (as returned by $PyModule_GetState()$) is NULL.

Modifié dans la version 3.9 : No longer called before the module state is allocated.

inquiry m_clear

A clear function to call during GC clearing of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (Py_mod_exec function). More precisely, this function is not called if m_size is greater than 0 and the module state (as returned by $PyModule_GetState()$) is NULL.

Like PyTypeObject.tp_clear, this function is not *always* called before a module is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and m_free is called directly.

Modifié dans la version 3.9 : No longer called before the module state is allocated.

freefunc m_free

A function to call during deallocation of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed (Py_mod_exec function). More precisely, this function is not called if m_size is greater than 0 and the module state (as returned by $PyModule_GetState()$) is NULL.

Modifié dans la version 3.9 : No longer called before the module state is allocated.

Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as "single-phase initialization", and uses one of the following two module creation functions:

```
PyObject *PyModule_Create (PyModuleDef *def)
```

Return value: New reference. Create a new module object, given the definition in def. This behaves like PyModule_Create2() with module_api_version set to PYTHON_API_VERSION.

```
PyObject *PyModule_Create2 (PyModuleDef *def, int module_api_version)
```

Return value: New reference. Part of the Stable ABI. Create a new module object, given the definition in def, assuming the API version module_api_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

Note: Most uses of this function should be using <code>PyModule_Create()</code> instead; only use this if you are sure you need it.

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like $PyModule_AddObjectRef()$.

Multi-phase initialization

An alternate way to specify extensions is to request "multi-phase initialization". Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and the *execution phase*, when it is populated. The distinction is similar to the __new__() and __init__() methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the *sys.modules* entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection -- as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using <code>PyModule_GetState())</code>, or its contents (such as the module's <code>__dict__</code> or individual classes created with <code>PyType_FromSpec())</code>.

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (PyInit_modulename) returns a PyModuleDef instance with non-empty m_slots . Before it is returned, the PyModuleDef instance must be initialized with the following function:

```
PyObject *PyModuleDef_Init (PyModuleDef *def)
```

Return value : Borrowed reference. Part of the Stable ABI *since version 3.5.* Ensures a module definition is a properly initialized Python object that correctly reports its type and reference count.

Returns def cast to PyObject*, or NULL if an error occurred.

Nouveau dans la version 3.5.

The *m_slots* member of the module definition must point to an array of PyModuleDef_Slot structures:

type PyModuleDef_Slot

int **slot**

A slot ID, chosen from the available values explained below.

void *value

Value of the slot, whose meaning depends on the slot ID.

Nouveau dans la version 3.5.

The m_slots array must be terminated by a slot with id 0.

The available slot types are:

Py_mod_create

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature :

```
PyObject *create_module (PyObject *spec, PyModuleDef *def)
```

The function receives a ModuleSpec instance, as defined in **PEP 451**, and the module definition. It should return a new module object, or set an error and return NULL.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple Py_mod_create slots may not be specified in one module definition.

If Py_{mod_create} is not specified, the import machinery will create a normal module object using $PyModule_New()$. The name is taken from spec, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of PyModule_Type. Any type can be used, as long as it supports setting and getting import-related attributes. However, only PyModule Type instances may

be returned if the PyModuleDef has non-NULL m_traverse, m_clear, m_free; non-zero m_size; or slots other than Py_mod_create.

Py_mod_exec

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module : typically, this function adds classes and constants to the module. The signature of the function is :

int exec_module (PyObject *module)

If multiple Py_mod_exec slots are specified, they are processed in the order they appear in the *m_slots* array.

Py_mod_multiple_interpreters

Specifies one of the following values:

Py_MOD_MULTIPLE_INTERPRETERS_NOT_SUPPORTED

The module does not support being imported in subinterpreters.

Py_MOD_MULTIPLE_INTERPRETERS_SUPPORTED

The module supports being imported in subinterpreters, but only when they share the main interpreter's GIL. (See isolating-extensions-howto.)

Py_MOD_PER_INTERPRETER_GIL_SUPPORTED

The module supports being imported in subinterpreters, even when they have their own GIL. (See isolating-extensions-howto.)

This slot determines whether or not importing this module in a subinterpreter will fail.

Multiple Py_mod_multiple_interpreters slots may not be specified in one module definition.

If Py_mod_multiple_interpreters is not specified, the import machinery defaults to Py_MOD_MULTIPLE_INTERPRETERS_NOT_SUPPORTED.

Nouveau dans la version 3.12.

See PEP 489 for more details on multi-phase initialization.

Low-level module creation functions

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both PyModule_FromDefAndSpec and PyModule_ExecDef must be called to fully initialize a module.

PyObject *PyModule_FromDefAndSpec (PyModuleDef *def, PyObject *spec)

Return value: New reference. Create a new module object, given the definition in def and the ModuleSpec spec. This behaves like PyModule_FromDefAndSpec2() with module_api_version set to PYTHON_API_VERSION. Nouveau dans la version 3.5.

PyObject *PyModule_FromDefAndSpec2 (PyModuleDef *def, PyObject *spec, int module_api_version)

Return value: New reference. Part of the Stable ABI since version 3.7. Create a new module object, given the definition in def and the ModuleSpec spec, assuming the API version module_api_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

Note: Most uses of this function should be using <code>PyModule_FromDefAndSpec()</code> instead; only use this if you are sure you need it.

Nouveau dans la version 3.5.

int PyModule_ExecDef (PyObject *module, PyModuleDef *def)

Part of the Stable ABI since version 3.7. Process any execution slots (Py_mod_exec) given in def. Nouveau dans la version 3.5.

```
int PyModule_SetDocString (PyObject *module, const char *docstring)
```

Part of the Stable ABI since version 3.7. Set the docstring for module to docstring. This function is called automatically when creating a module from PyModuleDef, using either PyModule_Create or PyModule FromDefAndSpec.

Nouveau dans la version 3.5.

```
int PyModule_AddFunctions (PyObject *module, PyMethodDef *functions)
```

Part of the Stable ABI since version 3.7. Add the functions from the NULL terminated functions array to module. Refer to the <code>PyMethodDef</code> documentation for details on individual entries (due to the lack of a shared module namespace, module level "functions" implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes). This function is called automatically when creating a module from <code>PyModuleDef</code>, using either <code>PyModule_Create</code> or <code>PyModule_FromDefAndSpec</code>.

Nouveau dans la version 3.5.

Support functions

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

```
int PyModule_AddObjectRef (PyObject *module, const char *name, PyObject *value)
```

Part of the Stable ABI since version 3.10. Add an object to module as name. This is a convenience function which can be used from the module's initialization function.

On success, return 0. On error, raise an exception and return -1.

Return NULL if *value* is NULL. It must be called with an exception raised in this case.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_DECREF(obj);
    return res;
}
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_XDECREF(obj);
    return res;
}
```

Note that $Py_XDECREF$ () should be used instead of Py_DECREF () in this case, since *obj* can be NULL. Nouveau dans la version 3.10.

```
int PyModule_AddObject (PyObject *module, const char *name, PyObject *value)
```

Part of the Stable ABI. Similar to PyModule_AddObjectRef(), but steals a reference to value on success (if it returns 0).

The new <code>PyModule_AddObjectRef()</code> function is recommended, since it is easy to introduce reference leaks by misusing the <code>PyModule_AddObject()</code> function.

Note: Unlike other functions that steal references, PyModule_AddObject() only releases the reference to *value* on success.

This means that its return value must be checked, and calling code must Py_DECREF () value manually on error.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_DECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
        // Py_DECREF(obj) is not needed here
    return 0;
}</pre>
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_XDECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}</pre>
```

Note that Py_XDECREF () should be used instead of Py_DECREF () in this case, since obj can be NULL.

int **PyModule_AddIntConstant** (*PyObject* *module, const char *name, long value)

Part of the Stable ABI. Add an integer constant to module as name. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

```
int PyModule AddStringConstant (PyObject *module, const char *name, const char *value)
```

Part of the Stable ABI. Add a string constant to module as name. This convenience function can be used from the module's initialization function. The string value must be NULL-terminated. Return -1 on error, 0 on success.

PyModule_AddIntMacro (module, macro)

Add an int constant to *module*. The name and the value are taken from *macro*. For example $PyModule_AddIntMacro(module, AF_INET)$ adds the int constant AF_INET with the value of AF_INET to *module*. Return -1 on error, 0 on success.

PyModule_AddStringMacro (module, macro)

Add a string constant to module.

int **PyModule_AddType** (*PyObject* *module, *PyTypeObject* *type)

Part of the Stable ABI since version 3.10. Add a type object to module. The type object is finalized by calling internally $PyType_Ready()$. The name of the type object is taken from the last component of tp_name after dot. Return -1 on error, 0 on success.

Nouveau dans la version 3.9.

Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

```
PyObject *PyState_FindModule (PyModuleDef *def)
```

Return value: Borrowed reference. Part of the Stable ABI. Returns the module object that was created from def for the current interpreter. This method requires that the module object has been attached to the interpreter state with PyState_AddModule() beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

```
int PyState_AddModule (PyObject *module, PyModuleDef *def)
```

Part of the Stable ABI *since version 3.3.* Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via *PyState_FindModule()*.

Only effective on modules created using single-phase initialization.

Python calls PyState_AddModule automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls PyState_FindModule. The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

The caller must hold the GIL.

Return 0 on success or -1 on failure.

Nouveau dans la version 3.3.

int PyState_RemoveModule (PyModuleDef *def)

Part of the Stable ABI since version 3.3. Removes the module object created from def from the interpreter state. Return 0 on success or -1 on failure.

The caller must hold the GIL.

Nouveau dans la version 3.3.

8.6.3 Itérateurs

Python provides two general-purpose iterator objects. The first, a sequence iterator, works with an arbitrary sequence supporting the <u>__getitem__()</u> method. The second works with a callable object and a sentinel value, calling the callable for each item in the sequence, and ending the iteration when the sentinel value is returned.

```
PyTypeObject PySeqIter_Type
```

Part of the Stable ABI. Type des itérateurs renvoyés par les fonctions $PySeqIter_New()$ et la forme à un argument de la fonction native iter() pour les séquences natives.

```
int PySeqIter_Check (PyObject *op)
```

Return true if the type of *op* is *PySeqIter_Type*. This function always succeeds.

```
PyObject *PySeqIter_New (PyObject *seq)
```

Return value : New reference. Part of the Stable ABI. Renvoie un itérateur sur la séquence seq. L'itération prend fin lorsque la séquence lève IndexError lors d'une tentative d'accès.

PyTypeObject PyCallIter_Type

Part of the Stable ABI. Type de l'itérateur renvoyé par les fonctions <code>PyCallIter_New()</code> et iter() à deux arguments.

int PyCallIter Check (PyObject *op)

Return true if the type of *op* is *PyCallIter_Type*. This function always succeeds.

```
PyObject *PyCallIter_New (PyObject *callable, PyObject *sentinel)
```

Return value: New reference. Part of the Stable ABI. Renvoie un nouvel itérateur. Le premier paramètre, callable, peut être n'importe quel objet Python appelable sans aucun paramètre; chaque appel doit renvoyer l'élément suivant de l'itération. Lorsque callable renvoie une valeur égale à sentinel, l'itération prend fin.

8.6.4 Les descripteurs

Les "Descripteurs" sont des objets décrivant des attributs pour un objet. Ils se trouvent dans le dictionnaire du type de l'objet.

PyTypeObject PyProperty_Type

Part of the Stable ABI. L'objet type des descripteurs natifs.

```
PyObject *PyDescr_NewGetSet (PyTypeObject *type, struct PyGetSetDef *getset)
```

Return value: New reference. Part of the Stable ABI.

```
PyObject *PyDescr_NewMember (PyTypeObject *type, struct PyMemberDef *meth)
```

Return value: New reference. Part of the Stable ABI.

```
PyObject *PyDescr_NewMethod (PyTypeObject *type, struct PyMethodDef *meth)
```

Return value: New reference. Part of the Stable ABI.

```
PyObject *PyDescr_NewWrapper (PyTypeObject *type, struct wrapperbase *wrapper, void *wrapped)
```

Return value: New reference.

```
PyObject *PyDescr_NewClassMethod (PyTypeObject *type, PyMethodDef *method)
```

Return value: New reference. Part of the Stable ABI.

```
int PyDescr_IsData (PyObject *descr)
```

Return non-zero if the descriptor objects *descr* describes a data attribute, or 0 if it describes a method. *descr* must be a descriptor object; there is no error checking.

```
PyObject *PyWrapper_New (PyObject*, PyObject*)
```

Return value: New reference. Part of the Stable ABI.

8.6.5 Slice Objects

PyTypeObject PySlice_Type

Part of the Stable ABI. The type object for slice objects. This is the same as slice in the Python layer.

```
int PySlice_Check (PyObject *ob)
```

Return true if *ob* is a slice object; *ob* must not be NULL. This function always succeeds.

```
PyObject *PySlice_New (PyObject *start, PyObject *stop, PyObject *step)
```

Return value: New reference. Part of the Stable ABI. Return a new slice object with the given values. The start, stop, and step parameters are used as the values of the slice object attributes of the same names. Any of the values may be NULL, in which case the None will be used for the corresponding attribute. Return NULL if the new object could not be allocated.

```
int PySlice_GetIndices (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Part of the Stable ABI. Retrieve the start, stop and step indices from the slice object *slice*, assuming a sequence of length *length*. Treats indices greater than *length* as errors.

Returns 0 on success and -1 on error with no exception set (unless one of the indices was not None and failed to be converted to an integer, in which case -1 is returned with an exception set).

You probably do not want to use this function.

Modifié dans la version 3.2: The parameter type for the slice parameter was PySliceObject* before.

```
int PySlice_GetIndicesEx (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *stop, Py_ssize_t *slicelength)
```

Part of the Stable ABI. Usable replacement for PySlice_GetIndices(). Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Returns 0 on success and -1 on error with exception set.

Note: This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of <code>PySlice_Unpack()</code> and <code>PySlice_AdjustIndices()</code> where

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength) < 0) {
    // return error
}</pre>
```

is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);</pre>
```

Modifié dans la version 3.2: The parameter type for the *slice* parameter was PySliceObject* before.

Modifié dans la version 3.6.1: If Py_LIMITED_API is not set or set to the value between 0x03050400 and 0x03060000 (not including) or 0x03060100 or higher PySlice_GetIndicesEx() is implemented as a macro using PySlice_Unpack() and PySlice_AdjustIndices(). Arguments *start*, *stop* and *step* are evaluated more than once.

Obsolète depuis la version 3.6.1 : If Py_LIMITED_API is set to the value less than 0×03050400 or between 0×03060000 and 0×03060100 (not including) PySlice_GetIndicesEx() is a deprecated function.

```
int PySlice_Unpack (PyObject *slice, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Part of the Stable ABI since version 3.7. Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than PY_SSIZE_T_MAX to PY_SSIZE_T_MAX, silently boost the start

and stop values less than $PY_SSIZE_T_MIN$ to $PY_SSIZE_T_MIN$, and silently boost the step values less than $-PY_SSIZE_T_MAX$ to $-PY_SSIZE_T_MAX$.

Return -1 on error, 0 on success.

Nouveau dans la version 3.6.1.

Py_ssize_t PySlice_AdjustIndices (Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t step)

Part of the Stable ABI since version 3.7. Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

Nouveau dans la version 3.6.1.

Ellipsis Object

PyObject *Py_Ellipsis

The Python Ellipsis object. This object has no methods. Like Py_None , it is an immortal singleton object. Modifié dans la version $3.12: Py_Ellipsis$ is immortal.

8.6.6 Objets de type MemoryView

Un objet Python memoryview expose le *protocole tampon* du C. Cet objet peut ensuite être passé comme n'importe quel objet.

PyObject *PyMemoryView_FromObject (PyObject *obj)

Return value : New reference. Part of the Stable ABI. Crée un objet memoryview à partir d'un objet implémentant le protocole tampon. Si obj permet d'exporter des tampons modifiables, l'objet memoryview crée acceptera la lecture et écriture, sinon l'objet crée est soit en lecture seule ou lecture/écriture, à la discrétion de l'exporteur.

PyObject *PyMemoryView_FromMemory (char *mem, Py_ssize_t size, int flags)

Return value: New reference. Part of the Stable ABI since version 3.7. Crée un objet memoryview utilisant mem comme un tampon sous-jacent. flags peut être PyBUF_READ ou PyBUF_WRITE.

Nouveau dans la version 3.3.

PyObject *PyMemoryView_FromBuffer (const Py_buffer *view)

Return value: New reference. Part of the Stable ABI since version 3.11. Crée un objet memoryview à partir de la structure tampon view. Pour de simples tampons d'octets, PyMemoryView FromMemory () est préférée.

PyObject *PyMemoryView_GetContiguous (PyObject *obj, int buffertype, char order)

Return value : New reference. Part of the Stable ABI. Crée un objet memoryview vers un segment de mémoire contiguous (organisé comme en 'C' ou comme en 'F' pour Fortran) à partir d'un objet qui expose le protocole tampon. Si la mémoire est contiguë, l'objet memoryview pointe vers la mémoire d'origine. Sinon une copie est faite et la memoryview pointe vers un nouvel objet bytes.

int PyMemoryView_Check (PyObject *obj)

Return true if the object *obj* is a memoryview object. It is not currently allowed to create subclasses of memoryview. This function always succeeds.

Py_buffer *PyMemoryView_GET_BUFFER (PyObject *mview)

Retourne un pointeur vers la copie privée du tampon de l'exporteur de memoryview. mview doit être une instance de memoryview; cette macro ne vérifie pas le type, vous devez le faire vous-même sinon vous pourriez subir un crash.

PyObject *PyMemoryView_GET_BASE (PyObject *mview)

Renvoie soit un pointeur vers l'objet exporté sur lequel est basé la *memoryview* ou NULL si la *memoryview* a été crée par *PyMemoryView_FromMemory()* ou *PyMemoryView_FromBuffer()*. *mview* doit être une instance de *memoryview*.

8.6.7 Objets à références faibles

Python gère les *références faibles* comme des objets de première classe. Il existe deux types d'objets spécifiques qui implémentent directement les références faibles. Le premier est un objet de référence simple, et le second agit autant que possible comme un mandataire vers l'objet original.

int PyWeakref_Check (PyObject *ob)

Return true if *ob* is either a reference or proxy object. This function always succeeds.

int PyWeakref_CheckRef (PyObject *ob)

Return true if *ob* is a reference object. This function always succeeds.

int PyWeakref_CheckProxy (PyObject *ob)

Return true if *ob* is a proxy object. This function always succeeds.

PyObject *PyWeakref_NewRef (PyObject *ob, PyObject *callback)

Return value: New reference. Part of the Stable ABI. Return a weak reference object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing reference object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

PyObject *PyWeakref_NewProxy (PyObject *ob, PyObject *callback)

Return value: New reference. Part of the Stable ABI. Return a weak reference proxy object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing proxy object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

PyObject *PyWeakref_GetObject (PyObject *ref)

Return value: Borrowed reference. Part of the Stable ABI. Return the referenced object from a weak reference, ref. If the referent is no longer live, returns Py None.

Note: This function returns a *borrowed reference* to the referenced object. This means that you should always call $Py_INCREF()$ on the object except when it cannot be destroyed before the last usage of the borrowed reference.

PyObject *PyWeakref_GET_OBJECT (PyObject *ref)

Return value: Borrowed reference. Similar to PyWeakref_GetObject(), but does no error checking.

void PyObject_ClearWeakRefs (PyObject *object)

Part of the Stable ABI. This function is called by the $tp_dealloc$ handler to clear weak references.

This iterates through the weak references for *object* and calls callbacks for those references which have one. It returns when all callbacks have been attempted.

8.6.8 Capsules

Reportez-vous à using-capsules pour plus d'informations sur l'utilisation de ces objets.

Nouveau dans la version 3.1.

type PyCapsule

This subtype of <code>PyObject</code> represents an opaque value, useful for C extension modules who need to pass an opaque value (as a <code>void*</code> pointer) through Python code to other C code. It is often used to make a C function pointer defined in one module available to other modules, so the regular import mechanism can be used to access C APIs defined in dynamically loaded modules.

type PyCapsule_Destructor

Part of the Stable ABI. The type of a destructor callback for a capsule. Defined as:

```
typedef void (*PyCapsule_Destructor) (PyObject *);
```

See PyCapsule_New() for the semantics of PyCapsule_Destructor callbacks.

int PyCapsule_CheckExact (PyObject *p)

Return true if its argument is a PyCapsule. This function always succeeds.

PyObject *PyCapsule_New (void *pointer, const char *name, PyCapsule_Destructor destructor)

Return value : New reference. Part of the Stable ABI. Create a *PyCapsule* encapsulating the *pointer*. The *pointer* argument may not be NULL.

On failure, set an exception and return NULL.

The *name* string may either be NULL or a pointer to a valid C string. If non-NULL, this string must outlive the capsule. (Though it is permitted to free it inside the *destructor*.)

If the destructor argument is not NULL, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the *name* should be specified as modulename. attributename. This will enable other modules to import the capsule using <code>PyCapsule_Import()</code>.

void *PyCapsule_GetPointer (*PyObject* *capsule, const char *name)

Part of the Stable ABI. Retrieve the pointer stored in the capsule. On failure, set an exception and return NULL.

The *name* parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is NULL, the *name* passed in must also be NULL. Python uses the C function strcmp () to compare capsule names.

PyCapsule_Destructor PyCapsule_GetDestructor (PyObject *capsule)

Part of the Stable ABI. Return the current destructor stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL destructor. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule_IsValid()</code> or <code>PyErr_Occurred()</code> to disambiguate.

void *PyCapsule_GetContext (PyObject *capsule)

Part of the Stable ABI. Return the current context stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL context. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule_IsValid()</code> or <code>PyErr_Occurred()</code> to disambiguate.

const char *PyCapsule_GetName (PyObject *capsule)

Part of the Stable ABI. Return the current name stored in the capsule. On failure, set an exception and return NULL. It is legal for a capsule to have a NULL name. This makes a NULL return code somewhat ambiguous; use PyCapsule_IsValid() or PyErr_Occurred() to disambiguate.

void *PyCapsule_Import (const char *name, int no_block)

Part of the Stable ABI. Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in module.attribute. The *name* stored in the capsule must match this string exactly.

Return the capsule's internal *pointer* on success. On failure, set an exception and return NULL.

Modifié dans la version 3.3 : *no_block* has no effect anymore.

int PyCapsule_IsValid (*PyObject* *capsule, const char *name)

Part of the Stable ABI. Determines whether or not capsule is a valid capsule. A valid capsule is non-NULL, passes PyCapsule_CheckExact(), has a non-NULL pointer stored in it, and its internal name matches the name parameter. (See PyCapsule_GetPointer() for information on how capsule names are compared.)

In other words, if PyCapsule_IsValid() returns a true value, calls to any of the accessors (any function starting with PyCapsule_Get) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return 0 otherwise. This function will not fail.

int PyCapsule SetContext (PyObject *capsule, void *context)

Part of the Stable ABI. Set the context pointer inside capsule to context.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetDestructor (PyObject *capsule, PyCapsule_Destructor destructor)

Part of the Stable ABI. Set the destructor inside capsule to destructor.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetName (PyObject *capsule, const char *name)

Part of the Stable ABI. Set the name inside *capsule* to *name*. If non-NULL, the name must outlive the capsule. If the previous *name* stored in the capsule was not NULL, no attempt is made to free it.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetPointer (PyObject *capsule, void *pointer)

Part of the Stable ABI. Set the void pointer inside capsule to pointer. The pointer may not be NULL.

Return 0 on success. Return nonzero and set an exception on failure.

8.6.9 Objets décrivant les frames

type PyFrameObject

Part of the Limited API (as an opaque struct). Structure des objets C utilisée pour décrire les objets frame.

Il n'y a pas de membres publics dans cette structure.

Modifié dans la version 3.11 : Les membres de la structure API publique ont été retirés de l'API publique de C. Visiter l'entrée dans la page des nouveautés de Python pour plus détails.

Les fonctions PyEval_GetFrame () et PyThreadState_GetFrame () peuvent être utilisées pour avoir un objet de frame.

Voir aussi Réflexion

PyTypeObject PyFrame_Type

Le type des objets de frame. C'est le même objet que types. Frame Type dans la couche de Python.

Modifié dans la version 3.11 : Précédemment, ce type était disponible uniquement après l'inclusion de <frameobject.h>.

int PyFrame_Check (PyObject *obj)

Renvoie un entier non nul si obj est un objet frame.

Modifié dans la version 3.11 : Précédemment, ce type était disponible uniquement après l'inclusion de <frameobject.h>.

PyFrameObject *PyFrame_GetBack (PyFrameObject *frame)

Renvoie la frame encadrant immédiatement à frame.

Renvoie un strong reference, ou NULL si frame n'a pas de frame encadrante.

Nouveau dans la version 3.9.

PyObject *PyFrame_GetBuiltins (PyFrameObject *frame)

Obtenir l'attribut f_buitins de frame.

Renvoie un strong reference. Le résultat ne peut être NULL.

Nouveau dans la version 3.11.

PyCodeObject *PyFrame_GetCode (PyFrameObject *frame)

Part of the Stable ABI since version 3.10. Obtenir le code frame.

Renvoie un strong reference.

Le résultat (code *frame*) ne peut être NULL.

Nouveau dans la version 3.9.

PyObject *PyFrame_GetGenerator (PyFrameObject *frame)

Obtenir le générateur, coroutine, ou un générateur asynchrone qui maintient cette *frame*, ou NULL si cette *frame* n'est pas maintenu par un générateur. Il ne lève pas d'exception, même si la valeur renvoyée est NULL.

Renvoie un strong reference, ou NULL.

Nouveau dans la version 3.11.

PyObject *PyFrame_GetGlobals (PyFrameObject *frame)

Obtenir l'attribut f_globals de frame.

Renvoie un strong reference. Le résultat ne peut être NULL.

Nouveau dans la version 3.11.

int PyFrame_GetLasti (PyFrameObject *frame)

Obtenir l'attribut f_lasti de frame.

Renvoie -1 si frame .f_lasti est None.

Nouveau dans la version 3.11.

PyObject *PyFrame_GetVar (PyFrameObject *frame, PyObject *name)

Get the variable name of frame.

- Return a *strong reference* to the variable value on success.
- Raise NameError and return NULL if the variable does not exist.
- Raise an exception and return NULL on error.

name type must be a str.

Nouveau dans la version 3.12.

PyObject *PyFrame_GetVarString (PyFrameObject *frame, const char *name)

Similar to PyFrame_GetVar(), but the variable name is a C string encoded in UTF-8.

Nouveau dans la version 3.12.

PyObject *PyFrame_GetLocals (PyFrameObject *frame)

Obtenir l'attribut (dict) f locals de frame.

Renvoie un strong reference.

Nouveau dans la version 3.11.

int PyFrame_GetLineNumber (PyFrameObject *frame)

Part of the Stable ABI since version 3.10. Renvoie le numéro de ligne que cette frame est en train d'exécuter.

Internal Frames

Unless using PEP 523, you will not need this.

struct _PyInterpreterFrame

The interpreter's internal frame representation.

Nouveau dans la version 3.11.

PyObject *PyUnstable_InterpreterFrame_GetCode (struct _PyInterpreterFrame *frame);

This is *Unstable API*. It may change without warning in minor releases.

Return a *strong reference* to the code object for the frame.

Nouveau dans la version 3.12.

int PyUnstable_InterpreterFrame_GetLasti (struct _PyInterpreterFrame *frame);

This is *Unstable API*. It may change without warning in minor releases.

Return the byte offset into the last executed instruction.

Nouveau dans la version 3.12.

int PyUnstable_InterpreterFrame_GetLine (struct _PyInterpreterFrame *frame);

This is *Unstable API*. It may change without warning in minor releases.

Return the currently executing line number, or -1 if there is no line number.

Nouveau dans la version 3.12.

8.6.10 Objets générateur

Python utilise des objets générateurs pour implémenter les itérations de générateurs. Ils sont normalement crées en itérant sur une fonction donnant des valeurs via yield, au lieu d'appeler explicitement $PyGen_New()$ ou $PyGen_NewWithQualName()$.

type PyGenObject

La structure C utilisée pour les objets générateurs.

PyTypeObject PyGen_Type

Le type objet correspondant aux objets générateurs.

```
int PyGen_Check (PyObject *ob)
```

Return true if *ob* is a generator object; *ob* must not be NULL. This function always succeeds.

int PyGen CheckExact (PyObject *ob)

Return true if *ob*'s type is *PyGen_Type*; *ob* must not be NULL. This function always succeeds.

PyObject *PyGen_New (PyFrameObject *frame)

Return value : New reference. Create and return a new generator object based on the *frame* object. A reference to *frame* is stolen by this function. The argument must not be NULL.

```
PyObject *PyGen_NewWithQualName (PyFrameObject *frame, PyObject *name, PyObject *qualname)
```

Return value: New reference. Create and return a new generator object based on the frame object, with __name__ and __qualname__ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be NULL.

8.6. Autres objets

8.6.11 Objets coroutines

Nouveau dans la version 3.5.

Les objets coroutines sont les objets renvoyés par les fonctions déclarées avec le mot clef async.

type PyCoroObject

La structure C utilisée pour les objets coroutine.

```
PyTypeObject PyCoro_Type
```

L'objet type correspondant aux objets coroutines.

```
int PyCoro_CheckExact (PyObject *ob)
```

Return true if *ob*'s type is *PyCoro_Type*; *ob* must not be NULL. This function always succeeds.

```
PyObject *PyCoro_New (PyFrameObject *frame, PyObject *name, PyObject *qualname)
```

Return value: New reference. Create and return a new coroutine object based on the frame object, with __name__ and __qualname__ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be <code>NULL</code>.

8.6.12 Context Variables Objects

Modifié dans la version 3.7.1:

Note: In Python 3.7.1 the signatures of all context variables C APIs were **changed** to use *PyObject* pointers instead of *PyContext*, *PyContextVar*, and *PyContextToken*, e.g.:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

See bpo-34762 for more details.

Nouveau dans la version 3.7.

This section details the public C API for the contextvars module.

type PyContext

The C structure used to represent a contextvars. Context object.

type PyContextVar

The C structure used to represent a contextvars.ContextVar object.

$type \; \textbf{PyContextToken}$

The C structure used to represent a contextvars. Token object.

PyTypeObject PyContext_Type

The type object representing the *context* type.

PyTypeObject PyContextVar_Type

The type object representing the *context variable* type.

PyTypeObject PyContextToken_Type

The type object representing the *context variable token* type.

Macros pour vérifier les types :

int PyContext_CheckExact (PyObject *o)

Return true if o is of type $PyContext_Type$. o must not be NULL. This function always succeeds.

int PyContextVar CheckExact (PyObject *o)

Return true if o is of type PyContextVar Type. o must not be NULL. This function always succeeds.

int PyContextToken_CheckExact (PyObject *o)

Return true if o is of type $PyContextToken_Type$. o must not be NULL. This function always succeeds.

Context object management functions:

PyObject *PyContext_New (void)

Return value: New reference. Create a new empty context object. Returns NULL if an error has occurred.

PyObject *PyContext_Copy (PyObject *ctx)

Return value : New reference. Create a shallow copy of the passed *ctx* context object. Returns NULL if an error has occurred.

PyObject *PyContext_CopyCurrent (void)

Return value: New reference. Create a shallow copy of the current thread context. Returns NULL if an error has occurred

int PyContext_Enter (PyObject *ctx)

Set ctx as the current context for the current thread. Returns 0 on success, and -1 on error.

int PyContext_Exit (PyObject *ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns 0 on success, and -1 on error.

Context variable functions:

PyObject *PyContextVar_New (const char *name, PyObject *def)

Return value: New reference. Create a new ContextVar object. The name parameter is used for introspection and debug purposes. The def parameter specifies a default value for the context variable, or NULL for no default. If an error has occurred, this function returns NULL.

```
int PyContextVar_Get (PyObject *var, PyObject *default_value, PyObject **value)
```

Get the value of a context variable. Returns -1 if an error has occurred during lookup, and 0 if no error occurred, whether or not a value was found.

If the context variable was found, *value* will be a pointer to it. If the context variable was *not* found, *value* will point to :

```
— default value, if not NULL;
```

- the default value of *var*, if not NULL;
- NULL

Except for NULL, the function returns a new reference.

PyObject *PyContextVar_Set (PyObject *var, PyObject *value)

Return value : New reference. Set the value of *var* to *value* in the current context. Returns a new token object for this change, or NULL if an error has occurred.

int PyContextVar_Reset (PyObject *var, PyObject *token)

Reset the state of the var context variable to that it was in before $PyContextVar_Set$ () that returned the token was called. This function returns 0 on success and -1 on error.

8.6. Autres objets

8.6.13 Objets DateTime

Various date and time objects are supplied by the datetime module. Before using any of these functions, the header file datetime.h must be included in your source (note that this is not included by Python.h), and the macro PyDateTime_IMPORT must be invoked, usually as part of the module initialisation function. The macro puts a pointer to a C structure into a static variable, PyDateTimeAPI, that is used by the following macros.

type PyDateTime_Date

This subtype of PyObject represents a Python date object.

type PyDateTime_DateTime

This subtype of PyObject represents a Python datetime object.

type PyDateTime_Time

This subtype of PyObject represents a Python time object.

type PyDateTime_Delta

This subtype of PyObject represents the difference between two datetime values.

PyTypeObject PyDateTime_DateType

This instance of PyTypeObject represents the Python date type; it is the same object as datetime. date in the Python layer.

PyTypeObject PyDateTime_DateTimeType

This instance of PyTypeObject represents the Python datetime type; it is the same object as datetime. datetime in the Python layer.

PyTypeObject PyDateTime_TimeType

This instance of PyTypeObject represents the Python time type; it is the same object as datetime.time in the Python layer.

PyTypeObject PyDateTime_DeltaType

This instance of PyTypeObject represents Python type for the difference between two datetime values; it is the same object as datetime.timedelta in the Python layer.

PyTypeObject PyDateTime_TZInfoType

This instance of PyTypeObject represents the Python time zone info type; it is the same object as datetime. tzinfo in the Python layer.

Macro pour accéder au singleton UTC:

PyObject *PyDateTime TimeZone UTC

Renvoie le singleton du fuseau horaire UTC, qui est le même objet que datetime.timezone.utc.

Nouveau dans la version 3.7.

Macros pour vérifier les types :

int PyDate_Check (PyObject *ob)

Return true if ob is of type $PyDateTime_DateType$ or a subtype of $PyDateTime_DateType$. ob must not be NULL. This function always succeeds.

int PyDate_CheckExact (PyObject *ob)

Return true if ob is of type $PyDateTime_DateType$. ob must not be NULL. This function always succeeds.

int PyDateTime_Check (PyObject *ob)

Return true if ob is of type $PyDateTime_DateTimeType$ or a subtype of $PyDateTime_DateTimeType$. ob must not be NULL. This function always succeeds.

int PyDateTime_CheckExact (PyObject *ob)

Return true if ob is of type $PyDateTime_DateTimeType.$ ob must not be NULL. This function always succeeds.

int PyTime_Check (*PyObject* *ob)

Return true if ob is of type $PyDateTime_TimeType$ or a subtype of $PyDateTime_TimeType$. ob must not be NULL. This function always succeeds.

int PyTime CheckExact (PyObject *ob)

Return true if ob is of type $PyDateTime_TimeType.$ ob must not be NULL. This function always succeeds.

int PyDelta_Check (PyObject *ob)

Return true if ob is of type $PyDateTime_DeltaType$ or a subtype of $PyDateTime_DeltaType$. ob must not be NULL. This function always succeeds.

int PyDelta_CheckExact (PyObject *ob)

Return true if ob is of type $PyDateTime_DeltaType$. ob must not be NULL. This function always succeeds.

int PyTZInfo_Check (PyObject *ob)

Return true if ob is of type $PyDateTime_TZInfoType$ or a subtype of $PyDateTime_TZInfoType$. ob must not be NULL. This function always succeeds.

int PyTZInfo_CheckExact (PyObject *ob)

Return true if ob is of type $PyDateTime_TZInfoType$. ob must not be NULL. This function always succeeds.

Macros pour créer des objets :

PyObject *PyDate_FromDate (int year, int month, int day)

Return value : New reference. Renvoie un objet datetime.date avec l'année, le mois et le jour spécifiés.

PyObject *PyDateTime_FromDateAndTime (int year, int month, int day, int hour, int minute, int second, int usecond)

Return value : New reference. Renvoie un objet datetime .datetime avec l'année, le mois, le jour, l'heure, la minute, la seconde et la microseconde spécifiés.

PyObject *PyDateTime_FromDateAndTimeAndFold (int year, int month, int day, int hour, int minute, int second, int usecond, int fold)

Return value : New reference. Renvoie un objet datetime . datetime avec l'année, le mois, le jour, l'heure, la minute, la seconde, la microseconde et le pli (fold en anglais) spécifiés.

Nouveau dans la version 3.6.

PyObject *PyTime_FromTime (int hour, int minute, int second, int usecond)

Return value : New reference. Renvoie un objet datetime.time avec l'heure, la minute, la seconde et la microseconde spécifiées.

PyObject *PyTime_FromTimeAndFold (int hour, int minute, int second, int usecond, int fold)

Return value : New reference. Renvoie un objet datetime.time avec l'heure, la minute, la seconde, la microseconde et le pli (fold en anglais) spécifiés.

Nouveau dans la version 3.6.

PyObject *PyDelta_FromDSU (int days, int seconds, int useconds)

Return value : New reference. Renvoie un objet datetime.timedelta représentant le nombre passé en paramètre de jours, de secondes et de microsecondes. Le résultat est normalisé pour que le nombre de microsecondes et de secondes tombe dans la plage documentée pour les objets datetime.timedelta.

8.6. Autres objets

PyObject *PyTimeZone_FromOffset (PyObject *offset)

Return value: New reference. Renvoie un objet datetime.timezone avec un décalage anonyme fixe représenté par l'argument offset.

Nouveau dans la version 3.7.

PyObject *PyTimeZone_FromOffsetAndName (PyObject *offset, PyObject *name)

Return value : New reference. Renvoie un objet datetime.timezone avec un décalage fixe représenté par l'argument offset et avec le nom de fuseau horaire name.

Nouveau dans la version 3.7.

Macros to extract fields from date objects. The argument must be an instance of PyDateTime_Date, including subclasses (such as PyDateTime_DateTime). The argument must not be NULL, and the type is not checked:

```
int PyDateTime_GET_YEAR (PyDateTime_Date *o)
```

Renvoie l'année, sous forme d'entier positif.

```
int PyDateTime_GET_MONTH (PyDateTime_Date *o)
```

Renvoie le mois, sous forme d'entier allant de 1 à 12.

```
int PyDateTime_GET_DAY (PyDateTime_Date *o)
```

Renvoie le jour, sous forme d'entier allant de 1 à 31.

Macros to extract fields from datetime objects. The argument must be an instance of PyDateTime_DateTime, including subclasses. The argument must not be NULL, and the type is not checked:

```
int PyDateTime_DATE_GET_HOUR (PyDateTime_DateTime *o)
```

Renvoie l'heure, sous forme d'entier allant de 0 à 23.

```
int PyDateTime_DATE_GET_MINUTE (PyDateTime_DateTime *o)
```

Renvoie la minute, sous forme d'entier allant de 0 à 59.

```
int PyDateTime_DATE_GET_SECOND (PyDateTime_DateTime *o)
```

Renvoie la seconde, sous forme d'entier allant de 0 à 59.

```
int PyDateTime DATE GET MICROSECOND (PyDateTime DateTime *0)
```

Renvoie la microseconde, sous forme d'entier allant de 0 à 999999.

```
int PyDateTime DATE GET FOLD (PyDateTime DateTime *o)
```

Return the fold, as an int from 0 through 1.

Nouveau dans la version 3.6.

PyObject *PyDateTime_DATE_GET_TZINFO (PyDateTime_DateTime *0)

Return the tzinfo (which may be None).

Nouveau dans la version 3.10.

Macros to extract fields from time objects. The argument must be an instance of PyDateTime_Time, including subclasses. The argument must not be NULL, and the type is not checked:

```
int PyDateTime_TIME_GET_HOUR (PyDateTime_Time *o)
```

Renvoie l'heure, sous forme d'entier allant de 0 à 23.

```
int PyDateTime_TIME_GET_MINUTE (PyDateTime_Time *o)
```

Renvoie la minute, sous forme d'entier allant de 0 à 59.

```
int PyDateTime TIME GET SECOND (PyDateTime *o)
```

Renvoie la seconde, sous forme d'entier allant de 0 à 59.

```
int PyDateTime_TIME_GET_MICROSECOND (PyDateTime_Time *o)
```

Renvoie la microseconde, sous forme d'entier allant de 0 à 999999.

```
int PyDateTime_TIME_GET_FOLD (PyDateTime_Time *o)
```

Return the fold, as an int from 0 through 1.

Nouveau dans la version 3.6.

```
PyObject *PyDateTime_TIME_GET_TZINFO (PyDateTime_Time *o)
```

Return the tzinfo (which may be None).

Nouveau dans la version 3.10.

Macros to extract fields from time delta objects. The argument must be an instance of PyDateTime_Delta, including subclasses. The argument must not be NULL, and the type is not checked:

```
int PyDateTime_DELTA_GET_DAYS (PyDateTime_Delta *o)
```

Renvoie le nombre de jours, sous forme d'entier allant de -99999999 à 999999999.

Nouveau dans la version 3.3.

```
int PyDateTime_DELTA_GET_SECONDS (PyDateTime_Delta *o)
```

Renvoie le nombre de secondes sous forme d'entier allant de 0 à 86399.

Nouveau dans la version 3.3.

```
int PyDateTime DELTA GET MICROSECONDS (PyDateTime Delta *o)
```

Renvoie le nombre de microsecondes, sous forme d'entier allant de 0 à 999999.

Nouveau dans la version 3.3.

Macros de confort pour les modules implémentant l'API DB:

```
PyObject *PyDateTime_FromTimestamp (PyObject *args)
```

Return value : New reference. Crée et renvoie un nouvel objet datetime à partir d'un n-uplet qui peut être passé à datetime .datetime .fromtimestamp().

```
PyObject *PyDate_FromTimestamp (PyObject *args)
```

Return value: New reference. Crée et renvoie un nouvel objet datetime.date à partir d'un n-uplet qui peut être passé à datetime.date.fromtimestamp().

8.6.14 Objects for Type Hinting

Various built-in types for type hinting are provided. Currently, two types exist -- GenericAlias and Union. Only GenericAlias is exposed to C.

```
PyObject *Py_GenericAlias (PyObject *origin, PyObject *args)
```

Part of the Stable ABI since version 3.9. Create a GenericAlias object. Equivalent to calling the Python class types.GenericAlias. The origin and args arguments set the GenericAlias's __origin__ and __args__ attributes respectively. origin should be a PyTypeObject*, and args can be a PyTupleObject* or any PyObject*. If args passed is not a tuple, a 1-tuple is automatically constructed and __args__ is set to (args,). Minimal checking is done for the arguments, so the function will succeed even if origin is not a type. The GenericAlias's __parameters__ attribute is constructed lazily from __args__. On failure, an exception is raised and NULL is returned.

Here's an example of how to make an extension type generic:

```
static PyMethodDef my_obj_methods[] = {
   // Other methods.
   ...
```

(suite sur la page suivante)

8.6. Autres objets 179

(suite de la page précédente)

```
{"__class_getitem__", Py_GenericAlias, METH_O|METH_CLASS, "See PEP 585"}
...
}
```

Voir aussi:

The data model method $__class_getitem__()$.

Nouveau dans la version 3.9.

PyTypeObject Py_GenericAliasType

Part of the Stable ABI since version 3.9. The C type of the object returned by $Py_GenericAlias$ (). Equivalent to types. GenericAlias in Python.

Nouveau dans la version 3.9.

CHAPITRE 9

Initialization, Finalization, and Threads

See also Python Initialization Configuration.

9.1 Before Python Initialization

In an application embedding Python, the $Py_Initialize()$ function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

The following functions can be safely called before Python is initialized:

```
— Configuration functions:
  — PyImport_AppendInittab()
  — PyImport_ExtendInittab()
  — PyInitFrozenExtensions()
  — PyMem_SetAllocator()
  — PyMem_SetupDebugHooks()
  — PyObject_SetArenaAllocator()
  — Py_SetPath()
  — Py_SetProgramName()
  — Py_SetPythonHome()
  — Py_SetStandardStreamEncoding()
  — PySys_AddWarnOption()
  — PySys_AddXOption()
  — PySys_ResetWarnOptions()
— Informative functions:
  — Py_IsInitialized()
  - PyMem GetAllocator()
  — PyObject_GetArenaAllocator()
  — Py_GetBuildInfo()
  — Py_GetCompiler()
  — Py_GetCopyright()
  — Py_GetPlatform()
  — Py_GetVersion()
```

Note: The following functions should not be called before Py_Initialize(): Py_EncodeLocale(), Py_GetPath(), Py_GetPrefix(), Py_GetExecPrefix(), Py_GetProgramFullPath(), Py_GetPythonHome(), Py_GetProgramName() and PyEval_InitThreads().

9.2 Global configuration variables

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example, $\neg b$ sets $Py_BytesWarningFlag$ to 1 and $\neg bb$ sets $Py_BytesWarningFlag$ to 2.

int Py_BytesWarningFlag

This API is kept for backward compatibility: setting PyConfig.bytes_warning should be used instead, see Python Initialization Configuration.

Issue a warning when comparing bytes or bytearray with str or bytes with int. Issue an error if greater or equal to 2.

Set by the -b option.

Obsolète depuis la version 3.12.

int Py_DebugFlag

This API is kept for backward compatibility: setting PyConfig.parser_debug should be used instead, see Python Initialization Configuration.

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the -d option and the PYTHONDEBUG environment variable.

Obsolète depuis la version 3.12.

int Py_DontWriteBytecodeFlag

This API is kept for backward compatibility: setting PyConfig.write_bytecode should be used instead, see Python Initialization Configuration.

If set to non-zero, Python won't try to write $\mbox{.pyc}$ files on the import of source modules.

Set by the -B option and the PYTHONDONTWRITEBYTECODE environment variable.

Obsolète depuis la version 3.12.

int Py_FrozenFlag

This API is kept for backward compatibility: setting PyConfig.pathconfig_warnings should be used instead, see Python Initialization Configuration.

Suppress error messages when calculating the module search path in Py GetPath ().

Private flag used by _freeze_module and frozenmain programs.

Obsolète depuis la version 3.12.

int Py HashRandomizationFlag

This API is kept for backward compatibility: setting PyConfig.hash_seed and PyConfig.use_hash_seed should be used instead, see Python Initialization Configuration.

Set to 1 if the PYTHONHASHSEED environment variable is set to a non-empty string.

If the flag is non-zero, read the PYTHONHASHSEED environment variable to initialize the secret hash seed.

Obsolète depuis la version 3.12.

int Py_IgnoreEnvironmentFlag

This API is kept for backward compatibility: setting <code>PyConfig.use_environment</code> should be used instead, see <code>Python Initialization Configuration</code>.

Ignore all PYTHON* environment variables, e.g. PYTHONPATH and PYTHONHOME, that might be set.

Set by the -E and -I options.

Obsolète depuis la version 3.12.

int Py_InspectFlag

This API is kept for backward compatibility: setting PyConfig.inspect should be used instead, see Python Initialization Configuration.

When a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Set by the -i option and the PYTHONINSPECT environment variable.

Obsolète depuis la version 3.12.

int Py_InteractiveFlag

This API is kept for backward compatibility: setting PyConfig.interactive should be used instead, see Python Initialization Configuration.

Set by the -i option.

Obsolète depuis la version 3.12.

int Py_IsolatedFlag

This API is kept for backward compatibility: setting PyConfig.isolated should be used instead, see Python Initialization Configuration.

Run Python in isolated mode. In isolated mode sys.path contains neither the script's directory nor the user's site-packages directory.

Set by the -I option.

Nouveau dans la version 3.4.

Obsolète depuis la version 3.12.

int Py_LegacyWindowsFSEncodingFlag

This API is kept for backward compatibility: setting <code>PyPreConfig.legacy_windows_fs_encoding</code> should be used instead, see <code>Python Initialization Configuration</code>.

If the flag is non-zero, use the mbcs encoding with replace error handler, instead of the UTF-8 encoding with surrogatepass error handler, for the *filesystem encoding and error handler*.

Set to 1 if the PYTHONLEGACYWINDOWSFSENCODING environment variable is set to a non-empty string.

Voir la PEP 529 pour plus d'informations.

Disponibilité: Windows.

Obsolète depuis la version 3.12.

int Py_LegacyWindowsStdioFlag

This API is kept for backward compatibility: setting <code>PyConfig.legacy_windows_stdio</code> should be used instead, see <code>Python Initialization Configuration</code>.

If the flag is non-zero, use io.FileIO instead of io._WindowsConsoleIO for sys standard streams.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

See PEP 528 for more details.

Disponibilité: Windows.

Obsolète depuis la version 3.12.

int Py_NoSiteFlag

This API is kept for backward compatibility: setting PyConfig.site_import should be used instead, see Python Initialization Configuration.

Désactive l'importation du module site et les modifications locales de sys.path qu'il implique. Désactive aussi ces manipulations si site est importé explicitement plus tard (appelez site.main() si vous voulez les déclencher).

Set by the -S option.

Obsolète depuis la version 3.12.

int Py_NoUserSiteDirectory

This API is kept for backward compatibility: setting <code>PyConfig.user_site_directory</code> should be used instead, see <code>Python Initialization Configuration</code>.

N'ajoute pas le répertoire utilisateur site-packages à sys.path.

Set by the -s and -I options, and the PYTHONNOUSERSITE environment variable.

Obsolète depuis la version 3.12.

int Py_OptimizeFlag

This API is kept for backward compatibility: setting <code>PyConfig.optimization_level</code> should be used instead, see <code>Python Initialization Configuration</code>.

Set by the -O option and the PYTHONOPTIMIZE environment variable.

Obsolète depuis la version 3.12.

int Py_QuietFlag

This API is kept for backward compatibility: setting PyConfig.quiet should be used instead, see Python Initialization Configuration.

N'affiche pas le copyright et la version, même en mode interactif.

Set by the -q option.

Nouveau dans la version 3.2.

Obsolète depuis la version 3.12.

int Py_UnbufferedStdioFlag

This API is kept for backward compatibility: setting PyConfig.buffered_stdio should be used instead, see Python Initialization Configuration.

Force the stdout and stderr streams to be unbuffered.

Set by the -u option and the PYTHONUNBUFFERED environment variable.

Obsolète depuis la version 3.12.

int Py_VerboseFlag

This API is kept for backward compatibility: setting PyConfig.verbose should be used instead, see Python Initialization Configuration.

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the -v option and the PYTHONVERBOSE environment variable.

Obsolète depuis la version 3.12.

9.3 Initializing and finalizing the interpreter

void Py_Initialize()

Part of the Stable ABI. Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (sys.modules), and creates the fundamental modules builtins, __main__ and sys. It also initializes the module search path (sys.path). It does not set sys.argv; use $PySys_SetArgvEx()$ for that. This is a no-op when called for a second time (without calling $Py_FinalizeEx()$ first). There is no return value; it is a fatal error if the initialization fails.

Use the Py_InitializeFromConfiq() function to customize the Python Initialization Configuration.

Note: On Windows, changes the console mode from O_TEXT to O_BINARY , which will also affect non-Python uses of the console using the C Runtime.

void Py_InitializeEx (int initsigs)

Part of the Stable ABI. This function works like $Py_Initialize()$ if initsigs is 1. If initsigs is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

Use the Py_InitializeFromConfig() function to customize the Python Initialization Configuration.

int Py_IsInitialized()

Part of the Stable ABI. Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After Py_FinalizeEx() is called, this returns false until Py_Initialize() is called again.

int Py_FinalizeEx()

Part of the Stable ABI since version 3.6. Undo all initializations made by $Py_Initialize()$ and subsequent use of Python/C API functions, and destroy all sub-interpreters (see $Py_NewInterpreter()$ below) that were created and not yet destroyed since the last call to $Py_Initialize()$. Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling $Py_Initialize()$ again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

Bugs and caveats: The destruction of modules and objects in modules is done in random order; this may cause destructors (__del__() methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls Py_Initialize() and Py_FinalizeEx() more than once.

Raises an auditing event cpython._PySys_ClearAuditHooks with no arguments.

Nouveau dans la version 3.6.

void Py_Finalize()

Part of the Stable ABI. This is a backwards-compatible version of $Py_FinalizeEx()$ that disregards the return value.

9.4 Process-wide parameters

int Py_SetStandardStreamEncoding (const char *encoding, const char *errors)

This API is kept for backward compatibility: setting PyConfig.stdio_encoding and PyConfig.stdio_errors should be used instead, see Python Initialization Configuration.

This function should be called before $Py_Initialize()$, if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in str.encode().

It overrides PYTHONIOENCODING values, and allows embedding code to control IO encoding when the environment variable does not work.

encoding and/or errors may be NULL to use PYTHONIOENCODING and/or default values (depending on other settings).

Note that sys.stderr always uses the "backslashreplace" error handler, regardless of this (or any other) setting. If $Py_FinalizeEx()$ is called, this function will need to be called again in order to affect subsequent calls to $Py_Initialize()$.

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized).

Nouveau dans la version 3.4.

Obsolète depuis la version 3.11.

void Py_SetProgramName (const wchar_t *name)

Part of the Stable ABI. This API is kept for backward compatibility: setting <code>PyConfig.program_name</code> should be used instead, see *Python Initialization Configuration*.

This function should be called before $Py_Initialize()$ is called for the first time, if it is called at all. It tells the interpreter the value of the argv[0] argument to the main() function of the program (converted to wide characters). This is used by $Py_GetPath()$ and some other functions below to find the Python run-time libraries relative to the interpreter executable. The default value is 'python'. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_t * string.

Obsolète depuis la version 3.11.

wchar_t *Py_GetProgramName()

Part of the Stable ABI. Return the program name set with *Py_SetProgramName()*, or the default. The returned string points into static storage; the caller should not modify its value.

This function should not be called before Py Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

$wchar_t *Py_GetPrefix()$

Part of the Stable ABI. Return the prefix for installed platform-independent files. This is derived through a number of complicated rules from the program name set with Py_SetProgramName() and some environment variables; for example, if the program name is '/usr/local/bin/python', the prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the prefix variable in the top-level Makefile and the --prefix argument to the configure script at build time. The value is available to Python code as sys.prefix. It is only useful on Unix. See also the next function.

This function should not be called before Py_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

wchar_t *Py_GetExecPrefix()

Part of the Stable ABI. Return the exec-prefix for installed platform-dependent files. This is derived through a number of complicated rules from the program name set with Py_SetProgramName() and some environment variables; for example, if the program name is '/usr/local/bin/python', the exec-prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the exec_prefix variable in the top-level Makefile and the --exec-prefix argument to the

configure script at build time. The value is available to Python code as sys.exec_prefix. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the /usr/local/plat subtree while platform independent may be installed in /usr/local.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share /usr/local between platforms while having /usr/local/plat be a different filesystem for each platform.

This function should not be called before Py_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

wchar_t *Py_GetProgramFullPath()

Part of the Stable ABI. Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by <code>Py_SetProgramName()</code> above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as <code>sys.executable</code>.

This function should not be called before Py_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

wchar_t *Py_GetPath()

Part of the Stable ABI. Return the default module search path; this is computed from the program name (set by $Py_SetProgramName()$ above) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is ':' on Unix and macOS, ';' on Windows. The returned string points into static storage; the caller should not modify its value. The list sys.path is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

This function should not be called before Py_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

void Py SetPath (const wchar t*)

Part of the Stable ABI since version 3.7. This API is kept for backward compatibility: setting PyConfig. module_search_paths and PyConfig.module_search_paths_set should be used instead, see Python Initialization Configuration.

Set the default module search path. If this function is called before <code>Py_Initialize()</code>, then <code>Py_GetPath()</code> won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is ':' on Unix and macOS, ';' on Windows.

This also causes sys.executable to be set to the program full path (see $Py_GetProgramFullPath()$) and for sys.prefix and sys.exec_prefix to be empty. It is up to the caller to modify these if required after calling $Py_Initialize()$.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

The path argument is copied internally, so the caller may free it after the call completes.

Modifié dans la version 3.8: The program full path is now used for sys.executable, instead of the program name.

Obsolète depuis la version 3.11.

const char *Py_GetVersion()

Part of the Stable ABI. Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.version.

See also the *Py_Version* constant.

const char *Py_GetPlatform()

Part of the Stable ABI. Return the platform identifier for the current platform. On Unix, this is formed from the "official" name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On macOS, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.platform.

const char *Py_GetCopyright()

Part of the Stable ABI. Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.copyright.

const char *Py_GetCompiler()

Part of the Stable ABI. Return an indication of the compiler used to build the current Python version, in square brackets, for example :

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

const char *Py_GetBuildInfo()

Part of the Stable ABI. Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

void PySys_SetArgvEx (int argc, wchar_t **argv, int updatepath)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.argv, PyConfig. parse_argv and PyConfig.safe_path should be used instead, see Python Initialization Configuration.

Set sys.argv based on argc and argv. These parameters are similar to those passed to the program's main () function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in argv can be an empty string. If this function fails to initialize sys.argv, a fatal condition is signalled using $Py_FatalError()$.

If *updatepath* is zero, this is all the function does. If *updatepath* is non-zero, the function also modifies sys.path according to the following algorithm:

- If the name of an existing script is passed in argv[0], the absolute path of the directory where the script is located is prepended to sys.path.
- Otherwise (that is, if *argc* is 0 or argv [0] doesn't point to an existing file name), an empty string is prepended to sys.path, which is the same as prepending the current working directory (".").

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

 $See \ also \ \textit{PyConfig.argv} \ and \ \textit{PyConfig.argv} \ members \ of \ the \ \textit{Python Initialization Configuration}.$

Note: It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as *updatepath*, and update sys.path themselves if desired. See CVE-2008-5983.

On versions before 3.1.3, you can achieve the same effect by manually popping the first sys.path element after having called $PySys_SetArgv()$, for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

Nouveau dans la version 3.1.3.

Obsolète depuis la version 3.11.

void PySys_SetArgv (int argc, wchar_t **argv)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.argv and PyConfig. parse_argv should be used instead, see Python Initialization Configuration.

This function works like $PySys_SetArgvEx()$ with *updatepath* set to 1 unless the **python** interpreter was started with the -I.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

See also PyConfig.orig_argv and PyConfig.argv members of the Python Initialization Configuration.

Modifié dans la version 3.4 : The *updatepath* value depends on −I.

Obsolète depuis la version 3.11.

void Py_SetPythonHome (const wchar_t *home)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig. home should be used instead, see Python Initialization Configuration.

Set the default "home" directory, that is, the location of the standard Python libraries. See PYTHONHOME for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

Obsolète depuis la version 3.11.

wchar_t *Py_GetPythonHome()

Part of the Stable ABI. Return the default "home", that is, the value set by a previous call to Py_SetPythonHome(), or the value of the PYTHONHOME environment variable if it is set.

This function should not be called before Py_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py_Initialize().

9.5 Thread State and the Global Interpreter Lock

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see sys.setswitchinterval()). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called <code>PyThreadState</code>. There's also one global variable pointing to the current <code>PyThreadState</code>: it can be retrieved using <code>PyThreadState_Get()</code>.

9.5.1 Releasing the GIL from extension code

Most extension code manipulating the GIL has the following simple structure :

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The Py_BEGIN_ALLOW_THREADS macro opens a new block and declares a hidden local variable; the Py_END_ALLOW_THREADS macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

Note: Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard zlib and hashlib modules release the GIL when compressing or hashing data.

9.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the threading module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The $PyGILState_Ensure()$ and $PyGILState_Release()$ functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the PyGILState_* functions assume there is only one global interpreter (created automatically by Py_Initialize()). Python supports the creation of additional interpreters (using Py_NewInterpreter()), but mixing multiple interpreters and the PyGILState_* API is unsupported.

9.5.3 Cautions about fork()

Another important thing to note about threads is their behaviour in the face of the $C \, fork \, ()$ call. On most systems with fork (), after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the "current" thread remains means any locks held by other threads will never be released. Python solves this for os.fork() by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as pthread_atfork() would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling fork() directly rather than through os.fork() (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork. Pyos_AfterFork_Child() tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which os.fork() does. This means finalizing all other <code>PyThreadState</code> objects belonging to the current interpreter and all other <code>PyInterpreterState</code> objects. Due to this and the special nature of the "main" interpreter, fork() should only be called in that interpreter's "main" thread, where the CPython global runtime was originally initialized. The only exception is if <code>exec()</code> will be called immediately after.

9.5.4 High-level API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

type PyInterpreterState

Part of the Limited API (as an opaque struct). This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

type PyThreadState

Part of the Limited API (as an opaque struct). This data structure represents the state of a single thread. The only public data member is:

PyInterpreterState *interp

This thread's interpreter state.

void PyEval_InitThreads()

Part of the Stable ABI. Deprecated function which does nothing.

In Python 3.6 and older, this function created the GIL if it didn't exist.

Modifié dans la version 3.9: The function now does nothing.

Modifié dans la version 3.7 : This function is now called by <code>Py_Initialize()</code>, so you don't have to call it yourself anymore.

Modifié dans la version 3.2 : This function cannot be called before Py_Initialize() anymore.

Obsolète depuis la version 3.9.

int PyEval_ThreadsInitialized()

Part of the Stable ABI. Returns a non-zero value if <code>PyEval_InitThreads()</code> has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

Modifié dans la version 3.7 : The GIL is now initialized by Py Initialize ().

Obsolète depuis la version 3.9.

PyThreadState *PyEval_SaveThread()

Part of the Stable ABI. Release the global interpreter lock (if it has been created) and reset the thread state to NULL, returning the previous thread state (which is not NULL). If the lock has been created, the current thread must have acquired it.

void PyEval_RestoreThread (PyThreadState *tstate)

Part of the Stable ABI. Acquire the global interpreter lock (if it has been created) and set the thread state to tstate, which must not be NULL. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

Note: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

PyThreadState *PyThreadState_Get ()

Part of the Stable ABI. Return the current thread state. The global interpreter lock must be held. When the current thread state is NULL, this issues a fatal error (so that the caller needn't check for NULL).

PyThreadState *PyThreadState_Swap (PyThreadState *tstate)

Part of the Stable ABI. Swap the current thread state with the thread state given by the argument *tstate*, which may be NULL. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

PyGILState_STATE PyGILState_Ensure()

Part of the Stable ABI. Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the global interpreter lock. This may be called as many times as desired by a thread as long as each call is matched with a call to <code>PyGILState_Release()</code>. In general, other thread-related APIs may be used between <code>PyGILState_Ensure()</code> and <code>PyGILState_Release()</code> calls as long as the thread state is restored to its previous state before the Release(). For example, normal usage of the <code>Py_BEGIN_ALLOW_THREADS</code> and <code>Py_END_ALLOW_THREADS</code> macros is acceptable.

The return value is an opaque "handle" to the thread state when <code>PyGILState_Ensure()</code> was called, and must be passed to <code>PyGILState_Release()</code> to ensure Python is left in the same state. Even though recursive calls are allowed, these handles <code>cannot</code> be shared - each unique call to <code>PyGILState_Ensure()</code> must save the handle for its call to <code>PyGILState_Release()</code>.

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

Note: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

void PyGILState_Release (PyGILState_STATE)

Part of the Stable ABI. Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding <code>PyGILState_Ensure()</code> call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to $PyGILState_Ensure()$ must be matched by a call to $PyGILState_Release()$ on the same thread.

PyThreadState *PyGILState_GetThisThreadState()

Part of the Stable ABI. Get the current thread state for this thread. May return NULL if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

int PyGILState_Check()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

Nouveau dans la version 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

Py_BEGIN_ALLOW_THREADS

Part of the Stable ABI. This macro expands to { PyThreadState *_save; _save = PyEval_SaveThread();. Note that it contains an opening brace; it must be matched with a following Py_END_ALLOW_THREADS macro. See above for further discussion of this macro.

Py_END_ALLOW_THREADS

Part of the Stable ABI. This macro expands to PyEval_RestoreThread(_save); }. Note that it contains a closing brace; it must be matched with an earlier $Py_BEGIN_ALLOW_THREADS$ macro. See above for further discussion of this macro.

Py_BLOCK_THREADS

Part of the Stable ABI. This macro expands to PyEval_RestoreThread(_save); : it is equivalent to Py_END_ALLOW_THREADS without the closing brace.

Py_UNBLOCK_THREADS

Part of the Stable ABI. This macro expands to _save = PyEval_SaveThread(); : it is equivalent to Py_BEGIN_ALLOW_THREADS without the opening brace and variable declaration.

9.5.5 Low-level API

All of the following functions must be called after Py_Initialize().

Modifié dans la version 3.7 : Py_Initialize () now initializes the GIL.

PyInterpreterState *PyInterpreterState_New()

Part of the Stable ABI. Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Raises an auditing event cpython.PyInterpreterState_New with no arguments.

void PyInterpreterState_Clear (PyInterpreterState *interp)

Part of the Stable ABI. Reset all information in an interpreter state object. The global interpreter lock must be held. Raises an auditing event cpython.PyInterpreterState_Clear with no arguments.

void PyInterpreterState_Delete (PyInterpreterState *interp)

Part of the Stable ABI. Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to PyInterpreterState Clear().

PyThreadState *PyThreadState_New (PyInterpreterState *interp)

Part of the Stable ABI. Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

void PyThreadState_Clear (PyThreadState *tstate)

Part of the Stable ABI. Reset all information in a thread state object. The global interpreter lock must be held.

Modifié dans la version 3.9: This function now calls the PyThreadState.on_delete callback. Previously, that happened in $PyThreadState_Delete()$.

void PyThreadState_Delete (PyThreadState *tstate)

Part of the Stable ABI. Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to <code>PyThreadState_Clear()</code>.

void PyThreadState_DeleteCurrent (void)

Destroy the current thread state and release the global interpreter lock. Like <code>PyThreadState_Delete()</code>, the global interpreter lock need not be held. The thread state must have been reset with a previous call to <code>PyThreadState_Clear()</code>.

PyFrameObject *PyThreadState_GetFrame (PyThreadState *tstate)

Part of the Stable ABI since version 3.10. Get the current frame of the Python thread state tstate.

Return a strong reference. Return NULL if no frame is currently executing.

See also PyEval_GetFrame().

tstate must not be NULL.

Nouveau dans la version 3.9.

uint64_t PyThreadState_GetID (PyThreadState *tstate)

Part of the Stable ABI since version 3.10. Get the unique thread state identifier of the Python thread state tstate. tstate must not be NULL.

Nouveau dans la version 3.9.

PyInterpreterState *PyThreadState_GetInterpreter (PyThreadState *tstate)

Part of the Stable ABI since version 3.10. Get the interpreter of the Python thread state tstate.

tstate must not be NULL.

Nouveau dans la version 3.9.

void PyThreadState_EnterTracing (PyThreadState *tstate)

Suspend tracing and profiling in the Python thread state tstate.

Resume them using the PyThreadState LeaveTracing() function.

Nouveau dans la version 3.11.

void PyThreadState_LeaveTracing (PyThreadState *tstate)

Resume tracing and profiling in the Python thread state *tstate* suspended by the *PyThreadState_EnterTracing()* function.

See also PyEval_SetTrace() and PyEval_SetProfile() functions.

Nouveau dans la version 3.11.

PyInterpreterState *PyInterpreterState_Get (void)

Part of the Stable ABI since version 3.9. Get the current interpreter.

Issue a fatal error if there no current Python thread state or no current interpreter. It cannot return NULL.

The caller must hold the GIL.

Nouveau dans la version 3.9.

int64_t PyInterpreterState_GetID (PyInterpreterState *interp)

Part of the Stable ABI since version 3.7. Return the interpreter's unique ID. If there was any error in doing so then -1 is returned and an error is set.

The caller must hold the GIL.

Nouveau dans la version 3.7.

PyObject *PyInterpreterState_GetDict (PyInterpreterState *interp)

Part of the Stable ABI since version 3.8. Return a dictionary in which interpreter-specific data may be stored. If this function returns NULL then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for $PyModule_GetState()$, which extensions should use to store interpreter-specific state information.

Nouveau dans la version 3.8.

typedef PyObject *(*_PyFrameEvalFunction)(PyThreadState *tstate, _PyInterpreterFrame *frame, int throwflag)

Type of a frame evaluation function.

The *throwflag* parameter is used by the throw () method of generators: if non-zero, handle the current exception. Modifié dans la version 3.9: The function now takes a *tstate* parameter.

Modifié dans la version 3.11 : The *frame* parameter changed from PyFrameObject* to _PyInterpreterFrame*.

_PyFrameEvalFunction _PyInterpreterState _GetEvalFrameFunc (PyInterpreterState *interp)

Get the frame evaluation function.

See the PEP 523 "Adding a frame evaluation API to CPython".

Nouveau dans la version 3.9.

void _PyInterpreterState_SetEvalFrameFunc (PyInterpreterState *interp, _PyFrameEvalFunction eval frame)

Set the frame evaluation function.

See the PEP 523 "Adding a frame evaluation API to CPython".

Nouveau dans la version 3.9.

PyObject *PyThreadState_GetDict()

Return value: Borrowed reference. Part of the Stable ABI. Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

int PyThreadState_SetAsyncExc (unsigned long id, PyObject *exc)

Part of the Stable ABI. Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

Modifié dans la version 3.7: The type of the *id* parameter changed from long to unsigned long.

void PyEval_AcquireThread (PyThreadState *tstate)

Part of the Stable ABI. Acquire the global interpreter lock and set the current thread state to *tstate*, which must not be NULL. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

Note: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Modifié dans la version 3.8 : Updated to be consistent with <code>PyEval_RestoreThread()</code>, <code>Py_END_ALLOW_THREADS()</code>, and <code>PyGILState_Ensure()</code>, and terminate the current thread if called while the interpreter is finalizing.

PyEval_RestoreThread() is a higher-level function which is always available (even when threads have not been initialized).

void PyEval_ReleaseThread (PyThreadState *tstate)

Part of the Stable ABI. Reset the current thread state to NULL and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be NULL, is only used to check that it represents the current thread state --- if it isn't, a fatal error is reported.

PyEval_SaveThread() is a higher-level function which is always available (even when threads have not been initialized).

void PyEval_AcquireLock()

Part of the Stable ABI. Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

Obsolète depuis la version 3.2: This function does not update the current thread state. Please use $PyEval_RestoreThread()$ or $PyEval_AcquireThread()$ instead.

Note: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Modifié dans la version 3.8 : Updated to be consistent with $PyEval_RestoreThread()$, $Py_END_ALLOW_THREADS()$, and $PyGILState_Ensure()$, and terminate the current thread if called while the interpreter is finalizing.

void PyEval_ReleaseLock()

Part of the Stable ABI. Release the global interpreter lock. The lock must have been created earlier.

Obsolète depuis la version 3.2: This function does not update the current thread state. Please use $PyEval_SaveThread()$ or $PyEval_ReleaseThread()$ instead.

9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The "main" interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The <code>PyInterpreterState_Main()</code> function returns a pointer to its state.

You can switch between sub-interpreters using the $PyThreadState_Swap()$ function. You can create and destroy them using the following functions:

type PyInterpreterConfig

Structure containing most parameters to configure a sub-interpreter. Its values are used only in *Py_NewInterpreterFromConfig()* and never modified by the runtime.

Nouveau dans la version 3.12.

Structure fields:

int use_main_obmalloc

If this is 0 then the sub-interpreter will use its own "object" allocator state. Otherwise it will use (share) the main interpreter's.

If this is 0 then <code>check_multi_interp_extensions</code> must be 1 (non-zero). If this is 1 then <code>gil</code> must not be <code>PyInterpreterConfig_OWN_GIL</code>.

int allow_fork

If this is 0 then the runtime will not support forking the process in any thread where the sub-interpreter is currently active. Otherwise fork is unrestricted.

Note that the subprocess module still works when fork is disallowed.

int allow_exec

If this is 0 then the runtime will not support replacing the current process via exec (e.g. os.execv()) in any thread where the sub-interpreter is currently active. Otherwise exec is unrestricted.

Note that the subprocess module still works when exec is disallowed.

int allow_threads

If this is 0 then the sub-interpreter's threading module won't create threads. Otherwise threads are allowed.

int allow_daemon_threads

If this is 0 then the sub-interpreter's threading module won't create daemon threads. Otherwise daemon threads are allowed (as long as allow threads is non-zero).

int check_multi_interp_extensions

If this is 0 then all extension modules may be imported, including legacy (single-phase init) modules, in any thread where the sub-interpreter is currently active. Otherwise only multi-phase init extension modules (see PEP 489) may be imported. (Also see Py_mod_multiple_interpreters.)

This must be 1 (non-zero) if use main obmalloc is 0.

int gil

This determines the operation of the GIL for the sub-interpreter. It may be one of the following:

PyInterpreterConfig_DEFAULT_GIL

Use the default selection (PyInterpreterConfig_SHARED_GIL).

PyInterpreterConfig_SHARED_GIL

Use (share) the main interpreter's GIL.

PyInterpreterConfig_OWN_GIL

Use the sub-interpreter's own GIL.

```
If this is PyInterpreterConfig_OWN_GIL then PyInterpreterConfig.use_main_obmalloc must be 0.
```

PyStatus Py_NewInterpreterFromConfig (PyThreadState **tstate_p, const PyInterpreterConfig *config)

Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules builtins, __main__ and sys. The table of loaded modules (sys.modules) and the module search path (sys.path) are also separate. The new environment has no sys.argv variable. It has new standard I/O stream file objects sys.stdin, sys.stdout and sys.stderr (however these refer to the same underlying file descriptors).

The given *config* controls the options with which the interpreter is initialized.

Upon success, *tstate_p* will be set to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, *tstate_p* is set to NULL; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state.

Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns. Likewise a current thread state must be set on entry. On success, the returned thread state will be set as current. If the sub-interpreter is created with its own GIL then the GIL of the calling interpreter will be released. When the function returns, the new interpreter's GIL will be held by the current thread and the previously interpreter's GIL will remain released here.

Nouveau dans la version 3.12.

Sub-interpreters are most effective when isolated from each other, with certain functionality restricted:

```
PyInterpreterConfig config = {
    .use_main_obmalloc = 0,
    .allow_fork = 0,
    .allow_exec = 0,
    .allow_threads = 1,
    .allow_daemon_threads = 0,
    .check_multi_interp_extensions = 1,
    .gil = PyInterpreterConfig_OWN_GIL,
};
PyThreadState *tstate = Py_NewInterpreterFromConfig(&config);
```

Note that the config is used only briefly and does not get modified. During initialization the config's values are converted into various *PyInterpreterState* values. A read-only copy of the config may be stored internally on the *PyInterpreterState*.

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. <code>PyModule_FromDefAndSpec()</code>, a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g. <code>PyModule_Create()</code>, the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's <code>init</code> function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see <code>Bugs and caveats</code> below).

Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling $Py_FinalizeEx()$ and $Py_Initialize()$; in that case, the extension's initmodule function is called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

PyThreadState *Py_NewInterpreter (void)

Part of the Stable ABI. Create a new sub-interpreter. This is essentially just a wrapper around

Py_NewInterpreterFromConfig() with a config that preserves the existing behavior. The result is an unisolated sub-interpreter that shares the main interpreter's GIL, allows fork/exec, allows daemon threads, and allows single-phase init modules.

void Py_EndInterpreter (PyThreadState *tstate)

Part of the Stable ABI. Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is NULL. All thread states associated with this interpreter are destroyed. The global interpreter lock used by the target interpreter must be held before calling this function. No GIL is held when it returns.

Py_FinalizeEx() will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

9.6.1 A Per-Interpreter GIL

Using Py_NewInterpreterFromConfig() you can create a sub-interpreter that is completely isolated from other interpreters, including having its own GIL. The most important benefit of this isolation is that such an interpreter can execute Python code without being blocked by other interpreters or blocking any others. Thus a single Python process can truly take advantage of multiple CPU cores when running Python code. The isolation also encourages a different approach to concurrency than that of just using threads. (See PEP 554.)

Using an isolated interpreter requires vigilance in preserving that isolation. That especially means not sharing any objects or mutable state without guarantees about thread-safety. Even objects that are otherwise immutable (e.g. None, (1, 5)) can't normally be shared because of the refcount. One simple but less-efficient approach around this is to use a global lock around all use of some state (or object). Alternately, effectively immutable objects (like integers or strings) can be made safe in spite of their refcounts by making them "immortal". In fact, this has been done for the builtin singletons, small integers, and a number of other builtin objects.

If you preserve isolation then you will have access to proper multi-core computing without the complications that come with free-threading. Failure to preserve isolation will expose you to the full consequences of free-threading, including races and hard-to-debug crashes.

Aside from that, one of the main challenges of using multiple isolated interpreters is how to communicate between them safely (not break isolation) and efficiently. The runtime and stdlib do not provide any standard approach to this yet. A future stdlib module would help mitigate the effort of preserving isolation and expose effective tools for communicating (and sharing) data between interpreters.

Nouveau dans la version 3.12.

9.6.2 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect --- for example, using low-level file operations like os.close() they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with PyGILState_* APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching PyGILState_Ensure() and PyGILState_Release() calls. Furthermore, extensions (such as ctypes) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

9.7 Asynchronous Notifications

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int Py_AddPendingCall (int (*func)(void*), void *arg)

Part of the Stable ABI. Schedule a function to be called from the main interpreter thread. On success, 0 is returned and *func* is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

— on a *bytecode* boundary;

— with the main thread holding the *global interpreter lock* (func can therefore use the full C API).

func must return 0 on success, or -1 on failure with an exception set. func won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

To call this function in a subinterpreter, the caller must hold the GIL. Otherwise, the function *func* can be scheduled to be called from the wrong interpreter.

Avertissement: This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the *PyGILState API*.

Modifié dans la version 3.9: If this function is called in a subinterpreter, the function *func* is now scheduled to be called from the subinterpreter, rather than being called from the main interpreter. Each subinterpreter now has its own list of scheduled calls.

Nouveau dans la version 3.1.

9.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

typedef int (*Py_tracefunc)(PyObject *obj, PyFrameObject *frame, int what, PyObject *arg)

The type of the trace function registered using <code>PyEval_SetProfile()</code> and <code>PyEval_SetTrace()</code>. The first parameter is the object passed to the registration function as <code>obj</code>, <code>frame</code> is the frame object to which the event pertains, <code>what</code> is one of the constants <code>PyTrace_CALL</code>, <code>PyTrace_EXCEPTION</code>, <code>PyTrace_LINE</code>, <code>PyTrace_RETURN</code>, <code>PyTrace_C_CALL</code>, <code>PyTrace_C_EXCEPTION</code>, <code>PyTrace_C_RETURN</code>, or <code>PyTrace_OPCODE</code>, and <code>arg</code> depends on the value of <code>what</code>:

Value of what	Meaning of arg
PyTrace_CALL	Always Py_None.
PyTrace_EXCEPTION	Exception information as returned by sys.exc_info().
PyTrace_LINE	Always Py_None.
PyTrace_RETURN	Value being returned to the caller, or NULL if caused by an exception.
PyTrace_C_CALL	Function object being called.
PyTrace_C_EXCEPTION	Function object being called.
PyTrace_C_RETURN	Function object being called.
PyTrace_OPCODE	Always Py_None.

int PyTrace_CALL

The value of the *what* parameter to a *Py_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

int PyTrace EXCEPTION

The value of the *what* parameter to a *Py_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

int PyTrace_LINE

The value passed as the *what* parameter to a $Py_tracefunc$ function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting f_trace_lines to θ on that frame.

int PyTrace_RETURN

The value for the *what* parameter to *Py_tracefunc* functions when a call is about to return.

int PvTrace C CALL

The value for the *what* parameter to Py_tracefunc functions when a C function is about to be called.

int PyTrace_C_EXCEPTION

The value for the *what* parameter to *Py_tracefunc* functions when a C function has raised an exception.

int PyTrace_C_RETURN

The value for the *what* parameter to Py_tracefunc functions when a C function has returned.

int PyTrace OPCODE

The value for the *what* parameter to $Py_tracefunc$ functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting $f_trace_opcodes$ to I on the frame.

void PyEval_SetProfile (Py_tracefunc func, PyObject *obj)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or NULL. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except *PyTrace_LINE PyTrace_OPCODE* and *PyTrace_EXCEPTION*.

See also the sys.setprofile() function.

The caller must hold the GIL.

void PyEval_SetProfileAllThreads (Py_tracefunc func, PyObject *obj)

Like PyEval_SetProfile() but sets the profile function in all running threads belonging to the current interpreter instead of the setting it only on the current thread.

The caller must hold the GIL.

As PyEval_SetProfile(), this function ignores any exceptions raised while setting the profile functions in all threads.

Nouveau dans la version 3.12.

```
void PyEval_SetTrace (Py_tracefunc func, PyObject *obj)
```

Set the tracing function to *func*. This is similar to *PyEval_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval_SetTrace()* will not receive *PyTrace_C_CALL*, *PyTrace_C_EXCEPTION* or *PyTrace_C_RETURN* as a value for the *what* parameter.

See also the sys.settrace() function.

The caller must hold the GIL.

```
void PyEval_SetTraceAllThreads (Py_tracefunc func, PyObject *obj)
```

Like PyEval_SetTrace() but sets the tracing function in all running threads belonging to the current interpreter instead of the setting it only on the current thread.

The caller must hold the GIL.

As PyEval_SetTrace(), this function ignores any exceptions raised while setting the trace functions in all threads.

Nouveau dans la version 3.12.

9.9 Support avancé du débogueur

These functions are only intended to be used by advanced debugging tools.

```
PyInterpreterState *PyInterpreterState_Head()
```

Return the interpreter state object at the head of the list of all such objects.

```
PyInterpreterState *PyInterpreterState_Main()
```

Return the main interpreter state object.

```
PyInterpreterState *PyInterpreterState_Next (PyInterpreterState *interp)
```

Return the next interpreter state object after *interp* from the list of all such objects.

```
PyThreadState *PyInterpreterState_ThreadHead (PyInterpreterState *interp)
```

Return the pointer to the first PyThreadState object in the list of threads associated with the interpreter interp.

```
PyThreadState *PyThreadState_Next (PyThreadState *tstate)
```

Return the next thread state object after *tstate* from the list of all such objects belonging to the same *PyInterpreterState* object.

9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (threading.local). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a void* value per thread.

The GIL does not need to be held when calling these functions; they supply their own locking.

Note that Python.h does not include the declaration of the TLS APIs, you need to include pythread.h to use thread-local storage.

Note: None of these API functions handle memory management on behalf of the void* values. You need to allocate and deallocate them yourself. If the void* values happen to be *PyObject**, these functions don't do refcount operations on them either.

9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type Py_tss_t instead of int to represent thread keys.

Nouveau dans la version 3.7.

Voir aussi:

"A New C-API for Thread-Local Storage in CPython" (PEP 539)

type Py_tss_t

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure

When Py_LIMITED_API is not defined, static allocation of this type by Py_tss_NEEDS_INIT is allowed.

Py_tss_NEEDS_INIT

This macro expands to the initializer for Py_tss_t variables. Note that this macro won't be defined with $Py_LIMITED_API$.

Dynamic Allocation

Dynamic allocation of the Py_tss_t , required in extension modules built with $Py_LIMITED_API$, where static allocation of this type is not possible due to its implementation being opaque at build time.

Py_tss_t *PyThread_tss_alloc()

Part of the Stable ABI since version 3.7. Return a value which is the same state as a value initialized with $Py_tss_NEEDS_INIT$, or NULL in the case of dynamic allocation failure.

void PyThread_tss_free (Py_tss_t *key)

Part of the Stable ABI since version 3.7. Free the given key allocated by PyThread_tss_alloc(), after first calling PyThread_tss_delete() to ensure any associated thread locals have been unassigned. This is a no-op if the key argument is NULL.

Note: A freed key becomes a dangling pointer. You should reset the key to NULL.

Méthodes

The parameter *key* of these functions must not be NULL. Moreover, the behaviors of *PyThread_tss_set()* and *PyThread_tss_get()* are undefined if the given *Py_tss_t* has not been initialized by *PyThread_tss_create()*.

int PyThread_tss_is_created (Py_tss_t *key)

Part of the Stable ABI since version 3.7. Return a non-zero value if the given Py_tss_t has been initialized by $PyThread_tss_create()$.

```
int PyThread_tss_create (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the key argument is not initialized by Py_tss_NEEDS_INIT. This function can be called repeatedly on the same key -- calling it on an already initialized key is a no-op and immediately returns success.

```
void PyThread_tss_delete (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by <code>PyThread_tss_create()</code>. This function can be called repeatedly on the same key -- calling it on an already destroyed key is a no-op.

```
int PyThread_tss_set (Py_tss_t *key, void *value)
```

Part of the Stable ABI since version 3.7. Return a zero value to indicate successfully associating a void* value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a void* value.

```
void *PyThread_tss_get (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Return the void* value associated with a TSS key in the current thread. This returns NULL if no value is associated with the key in the current thread.

9.10.2 Thread Local Storage (TLS) API

Obsolète depuis la version 3.7 : This API is superseded by *Thread Specific Storage (TSS) API*.

Note: This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to int. On such platforms, <code>PyThread_create_key()</code> will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

Due to the compatibility problem noted above, this version of the API should not be used in new code.

```
int PyThread_create_key()
          Part of the Stable ABI.
void PyThread_delete_key(int key)
          Part of the Stable ABI.
int PyThread_set_key_value(int key, void *value)
          Part of the Stable ABI.
void *PyThread_get_key_value(int key)
          Part of the Stable ABI.
void PyThread_delete_key_value(int key)
          Part of the Stable ABI.
void PyThread_ReInitTLS()
          Part of the Stable ABI.
```

CHAPITRE 10

Python Initialization Configuration

Nouveau dans la version 3.8.

Python can be initialized with $Py_InitializeFromConfig$ () and the PyConfig structure. It can be preinitialized with $Py_PreInitialize$ () and the PyPreConfig structure.

There are two kinds of configuration:

- The *Python Configuration* can be used to build a customized Python which behaves as the regular Python. For example, environment variables and command line arguments are used to configure Python.
- The *Isolated Configuration* can be used to embed Python into an application. It isolates Python from the system. For example, environment variables are ignored, the LC_CTYPE locale is left unchanged and no signal handler is registered.

The Py_RunMain () function can be used to write a customized Python program.

See also Initialization, Finalization, and Threads.

Voir aussi:

PEP 587 "Python Initialization Configuration".

10.1 Example

Example of customized Python always running in isolated mode:

(suite sur la page suivante)

(suite de la page précédente)

```
status = PyConfig_SetBytesArgv(&config, argc, argv);
if (PyStatus_Exception(status)) {
    goto exception;
}

status = Py_InitializeFromConfig(&config);
if (PyStatus_Exception(status)) {
    goto exception;
}
PyConfig_Clear(&config);

return Py_RunMain();

exception:
    PyConfig_Clear(&config);
    if (PyStatus_IsExit(status)) {
        return status.exitcode;
}
/* Display the error message and exit the process with non-zero exit code */
Py_ExitStatusException(status);
}
```

10.2 PyWideStringList

```
type PyWideStringList
      List of wchar t* strings.
      If length is non-zero, items must be non-NULL and all strings must be non-NULL.
      Methods:
      PyStatus PyWideStringList_Append (PyWideStringList *list, const wchar_t *item)
           Append item to list.
           Python must be preinitialized to call this function.
      PyStatus PyWideStringList_Insert (PyWideStringList *list, Py_ssize_t index, const wchar_t *item)
           Insert item into list at index.
           If index is greater than or equal to list length, append item to list.
           index must be greater than or equal to 0.
           Python must be preinitialized to call this function.
      Structure fields:
      Py_ssize_t length
           List length.
      wchar_t **items
           List items.
```

10.3 PyStatus

```
type PyStatus
     Structure to store an initialization function status: success, error or exit.
     For an error, it can store the C function name which created the error.
     Structure fields:
     int exitcode
          Exit code. Argument passed to exit ().
     const char *err_msg
          Error message.
     const char *func
          Name of the function which created an error, can be NULL.
     Functions to create a status:
     PyStatus PyStatus_Ok (void)
          Success.
     PyStatus_Error (const char *err_msg)
          Initialization error with a message.
          err_msg must not be NULL.
     PyStatus PyStatus_NoMemory (void)
          Memory allocation failure (out of memory).
     PyStatus_Exit (int exitcode)
          Exit Python with the specified exit code.
     Functions to handle a status:
     int PyStatus_Exception (PyStatus status)
          Is the status an error or an exit? If true, the exception must be handled; by calling
          Py_ExitStatusException() for example.
     int PyStatus_IsError (PyStatus status)
          Is the result an error?
     int PyStatus_IsExit (PyStatus status)
          Is the result an exit?
     void Py_ExitStatusException (PyStatus status)
          Call exit (exitcode) if status is an exit. Print the error message and exit with a non-zero exit code if
          status is an error. Must only be called if PyStatus_Exception (status) is non-zero.
```

Note: Internally, Python uses macros which set PyStatus.func, whereas functions to create a status set func to NULL.

Exemple:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}
```

(suite sur la page suivante)

10.3. PyStatus 207

(suite de la page précédente)

```
int main(int argc, char **argv)
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
   PyMem_Free(ptr);
    return 0;
```

10.4 PyPreConfig

```
type PyPreConfig
     Structure used to preinitialize Python.
     Function to initialize a preconfiguration:
     void PyPreConfig_InitPythonConfig (PyPreConfig *preconfig)
          Initialize the preconfiguration with Python Configuration.
     void PyPreConfig_InitIsolatedConfig (PyPreConfig *preconfig)
          Initialize the preconfiguration with Isolated Configuration.
     Structure fields:
     int allocator
          Name of the Python memory allocators:
          — PYMEM ALLOCATOR NOT SET (0): don't change memory allocators (use defaults).

    — PYMEM_ALLOCATOR_DEFAULT (1): default memory allocators.

          — PYMEM_ALLOCATOR_DEBUG (2): default memory allocators with debug hooks.
          — PYMEM_ALLOCATOR_MALLOC(3): use malloc() of the C library.
          — PYMEM_ALLOCATOR_MALLOC_DEBUG (4): force usage of malloc() with debug hooks.
          — PYMEM ALLOCATOR PYMALLOC (5): Python pymalloc memory allocator.

    — PYMEM_ALLOCATOR_PYMALLOC_DEBUG (6): Python pymalloc memory allocator with debug hooks.

          PYMEM_ALLOCATOR_PYMALLOC and PYMEM_ALLOCATOR_PYMALLOC_DEBUG are not supported if
          Python is configured using --without-pymalloc.
          See Memory Management.
          Default: PYMEM_ALLOCATOR_NOT_SET.
     int configure_locale
          Set the LC_CTYPE locale to the user preferred locale.
          If equals to 0, set coerce_c_locale and coerce_c_locale_warn members to 0.
          See the locale encoding.
          Default: 1 in Python config, 0 in isolated config.
     int coerce_c_locale
          If equals to 2, coerce the C locale.
          If equals to 1, read the LC_CTYPE locale to decide if it should be coerced.
          See the locale encoding.
          Default: -1 in Python config, 0 in isolated config.
     int coerce_c_locale_warn
          If non-zero, emit a warning if the C locale is coerced.
```

Default: -1 in Python config, 0 in isolated config.

int dev mode

Python Development Mode: see PyConfig.dev_mode.

Default: -1 in Python mode, 0 in isolated mode.

int isolated

Isolated mode: see *PyConfig.isolated*. Default: 0 in Python mode, 1 in isolated mode.

int legacy_windows_fs_encoding

If non-zero:

- Set PyPreConfig.utf8_mode to 0,
- Set PyConfig.filesystem_encoding to "mbcs",
- Set PyConfig.filesystem_errors to "replace".

Initialized the from PYTHONLEGACYWINDOWSFSENCODING environment variable value.

Only available on Windows. #ifdef MS_WINDOWS macro can be used for Windows specific code.

Default: 0.

int parse_argv

If non-zero, $Py_PreInitializeFromArgs()$ and $Py_PreInitializeFromBytesArgs()$ parse their argv argument the same way the regular Python parses command line arguments: see Command Line Arguments.

Default: 1 in Python config, 0 in isolated config.

int use_environment

Use environment variables? See PyConfig.use_environment.

Default: 1 in Python config and 0 in isolated config.

int utf8 mode

If non-zero, enable the Python UTF-8 Mode.

Set to 0 or 1 by the -X utf8 command line option and the PYTHONUTF8 environment variable.

Also set to 1 if the LC CTYPE locale is C or POSIX.

Default: -1 in Python config and 0 in isolated config.

10.5 Preinitialize Python with PyPreConfig

The preinitialization of Python:

- Set the Python memory allocators (PyPreConfig.allocator)
- Configure the LC_CTYPE locale (*locale encoding*)
- Set the Python UTF-8 Mode (PyPreConfig.utf8_mode)

The current preconfiguration (PyPreConfig type) is stored in _PyRuntime.preconfig.

Functions to preinitialize Python:

PyStatus Py PreInitialize (const PyPreConfig *preconfig)

Preinitialize Python from *preconfig* preconfiguration.

preconfig must not be NULL.

PyStatus Py_PreInitializeFromBytesArgs (const PyPreConfig *preconfig, int argc, char *const *argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (bytes strings) if *parse_argv* of *preconfig* is non-zero. *preconfig* must not be NULL.

PyStatus Py_PreInitializeFromArgs (const PyPreConfig *preconfig, int argc, wchar_t *const *argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (wide strings) if *parse_argv* of *preconfig* is non-zero. *preconfig* must not be NULL.

The caller is responsible to handle exceptions (error or exit) using PyStatus_Exception() and Py_ExitStatusException().

For *Python Configuration* (*PyPreConfig_InitPythonConfig()*), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the -X utf8 command line option enables the Python UTF-8 Mode.

PyMem_SetAllocator() can be called after $Py_PreInitialize()$ and before $Py_InitializeFromConfig()$ to install a custom memory allocator. It can be called before $Py_PreInitialize()$ if PyPreConfig.allocator is set to $PyMEM_ALLOCATOR_NOT_SET$.

Python memory allocation functions like $PyMem_RawMalloc()$ must not be used before the Python preinitialization, whereas calling directly malloc() and free() is always safe. $Py_DecodeLocale()$ must not be called before the Python preinitialization.

Example using the preinitialization to enable the Python UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}

/* at this point, Python speaks UTF-8 */

Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

10.6 PyConfig

```
type PyConfig
```

Structure containing most parameters to configure Python.

When done, the PyConfig Clear () function must be used to release the configuration memory.

Structure methods:

```
void PyConfig InitPythonConfig (PyConfig *config)
```

Initialize configuration with the *Python Configuration*.

void PyConfig_InitIsolatedConfig (PyConfig *config)

Initialize configuration with the Isolated Configuration.

PyStatus PyConfig_SetString (PyConfig *config, wchar_t *const *config_str, const wchar_t *str)

Copy the wide character string str into *config_str.

Preinitialize Python if needed.

```
PyStatus PyConfig_SetBytesString (PyConfig *config, wchar_t *config_str, const char *str)
```

Decode str using Py_DecodeLocale() and set the result into *config_str.

Preinitialize Python if needed.

PyStatus **PyConfig_SetArgv** (*PyConfig* *config, int argc, wchar_t *const *argv)

Set command line arguments (argv member of config) from the argv list of wide character strings. Preinitialize Python if needed.

```
PyStatus PyConfig_SetBytesArgv (PyConfig *config, int argc, char *const *argv)
```

Set command line arguments (argv member of config) from the argv list of bytes strings. Decode bytes using $Py_DecodeLocale()$.

Preinitialize Python if needed.

```
PyStatus PyConfig_SetWideStringList (PyConfig *config, PyWideStringList *list, Py_ssize_t length, wchar_t **items)
```

Set the list of wide strings list to length and items.

Preinitialize Python if needed.

```
PyStatus PyConfig_Read (PyConfig *config)
```

Read all Python configuration.

Fields which are already initialized are left unchanged.

Fields for *path configuration* are no longer calculated or modified when calling this function, as of Python 3.11.

The <code>PyConfig_Read()</code> function only parses <code>PyConfig.argv</code> arguments once: <code>PyConfig.parse_argv</code> is set to 2 after arguments are parsed. Since Python arguments are strippped from <code>PyConfig.argv</code>, parsing arguments twice would parse the application options as Python options. <code>Preinitialize Python</code> if needed.

Modifié dans la version 3.10: The <code>PyConfig.argv</code> arguments are now only parsed once, <code>PyConfig.parse_argv</code> is set to 2 after arguments are parsed, and arguments are only parsed if <code>PyConfig.parse_argv</code> equals 1.

Modifié dans la version 3.11: PyConfig_Read() no longer calculates all paths, and so fields listed under Python Path Configuration may no longer be updated until Py_InitializeFromConfig() is called.

void PyConfig_Clear (PyConfig *config)

Release configuration memory.

Most PyConfig methods *preinitialize Python* if needed. In that case, the Python preinitialization configuration (*PyPreConfig*) in based on the *PyConfig*. If configuration fields which are in common with *PyPreConfig* are tuned, they must be set before calling a *PyConfig* method:

- PyConfig.dev_mode
- PyConfig.isolated
- PyConfig.parse_argv
- PyConfig.use_environment

Moreover, if *PyConfig_SetArgv()* or *PyConfig_SetBytesArgv()* is used, this method must be called before other methods, since the preinitialization configuration depends on command line arguments (if *parse_argv* is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using PyStatus_Exception() and Py ExitStatusException().

Structure fields:

PyWideStringList argv

Command line arguments: sys.argv.

Set parse_argv to 1 to parse argv the same way the regular Python parses Python command line arguments and then to strip Python arguments from argv.

If argv is empty, an empty string is added to ensure that sys.argv always exists and is never empty.

Default: NULL.

See also the *orig_argv* member.

10.6. PyConfig 211

int safe path

If equals to zero, Py_RunMain() prepends a potentially unsafe path to sys.path at startup:

- If argv[0] is equal to L"-m" (python -m module), prepend the current working directory.
- If running a script (python script.py), prepend the script's directory. If it's a symbolic link, resolve symbolic links.
- Otherwise (python -c code and python), prepend an empty string, which means the current working directory.

Set to 1 by the -P command line option and the PYTHONSAFEPATH environment variable.

Default: 0 in Python config, 1 in isolated config.

Nouveau dans la version 3.11.

wchar_t *base_exec_prefix

```
sys.base_exec_prefix.
```

Default: NULL.

Part of the Python Path Configuration output.

wchar_t *base_executable

Python base executable: sys._base_executable.

Set by the ___PYVENV_LAUNCHER__ environment variable.

Set from PyConfig.executable if NULL.

Default: NULL.

Part of the *Python Path Configuration* output.

wchar_t *base_prefix

```
sys.base_prefix.
```

Default: NULL.

Part of the Python Path Configuration output.

$int \ buffered_stdio$

If equals to 0 and configure_c_stdio is non-zero, disable buffering on the C streams stdout and stderr.

Set to 0 by the -u command line option and the PYTHONUNBUFFERED environment variable.

stdin is always opened in buffered mode.

Default: 1.

int bytes_warning

If equals to 1, issue a warning when comparing bytes or bytearray with str, or comparing bytes with int

If equal or greater to 2, raise a BytesWarning exception in these cases.

Incremented by the -b command line option.

Default: 0.

int warn_default_encoding

If non-zero, emit a EncodingWarning warning when io. TextIOWrapper uses its default encoding. See io-encoding-warning for details.

Default: 0.

Nouveau dans la version 3.10.

int code_debug_ranges

If equals to 0, disables the inclusion of the end line and column mappings in code objects. Also disables traceback printing carets to specific error locations.

Set to 0 by the PYTHONNODEBUGRANGES environment variable and by the -X no_debug_ranges command line option.

Default: 1.

Nouveau dans la version 3.11.

wchar_t *check_hash_pycs_mode

Control the validation behavior of hash-based .pyc files : value of the --check-hash-based-pycs command line option.

Valid values:

- L"always": Hash the source file for invalidation regardless of value of the 'check_source' flag.
- L"never": Assume that hash-based pycs always are valid.
- L"default": The 'check source' flag in hash-based pycs determines invalidation.

Default: L"default".

See also PEP 552 "Deterministic pycs".

int configure_c_stdio

If non-zero, configure C standard streams:

- On Windows, set the binary mode (O_BINARY) on stdin, stdout and stderr.
- If buffered_stdio equals zero, disable buffering of stdin, stdout and stderr streams.
- If interactive is non-zero, enable stream buffering on stdin and stdout (only stdout on Windows).

Default: 1 in Python config, 0 in isolated config.

int dev_mode

If non-zero, enable the Python Development Mode.

Set to 1 by the -X dev option and the PYTHONDEVMODE environment variable.

Default: -1 in Python mode, 0 in isolated mode.

int dump_refs

Dump Python references?

If non-zero, dump all objects which are still alive at exit.

Set to 1 by the PYTHONDUMPREFS environment variable.

Need a special build of Python with the Py_TRACE_REFS macro defined : see the configure --with-trace-refs option.

Default: 0.

wchar_t *exec_prefix

The site-specific directory prefix where the platform-dependent Python files are installed : sys.exec_prefix.

Default: NULL.

Part of the Python Path Configuration output.

wchar_t *executable

The absolute path of the executable binary for the Python interpreter: sys.executable.

Default: NULL.

Part of the Python Path Configuration output.

int faulthandler

Enable faulthandler?

If non-zero, call faulthandler.enable() at startup.

Set to 1 by -X faulthandler and the PYTHONFAULTHANDLER environment variable.

Default: -1 in Python mode, 0 in isolated mode.

wchar_t *filesystem_encoding

Filesystem encoding: sys.getfilesystemencoding().

On macOS, Android and VxWorks: use "utf-8" by default.

On Windows: use "utf-8" by default, or "mbcs" if legacy_windows_fs_encoding of PyPreConfig is non-zero.

Default encoding on other platforms:

- "utf-8" if PyPreConfig.utf8_mode is non-zero.
- "ascii" if Python detects that nl_langinfo (CODESET) announces the ASCII encoding, whereas the mbstowcs () function decodes from a different encoding (usually Latin1).

10.6. PyConfig 213

```
— "utf-8" if nl_langinfo (CODESET) returns an empty string.
```

— Otherwise, use the locale encoding: nl_langinfo (CODESET) result.

At Python startup, the encoding name is normalized to the Python codec name. For example, "ANSI_X3.4-1968" is replaced with "ascii".

See also the filesystem_errors member.

wchar_t *filesystem_errors

Filesystem error handler: sys.getfilesystemencodeerrors().

On Windows: use "surrogatepass" by default, or "replace" if legacy_windows_fs_encoding of PyPreConfig is non-zero.

On other platforms: use "surrogateescape" by default.

Supported error handlers:

- "strict"
- "surrogateescape"
- "surrogatepass" (only supported with the UTF-8 encoding)

See also the filesystem_encoding member.

unsigned long hash_seed

int use_hash_seed

Randomized hash function seed.

If use_hash_seed is zero, a seed is chosen randomly at Python startup, and hash_seed is ignored.

Set by the PYTHONHASHSEED environment variable.

Default *use_hash_seed* value : -1 in Python mode, 0 in isolated mode.

wchar_t *home

Python home directory.

If Py_SetPythonHome () has been called, use its argument if it is not NULL.

Set by the PYTHONHOME environment variable.

Default: NULL.

Part of the Python Path Configuration input.

int import_time

If non-zero, profile import time.

Set the 1 by the -X importtime option and the PYTHONPROFILEIMPORTTIME environment variable.

Default: 0.

int inspect

Enter interactive mode after executing a script or a command.

If greater than 0, enable inspect: when a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Incremented by the -i command line option. Set to 1 if the PYTHONINSPECT environment variable is non-empty.

Default: 0.

int install_signal_handlers

Install Python signal handlers?

Default: 1 in Python mode, 0 in isolated mode.

int interactive

If greater than 0, enable the interactive mode (REPL).

Incremented by the -i command line option.

Default: 0.

int int_max_str_digits

Configures the integer string conversion length limitation. An initial value of -1 means the value will be taken from the command line or environment or otherwise default to 4300 (sys.int_info.default_max_str_digits). A value of 0 disables the limitation. Values greater than zero but less than 640 (sys.int_info.str_digits_check_threshold) are unsupported and will produce an error.

Configured by the -X int_max_str_digits command line flag or the PYTHONINTMAXSTRDIGITS environment variable.

Default: -1 in Python mode. 4300 (sys.int_info.default_max_str_digits) in isolated mode. Nouveau dans la version 3.12.

int isolated

If greater than 0, enable isolated mode:

- Set safe_path to 1: don't prepend a potentially unsafe path to sys.path at Python startup, such as
 the current directory, the script's directory or an empty string.
- Set use_environment to 0 : ignore PYTHON environment variables.
- Set user site directory to 0: don't add the user site directory to sys.path.
- Python REPL doesn't import readline nor enable default readline configuration on interactive prompts. Set to 1 by the -I command line option.

Default: 0 in Python mode, 1 in isolated mode.

See also the *Isolated Configuration* and *PyPreConfig.isolated*.

int legacy_windows_stdio

If non-zero, use io.FileIO instead of io._WindowsConsoleIO for sys.stdin, sys.stdout and sys.stderr.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

Only available on Windows. #ifdef MS_WINDOWS macro can be used for Windows specific code.

Default: 0.

See also the PEP 528 (Change Windows console encoding to UTF-8).

int malloc_stats

If non-zero, dump statistics on *Python pymalloc memory allocator* at exit.

Set to 1 by the PYTHONMALLOCSTATS environment variable.

The option is ignored if Python is configured using the --without-pymalloc option. Default: 0.

wchar_t *platlibdir

Platform library directory name: sys.platlibdir.

Set by the PYTHONPLATLIBDIR environment variable.

Default: value of the PLATLIBDIR macro which is set by the configure --with-platlibdir option (default: "lib", or "DLLs" on Windows).

Part of the Python Path Configuration input.

Nouveau dans la version 3.9.

Modifié dans la version 3.11: This macro is now used on Windows to locate the standard library extension modules, typically under DLLs. However, for compatibility, note that this value is ignored for any non-standard layouts, including in-tree builds and virtual environments.

wchar_t *pythonpath_env

Module search paths (sys.path) as a string separated by DELIM (os.pathsep).

Set by the PYTHONPATH environment variable.

Default: NULL.

Part of the Python Path Configuration input.

PyWideStringList module_search_paths

10.6. PyConfig 215

int module_search_paths_set

Module search paths: sys.path.

If module_search_paths_set is equal to 0, Py_InitializeFromConfig() will replace module_search_paths and sets module_search_paths_set to 1.

Default: empty list (module_search_paths) and 0 (module_search_paths_set).

Part of the Python Path Configuration output.

int optimization_level

Compilation optimization level:

- 0: Peephole optimizer, set __debug__ to True.
- 1: Level 0, remove assertions, set __debug__ to False.
- 2 : Level 1, strip docstrings.

Incremented by the <code>-O</code> command line option. Set to the <code>PYTHONOPTIMIZE</code> environment variable value.

Default: 0.

PyWideStringList orig_argv

The list of the original command line arguments passed to the Python executable: sys.orig_argv.

If orig_argv list is empty and argv is not a list only containing an empty string, PyConfig_Read() copies argv into orig_argv before modifying argv (if parse_argv is non-zero).

See also the argv member and the Py_GetArgcArgv() function.

Default: empty list.

Nouveau dans la version 3.10.

int parse_argv

Parse command line arguments?

If equals to 1, parse argv the same way the regular Python parses command line arguments, and strip Python arguments from argv.

The PyConfig_Read() function only parses PyConfig.argv arguments once: PyConfig. parse_argv is set to 2 after arguments are parsed. Since Python arguments are strippped from PyConfig.argv, parsing arguments twice would parse the application options as Python options.

Default: 1 in Python mode, 0 in isolated mode.

Modifié dans la version 3.10: The PyConfig.argv arguments are now only parsed if PyConfig. parse_argv equals to 1.

int parser_debug

Parser debug mode. If greater than 0, turn on parser debugging output (for expert only, depending on compilation options).

Incremented by the -d command line option. Set to the PYTHONDEBUG environment variable value.

Need a debug build of Python (the Py_DEBUG macro must be defined).

Default: 0.

int pathconfig_warnings

If non-zero, calculation of path configuration is allowed to log warnings into stderr. If equals to 0, suppress these warnings.

Default: 1 in Python mode, 0 in isolated mode.

Part of the Python Path Configuration input.

Modifié dans la version 3.11 : Now also applies on Windows.

wchar_t *prefix

The site-specific directory prefix where the platform independent Python files are installed: sys.prefix.

Default: NULL.

Part of the Python Path Configuration output.

wchar_t *program_name

Program name used to initialize <code>executable</code> and in early error messages during Python initialization.

```
— If Py_SetProgramName () has been called, use its argument.
```

- On macOS, use PYTHONEXECUTABLE environment variable if set.
- If the WITH_NEXT_FRAMEWORK macro is defined, use ___PYVENV_LAUNCHER__ environment variable if set.
- Use argv [0] of argv if available and non-empty.
- Otherwise, use L"python" on Windows, or L"python3" on other platforms.

Default: NULL.

Part of the Python Path Configuration input.

wchar_t *pycache_prefix

Directory where cached .pyc files are written: sys.pycache_prefix.

Set by the -X pycache_prefix=PATH command line option and the PYTHONPYCACHEPREFIX environment variable.

If NULL, sys.pycache_prefix is set to None.

Default: NULL.

int quiet

Quiet mode. If greater than 0, don't display the copyright and version at Python startup in interactive mode. Incremented by the -q command line option.

Default: 0.

wchar_t *run_command

Value of the -c command line option.

Used by Py_RunMain().

Default: NULL.

wchar_t *run_filename

Filename passed on the command line: trailing command line argument without -c or -m. It is used by the $Py_RunMain()$ function.

For example, it is set to script.py by the python3 script.py arg command line.

See also the PyConfig.skip_source_first_line option.

Default: NULL.

wchar_t *run_module

Value of the -m command line option.

Used by Py RunMain ().

Default: NULL.

int show_ref_count

Show total reference count at exit (excluding immortal objects)?

Set to 1 by -X showrefcount command line option.

Need a debug build of Python (the Py_REF_DEBUG macro must be defined).

Default: 0.

int site_import

Import the site module at startup?

If equal to zero, disable the import of the module site and the site-dependent manipulations of sys.path that it entails.

Also disable these manipulations if the site module is explicitly imported later (call site.main() if you want them to be triggered).

Set to 0 by the -S command line option.

sys.flags.no_site is set to the inverted value of site_import.

Default: 1.

10.6. PyConfig 217

int skip_source_first_line

If non-zero, skip the first line of the PyConfig.run_filename source.

It allows the usage of non-Unix forms of #! cmd. This is intended for a DOS specific hack only.

Set to 1 by the -x command line option.

Default: 0.

wchar_t *stdio_encoding

wchar_t *stdio_errors

Encoding and encoding errors of sys.stdin, sys.stdout and sys.stderr (but sys.stderr always uses "backslashreplace" error handler).

If Py_SetStandardStreamEncoding() has been called, use its error and errors arguments if they are not NULL.

Use the PYTHONIOENCODING environment variable if it is non-empty.

Default encoding:

- "UTF-8" if PyPreConfig.utf8 mode is non-zero.
- Otherwise, use the *locale encoding*.

Default error handler:

- On Windows: use "surrogateescape".
- "surrogateescape" if *PyPreConfig.utf8_mode* is non-zero, or if the LC_CTYPE locale is "C" or "POSIX".
- "strict" otherwise.

int tracemalloc

Enable tracemalloc?

If non-zero, call tracemalloc.start() at startup.

Set by -X tracemalloc=N command line option and by the PYTHONTRACEMALLOC environment variable.

Default: -1 in Python mode, 0 in isolated mode.

int perf_profiling

Enable compatibility mode with the perf profiler?

If non-zero, initialize the perf trampoline. See perf_profiling for more information.

Set by -X perf command line option and by the PYTHONPERFSUPPORT environment variable.

Default: -1.

Nouveau dans la version 3.12.

int use_environment

Use environment variables?

If equals to zero, ignore the environment variables.

Set to 0 by the -E environment variable.

Default: 1 in Python config and 0 in isolated config.

int user_site_directory

If non-zero, add the user site directory to sys.path.

Set to 0 by the -s and -I command line options.

Set to 0 by the PYTHONNOUSERSITE environment variable.

Default: 1 in Python mode, 0 in isolated mode.

int verbose

Verbose mode. If greater than 0, print a message each time a module is imported, showing the place (filename or built-in module) from which it is loaded.

If greater than or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Incremented by the -v command line option.

Set by the PYTHONVERBOSE environment variable value.

Default: 0.

PyWideStringList warnoptions

Options of the warnings module to build warnings filters, lowest to highest priority : sys. warnoptions.

The warnings module adds sys.warnoptions in the reverse order: the last *PyConfig.* warnoptions item becomes the first item of warnings.filters which is checked first (highest priority).

The -W command line options adds its value to warnoptions, it can be used multiple times.

The PYTHONWARNINGS environment variable can also be used to add warning options. Multiple options can be specified, separated by commas (,).

Default: empty list.

int write_bytecode

If equal to 0, Python won't try to write .pyc files on the import of source modules.

Set to 0 by the -B command line option and the PYTHONDONTWRITEBYTECODE environment variable.

sys.dont_write_bytecode is initialized to the inverted value of write_bytecode.

Default: 1.

PyWideStringList xoptions

Values of the -X command line options: sys._xoptions.

Default: empty list.

If parse_argv is non-zero, argv arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from argv.

The xoptions options are parsed to set other options : see the -X command line option.

Modifié dans la version 3.9 : The show_alloc_count field has been removed.

10.7 Initialization with PyConfig

Function to initialize Python:

PyStatus Py_InitializeFromConfig (const PyConfig *config)

Initialize Python from *config* configuration.

The caller is responsible to handle exceptions (error or exit) using $PyStatus_Exception()$ and $Py_ExitStatusException()$.

If PyImport_FrozenModules(), PyImport_AppendInittab() or PyImport_ExtendInittab() are used, they must be set or called after Python preinitialization and before the Python initialization. If Python is initialized multiple times, PyImport_AppendInittab() or PyImport_ExtendInittab() must be called before each Python initialization.

The current configuration (PyConfig type) is stored in PyInterpreterState.config.

Example setting the program name:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);

    /* Set the program name. Implicitly preinitialize Python. */
    status = PyConfig_SetString(&config, &config.program_name,
```

(suite sur la page suivante)

(suite de la page précédente)

```
L"/path/to/my_program");

if (PyStatus_Exception(status)) {
    goto exception;
}

status = Py_InitializeFromConfig(&config);

if (PyStatus_Exception(status)) {
    goto exception;
}
PyConfig_Clear(&config);
return;

exception:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
}
```

More complete example modifying the default configuration, read the configuration, and then override some parameters. Note that since 3.11, many parameters are not calculated until initialization, and so values cannot be read from the configuration structure. Any values set before initialize is called will be left unchanged by initialization:

```
PyStatus init_python(const char *program_name)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
   /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).
       Implicitly preinitialize Python. */
   status = PyConfig_SetBytesString(&config, &config.program_name,
                                     program_name);
   if (PyStatus_Exception(status)) {
       goto done;
   }
   /* Read all configuration at once */
   status = PyConfig_Read(&config);
   if (PyStatus_Exception(status)) {
       goto done;
   }
   /* Specify sys.path explicitly */
   /* If you want to modify the default set of paths, finish
       initialization first and then use PySys_GetObject("path") */
   config.module_search_paths_set = 1;
   status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/stdlib");
   if (PyStatus_Exception(status)) {
       goto done;
   status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
   if (PyStatus_Exception(status)) {
```

(suite sur la page suivante)

(suite de la page précédente)

10.8 Isolated Configuration

PyPreConfig_InitIsolatedConfig() and PyConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environment variables, command line arguments (PyConfig. argv is not parsed) and user site directory. The C standard streams (ex:stdout) and the LC_CTYPE locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration to determine paths that are unspecified. Ensure PyConfig.home is specified to avoid computing the default path configuration.

10.9 Python Configuration

PyPreConfig_InitPythonConfig() and PyConfig_InitPythonConfig() functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (PEP 538) and Python UTF-8 Mode (PEP 540) depending on the LC_CTYPE locale, PYTHONUTF8 and PYTHONCOERCECLOCALE environment variables.

10.10 Python Path Configuration

 $\ensuremath{\textit{PyConfig}}$ contains multiple fields for the path configuration :

- Path configuration inputs :
 - PyConfig.home
 - PyConfig.platlibdir
 - PyConfig.pathconfig_warnings
 - PyConfig.program_name
 - PyConfig.pythonpath_env
 - current working directory: to get absolute paths

- PATH environment variable to get the program full path (from PyConfig.program_name)
- __PYVENV_LAUNCHER__ environment variable
- (Windows only) Application paths in the registry under "SoftwarePythonPythonCoreX.YPythonPath" of HKEY_CURRENT_USER and HKEY_LOCAL_MACHINE (where X.Y is the Python version).
- Path configuration output fields:
 - PyConfig.base_exec_prefix
 - PyConfig.base executable
 - PyConfig.base prefix
 - PyConfig.exec prefix
 - PyConfig.executable
 - PyConfig.module_search_paths_set, PyConfig.module_search_paths
 - PyConfig.prefix

If at least one "output field" is not set, Python calculates the path configuration to fill unset fields. If <code>module_search_paths_set</code> is equal to 0, <code>module_search_paths</code> is overridden and <code>module_search_paths_set</code> is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. module_search_paths is considered as set if module_search_paths_set is set to 1. In this case, module_search_paths will be used without modification.

Set pathconfig_warnings to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If base_prefix or base_exec_prefix fields are not set, they inherit their value from prefix and exec prefix respectively.

Py_RunMain() and Py_Main() modify sys.path:

- If run_filename is set and is a directory which contains a __main__.py script, prepend run_filename to sys.path.
- If isolated is zero:
 - If run_module is set, prepend the current directory to sys.path. Do nothing if the current directory cannot be read.
 - If run_filename is set, prepend the directory of the filename to sys.path.
 - Otherwise, prepend an empty string to sys.path.

If <code>site_import</code> is non-zero, <code>sys.path</code> can be modified by the <code>site</code> module. If <code>user_site_directory</code> is non-zero and the user's site-package directory exists, the <code>site</code> module appends the user's site-package directory to <code>sys.path</code>.

The following configuration files are used by the path configuration:

- pyvenv.cfg
- _____pth file (ex : python._pth)
- pybuilddir.txt (Unix only)

If a ._pth file is present:

- Set isolated to 1.
- Set use_environment to 0.
- Set site_import to 0.
- Set $safe_path$ to 1.

The __PYVENV_LAUNCHER__ environment variable is used to set PyConfig.base_executable

10.11 Py_RunMain()

int Py_RunMain (void)

Execute the command (PyConfig.run_command), the script (PyConfig.run_filename) or the module (PyConfig.run_module) specified on the command line or in the configuration.

By default and when if -i option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the exit () function.

See Python Configuration for an example of customized Python always running in isolated mode using Py_RunMain().

10.12 Py_GetArgcArgv()

```
void Py_GetArgcArgv (int *argc, wchar_t ***argv)
```

Get the original command line arguments, before Python modified them.

See also PyConfig.orig_argv member.

10.13 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of PEP 432:

- "Core" initialization phase, "bare minimum Python":
 - Builtin types;
 - Builtin exceptions;
 - Builtin and frozen modules;
 - The sys module is only partially initialized (ex: sys.path doesn't exist yet).
- "Main" initialization phase, Python is fully initialized:
 - Install and configure importlib;
 - Apply the *Path Configuration*;
 - Install signal handlers;
 - Finish sys module initialization (ex: create sys.stdout and sys.path);
 - Enable optional features like faulthandler and tracemalloc;
 - Import the site module;
 - etc.

Private provisional API:

— PyConfig._init_main: if set to 0, Py_InitializeFromConfig() stops at the "Core" initialization phase.

PyStatus _Py_InitializeMain (void)

Move to the "Main" initialization phase, finish the Python initialization.

No module is imported during the "Core" phase and the importlib module is not configured: the *Path Configuration* is only applied during the "Main" phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom sys.meta_path importer or an import hook, etc.

It may become possible to calculate the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the **PEP 432** motivation.

The "Core" phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between "Core" and "Main" initialization phases:

```
void init_python(void)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
   config._init_main = 0;
   /* ... customize 'config' configuration ... */
   status = Py_InitializeFromConfig(&config);
   PyConfig_Clear(&config);
   if (PyStatus_Exception(status)) {
       Py_ExitStatusException(status);
   /* Use sys.stderr because sys.stdout is only created
      by _Py_InitializeMain() */
   int res = PyRun_SimpleString(
       "import sys; "
       "print('Run Python code before _Py_InitializeMain', "
              "file=sys.stderr)");
   if (res < 0) {
       exit(1);
   /* ... put more configuration code here ... */
   status = _Py_InitializeMain();
   if (PyStatus_Exception(status)) {
       Py_ExitStatusException(status);
   }
```

CHAPITRE 11

Memory Management

11.1 Aperçu

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: $\mathtt{malloc}()$, $\mathtt{calloc}()$, $\mathtt{realloc}()$ and $\mathtt{free}()$. This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
```

(suite sur la page suivante)

(suite de la page précédente)

```
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

Voir aussi:

The PYTHONMALLOC environment variable can be used to configure the memory allocators used by Python.

The PYTHONMALLOCSTATS environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

11.2 Allocator Domains

All allocating functions belong to one of three different "domains" (see also <code>PyMemAllocatorDomain</code>). These domains represent different allocation strategies and are optimized for different purposes. The specific details on how every domain allocates memory or what internal functions each domain calls is considered an implementation detail, but for debugging purposes a simplified table can be found at <code>here</code>. There is no hard requirement to use the memory returned by the allocation functions belonging to a given domain for only the purposes hinted by that domain (although this is the recommended practice). For example, one could use the memory returned by <code>PyMem_RawMalloc()</code> for allocating Python objects or the memory returned by <code>PyObject_Malloc()</code> for allocating memory for buffers.

The three allocation domains are:

- Raw domain: intended for allocating memory for general-purpose memory buffers where the allocation *must* go to the system allocator or where the allocator can operate without the *GIL*. The memory is requested directly to the system.
- "Mem" domain: intended for allocating memory for Python buffers and general-purpose memory buffers where the allocation must be performed with the *GIL* held. The memory is taken from the Python private heap.
- Object domain: intended for allocating memory belonging to Python objects. The memory is taken from the Python private heap.

When freeing memory previously allocated by the allocating functions belonging to a given domain, the matching specific deallocating functions must be used. For example, $PyMem_Free()$ must be used to free memory allocated using $PyMem_Malloc()$.

11.3 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, the *GIL* does not need to be held.

The *default raw memory allocator* uses the following functions: malloc(), calloc(), realloc() and free(); call malloc(1) (or calloc(1, 1)) when requesting zero bytes.

Nouveau dans la version 3.4.

void *PyMem_RawMalloc (size_t n)

Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_RawMalloc(1) had been called instead. The memory will not have been initialized in any way.

void *PyMem_RawCalloc (size_t nelem, size_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_RawCalloc(1, 1) had been called instead.

Nouveau dans la version 3.5.

void *PyMem_RawRealloc (void *p, size_t n)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem_RawMalloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyMem_RawMalloc()$, $PyMem_RawRealloc()$ or $PyMem_RawCalloc()$.

If the request fails, $PyMem_RawRealloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void PyMem_RawFree (void *p)

Frees the memory block pointed to by p, which must have been returned by a previous call to $PyMem_RawMalloc()$, $PyMem_RawRealloc()$ or $PyMem_RawCalloc()$. Otherwise, or if $PyMem_RawFree(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

11.4 Memory Interface

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default memory allocator uses the pymalloc memory allocator.

Avertissement : The *GIL* must be held when using these functions.

Modifié dans la version 3.6: The default allocator is now pymalloc instead of system malloc().

void *PyMem_Malloc (size_t n)

Part of the Stable ABI. Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_Malloc(1) had been called instead. The memory will not have been initialized in any way.

```
void *PyMem_Calloc (size_t nelem, size_t elsize)
```

Part of the Stable ABI since version 3.7. Allocates nelem elements each whose size in bytes is elsize and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if $PyMem_Calloc(1, 1)$ had been called instead.

Nouveau dans la version 3.5.

void *PyMem_Realloc (void *p, size_t n)

Part of the Stable ABI. Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyMem_Malloc()$, $PyMem_Realloc()$ or $PyMem_Calloc()$.

If the request fails, $PyMem_Realloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void PyMem_Free (void *p)

Part of the Stable ABI. Frees the memory block pointed to by p, which must have been returned by a previous call to $PyMem_Malloc()$, $PyMem_Realloc()$ or $PyMem_Calloc()$. Otherwise, or if $PyMem_Free(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

The following type-oriented macros are provided for convenience. Note that TYPE refers to any C type.

$\textbf{PyMem_New}\ (TYPE,\ n)$

Same as <code>PyMem_Malloc()</code>, but allocates (n * sizeof(TYPE)) bytes of memory. Returns a pointer cast to <code>TYPE*</code>. The memory will not have been initialized in any way.

$PyMem_Resize(p, TYPE, n)$

Same as $PyMem_Realloc()$, but the memory block is resized to (n * sizeof(TYPE)) bytes. Returns a pointer cast to TYPE*. On return, p will be a pointer to the new memory area, or NULL in the event of failure.

This is a C preprocessor macro; p is always reassigned. Save the original value of p to avoid losing memory when handling errors.

void PyMem_Del (void *p)

Same as PyMem_Free().

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- PyMem_MALLOC(size)
- PyMem_NEW(type, size)
- PyMem_REALLOC(ptr, size)
- PyMem_RESIZE(ptr, type, size)
- PyMem_FREE(ptr)
- PyMem_DEL(ptr)

11.5 Object allocators

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

Note: There is no guarantee that the memory returned by these allocators can be successfully cast to a Python object when intercepting the allocating functions in this domain by the methods described in the *Customize Memory Allocators* section.

The default object allocator uses the pymalloc memory allocator.

Avertissement: The *GIL* must be held when using these functions.

void *PyObject_Malloc (size_t n)

Part of the Stable ABI. Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyObject_Malloc(1) had been called instead. The memory will not have been initialized in any way.

void *PyObject_Calloc (size_t nelem, size_t elsize)

Part of the Stable ABI since version 3.7. Allocates nelem elements each whose size in bytes is elsize and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if $PyObject_Calloc(1, 1)$ had been called instead.

Nouveau dans la version 3.5.

void *PyObject_Realloc (void *p, size_t n)

Part of the Stable ABI. Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyObject_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyObject_Malloc()$, $PyObject_Realloc()$ or $PyObject_Calloc()$.

If the request fails, $PyObject_Realloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void PyObject_Free (void *p)

Part of the Stable ABI. Frees the memory block pointed to by p, which must have been returned by a previous call to $PyObject_Malloc()$, $PyObject_Realloc()$ or $PyObject_Calloc()$. Otherwise, or if $PyObject_Free(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

11.6 Default Memory Allocators

Default memory allocators:

Configuration	Nom	Py-	PyMem_Malloc	PyOb-
		Mem_RawMalloc		ject_Malloc
Release build	"pymalloc"	malloc	pymalloc	pymalloc
Debug build	"pymalloc_debug	"malloc + debug	pymalloc+de-	pymalloc+de-
			bug	bug
Release build, without py-	"malloc"	malloc	malloc	malloc
malloc				
Debug build, without py-	"malloc_debug"	malloc + debug	malloc + debug	malloc + debug
malloc				

Legend:

- Name : value for PYTHONMALLOC environment variable.
- malloc: system allocators from the standard C library, C functions: malloc(), calloc(), realloc() and free().
- pymalloc: pymalloc memory allocator.
- "+ debug": with debug hooks on the Python memory allocators.
- "Debug build": Python build in debug mode.

11.7 Customize Memory Allocators

Nouveau dans la version 3.4.

type PyMemAllocatorEx

Structure used to describe a memory block allocator. The structure has the following fields:

Champ	Signification
void *ctx	user context passed as first argument
<pre>void* malloc(void *ctx, size_t size)</pre>	allocate a memory block
<pre>void* calloc(void *ctx, size_t nelem, size_t</pre>	allocate a memory block initialized with
elsize)	zeros
<pre>void* realloc(void *ctx, void *ptr, size_t</pre>	allocate or resize a memory block
new_size)	
<pre>void free(void *ctx, void *ptr)</pre>	free a memory block

Modifié dans la version 3.5 : The PyMemAllocator structure was renamed to PyMemAllocatorEx and a new calloc field was added.

type PyMemAllocatorDomain

Enum used to identify an allocator domain. Domains:

PYMEM_DOMAIN_RAW

Functions:

- PyMem_RawMalloc()
- PyMem_RawRealloc()
- PyMem_RawCalloc()
- PyMem_RawFree()

PYMEM DOMAIN MEM

Functions:

- PyMem_Malloc(),
- PyMem_Realloc()
- PyMem_Calloc()
- PyMem_Free()

PYMEM_DOMAIN_OBJ

Functions:

- PyObject_Malloc()
- PyObject_Realloc()
- PyObject_Calloc()
- PyObject_Free()

void PyMem_GetAllocator (PyMemAllocatorDomain domain, PyMemAllocatorEx *allocator)

Get the memory block allocator of the specified domain.

void PyMem_SetAllocator (PyMemAllocatorDomain domain, PyMemAllocatorEx *allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the PYMEM_DOMAIN_RAW domain, the allocator must be thread-safe: the GIL is not held when the allocator is called.

For the remaining domains, the allocator must also be thread-safe : the allocator may be called in different interpreters that do not share a GIL.

If the new allocator is not a hook (does not call the previous allocator), the <code>PyMem_SetupDebugHooks()</code> function must be called to reinstall the debug hooks on top on the new allocator.

See also PyPreConfig. allocator and Preinitialize Python with PyPreConfig.

Avertissement: PyMem SetAllocator() does have the following contract:

- It can be called after Py_PreInitialize() and before Py_InitializeFromConfig() to install a custom memory allocator. There are no restrictions over the installed allocator other than the ones imposed by the domain (for instance, the Raw Domain allows the allocator to be called without the GIL held). See *the section on allocator domains* for more information.
- If called after Python has finish initializing (after Py_InitializeFromConfig() has been called) the allocator **must** wrap the existing allocator. Substituting the current allocator for some other arbitrary one is **not supported**.

Modifié dans la version 3.12 : All allocators must be thread-safe.

void PyMem_SetupDebugHooks (void)

Setup debug hooks in the Python memory allocators to detect memory errors.

11.8 Debug hooks on the Python memory allocators

When Python is built in debug mode, the <code>PyMem_SetupDebugHooks()</code> function is called at the <code>Python preinitialization</code> to setup debug hooks on Python memory allocators to detect memory errors.

The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode (ex:PYTHONMALLOC=debug).

The <code>PyMem_SetupDebugHooks()</code> function can be used to set debug hooks after calling <code>PyMem_SetAllocator()</code>.

These debug hooks fill dynamically allocated memory blocks with special, recognizable bit patterns. Newly allocated memory is filled with the byte 0xCD (PYMEM_CLEANBYTE), freed memory is filled with the byte 0xDD (PYMEM_DEADBYTE). Memory blocks are surrounded by "forbidden bytes" filled with the byte 0xFD (PYMEM_FORBIDDENBYTE). Strings of these bytes are unlikely to be valid addresses, floats, or ASCII strings.

Runtime checks:

- Detect API violations. For example, detect if PyObject_Free() is called on a memory block allocated by PyMem_Malloc().
- Detect write before the start of the buffer (buffer underflow).
- Detect write after the end of the buffer (buffer overflow).
- Check that the GIL is held when allocator functions of PYMEM_DOMAIN_OBJ (ex: PyObject_Malloc()) and PYMEM_DOMAIN_MEM (ex: PyMem_Malloc()) domains are called.

On error, the debug hooks use the tracemalloc module to get the traceback where a memory block was allocated. The traceback is only displayed if tracemalloc is tracing Python memory allocations and the memory block was traced.

Let $S = \mathtt{sizeof}(\mathtt{size_t})$. 2*S bytes are added at each end of each block of N bytes requested. The memory layout is like so, where p represents the address returned by a malloc-like or realloc-like function (p[i:j] means the slice of bytes from *(p+i) inclusive up to *(p+j) exclusive; note that the treatment of negative indices differs from a Python slice):

p[-2*S:-S] Number of bytes originally asked for. This is a size_t, big-endian (easier to read in a memory dump).

```
p[-S] API identifier (ASCII character):
```

- 'r' for PYMEM_DOMAIN_RAW.
- 'm' for PYMEM_DOMAIN_MEM.
- 'o' for PYMEM DOMAIN OBJ.

p[-S+1:0] Copies of PYMEM_FORBIDDENBYTE. Used to catch under- writes and reads.

p[0:N] The requested memory, filled with copies of PYMEM_CLEANBYTE, used to catch reference to uninitialized memory. When a realloc-like function is called requesting a larger memory block, the new excess bytes are also filled with PYMEM_CLEANBYTE. When a free-like function is called, these are overwritten with PYMEM_DEADBYTE, to catch reference to freed memory. When a realloc-like function is called requesting a smaller memory block, the excess old bytes are also filled with PYMEM_DEADBYTE.

p[N:N+S] Copies of PYMEM_FORBIDDENBYTE. Used to catch over- writes and reads.

```
p[N+S:N+2*S] Only used if the PYMEM DEBUG SERIALNO macro is defined (not defined by default).
```

A serial number, incremented by 1 on each call to a malloc-like or realloc-like function. Big-endian <code>size_t</code>. If "bad memory" is detected later, the serial number gives an excellent way to set a breakpoint on the next run, to capture the instant at which this block was passed out. The static function bumpserialno() in obmalloc.c is the only place the serial number is incremented, and exists so you can set such a breakpoint easily.

A realloc-like or free-like function first checks that the PYMEM_FORBIDDENBYTE bytes at each end are intact. If they've been altered, diagnostic output is written to stderr, and the program is aborted via Py_FatalError(). The other main failure mode is provoking a memory error when a program reads up one of the special bit patterns and tries to use it as an address. If you get in a debugger then and look at the object, you're likely to see that it's entirely filled with PYMEM_DEADBYTE (meaning freed memory is getting used) or PYMEM_CLEANBYTE (meaning uninitialized memory is getting used).

Modifié dans la version 3.6 : The <code>PyMem_SetupDebugHooks()</code> function now also works on Python compiled in release mode. On error, the debug hooks now use <code>tracemalloc</code> to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of <code>PYMEM_DOMAIN_OBJ</code> and <code>PYMEM_DOMAIN_MEM</code> domains are called.

Modifié dans la version 3.8 : Byte patterns $0 \times CB$ (PYMEM_CLEANBYTE), $0 \times DB$ (PYMEM_DEADBYTE) and $0 \times FB$ (PYMEM_FORBIDDENBYTE) have been replaced with $0 \times CD$, $0 \times DD$ and $0 \times FD$ to use the same values than Windows CRT debug malloc() and free().

11.9 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called "arenas" with a fixed size of either 256 KiB on 32-bit platforms or 1 MiB on 64-bit platforms. It falls back to <code>PyMem_RawMalloc()</code> and <code>PyMem_RawRealloc()</code> for allocations larger than 512 bytes.

pymalloc is the default allocator of the $PYMEM_DOMAIN_MEM$ (ex: $PyMem_Malloc()$) and $PYMEM_DOMAIN_OBJ$ (ex: $PyObject_Malloc()$) domains.

The arena allocator uses the following functions:

- VirtualAlloc() and VirtualFree() on Windows,
- mmap () and munmap () if available,
- malloc() and free() otherwise.

This allocator is disabled if Python is configured with the --without-pymalloc option. It can also be disabled at runtime using the PYTHONMALLOC environment variable (ex: PYTHONMALLOC=malloc).

11.9.1 Customize pymalloc Arena Allocator

Nouveau dans la version 3.4.

type PyObjectArenaAllocator

Structure used to describe an arena allocator. The structure has three fields:

Champ	Signification
void *ctx	user context passed as first argument
<pre>void* alloc(void *ctx, size_t size)</pre>	allocate an arena of size bytes
<pre>void free(void *ctx, void *ptr, size_t size)</pre>	free an arena

void PyObject_GetArenaAllocator (PyObjectArenaAllocator *allocator)

Get the arena allocator.

void PyObject_SetArenaAllocator (PyObjectArenaAllocator *allocator)

Set the arena allocator.

11.10 tracemalloc C API

Nouveau dans la version 3.7.

int PyTraceMalloc_Track (unsigned int domain, uintptr_t ptr, size_t size)

Track an allocated memory block in the tracemalloc module.

Return 0 on success, return -1 on error (failed to allocate memory to store the trace). Return -2 if tracemalloc is disabled.

If memory block is already tracked, update the existing trace.

int PyTraceMalloc_Untrack (unsigned int domain, uintptr_t ptr)

Untrack an allocated memory block in the tracemalloc module. Do nothing if the block was not tracked.

Return -2 if tracemalloc is disabled, otherwise return 0.

11.11 Exemples

Here is the example from section *Aperçu*, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2); /* Right -- allocated via malloc() */
free(buf1); /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with <code>PyObject_New</code>, <code>PyObject_NewVar</code> and <code>PyObject_Del()</code>.

These will be explained in the next chapter on defining and implementing new object types in C.

Implémentation d'objets

Ce chapitre décrit les fonctions, types, et macros utilisées pour définir de nouveaux types d'objets.

12.1 Allouer des objets dans le tas

```
PyObject *_PyObject_New (PyTypeObject *type)
```

Return value: New reference.

PyVarObject *_PyObject_NewVar (PyTypeObject *type, Py_ssize_t size)

Return value: New reference.

PyObject *PyObject Init (PyObject *op, PyTypeObject *type)

Return value: Borrowed reference. Part of the Stable ABI. Initialize a newly allocated object op with its type and initial reference. Returns the initialized object. If type indicates that the object participates in the cyclic garbage detector, it is added to the detector's set of observed objects. Other fields of the object are not affected.

PyVarObject *PyObject_InitVar (PyVarObject *op, PyTypeObject *type, Py_ssize_t size)

Return value : Borrowed reference. Part of the Stable ABI. Effectue les mêmes opérations que PyObject_Init() fait, et initialise également l'information de la longueur pour un objet de taille variable.

PyObject_New (TYPE, typeobj)

Allocate a new Python object using the C structure type TYPE and the Python type object typeobj (PyTypeObject*). Fields not defined by the Python object header are not initialized. The caller will own the only reference to the object (i.e. its reference count will be one). The size of the memory allocation is determined from the $tp_basicsize$ field of the type object.

PyObject_NewVar (TYPE, typeobj, size)

Allocate a new Python object using the C structure type *TYPE* and the Python type object *typeobj* (PyTypeObject*). Fields not defined by the Python object header are not initialized. The allocated memory allows for the *TYPE* structure plus *size* (Py_ssize_t) fields of the size given by the *tp_itemsize* field of *typeobj*. This is useful for implementing objects like tuples, which are able to determine their size at construction

time. Embedding the array of fields into the same allocation decreases the number of allocations, improving the memory management efficiency.

void PyObject_Del (void *op)

Releases memory allocated to an object using $PyObject_New$ or $PyObject_NewVar$. This is normally called from the $tp_dealloc$ handler specified in the object's type. The fields of the object should not be accessed after this call as the memory is no longer a valid Python object.

PyObject _Py_NoneStruct

Objet qui est visible en tant que None dans Python. Ne devrait être accessible uniquement en utilisant la macro Py_None, qui évalue cet objet à un pointeur.

Voir aussi:

PyModule_Create() Allouer et créer des modules d'extension.

12.2 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

12.2.1 Base object types and macros

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the PyObject and PyVarObject types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects. Additional macros can be found under *reference counting*.

type PyObject

Part of the Limited API. (Only some members are part of the stable ABI.) All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal "release" build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a PyObject, but every pointer to a Python object can be cast to a PyObject*. Access to the members must be done by using the macros Py_REFCNT and Py_TYPE.

type PyVarObject

Part of the Limited API. (Only some members are part of the stable ABI.) This is an extension of PyObject that adds the ob_size field. This is only used for objects that have some notion of length. This type does not often appear in the Python/C API. Access to the members must be done by using the macros Py_REFCNT , Py_TYPE , and Py_SIZE .

PyObject_HEAD

This is a macro used when declaring new types which represent objects without a varying length. The PyObject_HEAD macro expands to :

```
PyObject ob_base;
```

See documentation of PyObject above.

PyObject_VAR_HEAD

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The PyObject_VAR_HEAD macro expands to :

```
PyVarObject ob_base;
```

See documentation of PyVarObject above.

```
int Py_Is (PyObject *x, PyObject *y)
```

Part of the Stable ABI since version 3.10. Test if the x object is the y object, the same as x is y in Python.

Nouveau dans la version 3.10.

```
int Py_IsNone (PyObject *x)
```

Part of the Stable ABI since version 3.10. Test if an object is the None singleton, the same as x is None in Python.

Nouveau dans la version 3.10.

int Py_IsTrue (*PyObject* *x)

Part of the Stable ABI since version 3.10. Test if an object is the True singleton, the same as x is True in Python.

Nouveau dans la version 3.10.

int Py_IsFalse (PyObject *x)

Part of the Stable ABI since version 3.10. Test if an object is the False singleton, the same as x is False in Python.

Nouveau dans la version 3.10.

PyTypeObject *Py_TYPE (PyObject *o)

Get the type of the Python object o.

Return a borrowed reference.

Use the Py_SET_TYPE () function to set an object type.

Modifié dans la version $3.11: Py_TYPE()$ is changed to an inline static function. The parameter type is no longer const PyObject*.

int **Py_IS_TYPE** (*PyObject* *o, *PyTypeObject* *type)

Return non-zero if the object o type is type. Return zero otherwise. Equivalent to : Py_TYPE (o) == type. Nouveau dans la version 3.9.

void Py_SET_TYPE (PyObject *o, PyTypeObject *type)

Set the object o type to type.

Nouveau dans la version 3.9.

Py_ssize_t Py_SIZE (PyVarObject *o)

Get the size of the Python object o.

Use the Py_SET_SIZE () function to set an object size.

Modifié dans la version 3.11 : Py_SIZE () is changed to an inline static function. The parameter type is no longer const PyVarObject*.

void Py_SET_SIZE (PyVarObject *o, Py_ssize_t size)

Set the object o size to size.

Nouveau dans la version 3.9.

PyObject_HEAD_INIT (type)

This is a macro which expands to initialization values for a new PyObject type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

PyVarObject_HEAD_INIT (type, size)

This is a macro which expands to initialization values for a new PyVarObject type, including the ob_size field. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type, size,
```

12.2.2 Implementing functions and methods

type PyCFunction

Part of the Stable ABI. Type of the functions used to implement most Python callables in C. Functions of this type take two <code>PyObject*</code> parameters and return one such value. If the return value is <code>NULL</code>, an exception shall have been set. If not <code>NULL</code>, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

The function signature is:

type PyCFunctionWithKeywords

Part of the Stable ABI. Type of the functions used to implement Python callables in C with signature METH_VARARGS | METH_KEYWORDS. The function signature is:

type _PyCFunctionFast

Type of the functions used to implement Python callables in C with signature METH_FASTCALL. The function signature is:

$type \verb| _PyCFunctionFastWithKeywords| \\$

Type of the functions used to implement Python callables in C with signature *METH_FASTCALL* | *METH_KEYWORDS*. The function signature is :

type PyCMethod

Type of the functions used to implement Python callables in C with signature *METH_METHOD* | *METH_FASTCALL* | *METH_KEYWORDS*. The function signature is :

```
PyObject *PyCMethod(PyObject *self,

PyTypeObject *defining_class,

PyObject *const *args,

Py_ssize_t nargs,

PyObject *kwnames)
```

Nouveau dans la version 3.9.

type PyMethodDef

Part of the Stable ABI (including all members). Structure used to describe a method of an extension type. This structure has four fields:

const char *ml_name

Name of the method.

PyCFunction ml_meth

Pointer to the C implementation.

int ml flags

Flags bits indicating how the call should be constructed.

const char *ml doc

Points to the contents of the docstring.

The ml_meth is a C function pointer. The functions may be of different types, but they always return PyObject*. If the function is not of the PyCFunction, the compiler will require a cast in the method table. Even though PyCFunction defines the first parameter as PyObject*, it is common that the method implementation uses the specific C type of the self object.

The ml_flags field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are these calling conventions:

METH_VARARGS

This is the typical calling convention, where the methods have the type PyCFunction. The function expects two PyObject* values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using $PyArg_ParseTuple()$ or $PyArg_UnpackTuple()$.

METH_KEYWORDS

Can only be used in certain combinations with other flags: METH_VARARGS | METH_KEYWORDS, METH FASTCALL | METH KEYWORDS and METH METHOD | METH FASTCALL | METH KEYWORDS.

METH_VARARGS | **METH_KEYWORDS** Methods with these flags must be of type PyCFunctionWithKeywords. The function expects three parameters: self, args, kwargs where kwargs is a dictionary of all the keyword arguments or possibly NULL if there are no keyword arguments. The parameters are typically processed using PyArg_ParseTupleAndKeywords().

METH FASTCALL

Fast calling convention supporting only positional arguments. The methods have the type _PyCFunctionFast. The first parameter is *self*, the second parameter is a C array of PyObject* values indicating the arguments and the third parameter is the number of arguments (the length of the array).

Nouveau dans la version 3.7.

Modifié dans la version 3.10: METH_FASTCALL is now part of the *stable ABI*.

METH_FASTCALL | **METH_KEYWORDS** Extension of METH_FASTCALL supporting also keyword arguments, with methods of type _PyCFunctionFastWithKeywords. Keyword arguments are passed the same way as in the vectorcall protocol: there is an additional fourth PyObject* parameter which is a tuple representing the names of the keyword arguments (which are guaranteed to be strings) or possibly NULL if there are no keywords. The values of the keyword arguments are stored in the args array, after the positional arguments.

Nouveau dans la version 3.7.

METH METHOD

Can only be used in the combination with other flags: METH_METHOD | METH_FASTCALL | METH_KEYWORDS.

METH_METHOD | **METH_FASTCALL** | **METH_KEYWORDS** Extension of METH_FASTCALL | METH_KEYWORDS supporting the defining class, that is, the class that contains the method in question. The defining class might be a superclass of Py_TYPE(self).

The method needs to be of type <code>PyCMethod</code>, the same as for <code>METH_FASTCALL | METH_KEYWORDS</code> with <code>defining_class</code> argument added after <code>self</code>.

Nouveau dans la version 3.9.

METH_NOARGS

Methods without parameters don't need to check whether arguments are given if they are listed with the METH_NOARGS flag. They need to be of type PyCFunction. The first parameter is typically named self and will hold a reference to the module or object instance. In all cases the second parameter will be NULL.

The function must have 2 parameters. Since the second parameter is unused, Py_UNUSED can be used to prevent a compiler warning.

METH_O

Methods with a single object argument can be listed with the METH_O flag, instead of invoking PyArg_ParseTuple() with a "O" argument. They have the type PyCFunction, with the self parameter, and a PyObject* parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

METH_CLASS

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the classmethod() built-in function.

METH_STATIC

The method will be passed NULL as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the staticmethod() built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

METH_COEXIST

The method will be loaded in place of existing definitions. Without *METH_COEXIST*, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq_contains* slot, for example, would generate a wrapped method named __contains__ () and preclude the loading of a corresponding PyCFunction with the same name. With the flag defined, the PyCFunction will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to PyCFunctions are optimized more than wrapper object calls.

12.2.3 Accessing attributes of extension types

type PyMemberDef

Part of the Stable ABI (including all members). Structure which describes an attribute of a type which corresponds to a C struct member. When defining a class, put a NULL-terminated array of these structures in the tp_members slot.

Its fields are, in order:

const char *name

Name of the member. A NULL value marks the end of a PyMemberDef [] array.

The string should be static, no copy is made of it.

Py ssize t offset

The offset in bytes that the member is located on the type's object struct.

int type

The type of the member in the C struct. See *Member types* for the possible values.

int flags

Zero or more of the *Member flags*, combined using bitwise OR.

const char *doc

The docstring, or NULL. The string should be static, no copy is made of it. Typically, it is defined using PyDoc STR.

By default (when flags is 0), members allow both read and write access. Use the $Py_READONLY$ flag for readonly access. Certain types, like Py_T_STRING , imply $Py_READONLY$. Only $Py_T_OBJECT_EX$ (and legacy T_OBJECT) members can be deleted.

For heap-allocated types (created using <code>PyType_FromSpec()</code> or similar), <code>PyMemberDef</code> may contain a definition for the special member "__vectorcalloffset__", corresponding to <code>tp_vectorcall_offset</code> in type objects. These must be defined with <code>Py_T_PYSSIZET</code> and <code>Py_READONLY</code>, for example:

(You may need to #include <stddef.h> for offsetof().)

The legacy offsets $tp_dictoffset$ and $tp_weaklistoffset$ can be defined similarly using "__dictoffset__" and "__weaklistoffset__" members, but extensions are strongly encouraged to use $Py_TPFLAGS_MANAGED_DICT$ and $Py_TPFLAGS_MANAGED_WEAKREF$ instead.

Modifié dans la version 3.12 : PyMemberDef is always available. Previously, it required including "structmember.h".

PyObject *PyMember_GetOne (const char *obj_addr, struct PyMemberDef *m)

Part of the Stable ABI. Get an attribute belonging to the object at address *obj_addr*. The attribute is described by PyMemberDef *m*. Returns NULL on error.

Modifié dans la version 3.12 : PyMember_GetOne is always available. Previously, it required including "structmember.h".

```
int PyMember_SetOne (char *obj_addr, struct PyMemberDef *m, PyObject *o)
```

Part of the Stable ABI. Set an attribute belonging to the object at address *obj_addr* to object *o*. The attribute to set is described by PyMemberDef *m*. Returns 0 if successful and a negative value on failure.

Modifié dans la version 3.12 : PyMember_SetOne is always available. Previously, it required including "structmember.h".

Member flags

The following flags can be used with PyMemberDef.flags:

Py_READONLY

Not writable.

Py_AUDIT_READ

Emit an object. __getattr__ audit event before reading.

Py_RELATIVE_OFFSET

Indicates that the offset of this PyMemberDef entry indicates an offset from the subclass-specific data, rather than from PyObject.

Can only be used as part of Py_tp_members slot when creating a class using negative basicsize. It is mandatory in that case.

This flag is only used in PyTypeSlot. When setting tp_members during class creation, Python clears it and sets PyMemberDef.offset to the offset from the PyObject struct.

Modifié dans la version 3.10: The RESTRICTED, READ_RESTRICTED and WRITE_RESTRICTED macros available with #include "structmember.h" are deprecated. READ_RESTRICTED and RESTRICTED are equivalent to Py_AUDIT_READ; WRITE_RESTRICTED does nothing.

Modifié dans la version 3.12: The READONLY macro was renamed to $Py_READONLY$. The PY_AUDIT_READ macro was renamed with the Py_ prefix. The new names are now always available. Previously, these required #include "structmember.h". The header is still available and it provides the old names.

Member types

PyMemberDef.type can be one of the following macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type. When it is set from Python, it will be converted back to the C type. If that is not possible, an exception such as TypeError or ValueError is raised.

Unless marked (D), attributes defined this way cannot be deleted using e.g. del or delattr().

Macro name	Туре С	Python type
Py_T_BYTE	char	int
Py_T_SHORT	short	int
Py_T_INT	int	int
Py_T_LONG	long	int
Py_T_LONGLONG	long long	int
Py_T_UBYTE	unsigned char	int
Py_T_UINT	unsigned int	int
Py_T_USHORT	unsigned short	int
Py_T_ULONG	unsigned long	int
Py_T_ULONGLONG	unsigned long long	int
Py_T_PYSSIZET	Py_ssize_t	int
Py_T_FLOAT	float	float
Py_T_DOUBLE	double	float
Py_T_BOOL	char (written as 0 or 1)	bool
Py_T_STRING	const char*(*)	str(RO)
Py_T_STRING_INPLACE	const char[](*)	str(RO)
Py_T_CHAR	char (0-127)	str(**)
Py_T_OBJECT_EX	PyObject*	object (D)

- (*): Zero-terminated, UTF8-encoded C string. With Py_T_STRING the C representation is a pointer; with $Py_T_STRING_INLINE$ the string is stored directly in the structure.
- (**): String of length 1. Only ASCII is accepted.
- (RO): Implies Py_READONLY.
- (D): Can be deleted, in which case the pointer is set to NULL. Reading a NULL pointer raises AttributeError.

Nouveau dans la version 3.12: In previous versions, the macros were only available with #include "structmember.h" and were named without the Py_ prefix (e.g. as T_INT). The header is still available and contains the old names, along with the following deprecated types:

T OBJECT

Like Py_T_OBJECT_EX, but NULL is converted to None. This results in surprising behavior in Python: deleting the attribute effectively sets it to None.

T NONE

Always None. Must be used with Py_READONLY.

Defining Getters and Setters

type PyGetSetDef

Part of the Stable ABI (*including all members*). Structure to define property-like access for a type. See also description of the *PyTypeObject.tp getset* slot.

const char *name

attribute name

getter get

C function to get the attribute.

setter set

Optional C function to set or delete the attribute, if omitted the attribute is readonly.

const char *doc

optional docstring

void *closure

Optional function pointer, providing additional data for getter and setter.

The get function takes one *PyObject** parameter (the instance) and a function pointer (the associated closure):

```
typedef PyObject *(*getter)(PyObject *, void *);
```

It should return a new reference on success or NULL with a set exception on failure.

set functions take two PyObject* parameters (the instance and the value to be set) and a function pointer (the associated closure):

```
typedef int (*setter)(PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

12.3 Objets type

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the PyTypeObject structure. Type objects can be handled using any of the PyObject_* or PyType_* functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the *Exemples* section provides at-a-glance insight into the meaning and use of *PyTypeObject*.

12.3.1 Quick Reference

"tp slots"

PyTypeObject Slot ^{page 246, 1}	Туре	special methods/attrs		Info	page 246
				T	1 [
<r> tp_name</r>	const char *	name		X	П
tp_basicsize	Py_ssize_t		X	X	X
tp_itemsize	Py_ssize_t			X	X
tp_dealloc	destructor		X	X	X
tp_vectorcall_offset	Py_ssize_t			X	X
(tp_getattr)	getattrfunc	getattribute,getattr			G
(tp_setattr)	setattrfunc	setattr,delattr			G
tp_as_async	PyAsyncMethods*	sub-slots			%
tp_repr	reprfunc	repr	X	X	X
tp_as_number	PyNumberMethods*	sub-slots			%
tp_as_sequence	PySequenceMethods*	sub-slots			%
tp_as_mapping	PyMappingMethods*	sub-slots			%
tp_hash	hashfunc	hash	X		G
tp_call	ternaryfunc	call		X	X
tp_str	reprfunc	str	X		X
tp_getattro	getattrofunc	getattribute,getattr		X	G
tp_setattro	setattrofunc	setattr,delattr	X	X	G
tp_as_buffer	PyBufferProcs*				%
tp_flags	unsigned long		X	X	?
tp_doc	const char *	doc	X	X	П
tp_traverse	traverseproc			X	G
tp_clear	inquiry			X	G
tp_richcompare	richcmpfunc	lt,le,eq,ne	, X		G
		gt,ge			
(tp_weaklistoffset)	Py_ssize_t			X	?
tp_iter	getiterfunc	iter			X
tp_iternext	iternextfunc	next			X
tp_methods	PyMethodDef[]			X	П
tp_members	PyMemberDef[]			X	

suite sur la page suivante

Tableau 1 - suite de la page précédente

PyTypeObject Slot ^{page 246, 1}	Type	special methods/attrs	lı	Info ^{page} 246,		
		·	Q T	DI		
tp_getset	PyGetSetDef[]		XX			
tp_base	PyTypeObject*	base		X		
tp_dict	PyObject*	dict		?		
tp_descr_get	descrgetfunc	get		X		
tp_descr_set	descrsetfunc	set,delete		X		
(tp_dictoffset)	Py_ssize_t		Х	?		
tp_init	initproc	init	X X	X		
tp_alloc	allocfunc		X	? ?		
tp_new	newfunc	new	XX	? ?		
tp_free	freefunc		XX	? ?		
tp_is_gc	inquiry		Х	X		
<tp_bases></tp_bases>	PyObject*	bases		~		
<tp_mro></tp_mro>	PyObject*	mro		~		
[tp_cache]	PyObject*					
[tp_subclasses]	void *	subclasses				
[tp_weaklist]	PyObject*					
(tp_del)	destructor					
[tp_version_tag]	unsigned int					
tp_finalize	destructor	del		X		
tp_vectorcall	vectorcallfunc					
[tp_watched]	unsigned char					

^{1. ():} A slot name in parentheses indicates it is (effectively) deprecated.

2. Columns:

 $\hbox{\bf "O"}: set \ on \ {\tt PyBaseObject_Type}$

"T" : set on $PyType_Type$

"D": default (if slot is set to NULL)

- X PyType_Ready sets this value if it is NULL
- ~ PyType_Ready always sets this value (it should be NULL)
- ? PyType_Ready may set this value depending on other slots

Also see the inheritance column ("I").

"I": inheritance

- X type slot is inherited via *PyType_Ready* if defined with a *NULL* value
- % the slots of the sub-struct are inherited individually
- G inherited, but only in combination with other slots; see the slot's description
- ? it's complicated; see the slot's description

Note that some slots are effectively inherited through the normal attribute lookup chain.

<> : Names in angle brackets should be initially set to NULL and treated as read-only.

^{[]:} Names in square brackets are for internal use only.

<**R>** (as a prefix) means the field is required (must be non-NULL).

sub-slots

Slot	Туре	special methods
am_await	unaryfunc	await
am_aiter	unaryfunc	aiter
am_anext	unaryfunc	anext
am_send	sendfunc	
. 1 1.1	1-1	.1114
nb_add	binaryfunc	addradd
nb_inplace_add	binaryfunc	iadd
nb_subtract	binaryfunc binaryfunc	subrsub
nb_inplace_subtract	-	isub
nb_multiply	binaryfunc	mulrmul
nb_inplace_multiply	binaryfunc	imul
nb_remainder	binaryfunc	modrmod
nb_inplace_remainder	binaryfunc	imod
nb_divmod	binaryfunc	divmodrdiv-
nb_power	ternaryfunc	mod powrpow
nb_inplace_power	ternaryfunc	ipow
nb_negative	unaryfunc	ipow neg
nb_positive	unaryfunc	neg pos
nb_absolute	unaryfunc	abs
nb bool	inquiry	bool
nb_invert	unaryfunc	invert
nb_lshift	binaryfunc	lshiftrlshift
nb_inplace_lshift	binaryfunc	ilshift
nb_rshift	binaryfunc	rshiftrrshift
nb_inplace_rshift	binaryfunc	irshift
nb_and	binaryfunc	nshrt _andrand
nb_inplace_and	binaryfunc	iand
nb_xor	binaryfunc	xorrxor
nb_inplace_xor	binaryfunc	ixor
nb_or	binaryfunc	ror
nb_inplace_or	binaryfunc	ior
nb_int	unaryfunc	int
nb_reserved	void *	
nb float	unaryfunc	float
nb_floor_divide	binaryfunc	floordiv
nb_inplace_floor_divide	binaryfunc	ifloordiv
nb true divide	binaryfunc	truediv
nb_inplace_true_divide	binaryfunc	truediv
nb_index	unaryfunc	index
nb_matrix_multiply	binaryfunc	matmulrmat-
macrix_marcrpry	Dinaryranc	mul
nb_inplace_matrix_multiply	binaryfunc	imatmul
mp_length	lenfunc	len
mp_subscript	binaryfunc	getitem
mp_ass_subscript	objobjargproc	setitem,deli-
		tem

suite sur la page suivante

Tableau 2 - suite de la page précédente

Slot	Туре	special methods
	·	
sq_length	lenfunc	len
sq_concat	binaryfunc	add
sq_repeat	ssizeargfunc	mul
sq_item	ssizeargfunc	getitem
sq_ass_item	ssizeobjargproc	setitemdeli-
		tem
sq_contains	objobjproc	contains
sq_inplace_concat	binaryfunc	iadd
sq_inplace_repeat	ssizeargfunc	imul
	·	·
bf_getbuffer	getbufferproc()	
bf_releasebuffer	releasebufferproc()	

slot typedefs

typedef	Parameter Types	Return Type
allocfunc	2.	PyObject*
	PyTypeObject*	
	Py_ssize_t	
	FY_SSIZE_C	
destructor	void *	void
freefunc	void *	void
traverseproc		int
	void *	
	visitproc	
	void *	
	Void	
newfunc		PyObject*
	D0h + *	
	PyObject*	
	PyObject*	
	PyObject*	
initproc		int
_F		···
	PyObject*	
	PyObject*	
	PyObject*	
reprfunc	PyObject*	PyObject*
getattrfunc	Pyobject:	PyObject*
getattiint		1 you ject
	PyObject*	
	const char *	
setattrfunc		int
Secaccifunc		int
	PyObject*	
	const char *	
	PyObject*	
		D. 01- ' 1- *
getattrofunc		PyObject*
	PyObject*	
	PyObject*	
setattrofunc		int
	PyObject*	
	PyObject*	
	PyObject*	
descrgetfunc		PyObject*
	PyObject*	
	PyObject*	
	PyObject*	
2.3 Ohiets tyne		24
2.3. Objets type descrietfunc		int
	PyObject*	
	PyObject*	
	I YOU JECK	

See *Slot Type typedefs* below for more detail.

12.3.2 PyTypeObject Definition

The structure definition for PyTypeObject can be found in Include/object.h. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
   PyObject_VAR_HEAD
   const char *tp_name; /* For printing, in format "<module>.<name>" */
   Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */
   /* Methods to implement standard operations */
   destructor tp_dealloc;
   Py_ssize_t tp_vectorcall_offset;
   getattrfunc tp_getattr;
   setattrfunc tp_setattr;
   PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                    or tp_reserved (Python 3) */
   reprfunc tp_repr;
   /* Method suites for standard classes */
   PyNumberMethods *tp_as_number;
   PySequenceMethods *tp_as_sequence;
   PyMappingMethods *tp_as_mapping;
   /* More standard operations (here for binary compatibility) */
   hashfunc tp_hash;
   ternaryfunc tp_call;
   reprfunc tp_str;
   getattrofunc tp_getattro;
   setattrofunc tp_setattro;
   /* Functions to access object as input/output buffer */
   PyBufferProcs *tp_as_buffer;
   /* Flags to define presence of optional/expanded features */
   unsigned long tp_flags;
   const char *tp_doc; /* Documentation string */
   /* Assigned meaning in release 2.0 */
   /* call function for all accessible objects */
   traverseproc tp_traverse;
   /* delete references to contained objects */
   inquiry tp_clear;
   /* Assigned meaning in release 2.1 */
   /* rich comparisons */
   richcmpfunc tp_richcompare;
   /* weak reference enabler */
   Py_ssize_t tp_weaklistoffset;
```

(suite sur la page suivante)

(suite de la page précédente)

```
/* Iterators */
   getiterfunc tp_iter;
   iternextfunc tp_iternext;
   /* Attribute descriptor and subclassing stuff */
   struct PyMethodDef *tp_methods;
   struct PyMemberDef *tp_members;
   struct PyGetSetDef *tp_getset;
   // Strong reference on a heap type, borrowed reference on a static type
   struct _typeobject *tp_base;
   PyObject *tp_dict;
   descrgetfunc tp_descr_get;
   descrsetfunc tp_descr_set;
   Py_ssize_t tp_dictoffset;
   initproc tp_init;
   allocfunc tp_alloc;
   newfunc tp_new;
   freefunc tp_free; /* Low-level free-memory routine */
   inquiry tp_is_qc; /* For PyObject_IS_GC */
   PyObject *tp_bases;
   PyObject *tp_mro; /* method resolution order */
   PyObject *tp_cache;
   PyObject *tp_subclasses;
   PyObject *tp_weaklist;
   destructor tp_del;
   /* Type attribute cache version tag. Added in version 2.6 */
   unsigned int tp_version_tag;
   destructor tp_finalize;
   vectorcallfunc tp_vectorcall;
   /* bitset of which type-watchers care about this type */
   unsigned char tp_watched;
} PyTypeObject;
```

12.3.3 PyObject Slots

The type object structure extends the PyVarObject structure. The ob_size field is used for dynamic types (created by type_new(), usually called from a class statement). Note that $PyType_Type$ (the metatype) initializes $tp_itemsize$, which means that its instances (i.e. type objects) *must* have the ob_size field.

```
Py_ssize_t PyObject.ob_refcnt
```

Part of the Stable ABI. This is the type object's reference count, initialized to 1 by the PyObject_HEAD_INIT macro. Note that for *statically allocated type objects*, the type's instances (objects whose ob_type points back to the type) do *not* count as references. But for *dynamically allocated type objects*, the instances *do* count as references.

Inheritance:

This field is not inherited by subtypes.

PyTypeObject *PyObject.ob_type

Part of the Stable ABI. This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject_HEAD_INIT macro, and its value should normally be &PyType_Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass NULL to the PyObject_HEAD_INIT macro and to initialize this

field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. $PyType_Ready()$ checks if ob_type is NULL, and if so, initializes it to the ob_type field of the base class. $PyType_Ready()$ will not change this field if it is non-zero.

Inheritance:

This field is inherited by subtypes.

```
PyObject *PyObject._ob_next
PyObject *PyObject._ob_prev
```

These fields are only present when the macro Py_TRACE_REFS is defined (see the configure --with-trace-refs option).

Their initialization to NULL is taken care of by the PyObject_HEAD_INIT macro. For *statically allocated objects*, these fields always remain NULL. For *dynamically allocated objects*, these two fields are used to link the object into a doubly linked list of *all* live objects on the heap.

This could be used for various debugging purposes; currently the only uses are the sys.getobjects() function and to print the objects that are still alive at the end of a run when the environment variable PYTHONDUMPREFS is set.

Inheritance:

These fields are not inherited by subtypes.

12.3.4 PyVarObject Slots

```
Py_ssize_t PyVarObject.ob_size
```

Part of the Stable ABI. For statically allocated type objects, this should be initialized to zero. For dynamically allocated type objects, this field has a special internal meaning.

Inheritance:

This field is not inherited by subtypes.

12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If $PyType_Ready()$ may set a value when the field is set to NULL then there will also be a "Default" section. (Note that many fields set on $PyBaseObject_Type$ and $PyType_Type$ effectively act as defaults.)

```
const char *PyTypeObject.tp_name
```

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the tp_name initializer "P.Q.M.T".

For *dynamically allocated type objects*, this should just be the type name, and the module name explicitly stored in the type dict as the value for key '__module__'.

For *statically allocated type objects*, the *tp_name* field should contain a dot. Everything before the last dot is made accessible as the __module__ attribute, and everything after the last dot is made accessible as the __name__ attribute.

If no dot is present, the entire <code>tp_name</code> field is made accessible as the <code>__name__</code> attribute, and the <code>__module__</code> attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc.

This field must not be NULL. It is the only required field in PyTypeObject() (other than potentially $tp_itemsize$).

Inheritance:

This field is not inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_basicsize
Py_ssize_t PyTypeObject.tp_itemsize
```

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero $tp_itemsize$ field, types with variable-length instances have a non-zero $tp_itemsize$ field. For a type with fixed-length instances, all instances have the same size, given in $tp_basicsize$.

For a type with variable-length instances, the instances must have an ob_size field, and the instance size is $tp_basicsize$ plus N times $tp_itemsize$, where N is the "length" of the object. The value of N is typically stored in the instance's ob_size field. There are exceptions: for example, ints use a negative ob_size to indicate a negative number, and N is $abs(ob_size)$ there. Also, the presence of an ob_size field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful ob_size field).

The basic size includes the fields in the instance declared by the macro <code>PyObject_HEAD</code> or <code>PyObject_VAR_HEAD</code> (whichever is used to declare the instance struct) and this in turn includes the <code>_ob_prev</code> and <code>_ob_next</code> fields if they are present. This means that the only correct way to get an initializer for the <code>tp_basicsize</code> is to use the <code>sizeof</code> operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of $tp_basicsize$. Example: suppose a type implements an array of double. $tp_itemsize$ is sizeof(double). It is the programmer's responsibility that $tp_basicsize$ is a multiple of sizeof(double) (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be NULL.

Inheritance:

These fields are inherited separately by subtypes. If the base type has a non-zero $tp_itemsize$, it is generally not safe to set $tp_itemsize$ to a different non-zero value in a subtype (though this depends on the implementation of the base type).

```
destructor PyTypeObject.tp_dealloc
```

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons None and Ellipsis). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the $Py_DECREF()$ and $Py_XDECREF()$ macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type's tp_free function. If the type is not subtypable (doesn't have the $Py_TPFLAGS_BASETYPE$ flag bit set), it is permissible to call the object deallocator directly instead of via tp_free . The object deallocator should be the one used to allocate the instance; this is normally $PyObject_Del()$ if the instance was allocated using $PyObject_New$ or $PyObject_NewVar$, or $PyObject_GC_Del()$ if the instance was allocated using $PyObject_GC_New$ or $PyObject_GC_NewVar$.

If the type supports garbage collection (has the $Py_TPFLAGS_HAVE_GC$ flag bit set), the destructor should call $PyObject_GC_UnTrack$ () before clearing any member fields.

```
static void foo_dealloc(foo_object *self) {
   PyObject_GC_UnTrack(self);
```

12.3. Objets type 253

(suite sur la page suivante)

(suite de la page précédente)

```
Py_CLEAR(self->ref);
Py_TYPE(self)->tp_free((PyObject *)self);
}
```

Finally, if the type is heap allocated ($Py_TPFLAGS_HEAPTYPE$), the deallocator should release the owned reference to its type object (via $Py_DECREF()$) after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is :

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
    // free references and buffers here
    tp->tp_free(self);
    Py_DECREF(tp);
}
```

Inheritance:

This field is inherited by subtypes.

Py_ssize_t PyTypeObject.tp_vectorcall_offset

An optional offset to a per-instance function that implements calling the object using the *vectorcall protocol*, a more efficient alternative of the simpler tp_call .

This field is only used if the flag Py_TPFLAGS_HAVE_VECTORCALL is set. If so, this must be a positive integer containing the offset in the instance of a vectorcallfunc pointer.

The *vectorcallfunc* pointer may be NULL, in which case the instance behaves as if $PV_TPFLAGS_HAVE_VECTORCALL$ was not set: calling the instance falls back to tp_call .

Any class that sets Py_TPFLAGS_HAVE_VECTORCALL must also set tp_call and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting tp_call to $PyVectorcall_Call$ ().

Modifié dans la version 3.8 : Before version 3.8, this slot was named tp_print. In Python 2.x, it was used for printing to a file. In Python 3.0 to 3.7, it was unused.

Modifié dans la version 3.12: Before version 3.12, it was not recommended for *mutable heap types* to implement the vectorcall protocol. When a user sets __call__ in Python code, only *tp_call* is updated, likely making it inconsistent with the vectorcall function. Since 3.12, setting __call__ will disable vectorcall optimization by clearing the *Py_TPFLAGS_HAVE_VECTORCALL* flag.

Inheritance:

This field is always inherited. However, the *Py_TPFLAGS_HAVE_VECTORCALL* flag is not always inherited. If it's not set, then the subclass won't use *vectorcall*, except when *PyVectorcall_Call* () is explicitly called.

getattrfunc PyTypeObject.tp_getattr

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the $tp_getattro$ function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

```
{\bf Group:} \ tp\_getattr, \ tp\_getattro
```

This field is inherited by subtypes together with $tp_getattro$: a subtype inherits both $tp_getattr$ and $tp_getattro$ from its base type when the subtype's $tp_getattr$ and $tp_getattro$ are both NULL.

```
setattrfunc PyTypeObject.tp_setattr
```

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the $tp_setattro$ function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

```
Group: tp_setattr, tp_setattro
```

This field is inherited by subtypes together with $tp_setattro$: a subtype inherits both $tp_setattr$ and $tp_setattro$ from its base type when the subtype's $tp_setattr$ and $tp_setattro$ are both NULL.

PyAsyncMethods *PyTypeObject.tp_as_async

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

Nouveau dans la version 3.5 : Formerly known as tp_compare and tp_reserved.

Inheritance:

The tp_as_async field is not inherited, but the contained fields are inherited individually.

reprfunc PyTypeObject.tp_repr

An optional pointer to a function that implements the built-in function repr ().

The signature is the same as for PyObject_Repr():

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to eval(), given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '<' and ending with '>' from which both the type and the value of the object can be deduced.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, a string of the form <%s object at %p> is returned, where %s is replaced by the type name, and %p by the object's memory address.

PyNumberMethods *PyTypeObject.tp_as_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

Inheritance:

The tp as number field is not inherited, but the contained fields are inherited individually.

PySequenceMethods **PyTypeObject*.**tp_as_sequence**

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

Inheritance:

The tp_as_sequence field is not inherited, but the contained fields are inherited individually.

PyMappingMethods *PyTypeObject.tp_as_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

Inheritance:

The tp_as_mapping field is not inherited, but the contained fields are inherited individually.

hashfunc PyTypeObject.tp_hash

An optional pointer to a function that implements the built-in function hash ().

The signature is the same as for PyObject Hash():

```
Py_hash_t tp_hash(PyObject *);
```

The value -1 should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return -1.

When this field is not set (and $tp_richcompare$ is not set), an attempt to take the hash of the object raises TypeError. This is the same as setting it to $PyObject_HashNotImplemented()$.

This field can be set explicitly to <code>PyObject_HashNotImplemented()</code> to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of <code>__hash__</code> = <code>None</code> at the Python level, causing <code>isinstance(o, collections.Hashable)</code> to correctly return <code>False</code>. Note that the converse

is also true - setting $_$ hash $_$ = None on a class at the Python level will result in the tp_hash slot being set to $PyObject_HashNotImplemented()$.

Inheritance:

```
Group: tp_hash, tp_richcompare
```

This field is inherited by subtypes together with $tp_richcompare$: a subtype inherits both of $tp_richcompare$ and tp_hash , when the subtype's $tp_richcompare$ and tp_hash are both NULL.

```
ternaryfunc PyTypeObject.tp_call
```

An optional pointer to a function that implements calling the object. This should be NULL if the object is not callable. The signature is the same as for $PyObject_Call()$:

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

Inheritance:

This field is inherited by subtypes.

```
reprfunc PyTypeObject.tp_str
```

An optional pointer to a function that implements the built-in operation str(). (Note that str is a type now, and str() calls the constructor for that type. This constructor calls $PyObject_Str()$ to do the actual work, and $PyObject_Str()$ will call this handler.)

The signature is the same as for PyObject_Str():

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the print () function.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, PyObject_Repr() is called to return a string representation.

getattrofunc PyTypeObject.tp_getattro

An optional pointer to the get-attribute function.

The signature is the same as for PyObject_GetAttr():

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to PyObject_GenericGetAttr(), which implements the normal way of looking for object attributes.

Inheritance:

```
Group: tp_getattr, tp_getattro
```

This field is inherited by subtypes together with $tp_getattr$: a subtype inherits both $tp_getattr$ and $tp_getattr$ from its base type when the subtype's $tp_getattr$ and $tp_getattr$ are both NULL.

Default:

PyBaseObject Type uses PyObject GenericGetAttr().

```
setattrofunc PyTypeObject.tp_setattro
```

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for PyObject SetAttr():

```
int tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to NULL to delete an attribute must be supported. It is usually convenient to set this field to PyObject_GenericSetAttr(), which implements the normal way of setting object attributes.

Inheritance:

```
Group: tp_setattr, tp_setattro
```

This field is inherited by subtypes together with $tp_setattr$: a subtype inherits both $tp_setattr$ and $tp_setattro$ from its base type when the subtype's $tp_setattr$ and $tp_setattro$ are both NULL.

Default:

PyBaseObject_Type uses PyObject_GenericSetAttr().

PyBufferProcs *PyTypeObject.tp_as_buffer

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

Inheritance:

The tp_as_buffer field is not inherited, but the contained fields are inherited individually.

unsigned long PyTypeObject.tp_flags

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via tp_as_number , $tp_as_sequence$, $tp_as_mapping$, and tp_as_buffer) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

Inheritance:

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The <code>Py_TPFLAGS_HAVE_GC</code> flag bit is inherited together with the <code>tp_traverse</code> and <code>tp_clear</code> fields, i.e. if the <code>Py_TPFLAGS_HAVE_GC</code> flag bit is clear in the subtype and the <code>tp_traverse</code> and <code>tp_clear</code> fields in the subtype exist and have <code>NULL</code> values. .. XXX are most flag bits really inherited individually?

Default:

PyBaseObject Type uses Py TPFLAGS DEFAULT | Py TPFLAGS BASETYPE.

Bit Masks:

The following bit masks are currently defined; these can be ORed together using the | operator to form the value of the tp_flags field. The macro $PyType_HasFeature()$ takes a type and a flags value, tp and f, and checks whether $tp->tp_flags$ & f is non-zero.

Py TPFLAGS HEAPTYPE

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using $PyType_FromSpec()$. In this case, the ob_type field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob_type gets INCREF'ed or DECREF'ed).

Inheritance:

???

Py_TPFLAGS_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

Inheritance:

???

Py_TPFLAGS_READY

This bit is set when the type object has been fully initialized by PyType_Ready().

Inheritance:

???

Py_TPFLAGS_READYING

This bit is set while PyType_Ready () is in the process of initializing the type object.

Inheritance:

???

Py_TPFLAGS_HAVE_GC

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using $PyObject_GC_New$ and destroyed using $PyObject_GC_Del()$. More information in section Supporting Cyclic Garbage Collection. This bit also implies that the GC-related fields $tp_traverse$ and tp_clear are present in the type object.

Inheritance:

Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear

The $Py_TPFLAGS_HAVE_GC$ flag bit is inherited together with the $tp_traverse$ and tp_clear fields, i.e. if the $Py_TPFLAGS_HAVE_GC$ flag bit is clear in the subtype and the $tp_traverse$ and tp_clear fields in the subtype exist and have NULL values.

Py_TPFLAGS_DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: Py_TPFLAGS_HAVE_STACKLESS_EXTENSION.

Inheritance:

???

Py TPFLAGS METHOD DESCRIPTOR

This bit indicates that objects behave like unbound methods.

If this flag is set for type (meth), then:

- meth.__get__(obj, cls) (*args, **kwds) (with obj not None) must be equivalent to meth(obj, *args, **kwds).

This flag enables an optimization for typical method calls like obj.meth(): it avoids creating a temporary "bound method" object for obj.meth.

Nouveau dans la version 3.8.

Inheritance:

This flag is never inherited by types without the $Py_TPFLAGS_IMMUTABLETYPE$ flag set. For extension types, it is inherited whenever tp_descr_get is inherited.

Py_TPFLAGS_MANAGED_DICT

This bit indicates that instances of the class have a __dict__ attribute, and that the space for the dictionary is managed by the VM.

If this flag is set, Py_TPFLAGS_HAVE_GC should also be set.

Nouveau dans la version 3.12.

Inheritance:

This flag is inherited unless the $tp_dictoffset$ field is set in a superclass.

Py_TPFLAGS_MANAGED_WEAKREF

This bit indicates that instances of the class should be weakly referenceable.

Nouveau dans la version 3.12.

Inheritance:

This flag is inherited unless the $tp_weaklistoffset$ field is set in a superclass.

Py_TPFLAGS_ITEMS_AT_END

Only usable with variable-size types, i.e. ones with non-zero tp_itemsize.

Indicates that the variable-sized portion of an instance of this type is at the end of the instance's memory area, at an offset of Py_TYPE (obj) ->tp_basicsize (which may be different in each subclass).

When setting this flag, be sure that all superclasses either use this memory layout, or are not variable-sized. Python does not check this.

Nouveau dans la version 3.12.

Inheritance:

This flag is inherited.

Py_TPFLAGS_LONG_SUBCLASS

Py_TPFLAGS_LIST_SUBCLASS

Py TPFLAGS TUPLE SUBCLASS

Py_TPFLAGS_BYTES_SUBCLASS

Py_TPFLAGS_UNICODE_SUBCLASS

Py_TPFLAGS_DICT_SUBCLASS

Py_TPFLAGS_BASE_EXC_SUBCLASS

Py_TPFLAGS_TYPE_SUBCLASS

These flags are used by functions such as $PyLong_Check$ () to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like $PyObject_IsInstance$ (). Custom types that inherit from built-ins should have their tp_flags set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

Py_TPFLAGS_HAVE_FINALIZE

This bit is set when the tp_finalize slot is present in the type structure.

Nouveau dans la version 3.4.

Obsolète depuis la version 3.8 : This flag isn't necessary anymore, as the interpreter assumes the $tp_finalize$ slot is always present in the type structure.

Py_TPFLAGS_HAVE_VECTORCALL

This bit is set when the class implements the *vectorcall protocol*. See tp_vectorcall_offset for details.

Inheritance:

This bit is inherited if tp_call is also inherited.

Nouveau dans la version 3.9.

Modifié dans la version 3.12: This flag is now removed from a class when the class's __call__() method is reassigned.

This flag can now be inherited by mutable classes.

Py_TPFLAGS_IMMUTABLETYPE

This bit is set for type objects that are immutable: type attributes cannot be set nor deleted.

PyType_Ready() automatically applies this flag to static types.

Inheritance:

This flag is not inherited.

Nouveau dans la version 3.10.

Py_TPFLAGS_DISALLOW_INSTANTIATION

Disallow creating instances of the type : set tp_new to NULL and don't create the $__new_$ key in the type dictionary.

The flag must be set before creating the type, not after. For example, it must be set before $PyType_Ready()$ is called on the type.

The flag is set automatically on *static types* if tp_base is NULL or &PyBaseObject_Type and tp_new is NULL.

Inheritance:

This flag is not inherited. However, subclasses will not be instantiable unless they provide a non-NULL tp new (which is only possible via the C API).

Note: To disallow instantiating a class directly but allow instantiating its subclasses (e.g. for an *abstract base class*), do not use this flag. Instead, make tp_new only succeed for subclasses.

Nouveau dans la version 3.10.

Py_TPFLAGS_MAPPING

This bit indicates that instances of the class may match mapping patterns when used as the subject of a match block. It is automatically set when registering or subclassing collections.abc.Mapping, and unset when registering collections.abc.Sequence.

Note: Py_TPFLAGS_MAPPING and Py_TPFLAGS_SEQUENCE are mutually exclusive; it is an error to enable both flags simultaneously.

Inheritance:

This flag is inherited by types that do not already set Py_TPFLAGS_SEQUENCE.

Voir aussi:

PEP 634 -- Structural Pattern Matching: Specification

Nouveau dans la version 3.10.

Py_TPFLAGS_SEQUENCE

This bit indicates that instances of the class may match sequence patterns when used as the subject of a match block. It is automatically set when registering or subclassing collections.abc.Sequence, and unset when registering collections.abc.Mapping.

Note: Py_TPFLAGS_MAPPING and Py_TPFLAGS_SEQUENCE are mutually exclusive; it is an error to enable both flags simultaneously.

Inheritance:

This flag is inherited by types that do not already set Py_TPFLAGS_MAPPING.

Voir aussi:

PEP 634 -- Structural Pattern Matching: Specification

Nouveau dans la version 3.10.

Py_TPFLAGS_VALID_VERSION_TAG

Internal. Do not set or unset this flag. To indicate that a class has changed call PyType_Modified()

Avertissement : This flag is present in header files, but is an internal feature and should not be used. It will be removed in a future version of CPython

const char *PyTypeObject.tp_doc

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the __doc__ attribute on the type and instances of the type.

Inheritance:

This field is *not* inherited by subtypes.

traverseproc PyTypeObject.tp_traverse

An optional pointer to a traversal function for the garbage collector. This is only used if the <code>Py_TPFLAGS_HAVE_GC</code> flag bit is set. The signature is :

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

The $tp_traverse$ pointer is used by the garbage collector to detect reference cycles. A typical implementation of a $tp_traverse$ function simply calls $Py_VISIT()$ on each of the instance's members that are Python objects that the instance owns. For example, this is function local_traverse() from the _thread extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that $Py_VISIT()$ is called only on those members that can participate in reference cycles. Although there is also a self->key member, it can only be NULL or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the gc module's get_referents() function will include it.

Avertissement: When implementing $tp_traverse$, only the members that the instance *owns* (by having *strong references* to them) must be visited. For instance, if an object supports weak references via the $tp_weaklist$ slot, the pointer supporting the linked list (what $tp_weaklist$ points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that Py_VISIT () requires the *visit* and *arg* parameters to local_traverse() to have these specific names; don't name them just anything.

Instances of *heap-allocated types* hold a reference to their type. Their traversal function must therefore either visit $Py_TYPE\ (self)$, or delegate this responsibility by calling tp_traverse of another heap-allocated type (such as a heap-allocated superclass). If they do not, the type object may not be garbage-collected.

Modifié dans la version 3.9: Heap-allocated types are expected to visit Py_TYPE (self) in tp_traverse. In earlier versions of Python, due to bug 40217, doing this may lead to crashes in subclasses.

Inheritance:

```
Group:Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with tp_clear and the $Py_TPFLAGS_HAVE_GC$ flag bit: the flag bit, $tp_traverse$, and tp_clear are all inherited from the base type if they are all zero in the subtype.

```
inquiry PyTypeObject.tp_clear
```

An optional pointer to a clear function for the garbage collector. This is only used if the Py_TPFLAGS_HAVE_GC flag bit is set. The signature is :

```
int tp_clear(PyObject *);
```

The tp_clear member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all tp_clear functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a tp_clear function. For example, the tuple type does not implement a tp_clear function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the tp_clear functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing tp_clear .

Implementations of tp_clear should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to NULL, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->kw);
    return 0;
}
```

The $Py_CLEAR()$ macro should be used, because clearing references is delicate: the reference to the contained object must not be released (via $Py_DECREF()$) until after the pointer to the contained object is set to NULL. This is because releasing the reference may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference *self* again, it's important that the pointer to the contained object be NULL at that time, so that *self* knows the contained object can no longer be used. The $Py_CLEAR()$ macro performs the operations in a safe order.

Note that tp_clear is not always called before an instance is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and $tp_dealloc$ is called directly.

Because the goal of tp_clear functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's $tp_dealloc$ function to invoke tp_clear . More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

Inheritance:

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with $tp_traverse$ and the $Py_TPFLAGS_HAVE_GC$ flag bit: the flag bit, $tp_traverse$, and tp_clear are all inherited from the base type if they are all zero in the subtype.

richcmpfunc PyTypeObject.tp_richcompare

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by PyTypeObject.

The function should return the result of the comparison (usually Py_True or Py_False). If the comparison is undefined, it must return Py_NotImplemented, if another error occurred it must return NULL and set an exception condition.

The following constants are defined to be used as the third argument for $tp_richcompare$ and for $PyObject_RichCompare$ ():

Constante	Comparaison
Py_LT	<
Py_LE	<=
Py_EQ	==
Py_NE	!=
PY_GT	>
Py_GE	>=

The following macro is defined to ease writing rich comparison functions:

Py_RETURN_RICHCOMPARE (VAL_A, VAL_B, op)

Return Py_True or Py_False from the function, depending on the result of a comparison. VAL_A and VAL_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for $PyObject_RichCompare()$.

The returned value is a new *strong reference*.

On error, sets an exception and returns NULL from the function.

Nouveau dans la version 3.7.

Inheritance:

Group: tp_hash, tp_richcompare

This field is inherited by subtypes together with tp_hash : a subtype inherits $tp_richcompare$ and tp_hash when the subtype's $tp_richcompare$ and tp_hash are both NULL.

Default:

PyBaseObject_Type provides a $tp_richcompare$ implementation, which may be inherited. However, if only tp_hash is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

Py_ssize_t PyTypeObject.tp_weaklistoffset

While this field is still supported, $Py_TPFLAGS_MANAGED_WEAKREF$ should be used instead, if at all possible. If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by $PyObject_ClearWeakRefs$ () and the $PyWeakref_*$ functions. The instance structure needs to include a field of type PyObject* which is initialized to NULL.

Do not confuse this field with $tp_weaklist$; that is the list head for weak references to the type object itself.

It is an error to set both the $\textit{Py_TPFLAGS_MANAGED_WEAKREF}$ bit and $\textit{tp_weaklist}$.

Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via $tp_weaklistoffset$, this should not be a problem.

Default:

If the Py_TPFLAGS_MANAGED_WEAKREF bit is set in the tp_dict field, then tp_weaklistoffset will be set to a negative value, to indicate that it is unsafe to use this field.

getiterfunc PyTypeObject.tp_iter

An optional pointer to a function that returns an *iterator* for the object. Its presence normally signals that the instances of this type are *iterable* (although sequences may be iterable without this function).

This function has the same signature as PyObject_GetIter():

```
PyObject *tp_iter(PyObject *self);
```

Inheritance:

This field is inherited by subtypes.

iternextfunc PyTypeObject.tp_iternext

An optional pointer to a function that returns the next item in an *iterator*. The signature is :

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return <code>NULL</code>; a <code>StopIteration</code> exception may or may not be set. When another error occurs, it must return <code>NULL</code> too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the tp_iter function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as PyIter_Next ().

Inheritance:

This field is inherited by subtypes.

```
struct PyMethodDef *PyTypeObject.tp_methods
```

An optional pointer to a static NULL-terminated array of PyMethodDef structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a method descriptor.

Inheritance:

This field is not inherited by subtypes (methods are inherited through a different mechanism).

```
struct PyMemberDef *PyTypeObject.tp_members
```

An optional pointer to a static NULL-terminated array of PyMemberDef structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a member descriptor.

Inheritance:

This field is not inherited by subtypes (members are inherited through a different mechanism).

```
struct PyGetSetDef *PyTypeObject.tp_getset
```

An optional pointer to a static NULL-terminated array of PyGetSetDef structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a getset descriptor.

Inheritance:

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

PyTypeObject *PyTypeObject.tp_base

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

Note: Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be "address constants". Function designators like <code>PyType_GenericNew()</code>, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary '&' operator applied to a non-static variable like PyBaseObject_Type is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, tp_base should be set in the extension module's init function.

Inheritance:

This field is not inherited by subtypes (obviously).

Default:

This field defaults to &PyBaseObject_Type (which to Python programmers is known as the type object).

PyObject *PyTypeObject.tp_dict

The type's dictionary is stored here by PyType_Ready().

This field should normally be initialized to NULL before PyType_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once $PyType_Ready()$ has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like __add__()). Once initialization for the type has finished, this field should be treated as read-only.

Some types may not store their dictionary in this slot. Use $PyType_GetDict()$ to retrieve the dictionary for an arbitrary type.

Modifié dans la version 3.12: Internals detail: For static builtin types, this is always NULL. Instead, the dict for such types is stored on PyInterpreterState. Use PyType_GetDict() to get the dict for an arbitrary type.

Inheritance:

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

Default:

If this field is NULL, PyType_Ready () will assign a new dictionary to it.

Avertissement : It is not safe to use $PyDict_SetItem()$ on or otherwise modify tp_dict with the dictionary C-API.

descrgetfunc PyTypeObject.tp_descr_get

An optional pointer to a "descriptor get" function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

Inheritance:

This field is inherited by subtypes.

```
descrsetfunc PyTypeObject.tp_descr_set
```

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to NULL to delete the value.

Inheritance:

This field is inherited by subtypes.

Py_ssize_t PyTypeObject.tp_dictoffset

While this field is still supported, Py_TPFLAGS_MANAGED_DICT should be used instead, if at all possible.

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by $PyObject_GenericGetAttr()$.

Do not confuse this field with tp_dict ; that is the dictionary for attributes of the type object itself.

The value specifies the offset of the dictionary from the start of the instance structure.

The $tp_dictoffset$ should be regarded as write-only. To get the pointer to the dictionary call $PyObject_GenericGetDict()$. Calling $PyObject_GenericGetDict()$ may need to allocate memory for the dictionary, so it is may be more efficient to call $PyObject_GetAttr()$ when accessing an attribute on the object.

It is an error to set both the Py_TPFLAGS_MANAGED_WEAKREF bit and tp_dictoffset.

Inheritance:

This field is inherited by subtypes. A subtype should not override this offset; doing so could be unsafe, if C code tries to access the dictionary at the previous offset. To properly support inheritance, use Py_TPFLAGS_MANAGED_DICT.

Default:

This slot has no default. For *static types*, if the field is NULL then no ___dict__ gets created for instances.

If the $Py_TPFLAGS_MANAGED_DICT$ bit is set in the tp_dict field, then $tp_dictoffset$ will be set to -1, to indicate that it is unsafe to use this field.

initproc PyTypeObject.tp_init

An optional pointer to an instance initialization function.

This function corresponds to the __init__() method of classes. Like __init__(), it is possible to create an instance without calling __init__(), and it is possible to reinitialize an instance by calling its __init__() method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to __init__().

The tp_init function, if not NULL, is called when an instance is created normally by calling its type, after the type's tp_new function has returned an instance of the type. If the tp_new function returns an instance of some other type that is not a subtype of the original type, no tp_init function is called; if tp_new returns an instance of a subtype of the original type, the subtype's tp_init is called.

Returns 0 on success, -1 and sets an exception on error.

Inheritance:

This field is inherited by subtypes.

Default:

For *static types* this field does not have a default.

allocfunc PyTypeObject.tp_alloc

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

Default

For dynamic subtypes, this field is always set to $PyType_GenericAlloc()$, to force a standard heap allocation strategy.

For static subtypes, PyBaseObject_Type uses PyType_GenericAlloc(). That is the recommended value for all statically defined types.

newfunc PyTypeObject.tp_new

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwds);
```

The *subtype* argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that *subtype* doesn't have to equal the type whose tp_new function is called; it may be a subtype of that type (but not an unrelated type).

The tp_new function should call subtype->tp_alloc(subtype, nitems) to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the tp_init handler. A good rule of thumb is that for immutable types, all initialization should take place in tp_new , while for mutable types, most initialization should be deferred to tp_init .

Set the Py_TPFLAGS_DISALLOW_INSTANTIATION flag to disallow creating instances of the type in Python.

Inheritance:

This field is inherited by subtypes, except it is not inherited by *static types* whose tp_base is NULL or &PyBaseObject_Type.

Default:

For *static types* this field has no default. This means if the slot is defined as NULL, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

```
freefunc PyTypeObject.tp_free
```

An optional pointer to an instance deallocation function. Its signature is :

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is PyObject_Free().

Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

Default:

In dynamic subtypes, this field is set to a deallocator suitable to match $PyType_GenericAlloc()$ and the value of the $Py_TPFLAGS_HAVE_GC$ flag bit.

For static subtypes, PyBaseObject_Type uses PyObject_Del().

```
inquiry PyTypeObject.tp_is_gc
```

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's tp_flags field, and check the $Py_TPFLAGS_HAVE_GC$ flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype, P_YType_Type , defines this function to distinguish between statically and *dynamically allocated types*.)

Inheritance:

This field is inherited by subtypes.

Default:

This slot has no default. If this field is NULL, Py_TPFLAGS_HAVE_GC is used as the functional equivalent.

```
PyObject *PyTypeObject.tp_bases
```

Tuple of base types.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is <code>initialized</code>. For dynamically created classes, the <code>Py_tp_bases</code> <code>slot</code> can be used instead of the <code>bases</code> argument of <code>PyType FromSpecWithBases()</code>. The argument form is preferred.

Avertissement: Multiple inheritance does not work well for statically defined types. If you set tp_bases to a tuple, Python will not raise an error, but some slots will only be inherited from the first base.

Inheritance:

This field is not inherited.

PyObject *PyTypeObject.tp_mro

Tuple containing the expanded set of base types, starting with the type itself and ending with object, in Method Resolution Order.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is <code>initialized</code>.

Inheritance:

This field is not inherited; it is calculated fresh by PyType_Ready ().

PyObject *PyTypeObject.tp_cache

Unused. Internal use only.

Inheritance:

This field is not inherited.

```
void *PyTypeObject.tp_subclasses
```

A collection of subclasses. Internal use only. May be an invalid pointer.

To get a list of subclasses, call the Python method __subclasses__().

Modifié dans la version 3.12 : For some types, this field does not hold a valid PyObject*. The type was changed to void* to indicate this.

Inheritance:

This field is not inherited.

PyObject *PyTypeObject.tp_weaklist

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

Modifié dans la version 3.12: Internals detail: For the static builtin types this is always NULL, even if weakrefs are added. Instead, the weakrefs for each are stored on PyInterpreterState. Use the public C-API or the internal _PyObject_GET_WEAKREFS_LISTPTR() macro to avoid the distinction.

Inheritance:

This field is not inherited.

```
destructor PyTypeObject.tp_del
```

This field is deprecated. Use $tp_finalize$ instead.

```
unsigned int PyTypeObject.tp_version_tag
```

Used to index into the method cache. Internal use only.

Inheritance:

This field is not inherited.

```
destructor PyTypeObject.tp_finalize
```

An optional pointer to an instance finalization function. Its signature is :

```
void tp_finalize(PyObject *self);
```

If $tp_finalize$ is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

tp_finalize should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);

    /* ... */

    /* Restore the saved exception. */
    PyErr_Restore(error_type, error_value, error_traceback);
}
```

Also, note that, in a garbage collected Python, $tp_dealloc$ may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which $tp_dealloc$ is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called $tp_dealloc$ will not violate any assumptions of the library.

Inheritance:

This field is inherited by subtypes.

Nouveau dans la version 3.4.

Modifié dans la version 3.8 : Before version 3.8 it was necessary to set the Py_TPFLAGS_HAVE_FINALIZE flags bit in order for this field to be used. This is no longer required.

Voir aussi:

"Safe object finalization" (PEP 442)

```
vectorcallfunc PyTypeObject.tp_vectorcall
```

Vectorcall function to use for calls of this type object. In other words, it is used to implement *vectorcall* for type.__call__. If tp_vectorcall is NULL, the default call implementation using __new__() and __init__() is used.

Inheritance:

This field is never inherited.

Nouveau dans la version 3.9: (the field exists since 3.8 but it's only used since 3.9)

```
unsigned char PyTypeObject.tp_watched
```

Internal. Do not use.

Nouveau dans la version 3.12.

12.3.6 Static Types

Traditionally, types defined in C code are *static*, that is, a static PyTypeObject structure is defined directly in code and initialized using $PyType_Ready()$.

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state. Also, since PyTypeObject is only part of the *Limited API* as an opaque struct, any extension modules using static types must be compiled for a specific Python minor version.

12.3.7 Heap Types

An alternative to *static types* is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's class statement. Heap types have the Py_TPFLAGS_HEAPTYPE flag set.

```
This is done by filling a PyType\_Spec structure and calling PyType\_FromSpec(), PyType\_FromSpecWithBases(), PyType\_FromModuleAndSpec(), or PyType\_FromMetaclass().
```

12.4 Number Object Structures

type PyNumberMethods

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Number Protocol* section.

Here is the structure definition:

```
typedef struct {
    binaryfunc nb_add;
     binaryfunc nb_subtract;
     binaryfunc nb_multiply;
     binaryfunc nb_remainder;
    binaryfunc nb_divmod;
     ternaryfunc nb_power;
     unaryfunc nb_negative;
     unaryfunc nb_positive;
     unaryfunc nb_absolute;
     inquiry nb_bool;
     unaryfunc nb_invert;
     binaryfunc nb_lshift;
     binaryfunc nb_rshift;
     binaryfunc nb_and;
     binaryfunc nb_xor;
     binaryfunc nb_or;
     unaryfunc nb_int;
     void *nb_reserved;
     unaryfunc nb_float;
     binaryfunc nb_inplace_add;
     binaryfunc nb_inplace_subtract;
     binaryfunc nb_inplace_multiply;
     binaryfunc nb_inplace_remainder;
     ternaryfunc nb_inplace_power;
     binaryfunc nb_inplace_lshift;
     binaryfunc nb_inplace_rshift;
     binaryfunc nb_inplace_and;
     binaryfunc nb_inplace_xor;
     binaryfunc nb_inplace_or;
     binaryfunc nb_floor_divide;
     binaryfunc nb_true_divide;
     binaryfunc nb_inplace_floor_divide;
     binaryfunc nb_inplace_true_divide;
     unaryfunc nb_index;
     binaryfunc nb_matrix_multiply;
```

(suite sur la page suivante)

(suite de la page précédente)

```
binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;
```

Note: Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return Py_NotImplemented, if another error occurred they must return NULL and set an exception.

Note: The *nb_reserved* field should always be NULL. It was previously called *nb_long*, and was renamed in Python 3.0.1.

```
binaryfunc PyNumberMethods.nb_add
binaryfunc PyNumberMethods.nb_subtract
binaryfunc PyNumberMethods.nb_multiply
binaryfunc PyNumberMethods.nb_remainder
binaryfunc PyNumberMethods.nb_divmod
ternaryfunc PyNumberMethods.nb_power
unaryfunc PyNumberMethods.nb_negative
unaryfunc PyNumberMethods.nb_positive
unaryfunc PyNumberMethods.nb_absolute
inquiry PyNumberMethods.nb_bool
unaryfunc PyNumberMethods.nb_invert
binaryfunc PyNumberMethods.nb_lshift
binaryfunc PyNumberMethods.nb_rshift
binaryfunc PyNumberMethods.nb_and
binaryfunc PyNumberMethods.nb_xor
binaryfunc PyNumberMethods.nb or
unaryfunc PyNumberMethods.nb int
void *PyNumberMethods.nb reserved
unaryfunc PyNumberMethods.nb_float
binaryfunc PyNumberMethods.nb_inplace_add
binaryfunc PyNumberMethods.nb_inplace_subtract
binaryfunc PyNumberMethods.nb_inplace_multiply
```

```
binaryfunc PyNumberMethods.nb_inplace_remainder

ternaryfunc PyNumberMethods.nb_inplace_power

binaryfunc PyNumberMethods.nb_inplace_lshift

binaryfunc PyNumberMethods.nb_inplace_rshift

binaryfunc PyNumberMethods.nb_inplace_and

binaryfunc PyNumberMethods.nb_inplace_xor

binaryfunc PyNumberMethods.nb_inplace_or

binaryfunc PyNumberMethods.nb_floor_divide

binaryfunc PyNumberMethods.nb_true_divide

binaryfunc PyNumberMethods.nb_inplace_floor_divide

binaryfunc PyNumberMethods.nb_inplace_true_divide

unaryfunc PyNumberMethods.nb_index

binaryfunc PyNumberMethods.nb_index

binaryfunc PyNumberMethods.nb_inplace_matrix_multiply

binaryfunc PyNumberMethods.nb_inplace_matrix_multiply
```

12.5 Mapping Object Structures

type PyMappingMethods

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members :

lenfunc PyMappingMethods.mp_length

This function is used by $PyMapping_Size()$ and $PyObject_Size()$, and has the same signature. This slot may be set to NULL if the object has no defined length.

binaryfunc PyMappingMethods.mp_subscript

This function is used by $PyObject_GetItem()$ and $PySequence_GetSlice()$, and has the same signature as $PyObject_GetItem()$. This slot must be filled for the $PyMapping_Check()$ function to return 1, it can be NULL otherwise.

objobjargproc PyMappingMethods.mp_ass_subscript

This function is used by <code>PyObject_SetItem()</code>, <code>PyObject_DelItem()</code>, <code>PySequence_SetSlice()</code> and <code>PySequence_DelSlice()</code>. It has the same signature as <code>PyObject_SetItem()</code>, but <code>v</code> can also be set to <code>NULL</code> to delete an item. If this slot is <code>NULL</code>, the object does not support item assignment and deletion.

12.6 Sequence Object Structures

type PySequenceMethods

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

lenfunc PySequenceMethods.sq length

This function is used by PySequence_Size() and PyObject_Size(), and has the same signature. It is also used for handling negative indices via the sq_item and the sq_ass_item slots.

binaryfunc PySequenceMethods.sq_concat

This function is used by PySequence_Concat () and has the same signature. It is also used by the + operator, after trying the numeric addition via the nb add slot.

ssizeargfunc PySequenceMethods.sq_repeat

This function is used by PySequence_Repeat () and has the same signature. It is also used by the * operator, after trying numeric multiplication via the nb_multiply slot.

ssizeargfunc PySequenceMethods.sq_item

This function is used by $PySequence_GetItem()$ and has the same signature. It is also used by $PyObject_GetItem()$, after trying the subscription via the $mp_subscript$ slot. This slot must be filled for the $PySequence_Check()$ function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the sq_length slot is filled, it is called and the sequence length is used to compute a positive index which is passed to sq_item . If sq_length is NULL, the index is passed as is to the function.

ssizeobjargproc PySequenceMethods.sq_ass_item

This function is used by <code>PySequence_SetItem()</code> and has the same signature. It is also used by <code>PyObject_SetItem()</code> and <code>PyObject_DelItem()</code>, after trying the item assignment and deletion via the <code>mp_ass_subscript</code> slot. This slot may be left to <code>NULL</code> if the object does not support item assignment and deletion.

objobjproc PySequenceMethods.sq contains

This function may be used by <code>PySequence_Contains()</code> and has the same signature. This slot may be left to <code>NULL</code>, in this case <code>PySequence_Contains()</code> simply traverses the sequence until it finds a match.

binaryfunc PySequenceMethods.sq_inplace_concat

This function is used by $PySequence_InPlaceConcat()$ and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case $PySequence_InPlaceConcat()$ will fall back to $PySequence_Concat()$. It is also used by the augmented assignment +=, after trying numeric in-place addition via the $nb_inplace_add$ slot.

ssizeargfunc PySequenceMethods.sq_inplace_repeat

This function is used by $PySequence_InPlaceRepeat()$ and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case $PySequence_InPlaceRepeat()$ will fall back to $PySequence_Repeat()$. It is also used by the augmented assignment *=, after trying numeric in-place multiplication via the $nb_inplace_multiply$ slot.

12.7 Buffer Object Structures

type PyBufferProcs

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

getbufferproc PyBufferProcs.bf_getbuffer

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps :

- (1) Check if the request can be met. If not, raise BufferError, set view->obj to NULL and return -1.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set view->obj to exporter and increment view->obj.
- (5) Return 0.

If exporter is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets view->obj to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, view->obj will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the *Py_buffer* structure belongs to the exporter and must remain valid until there are no consumers left. *format*, *shape*, *strides*, *suboffsets* and *internal* are read-only for the consumer.

 $PyBuffer_FillInfo()$ provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject_GetBuffer() is the interface for the consumer that wraps this function.

releasebufferproc PyBufferProcs.bf_releasebuffer

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, PyBufferProcs. $bf_releasebuffer$ may be NULL. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is 0, free all memory associated with view.

The exporter MUST use the <code>internal</code> field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the <code>view</code> argument.

This function MUST NOT decrement view->obj, since that is done automatically in <code>PyBuffer_Release()</code> (this scheme is useful for breaking reference cycles).

PyBuffer Release() is the interface for the consumer that wraps this function.

12.8 Async Object Structures

Nouveau dans la version 3.5.

type PyAsyncMethods

This structure holds pointers to the functions required to implement *awaitable* and *asynchronous iterator* objects. Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
    sendfunc am_send;
} PyAsyncMethods;
```

unaryfunc PyAsyncMethods.am_await

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an *iterator*, i.e. PyIter_Check() must return 1 for it.

This slot may be set to NULL if an object is not an awaitable.

```
unaryfunc PyAsyncMethods.am_aiter
```

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an asynchronous iterator object. See __anext__ () for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

```
unaryfunc PyAsyncMethods.am_anext
```

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an awaitable object. See __anext__ () for details. This slot may be set to NULL.

```
sendfunc PyAsyncMethods.am_send
```

The signature of this function is:

```
PySendResult am_send(PyObject *self, PyObject *arg, PyObject **result);
```

See PyIter_Send() for details. This slot may be set to NULL.

Nouveau dans la version 3.10.

12.9 Slot Type typedefs

```
typedef PyObject *(*allocfunc)(PyTypeObject *cls, Py_ssize_t nitems)
```

Part of the Stable ABI. The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with ob_refcnt set to 1 and ob_type set to the type argument. If the type's $tp_itemsize$ is non-zero, the object's ob_size field should be initialized to *nitems* and the length of the allocated memory block should be $tp_basicsize + nitems*tp_itemsize$, rounded up to a multiple of sizeof(void*); otherwise, *nitems* is not used and the length of the block should be $tp_basicsize$.

```
be done by tp_new.
typedef void (*destructor)(PyObject*)
     Part of the Stable ABI.
typedef void (*freefunc)(void*)
     See tp_free.
typedef PyObject *(*newfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_new.
typedef int (*initproc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_init.
typedef PyObject *(*reprfunc)(PyObject*)
     Part of the Stable ABI. See tp_repr.
typedef PyObject *(*getattrfunc)(PyObject *self, char *attr)
     Part of the Stable ABI. Return the value of the named attribute for the object.
typedef int (*setattrfunc)(PyObject *self, char *attr, PyObject *value)
     Part of the Stable ABI. Set the value of the named attribute for the object. The value argument is set to NULL to
     delete the attribute.
typedef PyObject *(*getattrofunc)(PyObject *self, PyObject *attr)
     Part of the Stable ABI. Return the value of the named attribute for the object.
     See tp_getattro.
typedef int (*setattrofunc)(PyObject *self, PyObject *attr, PyObject *value)
     Part of the Stable ABI. Set the value of the named attribute for the object. The value argument is set to NULL to
     delete the attribute.
     See tp_setattro.
typedef PyObject *(*descrgetfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_descr_get.
typedef int (*descrsetfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_descr_set.
typedef Py_hash_t (*hashfunc)(PyObject*)
     Part of the Stable ABI. See tp_hash.
typedef PyObject *(*richcmpfunc)(PyObject*, PyObject*, int)
     Part of the Stable ABI. See tp_richcompare.
typedef PyObject *(*getiterfunc)(PyObject*)
     Part of the Stable ABI. See tp_iter.
typedef PyObject *(*iternextfunc)(PyObject*)
     Part of the Stable ABI. See tp_iternext.
typedef Py_ssize_t (*lenfunc)(PyObject*)
     Part of the Stable ABI.
typedef int (*getbufferproc)(PyObject*, Py_buffer*, int)
     Part of the Stable ABI since version 3.12.
```

This function should not do any other instance initialization, not even to allocate additional memory; that should

```
typedef void (*releasebufferproc)(PyObject*, Py_buffer*)
     Part of the Stable ABI since version 3.12.
typedef PyObject *(*unaryfunc)(PyObject*)
     Part of the Stable ABI.
typedef PyObject *(*binaryfunc)(PyObject*, PyObject*)
     Part of the Stable ABI.
typedef PySendResult (*sendfunc)(PyObject*, PyObject*, PyObject**)
     See am_send.
typedef PyObject *(*ternaryfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI.
typedef PyObject *(*ssizeargfunc)(PyObject*, Py_ssize_t)
     Part of the Stable ABI.
typedef int (*ssizeobjargproc)(PyObject*, Py_ssize_t, PyObject*)
     Part of the Stable ABI.
typedef int (*objobjproc)(PyObject*, PyObject*)
     Part of the Stable ABI.
typedef int (*objobjargproc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI.
```

12.10 Exemples

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see defining-new-types and new-types-topics.

A basic static type:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

12.10. Exemples 277

(suite sur la page suivante)

(suite de la page précédente)

```
/* tp_itemsize */
    0,
                                     /* tp_dealloc */
    (destructor)myobj_dealloc,
                                     /* tp_vectorcall_offset */
                                      /* tp_getattr */
    0,
                                      /* tp_setattr */
    0,
                                      /* tp_as_async */
    (reprfunc)myobj_repr,
                                     /* tp_repr */
                                     /* tp_as_number */
    0,
    0,
                                      /* tp_as_sequence */
    0,
                                      /* tp_as_mapping */
    0,
                                      /* tp_hash */
                                      /* tp_call */
    0,
    0,
                                     /* tp_str */
                                     /* tp_getattro */
    0,
                                      /* tp_setattro */
    0,
                                      /* tp_as_buffer */
    0,
                                      /* tp_flags */
    0,
                                      /* tp_doc */
   PyDoc_STR("My objects"),
                                      /* tp_traverse */
    0,
                                      /* tp_clear */
    0,
                                      /* tp_richcompare */
    0.
                                      /* tp_weaklistoffset */
    0,
                                      /* tp_iter */
    0,
                                      /* tp_iternext */
    0,
                                     /* tp_methods */
    0,
                                     /* tp_members */
    0,
                                     /* tp_getset */
                                     /* tp_base */
    0,
                                     /* tp_dict */
    0.
                                     /* tp_descr_get */
    0,
                                     /* tp_descr_set */
    0,
                                     /* tp_dictoffset */
    0,
    0,
                                     /* tp_init */
                                      /* tp_alloc */
    0,
   myobj_new,
                                      /* tp_new */
};
```

A type that supports weakrefs, instance dicts, and hashing:

```
typedef struct {
   PyObject_HEAD
   const char *data;
} MyObject;
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE |
         Py_TPFLAGS_HAVE_GC | Py_TPFLAGS_MANAGED_DICT |
        Py_TPFLAGS_MANAGED_WEAKREF,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
```

(suite sur la page suivante)

(suite de la page précédente)

```
.tp_repr = (reprfunc)myobj_repr,
.tp_hash = (hashfunc)myobj_hash,
.tp_richcompare = PyBaseObject_Type.tp_richcompare,
};
```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func) using Py_TPFLAGS_DISALLOW_INSTANTIATION flag:

```
typedef struct {
    PyUnicodeObject raw;
    char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = PyDoc_STR("my custom str"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_DISALLOW_INSTANTIATION,
    .tp_repr = (reprfunc)myobj_repr,
};
```

The simplest *static type* with fixed-length instances :

```
typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest *static type* with variable-length instances:

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};
```

12.10. Exemples 279

12.11 Supporting Cyclic Garbage Collection

Python's support for detecting and collecting garbage which involves circular references requires support from object types which are "containers" for other objects which may also be containers. Types which do not store references to other objects, or which only store references to atomic types (such as numbers or strings), do not need to provide any explicit support for garbage collection.

To create a container type, the tp_flags field of the type object must include the $Py_TPFLAGS_HAVE_GC$ and provide an implementation of the $tp_traverse$ handler. If instances of the type are mutable, a tp_clear implementation must also be provided.

Py_TPFLAGS_HAVE_GC Objects with a type with this flag set must conform with the rules documented here. For convenience these objects will be referred to as container objects.

Constructors for container types must conform to two rules:

- 1. The memory for the object must be allocated using PyObject GC New or PyObject GC NewVar.
- 2. Once all the fields which may contain references to other containers are initialized, it must call <code>PyObject_GC_Track()</code>.

Similarly, the deallocator for the object must conform to a similar pair of rules:

- 1. Before fields which refer to other containers are invalidated, PyObject_GC_UnTrack() must be called.
- 2. The object's memory must be deallocated using PyObject_GC_Del().

Avertissement : If a type adds the Py_TPFLAGS_HAVE_GC, then it *must* implement at least a *tp_traverse* handler or explicitly use one from its subclass or subclasses.

When calling $PyType_Ready()$ or some of the APIs that indirectly call it like $PyType_FromSpecWithBases()$ or $PyType_FromSpec()$ the interpreter will automatically populate the tp_flags , $tp_traverse$ and tp_clear fields if the type inherits from a class that implements the garbage collector protocol and the child class does not include the $Py_TPFLAGS_HAVE_GC$ flag.

PyObject_GC_New (TYPE, typeobj)

Analogous to PyObject_New but for container objects with the Py_TPFLAGS_HAVE_GC flag set.

PyObject GC NewVar(TYPE, typeobj, size)

Analogous to PyObject NewVar but for container objects with the Py TPFLAGS HAVE GC flag set.

PyObject *PyUnstable_Object_GC_NewWithExtraData (PyTypeObject *type, size_t extra_size)

This is *Unstable API*. It may change without warning in minor releases.

Analogous to <code>PyObject_GC_New</code> but allocates <code>extra_size</code> bytes at the end of the object (at offset <code>tp_basicsize</code>). The allocated memory is initialized to zeros, except for the <code>Python object header</code>. The extra data will be deallocated with the object, but otherwise it is not managed by Python.

Avertissement: The function is marked as unstable because the final mechanism for reserving extra data after an instance is not yet decided. For allocating a variable number of fields, prefer using <code>PyVarObject</code> and <code>tp_itemsize</code> instead.

Nouveau dans la version 3.12.

TYPE *PyObject_GC_Resize (TYPE, PyVarObject *op, Py_ssize_t newsize)

Resize an object allocated by PyObject_NewVar. Returns the resized object or NULL on failure. op must not be tracked by the collector yet.

void PyObject_GC_Track (PyObject *op)

Part of the Stable ABI. Adds the object op to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the $tp_traverse$ handler become valid, usually near the end of the constructor.

int PyObject_IS_GC (PyObject *obj)

Returns non-zero if the object implements the garbage collector protocol, otherwise returns 0.

The object cannot be tracked by the garbage collector if this function returns 0.

int PyObject_GC_IsTracked (PyObject *op)

Part of the Stable ABI since version 3.9. Returns 1 if the object type of op implements the GC protocol and op is being currently tracked by the garbage collector and 0 otherwise.

This is analogous to the Python function $gc.is_tracked()$.

Nouveau dans la version 3.9.

int PyObject_GC_IsFinalized (PyObject *op)

Part of the Stable ABI since version 3.9. Returns 1 if the object type of op implements the GC protocol and op has been already finalized by the garbage collector and 0 otherwise.

This is analogous to the Python function gc.is_finalized().

Nouveau dans la version 3.9.

void PyObject GC Del (void *op)

Part of the Stable ABI. Releases memory allocated to an object using PyObject_GC_New or PyObject_GC_NewVar.

void PyObject GC UnTrack (void *op)

Part of the Stable ABI. Remove the object op from the set of container objects tracked by the collector. Note that $PyObject_GC_Track$ () can be called again on this object to add it back to the set of tracked objects. The deal-locator ($tp_dealloc$ handler) should call this for the object before any of the fields used by the $tp_traverse$ handler become invalid.

 $Modifi\'e \ dans \ la \ version \ 3.8: The \ _PyObject_GC_TRACK () \ and \ _PyObject_GC_UNTRACK () \ macros \ have \ been \ removed \ from \ the \ public \ C \ API.$

The tp_traverse handler accepts a function parameter of this type :

```
typedef int (*visitproc)(PyObject *object, void *arg)
```

Part of the Stable ABI. Type of the visitor function passed to the tp_traverse handler. The function should be called with an object to traverse as *object* and the third parameter to the tp_traverse handler as arg. The Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The tp_traverse handler must have the following type:

```
typedef int (*traverseproc)(PyObject *self, visitproc visit, void *arg)
```

Part of the Stable ABI. Traversal function for a container object. Implementations must call the *visit* function for each object directly contained by *self*, with the parameters to *visit* being the contained object and the *arg* value passed to the handler. The *visit* function must not be called with a NULL object argument. If *visit* returns a non-zero value that value should be returned immediately.

To simplify writing $tp_traverse$ handlers, a $Py_VISIT()$ macro is provided. In order to use this macro, the $tp_traverse$ implementation must name its arguments exactly *visit* and arg:

```
void Py_VISIT (PyObject *o)
```

If o is not NULL, call the *visit* callback, with arguments o and arg. If *visit* returns a non-zero value, then return it. Using this macro, $tp_traverse$ handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The tp_clear handler must be of the inquiry type, or NULL if the object is immutable.

```
typedef int (*inquiry)(PyObject *self)
```

Part of the Stable ABI. Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after calling this method (don't just call $Py_DECREF()$) on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

12.11.1 Controlling the Garbage Collector State

The C-API provides the following functions for controlling garbage collection runs.

```
Py_ssize_t PyGC_Collect (void)
```

Part of the Stable ABI. Perform a full garbage collection, if the garbage collector is enabled. (Note that gc. collect() runs it unconditionally.)

Returns the number of collected + unreachable objects which cannot be collected. If the garbage collector is disabled or already collecting, returns 0 immediately. Errors during garbage collection are passed to sys.unraisablehook. This function does not raise exceptions.

int PyGC Enable (void)

Part of the Stable ABI since version 3.10. Enable the garbage collector: similar to gc.enable(). Returns the previous state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

```
int PyGC_Disable (void)
```

Part of the Stable ABI since version 3.10. Disable the garbage collector: similar to gc.disable(). Returns the previous state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

int PyGC_IsEnabled (void)

Part of the Stable ABI since version 3.10. Query the state of the garbage collector: similar to gc.isenabled(). Returns the current state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

12.11.2 Querying Garbage Collector State

The C-API provides the following interface for querying information about the garbage collector.

void PyUnstable_GC_VisitObjects (gcvisitobjects_t callback, void *arg)

This is *Unstable API*. It may change without warning in minor releases.

Run supplied callback on all live GC-capable objects. arg is passed through to all invocations of callback.

Avertissement : If new objects are (de)allocated by the callback it is undefined if they will be visited. Garbage collection is disabled during operation. Explicitly running a collection in the callback may lead to undefined behaviour e.g. visiting the same objects multiple times or not at all.

Nouveau dans la version 3.12.

typedef int (*gcvisitobjects_t)(PyObject *object, void *arg)

Type of the visitor function to be passed to <code>PyUnstable_GC_VisitObjects()</code>. arg is the same as the arg passed to <code>PyUnstable_GC_VisitObjects</code>. Return 0 to continue iteration, return 1 to stop iteration. Other return values are reserved for now so behavior on returning anything else is undefined.

Nouveau dans la version 3.12.

CHAPITRE 13

Version des API et ABI

CPython révèle son numéro de version dans les macros suivantes. À noter qu'ils correspondent au code de la version **compilée** avec, pas nécessairement la version utilisée à l'**exécution**.

Voir Stabilité de l'API C pour une discussion sur la stabilité des API et ABI entre (ou en fonction) de la version.

PY_MAJOR_VERSION

Le 3 dans 3.4.1a2.)

PY_MINOR_VERSION

Le 4 dans 3.4.1a2.

PY_MICRO_VERSION

Le 1 dans 3.4.1a2.)

PY_RELEASE_LEVEL

The a in 3.4.1a2. This can be 0xA for alpha, 0xB for beta, 0xC for release candidate or 0xF for final.

PY RELEASE SERIAL

Le 2 dans 3.4.1a2. Nul pour des versions finales.

PY_VERSION_HEX

Le numéro de version de Python encodé en un seul entier.

L'information sur la version sous-jacente peut être trouvée en la traitant comme un nombre sous 32 bits de la manière suivante :

Octets	Bits (ordre gros-boutiste)	Signification	Valeur pour 3.4.1a2
1	1-8	PY_MAJOR_VERSION	0x03
2	9-16	PY_MINOR_VERSION	0x04
3	17-24	PY_MICRO_VERSION	0x01
4	25-28	PY_RELEASE_LEVEL	0xA
	29-32	PY_RELEASE_SERIAL	0x2

Ainsi, 0x030401a2 est la version en notation hexadécimale sur un entier de 3.4.1a2 et 0x030a00f0 est la version en notation hexadécimale sur un entier de 3.10.0

Vous pouvez l'utiliser pour les comparaisons numériques, par exemple, $\#if\ PY_VERSION_HEX >= ...$ This version is also available via the symbol $Py_Version$.

const unsigned long Py_Version

Part of the Stable ABI since version 3.11. La version à l'exécution de Python est encodée en une constante, avec le même format que la macro PY_VERSION_HEX. Cela contient la version de Python utilisée lors de l'exécution. Nouveau dans la version 3.11.

Toutes les macros données sont définies dans Include/patchlevel.h.

ANNEXE A

Glossaire

- >>> L'invite de commande utilisée par défaut dans l'interpréteur interactif. On la voit souvent dans des exemples de code qui peuvent être exécutés interactivement dans l'interpréteur.
- ... Peut faire référence à :
 - L'invite de commande utilisée par défaut dans l'interpréteur interactif lorsqu'on entre un bloc de code indenté, dans des délimiteurs fonctionnant par paires (parenthèses, crochets, accolades, triple guillemets), ou après un avoir spécifié un décorateur.
 - La constante Ellipsis.
- **2to3** Outil qui essaie de convertir du code pour Python 2.x en code pour Python 3.x en gérant la plupart des incompatibilités qui peuvent être détectées en analysant la source et parcourant son arbre syntaxique.
 - 2to3 est disponible dans la bibliothèque standard sous le nom de lib2to3; un point d'entrée indépendant est fourni via Tools/scripts/2to3. Cf. 2to3-reference.
- classe mère abstraite Les classes mères abstraites (ABC, suivant l'abréviation anglaise Abstract Base Class) complètent le duck-typing en fournissant un moyen de définir des interfaces pour les cas où d'autres techniques comme hasattr() seraient inélégantes ou subtilement fausses (par exemple avec les méthodes magiques). Les ABC introduisent des sous-classes virtuelles qui n'héritent pas d'une classe mais qui sont quand même reconnues par isinstance() ou issubclass() (voir la documentation du module abc). Python contient de nombreuses ABC pour les structures de données (dans le module collections.abc), les nombres (dans le module numbers), les flux (dans le module io) et les chercheurs-chargeurs du système d'importation (dans le module importlib.abc). Vous pouvez créer vos propres ABC avec le module abc.
- **annotation** Étiquette associée à une variable, un attribut de classe, un paramètre de fonction ou une valeur de retour. Elle est utilisée par convention comme *type hint*.
 - Les annotations de variables locales ne sont pas accessibles au moment de l'exécution, mais les annotations de variables globales, d'attributs de classe et de fonctions sont stockées dans l'attribut spécial __annotations__ des modules, classes et fonctions, respectivement.
 - Voir *annotation de variable*, *annotation de fonction*, les **PEP 484** et **PEP 526**, qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.
- argument Valeur, donnée à une fonction ou à une méthode lors de son appel. Il existe deux types d'arguments :
 - argument nommé: un argument précédé d'un identifiant (comme name=) ou un dictionnaire précédé de **, lors d'un appel de fonction. Par exemple, 3 et 5 sont tous les deux des arguments nommés dans l'appel à complex () ici:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

— argument positionnel : un argument qui n'est pas nommé. Les arguments positionnels apparaissent au début de la liste des arguments, ou donnés sous forme d'un itérable précédé par *. Par exemple, 3 et 5 sont tous les deux des arguments positionnels dans les appels suivants :

```
complex(3, 5)
complex(*(3, 5))
```

Les arguments se retrouvent dans le corps de la fonction appelée parmi les variables locales. Voir la section calls à propos des règles dictant cette affectation. Syntaxiquement, toute expression est acceptée comme argument, et c'est la valeur résultante de l'expression qui sera affectée à la variable locale.

Voir aussi *paramètre* dans le glossaire, la question Différence entre argument et paramètre de la FAQ et la **PEP** 362.

- gestionnaire de contexte asynchrone An object which controls the environment seen in an async with statement by defining __aenter__() and __aexit__() methods. Introduced by PEP 492.
- **générateur asynchrone** Fonction qui renvoie un *itérateur de générateur asynchrone*. Cela ressemble à une coroutine définie par async def, sauf qu'elle contient une ou des expressions yield produisant ainsi uns série de valeurs utilisables dans une boucle async for.

Générateur asynchrone fait généralement référence à une fonction, mais peut faire référence à un *itérateur de générateur asynchrone* dans certains contextes. Dans les cas où le sens voulu n'est pas clair, utiliser l'ensemble des termes lève l'ambiguïté.

Un générateur asynchrone peut contenir des expressions await ainsi que des instructions async for, et async with.

itérateur de générateur asynchrone Objet créé par un générateur asynchrone.

This is an *asynchronous iterator* which when called using the __anext__ () method returns an awaitable object which will execute the body of the asynchronous generator function until the next yield expression.

Each yield temporarily suspends processing, remembering the location execution state (including local variables and pending try-statements). When the *asynchronous generator iterator* effectively resumes with another awaitable returned by __anext__ (), it picks up where it left off. See PEP 492 and PEP 525.

- **itérable asynchrone** An object, that can be used in an async for statement. Must return an *asynchronous iterator* from its __aiter__() method. Introduced by PEP 492.
- itérateur asynchrone An object that implements the __aiter__() and __anext__() methods.
 _anext__() must return an awaitable object. async for resolves the awaitables returned by an asynchronous iterator's __anext__() method until it raises a StopAsyncIteration exception.
 Introduced by PEP 492.
- **attribut** Valeur associée à un objet et habituellement désignée par son nom *via* une notation utilisant des points. Par exemple, si un objet *o* possède un attribut *a*, cet attribut est référencé par *o.a*.

Il est possible de donner à un objet un attribut dont le nom n'est pas un identifiant tel que défini pour les identifiers, par exemple en utilisant setatr(), si l'objet le permet. Un tel attribut ne sera pas accessible à l'aide d'une expression pointée et on devra y accéder avec getatr().

- attendable (awaitable) An object that can be used in an await expression. Can be a coroutine or an object with an __await__() method. See also PEP 492.
- **BDFL** Dictateur bienveillant à vie (*Benevolent Dictator For Life* en anglais). Pseudonyme de Guido van Rossum, le créateur de Python.
- **fichier binaire** Un *file object* capable de lire et d'écrire des *bytes-like objects*. Des fichiers binaires sont, par exemple, les fichiers ouverts en mode binaire ('rb', 'wb', ou 'rb+'), sys.stdin.buffer, sys.stdout.buffer, les instances de io.BytesIO ou de gzip.GzipFile.

Consultez fichier texte, un objet fichier capable de lire et d'écrire des objets str.

référence empruntée In Python's C API, a borrowed reference is a reference to an object, where the code using the object does not own the reference. It becomes a dangling pointer if the object is destroyed. For example, a garbage collection can remove the last *strong reference* to the object and so destroy it.

Il est recommandé d'appeler $Py_INCREF()$ sur la référence empruntée, ce qui la transforme in situ en une référence forte. Vous pouvez faire une exception si vous êtes certain que l'objet ne peut pas être supprimé avant la dernière utilisation de la référence empruntée. Voir aussi la fonction $Py_NewRef()$, qui crée une nouvelle référence forte.

objet octet-compatible Un objet gérant le *protocole tampon* et pouvant exporter un tampon (*buffer* en anglais) C-*contigu*. Cela inclut les objets bytes, bytearray et array ainsi que beaucoup d'objets memoryview. Les objets octets-compatibles peuvent être utilisés pour diverses opérations sur des données binaires, comme la compression, la sauvegarde dans un fichier binaire ou l'envoi sur le réseau.

Certaines opérations nécessitent de travailler sur des données binaires variables. La documentation parle de ceuxci comme des *read-write bytes-like objects*. Par exemple, bytearray ou une memoryview d'un bytearray en font partie. D'autres opérations nécessitent de travailler sur des données binaires stockées dans des objets immuables (« *objets octets-compatibles en lecture seule* »), par exemple des bytes ou des memoryview d'un objet bytes.

code intermédiaire (*bytecode*) Le code source, en Python, est compilé en un code intermédiaire (*bytecode* en anglais), la représentation interne à CPython d'un programme Python. Le code intermédiaire est mis en cache dans un fichier .pyc de manière à ce qu'une seconde exécution soit plus rapide (la compilation en code intermédiaire a déjà été faite). On dit que ce *langage intermédiaire* est exécuté sur une *virtual machine* qui exécute des instructions machine pour chaque instruction du code intermédiaire. Notez que le code intermédiaire n'a pas vocation à fonctionner sur différentes machines virtuelles Python ou à être stable entre différentes versions de Python.

La documentation du module dis fournit une liste des instructions du code intermédiaire.

appelable (*callable*) Un appelable est un objet qui peut être appelé, éventuellement avec un ensemble d'arguments (voir *argument*), avec la syntaxe suivante :

```
callable(argument1, argument2, argumentN)
```

Une *fonction*, et par extension une *méthode*, est un appelable. Une instance d'une classe qui implémente la méthode __call__() est également un appelable.

fonction de rappel (*callback*) Une fonction (classique, par opposition à une coroutine) passée en argument pour être exécutée plus tard.

classe Modèle pour créer des objets définis par l'utilisateur. Une définition de classe (*class*) contient normalement des définitions de méthodes qui agissent sur les instances de la classe.

variable de classe Une variable définie dans une classe et destinée à être modifiée uniquement au niveau de la classe (c'est-à-dire, pas dans une instance de la classe).

nombre complexe Extension des nombres réels familiers, dans laquelle tous les nombres sont exprimés sous la forme d'une somme d'une partie réelle et d'une partie imaginaire. Les nombres imaginaires sont les nombres réels multipliés par l'unité imaginaire (la racine carrée de -1, souvent écrite i en mathématiques ou j par les ingénieurs). Python comprend nativement les nombres complexes, écrits avec cette dernière notation : la partie imaginaire est écrite avec un suffixe j, exemple, 3+1j. Pour utiliser les équivalents complexes de math, utilisez cmath. Les nombres complexes sont un concept assez avancé en mathématiques. Si vous ne connaissez pas ce concept, vous pouvez tranquillement les ignorer.

gestionnaire de contexte An object which controls the environment seen in a with statement by defining __enter__() and __exit__() methods. See PEP 343.

variable de contexte Une variable qui peut avoir des valeurs différentes en fonction de son contexte. Cela est similaire au stockage par fil d'exécution (*Thread Local Storage* en anglais) dans lequel chaque fil d'exécution peut avoir une valeur différente pour une variable. Toutefois, avec les variables de contexte, il peut y avoir plusieurs contextes dans un fil d'exécution et l'utilisation principale pour les variables de contexte est de garder une trace des variables dans les tâches asynchrones concourantes. Voir contextvars.

contigu Un tampon (*buffer* en anglais) est considéré comme contigu s'il est soit *C-contigu* soit *Fortran-contigu*. Les tampons de dimension zéro sont C-contigus et Fortran-contigus. Pour un tableau à une dimension, ses éléments

doivent être placés en mémoire l'un à côté de l'autre, dans l'ordre croissant de leur indice, en commençant à zéro. Pour qu'un tableau multidimensionnel soit C-contigu, le dernier indice doit être celui qui varie le plus rapidement lors du parcours de ses éléments dans l'ordre de leur adresse mémoire. À l'inverse, dans les tableaux Fortrancontigu, c'est le premier indice qui doit varier le plus rapidement.

- **coroutine** Les coroutines sont une forme généralisée des fonctions. On entre dans une fonction en un point et on en sort en un autre point. On peut entrer, sortir et reprendre l'exécution d'une coroutine en plusieurs points. Elles peuvent être implémentées en utilisant l'instruction async def. Voir aussi la **PEP 492**.
- fonction coroutine Fonction qui renvoie un objet *coroutine*. Une fonction coroutine peut être définie par l'instruction async def et peut contenir les mots clés await, async for ainsi que async with. A été introduit par la PEP 492.
- **CPython** L'implémentation canonique du langage de programmation Python, tel que distribué sur python.org. Le terme "CPython" est utilisé dans certains contextes lorsqu'il est nécessaire de distinguer cette implémentation des autres comme *Jython* ou *IronPython*.
- **décorateur** Fonction dont la valeur de retour est une autre fonction. Un décorateur est habituellement utilisé pour transformer une fonction via la syntaxe @wrapper, dont les exemples typiques sont : classmethod() et staticmethod().

La syntaxe des décorateurs est simplement du sucre syntaxique, les définitions des deux fonctions suivantes sont sémantiquement équivalentes :

```
def f(arg):
    ...
f = staticmethod(f)

@staticmethod
def f(arg):
    ...
```

Quoique moins fréquemment utilisé, le même concept existe pour les classes. Consultez la documentation définitions de fonctions et définitions de classes pour en savoir plus sur les décorateurs.

- **descripteur** N'importe quel objet définissant les méthodes __get__(), __set__(), ou __delete__(). Lorsque l'attribut d'une classe est un descripteur, son comportement spécial est déclenché lors de la recherche des attributs. Normalement, lorsque vous écrivez *a.b* pour obtenir, affecter ou effacer un attribut, Python recherche l'objet nommé *b* dans le dictionnaire de la classe de *a*. Mais si *b* est un descripteur, c'est la méthode de ce descripteur qui est alors appelée. Comprendre les descripteurs est requis pour avoir une compréhension approfondie de Python, ils sont la base de nombre de ses caractéristiques notamment les fonctions, méthodes, propriétés, méthodes de classes, méthodes statiques et les références aux classes parentes.
 - Pour plus d'informations sur les méthodes des descripteurs, consultez descriptors ou le guide pour l'utilisation des descripteurs.
- **dictionnaire** Structure de donnée associant des clés à des valeurs. Les clés peuvent être n'importe quel objet possédant les méthodes __hash__ () et __eq__ (). En Perl, les dictionnaires sont appelés "hash".
- dictionnaire en compréhension (ou dictionnaire en intension) Écriture concise pour traiter tout ou partie des éléments d'un itérable et renvoyer un dictionnaire contenant les résultats. results = {n: n ** 2 for n in range (10)} génère un dictionnaire contenant des clés n liées à leurs valeurs n ** 2. Voir compréhensions.
- vue de dictionnaire Objets retournés par les méthodes dict.keys(), dict.values() et dict.items().
 Ils fournissent des vues dynamiques des entrées du dictionnaire, ce qui signifie que lorsque le dictionnaire change, la vue change. Pour transformer une vue en vraie liste, utilisez list (dictview). Voir dict-views.
- chaîne de documentation (docstring) Première chaîne littérale qui apparaît dans l'expression d'une classe, fonction, ou module. Bien qu'ignorée à l'exécution, elle est reconnue par le compilateur et placée dans l'attribut ___doc__ de la classe, de la fonction ou du module. Comme cette chaîne est disponible par introspection, c'est l'endroit idéal pour documenter l'objet.
- **typage canard** (*duck-typing*) Style de programmation qui ne prend pas en compte le type d'un objet pour déterminer s'il respecte une interface, mais qui appelle simplement la méthode ou l'attribut (*Si ça a un bec et que ça cancane*,

ça doit être un canard, duck signifie canard en anglais). En se concentrant sur les interfaces plutôt que les types, du code bien construit améliore sa flexibilité en autorisant des substitutions polymorphiques. Le duck-typing évite de vérifier les types via type () ou isinstance (), Notez cependant que le duck-typing peut travailler de pair avec les classes mère abstraites. À la place, le duck-typing utilise plutôt hasattr () ou la programmation EAFP.

- **EAFP** Il est plus simple de demander pardon que demander la permission (*Easier to Ask for Forgiveness than Permission* en anglais). Ce style de développement Python fait l'hypothèse que le code est valide et traite les exceptions si cette hypothèse s'avère fausse. Ce style, propre et efficace, est caractérisé par la présence de beaucoup de mots clés try et except. Cette technique de programmation contraste avec le style *LBYL* utilisé couramment dans les langages tels que C.
- expression Suite logique de termes et chiffres conformes à la syntaxe Python dont l'évaluation fournit une valeur. En d'autres termes, une expression est une suite d'éléments tels que des noms, opérateurs, littéraux, accès d'attributs, méthodes ou fonctions qui aboutissent à une valeur. Contrairement à beaucoup d'autres langages, les différentes constructions du langage ne sont pas toutes des expressions. On trouve également des *instructions* qui ne peuvent pas être utilisées comme expressions, tel que while. Les affectations sont également des instructions et non des expressions.
- **module d'extension** Module écrit en C ou C++, utilisant l'API C de Python pour interagir avec Python et le code de l'utilisateur.
- **f-string** Chaîne littérale préfixée de 'f' ou 'F'. Les "f-strings" sont un raccourci pour formatted string literals. Voir la **PEP 498**.
- **objet fichier** Objet exposant une ressource via une API orientée fichier (avec les méthodes read () ou write ()). En fonction de la manière dont il a été créé, un objet fichier peut interfacer l'accès à un fichier sur le disque ou à un autre type de stockage ou de communication (typiquement l'entrée standard, la sortie standard, un tampon en mémoire, un connecteur réseau...). Les objets fichiers sont aussi appelés *file-like-objects* ou *streams*.
 - Il existe en réalité trois catégories de fichiers objets : les *fichiers binaires* bruts, les *fichiers binaires* avec tampon (*buffer*) et les *fichiers textes*. Leurs interfaces sont définies dans le module io. Le moyen le plus simple et direct de créer un objet fichier est d'utiliser la fonction open ().
- objet fichier-compatible Synonyme de objet fichier.
- **encodage du système de fichiers et gestionnaire d'erreurs associé** Encodage et gestionnaire d'erreurs utilisés par Python pour décoder les octets fournis par le système d'exploitation et encoder les chaînes de caractères Unicode afin de les passer au système.

L'encodage du système de fichiers doit impérativement pouvoir décoder tous les octets jusqu'à 128. Si ce n'est pas le cas, certaines fonctions de l'API lèvent UnicodeError.

Cet encodage et son gestionnaire d'erreur peuvent être obtenus à l'aide des fonctions sys. getfilesystemencoding() et sys.getfilesystemencodeerrors().

L'encodage du système de fichiers et gestionnaire d'erreurs associé sont configurés au démarrage de Python par la fonction <code>PyConfig_Read()</code> : regardez <code>filesystem_encoding</code> et <code>filesystem_errors</code> dans les membres de <code>PyConfig</code>.

Voir aussi encodage régional.

chercheur Objet qui essaie de trouver un *chargeur* pour le module en cours d'importation.

Depuis Python 3.3, il existe deux types de chercheurs : les *chercheurs dans les méta-chemins* à utiliser avec sys.meta_path; les *chercheurs d'entrée dans path* à utiliser avec sys.path_hooks.

Voir les PEP 302, PEP 420 et PEP 451 pour plus de détails.

- **division entière** Division mathématique arrondissant à l'entier inférieur. L'opérateur de la division entière est //. Par exemple l'expression 11 // 4 vaut 2, contrairement à 11 / 4 qui vaut 2.75. Notez que (-11) // 4 vaut -3 car l'arrondi se fait à l'entier inférieur. Voir la **PEP 328**.
- **fonction** Suite d'instructions qui renvoie une valeur à son appelant. On peut lui passer des *arguments* qui pourront être utilisés dans le corps de la fonction. Voir aussi *paramètre*, *méthode* et function.
- **annotation de fonction** *annotation* d'un paramètre de fonction ou valeur de retour.

Les annotations de fonctions sont généralement utilisées pour des *indications de types* : par exemple, cette fonction devrait prendre deux arguments int et devrait également avoir une valeur de retour de type int :

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

L'annotation syntaxique de la fonction est expliquée dans la section function.

Voir *annotation de variable* et la **PEP 484**, qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.

__future__ Une importation depuis le futur s'écrit from __future__ import <fonctionnalité>.

Lorsqu'une importation du futur est active dans un module, Python compile ce module avec une certaine modification de la syntaxe ou du comportement qui est vouée à devenir standard dans une version ultérieure. Le module __future__ documente les possibilités pour *fonctionnalité*. L'importation a aussi l'effet normal d'importer une variable du module. Cette variable contient des informations utiles sur la fonctionnalité en question, notamment la version de Python dans laquelle elle a été ajoutée, et celle dans laquelle elle deviendra standard :

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

ramasse-miettes (*garbage collection* en anglais) Mécanisme permettant de libérer de la mémoire lorsqu'elle n'est plus utilisée. Python utilise un ramasse-miettes par comptage de référence et un ramasse-miettes cyclique capable de détecter et casser les références circulaires. Le ramasse-miettes peut être contrôlé en utilisant le module gc.

générateur Fonction qui renvoie un *itérateur de générateur*. Cela ressemble à une fonction normale, en dehors du fait qu'elle contient une ou des expressions yield produisant une série de valeurs utilisable dans une boucle *for* ou récupérées une à une via la fonction next ().

Fait généralement référence à une fonction génératrice mais peut faire référence à un *itérateur de générateur* dans certains contextes. Dans les cas où le sens voulu n'est pas clair, utiliser les termes complets lève l'ambiguïté.

itérateur de générateur Objet créé par une fonction générateur.

Chaque yield suspend temporairement l'exécution, en se rappelant l'endroit et l'état de l'exécution (y compris les variables locales et les *try* en cours). Lorsque l'itérateur de générateur reprend, il repart là où il en était (contrairement à une fonction qui prendrait un nouveau départ à chaque invocation).

expression génératrice Expression qui donne un itérateur. Elle ressemble à une expression normale, suivie d'une clause for définissant une variable de boucle, un intervalle et une clause if optionnelle. Toute cette expression génère des valeurs pour la fonction qui l'entoure :

```
>>> sum(i*i for i in range(10))  # sum of squares 0, 1, 4, ... 81
285
```

fonction générique Fonction composée de plusieurs fonctions implémentant les mêmes opérations pour différents types. L'implémentation à utiliser est déterminée lors de l'appel par l'algorithme de répartition.

Voir aussi single dispatch, le décorateur functools.singledispatch() et la PEP 443.

type générique Un *type* qui peut être paramétré; généralement un conteneur comme list ou dict. Utilisé pour les *indications de type* et les *annotations*.

Pour plus de détails, voir types alias génériques et le module typing. On trouvera l'historique de cette fonctionnalité dans les PEP 483, PEP 484 et PEP 585.

GIL Voir global interpreter lock.

verrou global de l'interpréteur (global interpreter lock en anglais) Mécanisme utilisé par l'interpréteur CPython pour s'assurer qu'un seul fil d'exécution (thread en anglais) n'exécute le bytecode à la fois. Cela simplifie l'implémentation de CPython en rendant le modèle objet (incluant des parties critiques comme la classe native dict) implicitement protégé contre les accès concourants. Verrouiller l'interpréteur entier rend plus facile l'implémentation de multiples fils d'exécution (multi-thread en anglais), au détriment malheureusement de beaucoup du parallélisme possible sur les machines ayant plusieurs processeurs.

Cependant, certains modules d'extension, standards ou non, sont conçus de manière à libérer le GIL lorsqu'ils effectuent des tâches lourdes tel que la compression ou le hachage. De la même manière, le GIL est toujours libéré lors des entrées-sorties.

Les tentatives précédentes d'implémenter un interpréteur Python avec une granularité de verrouillage plus fine ont toutes échouées, à cause de leurs mauvaises performances dans le cas d'un processeur unique. Il est admis que corriger ce problème de performance induit mènerait à une implémentation beaucoup plus compliquée et donc plus coûteuse à maintenir.

- *pyc* utilisant le hachage Un fichier de cache de code intermédiaire (*bytecode* en anglais) qui utilise le hachage plutôt que l'heure de dernière modification du fichier source correspondant pour déterminer sa validité. Voir pycinvalidation.
- hachable Un objet est *hachable* s'il a une empreinte (*hash*) qui ne change jamais (il doit donc implémenter une méthode __hash__()) et s'il peut être comparé à d'autres objets (avec la méthode __eq__()). Les objets hachables dont la comparaison par __eq__ est vraie doivent avoir la même empreinte.
 - La hachabilité permet à un objet d'être utilisé comme clé de dictionnaire ou en tant que membre d'un ensemble (type *set*), car ces structures de données utilisent ce *hash*.
 - La plupart des types immuables natifs de Python sont hachables, mais les conteneurs muables (comme les listes ou les dictionnaires) ne le sont pas ; les conteneurs immuables (comme les n-uplets ou les ensembles figés) ne sont hachables que si leurs éléments sont hachables. Les instances de classes définies par les utilisateurs sont hachables par défaut. Elles sont toutes considérées différentes (sauf avec elles-mêmes) et leur valeur de hachage est calculée à partir de leur id().
- **IDLE** Environnement d'apprentissage et de développement intégré pour Python. IDLE est un éditeur basique et un interpréteur livré avec la distribution standard de Python.
- **immuable** Objet dont la valeur ne change pas. Les nombres, les chaînes et les *n*-uplets sont immuables. Ils ne peuvent être modifiés. Un nouvel objet doit être créé si une valeur différente doit être stockée. Ils jouent un rôle important quand une valeur de *hash* constante est requise, typiquement en clé de dictionnaire.
- **chemin des importations** Liste de *entrées* dans lesquelles le *chercheur basé sur les chemins* cherche les modules à importer. Typiquement, lors d'une importation, cette liste vient de sys.path; pour les sous-paquets, elle peut aussi venir de l'attribut __path__ du paquet parent.
- importation Processus rendant le code Python d'un module disponible dans un autre.
- importateur Objet qui trouve et charge un module, en même temps un chercheur et un chargeur.
- interactif Python a un interpréteur interactif, ce qui signifie que vous pouvez écrire des expressions et des instructions à l'invite de l'interpréteur. L'interpréteur Python va les exécuter immédiatement et vous en présenter le résultat. Démarrez juste python (probablement depuis le menu principal de votre ordinateur). C'est un moyen puissant pour tester de nouvelles idées ou étudier de nouveaux modules (souvenez-vous de help(x)).
- **interprété** Python est un langage interprété, en opposition aux langages compilés, bien que la frontière soit floue en raison de la présence d'un compilateur en code intermédiaire. Cela signifie que les fichiers sources peuvent être exécutés directement, sans avoir à compiler un fichier exécutable intermédiaire. Les langages interprétés ont généralement un cycle de développement / débogage plus court que les langages compilés. Cependant, ils s'exécutent généralement plus lentement. Voir aussi *interactif*.
- arrêt de l'interpréteur Lorsqu'on lui demande de s'arrêter, l'interpréteur Python entre dans une phase spéciale où il libère graduellement les ressources allouées, comme les modules ou quelques structures de données internes. Il fait aussi quelques appels au *ramasse-miettes*. Cela peut déclencher l'exécution de code dans des destructeurs ou des fonctions de rappels de *weakrefs*. Le code exécuté lors de l'arrêt peut rencontrer des exceptions puisque les ressources auxquelles il fait appel sont susceptibles de ne plus fonctionner, (typiquement les modules des bibliothèques ou le mécanisme de *warning*).
 - La principale raison d'arrêt de l'interpréteur est que le module __main__ ou le script en cours d'exécution a terminé de s'exécuter.
- itérable An object capable of returning its members one at a time. Examples of iterables include all sequence types (such as list, str, and tuple) and some non-sequence types like dict, file objects, and objects of any classes you define with an __iter__() method or with a __getitem__() method that implements sequence semantics.
 - Les itérables peuvent être utilisés dans des boucles for et à beaucoup d'autres endroits où une séquence est requise (zip(), map()...). Lorsqu'un itérable est passé comme argument à la fonction native iter(), celle-ci fournit

en retour un itérateur sur cet itérable. Cet itérateur n'est valable que pour une seule passe sur le jeu de valeurs. Lors de l'utilisation d'itérables, il n'est habituellement pas nécessaire d'appeler iter() ou de s'occuper soi-même des objets itérateurs. L'instruction for le fait automatiquement pour vous, créant une variable temporaire anonyme pour garder l'itérateur durant la boucle. Voir aussi *itérateur*, *séquence* et *générateur*.

itérateur Objet représentant un flux de donnée. Des appels successifs à la méthode __next__ () de l'itérateur (ou le passer à la fonction native next ()) donne successivement les objets du flux. Lorsque plus aucune donnée n'est disponible, une exception StopIteration est levée. À ce point, l'itérateur est épuisé et tous les appels suivants à sa méthode __next__ () lèveront encore une exception StopIteration. Les itérateurs doivent avoir une méthode __iter__ () qui renvoie l'objet itérateur lui-même, de façon à ce que chaque itérateur soit aussi itérable et puisse être utilisé dans la plupart des endroits où d'autres itérables sont attendus. Une exception notable est un code qui tente plusieurs itérations complètes. Un objet conteneur, (tel que list) produit un nouvel itérateur neuf à chaque fois qu'il est passé à la fonction iter() ou s'il est utilisé dans une boucle for. Faire ceci sur un itérateur donnerait simplement le même objet itérateur épuisé utilisé dans son itération précédente, le faisant ressembler à un conteneur vide.

Vous trouverez davantage d'informations dans typeiter.

Particularité de l'implémentation CPython : CPython n'est pas toujours cohérent sur le fait de demander ou non à un itérateur de définir __iter__().

fonction clé Une fonction clé est un objet appelable qui renvoie une valeur à fins de tri ou de classement. Par exemple, la fonction locale.strxfrm() est utilisée pour générer une clé de classement prenant en compte les conventions de classement spécifiques aux paramètres régionaux courants.

Plusieurs outils dans Python acceptent des fonctions clés pour déterminer comment les éléments sont classés ou groupés. On peut citer les fonctions min(), max(), sorted(), list.sort(), heapq.merge(), heapq.nsmallest(), heapq.nlargest() et itertools.groupby().

Il existe plusieurs moyens de créer une fonction clé. Par exemple, la méthode str.lower() peut servir de fonction clé pour effectuer des recherches insensibles à la casse. Aussi, il est possible de créer des fonctions clés avec des expressions lambda, comme lambda r: (r[0], r[2]). Par ailleurs attrgetter(), itemgetter() et methodcaller() permettent de créer des fonctions clés. Voir le guide pour le tri pour des exemples de création et d'utilisation de fonctions clefs.

argument nommé Voir argument.

lambda Fonction anonyme sous la forme d'une *expression* et ne contenant qu'une seule expression, exécutée lorsque la fonction est appelée. La syntaxe pour créer des fonctions lambda est : lambda [parameters]: expression

LBYL Regarde avant de sauter, (*Look before you leap* en anglais). Ce style de programmation consiste à vérifier des conditions avant d'effectuer des appels ou des accès. Ce style contraste avec le style *EAFP* et se caractérise par la présence de beaucoup d'instructions if.

Dans un environnement avec plusieurs fils d'exécution (*multi-threaded* en anglais), le style *LBYL* peut engendrer un séquencement critique (*race condition* en anglais) entre le "regarde" et le "sauter". Par exemple, le code if key in mapping: return mapping [key] peut échouer si un autre fil d'exécution supprime la clé *key* du *mapping* après le test mais avant l'accès. Ce problème peut être résolu avec des verrous (*locks*) ou avec l'approche EAFP.

encodage régional Sous Unix, il est défini par la variable régionale LC_CTYPE. Il peut être modifié par locale. setlocale (locale.LC_CTYPE, new_locale).

Sous Windows, c'est un encodage ANSI (par ex.: "cp1252").

Sous Android et VxWorks, Python utilise "utf-8" comme encodage régional.

locale.getencoding() permet de récupérer l'encodage régional.

Voir aussi l'encodage du systèmes de fichiers et gestionnaire d'erreurs associé.

liste Un type natif de *sequence* dans Python. En dépit de son nom, une list ressemble plus à un tableau (*array* dans la plupart des langages) qu'à une liste chaînée puisque les accès se font en O(1).

liste en compréhension (ou liste en intension) Écriture concise pour manipuler tout ou partie des éléments d'une séquence et renvoyer une liste contenant les résultats. result = ['{:#04x}'.format(x) for x in range (256) if x % 2 == 0] génère la liste composée des nombres pairs de 0 à 255 écrits sous formes

de chaînes de caractères et en hexadécimal (0x...). La clause if est optionnelle. Si elle est omise, tous les éléments du range (256) seront utilisés.

chargeur Objet qui charge un module. Il doit définir une méthode nommée load_module(). Un chargeur est typiquement donné par un *chercheur*. Voir la PEP 302 pour plus de détails et importlib.ABC.Loader pour sa *classe mère abstraite*.

méthode magique Un synonyme informel de *special method*.

tableau de correspondances (*mapping* en anglais) Conteneur permettant de rechercher des éléments à partir de clés et implémentant les méthodes spécifiées dans les classes mères abstraites des tableaux de correspondances (immuables) ou tableaux de correspondances muables (voir les classes mères abstraites). Les classes suivantes sont des exemples de tableaux de correspondances : dict, collections.defaultdict, collections.OrderedDict et collections.Counter.

chercheur dans les méta-chemins Un *chercheur* renvoyé par une recherche dans sys.meta_path. Les chercheurs dans les méta-chemins ressemblent, mais sont différents des *chercheurs d'entrée dans path*.

Voir importlib.abc.MetaPathFinder pour les méthodes que les chercheurs dans les méta-chemins doivent implémenter.

métaclasse Classe d'une classe. Les définitions de classe créent un nom pour la classe, un dictionnaire de classe et une liste de classes parentes. La métaclasse a pour rôle de réunir ces trois paramètres pour construire la classe. La plupart des langages orientés objet fournissent une implémentation par défaut. La particularité de Python est la possibilité de créer des métaclasses personnalisées. La plupart des utilisateurs n'auront jamais besoin de cet outil, mais lorsque le besoin survient, les métaclasses offrent des solutions élégantes et puissantes. Elles sont utilisées pour journaliser les accès à des propriétés, rendre sûrs les environnements *multi-threads*, suivre la création d'objets, implémenter des singletons et bien d'autres tâches.

Plus d'informations sont disponibles dans : metaclasses.

méthode Fonction définie à l'intérieur d'une classe. Lorsqu'elle est appelée comme un attribut d'une instance de cette classe, la méthode reçoit l'instance en premier *argument* (qui, par convention, est habituellement nommé self). Voir *function* et *nested scope*.

ordre de résolution des méthodes L'ordre de résolution des méthodes (*MRO* pour *Method Resolution Order* en anglais) est, lors de la recherche d'un attribut dans les classes parentes, la façon dont l'interpréteur Python classe ces classes parentes. Voir The Python 2.3 Method Resolution Order pour plus de détails sur l'algorithme utilisé par l'interpréteur Python depuis la version 2.3.

module Objet utilisé pour organiser une portion unitaire de code en Python. Les modules ont un espace de nommage et peuvent contenir n'importe quels objets Python. Charger des modules est appelé *importer*.

Voir aussi paquet.

spécificateur de module Espace de nommage contenant les informations, relatives à l'importation, utilisées pour charger un module. C'est une instance de la classe importlib.machinery.ModuleSpec.

MRO Voir ordre de résolution des méthodes.

muable Un objet muable peut changer de valeur tout en gardant le même id (). Voir aussi immuable.

n-uplet nommé Le terme "n-uplet nommé" s'applique à tous les types ou classes qui héritent de la classe tuple et dont les éléments indexables sont aussi accessibles en utilisant des attributs nommés. Les types et classes peuvent avoir aussi d'autres caractéristiques.

Plusieurs types natifs sont appelés n-uplets, y compris les valeurs retournées par time.localtime() et os. stat(). Un autre exemple est sys.float_info:

```
>>> sys.float_info[1]  # indexed access
1024
>>> sys.float_info.max_exp  # named field access
1024
>>> isinstance(sys.float_info, tuple)  # kind of tuple
True
```

Certains *n-uplets nommés* sont des types natifs (comme les exemples ci-dessus). Sinon, un *n-uplet nommé* peut être créé à partir d'une définition de classe habituelle qui hérite de tuple et qui définit les champs nommés. Une telle classe peut être écrite à la main ou être créée avec la fonction collections namedtuple (). Cette dernière méthode ajoute des méthodes supplémentaires qui ne seront pas trouvées dans celles écrites à la main ni dans les n-uplets nommés natifs.

espace de nommage L'endroit où une variable est stockée. Les espaces de nommage sont implémentés avec des dictionnaires. Il existe des espaces de nommage globaux, natifs ou imbriqués dans les objets (dans les méthodes). Les espaces de nommage favorisent la modularité car ils permettent d'éviter les conflits de noms. Par exemple, les fonctions builtins.open et os.open() sont différenciées par leurs espaces de nom. Les espaces de nommage aident aussi à la lisibilité et la maintenabilité en rendant clair quel module implémente une fonction. Par exemple, écrire random.seed() ou itertools.islice() affiche clairement que ces fonctions sont implémentées respectivement dans les modules random et itertools.

paquet-espace de nommage Un paquet tel que défini dans la PEP 421 qui ne sert qu'à contenir des sous-paquets.
Les paquets-espace de nommage peuvent n'avoir aucune représentation physique et, plus spécifiquement, ne sont pas comme un paquet classique puisqu'ils n'ont pas de fichier __init__.py.
Voir aussi module.

portée imbriquée Possibilité de faire référence à une variable déclarée dans une définition englobante. Typiquement, une fonction définie à l'intérieur d'une autre fonction a accès aux variables de cette dernière. Souvenez-vous cependant que cela ne fonctionne que pour accéder à des variables, pas pour les assigner. Les variables locales sont lues et assignées dans l'espace de nommage le plus proche. Tout comme les variables globales qui sont stockés dans l'espace de nommage global, le mot clef nonlocal permet d'écrire dans l'espace de nommage dans lequel est déclarée la variable.

nouvelle classe Ancien nom pour l'implémentation actuelle des classes, pour tous les objets. Dans les anciennes versions de Python, seules les nouvelles classes pouvaient utiliser les nouvelles fonctionnalités telles que __slots__, les descripteurs, les propriétés, __getattribute__(), les méthodes de classe et les méthodes statiques.

objet N'importe quelle donnée comportant des états (sous forme d'attributs ou d'une valeur) et un comportement (des méthodes). C'est aussi (object) l'ancêtre commun à absolument toutes les *nouvelles classes*.

paquet *module* Python qui peut contenir des sous-modules ou des sous-paquets. Techniquement, un paquet est un module qui possède un attribut __path__.

Voir aussi paquet classique et namespace package.

paramètre Entité nommée dans la définition d'une *fonction* (ou méthode), décrivant un *argument* (ou dans certains cas des arguments) que la fonction accepte. Il existe cinq sortes de paramètres :

— *positional-or-keyword*: l'argument peut être passé soit par sa *position*, soit en tant que *argument nommé*. C'est le type de paramètre par défaut. Par exemple, *foo* et *bar* dans l'exemple suivant:

```
def func(foo, bar=None): ...
```

— positional-only: définit un argument qui ne peut être fourni que par position. Les paramètres positional-only peuvent être définis en insérant un caractère "/" dans la liste de paramètres de la définition de fonction après eux. Par exemple: posonly1 et posonly2 dans le code suivant:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

— *keyword-only*: l'argument ne peut être fourni que nommé. Les paramètres *keyword-only* peuvent être définis en utilisant un seul paramètre *var-positional*, ou en ajoutant une étoile (*) seule dans la liste des paramètres avant eux. Par exemple, *kw only1* et *kw only2* dans le code suivant :

```
def func(arg, *, kw_only1, kw_only2): ...
```

var-positional: une séquence d'arguments positionnels peut être fournie (en plus de tous les arguments positionnels déjà acceptés par d'autres paramètres). Un tel paramètre peut être défini en préfixant son nom par une *. Par exemple args ci-après:

```
def func(*args, **kwargs): ...
```

— var-keyword : une quantité arbitraire d'arguments peut être passée, chacun étant nommé (en plus de tous les arguments nommés déjà acceptés par d'autres paramètres). Un tel paramètre est défini en préfixant le nom du paramètre par **. Par exemple, kwargs ci-dessus.

Les paramètres peuvent spécifier des arguments obligatoires ou optionnels, ainsi que des valeurs par défaut pour les arguments optionnels.

Voir aussi *argument* dans le glossaire, la question sur la différence entre les arguments et les paramètres dans la FAQ, la classe inspect.Parameter, la section function et la PEP 362.

entrée de chemin Emplacement dans le *chemin des importations (import path* en anglais, d'où le *path*) que le *chercheur basé sur les chemins* consulte pour trouver des modules à importer.

chercheur de chemins *chercheur* renvoyé par un appelable sur un sys.path_hooks (c'est-à-dire un *point d'entrée pour la recherche dans path*) qui sait où trouver des modules lorsqu'on lui donne une *entrée de path*.

Voir importlib.abc.PathEntryFinder pour les méthodes qu'un chercheur d'entrée dans path doit implémenter.

point d'entrée pour la recherche dans *path* Appelable dans la liste sys.path_hook qui donne un *chercheur d'entrée dans path* s'il sait où trouver des modules pour une *entrée dans path* donnée.

chercheur basé sur les chemins L'un des *chercheurs dans les méta-chemins* par défaut qui cherche des modules dans un *chemin des importations*.

objet simili-chemin Objet représentant un chemin du système de fichiers. Un objet simili-chemin est un objet str ou un objet bytes représentant un chemin ou un objet implémentant le protocole os.PathLike. Un objet qui accepte le protocole os.PathLike peut être converti en un chemin str ou bytes du système de fichiers en appelant la fonction os.fspath().os.fsdecode() et os.fsencode() peuvent être utilisées, respectivement, pour garantir un résultat de type str ou bytes à la place. A été Introduit par la PEP 519.

PEP *Python Enhancement Proposal* (Proposition d'amélioration de Python). Une PEP est un document de conception fournissant des informations à la communauté Python ou décrivant une nouvelle fonctionnalité pour Python, ses processus ou son environnement. Les PEP doivent fournir une spécification technique concise et une justification des fonctionnalités proposées.

Les PEP sont censées être les principaux mécanismes pour proposer de nouvelles fonctionnalités majeures, pour recueillir les commentaires de la communauté sur une question et pour documenter les décisions de conception qui sont intégrées en Python. L'auteur du PEP est responsable de l'établissement d'un consensus au sein de la communauté et de documenter les opinions contradictoires.

Voir la PEP 1.

portion Jeu de fichiers dans un seul dossier (pouvant être stocké sous forme de fichier zip) qui contribue à l'espace de nommage d'un paquet, tel que défini dans la **PEP 420**.

argument positionnel Voir argument.

API provisoire Une API provisoire est une API qui n'offre aucune garantie de rétrocompatibilité (la bibliothèque standard exige la rétrocompatibilité). Bien que des changements majeurs d'une telle interface ne soient pas attendus, tant qu'elle est étiquetée provisoire, des changements cassant la rétrocompatibilité (y compris sa suppression complète) peuvent survenir si les développeurs principaux le jugent nécessaire. Ces modifications ne surviendront que si de sérieux problèmes sont découverts et qu'ils n'avaient pas été identifiés avant l'ajout de l'API.

Même pour les API provisoires, les changements cassant la rétrocompatibilité sont considérés comme des "solutions de dernier recours". Tout ce qui est possible sera fait pour tenter de résoudre les problèmes en conservant la rétrocompatibilité.

Ce processus permet à la bibliothèque standard de continuer à évoluer avec le temps, sans se bloquer longtemps sur des erreurs d'architecture. Voir la PEP 411 pour plus de détails.

paquet provisoire Voir provisional API.

Python 3000 Surnom donné à la série des Python 3.x (très vieux surnom donné à l'époque où Python 3 représentait un futur lointain). Aussi abrégé *Py3k*.

Pythonique Idée, ou bout de code, qui colle aux idiomes de Python plutôt qu'aux concepts communs rencontrés dans d'autres langages. Par exemple, il est idiomatique en Python de parcourir les éléments d'un itérable en utilisant for. Beaucoup d'autres langages n'ont pas cette possibilité, donc les gens qui ne sont pas habitués à Python utilisent parfois un compteur numérique à la place :

```
for i in range(len(food)):
    print(food[i])
```

Plutôt qu'utiliser la méthode, plus propre et élégante, donc Pythonique :

```
for piece in food:
    print(piece)
```

nom qualifié Nom, comprenant des points, montrant le "chemin" de l'espace de nommage global d'un module vers une classe, fonction ou méthode définie dans ce module, tel que défini dans la PEP 3155. Pour les fonctions et classes de premier niveau, le nom qualifié est le même que le nom de l'objet :

Lorsqu'il est utilisé pour nommer des modules, le *nom qualifié complet (fully qualified name - FQN* en anglais) signifie le chemin complet (séparé par des points) vers le module, incluant tous les paquets parents. Par exemple : email.mime.text:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

nombre de références The number of references to an object. When the reference count of an object drops to zero, it is deallocated. Some objects are "immortal" and have reference counts that are never modified, and therefore the objects are never deallocated. Reference counting is generally not visible to Python code, but it is a key element of the *CPython* implementation. Programmers can call the sys.getrefcount() function to return the reference count for a particular object.

paquet classique paquet traditionnel, tel qu'un dossier contenant un fichier __init__.py.

Voir aussi paquet-espace de nommage.

__slots__ Déclaration dans une classe qui économise de la mémoire en pré-allouant de l'espace pour les attributs des instances et qui élimine le dictionnaire (des attributs) des instances. Bien que populaire, cette technique est difficile à maîtriser et devrait être réservée à de rares cas où un grand nombre d'instances dans une application devient un sujet critique pour la mémoire.

séquence An *iterable* which supports efficient element access using integer indices via the __getitem__() special method and defines a __len__() method that returns the length of the sequence. Some built-in sequence types are list, str, tuple, and bytes. Note that dict also supports __getitem__() and __len__(), but is considered a mapping rather than a sequence because the lookups use arbitrary *immutable* keys rather than integers.

The collections.abc.Sequence abstract base class defines a much richer interface that goes beyond just __getitem__() and __len__(), adding count(), index(), __contains__(), and __reversed__(). Types that implement this expanded interface can be registered explicitly using register().

- ensemble en compréhension (ou ensemble en intension) Une façon compacte de traiter tout ou partie des éléments d'un itérable et de renvoyer un set avec les résultats. results = {c for c in 'abracadabra' if c not in 'abc'} génère l'ensemble contenant les lettres « r » et « d » { 'r', 'd'}. Voir comprehensions.
- **distribution simple** Forme de distribution, comme les *fonction génériques*, où l'implémentation est choisie en fonction du type d'un seul argument.
- **tranche** (*slice* en anglais), un objet contenant habituellement une portion de *séquence*. Une tranche est créée en utilisant la notation [] avec des : entre les nombres lorsque plusieurs sont fournis, comme dans variable_name[1:3:5]. Cette notation utilise des objets slice en interne.
- **méthode spéciale** (*special method* en anglais) Méthode appelée implicitement par Python pour exécuter une opération sur un type, comme une addition. De telles méthodes ont des noms commençant et terminant par des doubles tirets bas. Les méthodes spéciales sont documentées dans specialnames.
- **instruction** Une instruction (*statement* en anglais) est un composant d'un "bloc" de code. Une instruction est soit une *expression*, soit une ou plusieurs constructions basées sur un mot-clé, comme if, while ou for.
- **référence forte** In Python's C API, a strong reference is a reference to an object which is owned by the code holding the reference. The strong reference is taken by calling $Py_INCREF()$ when the reference is created and released with $Py_DECREF()$ when the reference is deleted.

Une référence forte est créée à l'aide de la fonction $Py_NewRef()$. Il faut normalement appeler $Py_DECREF()$ dessus avant de sortir de sa portée lexicale, sans quoi il y a une fuite de référence.

Voir aussi référence empruntée.

encodages de texte Une chaîne de caractères en Python est une suite de points de code Unicode (dans l'intervalle U+0000--U+10FFFF). Pour stocker ou transmettre une chaîne, il est nécessaire de la sérialiser en suite d'octets. Sérialiser une chaîne de caractères en une suite d'octets s'appelle « encoder » et recréer la chaîne à partir de la suite d'octets s'appelle « décoder ».

Il existe de multiples codecs pour la sérialisation de texte, que l'on regroupe sous l'expression « encodages de texte ».

fichier texte *Objet fichier* capable de lire et d'écrire des objets str. Souvent, un fichier texte (*text file* en anglais) accède en fait à un flux de donnée en octets et gère l'*encodage de texte* automatiquement. Des exemples de fichiers textes sont les fichiers ouverts en mode texte ('r' ou 'w'), sys.stdin, sys.stdout et les instances de io.StringIO.

Voir aussi fichier binaire pour un objet fichier capable de lire et d'écrire des objets octets-compatibles.

- **chaîne entre triple guillemets** Chaîne qui est délimitée par trois guillemets simples (') ou trois guillemets doubles ("). Bien qu'elle ne fournisse aucune fonctionnalité qui ne soit pas disponible avec une chaîne entre guillemets, elle est utile pour de nombreuses raisons. Elle vous autorise à insérer des guillemets simples et doubles dans une chaîne sans avoir à les protéger et elle peut s'étendre sur plusieurs lignes sans avoir à terminer chaque ligne par un \. Elle est ainsi particulièrement utile pour les chaînes de documentation (*docstrings*).
- type Le type d'un objet Python détermine quel genre d'objet c'est. Tous les objets ont un type. Le type d'un objet peut être obtenu via son attribut __class__ ou via type (obj).
- alias de type Synonyme d'un type, créé en affectant le type à un identifiant.

Les alias de types sont utiles pour simplifier les *indications de types*. Par exemple :

pourrait être rendu plus lisible comme ceci :

```
Color = tuple[int, int, int]

def remove_gray_shades(colors: list[Color]) -> list[Color]:
    pass
```

Voir typing et la PEP 484, qui décrivent cette fonctionnalité.

indication de type L'*annotation* qui spécifie le type attendu pour une variable, un attribut de classe, un paramètre de fonction ou une valeur de retour.

Les indications de type sont facultatives et ne sont pas indispensables à l'interpréteur Python, mais elles sont utiles aux outils d'analyse de type statique et aident les IDE à compléter et à réusiner (*code refactoring* en anglais) le code.

Les indications de type de variables globales, d'attributs de classe et de fonctions, mais pas de variables locales, peuvent être consultées en utilisant typing.get_type_hints().

Voir typing et la PEP 484, qui décrivent cette fonctionnalité.

retours à la ligne universels Une manière d'interpréter des flux de texte dans lesquels sont reconnues toutes les fins de ligne suivantes : la convention Unix '\n', la convention Windows '\r\n' et l'ancienne convention Macintosh '\r'. Voir la PEP 278 et la PEP 3116, ainsi que la fonction bytes.splitlines() pour d'autres usages.

annotation de variable annotation d'une variable ou d'un attribut de classe.

Lorsque vous annotez une variable ou un attribut de classe, l'affectation est facultative :

```
class C:
    field: 'annotation'
```

Les annotations de variables sont généralement utilisées pour des *indications de types* : par exemple, cette variable devrait prendre des valeurs de type int :

```
count: int = 0
```

La syntaxe d'annotation de variable est expliquée dans la section annassign.

Reportez-vous à *annotation de fonction*, à la **PEP 484** et à la **PEP 526** qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.

environnement virtuel Environnement d'exécution isolé (en mode coopératif) qui permet aux utilisateurs de Python et aux applications d'installer et de mettre à jour des paquets sans interférer avec d'autres applications Python fonctionnant sur le même système.

Voir aussi venv.

machine virtuelle Ordinateur défini entièrement par du logiciel. La machine virtuelle (*virtual machine*) de Python exécute le *code intermédiaire* produit par le compilateur de *bytecode*.

Le zen de Python Liste de principes et de préceptes utiles pour comprendre et utiliser le langage. Cette liste peut être obtenue en tapant "import this" dans une invite Python interactive.

ANNEXE B

À propos de ces documents

Ces documents sont générés à partir de sources en reStructuredText par Sphinx, un analyseur de documents spécialement conçu pour la documentation Python.

Le développement de la documentation et de ses outils est entièrement basé sur le volontariat, tout comme Python. Si vous voulez contribuer, allez voir la page reporting-bugs qui contient des informations pour vous y aider. Les nouveaux volontaires sont toujours les bienvenus!

Merci beaucoup à :

- Fred L. Drake, Jr., créateur des outils originaux de la documentation Python et rédacteur de la plupart de son contenu:
- le projet Docutils pour avoir créé reStructuredText et la suite d'outils Docutils;
- Fredrik Lundh pour son projet *Alternative Python Reference*, dont Sphinx a pris beaucoup de bonnes idées.

B.1 Contributeurs de la documentation Python

De nombreuses personnes ont contribué au langage Python, à sa bibliothèque standard et à sa documentation. Consultez Misc/ACKS dans les sources de la distribution Python pour avoir une liste partielle des contributeurs.

Ce n'est que grâce aux suggestions et contributions de la communauté Python que Python a une documentation si merveilleuse — Merci!

ANNEXE C

Histoire et licence

C.1 Histoire du logiciel

Python a été créé au début des années 1990 par Guido van Rossum, au Stichting Mathematisch Centrum (CWI, voir https://www.cwi.nl/) aux Pays-Bas en tant que successeur d'un langage appelé ABC. Guido est l'auteur principal de Python, bien qu'il inclut de nombreuses contributions de la part d'autres personnes.

En 1995, Guido continua son travail sur Python au Corporation for National Research Initiatives (CNRI, voir https://www.cnri.reston.va.us/) de Reston, en Viriginie, d'où il diffusa plusieurs versions du logiciel.

En mai 2000, Guido et l'équipe de développement centrale de Python sont partis vers BeOpen.com pour former l'équipe BeOpen PythonLabs. En octobre de la même année, l'équipe de PythonLabs est partie vers Digital Creations (désormais Zope Corporation; voir https://www.zope.com/). En 2001, la Python Software Foundation (PSF, voir https://www.python.org/psf/) voit le jour. Il s'agit d'une organisation à but non lucratif détenant les droits de propriété intellectuelle de Python. Zope Corporation en est un sponsor.

Toutes les versions de Python sont Open Source (voir https://www.opensource.org/ pour la définition d'Open Source). Historiquement, la plupart, mais pas toutes, des versions de Python ont également été compatible avec la GPL, le tableau ci-dessous résume les différentes versions.

Version	Dérivé de	Année	Propriétaire	Compatible avec la GPL?
0.9.0 à 1.2	n/a	1991-1995	CWI	oui
1.3 à 1.5.2	1.2	1995-1999	CNRI	oui
1.6	1.5.2	2000	CNRI	non
2.0	1.6	2000	BeOpen.com	non
1.6.1	1.6	2001	CNRI	non
2.1	2.0+1.6.1	2001	PSF	non
2.0.1	2.0+1.6.1	2001	PSF	oui
2.1.1	2.1+2.0.1	2001	PSF	oui
2.1.2	2.1.1	2002	PSF	oui
2.1.3	2.1.2	2002	PSF	oui
2.2 et ultérieure	2.1.1	2001-maintenant	PSF	oui

Note: Compatible GPL ne signifie pas que nous distribuons Python sous licence GPL. Toutes les licences Python, excepté la licence GPL, vous permettent la distribution d'une version modifiée sans rendre open source ces changements. La licence « compatible GPL » rend possible la diffusion de Python avec un autre logiciel qui est lui, diffusé sous la licence GPL; les licences « non-compatibles GPL » ne le peuvent pas.

Merci aux nombreux bénévoles qui ont travaillé sous la direction de Guido pour rendre ces versions possibles.

C.2 Conditions générales pour accéder à, ou utiliser, Python

Le logiciel Python et sa documentation sont distribués sous la licence d'utilisation PSF.

Depuis Python 3.8.6, les exemples, recettes et autres codes présents dans la documentation sont sous la double licence d'utilisation PSF et *la licence Zero-Clause BSD*.

Certains logiciels faisant partie de Python sont soumis à d'autres licences. Ces licences sont incluses avec le code lié à celles-ci. Voir *Licences et remerciements pour les logiciels tiers* pour une liste non exhaustive de ces licences.

C.2.1 PSF LICENSE AGREEMENT FOR PYTHON 3.12.0

- 1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"), \Box and
- the Individual or Organization ("Licensee") accessing and otherwise using \rightarrow Python
 - 3.12.0 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, PSF hereby grants Licensee a nonexclusive, royalty-free, world-wide license to—reproduce,
 - analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 3.12.0 alone or in any derivative version, provided, however, that PSF's License Agreement and PSF's notice.
- copyright, i.e., "Copyright © 2001-2023 Python Software Foundation; All- \rightarrow Rights
 - Reserved" are retained in Python 3.12.0 alone or in any derivative version prepared by Licensee.
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 3.12.0 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee.
- agrees to include in any such work a brief summary of the changes made to→Python 3.12.0.
- 4. PSF is making Python 3.12.0 available to Licensee on an "AS IS" basis.
 PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
 EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION.
- WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT. \rightarrow THE

USE OF PYTHON 3.12.0 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.12.0 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT.

MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 3.12.0, OR ANY.

→DERIVATIVE

THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

its terms and conditions.

- 7. Nothing in this License Agreement shall be deemed to create any—relationship
- of agency, partnership, or joint venture between PSF and Licensee. This—License

Agreement does not grant permission to use PSF trademarks or trade name in \rightarrow a

trademark sense to endorse or promote products or services of Licensee, or→any third party.

8. By copying, installing or otherwise using Python 3.12.0, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.2 LICENCE D'UTILISATION BEOPEN.COM POUR PYTHON 2.0

LICENCE D'UTILISATION LIBRE BEOPEN PYTHON VERSION 1

- 1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
- 2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
- 3. BeOpen is making the Software available to Licensee on an "AS IS" basis.
 BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
 EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
 WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
 USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 5. This License Agreement will automatically terminate upon a material breach of

its terms and conditions.

- 6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at http://www.pythonlabs.com/logos.html may be used according to the permissions granted on that web page.
- 7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.3 LICENCE D'UTILISATION CNRI POUR PYTHON 1.6.1

- 1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the internet using the following URL: http://hdd.handle.net/1895.22/1013."
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
- 4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
- 8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.4 LICENCE D'UTILISATION CWI POUR PYTHON 0.9.0 à 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.2.5 LICENCE BSD ZERO-CLAUSE POUR LE CODE DANS LA DOCUMENTATION DE PYTHON 3.12.0

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT,

INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3 Licences et remerciements pour les logiciels tiers

Cette section est une liste incomplète mais grandissante de licences et remerciements pour les logiciels tiers incorporés dans la distribution de Python.

C.3.1 Mersenne twister

The _random C extension underlying the random module includes code based on a download from http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/MT2002/emt19937ar.html. The following are the verbatim comments from the original code:

A C-program for MT19937, with initialization improved 2002/1/26. Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init_genrand(seed) or init_by_array(init_key, key_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura, All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The names of its contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome. http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)

C.3.2 Interfaces de connexion (sockets)

The socket module uses the functions, getaddrinfo(), and getnameinfo(), which are coded in separate source files from the WIDE Project, https://www.wide.ad.jp/.

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.3 Interfaces de connexion asynchrones

The test.support.asynchat and test.support.asyncore modules contain the following notice:

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.4 Gestion de témoin (cookie)

Le module http.cookies contient la note suivante :

```
Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>
```

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Timothy O'Malley not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.5 Traçage d'exécution

Le module trace contient la note suivante :

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...
err... reserved and offered to the public under the terms of the
Python 2.2 license.
Author: Zooko O'Whielacronx
http://zooko.com/
mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.
Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.
```

Author: Skip Montanaro

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of neither Automatrix, Bioreason or Mojam Media be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

C.3.6 Les fonctions UUencode et UUdecode

Le module uu contient la note suivante :

Copyright 1994 by Lance Ellinghouse
Cathedral City, California Republic, United States of America.

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Lance Ellinghouse not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:

- Use binascii module to do the actual line-by-line conversion between ascii and binary. This results in a 1000-fold speedup. The C version is still 5 times faster, though.
- Arguments more compliant with Python standard

C.3.7 Appel de procédures distantes en XML (RPC, pour Remote Procedure Call)

Le module xmlrpc.client contient la note suivante :

The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB
Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.8 test_epoll

The test.test_epoll module contains the following notice:

Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.9 Select kqueue

Le module select contient la note suivante pour l'interface kqueue :

Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.10 SipHash24

Le fichier Python/pyhash.c contient une implémentation par Marek Majkowski de l'algorithme SipHash24 de Dan Bernstein. Il contient la note suivante :

```
<MIT License>
Copyright (c) 2013 Marek Majkowski <marek@popcount.org>
Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:
The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
</MIT License>
Original location:
  https://github.com/majek/csiphash/
Solution inspired by code from:
   Samuel Neves (supercop/crypto_auth/siphash24/little)
   djb (supercop/crypto_auth/siphash24/little2)
   Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)
```

C.3.11 strtod et dtoa

The file Python/dtoa.c, which supplies C functions dtoa and strtod for conversion of C doubles to and from strings, is derived from the file of the same name by David M. Gay, currently available from https://web.archive.org/web/20220517033456/http://www.netlib.org/fp/dtoa.c. The original file, as retrieved on March 16, 2009, contains the following copyright and licensing notice:

C.3.12 OpenSSL

The modules hashlib, posix, ssl, crypt use the OpenSSL library for added performance if made available by the operating system. Additionally, the Windows and macOS installers for Python may include a copy of the OpenSSL libraries, so we include a copy of the OpenSSL license here. For the OpenSSL 3.0 release, and later releases derived from that, the Apache License v2 applies:

```
Apache License
                        Version 2.0, January 2004
                     https://www.apache.org/licenses/
TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION
1. Definitions.
   "License" shall mean the terms and conditions for use, reproduction,
   and distribution as defined by Sections 1 through 9 of this document.
   "Licensor" shall mean the copyright owner or entity authorized by
   the copyright owner that is granting the License.
   "Legal Entity" shall mean the union of the acting entity and all
   other entities that control, are controlled by, or are under common
   control with that entity. For the purposes of this definition,
   "control" means (i) the power, direct or indirect, to cause the
   direction or management of such entity, whether by contract or
  otherwise, or (ii) ownership of fifty percent (50%) or more of the
   outstanding shares, or (iii) beneficial ownership of such entity.
```

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

- 2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.
- 3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their

Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

- 4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:
 - (a) You must give any other recipients of the Work or Derivative Works a copy of this License; and
 - (b) You must cause any modified files to carry prominent notices stating that You changed the files; and
 - (c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
 - (d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

- 6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.
- 7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.
- 8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.
- 9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

C.3.13 expat

The pyexpat extension is built using an included copy of the expat sources unless the build is configured --with-system-expat:

Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to

(suite sur la page suivante)

the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.14 libffi

The _ctypes C extension underlying the ctypes module is built using an included copy of the libfli sources unless the build is configured --with-system-libffi:

Copyright (c) 1996-2008 Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the ``Software''), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.15 zlib

Le module zlib est compilé en utilisant une copie du code source de *zlib* si la version de *zlib* trouvée sur le système est trop vieille pour être utilisée :

Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it

(suite sur la page suivante)

freely, subject to the following restrictions:

- The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly Mark Adler

jloup@gzip.org madler@alumni.caltech.edu

C.3.16 cfuhash

L'implémentation des dictionnaires, utilisée par le module tracemalloc est basée sur le projet cfuhash:

Copyright (c) 2005 Don Owens All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.17 libmpdec

The $_decimal\ C$ extension underlying the $decimal\ module$ is built using an included copy of the libmpdec library unless the build is configured --with-system-libmpdec:

Copyright (c) 2008-2020 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.18 Ensemble de tests C14N du W3C

Les tests de C14N version 2.0 du module test (Lib/test/xmltestdata/c14n-20/) proviennent du site du W3C à l'adresse https://www.w3.org/TR/xml-c14n2-testcases/ et sont distribués sous licence BSD modifiée :

Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang), All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of works must retain the original copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the original copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name of the W3C nor the names of its contributors may be used to endorse or promote products derived from this work without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,

(suite sur la page suivante)

SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.19 Audioop

The audioop module uses the code base in g771.c file of the SoX project:

Programming the AdLib/Sound Blaster FM Music Chips Version 2.0 (24 Feb 1992) Copyright (c) 1991, 1992 by Jeffrey S. Lee jlee@smylex.uucp Warranty and Copyright Policy This document is provided on an "as-is" basis, and its author makes no warranty or representation, express or implied, with respect to its quality performance or fitness for a particular purpose. In no event will the author of this document be liable for direct, indirect, special, incidental, or consequential damages arising out of the use or inability to use the information contained within. Use of this document is at your own risk. This file may be used and copied freely so long as the applicable copyright notices are retained, and no modifications are made to the text of the document. No money shall be charged for its distribution beyond reasonable shipping, handling and duplication costs, nor shall proprietary changes be made to this document so that it cannot be distributed freely. This document may not be included in published material or commercial packages without the written consent of its author.

ANNEXE	U

Copyright

Python et cette documentation sont :

Copyright $\ensuremath{\mathbb{C}}$ 2001-2023 Python Software Foundation. All rights reserved.

Copyright © 2000 BeOpen.com. Tous droits réservés.

Copyright © 1995-2000 Corporation for National Research Initiatives. Tous droits réservés.

Copyright © 1991-1995 Stichting Mathematisch Centrum. Tous droits réservés.

Voir *Histoire et licence* pour des informations complètes concernant la licence et les permissions.

Non alphabétique _PyInterpreterState_SetEvalFrameFunc (Cfunction), 195 . . . , 287 _PyObject_GetDictPtr(C function), 83 2to3, 287 _PyObject_New (C function), 235 >>>, 287 _PyObject_NewVar (C function), 235 __all__ (package variable), 64 _PyTuple_Resize (C function), 141 __dict__ (module attribute), 158 _thread __doc__ (module attribute), 158 module, 192 ___file___ (module attribute), 158, 159 __future__, 292 Α ___import___ abort (), 64 built-in function, 64 abs __loader__ (module attribute), 158 built-in function, 92 ___main___ alias de type, 299 module, 12, 185, 198 allocfunc (C type), 275 __name__ (module attribute), 158 annotation, 287 __package__ (module attribute), 158 annotation de fonction, 291 ___PYVENV_LAUNCHER___, 212, 217 annotation de variable, 300 __slots__, **298** API provisoire, 297 _frozen (C struct), 67 appelable (callable), 289 _inittab (C struct), 67 argument, 287 _inittab.name (C member), 67 argument nommé, 294 _Py_c_diff (C function), 119 argument positionnel, 297 _Py_c_neg (*C function*), 119 argv (in module sys), 188 _Py_c_pow (*C function*), 119 arrêt de l'interpréteur, 293 _Py_c_prod (*C function*), 119 ascii _Py_c_quot (*C function*), 119 built-in function, 83 _Py_c_sum (*C function*), 119 attendable (awaitable), 288 _Py_InitializeMain(C function), 223 attribut. 288 _Py_NoneStruct (C var), 236 _PyBytes_Resize (*C function*), 122 _PyCFunctionFast (Ctype), 238 BDFL, 288 _PyCFunctionFastWithKeywords (Ctype), 238 binaryfunc (Ctype), 277 PyCode GetExtra, 156 buffer interface _PyCode_SetExtra, 156 (see buffer protocol), 98 _PyEval_RequestCodeExtraIndex, 156 buffer object _PyFrameEvalFunction (C type), 195 (see buffer protocol), 98 _PyInterpreterFrame (C struct), 173 buffer protocol, 98 _PyInterpreterState_GetEvalFrameFunc (Cbuilt-in function function), 195 __import__,64

abs, 92	D
ascii,83	décorateur, 290
bytes, 84	descreet func (C type), 276
classmethod, 240	descripteur, 290
compile,65	descriset func (C type), 276
divmod, 91	destructor (<i>C type</i>), 276
float,93	dictionary
hash, 84, 255	object, 144
int,93	dictionnaire, 290
len, 85, 94, 96, 143, 146, 149	dictionnaire en compréhension (ou diction-
рож, 91, 93	naire en intension), 290
repr, 83, 255	distribution simple, 299
staticmethod, 240	division entière, 291
tuple, 95, 144	divmod
type, 84	built-in function, 91
builtins	
module, 12, 185, 198	E
bytearray	EAFP, 291
object, 123	encodage du système de fichiers et
bytes	gestionnaire d'erreurs associé,
built-in function, 84	291
object, 121	encodage régional, 294
0	encodages de texte, 299
C	ensemble en compréhension (ou ensemble en in-
calloc(), 225	tension), 299
Capsule	entrée de chemin, 297
object, 170	environnement virtuel, 300
C-contiguous, 101, 289	EOFError (built-in exception), 157
chaîne de documentation (docstring), 290	espace de nommage, 296
chaîne entre triple guillemets, 299	exc_info() (in module sys), 11
chargeur, 295	executable (in module sys), 187
chemin des importations, 293	exit(),64
chercheur, 291	expression, 291
chercheur basé sur les chemins, 297	expression génératrice, 292
chercheur dans les méta-chemins, 295	F
chercheur de chemins, 297	Г
classe, 289	f-string, 291
classe mère abstraite, 287	fichier binaire, 288
classmethod	fichier texte, 299
built-in function, 240	file
cleanup functions, 64	object, 157
close() (in module os), 198	float
CO_FUTURE_DIVISION (C var), 39	built-in function, 93
code intermédiaire (bytecode), 289	floating point
code object, 153	object, 117
compile	fonction, 291
built-in function, 65	fonction clé, 294
complex number	fonction coroutine, 290
object, 119	fonction de rappel (callback), 289
contigu, 289	fonction générique, 292
contiguous, 101	Fortran contiguous, 101, 289
copyright (in module sys), 188	free(),225
coroutine, 290	freefunc ($C type$), 276
CPython, 290	freeze utility,67

frozenset	L
object, 148	lambda, 294
function	LBYL, 294
object, 150	Le zen de Python, 300
	len
G	built-in function, 85, 94, 96, 143, 146, 149
gcvisitobjects_t (<i>C type</i>), 283	lenfunc (<i>C type</i>), 276
générateur, 292	list
générateur asynchrone, 288	object, 142
gestionnaire de contexte, 289	liste, 294
gestionnaire de contexte asynchrone, 288	liste en compréhension (ou liste en intension),
getattrfunc ($C type$), 276	294
getattrofunc (C type), 276	lock, interpreter, 189
getbufferproc(<i>C type</i>), 276	long integer
getiterfunc (<i>C type</i>), 276	object, 113
GIL, 292	LONG_MAX, 114
global interpreter lock, 189	
	M
H	machine virtuelle, 300
hachable, 293	magic
hash	méthode, 295
built-in function, 84, 255	main(), 186, 188
hashfunc (<i>C type</i>), 276	malloc(), 225
nashrane (Crype), 270	mapping
	object, 144
IDIE 303	memoryview
IDLE, 293	object, 168
immuable, 293	métaclasse, 295
importateur, 293	METH_CLASS (C macro), 240
importation, 293	METH_COEXIST (C macro), 240
incr_item(),11,12	METH_FASTCALL (<i>C macro</i>), 239
indication de type, 300	METH_KEYWORDS (C macro), 239
initproc (<i>C type</i>), 276 inquiry (<i>C type</i>), 282	METH_METHOD (C macro), 239
· · · · · ·	METH_NOARGS (<i>C macro</i>), 240
instancemethod object,152	METH_O (<i>C macro</i>), 240
instruction, 299	METH_STATIC (C macro), 240
int	METH_VARARGS (C macro), 239
built-in function, 93	method
integer	object, 152
object, 113	méthode, 295
interactif, 293	magic, 295
interactif, 293	special, 299
interpreter lock, 189	méthode magique, 295
itérable, 293	méthode spéciale, 299
itérable asynchrone, 288	MethodType (in module types), 150, 152
itérateur, 294	module, 295
itérateur asynchrone, 288	main, 12, 185, 198
itérateur de générateur, 292	thread, 192
itérateur de générateur asynchrone, 288	builtins, 12, 185, 198
iterateur de generateur asynchrone, 200 iternextfunc (C type), 276	object, 158
recentioner and (o type), 210	search path, 12, 185, 187
K	signal, 52, 53
	sys, 12, 185, 198
KeyboardInterrupt (built-in exception), 52, 53	module d'extension, 291

modules (in module sys), 64, 185	Р
ModuleType (in module types), 158	package variable
MRO, 295	all,64
muable, 295	arr,04 paquet, 296
	paquet classique, 298
N	paquet provisoire, 297
n-uplet nommé, 295	·
newfunc (<i>C type</i>), 276	paquet-espace de nommage, 296
nom qualifié, 298	paramètre, 296
nombre complexe, 289	PATH, 12, 13
nombre de références, 298	path
None	module search, 12, 185, 187
object, 113	path (in module sys), 12, 185, 187
nouvelle classe, 296	PEP, 297
	platform (in module sys), 188
numeric	point d'entrée pour la recherche dans
object, 113	path, 297
0	portée imbriquée, 296
O	portion, 297
object	pow
bytearray, 123	built-in function, 91, 93
bytes, 121	Py_ABS (C macro), 5
Capsule, 170	Py_AddPendingCall (C function), 200
code, 153	Py_AddPendingCall(),200
complex number, 119	Py_ALWAYS_INLINE (C macro), 5
dictionary, 144	Py_AtExit (C function), 64
file, 157	Py_AUDIT_READ (<i>C macro</i>), 241
floating point, 117	Py_BEGIN_ALLOW_THREADS, 190
frozenset, 148	Py_BEGIN_ALLOW_THREADS (C macro), 193
function, 150	Py_BLOCK_THREADS (<i>C macro</i>), 193
instancemethod, 152	Py_buffer (C type), 99
integer, 113	Py_buffer.buf(C member), 99
list, 142	Py_buffer.format(<i>C member</i>), 99
	Py_buffer.internal (C member), 100
long integer, 113	
mapping, 144	Py_buffer.itemsize(C member), 99
memoryview, 168	Py_buffer.len(C member), 99
method, 152	Py_buffer.ndim(<i>C member</i>), 99
module, 158	Py_buffer.obj(C member),99
None, 113	Py_buffer.readonly(<i>C member</i>), 99
numeric, 113	Py_buffer.shape(<i>C member</i>), 100
sequence, 120	Py_buffer.strides(<i>C member</i>), 100
set, 148	Py_buffer.suboffsets(<i>C member</i>), 100
tuple, 140	Py_BuildValue (C function), 74
type, 7, 107	Py_BytesMain (C function), 35
objet, 296	Py_BytesWarningFlag($C\ var$), 182
objet fichier, 291	Py_CHARMASK (C macro), 5
objet fichier-compatible, 291	Py_CLEAR (C function), 42
objet octet-compatible, 289	Py_CompileString (C function), 37
objet simili-chemin, 297	Py_CompileString(),38,39
objobjargproc (<i>C type</i>), 277	Py_CompileStringExFlags(C function), 38
objobjproc (<i>C type</i>), 277	Py_CompileStringFlags (C function), 37
ordre de résolution des méthodes, 295	Py_CompileStringObject(C function), 38
OverflowError (built-in exception), 114, 115	Py_complex ($C type$), 119
	Py_DebugFlag (C var), 182
	Py_DecodeLocale (C function), 60

Py_DECREF (C function), 42	Py_InspectFlag(<i>C var</i>), 183
Py_DecRef (C function), 43	Py_InteractiveFlag(Cvar),183
Py_DECREF(),7	Py_Is (C function), 237
Py_DEPRECATED (C macro), 5	Py_IS_TYPE (C function), 237
Py_DontWriteBytecodeFlag(Cvar), 182	Py_IsFalse (C function), 237
Py_Ellipsis (C var), 168	Py_IsInitialized (C function), 185
Py_EncodeLocale (<i>C function</i>), 61	Py_IsInitialized(),13
Py_END_ALLOW_THREADS, 190	Py_IsNone (C function), 237
Py_END_ALLOW_THREADS (C macro), 193	Py_IsolatedFlag(C var), 183
Py_EndInterpreter (C function), 199	Py_IsTrue (C function), 237
Py_EnterRecursiveCall (C function), 56	Py_LE (<i>C macro</i>), 263
Py_EQ (<i>C macro</i>), 263	Py_LeaveRecursiveCall (C function), 56
Py_eval_input (<i>C var</i>), 38	Py_LegacyWindowsFSEncodingFlag(Cvar), 183
Py_Exit (C function), 64	Py_LegacyWindowsStdioFlag(Cvar), 183
Py_ExitStatusException (C function), 207	Py_LIMITED_API (<i>C macro</i>), 16
Py_False (<i>C var</i>), 116	Py_LT (<i>C macro</i>), 263
Py_FatalError (<i>C function</i>), 64	Py_Main (C function), 35
Py_FatalError(), 188	PY_MAJOR_VERSION (C macro), 285
Py_FdIsInteractive (<i>C function</i>), 59	Py_MAX (<i>C macro</i>), 5
Py_file_input (C var), 38	Py_MEMBER_SIZE (C macro), 5
Py_Finalize (<i>C function</i>), 185	PY_MICRO_VERSION (C macro), 285
Py_FinalizeEx (C function), 185	Py_MIN (<i>C macro</i>), 5
Py_FinalizeEx(), 64, 185, 198, 199	PY_MINOR_VERSION (C macro), 285
Py_FrozenFlag (<i>C var</i>), 182	Py_mod_create (<i>C macro</i>), 161
Py_GE (<i>C macro</i>), 263	Py_mod_exec (<i>C macro</i>), 162
Py_GenericAlias (<i>C function</i>), 179	Py_mod_multiple_interpreters (<i>C macro</i>), 162
Py_GenericAliasType (C var), 180	Py_MOD_MULTIPLE_INTERPRETERS_NOT_SUPPORTED
Py_GetArgcArgv (C function), 223	(<i>C macro</i>), 162
Py_GetBuildInfo (<i>C function</i>), 188	Py_MOD_MULTIPLE_INTERPRETERS_SUPPORTED
Py_GetCompiler (C function), 188	(C macro), 162
Py_GetCopyright (C function), 188	Py_MOD_PER_INTERPRETER_GIL_SUPPORTED (C
Py_GETENV (C macro), 5	macro), 162
Py_GetExecPrefix (C function), 186	Py_NE (<i>C macro</i>), 263
Py_GetExecPrefix(),13	Py_NewInterpreter (<i>C function</i>), 198
Py_GetPath (C function), 187	Py_NewInterpreterFromConfig(Cfunction), 198
Py_GetPath(), 13, 186, 187	Py_NewRef (C function), 41
Py_GetPlatform (C function), 188	Py_NO_INLINE (C macro), 6
Py_GetPrefix (C function), 186	Py_None (<i>C var</i>), 113
Py_GetPrefix(), 13	Py_NoSiteFlag(Cvar), 184
Py_GetProgramFullPath (C function), 187	Py_NotImplemented (C var), 81
Py_GetProgramFullPath(), 13	Py_NoUserSiteDirectory (<i>C var</i>), 184
Py_GetProgramName (C function), 186	Py_OptimizeFlag (<i>C var</i>), 184
Py_GetPythonHome (C function), 189	Py_PreInitialize (<i>C function</i>), 209
Py_GetVersion (<i>C function</i>), 187	Py_PreInitializeFromArgs (C function), 209
Py_GT (<i>C macro</i>), 263	Py_PreInitializeFromBytesArgs (C function),
Py_HashRandomizationFlag (C var), 182	209
Py_IgnoreEnvironmentFlag (C var), 183	Py_PRINT_RAW, 157
Py_INCREF (C function), 41	Py_QuietFlag (C var), 184
Py_IncRef (C function), 42	Py_READONLY (C macro), 241
Py_INCREF(),7	Py_REFCNT (C function), 41
Py_Initialize (C function), 185	Py_RELATIVE_OFFSET (C macro), 241
Py_Initialize(), 12, 186, 198	PY_RELEASE_LEVEL (C macro), 285
Py_InitializeEx (C function), 185	PY_RELEASE_SERIAL (C macro), 285
Py_InitializeFromConfig(C function), 219	Py_ReprEnter (C function), 56

Py_ReprLeave (C function), 56	Py_TPFLAGS_LIST_SUBCLASS (C macro), 259
Py_RETURN_FALSE (C macro), 117	Py_TPFLAGS_LONG_SUBCLASS (C macro), 259
Py_RETURN_NONE (C macro), 113	Py_TPFLAGS_MANAGED_DICT (C macro), 258
Py_RETURN_NOTIMPLEMENTED (C macro), 81	Py_TPFLAGS_MANAGED_WEAKREF (C macro), 258
Py_RETURN_RICHCOMPARE (C macro), 263	Py_TPFLAGS_MAPPING (C macro), 260
Py_RETURN_TRUE (C macro), 117	Py_TPFLAGS_METHOD_DESCRIPTOR (C macro), 258
Py_RunMain (<i>C function</i>), 223	Py_TPFLAGS_READY (C macro), 257
Py_SET_REFCNT (C function), 41	Py_TPFLAGS_READYING (C macro), 257
Py_SET_SIZE (C function), 237	Py_TPFLAGS_SEQUENCE (C macro), 260
Py_SET_TYPE (C function), 237	Py_TPFLAGS_TUPLE_SUBCLASS (C macro), 259
Py_SetPath (C function), 187	Py_TPFLAGS_TYPE_SUBCLASS (C macro), 259
Py_SetPath(), 187	Py_TPFLAGS_UNICODE_SUBCLASS (C macro), 259
Py_SetProgramName (C function), 186	Py_TPFLAGS_VALID_VERSION_TAG (C macro), 260
Py_SetProgramName(), 13, 185187	Py_tracefunc ($Ctype$), 200
Py_SetPythonHome (C function), 189	Py_True (<i>C var</i>), 116
Py_SETREF (C macro), 43	Py_tss_NEEDS_INIT (C macro), 203
Py_SetStandardStreamEncoding (C function),	Py_tss_t (<i>C type</i>), 203
186	Py_TYPE (<i>C function</i>), 237
Py_single_input (C var), 38	Py_UCS1 (<i>C type</i>), 124
Py_SIZE (C function), 237	Py_UCS2 (<i>C type</i>), 124
Py_ssize_t (C type), 10	Py_UCS4 (<i>C type</i>), 124
PY_SSIZE_T_MAX, 115	Py_UNBLOCK_THREADS (C macro), 193
Py_STRINGIFY (C macro), 6	Py_UnbufferedStdioFlag(Cvar), 184
Py_T_BOOL (<i>C macro</i>), 243	Py_UNICODE (C type), 124
Py_T_BYTE (<i>C macro</i>), 243	Py_UNICODE_IS_HIGH_SURROGATE (C function),
Py_T_CHAR (<i>C macro</i>), 243	127
Py_T_DOUBLE (<i>C macro</i>), 243	Py_UNICODE_IS_LOW_SURROGATE (C function), 127
Py_T_FLOAT (C macro), 243	Py_UNICODE_IS_SURROGATE (C function), 127
Py_T_INT (C macro), 243	Py_UNICODE_ISALNUM (C function), 126
Py_T_LONG (<i>C macro</i>), 243	Py_UNICODE_ISALPHA (C function), 126
Py_T_LONGLONG (C macro), 243	Py_UNICODE_ISDECIMAL (C function), 126
Py_T_OBJECT_EX (C macro), 243	Py_UNICODE_ISDIGIT (C function), 126
Py_T_PYSSIZET (C macro), 243	Py_UNICODE_ISLINEBREAK (<i>C function</i>), 126
Py_T_SHORT (<i>C macro</i>), 243	Py_UNICODE_ISLOWER (C function), 126
Py_T_STRING (<i>C macro</i>), 243	Py_UNICODE_ISNUMERIC (C function), 126
Py_T_STRING_INPLACE (C macro), 243	Py_UNICODE_ISPRINTABLE (<i>C function</i>), 126
Py_T_UBYTE (<i>C macro</i>), 243	Py_UNICODE_ISSPACE (C function), 126
Py_T_UINT (<i>C macro</i>), 243	Py_UNICODE_ISTITLE (<i>C function</i>), 126
Py_T_ULONG (C macro), 243	Py_UNICODE_ISUPPER (<i>C function</i>), 126
Py_T_ULONGLONG (C macro), 243	Py_UNICODE_JOIN_SURROGATES (<i>C function</i>), 127
Py_T_USHORT (C macro), 243	Py_UNICODE_TODECIMAL (<i>C function</i>), 127
Py_TPFLAGS_BASE_EXC_SUBCLASS (<i>C macro</i>), 259	Py_UNICODE_TODIGIT (<i>C function</i>), 127
Py_TPFLAGS_BASETYPE (C macro), 257	Py_UNICODE_TOLOWER (<i>C function</i>), 126
Py_TPFLAGS_BYTES_SUBCLASS (C macro), 259	Py_UNICODE_TOLOWER (C function), 120 Py_UNICODE_TONUMERIC (C function), 127
Py_TPFLAGS_DEFAULT (C macro), 258	- · · · · · · · · · · · · · · · · · · ·
- - , , , , , , , , , , , , , , , , , ,	Py_UNICODE_TOTITLE (C function), 127
Py_TPFLAGS_DICT_SUBCLASS (<i>C macro</i>), 259	Py_UNICODE_TOUPPER (C function), 126
Py_TPFLAGS_DISALLOW_INSTANTIATION (C ma-	Py_UNREACHABLE (C macro), 6
cro), 259	Py_UNUSED (C macro), 6
Py_TPFLAGS_HAVE_FINALIZE (C macro), 259	Py_VaBuildValue (<i>C function</i>), 75
Py_TPFLAGS_HAVE_GC (C macro), 258	PY_VECTORCALL_ARGUMENTS_OFFSET (C macro),
Py_TPFLAGS_HAVE_VECTORCALL (C macro), 259	87
Py_TPFLAGS_HEAPTYPE (C macro), 257	Py_VerboseFlag (<i>C var</i>), 184
Py_TPFLAGS_IMMUTABLETYPE (C macro), 259	Py_Version (<i>C var</i>), 286
Py_TPFLAGS_ITEMS_AT_END (C macro), 258	PY_VERSION_HEX (C macro), 285

Py_VISIT (C function), 281	PyBufferProcs, 98
Py_XDECREF (C function), 42	PyBufferProcs (C type), 274
Py_XDECREF(), 12	PyBufferProcs.bf_getbuffer(<i>C member</i>), 274
Py_XINCREF (C function), 41	PyBufferProcs.bf_releasebuffer(Cmember),
Py_XNewRef (C function), 42	274
Py_XSETREF (C macro), 43	PyByteArray_AS_STRING(C function), 123
PyAIter_Check (<i>C function</i>), 97	PyByteArray_AsString (C function), 123
PyAnySet_Check (<i>C function</i>), 148	PyByteArray_Check (C function), 123
PyAnySet_CheckExact (<i>C function</i>), 148	PyByteArray_CheckExact (C function), 123
PyArg_Parse (C function), 73	PyByteArray_Concat (C function), 123
PyArg_ParseTuple (C function), 73	PyByteArray_FromObject (C function), 123
PyArg_ParseTupleAndKeywords (C function), 73	PyByteArray_FromStringAndSize ($C\ function$),
PyArg_UnpackTuple (C function), 73	123
PyArg_ValidateKeywordArguments ($C\ func-$	PyByteArray_GET_SIZE (C function), 123
tion), 73	PyByteArray_Resize(Cfunction), 123
PyArg_VaParse (C function), 73	PyByteArray_Size (C function), 123
PyArg_VaParseTupleAndKeywords (\emph{C} function),	PyByteArray_Type (<i>C var</i>), 123
73	PyByteArrayObject (Ctype), 123
PyASCIIObject (<i>Ctype</i>), 124	PyBytes_AS_STRING (C function), 122
PyAsyncMethods (<i>C type</i>), 275	PyBytes_AsString (C function), 122
PyAsyncMethods.am_aiter(<i>C member</i>), 275	PyBytes_AsStringAndSize(C function), 122
PyAsyncMethods.am_anext(<i>C member</i>), 275	PyBytes_Check (C function), 121
PyAsyncMethods.am_await(<i>C member</i>), 275	PyBytes_CheckExact (C function), 121
PyAsyncMethods.am_send($\emph{C member}$), 275	PyBytes_Concat (C function), 122
PyBool_Check (<i>C function</i>), 116	PyBytes_ConcatAndDel ($C\ function$), 122
PyBool_FromLong (C function), 117	PyBytes_FromFormat (<i>C function</i>), 121
PyBool_Type ($C var$), 116	PyBytes_FromFormatV (C function), 121
PyBUF_ANY_CONTIGUOUS (C macro), 102	PyBytes_FromObject(Cfunction), 122
PyBUF_C_CONTIGUOUS (C macro), 102	PyBytes_FromString(Cfunction), 121
PyBUF_CONTIG (<i>C macro</i>), 102	PyBytes_FromStringAndSize(C function), 121
PyBUF_CONTIG_RO (<i>C macro</i>), 102	PyBytes_GET_SIZE (<i>C function</i>), 122
PyBUF_F_CONTIGUOUS (C macro), 102	PyBytes_Size (C function), 122
PyBUF_FORMAT (<i>C macro</i>), 101	PyBytes_Type (C var), 121
PyBUF_FULL (<i>C macro</i>), 102	PyBytesObject (C type), 121
PyBUF_FULL_RO (<i>C macro</i>), 102	pyc utilisant le hachage, 293
PyBUF_INDIRECT (C macro), 101	PyCallable_Check (C function), 90
PyBUF_MAX_NDIM (C macro), 100	PyCallIter_Check (C function), 166
PyBUF_ND (<i>C macro</i>), 101	PyCallIter_New (C function), 166
PyBUF_RECORDS (C macro), 102	PyCallIter_Type (<i>C var</i>), 166
PyBUF_RECORDS_RO (C macro), 102	PyCapsule ($Ctype$), 170
PyBUF_SIMPLE (<i>C macro</i>), 101	PyCapsule_CheckExact (C function), 170
PyBUF_STRIDED (C macro), 102	PyCapsule_Destructor(<i>Ctype</i>), 170
PyBUF_STRIDED_RO (C macro), 102	PyCapsule_GetContext (C function), 170
PyBUF_STRIDES (C macro), 101	PyCapsule_GetDestructor(C function), 170
PyBUF_WRITABLE (<i>C macro</i>), 101	PyCapsule_GetName (C function), 170
PyBuffer_FillContiguousStrides (C func-	PyCapsule_GetPointer(C function), 170
tion), 105	PyCapsule_Import (C function), 170
PyBuffer_FillInfo(<i>C function</i>), 105	PyCapsule_IsValid (C function), 171
PyBuffer_FromContiguous (C function), 104	PyCapsule_New (C function), 170
PyBuffer_GetPointer (C function), 104	PyCapsule_SetContext (C function), 171
PyBuffer_IsContiguous (<i>C function</i>), 104	PyCapsule_SetDestructor (C function), 171
PyBuffer_Release (C function), 104	PyCapsule_SetName (C function), 171
PyBuffer_SizeFromFormat ($C\mathit{function}$), 104	PyCapsule_SetPointer (C function), 171
PyBuffer_ToContiguous (<i>C function</i>), 104	PyCell_Check (C function), 153

PyCell_GET (C function), 153	PyComplex_Check (C function), 120
PyCell_Get (C function), 153	PyComplex_CheckExact (C function), 120
PyCell_New (C function), 153	PyComplex_FromCComplex(C function), 120
PyCell_SET (C function), 153	PyComplex_FromDoubles (C function), 120
PyCell_Set (C function), 153	PyComplex_ImagAsDouble (<i>C function</i>), 120
PyCell_Type ($C var$), 153	PyComplex_RealAsDouble (C function), 120
PyCellObject (C type), 153	PyComplex_Type (C var), 120
PyCFunction (C type), 238	PyComplexObject (C type), 120
PyCFunctionWithKeywords (<i>Ctype</i>), 238	PyConfig (<i>C type</i>), 210
PyCMethod (C type), 238	PyConfig_Clear (<i>C function</i>), 211
PyCode_Addr2Line (<i>C function</i>), 154	PyConfig_InitIsolatedConfig(Cfunction), 210
PyCode_Addr2Location (C function), 154	PyConfig_InitPythonConfig (C function), 210
PyCode_AddWatcher (C function), 155	PyConfig_Read (<i>C function</i>), 211
PyCode_Check (<i>C function</i>), 153	PyConfig_SetArgv (C function), 211
PyCode_ClearWatcher(C function), 155	PyConfig_SetBytesArgv (C function), 211
PyCode_GetCellvars(<i>C function</i>), 155	PyConfig_SetBytesString (C function), 210
PyCode_GetCode (C function), 154	PyConfig_SetString (C function), 210
PyCode_GetFreevars (<i>C function</i>), 155	PyConfig_SetWideStringList (C function), 211
PyCode_GetNumFree (C function), 153	PyConfig.argv (C member), 211
PyCode_GetVarnames (<i>C function</i>), 155	PyConfig.base_exec_prefix(<i>C member</i>), 212
PyCode_New, 154	PyConfig.base_executable (C member), 212
PyCode_NewEmpty (C function), 154	PyConfig.base_prefix(C member), 212
PyCode_NewWithPosOnlyArgs, 154	PyConfig.buffered_stdio(<i>C member</i>), 212
PyCode_Type (C var), 153	PyConfig.bytes_warning(C member), 212
PyCode_WatchCallback(<i>Ctype</i>), 155	PyConfig.check_hash_pycs_mode (<i>C member</i>),
<pre>PyCodec_BackslashReplaceErrors (C func- tion), 79</pre>	212 PyConfig.code_debug_ranges (<i>C member</i>), 212
PyCodec_Decode (<i>C function</i>), 78	PyConfig.configure_c_stdio (C member), 213
PyCodec_Decoder (<i>C function</i>), 78	PyConfig.dev_mode (C member), 213
PyCodec_Encode (<i>C function</i>), 78	PyConfig.dump_refs(<i>C member</i>), 213
PyCodec_Encoder (<i>C function</i>), 78	PyConfig.exec_prefix (C member), 213
PyCodec_IgnoreErrors (C function), 79	PyConfig.executable (C member), 213
PyCodec_IncrementalDecoder (<i>C function</i>), 78	PyConfig.faulthandler (<i>C member</i>), 213
PyCodec_IncrementalEncoder (<i>C function</i>), 78	PyConfig.filesystem_encoding (C member),
PyCodec_KnownEncoding (C function), 78	2.13
PyCodec_LookupError (<i>C function</i>), 79	PyConfig.filesystem_errors (<i>C member</i>), 214
PyCodec_NameReplaceErrors (<i>C function</i>), 79	PyConfig.hash_seed(<i>C member</i>), 214
PyCodec_Register (<i>C function</i>), 78	PyConfig.home (C member), 214
PyCodec_RegisterError(<i>C function</i>), 79	PyConfig.import_time (C member), 214
PyCodec_ReplaceErrors (<i>C function</i>), 79	PyConfig.inspect (C member), 214
PyCodec_StreamReader (<i>C function</i>), 78	PyConfig.install_signal_handlers (C mem-
PyCodec_StreamWriter (<i>C function</i>), 78	ber), 214
PyCodec_StrictErrors (C function), 79	PyConfig.int_max_str_digits(C member), 214
PyCodec_Unregister (C function), 78	PyConfig.interactive (<i>C member</i>), 214
PyCodec_XMLCharRefReplaceErrors (C func-	PyConfig.isolated (C member), 215
tion), 79	PyConfig.legacy_windows_stdio (C member),
PyCodeEvent (<i>C type</i>), 155	215
PyCodeObject (C type), 153	PyConfig.malloc_stats(C member), 215
PyCompactUnicodeObject (<i>C type</i>), 124	PyConfig.module_search_paths (<i>C member</i>),
PyCompilerFlags (<i>C struct</i>), 39	215
	PyConfig.module_search_paths_set (C mem-
member), 39	ber), 215
PyCompilerFlags.cf_flags(<i>C member</i>), 39	PyConfig.optimization_level(<i>C member</i>), 216
PyComplex_AsCComplex (C function), 120	PyConfig.orig_argv(<i>C member</i>), 216

PyConfig.parse_argv(C member), 216	PyDate_Check (C function), 176
PyConfig.parser_debug(C member), 216	PyDate_CheckExact (C function), 176
PyConfig.pathconfig_warnings (C member),	PyDate_FromDate (C function), 177
216	PyDate_FromTimestamp(C function), 179
PyConfig.perf_profiling(C member), 218	PyDateTime_Check (C function), 176
PyConfig.platlibdir(C member), 215	PyDateTime_CheckExact (C function), 176
PyConfig.prefix (C member), 216	PyDateTime_Date(Ctype), 176
PyConfig.program_name (C member), 216	PyDateTime_DATE_GET_FOLD (C function), 178
PyConfig.pycache_prefix(C member), 217	PyDateTime_DATE_GET_HOUR (C function), 178
PyConfig.pythonpath_env(C member), 215	PyDateTime_DATE_GET_MICROSECOND ($C\ func-$
PyConfig.quiet (C member), 217	tion), 178
PyConfig.run_command(<i>C member</i>), 217	PyDateTime_DATE_GET_MINUTE (C function), 178
PyConfig.run_filename (C member), 217	PyDateTime_DATE_GET_SECOND (C function), 178
PyConfig.run_module(<i>C member</i>), 217	PyDateTime_DATE_GET_TZINFO (C function), 178
PyConfig.safe_path(C member), 211	PyDateTime_DateTime (C type), 176
PyConfig.show_ref_count(C member), 217	PyDateTime_DateTimeType (C var), 176
PyConfig.site_import (C member), 217	PyDateTime_DateType (C var), 176
PyConfig.skip_source_first_line (C mem-	PyDateTime_Delta(C type), 176
ber), 217	PyDateTime_DELTA_GET_DAYS (C function), 179
PyConfig.stdio_encoding(C member), 218	PyDateTime_DELTA_GET_MICROSECONDS (C
PyConfig.stdio_errors(C member), 218	function), 179
PyConfig.tracemalloc(C member), 218	PyDateTime_DELTA_GET_SECONDS (C function),
PyConfig.use_environment (<i>C member</i>), 218	179
PyConfig.use_hash_seed(C member), 214	PyDateTime_DeltaType(C var), 176
PyConfig.user_site_directory (C member),	PyDateTime_FromDateAndTime (<i>C function</i>), 177
218	PyDateTime_FromDateAndTimeAndFold (C
PyConfig.verbose(<i>C member</i>), 218	function), 177
<pre>PyConfig.warn_default_encoding(Cmember),</pre>	PyDateTime_FromTimestamp (C function), 179
212	PyDateTime_GET_DAY (C function), 178
PyConfig.warnoptions (C member), 218	PyDateTime_GET_MONTH (C function), 178
PyConfig.write_bytecode (C member), 219	PyDateTime_GET_YEAR (C function), 178
PyConfig.xoptions (C member), 219	PyDateTime_Time (C type), 176
PyContext (C type), 174	PyDateTime_TIME_GET_FOLD (C function), 179
PyContext_CheckExact (C function), 175	PyDateTime_TIME_GET_HOUR (C function), 178
PyContext_Copy (C function), 175	PyDateTime_TIME_GET_MICROSECOND (C func-
PyContext_CopyCurrent (C function), 175	tion), 178
PyContext_Enter (C function), 175	PyDateTime_TIME_GET_MINUTE (C function), 178
PyContext_Exit (<i>C function</i>), 175	PyDateTime_TIME_GET_SECOND (C function), 178
PyContext_New (C function), 175	PyDateTime_TIME_GET_TZINFO (C function), 179
PyContext_Type (C var), 174	PyDateTime_TimeType(C var), 176
PyContextToken (C type), 174	PyDateTime_TimeZone_UTC (C var), 176
PyContextToken_CheckExact (C function), 175	PyDateTime_TZInfoType (C var), 176
PyContextToken_Type (C var), 174	PyDelta_Check (C function), 177
PyContextVar (<i>Ctype</i>), 174	PyDelta_CheckExact (C function), 177
PyContextVar_CheckExact (<i>C function</i>), 175	PyDelta_FromDSU (C function), 177
PyContextVar_Get (<i>C function</i>), 175	PyDescr_IsData (C function), 166
PyContextVar_New (<i>C function</i>), 175	PyDescr_NewClassMethod (C function), 166
PyContextVar_Reset (<i>C function</i>), 175	PyDescr_NewGetSet (C function), 166
PyContextVar_Set (C function), 175	PyDescr_NewMember (C function), 166
PyContextVar_Type (C var), 174	PyDescr_NewMethod (<i>C function</i>), 166
PyCoro_CheckExact (<i>C function</i>), 174	PyDescr_NewWrapper (<i>C function</i>), 166
PyCoro_New (<i>C function</i>), 174	PyDict_AddWatcher (C function), 147
PyCoro_Type (<i>C var</i>), 174	PyDict_Check (<i>C function</i>), 144
PyCoroObject ($Ctype$) 174	PyDict CheckExact (C function) 144

PyDict_Clear (C function), 144	PyErr_Restore (C function), 51
PyDict_ClearWatcher (C function), 147	PyErr_SetExcFromWindowsErr (<i>C function</i>), 47
PyDict_Contains (C function), 144	PyErr_SetExcFromWindowsErrWithFilename
PyDict_Copy (<i>C function</i>), 144	(C function), 48
PyDict_DelItem (C function), 145	PyErr_SetExcFromWindowsErrWithFilenameObject
PyDict_DelItemString (C function), 145	(C function), 48
PyDict_GetItem (<i>C function</i>), 145	PyErr_SetExcFromWindowsErrWithFilenameObjects
PyDict_GetItemString (C function), 145	(C function), 48
PyDict_GetItemWithError (C function), 145	PyErr_SetExcInfo (C function), 52
PyDict_Items (<i>C function</i>), 145	PyErr_SetFromErrno (<i>C function</i>), 47
PyDict_Keys (<i>C function</i>), 145	PyErr_SetFromErrnoWithFilename (C func-
PyDict_Merge (C function), 146	tion), 47
PyDict_MergeFromSeq2 (C function), 146	PyErr_SetFromErrnoWithFilenameObject (C
PyDict_New (C function), 144	function), 47
PyDict_Next (C function), 146	PyErr_SetFromErrnoWithFilenameObjects
PyDict_SetDefault (C function), 145	(C function), 47
PyDict_SetItem (C function), 144	PyErr_SetFromWindowsErr (<i>C function</i>), 47
PyDict_SetItemString (C function), 145	PyErr_SetFromWindowsErrWithFilename (C
PyDict_Size (C function), 146	function), 48
PyDict_Type (C var), 144	PyErr_SetHandledException (C function), 51
PyDict_Unwatch (<i>C function</i>), 147	PyErr_SetImportError (C function), 48
PyDict_Update (C function), 146	PyErr_SetImportErrorSubclass (C function),
PyDict_Values (C function), 145	48
PyDict_Watch (C function), 147	PyErr_SetInterrupt (C function), 53
PyDict_WatchCallback (C type), 147	PyErr_SetInterruptEx (C function), 53
PyDict_WatchEvent (C type), 147	PyErr_SetNone (C function), 47
PyDictObject(<i>Ctype</i>), 144	PyErr_SetObject (C function), 46
PyDictProxy_New (C function), 144	PyErr_SetRaisedException (C function), 50
PyDoc_STR (C macro), 6	PyErr_SetString (C function), 46
PyDoc_STRVAR (C macro), 6	<pre>PyErr_SetString(),11</pre>
PyErr_BadArgument (C function), 47	PyErr_SyntaxLocation (C function), 48
PyErr_BadInternalCall (C function), 48	PyErr_SyntaxLocationEx (C function), 48
PyErr_CheckSignals (C function), 52	PyErr_SyntaxLocationObject (C function), 48
PyErr_Clear (C function), 46	PyErr_WarnEx (C function), 49
PyErr_Clear(), 11, 12	PyErr_WarnExplicit (C function), 49
PyErr_DisplayException (C function), 46	PyErr_WarnExplicitObject (C function), 49
PyErr_ExceptionMatches (C function), 50	PyErr_WarnFormat (C function), 49
PyErr_ExceptionMatches(), 12	PyErr_WriteUnraisable (C function), 46
PyErr_Fetch (C function), 50	PyEval_AcquireLock (C function), 196
PyErr_Format (C function), 46	PyEval_AcquireThread (C function), 196
PyErr_FormatV (C function), 46	PyEval_AcquireThread(),192
PyErr_GetExcInfo (C function), 52	PyEval_EvalCode (<i>C function</i>), 38
PyErr_GetHandledException (<i>C function</i>), 51	PyEval_EvalCodeEx (C function), 38
PyErr_GetRaisedException (C function), 50	PyEval_EvalFrame (<i>C function</i>), 38
PyErr_GivenExceptionMatches (<i>C function</i>), 50	PyEval_EvalFrameEx (C function), 38
PyErr_NewException (C function), 53	PyEval_GetBuiltins (<i>C function</i>), 77
PyErr_NewExceptionWithDoc (C function), 53	PyEval_GetFrame (C function), 77
PyErr_NoMemory (C function), 47	PyEval_GetFuncDesc (C function), 77
PyErr_NormalizeException (<i>C function</i>), 51	PyEval_GetFuncName (<i>C function</i>), 77
PyErr_Occurred (C function), 50	PyEval_GetGlobals (<i>C function</i>), 77
PyErr_Occurred(), 10	PyEval_GetLocals (<i>C function</i>), 77
PyErr_Print (<i>C function</i>), 46	PyEval_InitThreads (<i>C function</i>), 191
PyErr_PrintEx (C function), 46	PyEval_InitThreads(), 185
PyErr_ResourceWarning (<i>C function</i>), 49	PyEval_MergeCompilerFlags (<i>C function</i>), 38
Tybri_nesourcewarming (C junction), 49	rymvar_mergecomprierriags (C junction), 30

PyEval_ReleaseLock (<i>C function</i>), 196	PyExc_RecursionError, 56
PyEval_ReleaseThread (<i>C function</i>), 196	PyExc_ReferenceError, 56
PyEval_ReleaseThread(), 192	PyExc_ResourceWarning, 58
PyEval_RestoreThread (<i>C function</i>), 192	PyExc_RuntimeError, 56
PyEval_RestoreThread(), 190, 192	PyExc_RuntimeWarning, 58
PyEval_SaveThread (<i>C function</i>), 192	PyExc_StopAsyncIteration, 56
PyEval_SaveThread(), 190, 192	PyExc_StopIteration, 56
PyEval_SetProfile (<i>C function</i>), 201 PyEval_SetProfileAllThreads (<i>C function</i>), 201	PyExc_SyntaxError, 56
PyEval_SetTrace (<i>C function</i>), 202	PyExc_SyntaxWarning, 58 PyExc_SystemError, 56
PyEval_SetTraceAllThreads (C function), 202	PyExc_SystemExit, 56
PyEval_ThreadsInitialized (C function), 192	PyExc_TabError, 56
PyExc_ArithmeticError, 56	PyExc_TimeoutError, 56
PyExc_AssertionError, 56	PyExc_TypeError, 56
PyExc_AttributeError, 56	PyExc_UnboundLocalError, 56
PyExc_BaseException, 56	PyExc_UnicodeDecodeError, 56
PyExc_BlockingIOError, 56	PyExc_UnicodeEncodeError, 56
PyExc_BrokenPipeError, 56	PyExc_UnicodeError, 56
PyExc_BufferError, 56	PyExc_UnicodeTranslateError, 56
PyExc_BytesWarning,58	PyExc_UnicodeWarning, 58
PyExc_ChildProcessError,56	PyExc_UserWarning,58
PyExc_ConnectionAbortedError, 56	PyExc_ValueError,56
PyExc_ConnectionError, 56	PyExc_Warning,58
PyExc_ConnectionRefusedError, 56	PyExc_WindowsError,58
PyExc_ConnectionResetError, 56	PyExc_ZeroDivisionError,56
PyExc_DeprecationWarning, 58	PyException_GetArgs (C function), 54
PyExc_EnvironmentError, 58	PyException_GetCause (C function), 54
PyExc_EOFError, 56	PyException_GetContext (C function), 54
PyExc_Exception, 56	PyException_GetTraceback(C function), 54
PyExc_FileExistsError,56	PyException_SetArgs (C function), 54
PyExc_FileNotFoundError, 56	PyException_SetCause (C function), 54
PyExc_FloatingPointError, 56	PyException_SetContext (C function), 54
PyExc_FutureWarning, 58	PyException_SetTraceback(C function), 54
PyExc_GeneratorExit, 56	PyFile_FromFd (C function), 157
PyExc_ImportError, 56	PyFile_GetLine (C function), 157
PyExc_ImportWarning, 58	PyFile_SetOpenCodeHook (C function), 157
PyExc_IndentationError, 56	PyFile_WriteObject (C function), 157
PyExc_IndexError, 56	PyFile_WriteString (C function), 158
PyExc_InterruptedError, 56	PyFloat_AS_DOUBLE (<i>C function</i>), 117
PyExc_IOError, 58	PyFloat_AsDouble (<i>C function</i>), 117
PyExc_IsADirectoryError, 56	PyFloat_Check (C function), 117
PyExc_KeyboardInterrupt, 56	PyFloat_CheckExact (<i>C function</i>), 117
PyExc_KeyError, 56	PyFloat_FromDouble (<i>C function</i>), 117
PyExc_LookupError, 56	PyFloat_FromString (<i>C function</i>), 117
PyExc_MemoryError, 56	PyFloat_GetInfo (<i>C function</i>), 117
PyExc_ModuleNotFoundError, 56	PyFloat_GetMax (<i>C function</i>), 117
PyExc_NameError, 56	PyFloat_GetMin (<i>C function</i>), 118
PyExc_NotADirectoryError, 56	PyFloat_Pack2 (<i>C function</i>), 118
PyExc_NotImplementedError, 56	PyFloat_Pack4 (<i>C function</i>), 118
PyExc_OSError, 56	PyFloat_Pack8 (C function), 118
PyExc_OverflowError, 56	PyFloat_Type (C var), 117
PyExc_PendingDeprecationWarning, 58	PyFloat_Type (C var), 117 PyFloat_Unpack2 (C function), 119
PyExc_PermissionError, 56	PyFloat_Unpack4 (C function), 119
PyExc_ProcessLookupError, 56	PyFloat_Unpack8 (C function), 119
rymac_rrocesshookupmiror, 30	ryr roat_onpacko (C juncuon), 119

PyFloatObject (Ctype), 117	PyGILState_Ensure (<i>C function</i>), 192
PyFrame_Check (C function), 171	PyGILState_GetThisThreadState ($C\ function$),
PyFrame_GetBack (C function), 172	193
PyFrame_GetBuiltins (C function), 172	PyGILState_Release (C function), 193
PyFrame_GetCode (C function), 172	PyImport_AddModule (C function), 65
PyFrame_GetGenerator(C function), 172	PyImport_AddModuleObject ($C\mathit{function}$), 65
PyFrame_GetGlobals (<i>C function</i>), 172	PyImport_AppendInittab (C function), 67
PyFrame_GetLasti(<i>C function</i>), 172	PyImport_ExecCodeModule (C function), 65
PyFrame_GetLineNumber (C function), 172	PyImport_ExecCodeModuleEx(C function), 66
PyFrame_GetLocals (<i>C function</i>), 172	PyImport_ExecCodeModuleObject ($C\ function$),
PyFrame_GetVar(<i>C function</i>), 172	66
PyFrame_GetVarString (C function), 172	PyImport_ExecCodeModuleWithPathnames (C
PyFrame_Type (C var), 171	function), 66
PyFrameObject ($Ctype$), 171	PyImport_ExtendInittab (C function), 67
PyFrozenSet_Check (C function), 148	PyImport_FrozenModules (C var), 67
PyFrozenSet_CheckExact (C function), 148	PyImport_GetImporter(C function), 66
PyFrozenSet_New (C function), 149	PyImport_GetMagicNumber (C function), 66
PyFrozenSet_Type (C var), 148	PyImport_GetMagicTag(C function), 66
PyFunction_AddWatcher (C function), 151	PyImport_GetModule (C function), 66
PyFunction_Check (C function), 150	PyImport_GetModuleDict(C function), 66
PyFunction_ClearWatcher (<i>C function</i>), 151	PyImport_Import (C function), 65
PyFunction_GetAnnotations (<i>C function</i>), 151	PyImport_ImportFrozenModule(C function), 67
PyFunction_GetClosure (C function), 150	PyImport_ImportFrozenModuleObject (C
PyFunction_GetCode (C function), 150	function), 67
PyFunction_GetDefaults (C function), 150	PyImport_ImportModule (C function), 64
PyFunction_GetGlobals (C function), 150	PyImport_ImportModuleEx(C function), 64
PyFunction_GetModule (C function), 150	PyImport_ImportModuleLevel (C function), 65
	Dr. Import ImportModial of orrol Object (1' tune
PyFunction_New (C function), 150	PyImport_ImportModuleLevelObject (C func-
${\tt PyFunction_NewWithQualName}~(C~\textit{function}),~150$	tion), 64
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function),</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 150 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151	<pre>tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function),</pre>
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151 PyFunctionObject (<i>C type</i>), 150	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151 PyFunctionObject (<i>C type</i>), 150 PyGC_Collect (<i>C function</i>), 282	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151 PyFunctionObject (<i>C type</i>), 150 PyGC_Collect (<i>C function</i>), 282 PyGC_Disable (<i>C function</i>), 282	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151 PyFunctionObject (<i>C type</i>), 150 PyGC_Collect (<i>C function</i>), 282 PyGC_Disable (<i>C function</i>), 282 PyGC_Enable (<i>C function</i>), 282	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_IsEnabled (C function), 282	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197 PyInterpreterConfig_DEFAULT_GIL (C macro),
PyFunction_NewWithQualName (<i>C function</i>), 150 PyFunction_SetAnnotations (<i>C function</i>), 151 PyFunction_SetClosure (<i>C function</i>), 151 PyFunction_SetDefaults (<i>C function</i>), 150 PyFunction_SetVectorcall (<i>C function</i>), 150 PyFunction_Type (<i>C var</i>), 150 PyFunction_WatchCallback (<i>C type</i>), 151 PyFunction_WatchEvent (<i>C type</i>), 151 PyFunctionObject (<i>C type</i>), 150 PyGC_Collect (<i>C function</i>), 282 PyGC_Disable (<i>C function</i>), 282 PyGC_Enable (<i>C function</i>), 282 PyGC_IsEnabled (<i>C function</i>), 282 PyGC_IsEnabled (<i>C function</i>), 282 PyGen_Check (<i>C function</i>), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197 PyInterpreterConfig_DEFAULT_GIL (C macro), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 282 PyGen_Check (C function), 173 PyGen_CheckExact (C function), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 282 PyGen_Check (C function), 173 PyGen_CheckExact (C function), 173 PyGen_New (C function), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro),
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_CheckExact (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig (C type), 197 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_CheckExact (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig_allow_daemon_threads
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 282 PyGen_Check (C function), 173 PyGen_CheckExact (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGen_Type (C var), 173 PyGenObject (C type), 173	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig_allow_daemon_threads (C member), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 151 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 282 PyGen_Check (C function), 173 PyGen_CheckExact (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGenObject (C type), 173 PyGetSetDef (C type), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig_allow_daemon_threads (C member), 197 PyInterpreterConfig.allow_exec(C member),
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_CheckExact (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGetSetDef (C type), 244 PyGetSetDef.closure (C member), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig.allow_daemon_threads (C member), 197 PyInterpreterConfig.allow_exec(C member), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_Check (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGenObject (C type), 244 PyGetSetDef.closure (C member), 244 PyGetSetDef.doc (C member), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig(C type), 197 PyInterpreterConfig_DEFAULT_GIL(C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig.allow_daemon_threads (C member), 197 PyInterpreterConfig.allow_exec(C member), 197 PyInterpreterConfig.allow_fork(C member), 197 PyInterpreterConfig.allow_fork(C member),
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_Check (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGetSetDef (C type), 244 PyGetSetDef.closure (C member), 244 PyGetSetDef.get (C member), 244 PyGetSetDef.get (C member), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig.allow_daemon_threads (C member), 197 PyInterpreterConfig.allow_exec (C member), 197 PyInterpreterConfig.allow_fork (C member), 197 PyInterpreterConfig.allow_fork (C member), 197
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_Check (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGetSetDef (C type), 244 PyGetSetDef.closure (C member), 244 PyGetSetDef.name (C member), 244 PyGetSetDef.name (C member), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_allow_daemon_threads (C member), 197 PyInterpreterConfig_allow_exec (C member), 197 PyInterpreterConfig_allow_fork (C member), 197 PyInterpreterConfig_allow_fork (C member), 197 PyInterpreterConfig_allow_fork (C member), 197 PyInterpreterConfig_allow_threads (C
PyFunction_NewWithQualName (C function), 150 PyFunction_SetAnnotations (C function), 151 PyFunction_SetClosure (C function), 151 PyFunction_SetDefaults (C function), 150 PyFunction_SetVectorcall (C function), 150 PyFunction_Type (C var), 150 PyFunction_WatchCallback (C type), 151 PyFunction_WatchEvent (C type), 150 PyFunctionObject (C type), 150 PyGC_Collect (C function), 282 PyGC_Disable (C function), 282 PyGC_Enable (C function), 282 PyGC_IsEnabled (C function), 173 PyGen_Check (C function), 173 PyGen_New (C function), 173 PyGen_NewWithQualName (C function), 173 PyGen_Type (C var), 173 PyGetSetDef (C type), 244 PyGetSetDef.closure (C member), 244 PyGetSetDef.get (C member), 244 PyGetSetDef.get (C member), 244	tion), 64 PyImport_ImportModuleNoBlock (C function), 64 PyImport_ReloadModule (C function), 65 PyIndex_Check (C function), 94 PyInstanceMethod_Check (C function), 152 PyInstanceMethod_Function (C function), 152 PyInstanceMethod_GET_FUNCTION (C function), 152 PyInstanceMethod_New (C function), 152 PyInstanceMethod_Type (C var), 152 PyInterpreterConfig_DEFAULT_GIL (C macro), 197 PyInterpreterConfig_OWN_GIL (C macro), 197 PyInterpreterConfig_SHARED_GIL (C macro), 197 PyInterpreterConfig.allow_daemon_threads (C member), 197 PyInterpreterConfig.allow_exec (C member), 197 PyInterpreterConfig.allow_fork (C member), 197 PyInterpreterConfig.allow_fork (C member), 197

PyInterpreterConfig.check_multi_interp_e	
(C member), 197	PyLong_CheckExact (C function), 113
PyInterpreterConfig.gil (C member), 197	PyLong_FromDouble (<i>C function</i>), 114
PyInterpreterConfig.use_main_obmalloc	PyLong_FromLong (C function), 113
(C member), 197	PyLong_FromLongLong (C function), 113
PyInterpreterState (C type), 191	PyLong_FromSize_t (<i>C function</i>), 113
PyInterpreterState_Clear (<i>C function</i>), 194	PyLong_FromSsize_t (<i>C function</i>), 113
PyInterpreterState_Delete (C function), 194	PyLong_FromString (C function), 114
PyInterpreterState_Get (C function), 195	PyLong_FromUnicodeObject (C function), 114
PyInterpreterState_GetDict(C function), 195	PyLong_FromUnsignedLong (C function), 113
PyInterpreterState_GetID (C function), 195	PyLong_FromUnsignedLongLong($Cfunction$), 114
PyInterpreterState_Head(C function), 202	PyLong_FromVoidPtr(<i>C function</i>), 114
PyInterpreterState_Main(C function), 202	PyLong_Type (C var), 113
PyInterpreterState_New (C function), 194	PyLongObject (Ctype), 113
PyInterpreterState_Next (C function), 202	PyMapping_Check (C function), 96
${\tt PyInterpreterState_ThreadHead}~(C~\textit{function}),$	PyMapping_DelItem (C function), 96
202	PyMapping_DelItemString (C function), 96
PyIter_Check (C function), 97	PyMapping_GetItemString (C function), 96
PyIter_Next (C function), 97	PyMapping_HasKey (C function), 96
PyIter_Send (C function), 98	PyMapping_HasKeyString (C function), 96
PyList_Append (C function), 143	PyMapping_Items (C function), 97
PyList_AsTuple (C function), 144	PyMapping_Keys (C function), 96
PyList_Check (C function), 142	PyMapping_Length (C function), 96
PyList_CheckExact (C function), 142	PyMapping_SetItemString (C function), 96
PyList_GET_ITEM (C function), 143	PyMapping_Size (C function), 96
PyList_GET_SIZE (C function), 143	PyMapping_Values (C function), 97
PyList_GetItem (C function), 143	PyMappingMethods (C type), 272
<pre>PyList_GetItem(),9</pre>	PyMappingMethods.mp_ass_subscript $(C$
PyList_GetSlice (C function), 143	member), 272
PyList_Insert (C function), 143	PyMappingMethods.mp_length(C member), 272
PyList_New (C function), 143	PyMappingMethods.mp_subscript (C member),
PyList_Reverse (C function), 144	272
PyList_SET_ITEM (C function), 143	PyMarshal_ReadLastObjectFromFile (C func-
PyList_SetItem (<i>C function</i>), 143	tion), 68
PyList_SetItem(),8	PyMarshal_ReadLongFromFile (C function), 68
PyList_SetSlice (<i>C function</i>), 143	PyMarshal_ReadObjectFromFile (C function),
PyList_Size (C function), 143	68
PyList_Sort (C function), 144	PyMarshal_ReadObjectFromString (C func-
PyList_Type (C var), 142	tion), 68
PyListObject (<i>C type</i>), 142	PyMarshal_ReadShortFromFile(C function), 68
PyLong_AsDouble (C function), 116	PyMarshal_WriteLongToFile (C function), 68
PyLong_AsLong (<i>C function</i>), 114	PyMarshal_WriteObjectToFile(<i>C function</i>), 68
PyLong_AsLongAndOverflow (C function), 114	PyMarshal_WriteObjectToString (C function),
PyLong_AsLongLong (<i>C function</i>), 114	68
PyLong_AsLongLongAndOverflow (C function),	PyMem_Calloc (C function), 228
115	PyMem_Del (C function), 228
PyLong_AsSize_t (C function), 115	PYMEM_DOMAIN_MEM (C macro), 230
PyLong_AsSsize_t (C function), 115	PYMEM_DOMAIN_OBJ (C macro), 231
PyLong_AsUnsignedLong (C function), 115	PYMEM_DOMAIN_RAW (C macro), 230
PyLong_AsUnsignedLongLong (C function), 115	PyMem_Free (C function), 228
PyLong_AsUnsignedLongLongMask (<i>C function</i>),	PyMem_GetAllocator (C function), 231
115	= · · · · · · · · · · · · · · · · · · ·
	PyMem_Malloc (C function), 227
PyLong_AsUnsignedLongMask (C function), 115	PyMem_Malloc (<i>C function</i>), 227 PyMem_New (<i>C macro</i>), 228

PyMem_RawFree (<i>C function</i>), 227	PyModule_GetFilename (C function), 159
PyMem_RawMalloc(<i>C function</i>), 227	PyModule_GetFilenameObject (C function), 158
PyMem_RawRealloc (C function), 227	PyModule_GetName (C function), 158
PyMem_Realloc(<i>C function</i>), 228	PyModule_GetNameObject (C function), 158
PyMem_Resize(<i>C macro</i>), 228	PyModule_GetState (C function), 158
PyMem_SetAllocator(<i>C function</i>), 231	PyModule_New (C function), 158
PyMem_SetupDebugHooks (C function), 231	PyModule_NewObject (C function), 158
PyMemAllocatorDomain ($Ctype$), 230	PyModule_SetDocString (C function), 162
PyMemAllocatorEx(<i>Ctype</i>), 230	PyModule_Type (<i>C var</i>), 158
PyMember_GetOne (<i>C function</i>), 241	PyModuleDef(<i>Ctype</i>), 159
PyMember_SetOne (<i>C function</i>), 241	PyModuleDef_Init (<i>C function</i>), 161
PyMemberDef ($Ctype$), 240	PyModuleDef_Slot (<i>Ctype</i>), 161
PyMemberDef.doc(<i>C member</i>), 241	PyModuleDef_Slot.slot(<i>C member</i>), 161
PyMemberDef.flags(<i>C member</i>), 241	PyModuleDef_Slot.value(<i>C member</i>), 161
PyMemberDef.name (<i>C member</i>), 240	PyModuleDef.m_base(<i>C member</i>), 159
PyMemberDef.offset(<i>C member</i>), 240	PyModuleDef.m_clear(<i>C member</i>), 160
PyMemberDef.type(<i>C member</i>), 241	PyModuleDef.m_doc(<i>C member</i>), 159
PyMemoryView_Check (C function), 168	PyModuleDef.m_free(<i>C member</i>), 160
PyMemoryView_FromBuffer(<i>C function</i>), 168	PyModuleDef.m_methods(<i>C member</i>), 159
PyMemoryView_FromMemory(<i>Cfunction</i>), 168	PyModuleDef.m_name(<i>C member</i>), 159
PyMemoryView_FromObject(<i>C function</i>), 168	PyModuleDef.m_size(<i>C member</i>), 159
PyMemoryView_GET_BASE (C function), 168	PyModuleDef.m_slots(<i>C member</i>), 159
PyMemoryView_GET_BUFFER (<i>C function</i>), 168	PyModuleDef.m_slots.m_reload (C member)
PyMemoryView_GetContiguous (C function), 168	159
PyMethod_Check (C function), 152	PyModuleDef.m_traverse(<i>C member</i>), 159
PyMethod_Function (C function), 152	PyNumber_Absolute (C function), 91
PyMethod_GET_FUNCTION (C function), 152	PyNumber_Add (C function), 91
PyMethod_GET_SELF (<i>C function</i>), 152	PyNumber_And (C function), 92
PyMethod_New (<i>C function</i>), 152	PyNumber_AsSsize_t (C function), 93
PyMethod_Self (C function), 152	PyNumber_Check (C function), 91
PyMethod_Type (<i>C var</i>), 152	PyNumber_Divmod (C function), 91
PyMethodDef ($Ctype$), 239	PyNumber_Float (C function), 93
PyMethodDef.ml_doc(<i>C member</i>), 239	PyNumber_FloorDivide ($C\mathit{function}$), 91
PyMethodDef.ml_flags(<i>C member</i>), 239	PyNumber_Index (C function), 93
PyMethodDef.ml_meth(C member), 239	PyNumber_InPlaceAdd(C function), 92
PyMethodDef.ml_name(C member), 239	PyNumber_InPlaceAnd (C function), 93
PyMODINIT_FUNC (C macro), 4	$PyNumber_InPlaceFloorDivide(Cfunction), 92$
PyModule_AddFunctions (C function), 163	PyNumber_InPlaceLshift (C function), 93
PyModule_AddIntConstant (<i>C function</i>), 164	PyNumber_InPlaceMatrixMultiply (C func
PyModule_AddIntMacro (<i>C macro</i>), 164	tion), 92
PyModule_AddObject (<i>C function</i>), 163	PyNumber_InPlaceMultiply (C function), 92
PyModule_AddObjectRef($C\mathit{function}$), 163	PyNumber_InPlaceOr (C function), 93
PyModule_AddStringConstant ($C\ function$), 164	PyNumber_InPlacePower (C function), 93
PyModule_AddStringMacro(<i>C macro</i>), 164	PyNumber_InPlaceRemainder (C function), 93
PyModule_AddType (C function), 164	PyNumber_InPlaceRshift (C function), 93
PyModule_Check (C function), 158	PyNumber_InPlaceSubtract (C function), 92
PyModule_CheckExact (C function), 158	PyNumber_InPlaceTrueDivide (C function), 92
PyModule_Create (C function), 160	PyNumber_InPlaceXor(C function), 93
PyModule_Create2 (C function), 160	PyNumber_Invert (C function), 92
PyModule_ExecDef (C function), 162	PyNumber_Long (C function), 93
PyModule_FromDefAndSpec (C function), 162	PyNumber_Lshift (C function), 92
PyModule_FromDefAndSpec2 (C function), 162	PyNumber_MatrixMultiply (C function), 91
PyModule_GetDef(C function), 158	PyNumber_Multiply (C function), 91
PyModule_GetDict (C function), 158	PyNumber_Negative (C function), 91

PyNumber_Or (C function), 92	PyNumberMethods.nb_power(<i>C member</i>), 271
PyNumber_Positive (C function), 91	PyNumberMethods.nb_remainder (C member),
PyNumber_Power (C function), 91	271
PyNumber_Remainder (C function), 91	PyNumberMethods.nb_reserved(<i>C member</i>), 271
PyNumber_Rshift (C function), 92	PyNumberMethods.nb_rshift(<i>C member</i>), 271
PyNumber_Subtract (C function), 91	PyNumberMethods.nb_subtract(C member), 271
PyNumber_ToBase (C function), 93	PyNumberMethods.nb_true_divide(Cmember),
PyNumber_TrueDivide (C function), 91	272
PyNumber_Xor (C function), 92	PyNumberMethods.nb_xor(<i>C member</i>), 271
PyNumberMethods (C type), 270	PyObject (C type), 236
PyNumberMethods.nb_absolute(<i>C member</i>), 271	PyObject_AsCharBuffer (C function), 105
PyNumberMethods.nb_add(C member), 271	PyObject_ASCII (C function), 83
PyNumberMethods.nb_and(C member), 271	PyObject_AsFileDescriptor (C function), 157
PyNumberMethods.nb_bool(<i>C member</i>), 271	PyObject_AsReadBuffer (C function), 105
PyNumberMethods.nb_divmod(C member), 271	PyObject_AsWriteBuffer (C function), 106
<pre>PyNumberMethods.nb_float (C member), 271</pre>	PyObject_Bytes (C function), 84
PyNumberMethods.nb_floor_divide (C mem-	PyObject_Call (C function), 88
ber), 272	PyObject_CallFunction (C function), 89
PyNumberMethods.nb_index(C member), 272	PyObject_CallFunctionObjArgs (C function),
PyNumberMethods.nb_inplace_add(Cmember),	89
271	PyObject_CallMethod (C function), 89
${\tt PyNumberMethods.nb_inplace_and} \ ({\it Cmember}),$	PyObject_CallMethodNoArgs (<i>C function</i>), 89
272	PyObject_CallMethodObjArgs (<i>C function</i>), 89
PyNumberMethods.nb_inplace_floor_divide	PyObject_CallMethodOneArg (C function), 90
(C member), 272	PyObject_CallNoArgs (C function), 89
${\tt PyNumberMethods.nb_inplace_lshift} \qquad (C$	PyObject_CallObject (C function), 89
member), 272	PyObject_Calloc(<i>C function</i>), 229
PyNumberMethods.nb_inplace_matrix_multi	p $ t PyObject_CallOneArg$ (C function), 89
(C member), 272	PyObject_CheckBuffer(C function), 104
${\tt PyNumberMethods.nb_inplace_multiply} (C$	PyObject_CheckReadBuffer(Cfunction), 105
member), 271	PyObject_ClearWeakRefs (C function), 169
${\tt PyNumberMethods.nb_inplace_or}~(C~\textit{member}),$	PyObject_CopyData (C function), 105
272	PyObject_Del(C function), 236
${\tt PyNumberMethods.nb_inplace_power}~(C~\textit{mem-}$	PyObject_DelAttr(<i>C function</i>), 82
ber), 272	PyObject_DelAttrString (C function), 82
	PyObject_DelItem (C function), 85
member), 271	PyObject_Dir(C function), 85
${\tt PyNumberMethods.nb_inplace_rshift} \qquad (C$	PyObject_Format (<i>C function</i>), 83
member), 272	PyObject_Free (C function), 229
${\tt PyNumberMethods.nb_inplace_subtract} (C$	PyObject_GC_Del(<i>C function</i>), 281
member), 271	PyObject_GC_IsFinalized (C function), 281
PyNumberMethods.nb_inplace_true_divide	PyObject_GC_IsTracked(<i>C function</i>), 281
(C member), 272	PyObject_GC_New (<i>C macro</i>), 280
PyNumberMethods.nb_inplace_xor(Cmember),	PyObject_GC_NewVar(<i>C macro</i>), 280
272	PyObject_GC_Resize (C function), 280
PyNumberMethods.nb_int(<i>C member</i>), 271	PyObject_GC_Track (C function), 280
PyNumberMethods.nb_invert(C member), 271	PyObject_GC_UnTrack (<i>C function</i>), 281
PyNumberMethods.nb_lshift(<i>C member</i>), 271	PyObject_GenericGetAttr(C function), 82
${\tt PyNumberMethods.nb_matrix_multiply} (C$	PyObject_GenericGetDict($C\mathit{function}$), 82
member), 272	PyObject_GenericSetAttr(C function), 82
PyNumberMethods.nb_multiply(<i>C member</i>),271	PyObject_GenericSetDict (C function), 83
PyNumberMethods.nb_negative(<i>C member</i>),271	PyObject_GetAIter (C function), 85
PyNumberMethods.nb_or(<i>C member</i>), 271	${\tt PyObject_GetArenaAllocator} \ ({\it Cfunction}), 233$
PyNumberMethods.nb_positive(<i>C member</i>), 271	PyObject_GetAttr(C function), 82

PyObject_GetAttrString(C function), 82	PyOS_InputHook (C var), 36
PyObject_GetBuffer (C function), 104	PyOS_ReadlineFunctionPointer(Cvar), 37
PyObject_GetItem(C function), 85	PyOS_setsig(C function), 60
PyObject_GetItemData(C function), 86	PyOS_snprintf(C function), 76
PyObject_GetIter(<i>C function</i>), 85	PyOS_stricmp (C function), 77
PyObject_GetTypeData (C function), 85	PyOS_string_to_double (<i>C function</i>), 76
PyObject_HasAttr(<i>C function</i>), 81	PyOS_strnicmp (<i>C function</i>), 77
PyObject_HasAttrString (C function), 81	PyOS_vsnprintf (<i>C function</i>), 76
PyObject_Hash (<i>C function</i>), 84	PyPreConfig (C type), 208
PyObject_HashNotImplemented (C function), 84	PyPreConfig_InitIsolatedConfig (C func-
PyObject_HEAD (<i>C macro</i>), 236	tion), 208
PyObject_HEAD_INIT (C macro), 237	PyPreConfig_InitPythonConfig (C function),
PyObject_Init (C function), 235	208
PyObject_InitVar (C function), 235	PyPreConfig.allocator(<i>C member</i>), 208
PyObject_IS_GC (C function), 281	PyPreConfig.coerce_c_locale(C member), 208
PyObject_IsInstance (C function), 84	PyPreConfig.coerce_c_locale_warn (C mem-
PyObject_IsSubclass (C function), 84	ber), 208
PyObject_IsTrue (C function), 84	PyPreConfig.configure_locale (C member),
PyObject_Length (C function), 85	208
PyObject_LengthHint (C function), 85	PyPreConfig.dev_mode(<i>C member</i>), 208
PyObject_Malloc (C function), 229	PyPreConfig.isolated (C member), 209
PyObject_New (C macro), 235	PyPreConfig.legacy_windows_fs_encoding
PyObject_NewVar (C macro), 235	(C member), 209
PyObject_Not (C function), 84	PyPreConfig.parse_argv(C member), 209
PyObjectob_next(C member), 252	PyPreConfig.use_environment(C member), 209
PyObjectob_prev(<i>C member</i>), 252	PyPreConfig.utf8_mode (C member), 209
PyObject_Print (C function), 81	PyProperty_Type $(C var)$, 166
PyObject_Realloc(<i>C function</i>), 229	PyRun_AnyFile (C function), 35
PyObject_Repr(C function), 83	PyRun_AnyFileEx (C function), 35
PyObject_RichCompare (C function), 83	PyRun_AnyFileExFlags (C function), 36
PyObject_RichCompareBool (C function), 83	PyRun_AnyFileFlags (C function), 35
PyObject_SetArenaAllocator (C function), 233	PyRun_File (C function), 37
PyObject_SetAttr (C function), 82	PyRun_FileEx (C function), 37
PyObject_SetAttrString(C function), 82	PyRun_FileExFlags (C function), 37
PyObject_SetItem(C function), 85	PyRun_FileFlags (C function), 37
PyObject_Size (C function), 85	PyRun_InteractiveLoop (C function), 36
PyObject_Str (C function), 83	PyRun_InteractiveLoopFlags (C function), 36
PyObject_Type (C function), 84	PyRun_InteractiveOne (C function), 36
PyObject_TypeCheck (C function), 85	PyRun_InteractiveOneFlags (C function), 36
PyObject_VAR_HEAD (C macro), 236	PyRun_SimpleFile (C function), 36
PyObject_Vectorcall (<i>C function</i>), 90	PyRun_SimpleFileEx(C function), 36
PyObject_VectorcallDict (C function), 90	PyRun_SimpleFileExFlags (C function), 36
PyObject_VectorcallMethod(C function), 90	PyRun_SimpleString (C function), 36
PyObjectArenaAllocator(Ctype), 233	PyRun_SimpleStringFlags (C function), 36
PyObject.ob_refcnt(C member), 251	PyRun_String (C function), 37
PyObject.ob_type (C member), 251	PyRun_StringFlags (C function), 37
PyOS_AfterFork (C function), 60	PySendResult (C type), 98
PyOS_AfterFork_Child(<i>C function</i>), 60	PySeqIter_Check (C function), 165
PyOS_AfterFork_Parent (C function), 59	PySeqIter_New (C function), 165
PyOS_BeforeFork (C function), 59	PySeqIter_Type (C var), 165
PyOS_CheckStack (C function), 60	PySequence_Check (C function), 94
PyOS_double_to_string (<i>C function</i>), 76	PySequence_Concat (C function), 94
PyOS_FSPath (C function), 59	PySequence_Contains (C function), 95
PyOS_getsig (<i>C function</i>), 60	PySequence_Count (C function), 95

PySequence_DelItem (C function), 95	PyState_FindModule (C function), 165
PySequence_DelSlice (C function), 95	PyState_RemoveModule (<i>C function</i>), 165
PySequence_Fast (C function), 95	PyStatus (<i>C type</i>), 207
PySequence_Fast_GET_ITEM(C function), 95	PyStatus_Error (<i>C function</i>), 207
PySequence_Fast_GET_SIZE (C function), 95	PyStatus_Exception (C function), 207
PySequence_Fast_ITEMS (C function), 95	PyStatus_Exit (<i>C function</i>), 207
PySequence_GetItem (C function), 94	PyStatus_IsError (<i>C function</i>), 207
PySequence_GetItem(),9	PyStatus_IsExit (<i>C function</i>), 207
PySequence_GetSlice (C function), 94	PyStatus_NoMemory (<i>C function</i>), 207
PySequence_Index (C function), 95	PyStatus_Ok (C function), 207
PySequence_InPlaceConcat (C function), 94	PyStatus.err_msg(<i>C member</i>), 207
PySequence_InPlaceRepeat (C function), 94	PyStatus.exitcode (C member), 207
PySequence_ITEM (C function), 96	PyStatus.func(C member), 207
PySequence_Length (C function), 94	PyStructSequence_Desc(C type), 141
PySequence_List (C function), 95	PyStructSequence_Desc.doc(C member), 141
PySequence_Repeat (C function), 94	PyStructSequence_Desc.fields (C member),
PySequence_SetItem (C function), 94	141
PySequence_SetSlice (C function), 95	PyStructSequence_Desc.n_in_sequence (C
PySequence_Size (C function), 94	member), 141
PySequence_Tuple (<i>C function</i>), 95	PyStructSequence_Desc.name (C member), 141
PySequenceMethods (<i>C type</i>), 273	PyStructSequence_Field(Ctype), 142
PySequenceMethods.sq_ass_item (C member),	PyStructSequence_Field.doc(C member), 142
273	PyStructSequence_Field.name(C member), 142
PySequenceMethods.sq_concat(C member), 273	PyStructSequence_GET_ITEM(<i>C function</i>), 142
PySequenceMethods.sq_contains (C member),	PyStructSequence_GetItem (<i>C function</i>), 142
273	PyStructSequence_InitType (<i>C function</i>), 141
PySequenceMethods.sq_inplace_concat (C	PyStructSequence_InitType2 (C function), 141
member), 273	PyStructSequence_New (C function), 142
PySequenceMethods.sq_inplace_repeat (C	PyStructSequence_NewType (C function), 141
member), 273	PyStructSequence_SET_ITEM(C function), 142
PySequenceMethods.sq_item(C member), 273	PyStructSequence_SetItem (C function), 142
PySequenceMethods.sq_length(Cmember), 273	PyStructSequence_UnnamedField(C var), 142
PySequenceMethods.sq_repeat(C member), 273	PySys_AddAuditHook (C function), 63
PySet_Add (C function), 149	PySys_AddWarnOption (<i>C function</i>), 62
PySet_Check (C function), 148	PySys_AddWarnOptionUnicode (C function), 62
PySet_CheckExact (C function), 148	PySys_AddXOption (C function), 63
PySet_Clear (<i>C function</i>), 149	PySys_Audit (<i>C function</i>), 63
PySet_Contains (<i>C function</i>), 149	PySys_FormatStderr(C function), 63
PySet_Discard (C function), 149	PySys_FormatStdout (C function), 62
PySet_GET_SIZE (<i>C function</i>), 149	PySys_GetObject (C function), 62
PySet_New (C function), 148	PySys_GetXOptions (<i>C function</i>), 63
PySet_Pop (C function), 149	PySys_ResetWarnOptions (C function), 62
PySet_Size (C function), 149	PySys_SetArgv (C function), 189
PySet_Type (C var), 148	PySys_SetArgv(),185
PySetObject (C type), 148	PySys_SetArgvEx (C function), 188
PySignal_SetWakeupFd (C function), 53	PySys_SetArgvEx(),185
PySlice_AdjustIndices (C function), 168	PySys_SetObject (C function), 62
PySlice_Check (<i>C function</i>), 167	PySys_SetPath (C function), 62
PySlice_GetIndices (C function), 167	PySys_WriteStderr (<i>C function</i>), 62
PySlice_GetIndicesEx (C function), 167	PySys_WriteStdout (<i>C function</i>), 62
PySlice_New (<i>C function</i>), 167	Python 3000, 297
PySlice_Type (C var), 167	Python Enhancement Proposals
PySlice_Unpack (<i>C function</i>), 167	PEP 1, 297
PyState AddModule (<i>C function</i>), 165	PEP 7,3,6

PEP 238,39	PYTHONINSPECT, 183, 214
PEP 278,300	PYTHONINTMAXSTRDIGITS, 215
PEP 302, 291, 295	PYTHONIOENCODING, 186, 218
PEP 328, 291	Pythonique, 298
PEP 343,289	PYTHONLEGACYWINDOWSFSENCODING, 183, 209
PEP 353,10	PYTHONLEGACYWINDOWSSTDIO, 183, 215
PEP 362, 288, 297	PYTHONMALLOC, 226, 230, 231, 233
PEP 383, 131, 132	PYTHONMALLOCSTATS, 215, 226
PEP 387, 15	PYTHONNODEBUGRANGES, 212
PEP 393, 124	PYTHONNOUSERSITE, 184, 218
PEP 411, 297	PYTHONOPTIMIZE, 184, 216
PEP 420, 291, 297	PYTHONPATH, 13, 183, 215
PEP 421, 296	PYTHONPERFSUPPORT, 218
PEP 432, 223	PYTHONPLATLIBDIR, 215
PEP 442, 269	PYTHONPROFILEIMPORTTIME, 214
PEP 443, 292	PYTHONPYCACHEPREFIX, 217
PEP 451, 161, 291	PYTHONS AFEPATH, 212
PEP 483, 292	PYTHONTRACEMALLOC, 218
PEP 484, 287, 292, 300	PYTHONUNBUFFERED, 184, 212
PEP 489, 162, 197	PYTHONUTF8, 209, 221
PEP 499, 102, 197 PEP 492, 288, 290	PYTHONUTE 8, 209, 221 PYTHONVERBOSE, 184, 218
PEP 498, 291	PYTHONWARNINGS, 219
PEP 519, 297	PyThread_create_key (C function), 204
PEP 523, 173, 195	PyThread_delete_key (<i>C function</i>), 204
PEP 525, 288	PyThread_delete_key_value (<i>C function</i>), 204
PEP 526, 287, 300	PyThread_get_key_value (<i>C function</i>), 204
PEP 528, 184, 215	PyThread_ReInitTLS (<i>C function</i>), 204
PEP 529, 132, 183	PyThread_set_key_value (C function), 204
PEP 538, 221	PyThread_tss_alloc(<i>C function</i>), 203
PEP 539, 203	PyThread_tss_create (C function), 203
PEP 540, 221	PyThread_tss_delete (C function), 204
PEP 552, 213	PyThread_tss_free (C function), 203
PEP 554, 199	PyThread_tss_get (C function), 204
PEP 578,63	PyThread_tss_is_created(<i>C function</i>), 203
PEP 585, 292	PyThread_tss_set (<i>C function</i>), 204
PEP 587, 205	PyThreadState, 189
PEP 590,86	PyThreadState ($Ctype$), 191
PEP 623, 124	PyThreadState_Clear(<i>C function</i>), 194
PEP 634,260	PyThreadState_Delete (C function), 194
PEP 3116,300	PyThreadState_DeleteCurrent(Cfunction), 194
PEP 3119,84	PyThreadState_EnterTracing (C function), 194
PEP 3121, 159	PyThreadState_Get (C function), 192
PEP 3147,66	PyThreadState_GetDict(C function), 195
PEP 3151,58	PyThreadState_GetFrame (<i>C function</i>), 194
PEP 3155,298	PyThreadState_GetID (C function), 194
PYTHONCOERCECLOCALE, 221	PyThreadState_GetInterpreter (<i>C function</i>),
PYTHONDEBUG, 182, 216	194
PYTHONDEVMODE, 213	PyThreadState_LeaveTracing (<i>C function</i>), 195
PYTHONDONTWRITEBYTECODE, 182, 219	PyThreadState_New (<i>C function</i>), 194
PYTHONDUMPREFS, 213, 252	PyThreadState_New (C function), 194 PyThreadState_Next (C function), 202
PYTHONEXECUTABLE, 217	PyThreadState_Next (C function), 202 PyThreadState_SetAsyncExc (C function), 195
	= · · · · · · · · · · · · · · · · · · ·
PYTHONIA CHEED, 182, 214	PyThreadState_Swap (<i>C function</i>), 192
PYTHONHOME 12 183, 214	PyThreadState.interp (<i>C member</i>), 191
PYTHONHOME, 13, 183, 189, 214	PyTime_Check (C function), 177

PyTime_CheckExact (<i>C function</i>), 177	PyType_Ready (<i>C function</i>), 109
PyTime_FromTime (C function), 177	PyType_Slot ($Ctype$), 112
PyTime_FromTimeAndFold(<i>C function</i>), 177	PyType_Slot.pfunc(<i>C member</i>), 112
PyTimeZone_FromOffset (C function), 177	PyType_Slot.slot(<i>C member</i>), 112
PyTimeZone_FromOffsetAndName (C function),	PyType_Spec ($Ctype$), 111
178	PyType_Spec.basicsize(C member), 111
PyTrace_C_CALL (C var), 201	PyType_Spec.flags (C member), 112
PyTrace_C_EXCEPTION(C var), 201	PyType_Spec.itemsize(C member), 111
PyTrace_C_RETURN (C var), 201	PyType_Spec.name (C member), 111
PyTrace_CALL(C var), 201	PyType_Spec.slots(<i>C member</i>), 112
PyTrace_EXCEPTION (C var), 201	РуТуре_Туре (<i>C var</i>), 107
PyTrace_LINE (C var), 201	PyType_Watch (C function), 108
PyTrace_OPCODE (C var), 201	PyType_WatchCallback (C type), 108
PyTrace_RETURN (C var), 201	PyTypeObject (C type), 107
PyTraceMalloc_Track (C function), 233	PyTypeObject.tp_alloc(C member), 266
PyTraceMalloc_Untrack (C function), 233	PyTypeObject.tp_as_async(C member), 255
PyTuple_Check (C function), 140	PyTypeObject.tp_as_buffer(C member), 257
PyTuple_CheckExact (C function), 140	PyTypeObject.tp_as_mapping(C member), 255
PyTuple_GET_ITEM (C function), 140	PyTypeObject.tp_as_number(C member), 255
PyTuple_GET_SIZE (C function), 140	PyTypeObject.tp_as_sequence(C member), 255
PyTuple_GetItem (C function), 140	PyTypeObject.tp_base(C member), 264
PyTuple_GetSlice (C function), 140	PyTypeObject.tp_bases(C member), 267
PyTuple_New (C function), 140	PyTypeObject.tp_basicsize(C member), 253
PyTuple_Pack (C function), 140	PyTypeObject.tp_cache(C member), 268
PyTuple_SET_ITEM (C function), 141	PyTypeObject.tp_call(C member), 256
PyTuple_SetItem (C function), 141	PyTypeObject.tp_clear(<i>C member</i>), 261
<pre>PyTuple_SetItem(),8</pre>	PyTypeObject.tp_dealloc(<i>C member</i>), 253
PyTuple_Size (C function), 140	PyTypeObject.tp_del(C member), 268
PyTuple_Type (C var), 140	PyTypeObject.tp_descr_get(C member), 265
PyTupleObject ($Ctype$), 140	PyTypeObject.tp_descr_set(C member), 265
PyType_AddWatcher (<i>C function</i>), 108	PyTypeObject.tp_dict(C member), 265
PyType_Check (C function), 107	PyTypeObject.tp_dictoffset(<i>C member</i>), 265
PyType_CheckExact (C function), 107	PyTypeObject.tp_doc(C member), 260
PyType_ClearCache (<i>C function</i>), 107	PyTypeObject.tp_finalize(<i>C member</i>), 268
PyType_ClearWatcher (C function), 108	PyTypeObject.tp_flags(<i>C member</i>), 257
PyType_FromMetaclass (C function), 110	PyTypeObject.tp_free(<i>C member</i>), 267
PyType_FromModuleAndSpec (<i>C function</i>), 111	PyTypeObject.tp_getattr(<i>C member</i>), 254
PyType_FromSpec (C function), 111	PyTypeObject.tp_getattro(<i>C member</i>), 256
PyType_FromSpecWithBases (<i>C function</i>), 111	PyTypeObject.tp_getset(C member), 264
PyType_GenericAlloc (C function), 109	PyTypeObject.tp_hash(<i>C member</i>), 255
PyType_GenericNew (C function), 109	PyTypeObject.tp_init(C member), 266
PyType_GetDict(C function), 108	PyTypeObject.tp_is_gc(C member), 267
PyType_GetFlags (C function), 108	PyTypeObject.tp_itemsize(<i>C member</i>), 253
PyType_GetModule (C function), 109	PyTypeObject.tp_iter(<i>C member</i>), 263
PyType_GetModuleByDef (C function), 110	PyTypeObject.tp_iternext(C member), 264
PyType_GetModuleState (C function), 110	PyTypeObject.tp_members(<i>C member</i>), 264
PyType_GetName (C function), 109	PyTypeObject.tp_methods(<i>C member</i>), 264
PyType_GetQualName (C function), 109	PyTypeObject.tp_mro(<i>C member</i>), 268
PyType_GetSlot (C function), 109	PyTypeObject.tp_name(<i>C member</i>), 252
PyType_GetTypeDataSize($C function$), 85	PyTypeObject.tp_new(C member), 266
PyType_HasFeature (C function), 108	PyTypeObject.tp_repr(<i>C member</i>), 255
PyType_IS_GC (C function), 108	PyTypeObject.tp_richcompare(C member), 262
PyType_IsSubtype (C function), 109	PyTypeObject.tp_setattr(<i>C member</i>), 254
PyType_Modified (C function), 108	PyTypeObject.tp_setattro(C member), 256

PyTypeObject.tp_str(C member), 256	PyUnicode_DecodeLocale (C function), 131
PyTypeObject.tp_subclasses(C member), 268	PyUnicode_DecodeLocaleAndSize (C function),
PyTypeObject.tp_traverse(<i>C member</i>), 260	131
PyTypeObject.tp_vectorcall(C member), 269	PyUnicode_DecodeMBCS (C function), 138
PyTypeObject.tp_vectorcall_offset $(C$	PyUnicode_DecodeMBCSStateful (C function),
member), 254	138
PyTypeObject.tp_version_tag(<i>C member</i>), 268	PyUnicode_DecodeRawUnicodeEscape (C func-
PyTypeObject.tp_watched(C member), 269	tion), 136
PyTypeObject.tp_weaklist(C member), 268	PyUnicode_DecodeUnicodeEscape (C function),
<pre>PyTypeObject.tp_weaklistoffset(Cmember),</pre>	136
263	PyUnicode_DecodeUTF7 (C function), 136
PyTZInfo_Check (C function), 177	PyUnicode_DecodeUTF7Stateful (C function),
PyTZInfo_CheckExact (C function), 177	136
PyUnicode_1BYTE_DATA (C function), 125	PyUnicode_DecodeUTF8 (C function), 134
PyUnicode_1BYTE_KIND (C macro), 125	PyUnicode_DecodeUTF8Stateful (C function),
PyUnicode_2BYTE_DATA (C function), 125	134
PyUnicode_2BYTE_KIND (C macro), 125	PyUnicode_DecodeUTF16 (C function), 135
PyUnicode_4BYTE_DATA (C function), 125	PyUnicode_DecodeUTF16Stateful (C function),
PyUnicode_4BYTE_KIND (C macro), 125	135
PyUnicode_AsASCIIString (C function), 137	PyUnicode_DecodeUTF32 (C function), 135
PyUnicode_AsCharmapString(C function), 137	PyUnicode_DecodeUTF32Stateful (C function),
PyUnicode_AsEncodedString (C function), 134	135
PyUnicode_AsLatin1String (C function), 137	PyUnicode_EncodeCodePage (C function), 138
PyUnicode_AsMBCSString (C function), 138	PyUnicode_EncodeFSDefault (C function), 132
PyUnicode_AsRawUnicodeEscapeString $(C$	PyUnicode_EncodeLocale (C function), 131
function), 136	PyUnicode_Fill (C function), 130
PyUnicode_AsuCS4 (C function), 130	PyUnicode_Find (C function), 139
PyUnicode_AsuCS4Copy (C function), 130	PyUnicode_FindChar (C function), 139
PyUnicode_AsUnicodeEscapeString ($C\ func$ -	PyUnicode_Format (C function), 139
tion), 136	PyUnicode_FromEncodedObject(Cfunction), 130
PyUnicode_AsUTF8 (C function), 134	PyUnicode_FromFormat (C function), 128
PyUnicode_AsUTF8AndSize(C function), 134	PyUnicode_FromFormatV(C function), 129
PyUnicode_AsUTF8String (C function), 134	PyUnicode_FromKindAndData(C function), 127
PyUnicode_AsUTF16String (C function), 136	PyUnicode_FromObject (C function), 129
PyUnicode_AsUTF32String(C function), 135	PyUnicode_FromString (C function), 128
PyUnicode_AsWideChar (<i>C function</i>), 133	${\tt PyUnicode_FromStringAndSize} \ ({\it Cfunction}), 127$
PyUnicode_AsWideCharString(C function), 133	PyUnicode_FromWideChar(Cfunction), 133
PyUnicode_Check (C function), 124	PyUnicode_FSConverter (<i>C function</i>), 132
PyUnicode_CheckExact (C function), 124	PyUnicode_FSDecoder (<i>C function</i>), 132
PyUnicode_Compare (<i>C function</i>), 139	PyUnicode_GET_LENGTH (C function), 125
${\tt PyUnicode_CompareWithASCIIString}~(C~func-$	PyUnicode_GetLength (C function), 130
tion), 139	PyUnicode_InternFromString(C function), 140
PyUnicode_Concat (C function), 138	PyUnicode_InternInPlace (C function), 140
PyUnicode_Contains (C function), 139	PyUnicode_IsIdentifier(C function), 126
PyUnicode_CopyCharacters ($\it Cfunction$), 130	PyUnicode_Join (C function), 139
PyUnicode_Count (C function), 139	PyUnicode_KIND (C function), 125
PyUnicode_DATA (<i>C function</i>), 125	PyUnicode_MAX_CHAR_VALUE (C function), 125
PyUnicode_Decode (<i>C function</i>), 134	PyUnicode_New (C function), 127
PyUnicode_DecodeASCII (C function), 137	PyUnicode_READ (C function), 125
PyUnicode_DecodeCharmap (C function), 137	PyUnicode_READ_CHAR (C function), 125
PyUnicode_DecodeFSDefault (C function), 132	PyUnicode_ReadChar (C function), 130
PyUnicode_DecodeFSDefaultAndSize (C func-	PyUnicode_READY (C function), 124
tion), 132	PyUnicode_Replace (C function), 139
PyUnicode_DecodeLatin1 (C function), 137	PyUnicode_RichCompare (C function), 139

PyUnicode_Split (C function), 138	PyUnstable_Code_New (C function), 153
PyUnicode_Splitlines (C function), 138	PyUnstable_Code_NewWithPosOnlyArgs ($\it C$
PyUnicode_Substring (C function), 130	function), 154
PyUnicode_Tailmatch (C function), 139	PyUnstable_Code_SetExtra(C function), 156
PyUnicode_Translate (C function), 137	PyUnstable_Eval_RequestCodeExtraIndex
PyUnicode_Type (C var), 124	(<i>C function</i>), 156
PyUnicode_WRITE (C function), 125	PyUnstable_Exc_PrepReraiseStar (C func-
PyUnicode_WriteChar (C function), 130	tion), 54
PyUnicodeDecodeError_Create (C function), 55	PyUnstable_GC_VisitObjects (C function), 282
PyUnicodeDecodeError_GetEncoding (C function), 55	PyUnstable_InterpreterFrame_GetCode (C function), 173
PyUnicodeDecodeError_GetEnd (C function), 55	PyUnstable_InterpreterFrame_GetLasti (C
PyUnicodeDecodeError_GetObject (C function), 55	function), 173 PyUnstable_InterpreterFrame_GetLine (C
PyUnicodeDecodeError_GetReason (C func-	function), 173
tion), 55	PyUnstable_Long_CompactValue (<i>C function</i>),
PyUnicodeDecodeError_GetStart (C function),	116
55	PyUnstable_Long_IsCompact (C function), 116
PyUnicodeDecodeError_SetEnd(<i>C function</i>), 55	PyUnstable_Object_GC_NewWithExtraData
PyUnicodeDecodeError_SetReason (C func-	(C function), 280
tion), 55	PyUnstable_PerfMapState_Fini (<i>C function</i>),
PyUnicodeDecodeError_SetStart (C function),	80
55	PyUnstable_PerfMapState_Init (C function),
PyUnicodeEncodeError_GetEncoding ($C\ func$ -	79
tion), 55	PyUnstable_Type_AssignVersionTag (C func-
PyUnicodeEncodeError_GetEnd(C function), 55	tion), 110
PyUnicodeError_GetObject (C function), 55	PyUnstable_WritePerfMapEntry (C function), 80
${\tt PyUnicodeEncodeError_GetReason} \ \ (C \ \textit{func-}$	PyVarObject (<i>Ctype</i>), 236
tion), 55	PyVarObject_HEAD_INIT(<i>C macro</i>), 237
${\tt PyUnicodeEncodeError_GetStart}~(C~\textit{function}),$	PyVarObject.ob_size(<i>C member</i>), 252
55	PyVectorcall_Call (C function), 88
PyUnicodeEncodeError_SetEnd(C function), 55	PyVectorcall_Function (C function), 88
PyUnicodeEncodeError_SetReason (C func-	PyVectorcall_NARGS (C function), 88
tion), 55	PyWeakref_Check (C function), 169
PyUnicodeEncodeError_SetStart (<i>C function</i>),	PyWeakref_CheckProxy (C function), 169
55	PyWeakref_CheckRef (<i>C function</i>), 169
PyUnicodeObject ($Ctype$), 124	PyWeakref_GET_OBJECT (<i>C function</i>), 169
	PyWeakref_GetObject(<i>C function</i>), 169
tion), 55	PyWeakref_NewProxy (<i>C function</i>), 169
-	PyWeakref_NewRef (<i>C function</i>), 169
function), 55	PyWideStringList(<i>Ctype</i>), 206
	PyWideStringList_Append (C function), 206
function), 55	PyWideStringList_Insert (<i>C function</i>), 206
PyUnicodeTranslateError_GetStart (<i>C func-</i>	PyWideStringList.items (<i>C member</i>), 206
tion), 55	PyWideStringList.length (<i>C member</i>), 206
PyUnicodeTranslateError_SetEnd (C function), 55	PyWrapper_New (<i>C function</i>), 166
${\tt PyUnicodeTranslateError_SetReason} \qquad (C$	R
function), 55	ramasse-miettes, 292
PyUnicodeTranslateError_SetStart (C func-	READ_RESTRICTED, 242
tion), 55	READONLY, 242
PyUnstable, 15	realloc(), 225
PyUnstable_Code_GetExtra(C function), 156	référence empruntée. 289

référence forte, 299	T_BYTE, 244
releasebufferproc(<i>Ctype</i>), 276	T_CHAR, 244
repr	T_DOUBLE, 244
built-in function, 83, 255	T_FLOAT, 244
reprfunc (<i>C type</i>), 276	T_INT, 244
RESTRICTED, 242	T_LONG, 244
retours à la ligne universels, 300	T_LONGLONG, 244
richempfunc (C type), 276	T_NONE (<i>C macro</i>), 244
	T_OBJECT (<i>C macro</i>), 244
S	T_OBJECT_EX, 244
sdterr	T_PYSSIZET, 244
stdin stdout, 186	T_SHORT, 244
search	T_STRING, 244
path, module, 12, 185, 187	T_STRING_INPLACE, 244
sendfunc (<i>C type</i>), 277	T_UBYTE, 244
	T_UINT, 244
sequence	T_ULONG, 244
object, 120	T_ULONGULONG, 244
séquence, 298	T_USHORT, 244
set	tableau de correspondances (mapping en an
object, 148	glais), 295
set_all(),9	ternaryfunc (<i>Ctype</i>), 277
setattrfunc(<i>Ctype</i>), 276	tranche, 299
setattrofunc (<i>Ctype</i>), 276	traverseproc (<i>C type</i>), 281
setswitchinterval() (in module sys), 189	· -
SIGINT, 52, 53	tuple
signal	built-in function, 95, 144 object, 140
module, 52, 53	_
SIZE_MAX, 115	typage canard (duck-typing), 290
special	type, 299
méthode, 299	built-in function, 84
spécificateur de module, 295	object, 7, 107
ssizeargfunc ($Ctype$), 277	type générique, 292
ssizeobjargproc(<i>C type</i>), 277	U
staticmethod	
built-in function, 240	ULONG_MAX, 115
stderr (in module sys), 198	unaryfunc ($C type$), 277
stdin	V
stdout sdterr, 186	V
stdin (<i>in module sys</i>), 198	variable de classe, 289
stdout	variable de contexte, 289
sdterr, stdin, 186	variable d'environnement
stdout (in module sys), 198	PYVENV_LAUNCHER, 212, 217
strerror(),47	PATH, 12, 13
string	PYTHONCOERCECLOCALE, 221
PyObject_Str (C function), 83	PYTHONDEBUG, 182, 216
structmember.h,244	PYTHONDEVMODE, 213
$sum_list(), 10$	PYTHONDONTWRITEBYTECODE, 182, 219
sum_sequence(), 10, 11	PYTHONDUMPREFS, 213, 252
sys	PYTHONEXECUTABLE, 217
module, 12, 185, 198	PYTHONFAULTHANDLER, 213
SystemError (built-in exception), 158, 159	PYTHONHASHSEED, 183, 214
_	PYTHONHOME, 13, 183, 189, 214
T	PYTHONINSPECT, 183, 214
T_BOOL, 244	PYTHONINTMAXSTRDIGITS, 215
	-, -

```
PYTHONIOENCODING, 186, 218
    PYTHONLEGACYWINDOWSFSENCODING,
                                        183.
       209
   PYTHONLEGACYWINDOWSSTDIO, 183, 215
    PYTHONMALLOC, 226, 230, 231, 233
    PYTHONMALLOCSTATS, 215, 226
    PYTHONNODEBUGRANGES, 212
   PYTHONNOUSERSITE, 184, 218
    PYTHONOPTIMIZE, 184, 216
   PYTHONPATH, 13, 183, 215
   PYTHONPERFSUPPORT, 218
   PYTHONPLATLIBDIR, 215
   PYTHONPROFILEIMPORTTIME, 214
   PYTHONPYCACHEPREFIX, 217
   PYTHONSAFEPATH, 212
    PYTHONTRACEMALLOC, 218
    PYTHONUNBUFFERED, 184, 212
   PYTHONUTF8, 209, 221
   PYTHONVERBOSE, 184, 218
   PYTHONWARNINGS, 219
vectorcallfunc (C type), 87
verrou global de l'interpréteur, 292
version (in module sys), 188
visitproc (Ctype), 281
vue de dictionnaire, 290
W
WRITE RESTRICTED, 242
```