LeadVolt terminal guide

Owner reference · Windows PowerShell to Ubuntu VPS
Prepared 26 October 2026 · Dubai time

1. Connect from your Windows PC

Open **PowerShell** and run this command. Enter your SSH-key passphrase privately when prompted. No characters may appear while you type it.

```
ssh -i "$env:USERPROFILE\.ssh\leadvolt-racknerd-staging" lvdeploy@192.236.172.196
```

After login, subsequent commands run on the VPS. If sudo asks for a password, use the server account's sudo password—not your CRM login password.

2. Discover the actual app service names

```
systemctl list-units --all --type=service 'leadvolt*'
```

Check the output first. The commands below use **leadvolt-staging.service** only as an example. Use them only if that exact service appears; otherwise substitute the actual staging service name. Production must be managed separately.

3. Check staging

```
sudo systemctl status leadvolt-staging.service --no-pager
```

Look for **Active: active (running)**. If it is failed or repeatedly restarting, inspect logs before restarting it repeatedly.

4. Start or restart staging

Start a stopped staging service:

```
sudo systemctl start leadvolt-staging.service
```

Restart staging when needed; this briefly interrupts access:

```
sudo systemctl restart leadvolt-staging.service
```

Run the status command again afterward. A restart does not deploy a new build.

Checks, access & recovery

The VPS and its services should keep running after you disconnect.

5. Read recent staging logs

```
sudo journalctl -u leadvolt-staging.service -n 50 --no-pager
```

Logs can include private data. Review and redact them before sharing. Do not print or share your environment files, API keys or encryption keys.

6. Check server health

```
uptime
free -h
df -h
```

uptime: running time and system load. **free -h:** memory usage. **df -h:** disk capacity and free space. These commands display information without changing settings.

Check the Nginx web server:

```
sudo systemctl status nginx --no-pager
```

7. Open staging in your browser

https://staging.leadvoltcrm.com/

Staging was restricted to an approved public IP address. If you change networks, the site may be blocked even while the service is running. Have the authorized access rule updated; do not disable the firewall.

8. Disconnect safely

```
exit
```

Closing SSH does not stop services managed by systemd.

Before you rely on this guide

Have your operator confirm the **actual staging and production service names**, automatic startup after reboot, and the backup destination, schedule, recovery passphrase storage and tested restore procedure. These were not independently checked while preparing this PDF.

Updates: use the verified deployment procedure with a recovery backup. Do not manually run another Node process or copy a local database over server data.

Recovery: restarting an app is different from restoring a database. Never overwrite newer user records with an older backup without a reviewed recovery plan.