## Learn, Share, Build

Each month, over 50 million developers come to Stack Overflow to learn, share their knowledge, and build their careers.

Google Facebook

OR

Join the world's largest developer community.

## How to set SELinux to 0 or permissive mode in android 4.4.4 and above?

I want to set the SELinux (Security Enhanced Linux) mode to Permissive or (0) on android 4.4.4 (and above if possible). I use the following command: setenforce 0, setenforce permissive and setenforce Permissive under root (my device is rooted). But the output of getenforce is always Enforcing . Now I am exhausted with this problem.

Can any one give me a solution? Thanks in advance.







## 3 Answers

Apparently Google has removed the <code>config\_security\_selinux\_develop</code> kernel flag from many of their Stock kernels. Thus the standard trick mentioned by William (below) probably doesn't work. An example of these devices is the Samsung Note 4 (SM-N910F) running AOS 4.4.4.

The link above states:

CONFIG SECURITY SELINUX DEVELOP aka global permissive mode, is useful for when you are first developing device-specific policy for a board (add 'androidboot.selinux=permissive' to BOARD\_KERNEL\_CMDLINE). It also permits transient setenforce 0 in -userdebug or -eng builds, which can be helpful for developers.

If the bootloader is locked, then you can't modify the kernel cmdline

"Also, the code in the init program for processing the androidboot.selinux= option is only compiled in -userdebug and -eng builds, so even aside from bootloader locking, you cannot use androidboot.selinux=permissive on a -user build."

The way to check what build type you have is:

\$ getprop ro.build.type

edited Feb 24 '16 at 13:37

answered Sep 18 '15 at 20:31 not2qubit **2,420** 21 36

Depending on how your device was rooted and what Android ROM your running will determine

第1页 共1页 2017/11/9 下午7:10