

# Operations Guide

| Field          | Value                                  |
|----------------|----------------------------------------|
| Document ID    | UAIL-ITDASH-OPS-ADM-001                |
| Version        | 1.1                                    |
| Status         | Internal review                        |
| Classification | Internal                               |
| Owner          | Tech-Unit IT                           |
| Last Updated   | 2026-07-19                             |
| Audience       | Operators, supervisors, administrators |

## 1. Purpose

This guide combines the earlier operator and admin manuals into one practical runtime guide for daily use, troubleshooting, and service recovery.

## 2. Access Points

| Surface  | URL Pattern                                    | Login Expectation      |
|----------|------------------------------------------------|------------------------|
| Operator | <code>http://&lt;server&gt;:21060/login</code> | Operator password only |
| Admin    | <code>http://&lt;server&gt;:21061/login</code> | Admin password only    |

## 3. Operator Workflow

Operator login

Operator dashboard

### 3.1 What Operators Monitor

- HCI cluster metrics
- Hindalco Service Desk workload and SLA
- network carrier and SDWAN links
- server fleet health

### 3.2 How To Read Card Link Status

- **OK** : collector is updating normally
- **STALE** : last success is older than expected
- **ERROR** : collector attempted refresh and failed
- **NEVER** : no successful sync has been recorded

Operational rule:

- if the link status is not healthy, treat the visible values as last-synced values rather than current live values

### 3.3 Color Language

- green: healthy or within threshold
- amber: early warning
- orange: elevated concern or SLA below target band
- red: critical or about to miss
- slate: offline or unavailable

### 3.4 Operator Filters

The operator surface supports show/hide filtering for:

- sections: HCI, HSD, Network, Servers
- server status: normal, warning, critical, offline
- server platform: HCI VM, On Prem
- server OS: Windows, Linux
- server source: Nutanix, SW45, fallback
- network carriers and paths
- HSD work types and special queues

### 3.5 Mobile And Portrait Use

Narrow screens use a stacked layout intended for monitoring and quick inspection. The wallboard layout on **1920x1200** remains the primary presentation target.

## 4. Admin Workflow

---

 Admin overview

 Admin sessions

### 4.1 Admin Console Areas

- **Overview** : quick health view and top-level actions
- **Services** : PM2-backed run state and control actions
- **Sessions** : HSD and SolarWinds session validation, reauth, and imports
- **Sources** : collector URLs, enable flags, usernames, passwords, and metadata
- **Help** : embedded PDF document set

### 4.2 Services Tab

Use **Services** to:

- inspect process state
- confirm health summaries
- start, stop, or restart specific services
- restart the full stack when the issue is cross-service

Expected services:

- **api-gateway**
- **dashboard-ui**
- **dashboard-frontdoor-operator**
- **dashboard-frontdoor-admin**
- **nutanix-collector**
- **solarwinds-collector**
- **symphony-collector**

### 4.3 Sessions Tab

Use **Sessions** to validate that saved browser state is still accepted by the live portals.

Typical states:

- AUTH OK
- EXPIRED
- UNREACHABLE
- MISSING
- INVALID

## 4.4 HSD Recovery

When HSD is expired:

1. Open the admin surface from the server itself if possible.
2. Go to **Sessions**.
3. Launch HSD reauthentication on the server.
4. Complete the interactive Edge login and wait for the refreshed storage-state file to be saved.

Use legacy-profile import only as an explicit recovery path when an older authenticated Edge profile already exists and must be migrated.

## 4.5 SolarWinds Recovery

When SolarWinds validation shows expiry or invalid state:

1. Go to **Sessions**.
2. Run the SolarWinds reauthentication helper.
3. Complete the browser login flow.
4. Revalidate the session snapshot.

## 4.6 Sources Tab

Use **Sources** to manage:

- enable or disable state
- target URLs
- usernames and passwords
- poll intervals
- source-specific metadata and notes

Current managed targets:

- Nutanix primary
- SolarWinds servers
- SolarWinds networks
- Symphony primary

## 5. Incident Handling

---

### 5.1 If A Dashboard Card Looks Wrong

1. Check the card data-link status.
2. If stale or erroring, treat values as last-synced.
3. If healthy but abnormal, treat it as a live operational condition.
4. Escalate collector or session problems to an admin.


### 5.2 If A Collector Stops Updating

1. Check `Services` .
2. Check `Sessions` for expiry or invalid state.
3. Check `Sources` for configuration drift.
4. Restart the affected collector only if the root cause is understood or after credentials are corrected.

### 5.3 After Credential Changes

1. Save the updated settings.
2. Restart the affected collector if required.
3. Validate the next sync and check the card link state.

# 6. Recovery Flow



## 7. Do And Do Not

---

Do:

- keep operator use focused on monitoring and filters
- use admin actions only from authorized accounts
- treat session expiry as a source availability issue
- keep internal services on loopback

Do not:

- expose `3001` or `4000` to the LAN
- assume session files are valid just because they exist
- use legacy HSD import as the normal login path
- treat fallback telemetry as primary source telemetry