安装部署 gitlab Runner

1.下载gitlab Runner安装包

```
wget https://mirrors.tuna.tsinghua.edu.cn/gitlab-runner/yum/el7-aarch64/gitlab-runner-16.9.0-1.aarch64.rpm
# 也可在 https://mirrors.tuna.tsinghua.edu.cn/ 或 https://gitlab-runner-downloads.s3.amazonaws.com/latest/index.html中下载符合自己环境的gitlab Runer安装包,这里以gitlab-runner-16.9.0-1.aarch64.rpm为例,进行手动下载后传至服务器
```

2.安装gitlab Runner安装包

```
yum install -y git tar
rpm -ivh gitlab-runner-16.9.0-1.aarch64.rpm
```

3.指定gitlab-runner

```
useradd Kunpeng_staff
gitlab-runner uninstall
gitlab-runner install --working-directory /home/Kunpeng_staff --user Kunpeng_staff
```

4.启动gitlab-runner

```
systemctl daemon-reload #重新加载配置
systemctl start gitlab-runner #启动服务
systemctl enable gitlab-runner #设置开机启动
systemctl restart gitlab-runner #重启服务
```

4. 查看 gitlab-runner

```
systemctl status gitlab-runner
```

成功启动如下图所示


```
| Croate|Coalhost home| # systemctl status gitlab-runner | Croate|Coalhost | Croate|Coalhost
```

5.设置权限


```
chown -R Kunpeng_staff.Kunpeng_staff /home/gitlab-runner
```

6.gitlab runner注册服务


登录gitlab,在管理中心Runner中新建一个runner



标签多个时用逗号隔开,只可为kunpeng_scanner, kunpeng_builder, kunpeng_executor,其他选项按需填写



根据所示url,token去gitlab-runner环境注册



运行 gitlab-runner register,参数如图根据实际情况填写,注册成功后会显示Runner registered successfully

```
| Frote | State | Sta
```

点击进入runners页面

