## NAME

ovn−detrace − convert ‘‘ovs−appctl ofproto/trace’’ output to combine OVN logical flow information.

## SYNOPSIS

**ovn−detrace** < *file*

Common options:

[**−h** | **−−help**] [**−V** | **−−version**]

## DESCRIPTION

The **ovn−detrace** program reads **ovs−appctl ofproto/trace** output on stdin, looking for flow cookies, and displays for each cookie the OVN south-bound records that contributed to its creation. It further displays the related north-bound information when applicable, e.g., the ACL that generated the logical flow that gets translated to an OpenFlow rule with a given cookie.

## OPTIONS

**−h**

**−−help** Prints a brief help message to the console.

**−V**

**−−version**

Prints version information to the console.

**−−ovnsb=***server*

The OVN Southbound DB remote to contact. If the **OVN_SB_DB** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/ovnsb_db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

**−−ovnnb=***server*

The OVN Northbound DB remote to contact. If the **OVN_NB_DB** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/ovnnb_db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

**−−ovs=** Also decode flow information (like OVS ofport) from the flows by connecting to the OVS DB.

**−−no-leader-only**

Connect to any cluster member, not just the leader. The option works for OVN Southbound DB and OVN Northbound DB.

**−−ovsdb=***server*

The OVS DB remote to contact if **−−ovs** is present. If the **OVS_RUNDIR** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

**−p** *privkey.pem*

**−−private−key=***privkey.pem*

Specifies a PEM file containing the private key used as **ovn−detrace**’s identity for outgoing SSL/TLS connections.

**−c** *cert.pem*

**−−certificate=***cert.pem*

Specifies a PEM file containing a certificate that certifies the private key specified on **−p** or **−−private−key** to be trustworthy. The certificate must be signed by the certificate authority (CA) that the peer in SSL/TLS connections will use to verify it.

**−C** *cacert.pem*

**−−ca−cert=***cacert.pem*

Specifies a PEM file containing the CA certificate that **ovn−detrace** should use to verify certificates presented to it by SSL/TLS peers. (This may be the same certificate that SSL/TLS peers use to verify the certificate specified on **−c** or **−−certificate**, or it may be a different one, depending on the PKI

design in use.)

## SEE ALSO

**ovs−appctl**(8),**ovn−sbctl**(8),**ovn−nbctl**(8),**ovn−trace**(8)