



Remove Spaces in Excel

The TRIM function in Excel removes leading spaces, extra spaces and trailing spaces. Use the SUBSTITUTE function to remove all spaces or non-breaking spaces.

1. The TRIM function below removes 2 leading spaces, 3 extra spaces and 2 trailing spaces.

[Discover more](#)

④ Spreadsheet Software

 Calculators

Office & Productivity Software

 Calculators & Reference Tools

Software

Word Processing Software

⚡ statistical

Note: the TRIM function does not remove single spaces between words.

2. To get the length of a string, use the LEN function.

Explanation: the LEN function counts 2 spaces, 2 characters, 4 spaces, 3 characters and 2 spaces.

3. You can use the SUBSTITUTE function to remove all spaces.

B1	:	X	✓	f _x	=SUBSTITUTE(A1," ","")				
	A	B	C	D	E	F	G	H	I
1	A	B	C	ABC					

Note: the SUBSTITUTE function substitutes spaces (second argument) with empty strings (third argument).

Text imported from other applications may contain ASCII characters. The CLEAN function removes the first 32 non-printable ASCII characters (codes 0 through 31).

4. The CLEAN function below removes a non-printable character, CHAR(7).

5. Simply combine CLEAN and TRIM to remove non-printable characters and spaces.

6. The CLEAN function removes line breaks. To enter a line break, press ALT + ENTER.

7. You can also use the SUBSTITUTE function to remove a line break, CHAR(10), and replace it with something else. For example, a comma and a space.

The CLEAN function doesn't remove all ASCII characters. Simply use the SUBSTITUTE function to remove other ASCII characters.

8. First, find out the code number of the character.

B1 : =CODE(A1)

1	182							
2								

9. Next, use SUBSTITUTE and CHAR to return the text string without this character.

B1	⋮	X	✓	f _x	=SUBSTITUTE(A1,CHAR(182),"")			
A	B	C	D	E	F	G	H	I
1	geo2¶	geo2						
2								

10. If your text contains non-breaking spaces, CHAR(160), the TRIM function doesn't work.

B1	⋮	X	✓	f _x	=TRIM(A1)			
A	B	C	D	E	F	G	H	I
1	Hi John	Hi John						
2								

11. You can use the SUBSTITUTE function to substitute non-breaking spaces, CHAR(160) with normal spaces, CHAR(32). Don't forget to add a TRIM function to remove the extra spaces.

B1	⋮	X	✓	f _x	=TRIM(SUBSTITUTE(A1,CHAR(160),CHAR(32)))			
A	B	C	D	E	F	G	H	I
1	Hi John	Hi John						
2								

Discover more [Spreadsheet Software](#)

[Office & Productivity Software](#)

[Calculators](#)

[Word Processing Software](#)

[Calculators & Reference Tools](#)

[statistical](#)

[Software](#)

[Statistics](#)

Search Entire Site

Go

Chapter

■ Text Functions

Learn more, it's easy

- Separate Strings
-

- Count Words
-

- Text to Columns
-

- Find
-

- Search
-

- Change Case
-

- Remove Spaces
-

- Compare Text
-

- Substitute vs Replace
-

- Text
-

- Concatenate
-

- Substring
-

↓ Download Excel File

- [remove-spaces.xlsx](#)
-

Next Chapter

- [Lookup & Reference Functions](#)
-

Follow Excel Easy



Become an Excel Pro

- [1. Introduction](#)
-

- [2. Basics](#)
-

- [3. Functions](#)
-

- 4. Data Analysis

- 5. VBA

Remove Spaces • © 2010-2026

Start with Excel in 2026: Range • Formulas and Functions • Ribbon • Cell References • Sort • Filter