权限	RESTAPI	ServerResource	ModuleMedthod
read_topology	/wm/device/?ipv4=.. **circuitpusher**	net.floodlightcontroller.devicemanager.web: AbstractDeviceResource.java:(GET) getDevices()	net.floodlightcontroller.devicemanager.internal; DeviceManagerImpl.java: queryDevices()
read_topology	/wm/topology/route/{src-dpid}/{src-port}/{dst-dpid}/{dst-port}/json **circuitpusher**	net.floodlightcontroller.topology.web; RouteResource.java:(GET) retrieve()	net.floodlightcontroller.topology; TopologyManager.java: getRoute(long,short,long,short,long)
flow_mod_route set_flow_priority	/wm/staticflowentrypusher/json **circuitpusher**	net.floodlightcontroller.staticflowentry.web; StaticFlowEntryPusherResource.java:(Post) store(String fmJson)	net.floodlightcontroller.storage; AbstractStorageSource.java: insertRowAsync()
flow_mod_drop	/wm/staticflowentrypusher/json **circuitpusher** /wm/staticflowentrypusher**/json/delete**	net.floodlightcontroller.staticflowentry.web; StaticFlowEntryPusherResource.java:(Delete) del(String fmJson) StaticFlowEntryDeleteResource.java: retrieve()	net.floodlightcontroller.storage; AbstractStorageSource.java: deleteRowAsync()
read_statistics	/wm/core/switch/all/{statType}/json statType=flow/port/queue **circuitpusher** /wm/core/switch/{switchId}/{statType}/json	net.floodlightcontroller.core.web; AllSwitchStatisticsResource.java:(GET) GetConcurrentStatsThread:run() SwitchStatisticsResource.java:(GET) retrieve()	net.floodlightcontroller.core.web; SwitchResourceBase.java： getSwitchStatistics(string,long,OFType) getSwitchStatistics(string,string,OFType) ***************
read_all_flow	/wm/staticflowentrypusher/list/{switch}/json switch=all/dpid	net.floodlightcontroller.staticflowentry.web; ListStaticFlowEntriesResource.java:（GET） ListStaticFlowEntries()	net.floodlightcontroller.staticflowentry; StaticFlowEntryPusher.java: getFlows() getFlows(String dpid) ***************
read_topology	wm/core/controller/switches/json /wm/core/switch/{switchId}/role/json	net.floodlightcontroller.core.web; ControllerSwitchesResource.java:(GET) retrieve() SwitchRoleResource.java:(GET) getRole()	net.floodlightcontroller.core.internal; Controller.java getAllSwitchMap() ***************
read_topology	/wm/topology/links/json /wm/topology//directed-links/json /wm/topology/external-links/json	net.floodlightcontroller.linkdiscovery.web; LinksResource.java:(GET) retrieve() DirectedLinksResource.java:(GET) retrieve()	net.floodlightcontroller.linkdiscovery.internal; LinkDiscoveryManager.java getLinks() ***************

		ExternalLinksResource.java:(GET) retrieve()	
read_controller_info	/wm/core/memory/json	net.floodlightcontroller.core.web; ControllerMemoryResource.java:(GET) retrieve()	net.floodlightcontroller.core.web; ControllerMemoryResource.java: retrieve()
set_device_config	/wm/storage/notify/json	2net.floodlightcontroller.linkdiscovery.internal; LinkDiscoveryManager.java: rowsModified() 3net.floodlightcontroller.storage; AbstractStorageSource.java: 3.1notifyListeners(notification); 3.2notifyListeners(List<StorageSourceNotification> notifications) 4net.floodlightcontroller.storage.web; StorageNotifyResource.java:(Post) notify(String entity)	1 net.floodlightcontroller.core; OFSwitchBase.java: setAttribute() ************************** 在4处做控制： net.floodlightcontroller.storage.web; StorageNotifyResource.java:(Post) notify(String entity) ***************************** 未测试
flow_mod_modify_hdr		net.floodlightcontroller.staticflowentry; StaticFlowEntryPusher.java: parseRow()	net.floodlightcontroller.staticflowentry; StaticFlowEntries.java: parseActionString() 未测试