Mode Line Control

Description	<u>Keystroke</u>	Function	Notes / Example description
Emacs Mode Line	An early version of a page that	at will describe tools to manage	the mode line.
See: <u>S Customize</u>	Currently PEL does not provide much support for controlling Emacs mode line. It provides the following: • The pel-pkg-for-modeline customization group that contains the user-options used to activate mode line related packages: • The delight external package PEL activates it when the pel-use-delight user-option is turned on (set to t). • Access this customization group with <f11> M-d <f2>. • When delight is used, PEL activates short lighters for some minor-modes.</f2></f11>		
a ===	_		tion of extra information shown on the mode line.
Open this PDF file. See also: <u>Nelp/Info</u>	<f11> M-d <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>Node Line</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
<u>➤ Customize</u> PEL mode line support	<f11> M-d <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL mode line support • If OTHER-WINDOW is non-nil (use C-u), display in another window.
∑ Customize Emacs mode line	<f11> M-d <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs mode line support: display-time, mode-line • If OTHER-WINDOW is non-nil (use C-u), display in another window.
Toggle which-function-mode to display name of current function at point See also: Menus Menus	• <f11> ? f • <f11> M-d f</f11></f11>	(which-function-mode &optional ARG)	 Toggle mode line display of current function (Which Function mode). With a prefix argument ARG, enable Which Function mode if ARG is positive, and disable it otherwise. The which-function-mode is a global minor mode. When enabled, the current function name is continuously displayed in the mode line, in certain major modes. ⚠ Detection of functions and variables depend on the imenu functionality. If you modify the content of a buffer, you need to force a menu rescan to get proper results. You can force a rescan with pel-imenu-rescan, bound to <f11> <f10> r.</f10></f11>
	 Identify the major modes where you want this activated in the which-function-mode user-option with M-x customize-option which-function-mode. With PEL you can use: <f11> ?</f11> <f3> to access the which-func customization group. Note that it will provide access to the customization group even when the feature has not yet been loaded.</f3> <f11> <f2> o which-function-mode RET to access the user-option directly.</f2></f11> 		
Toggle display of <u>ace-window</u> number on window mode line	• <f11> w # • <f11> M-d #</f11></f11>	(ace-window-display-mode &optional ARG)	Toggle the ace-window-display-mode, a minor mode that displays the ace window number of each window inside the left hand side of its mode line. Requires the ace-window external package. PEL activates it when the pel-
See also: <u>New Windows</u>			use-ace-window user-option is turned on. Use <f11> w <f2> to access the customization group where you can turn it on.</f2></f11>
Display Time on Mode Line	 Emacs can display time, date, current system load and other information on the mode line as controlled by the display-time customization group. Access it via the <f11> M-d <f3> key sequence.</f3></f11> If you want to display this information when Emacs starts, set the pel-modeline-display-time user-option on. You can also use the following command to toggle the display of time. 		
Toggle time display on mode line See also: Time Tracking	<f11> M-d t</f11>	(pel-toggle-time-display)	Toggle display of time on the mode line.
Display Column of point on Mode Line	The following command toggles the display of the current column on the mode line. Note that the display of several mode line elements can be activated through the Emacs Menu accessible via the <f10> key.</f10>		
Toggle display of column number on mode line	<f11> M-d c</f11>	(column-number-mode &optional ARG)	Toggle column number display in the mode line (Column Number mode). • With a prefix argument ARG, enable Column Number mode if ARG is positive, and disable it otherwise.
Mode Line Lighters	PEL uses some short lighter	ers made of non-ASCII symbols tomization and some may only	using Emacs with PEL are listed below. s that may or may not be rendered properly on various environments. work in terminal or graphics mode.
• ಙೡಁ • ಙឃ	undo-tree		See: <u>Nundo/Redo/Repeat/Arg</u>
ca	editor-config-mode		
E(1)	pel-electric-pair-lighter		See: • <u>MJ Org-Mode</u> • <u>ชุน - C</u> • <u>ชุน - C++</u> • ชุน - D
*	pel-tempo-mode		See: • » Inserting Text • » ι - C • » ι - C++ • ½ γι - Emacs Lisp • » ι - Erlang • » ι - UNIX Shell • Μ reStructuredText
SP	smartparens-mode		See: <u>∑x Smartparens</u>
SP/s	smartparens-strict-mode		
command-log	command-log-mode		<u></u> <u>N Help/Info</u>
 Makefile.am BSDmakefile Imakefile Makefile Makeppfile Nmake 	Major mode for various types of make files.		See: <u>Pi - Make</u>