rst-mode: reStructuredText Mode

Editing	Keystroke	Function	Note	
		on related to reStructuredText that ne		
	The reSructuredText files are supported by the ret-mode which is available in standard Emacs distribution. To activate it under PEL, you must set the PEL pel-use-rst-mode customization variable to t.			
Activate reStructuredText M-mode	-x rst-mode	(rst-mode)	Toggle the rst-mode used to edit reStructuredText markup.	
Get version of rst-mode C-	-h v rst-version		Shows the content of the variable rst-version. Works once the rst-mode is loaded only.	
Display table of content C-	-c C-t C-t	(rst-doc)	Display a table of contents for current buffer inside another buffer. Displays all section titles found in the current buffer in a hierarchical list. The resulting buffer can be navigated, and selecting a section title moves the cursor to that section.	
Indent list item <t< td=""><td>tab></td><td>(indent-for-tab-command &optional ARG)</td><td>When point is anywhere on a list item line (a line that starts with one if the supported bullet characters), this cycles the indentation through the possible indentations of the item.</td></t<>	tab>	(indent-for-tab-command &optional ARG)	When point is anywhere on a list item line (a line that starts with one if the supported bullet characters), this cycles the indentation through the possible indentations of the item.	
Comment M-	-;	(comment-dwim ARG)	Comment line or region.	
(See ∑ Comments)			TODO: the uncommenting does not work. According to the comment-dwim description it should. Need to investigate.	
•	C-M-a <f12> p</f12>	(rst-backward-section OFFSET)	Jump backward OFFSET section titles ending up at the start of the title line. OFFSET defaults to 1 and may be negative to move backward. An OFFSET of 0 does not move unless point is inside a title. Go to end or beginning of buffer if no more section titles in the desired direction.	
	C-M-e <f12> n</f12>	(rst-forward-section OFFSET)	Jump forward OFFSET section titles ending up at the start of the title line. OFFSET defaults to 1 and may be negative to move backward. An OFFSET of 0 does not move unless point is inside a title. Go to end or beginning of buffer if no more section titles in the desired direction.	
Mark complete current section	-M-h	(rst-mark-section &optional COUNT ALLOW-EXTEND)	Select COUNT sections around point. Mark following sections for positive COUNT or preceding sections for negative COUNT.	
		he rst-adjust command to create sec ails when market is used and not exp	ected by its code.	
oth lev PE	PEL provides a set of very simple commands that use multiple key bindings to adorn the current line to a fixed section level: title level and up to 10 other levels, from 1 to 9 and then 0 for 10. It also provides commands to adorn a line to the same level as the previous section or a lower or higher level. And then to increase or decrease the section level of the adornment of the current line. PEL provides 3 style of section adornments: default, Sphinx-Python and CRiSPer, which can be selected with commands. PEL remembers the preferred style inside the customizable variable: pel-rst-adornment-style.			
• (C-= C-c C-= C-c C-a C-a	(rst-adjust PFXARG)	 Auto-adjust the adornment around point. Adjust/rotate the section adornment for the section title around point or promote/ demote the adornments inside the region, depending on whether the region is active. This function is meant to be invoked possibly multiple times, and can vary its behavior with a positive PFXARG (toggle style), or with a negative PFXARG (alternate behavior). This function is a bit of a swiss knife. It is meant to adjust the adornments of a section title in reStructuredText. It tries to deal with all the possible cases gracefully and to do "the right thing" in all cases. 	
	<f12> = <f11> SPC r =</f11></f12>	(pel-rst-adorn-same-level)	Adorn current line with the same level as the previous section. If the line is already adorned, update the adornment: adjust to previous section level.	
-	<f12> + <f11> SPC r +</f11></f12>	(pel-rst-adorn-increase-level)	Adorn current line at a higher-level that current if already adorned. If the line is not already adorned, adorn it with a level higher than previous section.	
	<f12> - <f11> SPC r -</f11></f12>	(pel-rst-adorn-decrease-level)	Adorn current line at a lower-level than current if already adorned. If the line not already adorned, adorn it with a level lower than previous section.	
	<f12> t <f11> SPC r t</f11></f12>	(pel-rst-adorn-title)	Adorn current line with level-0 (title) reStructuredText section adornment.	
From level 1 to level 10	<f12> 1 <f11> SPC r 1 <f11> SPC r 1 <f12> 2 <f11> SPC r 2 <f12> 3 <f11> SPC r 3 <f12> 4 <f11> SPC r 4 <f11> SPC r 5 <f11> SPC r 5 <f11> SPC r 6 <f11> SPC r 6 <f11> SPC r 7 <f12> 8 <f11> SPC r 8 <f12> 9 <f11> SPC r 9 <f11> SPC r 9 <f11> SPC r 0</f11></f11></f11></f12></f11></f12></f11></f11></f11></f11></f11></f11></f12></f11></f12></f11></f12></f11></f11></f12>	• (pel-rst-adorn-1) • (pel-rst-adorn-2) • (pel-rst-adorn-3) • (pel-rst-adorn-4) • (pel-rst-adorn-5) • (pel-rst-adorn-6) • (pel-rst-adorn-7) • (pel-rst-adorn-8) • (pel-rst-adorn-9) • (pel-rst-adorn-0)	Adorn current line with level [1 to 10] reStructuredText section adornment. ➡The <f11> SPC 1 to <f11> SPC r 0 key sequences can be used inside any buffer. The <f12> keys can only be used in inside the buffers in rst-mode.</f12></f11></f11>	
	<f12> A d <f11> SPC r A d</f11></f12>	(pel-rst-adorn-default)	Set the default section adornment style. This is Emacs rst-mode default: a title with 7 levels.	
			Out the Outline Dathers and the order	
style • · · · Select Sphinx-Python • · · ·	<f12> A S <f11> SPC r A S</f11></f12>	(pel-rst-adorn-Sphinx-Python)	Set the Sphinx-Python section adornment style. This is what Sphinx supports: 6 levels: • parts, • chapters, • sections, • subsections, • subsubsections, • paragraphs.	

Description	Keystroke	Function	Note		
Writing Hyperlinks	The following 3 PEL commands help write hyperlink of various forms: • the embedded form where the URL is stored inside the text between angle brackets and • the full named format where the link is located elsewhere in the file on its own line. When editing a buffer using the rat-mode, the <f12> . keystroke runs the command that creates a hyperlink, the long named format by default: it uses the region (if one is highlighted) or the word at point otherwise as the title for the link and creates the link entry on a line identified by a dedicated bookmark: that bookmark is created by the <f12> s keystroke. That helps identify an area inside the file where the next (or several) hyperlinks will be located. In PEL, the <f12> key prefix is mode sensitive. If you want to use the same commands inside another mode, you can use the longer key chord that uses the <f11> SPC r prefix. In activate it under PEL, you must set the PEL pel-use-rst-mode customization variable to t.</f11></f12></f12></f12>				
Set location of hyperlinks	• <f12> s • <f11> SPC r s</f11></f12>	(pel-rst-set-ref-bookmark)	 Set the reference bookmark for the currently edited file at point. Used to identify the location where the next invocation of M-x pel-rst-mekelink inserts fully expanded links. Ensures the bookmark is at the beginning of an empty line which is followed by another empty line, by inserting 2 lines and placing the point at the beginning of the first of the 2 lines. 		
Go to hyperlink location	• <f12> g • <f11> SPC r g</f11></f12>	(pel-rst-goto-ref-bookmark)	Move point to the reference bookmark. Useful to see where the bookmark for storing the hyperlink are currently located or add empty lines for future references. Command pushes the mark on mark ring, type M-`to move back to previous location.		
Add an hyperlink for text at point	• <f12> . • <f11> SPC r .</f11></f12>	(pel-rst-makelink &optional ARG)	Create a reStructuredText hyperlink prefix for the word at point or region's text. If a region is active, use the text of the region to make the link, otherwise use the word at point. If an argument (ARG, which can be a C-u) is specified, use the embedded URI format. If no argument is specified, use the named hyperlink format: if the region is a single word, just append an underscore to make the link if the region is several words, surround the region with the """ start string and the ""_" end string. The named link is placed in the location of bookmark named "RST" if it exists and points to same file, otherwise the link is placed at the beginning of the next empty line. The cursor is placed where the URL is to be written. Command pushes the mark on mark ring, type M-`to move back to previous location.		
rst-preferred-adornment			Identifies the list of section adornments, how to identify each section level. • Set this variable to nil if you want to limit the section adornment to what is currently used inside the file.		
Editing Content	The following generic commands are useful when editing reStructuredText content.				
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	To justify as well: C-u M-q Note: in refill mode this is done automatically. In auto fill mode the filling is done at the end of the line.		
Align a set of lines on some text	<f11> t w a</f11>	(align-regexp BEG END REGEXP &optional GROUP SPACING REPEAT)	Align the current region using an ad-hoc rule read from the minibuffer. BEG and END mark the limits of the region. Interactively, this function prompts for the regular expression REGEXP to align with. • First select a region, then issue the command. For example, to align assignment of variables over the equal sign use = as the regexp. • The PEL package creates the ar alias for align-regexp, so it's also possible to invoke it with M-x ar <ret> — Useful command to align the hyperlink references on their URL: select all hyperlink lines and then issue the command, specifying http as the regexp to line them all vertically.</ret>		

rst-mode - References

Description & URL	Notes
Emacs Support for reStructuredText	
How to get the table of content with section numbers?	
reStructuredText	Main page for all reStructuredText documents.
reStructuredText markup Specifications	Formal markup specifications.
Sphinx Python Documentation Generator	
Sphinx - Documentation Contents	
Sphinx — Documentation — Sections	