Programming Language Support — C++

<u>Description</u>	<u>Keystroke</u>	Function	Note Note
Support for the			s package extends the Emacs CC Mode built-in package which supports the curly-bracket
C++ Programming Language	programming languages like C++. Important aspects of C++ source code syntax controlled by the CC Mode are customizable with PEL user option variables. PEL customization for C++: Simplifies editing C++ code configuration. (To change, use pel-cfg-pkg-c++ with <f12> <f2>), see below). Emacs customization group: pel-pkg-for-c++ pel-c++-indentation: Identifies the number of columns used for indentation. Defaults to 3. pel-c++-tab-width: The width of a tab. Defaults to 3. This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i will move point to columns that are multiple of 8 <tab> will indent to a column that is a multiple of 3. pel-c++-use-tabs: Whether hard tabs are used in indentation or not: t: tabs are used, nil: only spaces are used. Default: nil. pel-c++-backet-style: The bracket/indentation style supported by the electric keys. One of the values supported by Emacs (also possible to define your own with Elisp code). Default to "stroustrup".</tab></f2></f12>		
	 Emacs customization group: pel-pkg-for-cc. Applies to all CC Mode related modes (like c-mode). pel-cc-auto-newline: Whether automatic newline mode is active on all CC Mode (including c-mode). The values for those user option variables can also be stored inside directory local files and even as file local variables. You can also modify them for each buffer and view their current settings using the commands listed in the following set of rows. None of the commands below change PEL default; they change the value for the current buffer only. PEL provides the following set of mode-specific key prefixes: <f11> SPC C, <f12> and <m-f12> The first one is always available. The other two prefixes are only available in c++-mode buffers. The <m-f12> prefix helps the typing flow when the next key is a Meta key. For simplification, the <f11> SPC C prefix is normally omitted in the table.</f11></m-f12></m-f12></f12></f11> 		
Open this PDF file. See also: <u>∑ Help/Info</u>	• <f11> SPC C <f1> • <f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the local copy of the $\ \underline{\mathfrak{Pl}\ -\ C++}\ $ PDF file unless a command prefix (like $\ C-u$) was used. In that case it opens the Github-hosted file instead.
<u>∑ Customize</u> PEL C++ support	• <f11> SPC C <f2> • <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL C++ support: cpp. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
<u>∑ Customize</u> Emacs C++ support	• <f11> SPC C <f3> • <f12> <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs C++ support: cpp. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
CC Mode Style Management	You can impose an indentation cases you can use CC Mode's	style by customization. But y	its syntactic interpretation of the current line and the indentation mode in use. ou may use source code written by others and want to continue using the same style. In those I report it or start using it (installing it) with the following commands. nanual for more info.
Show/Modify syntactic context	C-c C-o	(c-set-offset SYMBOL OFFSET &optional IGNORED)	Change the value of a syntactic element symbol in 'c-offsets-alist'. • SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that syntactic element. The optional argument is not used and exists only for compatibility reasons.
Show syntactic information for current line	C-c C-s	(c-show-syntactic- information ARG)	Show syntactic information for current line. • With universal argument, inserts the analysis as a comment on that line.
Guess the style used in the current buffer, do not install it	M-x c-guess-buffer- no-install	(c-guess-buffer-no-install &optional ACCUMULATE)	Guess the style on the whole current buffer; don't install it. • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
Guess the style of the code in the buffer	M-x c-guess-buffer	(c-guess-buffer & optional ACCUMULATE)	Guess the style on the whole current buffer, and install it. The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
<u>Guess style</u> in the region	M-x c-guess	(c-guess &optional ACCUMULATE)	Guess the style in the region up to 'c-guess-region-max', and install it. The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
Guess the style of a region	M-x c-guess-region	(c-guess-region START END &optional ACCUMULATE)	Guess the style on the region and install it. The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
View Guessed style	M-x c-guess-view	(c-guess-view &optional WITH-NAME)	Emit emacs lisp code which defines the last guessed style, so you can put the code into .emacs if you prefer the guessed code. "STYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is given, it is used instead. WITH-NAME is expected as a string but if this function called interactively with prefix argument, the value for WITH-NAME is asked to the user.
Determine syntactic context of current line.	M-x c-guess-basic- syntax	(c-guess-basic-syntax)	Determine the syntactic context of the current line.
CC Mode support Behaviour control	The CC Mode controls the indentation and bracket style which controls what happens when electric characters are typed (when the electric mode is activated) and provide a better experience when editing C++ source code. • CC Mode state displayed in the mode line: \$C{}} where:		ch controls what happens when electric characters are typed (when the electric mode is source code.
	 		
Toggle Electric state	• C-c C-l • <f12> M-e • <m-f12> M-e</m-f12></f12>	(c-toggle-electric-state &optional ARG)	Toggle the electric indentation feature done with the electric character keys. • Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off when negative, and just toggles it when zero or left out.
Set indentation style	• C-c . • <f12> M-s • <m-f12> M-s</m-f12></f12>	(c-set-style STYLENAME &optional DONT-OVERRIDE)	Set the bracket/indentation style for the current buffer. • Prompts for the name. • Supports tab completion (so use tab to see the list). Can be one of the values supported by Emacs but you can also add your customized mode with some Emacs Lisp code.
Toggle syntactic indentation	• <f12> M-i • <m-f12> M-i</m-f12></f12>	(c-toggle-syntactic- indentation &optional ARG)	 Toggle syntactic indentation. Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out. When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable. When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Toggle Comment Style	• C-c C-k • <f12> M-; • <m-f12> M-;</m-f12></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block (/* */) and line (//) comments. • Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out. In this is part of CC Mode. Use <f12> M-? to display the current state.</f12>
Toggle Hungry Delete mode	• <f12> M-DEL • <m-f12> M-DEL</m-f12></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affects < DEL> and C-d keys. • Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out. • When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop. □ This is part of CC Mode. Use < £12> M-? to display the current state.
Toggle text alignment on pel-newline-and-indent-below See also: • ∑ Align • ∑ Indentation	<f11> M-RET</f11>	(pel-toggle-newline-indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. □ □ Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the major mode to the list in the pel-modes-activating-align-on-return user option. This affects the behaviour of the following commands: □ pel-cc-newline (assigned to RET in CC modes like c-mode, c++-mode and d-mode). □ pel-newline-and-indent-below (assigned the M−RET)
Toggle auto-newline insertion mode	• C-c C-a • <f12> M-RET • <m-f12> M-RET</m-f12></f12>	(c-toggle-auto-newline &optional ARG)	Toggle <u>auto-newline</u> feature. Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out. Turning on auto-newline automatically enables <i>electric indentation</i> . When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.
Change RET key behaviour: select return mode.	• <f12> RET • <m-f12> RET</m-f12></f12>	(pel-cc-change-newline- mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are: • context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument. • newline-and-indent: uses (newline ARG t) to insert newline and indent. • just-newline-no-indent: uses (electric-indent-just-newline ARG) —Emacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode. PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.
Display current Mode settings	• <f12> M-? • <m-f12> M-?</m-f12></f12>	(pel-cc-mode-info)	Display information about current <u>CC mode</u> derivative for the current c-mode buffer. The information includes the information described in the following row.
	M-s). The Emacs the c-def style that is used to set the Return key behaviour: RET (return key) mode. C Whether return performs State of electric C++ chara whether it is active or not whether auto-newline on RET). The fill column: the column Tab width and whether hard f2> to open the appropria Remember that tab w column. Indentation is co Indentation width and wheth The style currently used for create your own. The exam dynamically change for the companient of the companient o	ault-style user option defines style for c-mode. Use <f12> hange with pel-cc-change-new alignment. Change that with peters (toggle it on/off with c-tc, and when active what charac some characters (";" and some where force line wrap is done where force customization buffer to characteristic indentation mode indentation and bracket positic ple below shows "stroustrup", current buffer with c-set-style ("" to "") and C++-s amically for the current buffer with c-set-style ("" to "") and C++-s amically for the current buffer with custom subsequent buffer with custom subsequen</f12>	rel-toggle-indent-align (<f11> M-RET). reggle-electric-state (C-c C-l or <f12> M-e): ter(s) exhibit electric behaviour. other based on style) is active. Toggle this with c-toggle-auto-newline (C-c C-a or <f12> M-venenthe auto-fill-mode is active. Toggle auto fill mode with <f11> RET. by the user options pel-c++-tab-width and pel-c++-use-tabs. In a c++-mode buffer use <f12> rege them. Intation. It controls the spacing used in some commands moving point to the next tab stop ne. Is active. In active, should have the same value). Emacs identifies several built-in styles but you can identifying the Stroustrup C++ style used by C++ designer, Bjarne Stroustrup. You can command (C-c or <f12> M-s). In the PEL user option requested. This allows you to slightly modify an existing style without tyle (//) comments. With the c-toggle-comment-style command (C-c C-k or <f12> M-;). C comment cond one is used on a comment continuation line the remainder of the comment continuation has for the current buffer with c-toggle-hungry-state (<f12> M-DEL). (C++//la WK Fly 2 Anzu Abbrev) </f12></f12></f12></f12></f11></f12></f12></f11>
Electric Keys and Keywords	- PEL Bracket style - Comment style - Hungry delete The following electric C/C++	: stroustrup : Line comments: // : off, but the F11- characters have special mean	and F11-⊠ keys are available. ing when the electrical state is active in a buffer using c++-mode. toggle-electric-state (C-c C-1 or <f12> M-e).</f12>
	#	(c-electric-pound ARG)	Insert a "#". • If 'c-electric-flag' is set, handle it specially according to the variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is supplied, or if point is inside a literal or a macro, nothing special happens.
	• ((c-electric-paren ARG)	Insert a parenthesis. If 'c-syntactic-indentation' and 'c-electric-flag' are both non-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside a literal. Whitespace between a function name and the parenthesis may get added or removed; see the variable 'c-cleanup-list'. Also, if 'c-electric-flag' and 'c-auto-newline' are both non-nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.

Description	<u>Keystroke</u>	Function	Note
	• { • }	(c-electric-brace ARG)	Insert a brace. Insert a brace. If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings in 'c-hanging-braces-alist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.
	•	(c-electric-colon ARG)	Insert a colon. If 'c-electric-flag' is non-nil, the colon is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the colon based on the settings in 'c-hanging-colons-alist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, whitespace between two colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
	• ;	(c-electric-semi, ARG)	 Insert a comma or semicolon. If 'c-electric-flag' is non-nil, point isn't inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) When the auto-newline feature is turned on (indicated by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-semi&comma-criteria' for how newline insertion is determined. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, a comma following a brace list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-cleanup-list'.
	• <	(c-electric-lt-gt ARG)	 If the current language uses angle bracket parens (e.g. template arguments in C++), try to find out if the inserted character is a paren and give it paren syntax if appropriate. If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, the line will be reindented if the inserted character is a paren or if it finishes a C++ style stream operator in C++ mode. Exceptions are when a numeric argument is supplied, or the point is inside a literal.
Insert New Line(s)	active the point also moves to With PEL the default behavion command (bound to <f12> The pel-cc-newline comman</f12>	the proper indentation according can be selected by custom M-RET) see the CC-Mode behild also aligns comments and a	holde electric mode is active or not. When it is not active it simply inserts a new line. When it is ing to the syntactic context. The following commands can also be used. It is not active it simply inserts a new line. When it is ing to the syntactic context. The following commands can also be used. It is inserted in a syntactic new line in the pel-cc-change-newline-mode naviour control section above. It is instanced in the code block if the pel-modes-activating-align-on-return user option list is buffer can also be modified by the pel-cc-change-newline-mode command (<f11> M-RET).</f11>
Insert a new line and operate according to the currently active selected return mode. With PEL, modify	RET	(pel-cc-newline &optional N)	Insert a newline and perhaps align. • With argument N repeat N times. • For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below): • c-context-line-break (PEL default for RET) • newline (Emacs default for RET)
behaviour with <f12> M-RET.</f12>			 electric-indent-just-newline If the variable 'pel-newline-does-align' is t, then perform the text alignment done by the function 'align'.
	When point is outside which case the new lin When point is inside the The end of the cpp dire When point is inside a variables for details). The point is inside a variables for details).	e is indented as the previous n e content of a preprocessor di ective doesn't count as inside i comment, continue it with the 'he end of a C++-style line con	newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in non-empty line instead. rective, a line continuation backslash is inserted before the line break and aligned appropriately.
	Use: (newline &optional ARG INTERACTIVE): Insert a newline, and move to left margin of the new line if it's blank. • With ARG, insert that many newlines. • If option 'use-hard-newlines' is non-nil, the newline is marked with the text-property 'hard'. • If 'electric-indent-mode' is enabled, this indents the final new line that it adds, and reindents the preceding line. • To just insert a newline, use M-x electric-indent-just-newline. Calls 'auto-fill-function' if the current column number is greater than the value of 'fill-column' and ARG is nil.		
	Use: (electric-indent-just-newline ARG): Insert just a newline, without any auto-indentation. • With ARG, insert that many newlines.		
Insert an indented line below unbroken current line See also: <u>National Indentation</u>	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line. For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. You can toggle this on/off with <f11> M-RET. But Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	С-ј	(electric-newline-and-maybe-indent)	Insert a newline. In 'electric-indent-mode' is enabled, that's that, but if it is 'disabled' then additionally indent according to major mode. Indentation is done using the value of 'indent-line-function'. In programming language modes, this is the same as TAB. In some text modes, where TAB inserts a tab, this command indents to the column specified by the function 'current-left-margin'.
Open New Line in Context See also: • Whitespace	C-0	(c-context-open-line)	Insert a line break suitable to the context and leave point before it. • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details. • Normally C-o is bound to open-line. PEL rebinds it to c-context-open-line for the CC modes. If you want to open the line without indenting the next use open-line via <f12> C-o</f12>
Open new line	• <f12> C-o • <m-f12> C-o</m-f12></f12>	(open-line N)	Insert a newline and leave point before it. If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank. With arg N, insert N newlines.
C++ Comments	-		oport comments in C++.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
	/	(c-electric-slash ARG)	Insert a slash character. If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'. Indent the line as a comment, if: 1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or 2. The slash is part of a "*/" token that closes a block oriented comment. If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
	*	(c-electric-star ARG)	Insert a star character. Insert a star character. If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment. If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited. With this key it becomes easy to type the following two styles of multi-line block comment: /* Two star ** continuation ** prefix for ** multi-line ** C comment. */ /* Single star * prefix for * multi-line * C comment. */ When typing the '*' at the beginning of the line, it indents automatically. If another '*' is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.
Comment/un-comment	M-;	(comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer. • When no marked region and no comment: • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line. • On line with code: insert comment starter after the code for an end-of-line comment • With marked un-commented region: • Comment region (each line is commented) • With marked commented region: • removes the comment. • Call the comment command you want (Do What I Mean). • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'. • You can configure 'comment-style' to change the way regions are commented: see <f12> M-; to toggle the comment style.</f12>
	С-с С-с	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead. • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. • If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better.
Fill current paragraph See also: Filling/Justification	• M-q • <f12> F • <m-f12> F • <f11> SPC C F</f11></m-f12></f12>	(c-fill-paragraph &optional ARG)	Like <f11> t f p but handles // and /* */ style comments. • If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details). • If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following: char description[] = "\ A very long description of something that you want to fill to make nicely formatted output."; • If point is in any other situation, i.e. in normal code, do nothing. • Optional prefix ARG means justify paragraph as well.</f11>
Toggle subword-mode See also: • <u>∑ Text Modes</u>	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hide/Show comments See also: <u>▼ Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see S Comments). • PEL activates it when the pel-use-hide-comnt user option is t.
Hungry Deletion of Whitespace	The CC mode provides two commands that can perform "hungry whitespace deletion" that can also be used in every mode. PEL provides the convenient keys with the <f11> prefix keys for those 2 commands, available in all modes. In modes compatible with the CC Mode (e.g. for C, C++, D, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour of the simple and C-d, to perform hungry deletions. That's not currently supported in other modes. When the Hungry Delete Mode is on, the mode-line displays a "h" to the right of the "//!" indication of electric mode. The Hungry Mode also activates the key prefixes below that start with C-c. They are listed but remember they are only available once the Hungry state mode is activated (and that can only be done in modes that are CC Mode compatible). In modes derived from CC Mode you can also activate the hungry state to make standard delete commands delete hungrily, but that does not work for other modes. PEL provides the <f12> M-DEL key for those modes (like C++). Toggle hurry deletion mode of the DEL and C-d key for the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12></f12></f11>		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Delete preceding char	• C-c DEL	(c-hungry-delete-	Delete the preceding character or all preceding whitespace back to the previous non-
or all preceding whitespace. See also:	• C-c ⟨X • C-c C-⟨X • C-c <c-backspace></c-backspace>	backwards)	whitespace character. ☐ In terminal mode, even though C-⟨X , ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.
	• C-c C-DEL • <f11> ⊠</f11>		With PEL, the <f11> ☑ binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11>
Delete next char or all following whitespace.	• C-c C-d • C-c ⊗	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character.
See also: • <u>> Cut & Paste</u>	• C-c C-X • C-c <c-delete> • <f11> X</f11></c-delete>		□ In terminal mode, even though C-I and <c-delete> are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. With PEL, the <f11> binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11></c-delete>
Indentation	-		-Mode logic and provided commands listed below. It the end of this list. They are also listed in the ∑ Indentation table.
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line. • Behaviour depends on syntactic-indentation mode: on by default, toggled with <f12> M-i</f12>
See also: • ∑ Indentation			 With syntactic-indentation on (the default): In Transient Mark mode, when the region is active, reindent the region. Otherwise, with a prefix argument, rigidly reindent the expression starting on current line. Otherwise reindent just the current line. Hit <tab> anywhere in the line to adjust the indentation of the line or marked area.</tab> With syntactic-indentation off: <tab> always indent current line by one level</tab> C-u - <tab> or M- <tab> always un-indent current line by one level</tab></tab> Marked region is indented without syntax knowledge at the same level as previous line. If you want to indent rigidly you can use: (pel-indent-rigidly &optional N) (bound to C-x <tab> and to <f11> <tab><tab></tab>) to indent the line or region rigidly.</tab></f11></tab> (tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column.
Indent lines of list after point See also: • <u>National Indentation</u>	С-м-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it. • A prefix argument (C - u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	 Indent each nonblank line in the region. A numeric prefix argument specifies a column: indent each line to that column. With no prefix argument, the command chooses one of these methods and indents all the lines with it: If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. If 'indent-region-function' is non-nil, call that function to indent the region. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	Emacs provides the following command to indent without regards to semantics. More information on indentation is available in the <u>National Regards</u> table.		
Insert spaces or tabs to next defined tabstop column See also: • <u>Natural Indentation</u>	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column. • The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer. • With PEL, the indentation is controlled by the value of pel-c++-tab-width because PEL sets the value of tab-width in c-mode buffers to the value of pel-c++-tab-width for C++ buffers.
Indent/Unindent rigidly See also: • <u>National Indentation</u> • <u>National Key-Chords</u>	• C-x <tab> • <f11> <tab> <tab> • <tab>q</tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	Indent rigidly the marked region or current line N times. • If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes. • If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): • N = [-1, 0, 1] : operate on current line • N > 1 : operate on the current line and N-1 lines below. • N < -1 : operate on the current line and (abs N) -1 lines above. >> PEL rebinds this key, but it extends the functionality: pel-indent-rigidly uses indent-rigidly, described below the dashed line. Indent all lines starting in the region.
		➤ PEL uses the above instead of the standard:	 If called interactively with no prefix argument, activate a transient mode in which the indentation can be adjusted interactively by typing <left>, <right>, <s-left>, or <s- right="">.</s-></s-left></right></left>
		(indent-rigidly START END ARG &optional INTERACTIVE)	Both of these commands activate a transient mode where Emacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. The capabilities are controlled by the variable indent-rigidly-map with by default provides: • S- <right> indent-rigidly-right-to-tab-stop • S-<left> indent-rigidly-left-to-tab-stop • <right> indent-rigidly-left Typing any other key deactivates the transient mode. • The S-<right> and S-<left> keys indent/de-indent to the next tab-stop position, which is controlled by the tab-width user option. • With PEL, the indentation is controlled by the value of pel-c++-tab-width for buffers in c++-mode: for those PEL sets the value of tab-width to the value of pel-c++-tab-width. If you use the cua-mode: the cua-mode uses C-x, to invoke this command when cua-mode is active, type it really fast or type C-x C-x <tab> (or use the PEL binding <f11> <tab> <t< td=""></t<></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></f11></tab></left></right></right></left></right>

Description	<u>Keystroke</u>	Function	<u>Note</u>
Indent line(s) rigidly See also: • <u>∑ Indentation</u>	• <f6> <tab> • <f11> <tab> c</tab></f11></tab></f6>	(pel-indent-lines &optional N)	Indent current or marked lines by N indentation levels. Works with point anywhere on the line. All lines touched by the region are indented. A special argument N can specify more than one indentation level. It defaults to 1. If a negative number is specified, 'pel-unindent-lines' is used. If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.
Un-indent line(s) rigidly See also: • ∑ Indentation	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	 Un-indent current line or marked lines by N indentation levels. Works with point is anywhere on the line. All lines touched by the region are un-indented. If region was marked, the function does not deactivate it to allow repeated execution of the command. If a region was marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.
Inserting code			
Insert Parentheses	M- ((insert-parentheses &optional ARG)	For C++: insert a parenthesis pair '()', leaving point after open-paren. • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. • A negative ARG encloses the preceding ARG sexps instead. • No argument is equivalent to zero: just insert '()' and leave point between. • PEL makes 'parens-require-spaces' buffer local and set it to nil in C++ mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. • If region is active, insert enclosing characters at region boundaries. • This command assumes point is not in a string or comment.
Marking	Emacs provides the following	command to quickly mark the	whole content of the current function. More mark commands exists, see the <u>Narking</u> table.
Mark the complete function body See also: Marking	C-M-h	(c-mark-function)	Mark complete function. Put mark at end of the current top-level declaration or macro, point at beginning. If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function. A mark is left where the command started, unless the region is already active (in Transient Mark mode). As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a brace block.
Getting Syntactic Information	Use the following commands to extract syntactic information from the source code.		
Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it. With a prefix arg, push the name onto the kill ring too.
Search Support	In C++ mode, the superword mode can be useful since <u>snake_case</u> is often used. Using superword-mode helps searching. PEL activates the superword mode by default in C++ mode. To change this use the <f11> t <f2> to access the customize buffer.</f2></f11>		
Toggle superword-mode See also:	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	 Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In C++ '_' are treated as part of words. With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise. PEL provides the <f12> M-p key for the programming language modes where <u>snake case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Highlighting blocks	The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and []. • show-paren-mode, which highlights the parens that matches the one before or after point. • rainbow delimiters mode, where matching nested parens are highlighted with the same colour.		
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>Neighlight</u>	• <f11> b h (</f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (),(),[] See also: <u>N Highlight</u>	• <f12> M-r • <m-f12> M-r • <f11> b h R</f11></m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth. • Customize the depth and colours with M-x customize-group rainbow-delimiters Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t.
Navigation in C++	This current list below describe	the specialized commands or	nly. See the others inside Navigation
By definitions			ef for more information to activate the various engines that support cross referencing for C code.
Find definition of identifier at point	м	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. If there are more than one match, prompt in the *xref* buffer. To search for a symbol entered manually, type C-u M
See also: <u>▼ Xref</u> Go back to where M	М-,	(xref-pop-marker-stack)	With dumb-jump this performs a search using ag, ripgrep or git grep if available. Pop back to where M was last invoked. Marker depth is controlled by the vref-marker-ring-length user option.
By functions By structures	Move to beginning /end of fi Jump over comments. When point is located be		Marker depth is controlled by the xref-marker-ring-length user option. ucture definition blocks. er closing brace and show-paren-mode is on, the matching parentheses are highlighted.
Forward to start of next top level function or struct	• <f6> n • <f6> <down></down></f6></f6>	(pel-beginning-of-next-defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ. ⇒Shift marking is available. • This command complements what end-of-defun does. • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect. • It handles nested functions or class methods in languages like Python and others.

Description	<u>Keystroke</u>	Function	Note
Forward to end of	С-М-е	(c-end-of-defun &optional	Move forward to the end of a top level declaration.
current top-level function or struct.		ARG)	With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to next end of defun. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡Shift marking is available in graphics mode, not in terminal mode (both keys). ⚠ This command moves to the end of the next top-level function or class. It skips the nested functions and methods.
Backward to beginning of current top-level function or struct	С-м-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a defun. Every top level declaration that contains a brace paren block is considered to be a defun. With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of a defun. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However < f6> p handles Shift-marking fine in terminal mode. ⚠ This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions and methods that are more deeply nested.</home>
Backward to end of previous top level function or struct	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M-\[^\circ\]. Shift marking is available. In some cases it fails to detect the end of the previous block and fails.
By blocks	Move across C statements a	and C scope blocks, or any gro	
By List element	Move to the end or the be		
Backward block/list	С-М-р	(backward-list &optional	Move backward across one balanced group of parentheses.
See also: Navigation		ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move forward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.
Move block backward	• C-M-b	(backward-sexp &optional	Move backward across one balanced expression (sexp).
See also: • <u> ▼ Navigation</u>	• C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	ARG)	 With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. C-M-b : ➤ Shift marking is available in graphics mode, not in terminal mode. C-M-<left> : ➤ Shift marking works with this command.</left> With PEL: if you want to use Esc C-<left> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil, otherwise it does something else.</left> C-M-<left> does not work on Windows, but H-<left> works.</left></left> Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</left>
Forward block/list	C-M-n	(forward-list &optional	Move forward across one balanced group of parentheses.
See also: Navigation		ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move backward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.
Move block forward See also: ■ Navigation	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : ★ Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : ★ Shift marking works with this command. • ⚠ With PEL: if you want to use Esc C-<right> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<right> does not work on Windows, but H-<right> does. ⑤ Several Linux distros map C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</right></right></right></right></right>
in/out of blocks	Move in or out of C scope b	locks, or any group of (), [], {}	or <> blocks.
Backward Up/outside sexp hierarchy See also: Navigation (CLCB s1.lisp)	• C-M-u • C-M- <up> • C-[C-u • Esc C-u • Esc C-<up></up></up>	(backward-up-list &optional ARG ESCAPE- STRINGS NO-SYNTAX- CROSSING)	Move backward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. Mith PEL: if you want to use Esc C- <up> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil. C-M-u: Shift marking is available in graphics mode, not in terminal mode.</up>
			• C-M- <up> : ► Shift marking works with this command. • C-M-<up> does not work on Windows, but H-<up> does.</up></up></up>
Forward Up/outside sexp hierarchy See also: Navigation	C-M-]	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move forward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot.
Down/inside sexp/block See also: •	• C-M-d • C-M- <down> • C-[C-d • Esc C-d • Esc C-<down></down></down>	(down-list &optional ARG)	Move forward down one level of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do this that many times. A negative argument means move backward but still go down a level. • This command assumes point is not in a string or comment. • ⚠ With PEL: if you want to use Esc C- <down> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. • C-M-d: Shift marking is available in graphics mode, not in terminal mode. • C-M-<down> :★ Shift marking works with this command. • C-M-<down> does not work on Windows, but H-<down> does.</down></down></down></down>
By statements	Move to beginning /end of stat	tement of comment sentence.	• C-M-d : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <down> : ► Shift marking works with this command.</down>

ould not be executed with the ternal packages are listed by the ternal packages are listed by the hydra to hear the hydra external package. -UU-:F1 a cpp C preprocessor: Move to Hide	te Hide-ifdef mode. There are all elow. They can be used for education to the property of the control of the co	sor directives and to hide/show code areas based on preprocessor logic and defined variables. the pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix. Requires bel-use-hydra user option is set to t. (C++//la Ifdef WK Fly ² Anzu Abbrev)
macs supports navigation the could not be executed with the ternal packages are listed by the sternal packages are listed by the sternal packages. EL provides a key hydra to here to be supported by the sequences that so the hydra external package. LUU-:F1 a cpp C preprocessor: Move to Hide hydra external package. In next #: P: prev W: C-p: begin R: C-n: end H: C-u: up S: h: h: s: he following commands move. Af12> # p Af12> # p Af12> # f Af12> Af7> p Af12> # f C-c C-u Af12> Af7> C-u C-c C-u C-c C-p	Reptional COUNT LIM SENTENCE-FLAG) rough C preprocessor conditioned Hide-ifdef mode. There are also also also are to be used for educed in the process and the process are with <f12> <f7> open the preprocess are with <f12> <f7> open the preprocess are with <f12> and preprocess are with <f12> <f10< td=""></f10<></f12></f12></f7></f12></f7></f12>	With prefix arg, go forward N - 1 statements. Move forward to the end of the next statement if already at end, and move into nested blocks (use C-M-f) to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements. Mal statements, allow expansion of preprocessor macros, hiding pre-processor statements that also external packages that provide extra support. All commands provided by Emacs and liting C and C++ source code. Sor directives and to hide/show code areas based on preprocessor logic and defined variables. Mal pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix. Requires bel-use-hydra user option is set to t. C++//la Ifdef WK Fly ² Anzu Abbrev) Solution C++//la Ifdef WK Fly ² Anzu Abbrev)
ould not be executed with the ternal packages are listed by the ternal packages are listed by the hydra to he to hydra external package. -UU-:F1 a cpp C preprocessor: Move to Hide Hide Hide Hide Hide Hide Hide Hide	the Hide-ifder mode. There are all elow. They can be used for education to the process and the start with <f12> <f7> open the process are the start with <f12> <f7> open the process are the start with <f12> <f7> open the process are the start with <f12> <f7> open the process are the start with <f12> <f10> open the process are the start with <f12> open the sta</f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f12></f10></f12></f7></f12></f7></f12></f7></f12></f7></f12>	also external packages that provide extra support. All commands provided by Emacs and liting C and C++ source code. sor directives and to hide/show code areas based on preprocessor logic and defined variables. The pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix. Pequires pel-use-hydra user option is set to t. (C++//la Ifdef WK Fly ² Anzu Abbrev)
-UU-:F1 a cpp C preprocessor: Move to	de # Va toggle mode e: e toggle shadow d: d toggle RO u: u hide U: U show D: S hide block show block e point across the #if, #else, #	Other 's Show state efine (f7>: cancel can
<f12> # p <f12> <f1><f1><f1> r <f1><f1><f1< f=""> <f1< td=""></f1<></f1<></f1<></f1<></f1<></f1<></f1<></f1<></f1<></f1<></f1<></f1></f1></f1></f1></f1></f12></f12>	(pel-pp-prev-directive) (pel-pp-next-directive)	Move point to previous preprocessor directive. Move point to next preprocessor directive. Move back to the containing preprocessor conditional, leaving mark behind. • A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. • "#elif" is treated like "#else" followed by "#if", so the function stops at them when going
<pre>c <f12> <f7> p <f12> # n c <f12> <f7> n C-c C-u c <f12> <f7> C-u </f7></f12></f7></f12></f12></f7></f12></pre>	(pel-pp-next-directive)	Move point to next preprocessor directive. Move back to the containing preprocessor conditional, leaving mark behind. • A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. • "#elif" is treated like "#else" followed by "#if", so the function stops at them when going
C-c C-u : <f12> <f7> C-u C-c C-p</f7></f12>	(c-up-conditional COUNT)	 A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. "#elif" is treated like "#else" followed by "#if", so the function stops at them when going
_		backward, but not when going forward.
•	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move back across a preprocessor conditional, leaving mark behind. • A prefix argument acts as a repeat count. • With a negative argument, move forward across a preprocessor conditional.
-c C-n : <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move forward across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move backward across a preprocessor conditional. If there aren't enough conditionals after (or before) point, an error is signaled. "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed when tracking subconditionals.
* C-c C-e (c-macro-expand START END SUBST) * (xf12> # # (c-macro-expand START END SUBST) * (xm-12> # # (c-macro-expand START		Normally display output in temp buffer, but prefix arg means replace the region with it.
-c C-\	(c-backslash-region FROM TO DELETE-FLAG &optional LINE-MODE)	
 This function does not modify blank lines at the start of the region. If the region ends at the start of a line and the macro doesn't continue below it, the backslash (if any) at the end of the previous line is deleted. You can put the region around an entire macro definition and use this command to conveniently insert and align the necessary backslashes. Customizations: The backslash alignment is done according to: 'c-backslash-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'. 		
<f12> # ? : <f12> <f7> ?</f7></f12></f12>	(pel-pp-show-state)	Show state of C preprocessor control modes.
This feature hides blocks of the Hide-ifdef environment: Note that with PEL, in the tac prefix keys. Several customize user op 'hide-ifdef-env' An association list of ovariable, which limits l	code that would not be includ the hide-ifdef-env association able below the commands reaction variables affect how the hidefined symbols for the current nidelif to parse only one <i>C/C++</i> simultaneously in different buff when the SYMBOL is defined (when the symbol is defined with ore-defined symbol lists. Use 'h	e in the expanded file according to the state of pre-processor symbols that are maintained inside a list Emacs variable (use <f1> v to see the content of these variables. See Felp/Info. Shable via the <f12> prefix keys can also be reached via the <m-f12> and the <f11> SPC ding is done (to change, execute: M-x customize-group hide-ifdef): The project. Initially, the global value of 'hide-ifdef-env' is used. This variable was a buffer-local file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C/C-fers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. [but without explicit value] than explicit value. The project is used. This variable was a buffer-local file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C/C-fers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. [but without explicit value] than explicit value. The project is used. This variable was a buffer-local file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C/C-fers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. [but without explicit value] that an explicit value. The project is not contained in the contained in t</f11></m-f12></f12></f1>
ne T th	**:f12> # ? <f12> <f7> ? Hide-ifdef mode can hide his feature hides blocks of ne Hide-ifdef environment: lote that with PEL, in the tat prefix keys. Several customize user op 'hide-ifdef-env' An association list of ovariable, which limits here with the source files opened (SYMBOL) is used (SYMBOL VALUE) 'hide-ifdef-define-alist' An association list of past the current 'hide-ifdef-define set the current 'hide-ifdef-define-alist'</f7></f12>	(pel-pp-show-state) Hide-ifdef mode can hide portion of the C pre-processor his feature hides blocks of code that would not be included the Hide-ifdef environment: the hide-ifdef-env association lote that with PEL, in the table below the commands react prefix keys. Several customize user option variables affect how the hide-ifdef-env' An association list of defined symbols for the current variable, which limits hideif to parse only one C/C+++ source files opened simultaneously in different buffer (SYMBOL) is used when the SYMBOL is defined with hide-ifdef-define-alist'

Description	<u>Keystroke</u>	Function	<u>Note</u>
Toggle the Hide-Ifdef	• <f12> M-#</f12>	(hide-ifdef-mode &optional	Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode).
mode	• <m-f12> M-#</m-f12>	ARG)	 With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise. Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H</m-f12></f12>	(hide-ifdefs &optional NOMSG)	Hide the contents of some #ifdefs. Assume that defined symbols have been added to 'hide-ifdef-env'. The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined. With prefix command presents it will also hide the #ifdefs themselves. Turn off hiding by calling 'show-ifdefs'.
Restore all hidden into view	• C-c @ s • <f12> # S</f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h</f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor. • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s</f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d</f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'. This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u</f12>	(hide-ifdef-undef START END)	Undefine a VAR so that #ifdef VAR would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D</f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable. The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
Use a named symbol environment list	• C-c @ U • <f12> # U</f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Toggle read-only mode when text is hidden	• C-c @ C-q • <f12> # r</f12>	(hide-ifdef-toggle-read- only)	Toggle read-only: toggle 'hide-ifdef-read-only'. • Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w</f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).
Clear the complete list of #define'd symbols inside 'hide-ifdef-env'	• C-c @ C • <f12> # C</f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'. • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
Evaluate pre- processor macro	• C-c @ e • <f12> # e</f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region. If no region active, find the current #ifdefs and evaluate the result. Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments			cific markup code embedded inside C++ source code comments. This can be useful when finite-state machines for example.
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render-commented- plantumi PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. • Use region if identified otherwise use PlantUML block at point. • Uses prefix (as PREFIX) to choose where to display it: • 4 (when prefixing the command with C-u) -> new window • 16 (when prefixing the command with C-u C-u) -> new frame. • else -> new buffer • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment. Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.
Preview diagram created from Graphviz DOT markup embedded in comments See also: M Graphviz Dot	<f12> G</f12>	(pel-render-commented- graphviz-dot &optional POS)	Render the Graphviz-Dot markup embedded in current mode comment. Search at POS if specified, otherwise search around point. Use region if identified otherwise use Graphviz-Dot block. The graphviz DOT code must be located within a block delimited by the following special keywords (that are also in comments): @start-gdot @end-gdot The current implementation leaves the created image file in a temporary directory. You will probably want to move that file or delete it, otherwise the size of this directory will increase with each of these created files. The file names use the pel-gdot- prefix. Requires the graphviz-dot-mode package external package, activated by pel-use-graphviz-dot user option set to t.

Emacs & C++- References

Document	Notes
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor

Document	Notes
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
Demystify C++ Metaprograms using Emacs	
Programming in C++, Rules and Recommendations	ellemtel style
company-mode ; Modular in-buffer completion framework for Emacs	