Comments

Action	Key binding	Command	Notes	
Comment Commands	This is an early version of this page. More information is required on this topic.			
Insert, realign, comment/ uncomment region	м-;	(comment-dwim ARG)	Insert or realign comment on current line. If the region is active, comment or uncomment the region instead. C-u M-; executes comment-kill	
Comment/uncomment current line	• C-x C-; • <f11> ; 1</f11>	(comment-line N)	Comment/uncomment current line (the comment is at the beginning of the line). Since C-; is not an ASCII Control character, C-x C-; does not work in Terminal. Use the alternate keystroke.	
Comment the region as a box	<f11> ; B</f11>	(comment-box BEG END &optional ARG)	Comment the marked region in a comment box.	
Kill comment on current line	<f11> ; k</f11>	(comment-kill ARG)	Kill the complete comment text on the line (whether it is at the beginning of the line or after some code) and remember in kill ring. • With numeric argument, kill comment on as many lines staring with the current one. • For one line this can also be executed with C-u M-;	
Set comment column to current column	С-ж ;	(comment-set-column ARG)	Set the comment-column variable (shown in the ruler as '#').	
Set comment column to previous comment and adjust/ insert a comment	C-u C-x ;	(comment-set-column 1)	With no argument: set to the current column. With any positive argument set comment-column to the same column as the previous comment and align/create a comment on this line at that column. With - as arg, kill any comment on current line.	
New line & aligned comment	• M-j • C-M-j	Mapped to: C, C++ modes: (c-indent-new-comment-line & optional SOFT ALLOW-AUTO-FILL) Buffer Menu, text mode, python mode: (comment-dwim ARG)	When M-j is typed, on a line that contains a comment, a new line is entered and a comment is placed in the same column, with point placed after the same number of spaces.	
Set comment start string	<f11> ; b</f11>	(pel-comment-start)	Show and set comment start string for current mode. • Controlled by variable: comment-start	
Set comment end string	<f11> ; e</f11>	(pel-comment-end)	Show and set comment end string for current mode. • Controlled by variable: comment-end • By default it's "". It must be "" if the comment ends at the end of the line.	
Set comment continue (middle) string	<f11> ; m</f11>	(pel-comment-middle)	Show and set comment continue/middle string for current mode. Controlled by variable: comment-continue By default it is nil. Can be set to any string. This is used for multi-line comments	
Set Fill Column	C-x f	(set-fill-column ARG)	When no prefix value: prompts for column. If with C-u prefix: use current column. If with prefix value: use that value. Note: this command and other fill specific commands are described in the Fill/Justification table.	
Toggle auto fill inside comments only	<f11> t f C</f11>	(pel-auto-fill-only-comments)	Toggle the <i>comment-auto-fill-only-comments</i> variable to control whether filling is done everywhere or only inside the comments. Pote: this command and other fill specific commands are described in the Fill/Justification table.	
See all comment control variables	• C-h v comment- • <f1> v comment</f1>		Lists all variables that have a name that starts with the word "comment-". See the Help table for more information on getting help from within Emacs.	

Comments - References

GNU Emacs Manual - Manipulating Comments	
GNU Emacs Lisp — Tips on Writing Comments	Emacs Lisp comments conventions/guidelines.