## Programming Language Support — C

	Pr	ogramming La	inguage Support — C	
<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
• CC Mode • File extensions	PEL activates support for		ends the <u>CC Mode</u> that support the <u>curly-bracket programming languages</u> like <u>C</u> .  use-c or pel-use-bison user-option variables is set.  vacc	
• C • <u>bison-mode</u>	h • 🔀 If the pel-use-l	header files: .h, .i  • [a] If the pel-use-bison-mode is set, the .y and .yacc files are associated with [ilean mode], the .l and .lex with flex-mode and .jison		
• <u>∑ Speedbar</u>	with jison-mode inst		ecognized by speedbar, otherwise only the main ones are recognized.	
	Important aspects of C sou	irce code syntax controlled by	the CC Mode are customizable with PEL user option variables.	
	Emacs customization gro	Simplifies configuration for edup: pel-pkg-for-c (access with	h <f12> <f2>):</f2></f12>	
<ul> <li>indentation</li> </ul>	<ul> <li>pel-c-indent-width: Identifies the number of columns used for indentation. Defaults to 3.</li> <li>pel-c-tab-width: The width of a tab used for c-mode files. Defaults to 3.</li> <li>This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i will move point to columns that are multiple of 8 <tab> will indent to a column that is a multiple of 3. PEL stores this value inside the tab-width variable for c-mode buffers.</tab></li> <li>For most uses it is best to set both values to the width of your needed indentation level. This way you can use commands that use either to control the indentation level.</li> </ul>			
<ul><li>using tabs</li><li>bracket style</li></ul>	control the indentation level.  • pel-c-use-tabs: Whether hard tabs are used in indentation or not: t: tabs are used, nil: only spaces are used. Default: nil.  • C code style sub-group: pel-c-code-style			
	pel-c-fill-column:     When pel-c-fill-co     pel-c-backet-style     define your own 'us     More user options a	column where line-wrapping oc plumn user option is nil, c-mode The <u>bracket/indentation styl</u> er' with some Emacs Lisp code	cours: maximum line length (defaults to 80). You can change the value or set it nil.  e buffers use the Emacs fill-column value like other major modes.  e supported by the electric keys. You can select one of the values supported by Emacs or e. Default to "linux".  templates created with PEL tempo skeletons. They are described in tempo skeleton section	
	pel-cc-auto-newline:     The values for those user each buffer and view their	Whether automatic newline mo option variables can also be structurent settings using the con	o all CC Mode related modes (like c-mode). ode is active on all CC Mode (including c-mode). tored inside directory local files and even as file local variables. You can also modify them for nmands listed in the following set of rows. See File/Directory Variables for more info.	
		elow change PEL default; they g set of <b>mode-specific key pre</b>	change the value for the current buffer only.  efixes:	
	next key is a Meta key	. For simplification, the <b><f11></f11></b>	ces are only available in c-mode buffers. The <m-f12> prefix helps the typing flow when the SPC c prefix is normally omitted in the table.</m-f12>	
Open this PDF file. See also: <u>NHelp/Info</u>	<f11> SPC c <f1><f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$1 - C</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.	
<u><b>∑</b> Customize</u> PEL C support	<f11> SPC c <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL C support.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
<u><b>∑</b> Customize</u> Emacs C support	<f11> SPC c <f3> <f12> <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs C support.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
CC Mode Style Management	Automatic indentation is done by the CC Mode according to its syntactic interpretation of the current line and the indentation mode in use. You can impose an indentation style by customization. But you may use source code written by others and want to continue using the same style. In those cases you can use CC Mode's ability to analyze the style and report it or start using it (installing it) with the following commands.  Not all commands are documented here, see the CC Mode manual for more info.			
Show/Modify syntactic context	C-c C-o	(c-set-offset SYMBOL OFFSET &optional IGNORED)	Change the value of a syntactic element symbol in 'c-offsets-alist'.  SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that syntactic element. The optional argument is not used and exists only for compatibility reasons.	
Show syntactic information for current line	C-c C-s	(c-show-syntactic- information ARG)	<ul> <li>Show syntactic information for current line.</li> <li>Display the syntactic information list and highlight the reference position(s) listed as argument to the syntactic list.</li> <li>Each list starts with a <u>syntactic symbol</u> with zero or several reference positions.</li> <li>With universal argument, inserts the analysis as a comment on that line.</li> </ul>	
Guess the style used in the current buffer, do not install it	M-x c-guess-buffer- no-install	(c-guess-buffer-no-install &optional ACCUMULATE)	Guess the style on the whole current buffer; don't install it.  • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of the code in the buffer	M-x c-guess-buffer	(c-guess-buffer &optional ACCUMULATE)	Guess the style on the whole current buffer, and install it.  The style is given a name based on the file's absolute file name.  If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
<u>Guess style</u> in the region	M-x c-guess	(c-guess &optional ACCUMULATE)	Guess the style in the region up to 'c-guess-region-max', and install it.  • The style is given a name based on the file's absolute file name.  • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of a region	M-x c-guess-region	(c-guess-region START END &optional ACCUMULATE)	Guess the style on the region and install it.  • The style is given a name based on the file's absolute file name.  • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
View Guessed style	M-x c-guess-view	(c-guess-view &optional WITH-NAME)	Emit emacs lisp code which defines the last guessed style, so you can put the code into .emacs if you prefer the guessed code.  • "STYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is given, it is used instead. WITH-NAME is expected as a string but if this function called interactively with prefix argument, the value for WITH-NAME is asked to the user.	
Determine syntactic context of current line.	M-x c-guess-basic- syntax	(c-guess-basic-syntax)	Determine the syntactic context of the current line.  • It returns the same information that c-show-syntactic-information shows.	
CC Mode support Behaviour control	The following commands can be used to dynamically change the behaviour of important keys such as the return key, delete key, semi-colon, etc  The CC Mode controls the indentation and bracket style which controls what happens when electric characters are typed (when the electric mode is activated) and provide a better experience when editing C source code.  • CC Mode state displayed in the mode line: \$C{}\$ where:  • \$2\$ is the CC mode programming language name: C, C++, ObjC, etc  • C is the C comment style: '*' for block command (/* */) and '/' for line comments (//)  • {} are the other electric flags:  • '1' for electric mode  • 'a' for auto-newline mode			
	'h' for hungry mode     'w' for subword mod			

Description	<u>Keystroke</u>	Function	<u>Note</u>
Toggle Electric state	• C-c C-l • <f12> M-e • <m-f12> M-e</m-f12></f12>	(c-toggle-electric-state &optional ARG)	Toggle the electric indentation feature done with the electric character keys.  • Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off when negative, and just toggles it when zero or left out.
Set indentation style	• C-c . • <f12> M-s • <m-f12> M-s</m-f12></f12>	(c-set-style STYLENAME &optional DONT-OVERRIDE)	Set the <u>bracket/indentation style</u> for the current buffer.  Prompts for the name.  Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.
Toggle syntactic indentation	• <f12> M-i • <m-f12> M-i</m-f12></f12>	(c-toggle-syntactic- indentation &optional ARG)	<ul> <li>Toggle syntactic indentation.</li> <li>Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out.</li> <li>When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable.</li> <li>When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.</li> </ul>
Toggle Comment Style	• C-c C-k • <f12> M-; • <m-f12> M-;</m-f12></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block and line comments.  • Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out.  • The C++ style // comments (also called line comments) are compatible with C since C-99.  □ This is part of CC Mode. Use <f12> M-? to display the current state.</f12>
Toggle Hungry Delete mode	• <f12> M-DEL • <m-f12> M-DEL</m-f12></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affects <b><del></del></b> and <b>C−d</b> keys.  Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out.  When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop.  This is part of CC Mode. Use <b><f12> M−?</f12></b> to display the current state.
Toggle text alignment on pel-newline-and-indent-below See also:  • ∑ Align  • ∑ Indentation	<f11> M-RET</f11>	(pel-toggle-newline-indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates.  If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments.  Black light lig
Toggle auto-newline insertion mode	• C-c C-a • <f12> M-RET • <m-f12> M-RET</m-f12></f12>	(c-toggle-auto-newline &optional ARG)	Toggle auto-newline feature.  Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out.  Turning on auto-newline automatically enables electric indentation.  When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.
Change RET key behaviour: select return mode.	• <f12> RET • <m-f12> RET</m-f12></f12>	(pel-cc-change-newline-mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are:  • context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument.  • newline-and-indent: uses (newline ARG t) to insert newline and indent.  • just-newline-no-indent: uses (electric-indent-just-newline ARG)  —Emacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode.  PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.
Display current Mode settings	• <f12> M-? • <m-f12> M-?</m-f12></f12>	(pel-cc-mode-info)	Display information about current <b>CC mode</b> derivative for the current c-mode buffer. The information includes the information described in the following row.
	• <f11> SPC c M-?</f11>		

- CC mode style currently active, along with a list of styles associated with current mode. Change it for the current buffer with c-set-style (C-c . or <f12> M-s). The Émacs the c-default-style user option defines associations between major modes and the style to use. PEL provides the pel-c-backet-style that is used to set the style for c-mode. Use <f12> <f2> from a c-mode buffer to access the customization buffer to change it.
- Return key behaviour:
  - RET (return key) mode. Change with pel-cc-change-newline-mode (<f12> RET).
- Whether return performs alignment. Change that with pel-toggle-indent-align (<f11> M-RET).
- State of electric C characters (toggle it on/off with c-toggle-electric-state (C-c C-1 or <f12> M-e):
  - whether it is active or not, and when active what character(s) exhibit electric behaviour.
- whether auto-newline on some characters (';' and some other based on style) is active. Toggle this with c-toggle-auto-newline (C-c C-a or <f12> M-RET).
- The fill column: the column where force line wrap is done when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET.
- Tab width and whether hard tabs are used. These are set by the user options pel-c-tab-width and pel-c-use-tabs. In a c-mode buffer use <f12> <f2> to open the appropriate customization buffer to change them.
- 🤞 Remember that tab width does not identify the indentation. It controls the spacing used in some commands moving point to the next tab stop column. Indentation is controlled separately. See next line. Indentation width and whether syntactic indentation mode is active.
- The style currently used for indentation and bracket positioning (they should have the same value). Emacs identifies several built-in styles but you can create your own. The example below shows "bsd" with is another name for the <u>Allman style</u>. You can dynamically change for the current buffer with cset-style command ( $\mathbf{C}-\mathbf{c}$  . or  $<\mathbf{f12}>$  M-s).
  - 🤞 CC Mode styles identify everything, including the number of indentation columns. PEL configures the style from the requested pel-c-bracket-style and then updates the indentation and other settings from the PEL user option requested. This allows you to slightly modify an existing style without having to create a new style name for it.
- The comment style. Supports C-style (/\* \*/) and C++-style (//) comments since both are now accepted in C since C99.
  - This can be changed dynamically for the current buffer with the c-toggle-comment-style command (C-c C-k or <f12> M-; ). C comment continuation lines can use 1 or 2 star characters: if a second one is used on a comment continuation line the remainder of the comment continuation lines used two stars, otherwise only one is used.
- Whether hungry delete is used by DEL and C-d. Toggle this for the current buffer with c-toggle-hungry-state (<f12> M-DEL)

```
-UUU:---F1
                                          All (1,0)
                                                                  (C/*la WK Fly 2 Anzu Abbrev)
                                    bsd. c-default-style: (bsd)
   active style
   RET mode
   Auto newline
                                 : 3, using spaces only
: 3, using syntactic indentation
   Tab width
   Indent width
Syntactic indent
   c-indentation-style : bsd
PEL Bracket style : bsd
   Comment style
Hungry delete
                                 : Block comments: /* */ , continued line start with * : off, but the F11-\boxtimes and F11-\boxtimes keys are available.
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Electric Keys			when the electrical state is active in a buffer using c-mode.  toggle-electric-state (C-c C-1 or <f12> M-e).</f12>
	#	(c-electric-pound ARG)	Insert a "#".  • If 'c-electric-flag' is set, handle it specially according to the variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is supplied, or if point is inside a literal or a macro, nothing special happens.
	• (	(c-electric-paren ARG)	<ul> <li>Insert a parenthesis.</li> <li>If 'c-syntactic-indentation' and 'c-electric-flag' are both non-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside a literal.</li> <li>Whitespace between a function name and the parenthesis may get added or removed; see the variable 'c-cleanup-list'.</li> <li>Also, if 'c-electric-flag' and 'c-auto-newline' are both non-nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.</li> </ul>
	• {	(c-electric-brace ARG)	Insert a brace.  • If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings in 'c-hanging-bracesalist'.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.
	:	(c-electric-colon ARG)	Insert a colon.  • If 'c-electric-flag' is non-nil, the colon is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the colon based on the settings in 'c-hanging-colons-alist'.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, whitespace between two colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
	• ;	(c-electric-semi, ARG)	Insert a comma or semicolon.  If 'c-electric-flag' is non-nil, point isn't inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) When the auto-newline feature is turned on (indicated by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-semi&comma-criteria' for how newline insertion is determined.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, a comma following a brace list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-cleanup-list'.
Insert New Line(s)	The behaviour of the RET key depends on whether the CC Mode electric mode is active or not. When it is not active it simply inserts a new line. When it is active the point also moves to the proper indentation according to the syntactic context. The following commands can also be used.  • With PEL the default behaviour can be selected by customization and modified dynamically for the current buffer with the pel-cc-change-newline-mode command (bound to <f12> M-RET) see the CC-Mode behaviour control section above.  • The pel-cc-newline command also aligns comments and assignment in the code block if the pel-modes-activating-align-on-return user option list includes the current major mode. The state for the current buffer can also be modified by the pel-cc-change-newline-mode command (<f11> M-RET).</f11></f12>		
Insert a new line and operate according to the currently active selected return mode. With PEL, modify behaviour with <f12> M-RET.</f12>	RET	( <b>pel-cc-newline</b> &optional N)	Insert a newline and perhaps align.  With argument N repeat N times.  For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below):  c-context-line-break (PEL default for RET)  newline (Emacs default for RET)  electric-indent-just-newline  If the variable 'pel-newline-does-align' is t, then perform the text alignment done by the function 'align'.
	<ul> <li>Use: (c-context-line-break): Do a line break suitable to the context.</li> <li>When point is outside a comment or macro, insert a newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is which case the new line is indented as the previous non-empty line instead.</li> <li>When point is inside the content of a preprocessor directive, a line continuation backslash is inserted before the line break and aligned approximate and of the cpp directive doesn't count as inside it.</li> <li>When point is inside a comment, continue it with the appropriate comment prefix (see the 'c-comment-prefix-regexp' and 'c-block-comment variables for details). The end of a C++-style line comment doesn't count as inside it.</li> <li>When point is inside a string, only insert a backslash when it is also inside a preprocessor directive.</li> </ul>		newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in non-empty line instead. rective, a line continuation backslash is inserted before the line break and aligned appropriately. it. appropriate comment prefix (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' mment doesn't count as inside it.
	If 'electric-indent-mod     To just insert a newl	vlines' is non-nil, the newline is e' is enabled, this indents the f ine, use M-x electric-indent-jus	s marked with the text-property 'hard'. inal new line that it adds, and reindents the preceding line. st-newline. ' is greater than the value of 'fill-column' and ARG is nil.
	Use: (electric-indent-just-newline ARG): Insert just a newline, without any auto-indentation.  • With ARG, insert that many newlines.		
Insert an indented line below unbroken current line See also: Indentation	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line.  For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation.  If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments.  You can toggle this on/off with <f11> M-RET.  But lightly modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	с-ј	(electric-newline-and- maybe-indent)	Insert a newline.  If 'electric-indent-mode' is enabled, that's that, but if it is *disabled* then additionally indent according to major mode.  Indentation is done using the value of 'indent-line-function'.  In programming language modes, this is the same as TAB.  In some text modes, where TAB inserts a tab, this command indents to the column specified by the function 'current-left-margin'.
Open New Line in Context See also:  • Whitespace	C-0	(c-context-open-line)	Insert a line break suitable to the context and leave point before it.  • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details.  solution of the CC words. If you want to open the line without indenting the next use open-line via <f12> C-o</f12>

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Open new line	• <f12> C-o • <m-f12> C-o</m-f12></f12>	(open-line N)	Insert a newline and leave point before it.  If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank.  With arg N, insert N newlines.
<u>G Comments</u>	2 more characters have electri • C supports 2 types of comm • '*': Block Comments: • '/': Line Comments (	/* comment	
Comment characters, wrapping long comment lines	/	(c-electric-slash ARG)	Insert a slash character.  • If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'.  • Indent the line as a comment, if:  1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or  2. The slash is part of a "*/" token that closes a block oriented comment.  • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
See also:  Filling/Justification	*	(c-electric-star ARG)	Insert a star character.  If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment.  If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited.  With this key being electric it becomes easy to type the following two styles of multi-line block comment:  /* Two star  ** continuation  ** prefix for  ** multi-line  ** C comment.  */  When typing the '*' at the beginning of the line, it indents automatically. If another '*' is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.  When auto-fill-mode is active, when you type a comment that would be longer than the line, the line is wrapped and the comment continuation string used is automatically inserted. (toggle it with <f11> RET)</f11>
Comment/un-comment See also: Comments	M-;	(comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer.  • When no marked region and no comment:  • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line.  • On line with code: insert comment starter after the code for an end-of-line comment  • With marked un-commented region:  • Comment region (each line is commented)  • With marked commented region:  • removes the comment.  • Call the comment command you want (Do What I Mean).  • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  • You can toggle between C-style /* */ and C++ style // comments (compatible with C since C-99) <fi>f12&gt; M-;</fi>
	C-c C-c	( <b>comment-region</b> BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just C-u prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.  • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'.  • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.  • If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better.
Fill current paragraph See also: Filling/Justification	• M-q • <f12> F • <m-f12> F</m-f12></f12>	( <b>c-fill-paragraph</b> &optional ARG)	Like <f11> t f p but handles // and /* */ style comments.  • If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details).  • If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following:  char description[] = "\ A very long description of something that you want to fill to make nicely formatted output.";  • If point is in any other situation, i.e. in normal code, do nothing.  • Optional prefix ARG means justify paragraph as well.</f11>
Toggle subword- mode	• <f11> t m b • <f12> M-b</f12></f11>	( <b>subword-mode</b> &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words.
See also: • <u>Nature Modes</u>	• <f12> M-b • <m-f12> M-b</m-f12></f12>	· · · · · · · · · · · · · · · · · · ·	With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Hide/Show comments See also:  • <u>&gt; Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle & optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active then toggle in the region. Otherwise, in the whole buffer.  ■ This requires the hide-comnt.el package (see ∑ Comments).  ■ PEL activates it when the pel-use-hide-comnt user option is t.	
Hungry Deletion of Whitespace	The CC mode provides two commands that can perform "hungry whitespace deletion" that can also be used in every mode.  • Sell provides the convenient keys with the <f11> prefix keys for those 2 commands, available in all modes.  • In modes compatible with the CC Mode (e.g. for C, C++, D, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behavior of the simple <del> and C-d, to perform hungry deletions. That's not currently supported in other modes.  • When the Hungry Delete Mode is on, the mode-line displays a 'h' to the right of the '/l' indication of electric mode.  • The Hungry Mode also activates the key prefixes below that start with C-c. They are listed but remember they are only available once the Hungry star mode is activated (and that can only be done in modes that are CC Mode compatible).  • In modes derived from CC Mode you can also activate the hungry state to make standard delete commands delete hungrily, but that does not work for other modes. PEL provides the <f12> M-DEL key for those modes (like C).  • Toggle hurry deletion mode of the DEL and C-d key for the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12></f12></del></f11>		iix keys for those 2 commands, available in <b>all</b> modes.  b, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour s. That's not currently supported in other modes.  clays a 'n' to the right of the '//l' indication of electric mode.  that start with <b>C-c</b> . They are listed but remember they are only available once the Hungry state that are CC Mode compatible).  the hungry state to make standard delete commands delete hungrily, but that does not work for r those modes (like C).	
Delete preceding char or all preceding whitespace.  See also: <u>See also:</u> <u>Cut &amp; Paste</u>	• C-c DEL • C-c ☒ • C-c C-☒ • C-c C-DEL • <f11> ☒ ☒ • <f11> DEL DEL</f11></f11>	(c-hungry-delete- backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character.  □► In terminal mode, even though C-⟨S , ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.  ⑤ With PEL, the ⟨f11⟩ ⟨S  ⟨S  binding is always available, in all modes.  The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.	
Delete next char or all following whitespace.  See also:  Tut & Paste	• C-c C-d • C-c 🖄 • C-c C-\sqrt{\$\infty\$} • C-c <c-delete> • <f11> \sqrt{\$\infty\$}</f11></c-delete>	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character.  In terminal mode, even though $C-\boxtimes$ and $$ are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.  With PEL, the $<$ f11> $\boxtimes$ binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.	
Indentation	behaviour control section above You can also explicitly request • The first set of commands p	All syntactic indentation control for C is controlled by the CC-Mode state, the style and whether electric mode for some characters is active. See CC Mode behaviour control section above.  You can also explicitly request indentation using the commands below.  The first set of commands perform syntactic indentations s controlled by the CC Mode.  Rigid indentation commands are also available and listed at the end of this list. They are also listed in the Indentation table.		
Indent current line or region  See also:  •	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.  • Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <f12> M-i key):  • With syntactic-indentation on (the default):  • In Transient Mark mode, when the region is active, reindent the region.  • Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.  • Otherwise reindent just the current line.  • This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.  • With syntactic-indentation off:  • <tab> always indent current line by one level  • C-u - <tab> or M- <tab> always un-indent current line by one level  • Indenting marked region is done without syntax knowledge and at the same level as previous line.  • If you want to indent rigidly you can use:  • pel-indent-rigidly, bound to C-x <tab> and to <f11> <tab><tab><tab><tab><tab><tab><tab><tab></tab></tab></tab></tab></tab></tab></tab></tab></f11></tab></tab></tab></tab></tab></f12>	
Indent lines of list after point See also:  Indentation	C-M-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it.  • A prefix argument (C-u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.	
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.	
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.  • A numeric prefix argument specifies a column: indent each line to that column.  • With no prefix argument, the command chooses one of these methods and indents all the lines with it:  1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.  2. If 'indent-region-function' is non-nil, call that function to indent the region.  3. Indent each line via 'indent-according-to-mode'.  When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>	
Non Syntactic Indentation		, it's best to set pel-c-tab-wid	gards to semantics. More information on indentation is available in the <u>∑ Indentation</u> table.  th and pel-c-indent-width to the same value: the first 2 commands use the value of pel-c-tab-	
Insert spaces or tabs to next defined tabstop column See also: <u> Indentation</u>	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column.  The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer.  With PEL, the tab-stop interval is controlled by the value of pel-c-tab-width.  PEL sets tab-width to the value of pel-c-tab-width for each c-mode buffer.	
Indent/Unindent rigidly See also:  • <u>National Indentation</u> • <u>National Key-Chords</u>	• C-x <tab> • <f11> <tab> <tab> • <tab>q</tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	Indent rigidly the marked region or current line N times tab-width columns.  • If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes.  • If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1):  • N = [-1, 0, 1] : operate on current line  • N > 1 : operate on the current line and N-1 lines below.  • N < -1 : operate on the current line and (abs N) -1 lines above.	

Description	<u>Keystroke</u>	Function	<u>Note</u>
	indent-rigidly Indent all lines s	starting in the region. /ith no prefix argument, activate	indent-rigidly uses the original indent-rigidly.  e a transient mode in which the indentation can be adjusted interactively by typing <left>,</left>
	The capabilities are controlled  • S- <right> indent-  • S-<left> indent-  • <right> indent-  • <left> indent-  Typing any other key deactivat  • The S-<right> and S-  • With PEL, the tab-stop in  • PEL sets tab-width to</right></left></right></left></right>	S- <left> indent-rigidly-left-to-tab-stop  <li><right> indent-rigidly-right</right></li></left>	
Indent line(s) rigidly	• <f6> <tab></tab></f6>	(pel-indent-lines &optional	Indent current or marked lines by N indentation levels controlled by <b>pel-c-indent-width</b> .
See also:  • ∑Indentation	• <f11> <tab> c</tab></f11>	N)	<ul> <li>Works with point anywhere on the line.</li> <li>All lines touched by the region are indented.</li> <li>A special argument N can specify more than one indentation level. It defaults to 1.</li> <li>If a negative number is specified, 'pel-unindent-lines' is used.</li> <li>If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines.</li> <li>Use C-g to de-activate the region.</li> <li>Handles presence of hard tabs:</li> <li>If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters.</li> <li>If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.</li> </ul>
Un-indent line(s) rigidly See also: • <u>∑ Indentation</u>	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	<ul> <li>Un-indent current line or marked lines by N indentation levels controlled by pel-c-indentwidth.</li> <li>Works with point is anywhere on the line.</li> <li>All lines touched by the region are un-indented.</li> <li>If region was marked, the function does not deactivate it to allow repeated execution of the command.</li> <li>If a region was marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines</li> <li>Use C-g to de-activate the region.</li> <li>Handles presence of hard tabs:</li> <li>If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters.</li> <li>If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.</li> </ul>
Information about C code	There are several Emacs extension packages that can help writing C code.		
Toggle c-eldoc mode	<f12> ? e</f12>	(pel-toggle-c-eldoc-mode)	Toggle c-eldoc mode on/off.  • The c-eldoc mode provides the C prototype information in the echo area for the function at point. It currently appears when typing a new function with its arguments inside the code.
	<f11> SPC c ? e</f11>		<ul> <li>Property of the processing processing may slow Emacs.</li> <li>The extra processing may slow Emacs.</li> <li>This package could be improved into providing the information only on demand but a LSP-based system might be more performant anyway. I am currently looking at this to see if I can improve the performances and the feature set. c-eldoc uses the cpp command to preprocess the buffer content.</li> </ul>
Tempo skeletons for C  See also:  • ∑ Inserting Text for more info and information about tempo skeleton and yasnippet template-based text insertion	PEL creates key bindings to with the same key bindings  Several aspects of the Pedited with <f12> <f12> pel-c-skel-module-heac pel-c-skel-insert-file-tir pel-c-skel-doc-markup pel-c-skel-doc-markup pel-c-skel-doc-markup pel-c-skel-doc-markup pel-c-skel-file-section pel-c-skel-file-section pel-c-skel-file-section pel-c-skel-insert-functio pel-c-skel-insert-function pel-c-skel-function-defi  pel-c-skel-function-defi  pel-c-skel-function-defi  pel-c-skel-function-and pel-c-skel-with-license  pel-c-skel-mith-license  control the user options by defeeffect on a single file or all files change the behaviour for only templates for all files inside a control the user options affect Once a skeleton was just er</f12></f12>	o invoke the skeletons in the support of equivalent concepts (such a provided provid	ugh the Emacs built-in tempo skeleton mechanism. proported major modes, using the same key prefix sequence for each mode: <f12> <f12>, as file header block) as much as possible.  Ityle is controlled by the user options inside the pel-c-code-style group. This group can be and include the following options:  Ing a user-define module-header comment block.  In at of C-style continuation comments.  In at of C-style continuation comments.  In at of C-style continuation comments.  In at of C-c style group. This group can be and include the following options:  In a user-define module-header comment block.  In a to C-c style group. This group can be and include the following options:  In a user-define module-header comment block.  In a to C-c style group. This group can be and include the following options:  In a user-define module-header comment block.  In a to C-c style group. This group can be and include the function served in the function description comment.  In a to the comment block style in the function description comment.  In a to the C function templates sections inserted when pel-c-skel-insert-function-sections is to to ton comment block style. Several styles are provided:  In a to the C function templates sections identified by pel-c-skel-function-section-titles tempo skeleton loaded from a user specified file name. See the source code example.  In a to the comment block with the sections identified by pel-c-skel-function-section-titles tempo skeleton loaded from a user specified file name. See the source code example.  In a to the comment block with the sections identified by pel-c-skel-function name or just above.  In a to the comment block with the sections identified by pel-c-skel-function name or just above.  In a to the comment block with the sections identified by pel-c-skel-function name or just above.  In a to the comment by the comment by the comment by the comment by t</f12></f12>
∑ Customize PEL C Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL C skeleton layout.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.

Insert finicipals <   Column	Description	<u>Keystroke</u>	Function	<u>Note</u>
insert finalule 4.h  CF12> CF13> 1  (pel-c-include-tib)  Insert finalule 5.h  CF13> CF13> 1  (pel-c-include-tib)  Insert finalule 6.h  CF13> CF13> TI (pel-c-include-tib)  Insert finalule 6.h	Insert a file header	<f12> <f12> h</f12></f12>	(pel-elisp-file-header)	<ul> <li>Prompts for the file purpose.</li> <li>For header files, include guard is inserted if requested by customization.</li> <li>The layout of the entered text is controlled by user options. It is possible to create a user-specified skeleton this command will used instead of the one provided by PEL.</li> <li>See examples of generated outputs located in example/templates/c/files repo directory.</li> </ul>
If see is such between the begamins of the first and point, insert the statement on the read in survivors construct not be country for survivors (and the country of the private files) in the country of the country	Insert #define	<f12> <f12> d</f12></f12>	(pel-c-define)	If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line, even if there is text after point (to allow inserting it
If there is tax between the beginning of the line and point, most the statement on the mater of the control (included in the current line)	Insert #include <.h>	<f12> <f12> i</f12></f12>	(pel-c-include-lib)	<ul> <li>If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line.</li> <li>If there is text after point, insert a new line to place that text on the next line.</li> <li>The .h extension is written between the angle brackets and point left right before the period.</li> </ul>
- The command pumples for the function name and its purposes You cann't be true both prompted speedly no trait; in that case a turnop selection marker in the command pumple of the pumples You cann't be true both prompted speedly no trait; in that case a turnop selection marker in the pumple of the pumples of the p	Insert #include ".h"	<f12> <f12> I</f12></f12>	(pel-c-include-local)	<ul> <li>If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line.</li> <li>If there is text after point, insert a new line to place that text on the next line.</li> <li>The .h extension is written between the angle brackets and point left right before the period.</li> </ul>
PEL tempo mode activates C-c., and C-c. p., as well as to C-c. C-y. key bindings to navigate across tempo mark for the pel-tempo-mode is active the pel-tempo-mode is active the pel-tempo-mode is grating to perform the pel-tempo-mode is grating to perform the pel-tempo-mode is active the pel-tempo-mode is grating to perform the pel-tempo-mode is grating to perform the pel-tempo-mode is performed to the pel-tempo-mode is active the pel-tempo-mode is active the pel-tempo-mode is active.  Jump to previous tempo mark  * C-c A-f * C-c C- * C-c K-b * C-c K-b * C-c C- * (tempo-forward-mark) * C-c C- * (tempo-backward-mark) * (tempo-backward-mark) * C-c C- * (tempo-backward-mark) * (tempo-backward-mark) * C-c C- * (tempo-backward-mark) *	definition with	<f12> <f12> f</f12></f12>	(pel-c-function)	<ul> <li>The command prompts for the function name and its purpose.</li> <li>You can hit return both prompts to specify no text; in that case a tempo skeleton marker is left at the location where the text must be inserted and point is left at the first one.</li> <li>If you enter a function name, it must be a valid C function name (as far as the syntax is concerned). However leading and trailing whitespace is accepted and trimmed and dash characters ('-') are automatically replaced by underscores ('_') for convenience.</li> <li>If an invalid name is specified it is erased and you are prompted again. Use M-p to bring the old value back.</li> <li>Prompts for function and purpose maintain separate histories. Use M-p and M-n to navigate in the histories at the prompt. You can also use the <up>and <down> keys.</down></up></li> <li>The style of the code inserted is controlled by the user options inside the pel-c-code-style group and the various C style element controls of the CC-mode.</li> </ul>
Inside the inserted skeleton.   Inside the inserted skeleton.   Inside the inserted skeleton.   Insert parentheses		<f12> <f12> SPC</f12></f12>		PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-rst commands, the pel-
Tempo Template Tag   Insertion   Fig. 2 < £12 > £12		• C-c .	(tempo-forward-mark)	inside the inserted skeleton.
Insertion   Soptional SILENT    Soptional Si		• C-c ,	(tempo-backward-mark)	
Insert Parentheses  M−(  (insert-parentheses & optional ARG)  M−(  (insert-parentheses & optional ARG sexps instead.  No argument is equivalent to zero: just insert ()¹ and leave point between.  PEL makes 'parens-requier spaces' buffer local and set it to nil in C mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.  This command assumes point is not in a string or comment.  Mark the complete function.  Mark complete function.  Mark complete function.  Put mark at end of the current top-level declaration or macro, point at beginning.  Put mark at end of the current top-level declaration or macro, point at beginning.  Put mark at end of the current top-level declaration or macro, point at beginning.  A mark is left where the command started, unless the region is already active (in Transient Mark mode).  A mark is left where the command started, unless the region is already active (in Transient Mark mode).  A sopposed to C-M-a and C-M-e, this function does not require the declaration to contain brace block.  Methods:  Mark the complete function.  A mark is left where the command started, unless the region is already active (in Transient Mark mode).  A sopposed to C-M-a and C-M-e,		<f12> <f12> <f12></f12></f12></f12>		Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit <f12> <f12> <f12> A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the templates in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all.  If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.  Since only one template is available in emac-lisp-mode, the usefulness of this command is</f12></f12></f12></f12></f12>
A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.  A negative ARG encloses the preceding ARG sexps in parenthesis if they are balanced.  A negative ARG encloses the preceding ARG sexps instead.  No argument is equivalent to zero: just insert (') and leave point between.  PEL makes 'parens-require-spaces' buffer local and set it to nil in C mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.  If region is active, insert enclosing characters at region boundaries.  This command assumes point is not in a string or comment.  Mark the complete function.  Mark complete function.  C-M-h  (c-mark-function)  Mark complete function.  Put mark at end of the current top-level declaration or macro, point at beginning.  If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.  A mark is left where the command started, unless the region is already active (in Transient Mark mode).  As opposed to C-M-a and C-M-e, this function does not require the declaration to contain brace block.  Getting Syntactic Information  Use the following commands to extract syntactic information from the source code.	Inserting code	Extra text insertion can be dor	ne with the following command	S.
Mark the complete function body       C-M-h       (c-mark-function)       Mark complete function. <ul> <li>Put mark at end of the current top-level declaration or macro, point at beginning.</li> <li>If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.</li> <li>A mark is left where the command started, unless the region is already active (in Transient Mark mode).</li> <li>As opposed to C-M-a and C-M-e, this function does not require the declaration to contain brace block.</li> </ul> <li>Getting Syntactic Information</li>	Insert Parentheses	M- (		<ul> <li>A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.</li> <li>A negative ARG encloses the preceding ARG sexps instead.</li> <li>No argument is equivalent to zero: just insert '()' and leave point between.</li> <li>PEL makes 'parens-require-spaces' buffer local and set it to nil in C mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.</li> <li>If region is active, insert enclosing characters at region boundaries.</li> </ul>
Function body  Put mark at end of the current top-level declaration or macro, point at beginning.  If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.  A mark is left where the command started, unless the region is already active (in Transient Mark mode).  As opposed to C-M-a and C-M-e, this function does not require the declaration to contain brace block.  Getting Syntactic Information  Use the following commands to extract syntactic information from the source code.	Marking	Emacs provides the following command to quickly mark the whole content of the current function. More mark commands exists, see the <u>Narking</u> table.		
See also: Marking  • If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.  • A mark is left where the command started, unless the region is already active (in Transient Mark mode).  • As opposed to C-M-a and C-M-e, this function does not require the declaration to contain brace block.  Getting Syntactic Information  Use the following commands to extract syntactic information from the source code.		С-м-h	(c-mark-function)	·
Information				<ul> <li>If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.</li> <li>A mark is left where the command started, unless the region is already active (in Transient Mark mode).</li> <li>As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a</li> </ul>
		Use the following commands to	to extract syntactic information	from the source code.
current function  • <f12> f • <m-f12> f • <m-f12> f</m-f12></m-f12></f12>	Display name of		(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it.  With a prefix arg, push the name onto the kill ring too.

Description	<u>Keystroke</u>	Function	Note
Search Support			<u>case</u> is often used. Using superword-mode helps searching. change this use the <f11> t <f2> to access the customize buffer.</f2></f11>
Toggle superword-	• <f11> t m p</f11>	(superword-mode	Toggle superword-mode: a minor mode that treats snake_case as one word. In C '_' are
mode See also:  • <u>∑ Text Modes</u> • <u>∑ Search/Replace</u>	• <f12> M-p</f12>	&optional ARG)	<ul> <li>treated as part of words.</li> <li>With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.</li> </ul>
Highlighting blocks	show-paren-mode, which h	ighlights the parens that match here matching nested parens a	seful modes to highlight blocks of (), {}, and [].  les the one before or after point.  tre highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it
See also: <u>➤ Highlight</u>	• <f11> h (</f11>		<ul> <li>otherwise.</li> <li>Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.</li> </ul>
Enable/Disable coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.
nested blocks (),{},[] See also: <u>∑ Highlight</u>	• <f11> h R</f11>		<ul> <li>Customize the depth and colours with M-x customize-group rainbow-delimiters</li> <li>Requires: rainbow-delimiters.el</li> <li>PEL activates this when the pel-use-rainbow-delimiters user option is set to t.</li> </ul>
Navigation in C	This current list below describ	e the specialized commands o	nly. See the others inside <u>▼ Navigation</u>
By definitions	Move to the definition of funct	ion or type at point. See Xre	ef for more information to activate the various engines that support cross referencing for C code.
Find definition of identifier at point  See also: Xref	м	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition.  If there are more than one match, prompt in the *xref* buffer.  To search for a symbol entered manually, type C-u M  With dumb-jump this performs a search using ag, ripgrep or git grep if available.
Go back to where M was last issued	М-,	(xref-pop-marker-stack)	Pop back to where M was last invoked. Marker depth is controlled by the xref-marker-ring-length user option.
By functions		unction definition blocks or str	
By structures	<ul><li>Jump over comments.</li><li>When point is located be</li></ul>	efore opening brace or right aft	er closing brace and <b>show-paren-mode</b> is on, the matching parentheses are highlighted.
Forward to start of next top level function or struct	• <f6> n • <f6> <down></down></f6></f6>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function or type definition.  • Move point before the function type or the struct or typedef keyword.  • Beeps if does not find beginning of next function unless SILENT is non-nil.  • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M−ˆ.  □ Shift marking is available.  □ This command complements what end-of-defun does.  • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.
Forward to end of current top-level function or struct.	С-М-е	( <b>c-end-of-defun</b> &optional ARG)	Move forward to the end of a top level declaration.  • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	( <b>end-of-defun</b> &optional ARG)	Move forward to the end of next function or type definition.  With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  ➡Shift marking is available in graphics mode, not in terminal mode (both keys).  This command moves to the end of the next top-level function. It skips the nested functions.
Backward to beginning of current top-level function or	С-М-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a function or type definition.  With a positive argument, move backward that many functions or structures. A negative argument -N means move forward to the Nth following beginning.
struct	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of function or type definition.  • Move point before the function type or the struct or typedef keyword.  • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.  ► Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p handles Shift-marking fine in terminal mode.  ↑ This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions that are more deeply nested.</f6></home>
Backward to end of previous top level function or struct	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function or type definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M− `.  ⇒ Shift marking is available.  • This command complements this set of 4 commands.  In some cases it fails to detect the end of the previous block and fails.
By blocks	Move across C statements	and C scope blocks, or any gro	oup of (), [], {} or <> blocks.
By List element  Perloyand blook/list	Move to the end or the b		Mana backward assess and believed assess of a 11
Backward block/list  See also: Navigation	С-м-р	(backward-list &optional ARG)	Move backward across one balanced group of parentheses.  • This command will also work on other parentheses-like expressions defined by the current language mode.  • With ARG, do it that many times.  • Negative arg -N means move forward across N groups of parentheses.  • This command assumes point is not in a string or comment.  • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.
Move block backward See also: •   Navigation	• C-M-b • C-M- <left> • C-[ C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp).  • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment.  • C-M-b : → Shift marking is available in graphics mode, not in terminal mode.  • C-M- <left> : → Shift marking works with this command.  • ⚠ With PEL: if you want to use Esc C-<left> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil, otherwise it does something else.  • C-M-<left> does not work on Windows, but H-<left> works.  ⑤ Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems-&gt;settings-&gt;keyboard-&gt;shortcuts to prevent it from using that key sequence.</left></left></left></left></left>

Description	<u>Keystroke</u>	Function	Note
Forward block/list	C-M-n	(forward-list &optional	Move forward across one balanced group of parentheses.
I OI WAI'U DIOCK/IISL	C-M-II	ARG)	This command will also work on other parentheses-like expressions defined by the current
See also: Navigation			language mode.  • With ARG, do it that many times.
			Negative arg -N means move backward across N groups of parentheses.
			This command assumes point is not in a string or comment.      This command assumes point is not in a string or comment.      This command assumes point is not in a string or comment.
			• C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.
Move block forward	• C-M-f	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp).  • With ARG, do it that many times. Negative arg -N means move backward across N balanced
See also:	• C-M- <right> • C-[ C-f</right>	And)	expressions. This command assumes point is not in a string or comment.
• <u>∑ Navigation</u>	• Esc C-f		• C-M-f : ► Shift marking is available in graphics mode, not in terminal mode.
	• Esc C- <right> 🔔</right>		• C-M- <right> : - Shift marking works with this command.</right>
			<ul> <li>Mith PEL: if you want to use Esc C-<right> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil, otherwise it does something else.</right></li> </ul>
			<b>♦ C-M-<right></right></b> does not work on Windows, but <b>H-<right></right></b> does.
			Several Linux distros map C-M- <right> to desktop workspace operation. In that case</right>
			you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.
in/out of blocks	Move in or out of C scope b	locks, or any group of (), [], {}	or < > blocks.
Backward Up/outside	• C-M-u	(backward-up-list	Move backward out of one level of parentheses or nested blocks.
sexp hierarchy	• C-M- <up></up>	&optional ARG ESCAPE-	This command will also work on other parentheses-like expressions defined by the current
See also:	• C-[ C-u	STRINGS NO-SYNTAX- CROSSING)	language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot.
• <u>∑ Navigation</u>	• Esc C-u • Esc C- <up></up>	0.1000	• A With PEL: if you want to use Esc C- <up> binding you must ensure that pel-</up>
	Esc c-\up>		windmove-on-esc-cursor user option is set to nil.
			<ul> <li>C-M-u : ► Shift marking is available in graphics mode, not in terminal mode.</li> <li>C-M-<up> : ► Shift marking works with this command.</up></li> </ul>
			C-M- <up> does not work on Windows, but H-<up> does.</up></up>
Forward Up/outside	C-M-1	(up-list &optional ARG	Move forward out of one level of parentheses or nested blocks.
sexp hierarchy	_	ESCAPE-STRINGS NO-	This command will also work on other parentheses-like expressions defined by the current
See also: Navigation		SYNTAX-CROSSING)	<ul> <li>language mode.</li> <li>With ARG, do this that many times. A negative argument means move backward but still to a</li> </ul>
<u>//gaudii</u>			less deep spot.
Down/inside sexp/	• C-M-d	(down-list &optional ARG)	Move forward down one level of parentheses.
block	• C-M- <down></down>		<ul> <li>This command will also work on other parentheses-like expressions defined by the current language mode.</li> </ul>
See also:	• Esc C-d		With ARG, do this that many times. A negative argument means move backward but still go
<ul> <li>Navigation</li> </ul>	• Esc C- <down></down>		down a level.  This command assumes point is not in a string or comment.
			With PEL: if you want to use <b>Esc C-<down></down></b> binding you must ensure that <b>pel-</b>
			windmove-on-esc-cursor user option is set to nil.
			<ul> <li>C-M-d : ► Shift marking is available in graphics mode, not in terminal mode.</li> <li>C-M-<down> : ► Shift marking works with this command.</down></li> </ul>
			<b>♦ C-M-<down></down></b> does not work on Windows, but <b>H-<down></down></b> does.
By statements	Move to beginning /end of sta	tement of comment sentence.	
Go to beginning of	м-а	(c-beginning-of-statement	Go to the beginning of the innermost statement.
statement (backward)		&optional COUNT LIM SENTENCE-FLAG)	<ul> <li>With prefix arg, go back N - 1 statements.</li> <li>If already at the beginning of a statement then go to the beginning of the closest preceding</li> </ul>
(backwaiu)		SENTENCE-LEAG)	one, moving into nested blocks if necessary (use <b>C-M-b</b> to skip over a block).
			If within or next to a comment or multilline string, move by sentences instead of statements.
Go to the end of statement (forward)	м-е	(c-end-of-statement &optional COUNT LIM	Go to the end of the innermost statement.  • With prefix arg, go forward N - 1 statements.
<u>statement</u> (ioiwaru)		SENTENCE-FLAG)	Move forward to the end of the next statement if already at end, and move into nested blocks
			<ul> <li>(use C-M-f to skip over a block).</li> <li>If within or next to a comment or multiline string, move by sentences instead of statements.</li> </ul>
C Preprocessor	Emacs supports navigation through C preprocessor conditional statements, allow expansion of preprocessor macros, hiding pre-processor statements that		
<u>G Preprocessor</u>	would not be executed with the Hide-ifdet mode. There are also external packages that provide extra support. All commands provided by Emacs and		
	external packages are listed by	elow. They can be used for ed	iting C and C++ source code.
			sor directives and to hide/show code areas based on preprocessor logic and defined variables.
		_	ne pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix.   Requires
	the <u>hydra</u> external packag	e 🛂 PEL activates when the p	pel-use-hydra user option is set to t.
	-UUU:**F1 a c :	file.c All (4,0)	(C/*la Ifdef WK Fly <sup>2</sup> Anzu Abbrev)
	C preprocessor:	(1/0)	
Open the C	Move to His	de # 1	/ars Other
preprocessor <u>hydra</u> with <f12> <f7></f7></f12>	n: next #:	toggle mode   e:	evaluate : Show state
followed by on of the			define   <f7>: cancel</f7>
hydra keys:	:		undef
			Use list   Save list
	- !		Clear all
	S:	show block	
N	TI CIII		
Navigate across pre- processor conditionals	The following commands mov	e point across the <b>#if</b> , <b>#else</b> , #	#elif and #endif C pre-processor conditional statements.
Move to previous preprocessor directive	• <f12> # p * <f12> <f7> p</f7></f12></f12>	(pel-pp-prev-directive)	Move point to previous preprocessor directive.
Move to next preprocessor directive	• <f12> # n * <f12> <f7> n</f7></f12></f12>	(pel-pp-next-directive)	Move point to next preprocessor directive.
Move up in the pre- processor conditional	• C-c C-u * <f12> <f7> C-u</f7></f12>	(c-up-conditional COUNT)	Move back to the containing preprocessor conditional, leaving mark behind.  • A prefix argument acts as a repeat count. With a negative argument, move forward to the
block			<ul><li>end of the containing preprocessor conditional.</li><li>"#elif" is treated like "#else" followed by "#if", so the function stops at them when going backward, but not when going forward.</li></ul>
Move to the previous	• C-c C-p	(c-backward-conditional	Move back across a preprocessor conditional, leaving mark behind.
pre-processor conditional block	* <f12> <f7> C-p</f7></f12>	COUNT & optional TARGET- DEPTH WITH-ELSE)	<ul> <li>A prefix argument acts as a repeat count.</li> <li>With a negative argument, move forward across a preprocessor conditional.</li> </ul>
_		· · · · · · · · · · · · · · · · · · ·	

<u>Description</u>	<u>Keystroke</u>	Function	Note
Move to the next pre- processor conditional block	C-c C-n * <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move forward across a preprocessor conditional, leaving mark behind.  • A prefix argument acts as a repeat count.  • With a negative argument, move backward across a preprocessor conditional.  • If there aren't enough conditionals after (or before) point, an error is signaled.  • "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed when tracking subconditionals.
Expand Pre- Processor	• C-c C-e • <f12> # # • <m-12> # #</m-12></f12>	(c-macro-expand START END SUBST)	Expand C macros in the region, using the C preprocessor.  Normally display output in temp buffer, but prefix arg means replace the region with it.
		-preprocessor' specifies the -prompt-flag' is non-nil promp	preprocessor to use.  It for arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-
Insert/align or delete end-of-line backslash	C-c C-\	(c-backslash-region FROM TO DELETE-FLAG &optional LINE-MODE)	Insert, align, or delete end-of-line backslashes on the lines in the region.  With no argument, inserts backslashes and aligns existing backslashes.  With an argument, deletes the backslashes.
	<ul><li>backslash (if any) at the end</li><li>You can put the region arou</li></ul>	of the previous line is deleted and an entire macro definition a	e region. If the region ends at the start of a line and the macro doesn't continue below it, the .  nd use this command to conveniently insert and align the necessary backslashes.  ding to: 'c-backslash-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'.
Show state preprocessor modes	• <f12> # ? * <f12> <f7> ?</f7></f12></f12>	(pel-pp-show-state)	Show state of C preprocessor control modes.
Hide-ifdef Mode	it hides blocks of code that ifdef environment: the hide-     With PEL, the commands re     Several customize user op     'hide-ifdef-env'     An association list of ovariable, which limits In C++ source files open     (SYMBOL) is used	ifdef-env association list Emar eachable via the <f12> prefix lition variables affect how the hidelined symbols for the current nidefined symbols for the current nidefit to parse only one C/C++</f12>	panded file according to the state of pre-processor symbols that are maintained inside the Hidecs variable (use <f1> v to see the content of these variables. See <a href="Melp/Info">Melp/Info</a>. keys can also be reached via the <m-f12> and the <f11> SPC c prefix keys. ding is done (to change, execute: M-x customize-group hide-ifdef):  project. Initially, the global value of 'hide-ifdef-env' is used. This variable was a buffer-local file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C/puffers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. (but without explicit value)</f11></m-f12></f1>
	An association list of pre-defined symbol lists. Use 'hide-ifdef-set-define-alist' to save the current 'hide-ifdef-env' and 'hide-ifdef-use-define-alist'.  • 'hide-ifdef-lines' Set to non-nil to not show #if, #ifdef, #else, and #endif lines when hiding.  • 'hide-ifdef-initially' Indicates whether 'hide-ifdefs' should be called when Hide-Ifdef mode is activated.  • 'hide-ifdef-read-only' Set to non-nil if you want to make buffers read only while hiding. After 'show-ifdefs', read-only status is restored to previous value.  ★ The key sequences that start with <f12> <f7> open the pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix.</f7></f12>		n 'hide-ifdef-define-alist'.  and #endif lines when hiding.  n Hide-Ifdef mode is activated.  while hiding.  evious value.
Toggle the Hide-Ifdef mode	• <f12> M-# • <m-f12> M-# * <f12> <f7> # • <f11> SPC c M-#</f11></f7></f12></m-f12></f12>	(hide-ifdef-mode &optional ARG)	Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode).  With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise.  Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
Toggle read-only mode when text is hidden	• C-c @ C-q • <f12> # r * <f12> <f7> R</f7></f12></f12>	(hide-ifdef-toggle-read- only)	Toggle read-only: toggle 'hide-ifdef-read-only'.  • Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w * <f12> <f7> W</f7></f12></f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the <a href="mailto:shadow face">shadow face</a> (normally something dim, all depending of the theme used).
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H * <f12> <f7> H • <f11> SPC c # H</f11></f7></f12></m-f12></f12>	(hide-ifdefs &optional NOMSG)	<ul> <li>Hide the contents of some #ifdefs.</li> <li>Assume that defined symbols have been added to 'hide-ifdef-env'.</li> <li>The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined.</li> <li>With prefix command presents it will also hide the #ifdefs themselves.</li> <li>Turn off hiding by calling 'show-ifdefs'.</li> </ul>
Restore all hidden into view	• C-c @ s • <f12> # S * <f12> <f7> S</f7></f12></f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h * <f12> <f7> h</f7></f12></f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor.  • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s * <f12> <f7> s</f7></f12></f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d * <f12> <f7> d</f7></f12></f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'.  This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u * <f12> <f7> u</f7></f12></f12>	(hide-ifdef-undef START END)	Undefine a VAR so that <b>#ifdef VAR</b> would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D * <f12> <f7> D</f7></f12></f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable.  The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
Use a named symbol environment list	• C-c @ U • <f12> # U * <f12> <f7> U</f7></f12></f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Clear the complete list of #define'd symbols inside 'hide- ifdef-env'	• C-c @ C • <f12> # C * <f12> <f7> C</f7></f12></f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'.  • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Evaluate pre- processor macro	• C-c @ e • <f12> # e * <f12> <f7> e</f7></f12></f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region.     If no region active, find the current #ifdefs and evaluate the result.     Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside C source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.  You can also use Graphviz, see M Graphviz Dot		
Preview UML diagram from plantUML source in current plantUML region of commented source code  See also: M PlantUML	<f12> u</f12>	(pel-render-commented- plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment.  Use region if identified otherwise use PlantUML block at point.  Uses prefix (as PREFIX) to choose where to display it:  4 (when prefixing the command with C-u) -> new window  16 (when prefixing the command with C-u C-u) -> new frame.  else -> new buffer  This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.  Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.

## Emacs & C - References

Document	Notes
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
company-mode ; Modular in-buffer completion framework for Emacs	