Emacs support for Make Files

Keystroke Emacs natively supports several sev	Function veral Make dialect modes as listed below.	<u>Note</u>	
PEL adds several command	s and user-options that add control to the editing		
• pel-modes-activating-superword-mode : PEL automatically activates super-word-mode for make files. Use <f11> t <f2> to access the customization group See language specific info: GNIL Make</f2></f11>			
2025-06-14			
<f11> SPC M <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$\mathbb{Y}\circ\ Make\ \end{are}\ \text{local PDF.} If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option</u>	
<f12> <f1></f1></f12>		is set it's the other way around.	
<f11> SPC M <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL make support: pel-use-makefile • pel-make-mode-alist to identify more file regexp and a make file major mode that must	
<f12> <f2></f2></f12>		 be used for those files. pel-makefile-activates-minor-modes lists minor modes to automatically activate in 	
		makefile major modes. If OTHER-WINDOW is non-nil (use C-u), display in another window.	
<f11> SPC M <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs makefile support: makefile. • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
<f12> <f3></f3></f12>	·		
mode-alist variable. The supp		when a file is visited using the mode and file specification association identified in the auto- make files with the corresponding dialect mode. The following make file dialect modes are	
makefile-mode (the base)		ived):	
 makefile-bsdmake-mo 	de : [Mm]akefile, .mk, .make		
 makefile-imake-mode 	: Imakefile		
 makefile-nmake-mode 	e : .mak PEL implements the makefile-n	make-mode to support Microsoft NMAKE syntax. or example).	
		ode: write something like this on the first line: -*- mode: makefile-gmake; -*- modes when on of them is already active.	
• C-c RET C-a	(makefile-automake-mode)	Activates the <u>automake</u> mode • The mode-line lighter is: Makefile.am	
• C-c C-m C-a	(makefile-bsdmake-mode)	Activates the BSD make mode.	
• C-c C-m C-b	,	BSD Make is the default make on macOS and BSD OS systems. The mode-line lighter is: BSDmakefile	
• C-c RET C-g	(makefile-gmake-mode)	Activates the <u>GNU make</u> mode.	
• C-c C-m C-g		 The mode-line lighter is: GNUmakefile Because this key sequence ends with C-g, type the Esc key 3 times to escape from the 	
• C a PEM <+ab>	(makafila-imaka-mada)	C-c C-m prefix. You can also use a key not in the list. Activate the imake mode	
• C-c C-m C-i	(makeme-imake-mode)	The mode-line lighter is : Imakefile	
• C-c RET RET • C-c C-m C-m	(makefile-mode)	Activates the major mode for editing standard Makefiles. • The mode-line lighter is: Makefile	
• C-c RET C-p • C-c C-m C-p	(makefile-makepp-mode)	Activates the <u>makepp</u> mode. Also called <u>make++</u> • makepp is written in Perl. It is mostly useful for writing C++ specific make files, as it expands GNU Make and removes the requirement of using recursive make. • The mode-line lighter is: Makeppfile	
• C-c RET C-n • C-c C-m C-n	(makefile-nmake-mode)	Activates the nmake mode, supporting Microsoft's NMAKE makefile syntax. • The mode-line lighter is: Nmake	
		igate across make target/dependency statements. PEL complements this with commands to	
C- <right></right>	(pel-forward-token-start &optional N)	Move to the beginning of next word/symbol.	
It handles characters that may be part of symbol in the current major mode, and jumps over them but stops at whitespace and operators. Supports numerical argument for repetition. Negative argument reverses the movement direction. The command support shift-marking.			
C- <left></left>	(pel-backward-token-start &optional N)	Move to the beginning of previous word/symbol.	
 It handles characters that may be part of symbol in the current major mode (like '_' in C), and jumps over them but stops at whitespace and operators. Supports numerical argument for repetition. Negative argument reverses the movement direction. The command support shift-marking. Useful when the superword-mode is not activated: allows jumping to previous symbol while the word commands stop at each word separator character. 			
• M-n • <f12> <down></down></f12>	(makefile-next-dependency)	Move point to the beginning of the next dependency line. • Skips comments and macro definitions.	
• M- <f12> <down></down></f12>			
<f11> SPC M <down></down></f11>	(makafila mu-d-o-d-o-d-o-d-o-d-o-d-o-d-o-d-o-d-o-d-	Mayo point to the heginalar of the available of the same of the sa	
• M-p • <f12> <up></up></f12>	(makerile-previous-dependency)	Move point to the beginning of the previous dependency line. • Skips comments and macro definitions.	
• <f12> M-<down></down></f12>	(pel-make-next-macro &optional N SILENT	Move to the beginning of next N make file macro definition statement.	
• M- <f12> M-<down></down></f12>	DONT-PUSH-MARK	The function skips over comments. In ovalid form is found, don't move point, issue an error describing the failure unless	
<f11> SPC M M-<down> SILENT is non-nil, in which case the function returns nil on error and non-nil on success. • The error message states the number of instanced searched, the regexp used and the number of instances found.</down></f11>			
On success, the function push original position on the mark ring unless DONT-PUSH-MARK is non-nil. The command support shift-marking.			
• <f12> M-<up> • M-<f12> M-<up></up></f12></up></f12>	(pel-make-previous-macro &optional N SILENT DONT-PUSH-MARK)	Move to the beginning of previous N make file macro definition statement. The function skips over comments. If no vilid form is found, don't make point increase a correct describing the failure values.	
• If no valid form is found, don't move point, issue an error describing the failure uniform some support of the failure o			
The error message states the number of instanced searched, the regexp used and the number of instances found. On success, the function push original position on the mark ring unless DONT-PUSH-MARK is non-nil. The command support shift-marking.			
		to navigate across GNU Make if statements. The first 2 also accept prefix to move to else.	
<f6> <right></right></f6>	(pel-make-forward-conditional &optional TO-ELSE)	Move point forward to matching end of make conditional: if point is before a <u>make</u> conditional if statement it moves to the matching endif, or else when prefix arg is used.	
	,	With C-u or numerical arg: move backward to matching else. On success, push the original position on the mark ring and return the new position. On	
		,, para and any position on the many and retain the new position. Off	
		error, issue user error on mismatch. Shift marking is available with C-M- <right></right>	
	• Emacs natively supports se • PEL adds several command • pel-modes-activating-s See language specific info: G 2025-06-14 <f11> SPC M <f1> <f12> <f1> <f12> <f1> </f1></f12> <f11> SPC M <f2> </f2></f11></f1></f12> <f11> SPC M <f3> <f12> <f3> Emacs supports several dialed mode-alist variable. The supported: • makefile-mode (the base makefile-make-mode makefile-make-mode makefile-imake-mode makefile-imake-mode makefile-imake-mode) • makefile-make-mode makefile-make-mode • makefile-make-mode • makefile-make-mode • Mith PEL, set up the asse in you can access the relevance in the second of the secon</f3></f12></f3></f11></f1></f11>	Emacs natively supports several Make dialect modes as listed below. PEL adds several commands and user-options that add control to the editin pel-modes-activating-supervord-mode: PEL automatically activates in pel-modes-activating-supervord-mode: PEL automatically activates in pel-modes and user-options that add control to the editin pel-modes of the pel-mode in the control of the pel-mode in the control of the pel-mode in the control of the pel-mode in	

Description	Keystroke	Function	Note	
Move outward forward to matching endif	<f6> <down></down></f6>	(pel-make-outward-forward-conditional &optional NEST-COUNT)	Move point forward, outward to end of current if statement. By default move 1 nest level outward. A larger count can be specified with optional NEST-COUNT numeric argument. On success, push the original position on the mark ring and return the new position. On error, issue user error on mismatch.	
Move outward backward to matching if	<f6> <up></up></f6>	(pel-make-outward-backward-conditional &optional NEST-COUNT)	Move point backward, outward to beginning of current if statement. By default move 1 nest level outward. A larger count can be specified with optional NEST-COUNT numeric argument. On success, push the original position on the mark ring and return the new position. On error, issue user error on mismatch.	
Show all Make conditional statements inside an occur buffer	<f6> o</f6>	(pel-make-conditionals-occur &optional NLINES)	Show make conditional statements inside an occur buffer. • Each line is shown with NLINES before and after, or -NLINES before if NLINES is negative. • NLINES defaults to list-matching-lines-default-context-lines user-option value. • If a region is defined the search is restricted to the region. See occur search	
• by blocks	Move to the matching pair of c	haracter in the following sets: (),[],{},<>,"", ''.		
block backward	• C-M-b • C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-b : ▶ Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ▶ Shift marking works with this command.</left>	
	• ⚠ With PEL: if you want to use Esc C- <left> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. ♦ C-M-<left> does not work on Windows, but H-<left> works. ⑤ Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</left></left></left></left>			
block forward	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : ♥ Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : ▼ Shift marking works with this command.</right>	
	❖ C-M- <right> does not wo. ⑤ Several Linux distros map 0</right>	rk on Windows, but H-<right></right> does. C-M-<right></right> to desktop workspace operation	on. In that case you can either use another key binding or change Linux key binding in	
iMenu/Speedbar See also:	Systems->settings->keyboard->shortcuts to prevent it from using that key sequence. You can navigate through makefile macros and targets (identified as <i>dependencies</i>) using Emacs iMenu and Speedbar capabilities. • Several commands are available to get a list of the various elements and move point to it. • These commands include the following. More are listed in the <u>E Completion/Input</u> . • Several packages extend the completion and how entry is done. PEL allows dynamic selection of several methods and can display the current status with M-g? • You can also use the <u>E Speedbar</u> to list all items on a vertical side-bar and navigate through them.			
Find definitions using	• <f11> <f10> i</f10></f11>	(imenu INDEX-ITEM)	Lists imenu-detected items from the current buffer (according to its major mode).	
See also: • © Completion/ Input • © Menus	• M-g i • M-g M-i	function does the parsing (it can be semantic Provides one of the following interfaces to let u • The default: input completion, using the mini • a pop-up window: available in Graphics mo popup-menu user-option is turned on.	user select entry to jump to:	
Move to imenu detected symbol definition in current buffer * *	• M-g h • M-g M-h	(pel-goto-symbol)	Prompt using for imenu symbol of the current buffer and move point to it. • Refresh imenu and jump to a place in the buffer using the completion method selected. • Modify user interface currently used with M-g <f4> h. • The command sets a ref-marker before moving. Return to previous location with M-,</f4>	
	M-g ?	(pel-show-goto-symbol-settings)	Display current settings used by the goto symbol commands in the echo area. For example: -UU-:F1 makefile Top (1,0) (BSDmakefile WK Anzu F1 pel-goto-symbol UI (M-g <f4> h) is: Ivy pel-goto-symbol-any-buffer UI (M-g <f4> y) is: Ido - iMenu UI is: pop-up menu - Ido requires: Ido Ubiquitous (M-g <f4> M-u) is: off - flx-ido (fuzzy matching) (M-g <f4> M-f) is: off - iMenu lists are hierarchical Ido uses: - Ido prompt geometry (<f1!> M-c M-g): ido-grid - Ido Ubiquitous mode (<f1!> M-c M-u): off - flx-ido mode (<f1!> M-c M-l): off - iMenu+ support is: on, which impacts all Ido-based prompts - Semantic mode is: off</f1!></f1!></f1!></f4></f4></f4></f4>	
Insert & Edit	The following commands help	the editing of the makefile contents.		
Insert <u>GNU make</u> <u>function statemen</u> t	• C-c Tab • C-c C-i	(makefile-insert-gmake-function)	Insert a GNU make function call. Asks for the name of the function to use (with completion). Then prompts for all required parameters.	
Insert target at point	C-c :	(makefile-insert-target-ref TARGET-NAME)	Complete on a list of known targets, then insert TARGET-NAME at point.	
Add/remove line continuation trailing backslashes	C-c C-\ This function does not modify	(makefile-backslash-region FROM TO DELETE-FLAG) the last line of the region if the region ends right	Insert, align, or delete end-of-line backslashes on the lines in the region. • With no argument, inserts backslashes and aligns existing backslashes. • With an argument, deletes the backslashes. at the start of the following line; it does not modify blank lines at the start of the region. So	
	you can put the region around	an entire macro definition and conveniently use	this command.	
Perform completion at point	C-M-i <f12> . <f6> .</f6></f12>	(completion-at-point)	Perform completion on the text around point. The completion method is determined by 'completion-at-point-functions'. The C-M-i is also often bound to flyspell command. Use <f12> . instead.</f12>	
Electric Insert	When the makefile-mode make	efile-electric-keys user-option is turned on (it is o	off by default), the characters \$: = and . have special behaviour, described below.	
Insert macro reference	\$	(makefile-insert-macro-ref MACRO-NAME)	Complete on a list of known macros, then insert complete ref at point.	
Insert new target	:	(makefile-electric-colon ARG)	Prompt for name of new target. Only prompts if point is at beginning of line. Anywhere else just self-inserts.	
Insert macro defintion	=	(makefile-electric-equal ARG)	Prompt for name of a macro to insert. Only prompts if point is at beginning of line. Anywhere else just self-inserts.	
Insert special target	•	(makefile-electric-dot ARG)	Prompt for the name of a special target to insert. Supports tab completion. Only does electric insertion at beginning of line. Anywhere else just self-inserts.	
Indenting		aracter is important. The make program distingues bound to prog-indent-sexp but it does not wo	rk well in makefile. Use the other 3 commands.	
Insert a tab character	<tab></tab>	(indent-for-tab-command &optional ARG)	Inserts a tab character in a makefile.	
Indent line(s) rigidly	• <f6> <tab> • <f11> <tab> c</tab></f11></tab></f6>	(pel-indent-lines &optional N)	Indent current or marked lines by N indentation levels. Each level uses a tab character. • Works with point anywhere on the line.	
	 A special argument N can specify more than one indentation level. It defaults to 1. If a negative number is specified, 'pel-unindent-lines' is used. If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. Use C-g to de-activate the region. 			

Description	Keystroke	Function	<u>Note</u>	
Un-indent line(s) rigidly	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	Un-indent current line or marked lines by N indentation levels. Works with point is anywhere on the line. All lines touched by the region are un-indented. If region was marked, the function does not deactivate it to allow repeated execution of the command. If a region was marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines Use C-g to de-activate the region.	
Indent expression	С-М-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. • When interactively called with prefix, indent the enclosing defun instead. A This command does not work well in makefiles.	
Comment control	Although the make file modes provide the comment-region command, it's best to use comment-dwim as it works much better: • Insert a comment, comment or un-comment a region with M-;			
Comment/un-	M-;	(comment-dwim ARG)	Comment or un-comment line or region.	
comment		(pel-comment-dwim ARG)	Same as comment-dwim but comments the current line with a numeric ARG or 0.	
See also: Comments With PEL: Comment the current line with M-0 M-;	When no marked region and no comment: On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line.			
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. A Prefer comment-dwim: it works better.	
	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. If ARG is negative, delete that many comment characters instead. • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.			
Toggle display of comments in buffer or active region See also: Comments	<f11> ; ;</f11>	(hide/show-comments-toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see EComments). PEL activates it when the pel-use-hide-comnt user option is t.	
Analyze	The following commands analyze the content of the make file or the file system.			
Scan current directory files, checking for targets	C-c C-f	(makefile-pickup-filenames-as-targets)	Scan the current directory for filenames to use as targets. • Checks each filename against 'makefile-ignored-files-in-pickup-regex' and adds all qualifying names to the list of known targets.	
Scan current buffer for makefile content	С-с С-р	(makefile-pickup-everything ARG)	Notice names of all macros and targets in Makefile. • Prefix arg means force pickups to be redone. Use this to refresh the list of macros and targets located in the makefile before executing another action on those.	
Update scan with latest makefile buffer content	C-c C-u	(makefile-create-up-to-date-overview)	Create a buffer containing an overview of the state of all known targets. Known targets are targets that are explicitly defined in that makefile; in other words, all targets that appear on the left hand side of a dependency in the makefile.	
List macros and targets in dedicated buffer	C-c C-b	(makefile-switch-to-browser)	Open a *Macros and Target* buffer that only lists them. It operates in Fundamental mode and aside listing the macros and targets provides nothing more.	

Emacs & Makefile - References

Document	Notes
Make tools	See also: GNU Autotools @ Wikipedia, GNU Coding Standard, section 7, Filesystem Hierarchy Standard (FHS 3.0)
GNU Make Manuals	GNU Make Top page How to run make GNU Make - Appendix A - Quick Reference Makefile Conventions Autoconf Portable Make Programming
Makepp home page	Makepp, also called make++ is a GNU Make replacement, written in Perl. It addresses the recursive make problem.
Make generic information	
Recursive Make Considered Harmful - Steve Miller	PDF paper (from the wayback machine archive) written by Steve Miller in 1997 describing the concept of recursive make technique showing why it causes several problems and what can be done to avoid them.
Non-Recursive Make Considered Harmful	A march 2016 PDF paper from Andrey Mokhov, Neil Mitchell, Simon Peyton Jones and Simon Marlow describe how even a non-recursive make based build system can be difficult to maintain and they propose something based on the Shake Haskell library.
Rules of Makefiles	Simple and clear rules to use as a guide for writing good make files.
How Not To Use VPATH	Describe problems to avoid when using VPATH
Multi-Architecture Builds	Describe a proper way to create make files.