Programming Language Support — C

Donasis tias	Vtt	F	No.	
<u>Description</u>	<u>Keystroke</u>	Function	Note	
Support for the			ends the <u>CC Mode</u> that support the <u>curly-bracket programming languages</u> like C. the CC Mode are customizable with PEL user option variables.	
C Programming Language		: Simplifies configuration for ed		
<u> Lariguago</u>		oup: pel-pkg-for-c (access wit	th <f12> <f2>): used for indentation. Defaults to 3.</f2></f12>	
		• pel-c-tab-width: The width of a tab used for c-mode files. Defaults to 3.		
		 This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i will move point to columns that are multiple of 8 <tab> will indent to a column that is a multiple of 3. PEL stores this value inside the tab-width variable for c-mode buffers.</tab> 		
	• pel-c-use-tabs: Whet	• pel-c-use-tabs: Whether hard tabs are used in indentation or not: t: tabs are used, nil: only spaces are used. Default: nil.		
	 C code style sub-grou pel-c-fill-column : 		ccurs : maximum line length (defaults to 80). You can change the value or set it nil.	
	When pel-c-fill-co	olumn user option is nil, c-mod	e buffers use the Emacs fill-column value like other major modes.	
		er' with some Emacs Lisp code	<u>le</u> supported by the electric keys. You can select one of the <u>values supported by Emacs</u> or e. Default to "linux".	
	 More user options are used for controlling C code templates created with PEL tempo skeletons. They are described in tempo skeleton section below. 			
	• Emacs customization group: pel-pkg-for-cc. Applies to all CC Mode related modes (like c-mode).			
			ode is active on all CC Mode (including c-mode). tored inside directory local files and even as file local variables. You can also modify them for	
			mmands listed in the following set of rows. See <u>File/Directory Variables</u> for more info.	
		g set of mode-specific key pro	,	
	• <f11> SPC c</f11>	g set of mode-specific key pro	onico.	
	• <f12> • <m-f12></m-f12></f12>			
	The first one is always		xes are only available in c-mode buffers. The <m-f12> prefix helps the typing flow when the</m-f12>	
	next key is a Meta key	r. For simplification, the <f11></f11>	> SPC c prefix is normally omitted in the table.	
Open this PDF file. See also: <u>Nelp/Info</u>	• <f11> SPC c <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the local copy of the <u>\$\mathbb{y}\$ - C</u> PDF file unless a command prefix (like C-u) was used. In	
	• <f12> <f1></f1></f12>	,	that case it opens the Github-hosted file instead.	
<u>∑ Customize</u> PEL C support	• <f11> SPC c <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL C support. • If OTHER-WINDOW is non-nil (use C - u), display in another window.	
Зарроп	• <f12> <f2></f2></f12>	.,	alpay in another mindew.	
<u>∑ Customize</u> Emacs C support	• <f11> SPC c <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs C support. • If OTHER-WINDOW is non-nil (use C - u), display in another window.	
support	• <f12> <f3></f3></f12>	doptional official window)	ii o ii let viive ovi is ii oli iiii (ase e - a), aispiay iii ai odici wiiidow.	
CC Mode Style			its syntactic interpretation of the current line and the indentation mode in use.	
Management	cases you can use CC Mode's	You can impose an indentation style by customization. But you may use source code written by others and want to continue using the same style. In those cases you can use CC Mode's ability to analyze the style and report it or start using it (installing it) with the following commands.		
		ented here, see the CC Mode n		
Show/Modify syntactic context	C-c C-o	(c-set-offset SYMBOL OFFSET &optional	Change the value of a syntactic element symbol in 'c-offsets-alist'. • SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that	
		IGNORED)	syntactic element. The optional argument is not used and exists only for compatibility reasons.	
Show syntactic	C-c C-s	(c-show-syntactic-	Show syntactic information for current line.	
information for	C-C C-S	information ARG)	Display the syntactic information list and highlight the reference position(s) listed as argument	
current line			to the syntactic list. • Each list starts with a syntactic symbol with zero or several reference positions.	
			With universal argument, inserts the analysis as a comment on that line.	
Guess the style used in the current buffer,	M-x c-guess-buffer- no-install	(c-guess-buffer-no-install &optional ACCUMULATE)	Guess the style on the whole current buffer; don't install it. • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the	
do not install it		,	previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of the code in the buffer	M-x c-guess-buffer	(c-guess-buffer &optional ACCUMULATE)	Guess the style on the whole current buffer, and install it. • The style is given a name based on the file's absolute file name.	
oodo iii die builei		THOO GIVING LATELY	If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the	
0		/ 0 1: 1	previous guess is extended, otherwise a new guess is made from scratch.	
Guess style in the region	M-x c-guess	(c-guess &optional ACCUMULATE)	Guess the style in the region up to 'c-guess-region-max', and install it. • The style is given a name based on the file's absolute file name.	
			If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of a	M-x c-guess-region	(c-guess-region START	Guess the style on the region and install it.	
region	n o guess-region	END &optional	The style is given a name based on the file's absolute file name.	
		ACCUMULATE)	 If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch. 	
View Guessed style	M-x c-guess-view	(c-guess-view &optional	Emit emacs lisp code which defines the last guessed style, so you can put the code	
		WITH-NAME)	into .emacs if you prefer the guessed code. • "STYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is	
			given, it is used instead. WITH-NAME is expected as a string but if this function called	
Dotormino ourstastis	M m a arrang lands	(o guess basis sumtan)	interactively with prefix argument, the value for WITH-NAME is asked to the user.	
Determine syntactic context of current	M-x c-guess-basic- syntax	(c-guess-basic-syntax)	Determine the syntactic context of the current line. It returns the same information that c-show-syntactic-information shows.	
line.	T. ()			
CC Mode support Behaviour control			e the behaviour of important keys such as the return key, delete key, semi-colon, etc ch controls what happens when electric characters are typed (when the electric mode is	
Deliaviour control	activated) and provide a better	r experience when editing C so	urce code.	
		in the mode line: £ C{} when gramming language name: C, C		
	C is the C comment st	yle: '*' for block command ((/* */) and '/' for line comments (//)	
	{} are the other elect'1' for electric mode			
	'a' for auto-newline	mode		
	'h' for hungry mode'w' for subword mod			
Toggle Electric state	• C-c C-1	(c-toggle-electric-state	Toggle the electric indentation feature done with the electric character keys.	
	• <f12> M-e • <m-f12> M-e</m-f12></f12>	&optional ARG)	Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off when negative, and just toggles it when zero or left out.	
Set indentation style	• C-c .	(c-set-style STYLENAME	Set the bracket/indentation style for the current buffer.	
Set muentation style	• C-C . • <f12> M-s</f12>	&optional DONT-OVERRIDE)	Prompts for the name.	
	• <m-f12> M-s</m-f12>		Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Toggle syntactic indentation	• <f12> M-i • <m-f12> M-i</m-f12></f12>	(c-toggle-syntactic- indentation &optional ARG)	 Toggle syntactic indentation. Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out. When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable. When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.
Toggle Comment Style	• C-c C-k • <f12> M-; • <m-f12> M-;</m-f12></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block and line comments. Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out. The C++ style // comments (also called line comments) are compatible with C since C-99. This is part of CC Mode. Use < £12> M-? to display the current state.
Toggle Hungry Delete mode	• <f12> M-DEL • <m-f12> M-DEL</m-f12></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affects and C-d keys. Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out. When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop. This is part of CC Mode. Use <f12> M-? to display the current state.</f12>
Toggle text alignment on pel-newline-and-indent-below See also: • <u>∑ Align</u> • <u>∑ Indentation</u>	<f11> M-RET</f11>	(pel-toggle-newline- indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. Lighter than the current block: the comments, the assignments. Lighter than the current block: the comments, the assignments. Lighter than the current block: the comments, the current block: the comments, the assignments. Lighter than the current block: the comments align is automatically activated (set to t) by adding the major mode to the list in the pel-modes-activating-align-on-return user option. This affects the behaviour of the following commands: Pel-cc-newline (assigned to RET in CC modes like c-mode, c++-mode and d-mode). Pel-newline-and-indent-below (assigned the M-RET)
Toggle auto-newline insertion mode	• C-c C-a • <f12> M-RET • <m-f12> M-RET</m-f12></f12>	(c-toggle-auto-newline &optional ARG)	Toggle <u>auto-newline</u> feature. Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out. Turning on auto-newline automatically enables <i>electric indentation</i> . When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.
Change RET key behaviour: select return mode.	• <f12> RET • <m-f12> RET</m-f12></f12>	(pel-cc-change-newline-mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are: • context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument. • newline-and-indent: uses (newline ARG t) to insert newline and indent. • just-newline-no-indent: uses (electric-indent-just-newline ARG) Femacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode. PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.
Display current Mode settings	• <f12> M-? • <m-f12> M-?</m-f12></f12>	(pel-cc-mode-info)	Display information about current <u>CC mode</u> derivative for the current c-mode buffer. The information includes the information described in the following row.
	M-s). The Emacs the c-def that is used to set the style of that is used to set the style of that is used to set the style of the style currently used for create your own. The exam set-style command (C-c.) Choole of the style	ault-style user option defines for c-mode. Use <f12> <f2: "bsd"="" (';'="" (toggle="" <f12="" active="" alignment.="" and="" below="" bracket="" c-togg,="" change="" characters="" characters.="" done="" force="" hange="" indentation="" is="" it="" line="" mode="" next="" off="" on="" or="" pel-cc-change-nev="" pers="" ple="" positic="" resyntactic="" see="" sent="" shows="" some="" that="" what="" when="" where="" with="" wrap=""> M-s). If yeverything, including the numentation and other settings from yellen ame for it. Its C-style (/* */) and C++-s amically for the current buffer yellen and C-d. Toggle the context-newline active on: #*/() {}:; on some some specific in the context-newline active on: #*/() {}:; on some specific in the context-newline setting syntactic is some specific in the specific syntam syntactic is some specific syntam syntactic is some specific syntam syntactic is specific syntam synt</f2:></f12>	pel-toggle-indent-align (<f11> M-RET). gle-electric-state (C-c C-1 or <f12> M-e): ster(s) exhibit electric behaviour. e other based on style) is active. Toggle this with c-toggle-auto-newline (C-c C-a or <f12> M-e) when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET. by the user options pel-c-tab-width and pel-c-use-tabs. In a c-mode buffer use <f12> <f2> em. ntation. It controls the spacing used in some commands moving point to the next tab stop line. is active. oning (they should have the same value). Emacs identifies several built-in styles but you can another name for the Allman style. You can dynamically change for the current buffer with c- timber of indentation columns. PEL configures the style from the requested pel-c-bracket-style mithe PEL user option requested. This allows you to slightly modify an existing style without style (//) comments since both are now accepted in C since C99. with the c-toggle-comment-style command (C-c C-k or <f12> M-;). C comment cond one is used on a comment continuation line the remainder of the comment continuation his for the current buffer with c-toggle-hungry-state (<f12> M-DEL). C/*1a WK Fly 2 Anzu Abbrev)</f12></f12></f2></f12></f11></f12></f12></f11>
Electric Keys	The following electric C char	racters have special meaning v	when the electrical state is active in a buffer using c-mode. toggle-electric-state (C-c C-1 or <f12> M-e).</f12>
	#	(c-electric-pound ARG)	Insert a "#". • If 'c-electric-flag' is set, handle it specially according to the variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is supplied, or if point is inside a literal or a macro, nothing special happens.

<u>Description</u>	<u>Keystroke</u>	Function	Note
	• ((c-electric-paren ARG)	Insert a parenthesis. Insert a parenthesis. If 'c-syntactic-indentation' and 'c-electric-flag' are both non-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside a literal. Whitespace between a function name and the parenthesis may get added or removed; see the variable 'c-cleanup-list'. Also, if 'c-electric-flag' and 'c-auto-newline' are both non-nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.
	• {	(c-electric-brace ARG)	Insert a brace. If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings in 'c-hanging-bracesalist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.
	:	(c-electric-colon ARG)	Insert a colon. If 'c-electric-flag' is non-nil, the colon is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the colon based on the settings in 'c-hanging-colons-alist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, whitespace between two colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
	• ;	(c-electric-semi, ARG)	Insert a comma or semicolon. If 'c-electric-flag' is non-nil, point isn't inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) When the auto-newline feature is turned on (indicated by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-semi&comma-criteria' for how newline insertion is determined. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, a comma following a brace list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-cleanup-list'.
Insert New Line(s)	active the point also moves to With PEL the default behavi command (bound to <f12> The pel-cc-newline comman</f12>	the proper indentation accordi our can be selected by custom M-RET) see the CC-Mode belnd also aligns comments and a	lode electric mode is active or not. When it is not active it simply inserts a new line. When it is not not to the syntactic context. The following commands can also be used. It is not active it simply inserts a new line. When it is not active it simply inserts a new line. The content is not active it simply inserts a new line in the new line in the new line. The content is not
Insert a new line and operate according to the currently active selected return mode. With PEL, modify behaviour with <f12></f12>	RET	(pel-cc-newline &optional N)	Insert a newline and perhaps align. • With argument N repeat N times. • For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below): • c-context-line-break (PEL default for RET) • newline (Emacs default for RET) • electric-indent-just-newline
M-RET.	When point is outside which case the new lin When point is inside the The end of the cpp din When point is inside a variables for details). When point is inside a	e is indented as the previous r ne content of a preprocessor di ective doesn't count as inside comment, continue it with the The end of a C++-style line cor string, only insert a backslash	newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in ion-empty line instead. rective, a line continuation backslash is inserted before the line break and aligned appropriately. it. appropriate comment prefix (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' nament doesn't count as inside it. when it is also inside a preprocessor directive.
	With ARG, insert that r If option 'use-hard-nev If 'electric-indent-mod To just insert a newl Calls 'auto-fill-functior	many newlines. wlines' is non-nil, the newline is e' is enabled, this indents the f ine, use M-x electric-indent-jus ' if the current column number	is greater than the value of 'fill-column' and ARG is nil.
	Use: (electric-indent-just • With ARG, insert that r		ewline, without any auto-indentation.
Insert an indented line below unbroken current line See also: > Indentation	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent-below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line. For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. You can toggle this on/off with <f11> M-RET. Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	C-j	(electric-newline-and-maybe-indent)	Insert a newline. In 'electric-indent-mode' is enabled, that's that, but if it is 'disabled' then additionally indent according to major mode. Indentation is done using the value of 'indent-line-function'. In programming language modes, this is the same as TAB. In some text modes, where TAB inserts a tab, this command indents to the column specified by the function 'current-left-margin'.
Open New Line in Context See also: • <u>New Whitespace</u>	C-0	(c-context-open-line)	Insert a line break suitable to the context and leave point before it. • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details. Sometimes Normally C-o is bound to open-line. PEL rebinds it to c-context-open-line for the CC modes. If you want to open the line without indenting the next use open-line via <fi>C-o</fi>
Open new line	• <f12> C-o • <m-f12> C-o</m-f12></f12>	(open-line N)	Insert a newline and leave point before it. If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank. With arg N, insert N newlines.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
<u>C Comments</u>	2 more characters have electri C supports 2 types of comm	ic behaviour: / and * to help sup	oport comments in C.
	• '*': Block Comments • '/': Line Comments (: /* comment	*/ to end of line (available since C-99)
Comment characters, wrapping long comment lines	/	(c-electric-slash ARG)	Insert a slash character. • If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'. • Indent the line as a comment, if: 1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or 2. The slash is part of a "*/" token that closes a block oriented comment. • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-spectric floo' is all indeptrices in inside a literal.
See also: Filling/Justification	*	(c-electric-star ARG)	electric-flag' is nil, indentation is inhibited. Insert a star character. If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment. If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited. With this key being electric it becomes easy to type the following two styles of multi-line block comment: /* Two star ** continuation
			** prefix for ** multi-line ** C comment. // Single star * prefix for * multi-line * C comment. */ * When typing the '*' at the beginning of the line, it indents automatically. If another '*' is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.
			• When auto-fill-mode is active, when you type a comment that would be longer than the line, the line is wrapped and the comment continuation string used is automatically inserted. (toggle it with <f11> RET)</f11>
Comment/un-comment	M-;	(comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer. • When no marked region and no comment: • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line. • On line with code: insert comment starter after the code for an end-of-line comment • With marked un-commented region: • Comment region (each line is commented) • With marked commented region: • removes the comment. Call the comment command you want (Do What I Mean). • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'. • You can toggle between C-style /* */ and C++ style // comments (compatible with C since C-99) <fi>12> M-;</fi>
	C-e C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. With just C-u prefix arg, uncomment each line in region BEG END. Numeric prefix ARG means use ARG comment characters. If ARG is negative, delete that many comment characters instead. The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better.
Fill current paragraph See also: Filling/Justification	• M-q • <f12> F • <m-f12> F</m-f12></f12>	(c-fill-paragraph & optional ARG)	Like <f11> t f p but handles // and /* */ style comments. • If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details). • If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following: char description[] = "\</f11>
			A very long description of something that you want to fill to make nicely formatted output."; If point is in any other situation, i.e. in normal code, do nothing. Optional prefix ARG means justify paragraph as well.
Toggle subword- mode See also: Text Modes	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hide/Show comments See also: • <u>S</u> Comments	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-commt.el package (see S Comments). • PEL activates it when the pel-use-hide-commt user option is t.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Hungry Deletion of Whitespace	PEL provides the converted in modes compatible with the simple DEL and C When the Hungry Delete The Hungry Mode also as mode is activated (and the In modes derived from C other modes. PEL provi	nient keys with the <f11> prefine CC Mode (e.g. for C, C++, E-d, to perform hungry deletion Mode is on, the mode-line disperivates the key prefixes below that can only be done in modes C Mode you can also activate des the <f12> M-DEL key for the CC Mode you can also activate and the control of the control</f12></f11>	ngry whitespace deletion" that can also be used in every mode. fix keys for those 2 commands, available in all modes. O, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour s. That's not currently supported in other modes. olays a 'h' to the right of the '//l' indication of electric mode. that start with C-c. They are listed but remember they are only available once the Hungry state that are CC Mode compatible). the hungry state to make standard delete commands delete hungrily, but that does not work for or those modes (like C). the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12>
Delete preceding char or all preceding whitespace. See also: Cut & Paste	• C-c DEL • C-c ☒ • C-c C-☒ • C-c <c-backspace> • C-c C-DEL • <f11> ☒</f11></c-backspace>	(c-hungry-delete- backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character. In terminal mode, even though C-⟨Z⟩, ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. With PEL, the ⟨f11⟩ ⟨Z⟩ binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.
Delete next char or all following whitespace. See also: Cut & Paste	• C-c C-d • C-c 🖄 • C-c C-\overline{\times} • C-c <c-delete> • <f11> \overline{\times}</f11></c-delete>	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character. In terminal mode, even though $C-\boxtimes$ and $$ are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. With PEL, the \boxtimes binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.
Indentation	behaviour control section above You can also explicitly requested. The first set of commands process.	ve. indentation using the commar perform syntactic indentations	
Indent current line or region See also: Indentation	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line. • Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <f12> M-i key): • With syntactic-indentation on (the default): • In Transient Mark mode, when the region is active, reindent the region. • Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line. • Otherwise reindent just the current line. • This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked. • With syntactic-indentation off: • <tab> always indent current line by one level • C-u - <tab> or M- <tab> always un-indent current line by one level • Indenting marked region is done without syntax knowledge and at the same level as previous line. • If you want to indent rigidly you can use: • pel-indent-rigidly, bound to C-x <tab> and to <f11> <tab> <tab> <tab> to indent the line or region rigidly. • tab-to-tab-stop, bound to M-i to insert spaces to the next tab stop column.</tab></tab></tab></f11></tab></tab></tab></tab></tab></f12>
Indent lines of list after point See also: <u> Indentation</u>	C-M-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it. • A prefix argument (C - u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	Emacs provides the following	command to indent without rec	gards to semantics. More information on indentation is available in the <u>Nation</u> table.
Insert spaces or tabs to next defined tabstop column See also: Indentation	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column. The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer. With PEL, the indentation is controlled by the value of pel-c-tab-width because PEL sets the value of tab-width in c-mode buffers to the value of pel-c-tab-width for C buffers.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Indent/Unindent rigidly See also: • » Indentation • » Key-Chords	• C-x <tab> • <fi1> <tab> <tab> <</tab></tab></fi1></tab>	(pel-indent-rigidly &optional N) PEL uses the above instead of the standard:	Indent rigidly the marked region or current line N times. • If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes. • If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): • N = [-1, 0, 1] : operate on current line • N > 1 : operate on the current line and N-1 lines below. • N < -1 : operate on the current line and (abs N) -1 lines above. ★ PEL rebinds this key, but it extends the functionality: pel-indent-rigidly uses indent-rigidly, described below the dashed line. Indent all lines starting in the region. • If called interactively with no prefix argument, activate a transient mode in which the indentation can be adjusted interactively by typing <1eft>, <riqht>, <s-left>, or <s-< td=""></s-<></s-left></riqht>
		(indent-rigidly START END ARG &optional INTERACTIVE)	right>. Both of these commands activate a transient mode where Emacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. The capabilities are controlled by the variable indent-rigidly-map with by default provides: S- <right> indent-rigidly-right-to-tab-stop S-<left> indent-rigidly-left-to-tab-stop indent-rigidly-right indent-rigidly-left Typing any other key deactivates the transient mode. The S-<right> and S-<left> keys indent/de-indent to the next tab-stop position, which is controlled by the tab-width user option. With PEL, the indentation is controlled by the value of pel-c-tab-width. If you use the cua-mode: the cua-mode uses C-x, to invoke this command when cua-mode is active, type it really fast or type C-x C-x <tab> (or use the PEL binding <f11> <tab> <tab <tab="" <tr=""> LeftLeftLeftLeftLeftLeftLeftLeftLeftLeftLeftLeft Which is controlled by the tab-width user option.Left<!--</td--></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></f11></tab></left></right></left></right>
Indent line(s) rigidly See also: • <u>∑ Indentation</u>	• <f6> <tab> • <f11> <tab> c</tab></f11></tab></f6>	(pel-indent-lines &optional N)	Indent current or marked lines by N indentation levels. • Works with point anywhere on the line. • All lines touched by the region are indented. • A special argument N can specify more than one indentation level. It defaults to 1. • If a negative number is specified, 'pel-unindent-lines' is used. • If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. • Use C-g to de-activate the region.
Un-indent line(s) rigidly See also: • <u>∑ Indentation</u>	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	 Un-indent current line or marked lines by N indentation levels. Works with point is anywhere on the line. All lines touched by the region are un-indented. If region was marked, the function does not deactivate it to allow repeated execution of the command. If a region was marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines Use C-g to de-activate the region. Limitation: does not handle hard tabs properly.
Information about C code	There are several Emacs exter	nsion packages that can help w	vriting C code.
Toggle c-eldoc mode	<f12> ? e</f12>	(pel-toggle-c-eldoc-mode)	Toggle c-eldoc mode on/off. • The c-eldoc mode provides the C prototype information in the echo area for the function at point. It currently appears when typing a new function with its arguments inside the code.
	<f11> SPC c ? e</f11>		Requires c-eldoc external package. Activated when pel-use-c-eldoc is set to t. A The extra processing may slow Emacs. This package could be improved into providing the information only on demand but a LSP-based system might be more performant anyway. I am currently looking at this to see if I can improve the performances and the feature set. c-eldoc uses the cpp command to preprocess the buffer content.
Tempo skeletons for C See also: •	PEL creates key bindings to with the same key bindings Several aspects of the Pedited with <f12> <f2> froiton pel-c-skel-module-head pel-c-skel-insert-file-tine pel-c-skel-insert-file-tine pel-c-skel-insert-module-pel-c-skel-insert-module-pel-c-skel-insert-function-sected pel-c-skel-insert-function-sected pel-c-skel-function-sected pel-c-skel-function-defixed pe</f2></f12>	invoke the skeletons in the su for equivalent concepts (such for equivalent concepts) (such for equivalent contents) (such f	ugh the Emacs built-in tempo skeleton mechanism. pported major modes, using the same key prefix sequence for each mode: <f12> <f12>, as file header block) as much as possible. Style is controlled by the user options inside the pel-c-code-style group. This group can be the following options: ing a user-define module-header comment block. mat of C-style continuation comments. automatically updated timestamp is inserted in the file header block. buts use horizontal separator lines. cumentation markup supported by the templates. Currently 'none' and 'Doxygen' are available. template inserts documentation sections in the comment block documenting the C file. to of the module sections inserted when pel-c-skel-insert-module-sections is t. autotion templates are inserted in the function description comment. The office of the C function templates sections inserted when pel-c-skel-insert-function-sections is t. action comment block style. Several styles are provided:</f12></f12>

Description	<u>Keystroke</u>	Function	<u>Note</u>
Insert a file header	<f12> <f12> h</f12></f12>	(pel-c-file-header)	Insert a large file header the includes sections controlled by the user options in the pel-c-code-
comment block			 style customization group and some aspects of the C style currently active. Prompts for file purpose and insert a complete file header block with the file name, its purpose, automatically updated timestamp if required by customization, license text if required by customization. If the file is a C header, inserts a safe and portable C pre-processor #include guard statement that uses a symbol made out of the file base name and an automatically generated UUID string. This eliminates possibility of include header file clash. It is inserted when activated by customization (default is on). If the file is a C source code file, it inserts a set of code section blocks when activated by customization, potentially separated by horizontal separator lines. The blocks identify the code location of header file inclusion, local type, local variables, code, etc Automatically activates the PEL tempo skeleton mode so you can move to the target points where extra text must be entered to complete the template. Use C-g to cancel at any prompt. See some examples in the PEL manual.
Insert a function definition with comment block	<f12> <f12> f</f12></f12>	(pel-c-function)	 Insert a C function definition code and comment template. The command prompts for the function name and its purpose. You can hit return both prompts to specify no text; in that case a tempo skeleton marker is left at the location where the text must be inserted and point is left at the first one. If you enter a function name, it must be a valid C function name (as far as the syntax is concerned). However leading and trailing whitespace is accepted and trimmed and dash characters ('-') are automatically replaced by underscores ('_') for convenience. If an invalid name is specified it is erased and you are prompted again. Use M-p to bring the old value back. Prompts for function and purpose maintain separate histories. Use M-p and M-n to navigate in the histories at the prompt. You can also use the <up> and <down> keys.</down></up> The style of the code inserted is controlled by the user options inside the pel-c-code-style
			group and the various C style element controls of the CC-mode. • Use C-g to cancel at any prompt.
Insert #define	<f12> <f12> d</f12></f12>	(pel-c-define)	See some examples in the PEL manual. Insert a C pre-processor #define statement. If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line, even if there is text after point (to allow inserting it before the name of the symbol to define).
Insert #include <.h>	<f12> <f12> i</f12></f12>	(pel-c-include-lib)	Insert a C pre-processor #include <> statement to include a library file. If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. If there is text after point, insert a new line to place that text on the next line. The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c . move point there).
Insert #include ".h"	<f12> <f12> I</f12></f12>	(pel-c-include-local)	Insert a C pre-processor #include "" statement to include a local file. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. • If there is text after point, insert a new line to place that text on the next line. • The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c · move point there).
Toggle pel-tempo- mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-rst commands, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.
Tempo Template Tag Insertion	<f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit <f12> <f12> <f12> <f12>. A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template. • All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. • If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed. • Since only one template is available in emac-lisp-mode, the usefulness of this command is limited here.</f12></f12></f12></f12></f12></f12>
Inserting code	Extra text insertion can be don	ne with the following command	S.
Insert Parentheses	м- ((insert-parentheses &optional ARG)	For C: insert a parenthesis pair '()', leaving point after open-paren. • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. • A negative ARG encloses the preceding ARG sexps instead. • No argument is equivalent to zero: just insert '()' and leave point between. • PEL makes 'parens-require-spaces' buffer local and set it to nil in C mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. • If region is active, insert enclosing characters at region boundaries. • This command assumes point is not in a string or comment.
Marking	Emacs provides the following	command to quickly mark the	whole content of the current function. More mark commands exists, see the <u>Narking</u> table.
Mark the complete function body See also: Marking	C-M-h	(c-mark-function)	Mark complete function. Put mark at end of the current top-level declaration or macro, point at beginning. If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function. A mark is left where the command started, unless the region is already active (in Transient Mark mode). As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a brace block.
Getting Syntactic Information	Use the following commands t	o extract syntactic information	from the source code.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it. With a prefix arg, push the name onto the kill ring too.
Search Support			case is often used. Using superword-mode helps searching. change this use the <f11> t <f2> to access the customize buffer.</f2></f11>
Toggle superword- mode See also: • ∑ Text Modes • ∑ Search/Replace	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats snake_case as one word. In C '_' are treated as part of words. • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.
Highlighting blocks	show-paren-mode, which h	ighlights the parens that match	seful modes to highlight blocks of (), {}, and []. es the one before or after point. re highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>Neighlight</u>	• <f11> b h (</f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (),{},[]	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth. • Customize the depth and colours with M-x customize-group rainbow-delimiters
See also: Highlight	• <f11> b h R</f11>		Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t.
Navigation in C	This current list below describ	e the specialized commands or	nly. See the others inside <u>▶ Navigation</u>
By definitions	Move to the definition of funct	ion or type at point. See ∑ Xre	of for more information to activate the various engines that support cross referencing for C code.
Find definition of identifier at point	м	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. If there are more than one match, prompt in the *xref* buffer. To search for a symbol entered manually, type C-u M
See also: Xref Go back to where M	м-,	(xref-pop-marker-stack)	 With dumb-jump this performs a search using ag, ripgrep or git grep if available. Pop back to where M was last invoked.
was last issued	·	, , ,	Marker depth is controlled by the xref-marker-ring-length user option.
By functions By structures	Jump over comments.	unction definition blocks or stru	er closing brace and show-paren-mode is on, the matching parentheses are highlighted.
Forward to start of next top level function or struct	• <f6> n • <f6> <down></down></f6></f6>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function or type definition. • Move point before the function type or the struct or typedef keyword. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ. ⇒ Shift marking is available. □ This command complements what end-of-defun does. • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.
Forward to end of current top-level function or struct.	С-М-е	(c-end-of-defun & optional ARG)	Move forward to the end of a top level declaration. • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to the end of next function or type definition. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡Shift marking is available in graphics mode, not in terminal mode (both keys). ⚠ This command moves to the end of the next top-level function. It skips the nested functions.
Backward to beginning of current top-level function or	С-М-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a function or type definition. With a positive argument, move backward that many functions or structures. A negative argument -N means move forward to the Nth following beginning.
struct	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of function or type definition. • Move point before the function type or the struct or typedef keyword. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ➡Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p handles Shift-marking fine in terminal mode. ⚠ This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions that are more deeply nested.</f6></home>
Backward to end of previous top level function or struct	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function or type definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−`. Shift marking is available. ☐ This command complements this set of 4 commands. ⚠ In some cases it fails to detect the end of the previous block and fails. ☐ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □
By blocks	Move across C statements	and C scope blocks, or any gro	oup of (), [], {} or <> blocks.
By List element	Move to the end or the be	eginning of a block	
Backward block/list	С-М-р	(backward-list &optional	Move backward across one balanced group of parentheses.
See also: <u>Navigation</u>		ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move forward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-p : Shift marking is available in graphics mode, not in terminal mode.

See also: • C-[C-b • Esc C-b • C-M-b	<u>Note</u>	
• Esc C- <left> ! C-M-<left> : F Snift marking</left></left>	nced expression (sexp). s. Negative arg -N means move forward across N balanced sumes point is not in a string or comment. g is available in graphics mode, not in terminal mode. g works with this command.	
windmove-on-esc-cursor use ❖ C-M- <left> does not work o ③ Several Linux distros map C-I</left>	The Esc C- <left> binding you must ensure that peler option is set to nil, otherwise it does something else. In Windows, but H-<left> works. M-<left> to desktop workspace operation. In that case anding or change Linux key binding in Systems->settingsit from using that key sequence.</left></left></left>	
See also: Navigation language mode. With ARG, do it that many time Negative arg -N means move b This command assumes point i	n other parentheses-like expressions defined by the current as. sackward across N groups of parentheses.	
Move block forward See also:	ed expression (sexp). s. Negative arg -N means move backward across N balanced ssumes point is not in a string or comment. ng is available in graphics mode, not in terminal mode.	
>keyboard->shortcuts to prevent		
See also:	n other parentheses-like expressions defined by the current of this that many times. A negative argument means move spot. See Esc C- <up> binding you must ensure that peleval option is set to nil. So available in graphics mode, not in terminal mode. Servorks with this command.</up>	
SYNTAX-CROSSING) language mode.	parentheses or nested blocks. In other parentheses-like expressions defined by the current mes. A negative argument means move backward but still to a	
See also: • C-[C-d • Esc C-d • Esc C-d • Language mode. • With ARG, do this that many tirdown a level. • This command assumes point in the windmove-on-esc-cursor uses.	n other parentheses-like expressions defined by the current mes. A negative argument means move backward but still go is not in a string or comment. See Esc C- <down> binding you must ensure that peler option is set to nil. If g is available in graphics mode, not in terminal mode. If g works with this command.</down>	
By statements Move to beginning /end of statement of comment sentence.	Move to beginning /end of statement of comment sentence.	
one, moving into nested blocks		
(use C-M-f to skip over a blo	1 statements. next statement if already at end, and move into nested blocks	
Emacs supports navigation through C preprocessor conditional statements, allow expansion of would not be executed with the Hide-ifdef mode. There are also external packages that provide external packages are listed below. They can be used for editing C and C++ source code. PEL provides a key hydra to help navigate trough preprocessor directives and to hide/show code.	e extra support. All commands provided by Emacs and	
* The key sequences that start with <f12> <f7> open the pel-∑c-preproc Hydra allowing f the <u>hydra</u> external package PEL activates when the pel-use-hydra user option is set to</f7></f12>	further hydra keys to be typed without any prefix. Pequires t.	
-UUU:**F1 a_c_file.c All (4,0) (C/*la Ifdef WK C preprocessor:		
Open the C preprocessor hydra Move to Hide # Vars Other	w state	
Open the C Move to Hide # Vars Other	cel	
Open the C preprocessor hydra with <f12> <f7> followed by on of the hydra keys: C-p: begin R: toggle RO u: undef </f7></f12>		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Move to next	• <f12> # n</f12>	(pel-pp-next-directive)	Move point to next preprocessor directive.
preprocessor directive	* <f12> <f7> n</f7></f12>		
Move up in the pre- processor conditional block	• C-c C-u * <f12> <f7> C-u</f7></f12>	(c-up-conditional COUNT)	Move back to the containing preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. "#elif" is treated like "#else" followed by "#if", so the function stops at them when going backward, but not when going forward.
Move to the previous pre-processor conditional block	• C-c C-p * <f12> <f7> C-p</f7></f12>	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move back across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward across a preprocessor conditional.
Move to the next pre- processor conditional block	C-c C-n * <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move forward across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move backward across a preprocessor conditional. If there aren't enough conditionals after (or before) point, an error is signaled. "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed when tracking subconditionals.
Expand Pre- Processor	• C-c C-e • <f12> # # • <m-12> # #</m-12></f12>	(c-macro-expand START END SUBST)	Expand C macros in the region, using the C preprocessor. Normally display output in temp buffer, but prefix arg means replace the region with it.
	Customizations: 'c-macro- If the user option 'c-macro- cppflags'.		preprocessor to use. t for arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-
Insert/align or delete end-of-line backslash	C-c C-\	(c-backslash-region FROM TO DELETE-FLAG &optional LINE-MODE)	Insert, align, or delete end-of-line backslashes on the lines in the region. With no argument, inserts backslashes and aligns existing backslashes. With an argument, deletes the backslashes.
		fy blank lines at the start of the of the previous line is deleted.	region. If the region ends at the start of a line and the macro doesn't continue below it, the
	You can put the region around	nd an entire macro definition a	nd use this command to conveniently insert and align the necessary backslashes. ling to: 'c-backslash-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'.
Show state	• <f12> # ?</f12>	(pel-pp-show-state)	Show state of C preprocessor control modes.
preprocessor modes Hide-ifdef Mode	* <f12> <f7> ?</f7></f12>	portion of the C preprocessor	blocks
	ifdef environment: the hide-ifdef-env association list Emacs variable (use <f1> v to see the content of these variables. See</f1>		
Toggle the Hide-Ifdef mode	• <f12> M-# • <m-f12> M-# * <f12> <f7> # • <f11> SPC c M-#</f11></f7></f12></m-f12></f12>	(hide-ifdef-mode &optional ARG)	Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode). With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise. Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When
		4	enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
Toggle read-only mode when text is hidden	• C-c @ C-q • <f12> # r * <f12> <f7> R</f7></f12></f12>	(hide-ifdef-toggle-read- only)	 Toggle read-only: toggle 'hide-ifdef-read-only'. Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w * <f12> <f7> W</f7></f12></f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H * <f12> <f7> H • <f11> SPC c # H</f11></f7></f12></m-f12></f12>	(hide-ifdefs &optional NOMSG)	Hide the contents of some #ifdefs. Assume that defined symbols have been added to 'hide-ifdef-env'. The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined. With prefix command presents it will also hide the #ifdefs themselves. Turn off hiding by calling 'show-ifdefs'.
Restore all hidden into view	• C-c @ s • <f12> # S * <f12> <f7> S</f7></f12></f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h * <f12> <f7> h</f7></f12></f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor. • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s * <f12> <f7> s</f7></f12></f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d * <f12> <f7> d</f7></f12></f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'. This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u * <f12> <f7> u</f7></f12></f12>	(hide-ifdef-undef START END)	Undefine a VAR so that #ifdef VAR would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D * <f12> <f7> D</f7></f12></f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable. The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Use a named symbol environment list	• C-c @ U • <f12> # U * <f12> <f7> U</f7></f12></f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Clear the complete list of #define'd symbols inside 'hide- ifdef-env'	• C-c @ C • <f12> # C * <f12> <f7> C</f7></f12></f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'. • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
Evaluate pre- processor macro	• C-c @ e • <f12> # e * <f12> <f7> e</f7></f12></f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region. If no region active, find the current #ifdefs and evaluate the result. Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments		used to create images from spe sscribe UML diagrams or finite-	scific markup code embedded inside C source code comments. This can be useful when using state machines for example.
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render-commented-plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. Use region if identified otherwise use PlantUML block at point. Uses prefix (as PREFIX) to choose where to display it: 4 (when prefixing the command with C-u) -> new window 16 (when prefixing the command with C-u C-u) -> new frame. else -> new buffer This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment. Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.
Preview diagram created from Graphviz DOT markup embedded in comments See also: M Graphviz Dot	<f12> G</f12>	(pel-render-commented- graphviz-dot &optional POS)	Render the Graphviz-Dot markup embedded in current mode comment. Search at POS if specified, otherwise search around point. Use region if identified otherwise use Graphviz-Dot block. The graphviz DOT code must be located within a block delimited by the following special keywords (that are also in comments): @start-gdot @end-gdot The current implementation leaves the created image file in a temporary directory. You will probably want to move that file or delete it, otherwise the size of this directory will increase with each of these created files. The file names use the pel-gdot- prefix. Requires the graphviz-dot-mode package external package, activated by pel-use-graphviz-dot user option set to t.

Emacs & C - References

Document	Notes
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
company-mode ; Modular in-buffer completion framework for Emacs	