Programming Language Support — C++

Description			Iguage Support — C++
Description Editing C++ Files	Keystroke Emacs supports C++ natively	Function via the built-in c++-mode.	<u>Note</u>
Editing C++ Files • CC Mode	This package extends the Ema		which supports the <u>curly-bracket programming languages</u> like C++.
File extensions		eader files: .h, .hh, .HH	, .hpp, .hxx, .h++, .ii, .inl The .inl is added by PEL.
• <u>∑ Speedbar</u>	When pel-use-speedbar is		file is analyzed to distinguish between C and C++ and activate the appropriate major mode. ecognized by speedbar, otherwise only the main ones are recognized.
. V Customins			by the CC Mode are customizable with PEL user option variables.
<u>Sustomize</u> indentation		++: Simplifies editing C++ cod	e configuration. (To change, use pel-cfg-pkg-c++ with <f12> <f2></f2></f12>), see below).
	 pel-c++-indent-width 	: Identifies the number of colur	nns used for indentation. Defaults to 3.
	-		This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i b> will indent to a column that is a multiple of 3.
using tabs			e width of your needed indentation level. This way you can use commands that use either to
bracket style	control the indentati • pel-c++-use-tabs: Wh		dentation or not: t: tabs are used, nil: only spaces are used. Default: nil.
auto newline		The <u>bracket/indentation style</u> de). Default to "stroustrup".	supported by the electric keys. One of the <u>values supported by Emacs</u> (also possible to define
	Emacs customization gro	up: pel-pkg-for-cc. Applies to	o all CC Mode related modes (like c-mode). ode is active on all CC Mode (including c-mode).
	The values for those user optic	on variables can also be stored	inside directory local files and even as file local variables. You can also modify them for each
	the value for the current buffer		ted in the following set of rows. None of the commands below change PEL default; they change
	-		ixes: <f11> SPC C, <f12> and <m-f12> are only available in c++-mode buffers.</m-f12></f12></f11>
	The <m-f12> prefix helps</m-f12>	the typing flow when the next	key is a Meta key.
		1> SPC C prefix is normally	
Open this PDF file. See also: <u>∑ Help/Info</u>	<f11> SPC C <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$1 - C++</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's
	<f12> <f1></f1></f12>		the other way around.
<u>∑ Customize</u> PEL C++ support	<f11> SPC C <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL C++ support: cpp. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
	<f12> <f2></f2></f12>		
∑ Customize Emacs C++ support	<f11> SPC C <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	 Customize Emacs C++ support: cpp. If OTHER-WINDOW is non-nil (use C-u), display in another window.
	<f12> <f3></f3></f12>		
CC Mode Style Management	You can impose an indentate	ion style by customization.	C/C++ stylistic elements are controlled by the CC Mode and the CC mode variables.
Learn style			t buffer: Emacs provides the following commands to parse the source code and identify the style iables from what it detects in the buffer.
used in current	• Use this to adapt to source	ce code written by others and	want to continue using the same style.
buffer	For the following comman	nds all commands that use a k	ey binding that ends with an upper case letter install the style.
Show/Modify syntactic context	C-c C-o	(c-set-offset SYMBOL OFFSET & optional	Change the value of a syntactic element symbol in 'c-offsets-alist'. • SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that
		IGNORED)	syntactic element. The optional argument is not used.
Show syntactic information for	C-c C-s	(c-show-syntactic- information ARG)	Show syntactic information for current line. • Display the syntactic information list and highlight the reference position(s) listed as argument
current line			to the syntactic list. • Each list starts with a syntactic symbol with zero or several reference positions.
			With universal argument, inserts the analysis as a comment on that line.
Guess the style used in the current buffer,	<f12> <f4> g g</f4></f12>	(c-guess-buffer-no-install &optional ACCUMULATE)	Guess the style on the whole current buffer; don't install it. • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the
do not install it			previous guess is extended, otherwise a new guess is made from scratch.
Guess the style of the code in the buffer and	<f12> <f4> g B</f4></f12>	(c-guess-buffer &optional ACCUMULATE)	Guess the style on the whole current buffer, and install it. • The style is given a name based on the file's absolute file name.
install it.			 If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
Guess style in the	<f12> <f4> g G</f4></f12>	(c-guess &optional	Guess the style using the first 'c-guess-region-max' bytes of the file, and install it.
region and install it.		ACCUMULATE)	 The c-guess-region-max user-option defaults to 50,000 bytes, nil means all buffer. The style is given a name based on the file's absolute file name.
			If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.
Guess the style of a	<f12> <f4> g R</f4></f12>	(c-guess-region START	Guess the style on the region and install it.
region		END &optional ACCUMULATE)	The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the
		,	previous guess is extended, otherwise a new guess is made from scratch.
Set buffer style to guessed style and	<f12> <f4> g I</f4></f12>	(c-guess-install &optional STYLE-NAME)	Install the latest guessed style into the current buffer. • This guessed style is a combination of 'c-guess-guessed-basic-offset', 'c-guess-guessed-
install it.		·	offsets-alist' and 'c-offsets-alist'. • The style is entered into CC Mode's style system by 'c-add-style'. Its name is either STYLE-
			NAME, or a name based on the absolute file name of the file if STYLE-NAME is nil.
View Guessed style as a set of Emacs Lisp	<f12> <f4> g ?</f4></f12>	(c-guess-view &optional WITH-NAME)	Emit emacs lisp code which defines the last guessed style, so you can put the code into .emacs if you prefer the guessed code.
statements		,	"STYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is given, it is used instead. WITH-NAME is expected as a string but if this function called
			interactively with prefix argument, the value for WITH-NAME is asked to the user.
CC Mode support			the behaviour of important keys such as the return key, delete key, semi-colon, etc
Behaviour control	activated) and provide a better	experience when editing C++	source code.
	• CC Mode state displayed i • 3 is the CC mode prog	n the mode line : & C{} wher pramming language name: C, C	
		yle: '*' for block command (/* */) and '/' for line comments (//)
	'1' for electric mode		
	'a' for auto-newline'h' for hungry mode		
	• 'w' for subword mod	le	Use <f12> M-? to display the current state.</f12>
Toggle Electric state	• C-c C-l • <f12> <f4> e</f4></f12>	(c-toggle-electric-state &optional ARG)	Toggle the electric indentation feature done with the electric character keys. • Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off
		,	when negative, and just toggles it when zero or left out.

Description	V	Fr	N :
<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Set indentation style	• C-c . • <f12> <f4> s</f4></f12>	(c-set-style STYLENAME &optional DONT-OVERRIDE)	Set the <u>bracket/indentation style</u> for the current buffer. Prompts for the name. Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.
Override indentation width for current buffer	<f12> <f4> TAB</f4></f12>	(pel-cc-set-indent-width &optional NEW-WIDTH)	Interactively change the Indentation with for current buffer to NEW-WIDTH. • Prompt for new value. • Use 0 to restore value specified by configuration (pel-c++-indent-width). • This can be used to change indentation several times in a file.
Toggle syntactic indentation	<f12> <f4> i</f4></f12>	(c-toggle-syntactic- indentation &optional ARG)	Toggle syntactic indentation. Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out. When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable. When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.
Toggle Comment Style	• C-c C-k • <f12> <f4> M-;</f4></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block (/* */) and line (//) comments. • Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out. • This is part of CC Mode. Use <f12> M-? to display the current state.</f12>
Toggle Hungry Delete mode	<f12> <f4> DEL</f4></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affects and C-d keys. • Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out. • When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop. • This is part of CC Mode. Use <f12> M-? to display the current state.</f12>
Toggle text alignment on pel-newline-and-indent-below See also: ■ ∑ Align ■ ∑ Indentation	<f11> M-RET</f11>	(pel-toggle-newline- indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the major mode to the list in the pel-modes-activating-align-on-return user option. This affects the behaviour of the following commands: pel-cc-newline (assigned to RET in CC modes like c-mode, c++-mode and d-mode). pel-newline-and-indent-below (assigned the M-RET)
Toggle auto-newline insertion mode	• C-c C-a • <f12> <f4> M-RET</f4></f12>	(c-toggle-auto-newline &optional ARG)	Toggle auto-newline feature. Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out. Turning on auto-newline automatically enables electric indentation. When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.
Change RET key behaviour: select return mode.	<f12> <f4> RET</f4></f12>	(pel-cc-change-newline-mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are: • context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument. • newline-and-indent: uses (newline ARG t) to insert newline and indent. • just-newline-no-indent: uses (electric-indent-just-newline ARG) Fermacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode. PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.
Display current Mode settings	 • <f12> <f4> ?</f4></f12> Display information about current CC mode derivative for the current c-mode buffer. The information includes the following: • CC mode style currently active, along with a list of styles associated with current mode. Change it for the current buffer with C-c • or <f12> <f4> s.</f4></f12> The Emacs the c-default-style user option defines associations between major modes and the style to use. PEL provides the pel-c++-backet-style that is used to set the style for c-mode. Use <f12> <f2> from a c-mode buffer to access the customization buffer to change it.</f2></f12> Return key behaviour: • RET (return key) mode. Change with pel-cc-change-newline-mode (<f12> <f4> RET).</f4></f12> • Whether return performs alignment. Change that with pel-toggle-indent-align (<f11> M-RET).</f11> • State of electric C++ characters (toggle it on/off with c-toggle-electric-state (C-c C-1 or <f12> <f4> e):</f4></f12> • whether it is active or not, and when active what character(s) exhibit electric behaviour. • if auto-newline on some characters (';' and some other based on style) is active. Toggle this with C-c C-a or <f12> <f4> M-RET).</f4></f12> • The fill column: the column where force line wrap is done when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET.</f11> • Tab width and whether hard tabs are used. These are set by the user options pel-c++-tab-width and pel-c++-use-tabs. • In a c++-mode buffer use <f12> <f2> to open the appropriate customization buffer to change them.</f2></f12> 		

- 🤘 Remember that tab width does **not** identify the indentation. It controls the spacing used in some commands moving point to the next tab stop column. Indentation is controlled separately. See next line. Indentation width controlled by **c-basic-offset** normally set by **pel-c++-indent-width** in PEL and whether syntactic indentation mode is active. Shows how
- it is set and whether it was override by executing the pel-cc-set-indent-width command for this buffer (use <f12> TAB) for that command.
- The style currently used for indentation and bracket positioning (they should have the same value). Emacs identifies several built-in styles but you can create your own. The example below shows "stroustrup", identifying the Stroustrup C++ style used by C++ designer, Bjarne Stroustrup. You can dynamically change for the current buffer with c-set-style command (C-c . or <f12> <f4> s).
- 6 CC Mode styles identify everything, including the number of indentation columns. PEL configures the style from the requested pel-c++-bracket-style and then updates the indentation and other settings from the PEL user option requested. This allows you to slightly modify an existing style without having to create a new style name for it.

 • The comment style. Supports C-style (/* */) and C++-style (//) comments.
- This can be changed dynamically for the current buffer with the c-toggle-comment-style command (C-c C-k or <f12> <f4> M-;). C comment continuation lines can use 1 or 2 star characters: if a second one is used on a comment continuation line the remainder of the comment continuation lines used two stars, otherwise only one is used.
- Whether hungry delete is used by DEL and C-d. Toggle this for the current buffer with c-toggle-hungry-state (<f12> <f4> DEL).

```
-UU-:----F1 cpp file.cpp All (1,0)
c++-mode state:
- active style : stroustrup. c-
                                                                         (C++//la- WK Anzu Fly 2 Abv) 10:34am 1.65
                         Notice the name of
the PEL user-options
that set the significant
feature controlling
Emacs variables in the
message
                          Indent width : 3
Syntactic indent : on
c-indentation-style : stroustrup
PEL Bracket style : stroustrup
Comment style : Line comments: //
Hungry delete : off, but the F11-☒ and F11-☒ keys are available.
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Electric Keys and Keywords			ing when the electrical state is active in a buffer using c++-mode. toggle-electric-state (C-c C-1 or <f12> <f4> e).</f4></f12>
#	#	(c-electric-pound ARG)	Insert a "#".
	,	dle it specially according to the a literal or a macro, nothing sp	e variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is pecial happens.
()	• ()	(c-electric-paren ARG)	Insert a parenthesis.
	If 'c-syntactic-indentation' a a literal.	and 'c-electric-flag' are both no	n-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside
			may get added or removed; see the variable 'c-cleanup-list'. nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.
{}	• { }	(c-electric-brace ARG)	Insert a brace.
	a) If the auto-newline feat in 'c-hanging-braces-a b) Any auto-newlines are	ture is turned on (indicated by lilist'. indented. The original line is a	and a numeric ARG hasn't been supplied, the command performs several electric actions: "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings also reindented unless 'c-syntactic-indentation' is nil.
	,	cd on, various newline cleanups (c-electric-colon ARG)	s based on the settings of 'c-cleanup-list' are done. Insert a colon.
	a) If the auto-newline feat 'c-hanging-colons-alis' b) Any auto-newlines are	the colon is not inside a literal ture is turned on (indicated by t'. indented. The original line is a	and a numeric ARG hasn't been supplied, the command performs several electric actions: "/la" on the mode line) newlines are inserted before and after the colon based on the settings in also reindented unless 'c-syntactic-indentation' is nil. b colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
:,	• ;	(c-electric-semi,	Insert a comma or semicolon.
	a) When the auto-newline semi&comma-criteria?	point isn't inside a literal and a e feature is turned on (indicated for how newline insertion is de	numeric ARG hasn't been supplied, the command performs several electric actions: d by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-termined. elso reindented unless 'c-syntactic-indentation' is nil.
	c) If auto-newline is turne	ed on, a comma following a bra	ace list or a semicolon following a defun might be cleaned up, depending on 'c-cleanup-list'.
<>	• < >	(c-electric-lt-gt ARG)	If the current language uses angle bracket parens (e.g. template arguments in C++), try to find out if the inserted character is a paren and give it paren syntax if appropriate.
			on-nil, the line will be reindented if the inserted character is a paren or if it finishes a C++ style neric argument is supplied, or the point is inside a literal.
Electric pairs	Type the first of a pair to inse	ert this one and its matching ch	activating the electric-pair-mode in the buffer. naracter for (), [], $\{$, "" and ". line lighter set by the pel-electric-pair-lighter is show. This defaults to $E(1)$
Toggle electric-pair- mode in current buffer	<f11> M-e</f11>	(electric-pair-local-mode & optional ARG)	Toggle automatic parens pairing (Electric Pair mode) and org-mode special pair electric keys only in this buffer.
•			 With a prefix argument ARG, enable Electric Pair mode if ARG is positive, and disable it otherwise.
Lighter:= $\xi(I)$			 Electric Pair mode is a global minor mode. When enabled, typing an open parenthesis automatically inserts the corresponding closing parenthesis, and vice versa. (Likewise for brackets, etc.). If the region is active, the parentheses (brackets, etc.) are inserted around the region instead.
Insert New Line(s)	active the point also moves to With PEL the default behavion command (bound to <f12> The pel-cc-newline comman</f12>	the proper indentation accordi our can be selected by custom M-RET) see the CC-Mode belind also aligns comments and a	lode electric mode is active or not. When it is not active it simply inserts a new line. When it is ing to the syntactic context. The following commands can also be used. nization and modified dynamically for the current buffer with the pel-cc-change-newline-mode naviour control section above. Issignment in the code block if the pel-modes-activating-align-on-return user option list buffer can also be modified by the pel-cc-change-newline-mode command (<f11> M-RET).</f11>
Insert a new line and operate according to the currently active selected return mode. With PEL, modify behaviour with <f12> M-RET.</f12>	RET	(pel-cc-newline &optional N)	Insert a newline and perhaps align. • With argument N repeat N times. • For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below): • c-context-line-break (PEL default for RET) • newline (Emacs default for RET) • electric-indent-just-newline • If the variable 'pel-newline-does-align' is t, then perform the text alignment done by the function 'align'.
	When point is outside which case the new lin When point is inside the the cape dire When point is inside a variables for details).	e is indented as the previous note content of a preprocessor disective doesn't count as inside in comment, continue it with the The end of a C++-style line contents.	newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in non-empty line instead. Irective, a line continuation backslash is inserted before the line break and aligned appropriately.
	Use: (newline &optional A With ARG, insert that r If option 'use-hard-new If 'electric-indent-mod To just insert a newl	RG INTERACTIVE): Insert a ner nany newlines. wlines' is non-nil, the newline is e' is enabled, this indents the f ine, use M-x electric-indent-jus	wline, and move to left margin of the new line if it's blank. s marked with the text-property 'hard'. inal new line that it adds, and reindents the preceding line.
	Use: (electric-indent-just • With ARG, insert that r		ewline, without any auto-indentation.
Insert an indented line below unbroken current line See also: ∑ Indentation	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line. For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. You can toggle this on/off with <f11> M-RET. But ldentify modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	с-ј	(electric-newline-and- maybe-indent)	Insert a newline. If 'electric-indent-mode' is enabled, that's that, but if it is *disabled* then additionally indent according to major mode. Indentation is done using the value of 'indent-line-function'. In programming language modes, this is the same as TAB. In some text modes, where TAB inserts a tab, this command indents to the column specified by the function 'current-left-margin'.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Open New Line in Context See also: • <u>New Whitespace</u>	C-0	(c-context-open-line)	Insert a line break suitable to the context and leave point before it. • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details. • Normally C-o is bound to open-line. PEL rebinds it to c-context-open-line for the CC modes. If you want to open the line without indenting the next use open-line via <f12> C-o</f12>
Open new line	• <f12> C-o • <m-f12> C-o</m-f12></f12>	(open-line N)	Insert a newline and leave point before it. If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank. With arg N, insert N newlines.
C++ Comments		the state of the s	oport comments in C++.
/	/	(c-electric-slash ARG)	Insert a slash character. If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'. Indent the line as a comment, if: 1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or 2. The slash is part of a "*/" token that closes a block oriented comment. If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
*	*	(c-electric-star ARG)	Insert a star character. • If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment. • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited. With this key it becomes easy to type the following two styles of multi-line block comment: /* Two star ** continuation ** prefix for ** multi-line ** C comment. */ /* Single star * prefix for * multi-line * C comment. */ When typing the '*' at the beginning of the line, it indents automatically. If another '*' is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.
Comment/un-comment See also: <u>▼ Comments</u>	M-;	(comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer. • When no marked region and no comment: • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line. • On line with code: insert comment starter after the code for an end-of-line comment • With marked un-commented region: • Comment region (each line is commented) • With marked commented region: • removes the comment • Call the comment command you want (Do What I Mean). • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'. • You can configure 'comment-style' to change the way regions are commented: see <f12> M-; to toggle the comment style.</f12>
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead. • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better.
Fill current paragraph See also: Filling/Justification	• M-q • <f12> F • <m-f12> F • <f11> SPC C F</f11></m-f12></f12>	(c-fill-paragraph &optional ARG)	Like <f11> t f p but handles // and /* */ style comments. • If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details). • If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following: char description[] = "\ A very long description of something that you want to fill to make nicely formatted output."; • If point is in any other situation, i.e. in normal code, do nothing. • Optional prefix ARG means justify paragraph as well.</f11>
Toggle subword-mode See also: ■ Text Modes	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of camelCase and PascalCase as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hide/Show comments See also: <u>Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-commt.el package (see S Comments). • PEL activates it when the pel-use-hide-commt user option is t.

<u>Description</u>	<u>Keystroke</u>	Function	Note
Hungry Deletion of Whitespace	The CC mode provides two commands that can perform "hungry whitespace deletion" that can also be used in every mode. • Selection PEL provides the convenient keys with the <f11> prefix keys for those 2 commands, available in all modes. • In modes compatible with the CC Mode (e.g. for C, C++, D, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behavior of the simple <pre> • DEL></pre> and C-d, to perform hungry deletions. That's not currently supported in other modes. • When the Hungry Delete Mode is on, the mode-line displays a 'h' to the right of the '//!' indication of electric mode. • The Hungry Mode also activates the key prefixes below that start with C-c. They are listed but remember they are only available once the Hungry star mode is activated (and that can only be done in modes that are CC Mode compatible). • In modes derived from CC Mode you can also activate the hungry state to make standard delete commands delete hungrily, but that does not work for other modes. PEL provides the <f12> M-DEL key for those modes (like C++). • Toggle hurry deletion mode of the DEL and C-d key for the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12></f12></f11>		ix keys for those 2 commands, available in all modes. 1, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour is. That's not currently supported in other modes. 1
Delete preceding char or all preceding whitespace. See also: Total Paste	• C-c DEL • C-c ☒ • C-c C-☒ • C-c <c-backspace> • C-c C-DEL</c-backspace>	(c-hungry-delete- backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character. □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
<u>// Units : 10.00</u>	• <f11> 🗵 🗵 • <f11> DEL DEL</f11></f11>		⊌ With PEL, the <f11> ☑ ☑ binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11>
Delete next char or all following whitespace.	• C-c C-d • C-c ☒ • C-c C-☒	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character. □ In terminal mode, even though C-I and <c-delete> are not available, they are</c-delete>
See also: • <u>S Cut & Paste</u>	• C-c <c-delete> • <f11> 🗵</f11></c-delete>		mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. With PEL, the <f11> binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11>
Indentation	-		Mode logic and provided commands listed below. It the end of this list. They are also listed in the <u>∑ Indentation</u> table.
Indent current line or region See also: • ∑ Indentation	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line. • Behaviour depends on syntactic-indentation mode: on by default, toggled with <f12> M-i • With syntactic-indentation on (the default): • In Transient Mark mode, when the region is active, reindent the region. • Otherwise, with a prefix argument, rigidly reindent the expression starting on current line. • Otherwise reindent just the current line. • Hit <tab> anywhere in the line to adjust the indentation of the line or marked area. • With syntactic-indentation off: • <tab> always indent current line by one level • C-u - <tab> or M- <tab> always un-indent current line by one level • Marked region is indented without syntax knowledge at the same level as previous line. • If you want to indent rigidly you can use: • (pel-indent-rigidly &optional N) (bound to C-x <tab> and to <f11> <tab><tab>) to indent the line or region rigidly. • (tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column.</tab></tab></f11></tab></tab></tab></tab></tab></f12>
Indent lines of list after point See also: • Indentation	С-м-ф	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it. • A prefix argument (C - u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	For most editing scena		pards to semantics. More information on indentation is available in the <u>Nation</u> table. Indentation Indentati
Insert spaces or tabs to next defined tabstop column See also: <u> </u>	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column. The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer. With PEL, the tab-stop interval is controlled by the value of pel-c++-tab-width. PEL sets tab-width to the value of pel-c++-tab-width for each c++-mode buffer.
Indent/Unindent rigidly See also:	• C-x <tab> • <f11> <tab> <tab> • <tab>q</tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	 Indent rigidly the marked region or current line N times. If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes. If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): N = [-1, 0, 1] : operate on current line N > 1 : operate on the current line and N-1 lines below. N < -1 : operate on the current line and (abs N) -1 lines above.
	PEL rebinds this key, but it extends the functionality: pel-indent-rigidly uses the original indent-rigidly. indent-rigidly Indent all lines starting in the region. • If called interactively with no prefix argument, activate a transient mode in which the indentation can be adjusted interactively by typing <left></left>		indent-rigidly uses the original indent-rigidly. e a transient mode in which the indentation can be adjusted interactively by typing <left>, nacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. nap with by default provides: to the next tab-stop position, which is controlled by the tab-width user option. e of pel-c++-tab-width. I for each c++-mode buffer.</left>

<u>Description</u>	<u>Keystroke</u>	Function	Note
Indent line(s) rigidly	• <f6> <tab></tab></f6>	(pel-indent-lines &optional	Indent current or marked lines by N indentation levels controlled by pel-c++-indent-width .
See also:	• <f11> <tab> c</tab></f11>	<u>N</u>)	Works with point anywhere on the line.
• <u>∑ Indentation</u>	 All lines touched by the region are indented. A special argument N can specify more than one indentation level. It defaults to 1. If a negative number is specified, 'pel-unindent-lines' is used. If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left. 		
Un-indent line(s) rigidly	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	 Un-indent current line or marked lines by N indentation levels controlled by pel-c++-indent-width. Works with point is anywhere on the line.
See also: • Nation Indentation	If a region was marked, the in all affected lines. Use Handles presence of hard ta If indent-tabs-mode is no	nction does not deactivate it to function does not deactivate it C-g to de-activate the region. lbs: n-nil the indentation is created, any hard tab in the indentatio	o allow repeated execution of the command. to allow repeated execution of the command. It also modifies the region to include all characters with a mix of hard-tabs and space characters. In of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-
Open file at point	the input completion method of Note that when using the lo	currently used. do completion mode, it is poss	low opening files from the file name taken at point (the cursor location). They work regardless of ible to instruct Ido to use a file name at point as the basis for the file name to open. This Ido er-option. With PEL you can control it globally or locally with <f11> f M</f11>
Open file or web-page whose name is at point	• C-^ • <f11> f . • <m-f11> M-f M</m-f11></f11>	(pel-open-at-point &optional N)	Open the file, library or the URL, named at point, with potential line & column #s. The <u>6v</u> key-chord is available if pel-use-key-chord is non-nil. Command prefixes are supported with the key-chord. See Xey-Chords .
**	• <u>6y</u>		Goniniand preines are supported with the key-chord. See <u>// Rey-chords</u> .
See also: • <u>∑ File mngt</u>		•	e #include statement. The various search methods (see below) support searching inside the y an INCLUDE environment variable or from the directories identified explicitly.
• <u>∑ Key-Chords</u> • <u>M reStructuredText</u> • <u>¾I - C</u>	If embedded space(s) are all	lowed in the filename, then poi	oint. The file name is either surrounded by white space characters or the delimiters listed below. In must be located at the first of the 2 delimiter characters. "`' ()[]{}<> ''" 「」 () 〈) 《》 [] () «» ↔ ••••••••••••••••••••••••••••••••••
• ֆլ - Erlang	 Tab and newline are also delimiter characters. If embedded space in the file name is not allowed, then the file name must also be enclosed in the above delimiters, the space acts as an extra delimiter, and point can be positioned anywhere between the delimiters. If the string identifies a URL, the function opens the page in the systems' default browser. The file name extracted from the file may include glob characters (even though this is not used in a #include "" or #include <> statement but it can be used elsewhere). Otherwise the command attempts to open the file name with the specified name. If that file does not exists it then proceed to search for it. If the file name is followed by line and column numbers the point is moved to that position. 		
Select search method	The command searches for the file to open using the method identified by the pel-c++-file-finder-method user-option, one of the following: • generic: the command searches for a file in the directory tree of the parent root directory. The parent root directory is a directory parent of the current file that holds a project marker file, one of the file identified in the pel-project-root-identifiers user option. Something like .git, .hg, .project or .pel-project by default. • environment variable name: the name of an environment variable (like INCLUDE) that holds a list of directory names to search files in. • explicit lists: two lists of directory names: one list holds the project directory names, the other hold the tool and library directory names. The lists may identify directory names indirectly via environment variables. The \$VARNAME format must be used.		
Select prompt method	When several file names a	re found, the command lists th	em and prompts using the method selected by pel-prompt-read-method user-option.
•	The default is a very prim With ivy selected PEL	itive function implemented by l will automatically set <mark>ಚ pel-u</mark>	PEL. You can select a more powerful ivy prompting instead. se-ivy to t and <u>Ivy mode</u> will be installed automatically when you restart Emacs. scified search method, it does not only use the first one found.
Select target window	 • This allows you to detect potential duplication in header file names in large include paths. • It Prompts for incomplete file names, allowing editing the find file (with completion), search for libraries files (type 1) according to current file type. 		
See function	 Select target window: Without argument: If file is already opened in a window, move point to that window and to the line column coordinates if specified following the file name at point. If no window holds that file, select the target window based on the number of editable windows in frame: if 1, split that window and use the new window, if 2: use the other window, if 3 or more, use the current window. With numeric argument N: N < 0: create a new window and use that. N = 0: use the 'other' (the next) window. N = 1, 3, 7or above (excluding 8, 9 and 10): select the target window based on the number of editable windows in frame: if 1 window: split that window and use the new window, if 2 windows: use the other window. if 3 or more windows: use the current window. 		
docstring for more info.	open a directo N is 10: open the URL	n the system's browser,	

Description	<u>Keystroke</u>	Function	Note
	 PEL creates key bindings to 	invoke the skeletons in the sur	igh the Emacs built-in tempo skeleton mechanism. oported major modes, using the same key prefix sequence for each mode: <f12> <f12>, as file header block) as much as possible.</f12></f12>
	with the same key bindings for equivalent concepts (such as file header block) as much as possible. * Several aspects of the PEL Emacs Lisp Source Code Style is controlled by the user options inside the pel-c++-code-style group. This group can be edited with <f12> <f12> <f2> from a C++ mode buffer and include the following options: * pel-c++-skel-module-header-block-style: allows selecting a user-define module-header comment block. * pel-c++-skel-insert-file-timestamp pel-c++-skel-les-esparators : set whether an automatically updated timestamp is inserted in the file header block. * pel-c++-skel-doo-markup : identifies documentation markup supported by the templates. Not yet implemented. * pel-c++-skel-file-section-titles : identifies documentation section titles inserted in header files. A section titled "." split sections placed befind after the include guard. If not present all sections are placed after the include guard. * pel-c++-skel-function-sections: set whether C++ function templates are inserted in header files. A section titled "." split sections placed befind after the include guard. If not present all sections are placed after the include guard. * pel-c++-skel-function-section-titles: identifies of the C++ function templates sections inserted when pel-c++-skel-insert-function-sections: select the C++ function comment block style. Several styles are provided: * pel-c++-skel-function-name-on-first-column: identifies whether return type is located on the same line as function name or just above. * pel-c++-skel-with-license * pel-c++-skel-with-license * pel-c++-skel-function-name-on-first-column: identifies whether return type is located on the same line as function name or just above. * pel-c++-skel-function-section-titles on place and tempos besides to lace and the same line as function name or just above. * pel-c++-skel-function-section-titles: inserted in header files. A no ption provide ability to insert open source software license is specified. An option provide ability to insert op</f2></f12></f12>		
<u>// </u>	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER-WINDOW)	M-b or some other keys like C-c . and C-c ,. Customize PEL C++ skeleton layout. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
Insert a file header	<f12> <f12> h</f12></f12>	(pel-elisp-file-header)	 In OTHER-WINDOW is non-fill (use C-u), display in another window. Insert a file description block. Distinguish between code files and header files. Prompts for the file purpose. For header files, include guard is inserted if requested by customization. The layout of the entered text is controlled by user options. It is possible to create a user-specified skeleton this command will used instead of the one provided by PEL. See examples of generated code located in the example/templates/cpp repo directory. Access the customization buffer by typing: <f12> <f12> <f2></f2></f12></f12>
Insert a function definition with comment block	<f12> <f12> f</f12></f12>	(pel-c++-function)	 Insert a C++ function definition code and comment template. The command prompts for the function name and its purpose. You can hit return both prompts to specify no text; in that case a tempo skeleton marker is left at the location where the text must be inserted and point is left at the first one. If you enter a function name, it must be a valid C function name (as far as the syntax is concerned). However leading and trailing whitespace is accepted and trimmed and dash characters ('-') are automatically replaced by underscores ('_') for convenience. If an invalid name is specified it is erased and you are prompted again. Use M-p to bring the old value back. Prompts for function and purpose maintain separate histories. Use M-p and M-n to navigate in the histories at the prompt. You can also use the <up>and <down> keys.</down></up> The style of the code inserted is controlled by the user options inside the pel-c++-code-style group and the various C style element controls of the CC-mode. Use C-g to cancel at any prompt.
Insert a class definition	<f12> <f12> c</f12></f12>	(pel-c++-class)	Insert a C++ definition code template. • Prompts for the class name. Replaces dash by underscores. • When pel-c++-has-doc-block is t, prompts for the purpose of the class. Capitalize the first letter and appends a period if there is none. • The layout of the class definition is controlled by the following user-options: • pel-c++-has-doc-block • pel-c++-class-doc-section-titles • pel-c++class-members-sections: this identifies the member sections, their access (public/protected/private) and code/comment lines. The strings may contain the following markers: • \$\$: identify the location of a tempo mark (see the navigation commands below) • \$class-name: replaced by the name of the class.
Insert #define	<f12> <f12> d</f12></f12>	(pel-c-define)	Insert a C pre-processor #define statement. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line, even if there is text after point (to allow inserting it before the name of the symbol to define).
Insert #include <.h>	<f12> <f12> i</f12></f12>	(pel-c-include-lib)	Insert a C pre-processor #include <> statement to include a library file. If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. If there is text after point, insert a new line to place that text on the next line. The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c · move point there).
Insert #include ".h"	<f12> <f12> I</f12></f12>	(pel-c-include-local)	Insert a C pre-processor #include "" statement to include a local file. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. • If there is text after point, insert a new line to place that text on the next line. • The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c • move point there).
Toggle pel-tempo- mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-rst commands, the pel-tempo-mode is automatically activated.
mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Inserting code Insert Parentheses	<f12> <f12> <f12></f12></f12></f12>	(insert-parentheses & optional ARG)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit <f12> <f12> <f12> . A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template. • All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. • If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed. • Since only one template is available in emac-lisp-mode, the usefulness of this command is limited here. For C++: insert a parenthesis pair '()', leaving point after open-paren. • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. • A negative ARG encloses the preceding ARG sexps instead.</f12></f12></f12></f12></f12>
			 No argument is equivalent to zero: just insert '()' and leave point between. PEL makes 'parens-require-spaces' buffer local and set it to nil in C++ mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. If region is active, insert enclosing characters at region boundaries. This command assumes point is not in a string or comment.
Marking	Emacs provides the following	command to quickly mark the	whole content of the current function. More mark commands exists, see the <u>Narking</u> table.
Mark the complete function body See also: Marking	С-м-h	(c-mark-function)	Mark complete function. Put mark at end of the current top-level declaration or macro, point at beginning. If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function. A mark is left where the command started, unless the region is already active (in Transient Mark mode). As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a brace block.
Getting Syntactic	Use the following commands t	to extract syntactic information	from the source code.
Information Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it. With a prefix arg, push the name onto the kill ring too.
Search Support			e case is often used. Using superword-mode helps searching. To change this use the <f11> t <f2> to access the customize buffer.</f2></f11>
Toggle superword- mode	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In C++ '_' are treated as part of words. • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it
See also: • <u>National Text Modes</u> • <u>National See also:</u> • <u>National See also:</u>			 otherwise. PEL provides the <f12> M-p key for the programming language modes where snake case is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Highlighting blocks	show-paren-mode, which hi	ighlights the parens that match	seful modes to highlight blocks of (), {}, and []. es the one before or after point. ire highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>Nationals</u> Highlight	• <f11> h (</f11>	(rainbow-delimiters-mode	Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time. Ulablight parted parentheses breekets and breese with different selections as their parentheses.
Enable/Disable coloured highlight of nested blocks (),{},[]	• <f12> M-r • <m-f12> M-r</m-f12></f12>	&optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth. • Customize the depth and colours with M-x customize-group rainbow-delimiters
See also: <u>∑ Highlight</u>	• <f11> h R</f11>		Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t.
Navigation in C++	This current list below describe	e the specialized commands or	nly. See the others inside <u>Navigation</u>
By definitions	Move to the definition of functi	ion or type at point. See Xre	ef for more information to activate the various engines that support cross referencing for C code.
Find definition of identifier at point	М	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. If there are more than one match, prompt in the *xref* buffer. To search for a symbol entered manually, type C-u M
See also: <u>∑ Xref</u> Go back to where M was last issued	м-,	(xref-pop-marker-stack)	 With dumb-jump this performs a search using ag, ripgrep or git grep if available. Pop back to where M was last invoked. Marker depth is controlled by the xref-marker-ring-length user option.
By functions By structures	Jump over comments.	unction definition blocks or struefore opening brace or right aft	
Forward to start of	<f6> <down></down></f6>	(pel-beginning-of-next-	Move forward to the beginning of the next function or type definition.
next top level function or struct	<f12> <down></down></f12>	defun &optional SILENT DONT-PUSH_MARK)	Move point before the function type or the struct or typedef keyword. Beeps if does not find beginning of next function unless SILENT is non-nil. If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. Move back to previous position with M−ˆ. Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key. This command complements what end-of-defun does. It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.</f12></f6>
Forward to end of current top-level function or struct.	С-М-е	(c-end-of-defun & optional ARG)	Move forward to the end of a top level declaration. • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to the end of next function or type definition. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key.</f12></f6>
	<f12> <right></right></f12>		⚠ This command moves to the end of the next top-level function. It skips nested functions.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Backward to beginning of current top-level function or	С-М-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a function or type definition. With a positive argument, move backward that many functions or structures. A negative argument -N means move forward to the Nth following beginning.
struct	• C-M- <home> • <f6> <up> <f12> <up></up></f12></up></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of function or type definition. • Move point before the function type or the struct or typedef keyword. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ► Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key. ↑ This command moves to the beginning go the next function or of the same nesting level of</f12></f6>
Backward to end of previous top level function or struct	<f6> <left> <f12> <left></left></f12></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	the current location. It skips the functions that are more deeply nested. Move backwards to the end of the previous function or type definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M-`. —Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key.</f12></f6>
			⚠ In some cases it fails to detect the end of the previous block and fails. ₩
By blocks	Move across C statements a	and C scope blocks, or any gro	oup of (), [], {} or < > blocks.
By List element	Move to the end or the be		
Backward block/list See also: Navigation	С-м-р	(backward-list &optional ARG)	Move backward across one balanced group of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do it that many times. • Negative arg -N means move forward across N groups of parentheses. • This command assumes point is not in a string or comment. • C-M-p : ➤ Shift marking is available in graphics mode, not in terminal mode.
Move block backward See also: • Navigation	• C-M-b • C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-b : Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : Shift marking works with this command. • ⚠ With PEL: if you want to use Esc C-<left> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<left> does not work on Windows, but H-<left> works. ⑤ Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</left></left></left></left></left>
Forward block/list	C-M-n	(forward-list &optional	Move forward across one balanced group of parentheses.
See also: Navigation		ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move backward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.
Move block forward See also: ■ Navigation	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : → Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : → Shift marking works with this command. • ⚠ With PEL: if you want to use Esc C-<right> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<right> does not work on Windows, but H-<right> does. ■ Several Linux distros map C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</right></right></right></right></right>
• in/out of blocks	Move in or out of C scope b	locks, or any group of (), [], { }	or <> blocks.
Backward Up/outside sexp hierarchy See also: Mavigation	• C-M-u • C-M- <up> • C-[C-u • Esc C-u • Esc C-<up></up></up>	(backward-up-list &optional ARG ESCAPE- STRINGS NO-SYNTAX- CROSSING)	Move backward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. Mith PEL: if you want to use Esc C- <up> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. C-M-u : ► Shift marking is available in graphics mode, not in terminal mode. C-M-<up> is Shift marking works with this command. C-M-<up> does not work on Windows, but H-<up> does.</up></up></up></up>
Forward Up/outside sexp hierarchy See also: Navigation	C-M-]	(up-list & optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move forward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot.
Down/inside sexp/block See also: • ∑ Navigation	• C-M-d • C-M- <down> • C-[C-d • Esc C-d</down>	(down-list &optional ARG)	Move forward down one level of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do this that many times. A negative argument means move backward but still go down a level. • This command assumes point is not in a string or comment. • ⚠ With PEL: if you want to use Esc C- <down> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. • C-M-d : Shift marking is available in graphics mode, not in terminal mode. • C-M-<down> : Shift marking works with this command. • C-M-<down> does not work on Windows, but H-<down> does.</down></down></down></down>
By statements	Move to beginning /end of stat	ement of comment sentence.	
Go to beginning of statement (backward)	м-а	(c-beginning-of-statement &optional COUNT LIM SENTENCE-FLAG)	Go to the beginning of the innermost statement. • With prefix arg, go back N - 1 statements. • If already at the beginning of a statement then go to the beginning of the closest preceding one, moving into nested blocks if necessary (use C-M-b to skip over a block). • If within or next to a comment or multiline string, move by sentences instead of statements.
Go to the end of statement (forward)	М-е	(c-end-of-statement &optional COUNT LIM SENTENCE-FLAG)	Go to the end of the innermost statement. • With prefix arg, go forward N - 1 statements. • Move forward to the end of the next statement if already at end, and move into nested blocks (use C-M-f to skip over a block). • If within or next to a comment or multiline string, move by sentences instead of statements.

Description	<u>Keystroke</u>	Function	<u>Note</u>
C Preprocessor		e Hide-ifdef mode. There are a	all statements, allow expansion of preprocessor macros, hiding pre-processor statements that also external packages that provide extra support. All commands provided by Emacs and ting C and C++ source code.
Open the C preprocessor hydra with <f12> <f7> followed by on of the hydra keys:</f7></f12>	* The key sequences that st the hydra external packag -UU-:F1 a cpp C preprocessor: Move to Hid	art with <f12> <f7> open the PEL activates when the profile.cpp All (2,0) e</f7></f12>	os Other valuate ?: Show state efine <f7>: cancel</f7>
Navigate across pre- processor conditionals	The following commands move	e point across the #if , #else , #	relif and #endif C pre-processor conditional statements.
Move to previous preprocessor directive	• <f12> # p * <f12> <f7> p</f7></f12></f12>	(pel-pp-prev-directive)	Move point to previous preprocessor directive.
Move to next preprocessor directive	• <f12> # n * <f12> <f7> n</f7></f12></f12>	(pel-pp-next-directive)	Move point to next preprocessor directive.
Move up in the pre- processor conditional block	• C-c C-u * <f12> <f7> C-u</f7></f12>	(c-up-conditional COUNT)	Move back to the containing preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. "#elif" is treated like "#else" followed by "#if", so the function stops at them when going backward, but not when going forward.
Move to the previous pre-processor conditional block	• C-c C-p * <f12> <f7> C-p</f7></f12>	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move back across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward across a preprocessor conditional.
Move to the next pre- processor conditional block	C-c C-n * <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move forward across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move backward across a preprocessor conditional. If there aren't enough conditionals after (or before) point, an error is signaled. "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed when tracking subconditionals.
Expand Pre-Processor	• <f12> # # • <m-12> # #</m-12></f12>	(c-macro-expand START END SUBST)	Expand C macros in the region, using the C preprocessor. Normally display output in temp buffer, but prefix arg means replace the region with it.
	Customizations: 'c-macro- If the user option 'c-macro- cppflags'.		oreprocessor to use. If or arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-
Insert/align or delete end-of-line backslash	C-c C-\	(c-backslash-region FROM TO DELETE-FLAG &optional LINE-MODE)	Insert, align, or delete end-of-line backslashes on the lines in the region. • With no argument, inserts backslashes and aligns existing backslashes. • With an argument, deletes the backslashes.
	backslash (if any) at the end You can put the region aroun	of the previous line is deleted. nd an entire macro definition ar	region. If the region ends at the start of a line and the macro doesn't continue below it, the nd use this command to conveniently insert and align the necessary backslashes. ing to: 'c-backslash-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'.
Show state preprocessor modes	• <f12> # ? * <f12> <f7> ?</f7></f12></f12>	(pel-pp-show-state)	Show state of C preprocessor control modes.
Hide-ifdef Mode	The Hide-ifdef mode can hide portion of the C pre-processor blocks. This feature hides blocks of code that would not be include in the expanded file according to the state of pre-processor symbols that are maintained inside the Hide-ifdef environment: the hide-ifdef-env association list Emacs variable (use <f1> v to see the content of these variables. See Melp/Info. Note that with PEL, in the table below the commands reachable via the <f12> prefix keys can also be reached via the <m-f12> and the <f11> SPC c prefix keys. Several customize user option variables affect how the hiding is done (to change, execute: M-x customize-group hide-ifdef): 'hide-ifdef-env' An association list of defined symbols for the current project. Initially, the global value of 'hide-ifdef-env' is used. This variable was a buffer-local variable, which limits hideif to parse only one C/C++ file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C/C++ source files opened simultaneously in different buffers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. (SYMBOL) is used when the SYMBOL is defined (but without explicit value) (SYMBOL) VALUE) when the symbol is defined with an explicit value. 'hide-ifdef-define-alist' An association list of pre-defined symbol lists. Use 'hide-ifdef-set-define-alist' to save the current 'hide-ifdef-env' and 'hide-ifdef-use-define-alist' to set the current 'hide-ifdef-env' from one of the lists in 'hide-ifdef-define-alist'. 'hide-ifdef-lines' Set to non-nil to not show #if, #ifdef, #ifndef, #else, and #endif lines when hiding.</f11></m-f12></f12></f1>		
	 'hide-ifdef-initially' Indicates whether 'hide-ifdefs' should be called when Hide-Ifdef mode is activated. 'hide-ifdef-read-only' Set to non-nil if you want to make buffers read only while hiding.		
Toggle the Hide-Ifdef mode	• <f12> M-# • <m-f12> M-# * <f12> <f7> # • <f11> SPC c M-#</f11></f7></f12></m-f12></f12>	(hide-ifdef-mode &optional ARG)	 Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode). With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise. Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
Toggle read-only mode when text is hidden	• C-c @ C-q • <f12> # r * <f12> <f7> R</f7></f12></f12>	(hide-ifdef-toggle-read- only)	Toggle read-only: toggle 'hide-ifdef-read-only'. Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w * <f12> <f7> W</f7></f12></f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).

Description	<u>Keystroke</u>	Function	<u>Note</u>
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H * <f12> <f7> H • <f11> SPC c # H</f11></f7></f12></m-f12></f12>	(hide-ifdefs &optional NOMSG)	Hide the contents of some #ifdefs. Assume that defined symbols have been added to 'hide-ifdef-env'. The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined. With prefix command presents it will also hide the #ifdefs themselves. Turn off hiding by calling 'show-ifdefs'.
Restore all hidden into view	• C-c @ s • <f12> # S * <f12> <f7> S</f7></f12></f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h * <f12> <f7> h</f7></f12></f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor. • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s * <f12> <f7> s</f7></f12></f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d * <f12> <f7> d</f7></f12></f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'. This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u * <f12> <f7> u</f7></f12></f12>	(hide-ifdef-undef START END)	Undefine a VAR so that #ifdef VAR would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D * <f12> <f7> D</f7></f12></f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable. 1. The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
Use a named symbol environment list	• C-c @ U • <f12> # U * <f12> <f7> U</f7></f12></f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Clear the complete list of #define'd symbols inside 'hide-ifdef-env'	• C-c @ C • <f12> # C * <f12> <f7> C</f7></f12></f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'. • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
Evaluate pre- processor macro	• C-c @ e • <f12> # e * <f12> <f7> e</f7></f12></f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region. If no region active, find the current #ifdefs and evaluate the result. Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments		to describe UML diagrams or	cific markup code embedded inside C++ source code comments. This can be useful when finite-state machines for example.
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render-commented- plantumi PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. • Use region if identified otherwise use PlantUML block at point. • Uses prefix (as PREFIX) to choose where to display it: • 4 (when prefixing the command with C-u) -> new window • 16 (when prefixing the command with C-u C-u) -> new frame. • else -> new buffer • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment. Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.

Emacs & C++- References

Document	Notes
Emacs Support for C++	
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.

Document	Notes
Demystify C++ Metaprograms using Emacs	
Programming in C++, Rules and Recommendations	ellemtel style
company-mode ; Modular in-buffer completion framework for Emacs	
C++	
C++ @ Wikipedia	See also these Wikipedia pages • Criticism of C++ • C++23, C++20, C++17, C++14, C++11, C++03 • C and C++ operators
C++ Standard @ ISO C++	
JTC1/SC22/WG21 - The C++ Standard Committee ISOCPP	See also: C++ Standard Draft Sources @ GitHub
C++ Reference @ cppreference.com	
C++ Core Guidelines @ GitHub	
CppCon The C++ Conference	
C++ Annotations	
PC-lint Plus from Gimpel	Strongly recommended static analyzer for C and C++. Will improve your knowledge of C++. Best used when you instrument your code with some directives. For serious C++ development, as it requires some time investment.
Edison Design Group C++	The Edison Design Group provides C++ parsing and tools to several C++ tool vendors. So it's a good thing to know what version of C++ EDG supports. They also provide a good source of links for C++ standard features in forms of Google Sheets: • C++ 20 features • C++17 features • C++14 features • C++11 features