Undo/Redo/Repeat/Command Prefix Arguments

<u>Operation</u>	Keystroke	Function		<u>Note</u>		
<u>Undo</u>	Emacs standard need to think all	d undo command allows und	or redo and may need to type so	ors because: g redo capability. This comes with a complexity cost because the user mething just to change from undo to redo or vice-versa. For a lot of		
	Fortunately for people that find it difficult to handle Emacs default undo, there is a nice external package: the undo-tree package. • The undo-tree package provides 2 different command for undo and redo. The undo only undoes. And the commands maintain a tree of undo/redo operations that can be shown visually with the extra ability to select undo/redo history branches.					
	PEL customization allows selection of either mechanism: • If the pel-use-undo-tree user option is t , then PEL uses the undo-tree package, otherwise it uses the standard Emacs undo.					
	The first row below shows the PEL bindings to standard undo. The rows after that describe the binding used when the undo-tree package is activated. Note that even when undo-tree package is activated and used, it is possible to disable the undo-tree-mode globally or locally using the global-undo-tree-mode and undo-tree-mode commands. When that's the case, the bindings use what is described on the first row. But it's also possible to switch back to the undo-tree-mode using the same commands again.					
	Restrict undo to a region: One very interesting aspect of the Emacs undo system is that we can restrict it to an area of the buffer by first selecting a region and then performing the undo operation while the region is active/visible. Nothing outside the region will be affected by the undo commands. The undo actions outside of the marked region are not lost; once the there is no marked region further undo actions will undo changes in the text.					
	C is normally bound to (undo) but the PEL setup sets it to (negative-argument) to help editing motion flow. M and C are also bound to (negative-argument) for the same reasons, not to the undo or redo commands.					
Open this PDF file. See also: <u>▼ Help/Info</u>	<f11> u <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)		at/Arg local PDF. If the prefix argument (like C-u or M) is used, then sted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's		
<u>Customize</u> PEL undo control	<f11> u <f2></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL undo support. • If OTHER-WINDOW is non-n	il (use C-u), display in other window.		
<u>S Customize</u> Emacs undo control	<f11> u <f3></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs undo suppor	rt: undo, undo-tree.		
Undoing Changes	The following commands are available to undo changes to a buffer. • It's also possible to undo all changes to a buffer associated with a file by reverting the content of the buffer to the content of the file. • See the File Management section: File-mngt PEL provides the powerful undo-tree external package instead of the default undo when the pel-use-undo-tree user option is set to t. Note, however, that undo-tree may break during intensive redo operations. Use with care. With Emacs 28 better alternatives exist and will be incorporated by PEL soon. You may want to use simple-undo with Emacs 28. See below.					
Simple undo/redo	Since Emacs 28, undo-redo is available and complements the undo-only that was available since Emacs 22, allowing the use of undo/redo system more familiar to most people not already familiar with Emacs.					
Simple undo : pel-use-undo-tree = nil : pel-use-simple-undo = t : Emacs >= 28	• C-/ • C-x u • M-u • C-z • s-z • %-z	(undo-only &optional ARG)	Undo some previous changes. Repeat this command to und A numeric ARG serves as a r Contrary to 'undo', this will n	epeat count.		
Simple redo : pel-use-undo-tree = nil : pel-use-simple-undo = t . For Emacs >= 28	• C-? • C-M • M-U • <f11> u r</f11>	(undo-redo &optional ARG)	3,	ix numeric argument and defaults to 1. nmands, but doesn't record itself as an undoable command, as opposed		
Classic Emacs Undo/Redo	Original/standard Emacs undo/redo system. As explained in Emacs Manual Undo section: "Any command other than an undo command breaks the sequence of undo commands. Starting from that moment, the entire sequence of undo commands that you have just performed are themselves placed into the undo record."					
<u>Undo</u>	• C-/ • C-x u	(undo &optional ARG)	Undo last changes using stand • A numeric ARG serves as a	dard Emacs undo. Also used to undo an undo, causing a redo! repeat count.		
: pel-use-undo-tree = nil : pel-use-simple-undo = nil	• M-u • C-z • S-z		If you are not familiar with st	se-undo-tree user option is nil (the default). andard Emacs undo, please first read about it before using it. at first to use the same key to undo and redo.		
Undo : pel-use-undo-tree = t : pel-use-simple-undo = nil	• %-z • <f11> u u</f11>	(pel-undo &optional ARG) • (undo-tree-undo &optional ARG) • (undo &optional ARG)	Undo changes. Does not redo. • A numeric ARG serves as a r • In Transient Mark mode where Similarly, when not in Transie the current region. • C-/ only works in graphics r	repeat count. In the mark is active, only undo changes within the current region. In the mark mode, just C-u as an argument limits undo to changes within		
	 ✓ ⚠ With PEL, when pel-use-undo-tree is t, this key is bound to pel-undo which uses undo-tree-undo by default. You can, however toggle the local or global undo-tree-mode by issuing the M-x global-undo-tree-mode or M-x undo-tree-mode. If the undo-tree-mode is not set in the buffer, PEL will use the Emacs standard undo command until the undo-tree-mode is re-enabled. 					
Redo Percentage in the second of the second	• M-U • <f11> u r • s-Z • %-Z</f11>	 (pel-redo &optional ARG) (undo-tree-redo &optional ARG) (undo &optional ARG) 		n the mark is active, only redo changes within the current region. In Mark mode, just C-u as an argument limits redo to changes within In graphics mode		
	With PEL, when pel-use-undo-tree is t, this key is bound to pel-redo which uses undo-tree-redo by default. You can, however toggle the local or global undo-tree-mode by issuing the M-x global-undo-tree-mode or M-x undo-tree-mode. If the undo-tree-mode is not set in the buffer, PEL will use the Emacs standard undo command until the undo-tree-mode is re-enabled.					
Show undo tree Property 20 to 10 to	<f11> u v</f11>	(undo-tree-visualize)	Show undo tree of current buffer The *undo tree* keys are: • <up>/<down></down></up>			
	, -	ne of these via the global-und		lobal or local undo-tree-mode is active, which it should be unless you commands. If that is the case, re-enable the undo-tree-mode and you		

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Switch branch of undo tree	<f11> u x</f11>	(undo-tree-switch- branch BRANCH)	Switch to a different BRANCH of the undo tree. • This will affect which branch to descend when *redoing* changes using 'undo-tree-redo'.	
pel-use-undo-tree = t	With PEL, this is available when pel-use-undo-tree is t but also while the global or local undo-tree-mode is active, which it should be unless you explicitly disabled one of these via the global-undo-tree-mode or undo-tree-mode commands. If that is the case, re-enable the undo-tree-mode and you will be able to use the command.			
Goto last change	• <f11> u \ • C-x C-\ • <f6> \</f6></f11>	(goto-last-change &optional MARK-POINT MINIMAL-LINE- DISTANCE)	Set point to the position of the last change in the current buffer. Consecutive calls set point to the position of the previous change. With a prefix arg (optional arg MARK-POINT non-nil), set mark so C-x C-x will return point to the current position. This requires the goto-last-change.el package. Under PEL set the pel-use-goto-last-change user option to activate this.	
Enable undo in buffer		(buffer-enable-undo &optional BUFFER)	Enable undo recording in the current buffer. No effect if the undo was already recorded as its the case for all buffers except some (like the buffers that have a name that starts with a space). • Interactively it's not possible to pass an argument.	
Disable undo in buffer		(buffer-disable-undo &optional BUFFER)	Disable undo in current buffer. Deletes all previous undo information for that buffer if it previously existed. No effect if undo was previously disabled. Interactively it's not possible to pass an argument.	
Repeat	The following commands can repeat the last command and show			
Repeat last operation	• C-x z • <f5></f5>	(repeat REPEAT-ARG)	Repeat most recently executed command. With a prefix argument, supply a prefix argument to that command. Otherwise, give the command the same prefix argument it was given before, if any. When using C-x z to perform repeat, once one C-x z has been typed for the first repeat, type z again to again repeat. Typing z continuously continue to repeat last command (any command, even undo). PEL provides the <f5> key to perform repeat.</f5>	
Redo/edit last complex command executed	• C-x Esc Esc • C-x M-Esc • C-x M-:	(repeat-complex-command ARG)	 Edit and re-evaluate last complex command, or ARGth from last. A complex command is one which used the minibuffer. The command is placed in the minibuffer as a Lisp form for editing. The result is executed, repeating the command as changed. If the command has been changed or is not the most recent previous command it is added to the front of the command history. You can use the minibuffer history commands M-n and M-p to get different commands to edit and resubmit. 	
List command history See also: ∑ Help	<f11> ? d H</f11>	(list-command-history)	List history of commands that used the minibuffer. • Show list of commands in the *Command History* buffer as a list of Emacs Lisp forms.	
Command Arguments	All Emacs keystrokes are bindings to an Emacs command, a function that supports interactive use. A lot of these commands have arguments. The user can provide these arguments by using the following key strokes before typing the needed command using the keys listed below.			
Prefix repeat N time	M- <number> Keystroke</number>		Meta N, where N is a typed number, tells Emacs to repeat the next <i>Keystroke</i> operation N times. • N may be larger than 9: to pass a numeric prefix of 23 Hold the Meta key then type 2 followed by 3.	
Repeat prefix	C-u <number> Keystroke</number>	(universal-argument)	 C-u N, where N is a typed number, tells emacs to repeat the next operation N times. Pressing C-u before executing a command is a way to pass extra information to that command. For example, C-u 5 C-b means move the cursor left 5 characters. Sometimes the extra information is just the fact that C-u was pressed. 	
Prefix repeat 4 times	C-u	(universal-argument)	C-u alone stands for a flag, or a repeat factor of 4.	
Prefix repeat 16 times	C-u C-u	(universal-argument)	C-u C-u means 4 * 4 = 16	
Prefix repeat 64 times	C-u C-u C-u	(universal-argument)	C-u C-u means 4*4*4 = 64 repeat.	
Negative argument	• C • M • C-M • C • M	(negative-argument)	 Begin a negative numeric argument for the next command. If needed, C-u following digits or minus sign ends the argument. The PEL package also binds the Control and Meta underscore keys to the negative-argument function to help improve typing speed when entering negative arguments. 	

Undo - Reference

GNU EMacs Lisp Manual — Command Overview	Describes that prior to executing a command Emacs runs undo-boundary to create undo boundary.	
GNU Emacs Lisp Manual — Maintaining Undo Lists	Describes the standard Emacs undo mechanism.	
Emacs undo-tree package	Author's we site, describes undo-tree.	