Programming Language Support — C

Editing C Files CC Mode File extensions C bison-mode Description Emacs supports C natively via the built-in c-mode which extends the CC Mode that support the curly-bracket programming land the pel-use-c or pel-use-bison user-option variables is set. Supported file extensions: code files: .c, .lex, .y, .yacc header files: .h, .i If pel-use-bison-mode is set, the .y and .yacc files are associated with bison-mode, the .l and .lex with flex-mode which extends the CC Mode that support the curly-bracket programming land the pel-use-bison user-option variables is set. Supported file extensions: code files: .c, .lex, .y, .yacc header files: .h, .i If pel-use-bison-mode is set, the .y and .yacc files are associated with bison-mode, the .l and .lex with flex-mode which extends the CC Mode are customizable with PEL user option variables.	guages like <u>C</u> .
• CC Mode • File extensions • C • bison-mode • Dison-mode • PEL activates support for C when one or both of the pel-use-c or pel-use-bison user-option variables is set. • Supported file extensions: code files: .c, .lex, .y, .yacc header files: .h, .i • ☑ If pel-use-bison-mode is set, the .y and .yacc files are associated with bison-mode, the .l and .lex with flex-mode When pel-use-speedbar is set all these extensions are recognized by speedbar, otherwise only the main ones are recognized.	guages like <u>C</u> .
 File extensions C bison-mode If pel-use-bison-mode is set, the .y and .yacc files are associated with bison-mode, the .l and .lex with flex-mode When pel-use-speedbar is set all these extensions are recognized by speedbar, otherwise only the main ones are recognized. 	
• bison-mode • till fel-use-bison-mode is set, the .y and .yacc files are associated with bison-mode, the .l and .lex with flex-mode When pel-use-speedbar is set all these extensions are recognized by speedbar, otherwise only the main ones are recognized.	
When pel-use-speedbar is set all these extensions are recognized by speedbar, otherwise only the main ones are recognized.	
	and .jison with jison-mode
Important aspects of C source code syntax controlled by the CC Mode are customizable with PEL user option variables	
PEL customization for C: Simplifies configuration for editing C source code.	
 Emacs customization group: pel-pkg-for-c (access with <f12> <f2>):</f2></f12> pel-c-indent-width: Identifies the number of columns used for indentation. Defaults to 3. 	
• indentation • pel-c-tab-width: The width of a tab used for c-mode files. Defaults to 3.	
 This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i will move point to colum <tab> will indent to a column that is a multiple of 3. PEL stores this value inside the tab-width variable for c-mode buff</tab> 	· ·
• So For most uses it is best to set both values to the width of your needed indentation level. This way you can use comm	
control the indentation level. • pel-c-use-tabs: Whether hard tabs are used in indentation or not: t: tabs are used, nil: only spaces are used. Default: nil.	
using tabs C code style sub-group: pel-c-code-style	ou ook ik mil
When pel-c-fill-column user option is nil, c-mode buffers use the Emacs fill-column value like other major modes.	
 pel-c-backet-style: The <u>bracket/indentation style</u> supported by the electric keys. You can select one of the <u>values supported</u> define your own 'user' with some Emacs Lisp code. Default to "linux". 	pported by Emacs or
 More user options are used for controlling C code templates created with PEL tempo skeletons. They are described in to below. 	empo skeleton section
Emacs customization group: pel-pkg-for-cc. Applies to all CC Mode related modes (like c-mode).	
 pel-cc-auto-newline: Whether automatic newline mode is active on all CC Mode (including c-mode). The values for those user option variables can also be stored inside directory local files and even as file local variables. You can be stored inside directory local files and even as file local variables. 	an also modify them for
each buffer and view their current settings using the commands listed in the following set of rows. See <u>File/Directory Variance</u>	
None of the commands below change PEL default; they change the value for the current buffer only. PEL provides the following set of mode provides the value of the command of the co	
PEL provides the following set of mode-specific key prefixes: <f11> SPC c as well as <f12> and <m-f12> The first one is always available. The other two prefixes are only available in c-mode buffers. They are not all shown in keys</m-f12></f12></f11>	stroke shells for brevity.
Open this PDF file. <f11> SPC c <f1> (pel-help-pdf &optional Open the %) I - C local PDF. If the prefix argument (like C-u or M)</f1></f11>	-
See also: <u>Neep/Info</u> Verifies PAGE remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg other way around.	•
Support Spc c <f2> Spc c <f2> Support Spc c <f2> Support Spc c <f2> Support Spc c <f2> Spc c <f< th=""><td></td></f<></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2></f2>	
support	N.
∑ Customize Emacs C <f11> SPC c <f3> (pel-customize-library Customize Emacs C support.</f3></f11>	
support &optional OTHER-WINDOW) • If OTHER-WINDOW is non-nil (use C-u), display in another window	W.
CC Mode Style Automatic indentation, brace format style and several other C stylistic elements are controlled by the CC Mode and the CC mode v	variables.
 You can impose an indentation style by customization. You can also adjust the style to what is used in the current buffer: Emacs provides the following commands to parse the source 	code and identify the style
• Learn style it uses. It learns the style and sets the style controlling variables from what it detects in the buffer.	
used in • Use this to adapt to source code written by others and want to continue using the same style. • Use this to adapt to source code written by others and want to continue using the same style. • For the following commands all commands that use a key binding that ends with an upper case letter install the style.	
Show/Modify syntactic context C-c C-o (c-set-offset SYMBOL OFFSET & OFFSET & OFFSET & Syntactic element symbol in 'c-offsets-alist'. SYMBOL is the syntactic element symbol to change and OFFSET syntactic element. The optional argument is not used.	is the new offset for that
Show syntactic C-c C-s (c-show-syntactic- Show syntactic information for current line.	() !!
information for current line information ARG) • Display the syntactic information list and highlight the reference potential to the syntactic list.	.,
 Each list starts with a <u>syntactic symbol</u> with zero or several refe With universal argument, inserts the analysis as a comment on tha 	•
Guess the style used <f12> <f4> g g (c-guess-buffer-no-install Guess the style on the whole current buffer; don't install it.</f4></f12>	-
 in the current buffer, do not install it &optional ACCUMULATE) If given a prefix argument (or if the optional argument ACCUMULATE) previous guess is extended, otherwise a new guess is made from several previous guess is extended. 	•
Guess the style of the <f12> <f4> g B (c-guess-buffer &optional Guess the style on the whole current buffer, and install it.</f4></f12>	
 code in the buffer and install it. ACCUMULATE) The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULA) 	JF is non-nil) then the
previous guess is extended, otherwise a new guess is made from s	•
Guess style in the <f12> <f4> g G (c-guess & optional Guess the style using the first 'c-guess-region-max' bytes of the file</f4></f12>	
region and install it. ACCUMULATE) • The c-guess-region-max user-option defaults to 50,000 bytes, nil • The style is given a name based on the file's absolute file name.	means all buffer.
If given a prefix argument (or if the optional argument ACCUMULA previous guess is extended, otherwise a new guess is made from second previous guess.)	
Guess the style of a	Jordion.
region and install it. END & optional • The style is given a name based on the file's absolute file name.	
ACCUMULATE) If given a prefix argument (or if the optional argument ACCUMULATE) previous guess is extended, otherwise a new guess is made from several previous guess.	
Set buffer style to <f12> <f4> g I (c-guess-install &optional Install the latest guessed style into the current buffer.</f4></f12>	
guessed style and install it. STYLE-NAME) • This guessed style is a combination of 'c-guess-guessed-basic-off offsets-alist' and 'c-offsets-alist'.	fset', 'c-guess-guessed-
The style is entered into CC Mode's style system by 'c-add-style'.	
NAME, or a name based on the absolute file name of the file if STY	
View Guessed style as a set of Emacs (c-guess-view & optional with NAME) Emit emacs lisp code which defines the last guessed style, so you can into emacs if you prefer the guessed code.	an put the code
Lisp statements • "STYLE NAME HERE" is used as the name for the style in the emit given, it is used instead. WITH-NAME is expected as a string but if	
interactively with prefix argument, the value for WITH-NAME is ask	
CC Mode support The following commands can be used to dynamically change the behaviour of important keys such as the return key, delete key, see	
Behaviour control The CC Mode controls the indentation and bracket style which controls what happens when electric characters are typed (when the activated) and provide a better experience when editing C source code.	e electric mode is
CC Mode state displayed in the mode line: 2C{} where:	
• 2 is the CC mode programming language name: C, C++, ObjC, etc	
 C is the C comment style: '*' for block command (/* */) and '/' for line comments (//) {} are the other electric flags: 	
• '1' for electric mode	
'a' for auto-newline mode 'h' for hungry mode 'w' for subword mode Use <f12> M-? to display</f12>	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Toggle Electric state	• C-c C-l • <f12> <f4> e</f4></f12>	(c-toggle-electric-state &optional ARG)	Toggle the electric indentation feature done with the electric character keys. • Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off when negative, and just toggles it when zero or left out.
Set indentation style	• C-c . • <f12> <f4> s</f4></f12>	(c-set-style STYLENAME &optional DONT-OVERRIDE)	Set the <u>bracket/indentation style</u> for the current buffer. Prompts for the name. Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.
Change indentation width for current buffer	<f12> <f4> TAB</f4></f12>	(pel-cc-set-indent-width &optional NEW-WIDTH)	Interactively change the Indentation with for current buffer to NEW-WIDTH. • Prompt for new value. • Use 0 to restore value specified by configuration (pel-c-indent-width). Solution This can be used to change indentation several times in a file.
Toggle syntactic indentation	<f12> <f4> i</f4></f12>	(c-toggle-syntactic- indentation &optional ARG)	Toggle syntactic indentation. Toggle if no ARG or if ARG is 0. • With positive ARG turn on syntactic indentation, turns it off when negative.
	 When it's turned off, the election M-x c-indent-command adjusted 	ctric keys don't reindent, the in	entation functions and electric keys indent according to syntactic context keys, when applicable. dentation functions indents every new line to the same level as the previous nonempty line, and becified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the ok'.
Toggle Comment Style	• C-c C-k • <f12> <f4> M-;</f4></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block and line comments. Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out. The C++ style // comments (also called line comments) are compatible with C since C-99.
Toggle Hungry Delete mode	<f12> <f4> DEL</f4></f12>	(c-toggle-hungry-state &optional ARG)	 Toggle hungry-delete-key feature. Affects < DEL> and C-d keys. Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out. When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop.
Toggle text alignment on pel-newline-and-indent-below See also: • ∑ Align • ∑ Indentation	<f11> M-RET</f11>	(pel-toggle-newline- indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. If pel-newline-does-align is automatically activated (set to t) by adding the major mode to the list in the pel-modes-activating-align-on-return user option. This affects the behaviour of the following commands: pel-cc-newline (assigned to RET in CC modes like c-mode, c++-mode and d-mode). pel-newline-and-indent-below (assigned the M-RET)
Toggle auto-newline insertion mode	• C-c C-a • <f12> <f4> M-RET</f4></f12>	(c-toggle-auto-newline &optional ARG)	Toggle auto-newline feature. Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out. Turning on auto-newline automatically enables electric indentation. When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.
Change RET key behaviour: select return mode.	<f12> <f4> RET</f4></f12>	(pel-cc-change-newline-mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are: 1. context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument. 2. newline-and-indent: uses (newline ARG t) to insert newline and indent. 3. just-newline-no-indent: uses (electric-indent-just-newline ARG) Emacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode. PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.
Display current Mode	<f12> <f4> ?</f4></f12>	(pel-cc-mode-info)	Display information about current CC mode derivative for the current c-mode buffer.
settings	The information includes the following: CC mode style currently active, along with a list of styles associated with current mode. Change it for the current buffer with C-c . or <f12> <f4> s. The Emacs the c-default-style user option defines associations between major modes and the style to use. PEL provides the pel-c-backet-style that is used to set the style for c-mode. Use <f12> <f2> <f2> form a c-mode buffer to access the customization buffer to change it. REIT (return key) mode. Change with pel-cc-change-newline-mode (<f12> <f4> RET). Whether return performs alignment. Change that with pel-toggle-indent-align (<f11> M-RET). State of electric C characters (toggle it on/off with c-toggle-electric-state (C-c C-1 or <f12> <f4> e): whether it is active or not, and when active what character(s) exhibit electric behaviour. if auto-newline on some characters (';' and some other based on style) is active. Toggle it with C-c C-a or <f12> <f4> M-RET. The fill column: the column where force line wrap is done when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET. The fill column: the column where force line wrap is done when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET. The fill column: the column where force line wrap is done when the sub-fill-mode is active. Toggle auto fill mode with <f11> RET. The fill column: the column where force line wrap is done when the sub-fill-mode is active. Toggle auto fill mode with <f11> RET. In c-mode buffer use <f12> <f2> to open the appropriate customization buffer to change them. In c-mode buffer use <f12> <f2> to open the appropriate customization buffer to change them. In c-mode buffer use <f12> <f2> to open the appropriate customization buffer to change them. In c-mode buffer wise defined separately. See next line. In c-mode buffer wise of the customization is controlled separately. See next line. In c-mode buffer wise of the customization is controlled separately. See next line. In c-mode buffer wise of the customization an</f2></f12></f2></f12></f2></f12></f11></f11></f11></f11></f4></f12></f4></f12></f11></f4></f12></f2></f2></f12></f4></f12>		
Notice the name of the PEL user-options that set the significant feature controlling Emacs variables in the message	- RET mode : co - Electric characters : ac - Auto newline : on	d. c-default-style: (bsd) ntext-newline tive on: #*/(){}:;, , auto-filling: off. Set via: aces only Set via: Set via:	<pre>### Property of the company of</pre>
	- c-indentation-style : bs - PEL Bracket style : bs - Comment style : Bl	d	tinued line start with $*$ $- \otimes$ keys are available.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Electric Keys	-		then the electrical state is active in a buffer using c-mode. toggle-electric-state (C-c C-1 or <f12> <f4> e).</f4></f12>
#	#	(c-electric-pound ARG)	Insert a "#".
	,	dle it specially according to the a literal or a macro, nothing sp	e variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is becall happens.
0	• ()	(c-electric-paren ARG)	Insert a parenthesis.
	If 'c-syntactic-indentation' a inside a literal.	and 'c-electric-flag' are both no	n-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted
			may get added or removed; see the variable 'c-cleanup-list'. nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.
{}	• { }	(c-electric-brace ARG)	Insert a brace.
	• If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as settings in 'c-hanging-braces-alist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.		"/la" on the mode line) newlines are inserted before and after the brace as directed by the also reindented unless 'c-syntactic-indentation' is nil.
:	a) If the auto-newline feat	ture is turned on (indicated by	Insert a colon. and a numeric ARG hasn't been supplied, the command performs several electric actions: "/la" on the mode line) newlines are inserted before and after the colon based on the settings in
		indented. The original line is a	lso reindented unless 'c-syntactic-indentation' is nil. o colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
:,	• ; ,	(c-electric-semi, ARG)	Insert a comma or semicolon.
	a) When the auto-newline semi&comma-criteria' b) Any auto-newlines are	feature is turned on (indicated for how newline insertion is de indented. The original line is a	numeric ARG hasn't been supplied, the command performs several electric actions: d by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-termined. Ilso reindented unless 'c-syntactic-indentation' is nil. Icce list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-
Electric pairs	Type the first of a pair to inse	ert this one and its matching ch	activating the electric-pair-mode in the buffer. laracter for (), [], $\langle \cdot \rangle$, "" and ". line lighter set by the pel-electric-pair-lighter is show. This defaults to $\mathcal{E}(1)$
Toggle electric-pair-	<f11> M-e</f11>	(electric-pair-local-mode	Toggle automatic parens pairing (Electric Pair mode) and org-mode special pair electric keys
mode in current buffer		&optional <u>ARG</u>)	only in this buffer. • With a prefix argument ARG, enable Electric Pair mode if ARG is positive, and disable it
Lighter:= $E(1)$			 Electric Pair mode is a global minor mode. When enabled, typing an open parenthesis automatically inserts the corresponding closing parenthesis, and vice versa. (Likewise for brackets, etc.). If the region is active, the parentheses (brackets, etc.) are inserted around the region instead.
Insert New Line(s)	The behaviour of the RET key depends on whether the CC Mode electric mode is active or not. When it is not active it simply inserts a new line. When it is active the point also moves to the proper indentation according to the syntactic context. The following commands can also be used. • With PEL the default behaviour can be selected by customization and modified dynamically for the current buffer with the pel-cc-change-newline-mode command (bound to <f12> M-RET) see the CC-Mode behaviour control section above. • The pel-cc-newline command also aligns comments and assignment in the code block if the pel-modes-activating-align-on-return user option list includes the current major mode. The state for the current buffer can also be modified by the pel-cc-change-newline-mode command (<f11> M-RET)</f11></f12>		
Insert a new line and operate according to the currently active selected return mode. With PEL, modify behaviour with <f12></f12>	RET	(pel-cc-newline &optional N)	Insert a newline and perhaps align. With argument N repeat N times. For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below): c-context-line-break (PEL default for RET) newline (Emacs default for RET) electric-indent-just-newline If 'pel-newline-does-align' is t, then perform the text alignment done by the function 'align'.
M-RET.	Use: (c-context-line-break): Do a line break suitable to the context. • When point is outside a comment or macro, insert a newline and indent according to the syntactic context, unless 'c-syntactic-indentation which case the new line is indented as the previous non-empty line instead. • When point is inside the content of a preprocessor directive, a line continuation backslash is inserted before the line break and aligned app. The end of the cpp directive doesn't count as inside it. • When point is inside a comment, continue it with the appropriate comment prefix (see the 'c-comment-prefix-regexp' and 'c-block-comment variables for details). The end of a C++-style line comment doesn't count as inside it. • When point is inside a string, only insert a backslash when it is also inside a preprocessor directive. Use: (newline & optional ARG INTERACTIVE): Insert a newline, and move to left margin of the new line if it's blank. • With ARG, insert that many newlines. • If option 'use-hard-newlines' is non-nil, the newline is marked with the text-property 'hard'. • If 'electric-indent-mode' is enabled, this indents the final new line that it adds, and reindents the preceding line. • To just insert a newline, use M-x electric-indent-just-newline.		newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in incon-empty line instead. rective, a line continuation backslash is inserted before the line break and aligned appropriately. it. appropriate comment prefix (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' nment doesn't count as inside it. when it is also inside a preprocessor directive. wline, and move to left margin of the new line if it's blank. s marked with the text-property 'hard'. inal new line that it adds, and reindents the preceding line.
	Use: (electric-indent-just		ewline, without any auto-indentation.
Insert an indented line below unbroken current line See also: Indentation	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line. For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. You can toggle this on/off with <f11> M-RET. Bulletify modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	C-j	(electric-newline-and- maybe-indent)	Insert a newline. • If 'electric-indent-mode' is enabled, that's that, but if it is *disabled* then:
	 In programming langua 	age modes, this is the same as	Indentation is done using the value of 'indent-line-function': TAB. mmand indents to the column specified by the function 'current-left-margin'.
Open New Line in	C-o	(c-context-open-line)	Insert a line break suitable to the context and leave point before it.
Context See also: • <u>▼ Whitespace</u>	Solution Normally C-o is bound to o	ppen-line. PEL rebinds it to c-c	e', which is normally bound to C-o . See 'c-context-line-break' for the details.
Open new line	• <f12> C-o</f12>	e line without indenting the nex	tt use open-line via <f12> C-o Insert a newline and leave point before it. With arg N, insert N newlines.</f12>
	• <m-f12> C-o</m-f12>		If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank.

<u>Description</u>	<u>Keystroke</u>	Function	Note
C Comments		c behaviour: / and * to help sup	oport comments in C.
	 C supports 2 types of comments '*': Block Comments 		*/
	• '/' : Line Comments (to end of line (available since C-99)
Comment characters, wrapping long comment lines	/	(c-electric-slash ARG)	Insert a slash character. • If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'. • Indent the line as a comment, if: 1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or 2. The slash is part of a "*/" token that closes a block oriented comment. • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
See also: Filling/Justification	*	(c-electric-star ARG)	Insert a star character. Insert a star character. If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment. If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited. With this key being electric it becomes easy to type the following two styles of multi-line block comment:
			<pre>/* Two star</pre>
			* prefix for * multi-line * C comment. */ • When typing the '*' at the beginning of the line, it indents automatically. If another '*' is
			typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation. • When auto-fill-mode is active, when you type a comment that would be longer than the line, the line is wrapped and the comment continuation string used is automatically inserted. (toggle it with <f11> RET)</f11>
Comment/un- comment ★★ See also: <u>▼ Comments</u>	M-;	(pel-c-comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer. • When no marked region and no comment: • On empty line: insert comment starter at the proper indentation level. • Typed again: move it toward end of line. • On line with code: insert comment starter after the code for an end-of-line comment • With marked un-commented region: • Comment region with style selected by pel-c-multiline-comments user-option: • default (like comment-dwim): each line is commented with a / * * / • 1: single start multi-line comment (see example in box above) • 2: double star multi-line comment (see example in the box above) • With marked commented region: • removes the comment. • When a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'. • You can toggle between C-style / * */ and C++ style // comments (compatible with C since C-99) <f12> M-;</f12>
Comment/un-comment See also: Comments	С-с С-с	(comment-region BEG END & optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead. • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better and pel-c-comment-dwim even better.
Fill current paragraph See also: Filling/Justification	• M-q • <f12> F • <m-f12> F</m-f12></f12>	(c-fill-paragraph &optional ARG)	Like <f11> t f p but handles // and /* */ style comments. If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details). If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following: char description[] = "\ A very long description of something that you want to fill to make nicely formatted output."; If point is in any other situation, i.e. in normal code, do nothing. Optional prefix ARG means justify paragraph as well.</f11>
Toggle subword-mode See also: Text Modes	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hide/Show comments See also: • <u>Somments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see S Comments). • PEL activates it when the pel-use-hide-comnt user option is t.
			per and mad domine addition option to the

<u>Description</u>	Keystroke	Function	Note
Hungry Deletion of Whitespace	 The CC mode provides two commands that can perform "hungry whitespace deletion" that can also be used in every mode. PEL provides the convenient keys with the <f11> prefix keys for those 2 commands, available in all modes.</f11> In modes compatible with the CC Mode (e.g. for C, C++, D, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour of the simple and C-d, to perform hungry deletions. That's not currently supported in other modes. When the Hungry Delete Mode is on, the mode-line displays a 'h' to the right of the '/l' indication of electric mode. The Hungry Mode also activates the key prefixes below that start with C-c. They are listed but remember they are only available once the Hungry state mode is activated (and that can only be done in modes that are CC Mode compatible). In modes derived from CC Mode you can also activate the hungry state to make standard delete commands delete hungrily, but that does not work for other modes. PEL provides the <f12> M-DEL key for those modes (like C).</f12> Toggle hurry deletion mode of the DEL and C-d key for the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12> 		
Delete preceding char or all preceding whitespace. See also: <u>See Cut & Paste</u>	• C-c DEL • C-c ☒ • C-c C-☒ • C-c C-backspace> • C-c C-DEL • <f11> ☒ ☒</f11>	(c-hungry-delete- backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character. □► In terminal mode, even though C-⟨S⟩, ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. ⊍ With PEL, the ⟨f11⟩ ⟨S⟩ ⇒ binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts
	• <f11> DEL DEL</f11>		with other modes that may use the popular C-c bindings.
Delete next char or all following whitespace. See also: Cut & Paste	• C-c C-d • C-c 🔊 • C-c C-🔊 • C-c <c-delete> • <f11> 🗵</f11></c-delete>	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character. In terminal mode, even though C-ID and CC-delete> are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized. With PEL, the <f11> ID binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11>
Indentation	behaviour control section abov You can also explicitly request • The first set of commands p	ve. indentation using the commar perform syntactic indentations	-Mode state, the style and whether electric mode for some characters is active. See CC Mode ands below.
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.
See also: •	 Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <f12> M-i key):</f12> With syntactic-indentation on (the default): In Transient Mark mode, when the region is active, reindent the region. Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line. Otherwise reindent just the current line. This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.</tab> With syntactic-indentation off: <tab> always indent current line by one level</tab> C-u - <tab> or M <tab> always un-indent current line by one level.</tab></tab> Indenting marked region is done without syntax knowledge and at the same level as previous line. If you want to indent rigidly you can use: pel-indent-rigidly, bound to C-x <tab> and to <f11> <tab> <tab> to indent the line or region rigidly.</tab></tab></f11></tab> tab-to-tab-stop, bound to M-i to insert spaces to the next tab stop column. 		
Indent lines of list after point See also: Indentation	C-M-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it. • A prefix argument (C - u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun) Indent the content of the current top-level function or class. Leaves point unchanged.	
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	and the second s	, it's best to set pel-c-tab-wid	gards to semantics. More information on indentation is available in the ∑ Indentation table. th and pel-c-indent-width to the same value: the first 2 commands use the value of pel-c-tab-
Insert spaces or tabs to next defined tabstop column See also: <u> </u>	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column. The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer. With PEL, the tab-stop interval is controlled by the value of pel-c-tab-width. PEL sets tab-width to the value of pel-c-tab-width for each c-mode buffer.
Indent/Unindent rigidly See also: • ∑ Indentation • ∑ Key-Chords	• C-x <tab> • <f11> <tab> <tab> • <tab>q</tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	 Indent rigidly the marked region or current line N times tab-width columns. If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes. If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): N = [-1, 0, 1] : operate on current line N > 1 : operate on the current line and N-1 lines below. N < -1 : operate on the current line and (abs N) -1 lines above.
	 ➢ PEL rebinds this key, but it extends the functionality: pel-indent-rigidly uses the original indent-rigidly. indent-rigidly Indent all lines starting in the region. If called interactively with no prefix argument, activate a transient mode in which the indentation can be adjusted interactively by typing <left>, <right>, <s-left>, or <s-right>.</s-right></s-left></right></left> Both of these commands activate a transient mode where Emacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. The capabilities are controlled by the variable indent-rigidly-map with by default provides: S-<right> indent-rigidly-left-to-tab-stop</right> S-<left> indent-rigidly-left-to-tab-stop</left> <right> indent-rigidly-left to-tab-stop</right> <le><right> indent-rigidly-left</right></le> Typing any other key deactivates the transient mode. The S-<right> and S-<left> keys indent/de-indent to the next tab-stop position, which is controlled by the tab-width user option.</left></right> With PEL, the tab-stop interval is controlled by the value of pel-c-tab-width. PEL sets tab-width to the value of pel-c-tab-width for each c-mode buffer. If you use the cua-mode: the cua-mode uses C-x, to invoke this command when cua-mode is active, type it really fast or type C-x C-x <tab> (or us the PEL binding <f11> <tab> <tab> (cab)</tab> </tab></f11></tab>		

Description	<u>Keystroke</u>	Function	<u>Note</u>
Indent line(s) rigidly	• <f6> <tab></tab></f6>	(pel-indent-lines	Indent current or marked lines by N indentation levels controlled by pel-c-indent-width .
See also:	• <f11> <tab> c</tab></f11>	&optional <u>N</u>)	Works with point anywhere on the line.
• <u>Nation</u>	 All lines touched by the region are indented. A special argument N can specify more than one indentation level. It defaults to 1. If a negative number is specified, 'pel-unindent-lines' is used. If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left. 		
Un-indent line(s) rigidly	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	 Un-indent current line or marked lines by N indentation levels controlled by pel-c-indent-width. Works with point is anywhere on the line.
See also: • <u>∑ Indentation</u>	If a region was marked, the characters in all affected line Handles presence of hard ta If indent-tabs-mode is no	nction does not deactivate it to function does not deactivate it es. Use C-g to de-activate abs: nn-nil the indentation is created any hard tab in the indentatio	o allow repeated execution of the command. to allow repeated execution of the command. It also modifies the region to include all e the region. with a mix of hard-tabs and space characters. n of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-
	There are several Emacs exter	nsion packages that can help w	vriting C code.
Toggle c-eldoc mode	<f12> ? e</f12>	(pel-toggle-c-eldoc-mode)	Toggle c-eldoc mode on/off. • The c-eldoc mode provides the C prototype information in the echo area for the function at point. It currently appears when typing a new function with its arguments inside the code.
	CITIZ SPC C ? E		Requires <u>c-eldoc</u> external package. Activated when pel-use-c-eldoc is set to t. The extra processing may slow Emacs. This package could be improved into providing the information only on demand but a LSP-based system might be more performant anyway. I am currently looking at this to see if I can improve the performances and the feature set. c-eldoc uses the cpp command to preprocess the buffer content.
Open file at point	The following commands, follothe input completion method of		llow opening files from the file name taken at point (the cursor location). They work regardless of
point			ible to instruct Ido to use a file name at point as the basis for the file name to open. This Ido er-option. With PEL you can control it globally or locally with <f11> f M</f11>
Open file or web-page whose name is at point	• C-^ • <f11> f . • <m-f11> M-f M</m-f11></f11>	(pel-open-at-point &optional N)	Open the file, library or the URL, named at point, with potential line & column #s. $\boxed{\underline{\mathbf{6y}}}$ The $\underline{\mathbf{6y}}$ key-chord is available if pel-use-key-chord is non-nil.
	• <u>6y</u>		Command prefixes are supported with the key-chord. See <u>X Key-Chords</u> .
See also: • ∑ File mngt • ∑ Key-Chords • ½ reStructuredText • ¾I - C++ • ¾I - Erlang	This command extracts the file name to search from text at point. The file name is either surrounded by white space characters or the delimiters listed below. If embedded space(s) are allowed in the filename, then point must be located at the first of the 2 delimiter characters. These delimiter character can be any of the following: "`' ()[]{}<> ''"" 「」 () 《》 [] () 《》 [] () «» · · · · · · · · · · · · · · · · · ·		
Select search method	 Otherwise the command attempts to open the file name with the specified name. If that file does not exists it then proceed to search for it. The command searches for the file to open using the method identified by the pel-c-file-finder-method user-option, one of the following: generic: the command searches for a file in the directory tree of the parent root directory. The parent root directory is a directory parent of the current file that holds a project marker file, one of the file identified in the pel-project-root-identifiers user option. Something like .git, .hg, .project or .pel-project by default. environment variable name: the name of an environment variable (like INCLUDE) that holds a list of directory names to search files in. explicit lists: two lists of directory names: one list holds the project directory names, the other hold the tool and library directory names. The lists may identify directory names indirectly via environment variables. The \$VARNAME format must be used. 		
Select prompt method	 When several file names are found, the command lists them and prompts using the method selected by pel-prompt-read-method user-option. Note that the command shows all files found by the specified search method, it does not only use the first one found. This allows you to detect potential duplication in header file names in large include paths. 		
Select target window	 It Prompts for incomplete file names, allowing editing the find file (with completion), search for libraries files (type 1) according to current file type. Select target window: Without argument: If file is already opened in a window, move point to that window and to the line column coordinates if specified following the file name at point. If no window holds that file, select the target window based on the number of editable windows in frame: if 1, split that window and use the new window, if 2: use the other window, if 3 or more, use the current window. With numeric argument N: N < 0: create a new window and use that. N = 0: use the 'other' (the next) window. N = 1,3,7or above (excluding 9): select the target window based on the number of editable windows in frame: if 1, split that window and use the new window, if 2: use the other window, if 3 or more, use the current window. N is: 8: up, 2: down, 4:left, 5:current, 6:right. N is 9: open the file in the system's browser, and for a directory name at point open the application associated with directory browsing (eg. macOS) 		
See function docstring for more info.	Selecting Minibuffer, inex	at point in the system's brows istent or dedicated window is	

Description	<u>Keystroke</u>	Function	<u>Note</u>
Tempo skeletons for C	PEL creates key bindings to with the same key bindings	invoke the skeletons in the su for equivalent concepts (such	as file header block) as much as possible.
See also: •	 PEL creates key bindings to invoke the skeletons in the supported major modes, using the same key pindings for equivalent concepts (such as file header block) as much as possible. ■ Several aspects of the PEL Emracs Lisp Source Code Style is controlled by the user options inside the pel-o-code-style group. This group can be edited with <f12> <f12> <f2> from a C mode buffer and include the following options:</f2></f12></f12> pel-o-skel-module-header-block-style: allows selecting a user-define module-header comment block. pel-o-skel-module-header-block-style: allows selecting a user-define module-header comment block. pel-o-skel-insert-file-timestamp: set whether an automatically updated timestamp is inserted in the file header block. set whether blocks use horizontal separator lines. pel-o-skel-doc-markup: set whether blocks use horizontal separator lines. pel-o-skel-doc-markup: set whether blocks use horizontal separator lines. pel-o-skel-file-section-titles: identifies documentation section titles inserted in the function description comment. pel-o-skel-file-section-titles: identifies the title of the C function templates are inserted in the function description comment. pel-o-skel-function-define-style: identifies the title of the C function templates are inserted in the function description comment. a basic, free-format style to describe the function above its code. a Man-page style comment block style. Several styles are provided: no a special comment. a basic, free-format style to describe the function above its code. a Man-page style comment block with the sections identified by pel-o-skell-function-section-titles. a user defined tempo skeleton loaded from a user specified file name. See the source code example. pel-o-skel-with-license: specify whether copy right and code license is specified. An option		
<u>▼ Customize</u> PEL C	with the standard tempo-me <f12> <f12> <f2></f2></f12></f12>	ode keys C-c M-f and C-c (pel-customize-pel &optional OTHER-WINDOW)	M-b or some other keys like C-c . and C-c ,. Customize PEL C skeleton layout. If OTHER-WINDOW is non-nil (use C-u), display in another window.
Insert a file header	<f12> <f12> h</f12></f12>	(pel-elisp-file-header)	Insert a file description block. Distinguish between code files and header files. • Prompts for the file purpose. • For header files, include guard is inserted if requested by customization. • The layout of the entered text is controlled by user options. It is possible to create a user-specified skeleton this command will used instead of the one provided by PEL. • See examples of generated outputs located in example/templates/c/files repo directory. • Access the customization buffer by typing: <f12> <f12> <f2></f2></f12></f12>
Insert #define	<f12> <f12> d</f12></f12>	(pel-c-define)	Insert a C pre-processor #define statement. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line, even if there is text after point (to allow inserting it before the name of the symbol to define).
Insert #include <.h>	<f12> <f12> i</f12></f12>	(pel-c-include-lib)	Insert a C pre-processor #include <> statement to include a library file. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. • If there is text after point, insert a new line to place that text on the next line. • The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c · move point there).
Insert #include ".h"	<f12> <f12> I</f12></f12>	(pel-c-include-local)	Insert a C pre-processor #include "" statement to include a local file. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. • If there is text after point, insert a new line to place that text on the next line. • The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c • move point there).
Insert a function definition with comment block	<f12> <f12> f</f12></f12>	(pel-c-function)	Insert a C function definition code and comment template. • The command prompts for the function name and its purpose. • You can hit return both prompts to specify no text; in that case a tempo skeleton marker is left at the location where the text must be inserted and point is left at the first one. • If you enter a function name, it must be a valid C function name (as far as the syntax is concerned). However leading and trailing whitespace is accepted and trimmed and dash characters ('-') are automatically replaced by underscores ('') for convenience. • If an invalid name is specified it is erased and you are prompted again. Use M-p to bring the old value back. • Prompts for function and purpose maintain separate histories. Use M-p and M-n to navigate in the histories at the prompt. You can also use the <up>and <down> keys. • The style of the code inserted is controlled by the user options inside the pel-c-code-style group and the various C style element controls of the CC-mode. • Use C-g to cancel at any prompt. See some examples in the PEL manual.</down></up>
Toggle pel-tempo- mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-rst commands, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.

Description	Keystroke	Function	Note
-	<f12> <f12> <f12></f12></f12></f12>		
Tempo Template Tag Insertion	<f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit <f12> <f12> <f12> <f12>. A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template. All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed. Since only one template is available in emac-lisp-mode, the usefulness of this command is limited here.</f12></f12></f12></f12></f12></f12>
Inserting code	Extra text insertion can be dor	ne with the following command	S.
Insert Parentheses	M- ((insert-parentheses &optional ARG)	For C: insert a parenthesis pair '()', leaving point after open-paren. • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. • A negative ARG encloses the preceding ARG sexps instead. • No argument is equivalent to zero: just insert '()' and leave point between. • PEL makes 'parens-require-spaces' buffer local and set it to nil in C mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. • If region is active, insert enclosing characters at region boundaries. • This command assumes point is not in a string or comment.
Marking	Emacs provides the following	command to quickly mark the	whole content of the current function. More mark commands exists, see the <u>Narking</u> table.
Mark the complete function body See also: Marking	C-M-h	(c-mark-function)	Mark complete function. Put mark at end of the current top-level declaration or macro, point at beginning. If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function. A mark is left where the command started, unless the region is already active (in Transient Mark mode). As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a brace block.
Getting Syntactic Information	Use the following commands	to extract syntactic information	from the source code.
Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it. • With a prefix arg, push the name onto the kill ring too.
Search Support		de can be useful since snake case is often used. Using superword-mode helps searching. node by default in C mode. To change this use the <f11> t <f2> to access the customize buffer.</f2></f11>	
Toggle superword-mode See also: Text Modes Search/Replace	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	 Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In C '_' are treated as part of words. With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.
Highlighting blocks	The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and []. • show-paren-mode, which highlights the parens that matches the one before or after point. • rainbow delimiters mode, where matching nested parens are highlighted with the same colour.		
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>National Highlight</u> Enable/Disable	• <f11> h (</f11>	(rainbow-delimiters-mode	Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	&optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.
nested blocks (),{},[] See also: <u>∑ Highlight</u>	• <f11> h R</f11>		 Customize the depth and colours with M-x customize-group rainbow-delimiters Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t.
Navigation in C	This current list below describ	e the specialized commands of	nly. See the others inside ∑ Navigation
By definitions			ef for more information to activate the various engines that support cross referencing for C code.
Find definition of identifier at point	M	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. If there are more than one match, prompt in the *xref* buffer. To search for a symbol entered manually, type C-u M
See also: <u>∑ Xref</u>			With dumb-jump this performs a search using ag, ripgrep or git grep if available.
Go back to where M was last issued	M-,	(xref-pop-marker-stack)	 Pop back to where M was last invoked. Marker depth is controlled by the xref-marker-ring-length user option.
By functions By structures	 Move to beginning /end of function definition blocks or structure definition blocks. Jump over comments. When point is located before opening brace or right after closing brace and show-paren-mode is on, the matching parentheses are highlighted. 		
Forward to start of next top level function or struct	<f6> <down></down></f6>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function or type definition. Move point before the function type or the struct or typedef keyword. Beeps if does not find beginning of next function unless SILENT is non-nil. If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. Move back to previous position with M— .
			→ Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key. Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key. It is command complements what end-of-defun does. It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.</f12></f6></f12></f6>
Forward to end of current top-level function or struct.	С-М-е	(c-end-of-defun &optional ARG)	Move forward to the end of a top level declaration. With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to the end of next function or type definition. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key.</f12></f6>
	<f12> <right></right></f12>		This command moves to the end of the next top-level function. It skips nested functions.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Backward to beginning of current top-level function or struct	С-М-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a function or type definition. With a positive argument, move backward that many functions or structures. A negative argument -N means move forward to the Nth following beginning.
<u> </u>	• C-M- <home> • <f6> <up></up></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of function or type definition. Move point before the function type or the struct or typedef keyword. With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.
	<f12> <up></up></f12>		→ Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key. ⚠ This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions that are more deeply nested.</f12></f6>
Backward to end of previous top level function or struct	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function or type definition. Beeps if does not find end of previous function unless SILENT is non-nil. If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.
	<f12> <left></left></f12>		 Move back to previous position with M-⁻. Shift marking is available. With <f6> and <f12> hit Shift after function key, before cursor key.</f12></f6> In some cases it fails to detect the end of the previous block and fails.
By blocks	Move across C statements	and C scope blocks, or any gro	oup of (), [], {} or <> blocks.
By List element	Move to the end or the be	eginning of a block	
Backward block/list See also: Navigation	С-м-р	(backward-list &optional ARG)	Move backward across one balanced group of parentheses. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move forward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.
Move block backward See also: ■ Navigation	• C-M-b • C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-b : ➤ Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ➤ Shift marking works with this command. • ⚠ With PEL: if you want to use Esc C-<left> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<left> does not work on Windows, but H-<left> works. ⑤ Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</left></left></left></left></left>
Forward block/list	C-M-n	(forward-list &optional	Move forward across one balanced group of parentheses.
See also: <u>Navigation</u>		ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move backward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.
Move block forward See also: • Navigation	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : → Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : → Shift marking works with this command. • ⚠ With PEL: if you want to use Esc C-<right> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<right> does not work on Windows, but H-<right> does. ■ Several Linux distros map C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</right></right></right></right></right>
in/out of blocks	Move in or out of C scope b	locks, or any group of $(), [], \{\}$	or < > blocks.
Backward Up/outside sexp hierarchy See also: • Navigation	• C-M-u • C-M- <up> • C-[C-u • Esc C-u • Esc C-<up></up></up>	(backward-up-list &optional ARG ESCAPE- STRINGS NO-SYNTAX- CROSSING)	Move backward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. Mith PEL: if you want to use Esc C- <up> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. C-M-u: Shift marking is available in graphics mode, not in terminal mode. C-M-<up> i Shift marking works with this command. C-M-<up> does not work on Windows, but H-<up> does.</up></up></up></up>
Forward Up/outside	C-M-]	(up-list &optional ARG ESCAPE-STRINGS NO-	Move forward out of one level of parentheses or nested blocks.
sexp hierarchy See also: <u>Navigation</u>		SYNTAX-CROSSING)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot.
Down/inside sexp/ block See also:	• C-M-d • C-M- <down> • C-[C-d</down>	(down-list &optional ARG)	Move forward down one level of parentheses. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still go
• <u>∑ Navigation</u>	• Esc C-d • Esc C- <down></down>		down a level. This command assumes point is not in a string or comment. Mith PEL: if you want to use Esc C- <down> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. C-M-d : ► Shift marking is available in graphics mode, not in terminal mode. C-M-<down> : ► Shift marking works with this command. C-M-<down> does not work on Windows, but H-<down> does.</down></down></down></down>
By statements	Move to beginning /end of sta		
Go to beginning of statement (backward)	м-а	(c-beginning-of-statement &optional COUNT LIM SENTENCE-FLAG)	Go to the beginning of the innermost statement. With prefix arg, go back N - 1 statements. If already at the beginning of a statement then go to the beginning of the closest preceding one, moving into nested blocks if necessary (use C-M-b to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.
Go to the end of statement (forward)	м-е	(c-end-of-statement &optional COUNT LIM SENTENCE-FLAG)	Go to the end of the innermost statement. With prefix arg, go forward N - 1 statements. Move forward to the end of the next statement if already at end, and move into nested blocks (use C-M-f to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.

Open the C preprocessor hydra with <f12> <f7></f7></f12>	vould not be executed with the external packages are listed be external packages are listed be the provides a key hydra to he the hydra external package. The key sequences that state hydra external package. -UUU:**F1 a c f C preprocessor: Move to Hide hydra in ext #:	e Hide-ifdef mode. There are a clow. They can be used for edielow. They can be used for edielo navigate trough preprocess art with <f12> <f7> open the 2 PEL activates when the period of the company of</f7></f12>	also external pack iting C and C++ s sor directives and ne pel-∑c-preprod	to hide/show code areas based on preprocessor logic and defined variables. Hydra allowing further hydra keys to be typed without any prefix. Requires
Open the C preprocessor hydra with <f12> <f7></f7></f12>	The key sequences that state the hydra external package -UUU:**F1 a_c_1 C preprocessor: Move to	art with <f12> <f7> open the example PEL activates when the per Eile.c All (4,0)</f7></f12>	ne pel-∑c-preprod	Hydra allowing further hydra keys to be typed without any prefix. PRequires
preprocessor <u>hydra</u> with <f12> <f7></f7></f12>	C preprocessor: Move to Hid			or option to dot to a
preprocessor <u>hydra</u> with <f12> <f7></f7></f12>	Move to Hid n: next #:	le # 1	(C/*]	a Ifdef WK Fly ² Anzu Abbrev)
followed by on of the hydra keys:	C-p: begin R: C-n: end H: C-u: up S: h:	toggle mode e: toggle shadow d: toggle RO u: hide U: show D:	Vars	Other ?: Show state <f7>: cancel</f7>
Navigate across pre- processor conditionals	The following commands move	e point across the #if , #else , #	elif and #endif	C pre-processor conditional statements.
Move to previous •	<f12> # p k <f12> <f7> p</f7></f12></f12>	(pel-pp-prev-directive)	Move point to pr	revious preprocessor directive.
	<f12> # n k <f12> <f7> n</f7></f12></f12>	(pel-pp-next-directive)	Move point to ne	ext preprocessor directive.
	C-c C-u k <f12> <f7> C-u</f7></f12>	(c-up-conditional COUNT)	A prefix argunend of the cor "#elif" is treater	e containing preprocessor conditional, leaving mark behind. nent acts as a repeat count. With a negative argument, move forward to the ntaining preprocessor conditional. ed like "#else" followed by "#if", so the function stops at them when going t not when going forward.
	C-c C-p k <f12> <f7> C-p</f7></f12>	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	A prefix argun	ss a preprocessor conditional, leaving mark behind. nent acts as a repeat count. re argument, move forward across a preprocessor conditional.
	'-c C-n k <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	A prefix argunWith a negativeIf there aren't"#elif" is treate	cross a preprocessor conditional, leaving mark behind. nent acts as a repeat count. re argument, move backward across a preprocessor conditional. renough conditionals after (or before) point, an error is signaled. red like "#else" followed by "#if", except that the nesting level isn't changed subconditionals.
<u>Processor</u>	C-c C-e 0 <f12> # # 0 <m-12> # #</m-12></f12>	(c-macro-expand START END SUBST)		os in the region, using the C preprocessor. lay output in temp buffer, but prefix arg means replace the region with it.
	Customizations: 'c-macro-preprocessor' specifies the preprocessor to use. • If the user option 'c-macro-prompt-flag' is non-nil prompt for arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-cppflags'.			
end-of-line backslash	:-c C-\	(c-backslash-region FROM TO DELETE-FLAG &optional LINE-MODE)	With no argun With an argun	delete end-of-line backslashes on the lines in the region. nent, inserts backslashes and aligns existing backslashes. nent, deletes the backslashes.
	backslash (if any) at the end You can put the region arour	of the previous line is deleted. nd an entire macro definition ar	nd use this comm	ion ends at the start of a line and the macro doesn't continue below it, the and to conveniently insert and align the necessary backslashes. sh-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'.
	<f12> # ? k <f12> <f7> ?</f7></f12></f12>	(pel-pp-show-state)	Show state of C	preprocessor control modes.
			fI> v to see the content of these variables. See <u>N Help/Info</u> eached via the <m-f12> and the <f11> SPC c prefix keys. hange, execute: M-x customize-group hide-ifdef):</f11></m-f12>	
			ve extended hideif to support parsing a C/C++ project containing multiple C/ 'hide-ifdef-env' can no longer be buffer local but must be global. it value) e. ne-alist' to save the current 'hide-ifdef-env' and 'hide-ifdef-use-define-alist' to e-alist'. nen hiding.	
k			Hydra allowing further hydra keys to be typed without any prefix. Pequires	
mode *	<pre>> <f12> M-# > <m-f12> M-# \$ <f12> <f7> # > <f11> SPC c M-#</f11></f7></f12></m-f12></f12></pre>	(hide-ifdef-mode &optional ARG)	With a prefix a otherwise. Hide-Ifdef mo enabled, code	to hide/show #ifdef blocks (Hide-Ifdef mode). argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it de is a buffer-local minor mode for use with C and C-like major modes. When be within #ifdef constructs that the C preprocessor would eliminate may be
mode when text is	C-c @ C-q > <f12> # r k <f12> <f7> R</f7></f12></f12>	(hide-ifdef-toggle-read- only)	 Note that you 	iew. r: toggle 'hide-ifdef-read-only'. can make the file read only by default when hide-ifdef is hiding text, by setting f-read-only' user option to t.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w * <f12> <f7> W</f7></f12></f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H * <f12> <f7> H • <f11> SPC c # H</f11></f7></f12></m-f12></f12>	(hide-ifdefs &optional NOMSG)	Hide the contents of some #ifdefs. Assume that defined symbols have been added to 'hide-ifdef-env'. The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined. With prefix command presents it will also hide the #ifdefs themselves. Turn off hiding by calling 'show-ifdefs'.
Restore all hidden into view	• C-c @ s • <f12> # S * <f12> <f7> S</f7></f12></f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h * <f12> <f7> h</f7></f12></f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor. • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s * <f12> <f7> s</f7></f12></f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d * <f12> <f7> d</f7></f12></f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'. • This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u * <f12> <f7> u</f7></f12></f12>	(hide-ifdef-undef START END)	Undefine a VAR so that #ifdef VAR would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D * <f12> <f7> D</f7></f12></f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable. The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
Use a named symbol environment list	• C-c @ U • <f12> # U * <f12> <f7> U</f7></f12></f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Clear the complete list of #define'd symbols inside 'hide- ifdef-env'	• C-c @ C • <f12> # C * <f12> <f7> C</f7></f12></f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'. • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
Evaluate pre- processor macro	• C-c @ e • <f12> # e * <f12> <f7> e</f7></f12></f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region. If no region active, find the current #ifdefs and evaluate the result. Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside C source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example. You can also use Graphviz, see M Graphviz Dot		
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render-commented-plantum! PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. • Use region if identified otherwise use PlantUML block at point. • Uses prefix (as PREFIX) to choose where to display it: • 4 (when prefixing the command with C-u) -> new window • 16 (when prefixing the command with C-u C-u) -> new frame. • else -> new buffer • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment. • Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. • Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.

Emacs & C - References

Document	Notes
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
company-mode ; Modular in-buffer completion framework for Emacs	