

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Perl Editing	Emacs provides two maj	or modes for Perl: perl-mode (Emacs defau	llt, simpler mode) and cperl-mode. HaraldJoerg/cperl-mode has support for new Perl		
Activate Perl     Select major     mode     PEL prefix key	language features.  PEL activates Perl support with the pel-use-perl user-options. When turned on:  PEL provides supports all of them: pel-perl-mode selects the mode, using HaraldJoerg/cperl-mode by default because it has the best support for Perl.  After using HaraldJoerg/cperl-mode if you want to change to Emacs own cperl mode, you need to remove the cperl files from ~/.emacs.d/utils				
• <u>Speedbar</u>	It activates the ability to a compare the	<ul> <li>The <f11> SPC P prefix is made available. In a perl buffer these commands are accessible via the <f12> key.</f12></f11></li> <li>It activates the ability to activate minor modes for the perl major mode through the PEL pel-perl-activates-minor-modes user-option.</li> <li>If pel-use-speedbar is on, speedbar support for Perl is activated.</li> </ul>			
• <u>∑ Indentation</u> control ►	Perl indentation is controlled by the following user-options:  • perl-indent-level sets the number of columns used for indentation. It defaults to 4.  • PEL sets tab-width with the same value in rust buffers so that manual indentation commands use the same number of columns to indent.  • pel-perl-use-tabs controls whether hard tabs are used for indentation (nil by default).  • PEL sets indent-tabs-mode with the value of pel-perl-use-tabs in perl buffers.				
Open this PDF file. See also: <u>∑ Help/</u> Info	<f11> SPC P <f1><f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN-WEB- PAGE)	Open the <u>\$\mathbf{y}\tau-\text{Perl}\text{ local PDF.} If the prefix argument (like <b>C-u</b> or <b>M</b>) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.</u>		
∑ Customize PEL Perl support	<f11> SPC P <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Perl support.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.		
∑ Customize     Emacs Perl support	<f11> SPC P <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs Perl support: perl.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.		
Comments					
Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments-toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active then toggle in the region. Otherwise, in the whole buffer.  • This requires the <u>hide-comnt.el</u> package (see <u>∑ Comments</u> ).   • PEL activates it when the <u>pel-use-hide-comnt</u> user option is t.		
cperl-mode					
Toggle auto- newline	C-c C-a	(cperl-toggle-auto-newline)	Toggle the state of 'cperl-auto-newline'.		
Find code for whitespace	C-c C-b	(cperl-find-bad-style)	Find places in the buffer where insertion of a whitespace may help.  • Prompts user for insertion of spaces. Currently it is tuned to C and Perl syntax.		
Spell-check here- docs	C-c C-d	(cperl-here-doc-spell)	Spell-check HERE-documents in the Perl buffer.  • If a region is highlighted, restricts to the region.		
Toggle electric mode	C-c C-e	(cperl-toggle-electric)	Toggle the state of parentheses doubling in CPerl mode. When typing an opening parens character the closing one is automatically entered.		
Toggle auto-fill mode	C-c C-f  • <f11> t f a</f11>	(auto-fill-mode &optional ARG)	Toggle automatic line breaking (Auto Fill mode).  With a prefix argument, enable Auto Fill mode if the prefix argument is positive, and disable it otherwise.  When the Fill was to be a part of the prefix argument fill.		
	• <f11> C T a</f11>		<ul> <li>When Auto Fill mode is enabled, inserting a space at a column beyond 'current-fill-column' automatically breaks the line at a previous space.</li> </ul>		
Perl new line	C-c C-j	(cperl-linefeed)	Go to end of line, open a new line and indent appropriately.  If in POD, insert appropriate lines.  This is a convenience replacement for typing carriage return. It places you in the next line with proper indentation, or if you type it inside the inline block of control construct, like foreach (@lines) {print; print}  and you are on a boundary of a statement inside braces, it will transform the construct into a multiline and will place you into an appropriately indented blank line.  If you need a usual 'newline-and-indent' behavior, it is on C-j, see documentation on 'cperl-electric-linefeed'.		
Toggle keyword expansion	C-c C-k	(cperi-toggle-abbrev)	Toggle the state of automatic keyword expansion in CPerl mode.		
Narrows to here- doc	C-c C-n	(cperl-narrow-to-here-doc &optional POS)	Narrows editing region to the HERE-DOC at POS. POS defaults to the point.		
Spell-check POD documentation	С-с С-р	(cperl-pod-spell &optional DO-HERES)	Spell-check POD documentation.  If invoked with prefix argument, will do HERE-DOCs instead.  If a region is highlighted, restricts to the region.		
Refactor: if (A) {B}' ↔ 'B if A;'	C-c C-t	(cperl-invert-if-unless)	Change 'if (A) {B}' into 'B if A;' etc (or visa versa) if possible.  • If the cursor is not on the leading keyword of the BLOCK flavor of construct, will assume it is the STATEMENT flavor, so will try to find the appropriate statement modifier.		
Move to next interpolated	C-c C-v	(cperl-next-interpolated-REx &optional SKIP BEG LIMIT)	<ul> <li>Move point to next REx which has interpolated parts.</li> <li>SKIP is a list of possible types to skip, BEG and LIMIT are the starting point and the limit of search (default to point and end of buffer).</li> <li>SKIP may be a number, then it behaves as list of numbers up to SKIP; this semantic may be used as a numeric argument.</li> <li>Types are 0 for / \$rex /o (interpolated once), 1 for /\$rex/ (if \$rex is a result of qr//, this is not a performance hit), t for the rest</li> </ul>		
	С-с С-х	(cperl-next-interpolated-REx-0)	Move point to next REx which has interpolated parts without //o.		
	С-с С-у	(cperl-next-interpolated-REx-1)	Move point to next REx which has interpolated parts without //o.  Skips RExes consisting of one interpolated variable.  Note that skipped RExen are not performance hits.		
Toggle space fix	C-c C-w	(cperl-toggle-construct-fix)	Toggle whether 'indent-region'/'indent-sexp' fix whitespace too.		
Show command info	C-c C-h F	(cperl-info-on-command COMMAND)	Show documentation for Perl command COMMAND in other window.  If perl-info buffer is shown in some frame, uses this frame.  Customized by setting variables 'cperl-shrink-wrap-info-frame', 'cperl-max-help-size'.		
peridoc at point	C-c C-h P	(cperl-perldoc-at-point)	Run a 'perldoc' on the word around point.		
	C-c C-h p	(cperl-perldoc WORD &optional SECTION)	Run the shell command 'perldoc' on WORD, on Win32 platforms.		
toggle Perl auto- help	C-c C-h a	(cperl-toggle-autohelp)	Toggle the state of Auto-Help on Perl constructs (put in the message area).  • Delay of auto-help controlled by 'cperl-lazy-help-time'.		
Show Perl doc	C-c C-h f	(cperl-info-on-current-command)	Show documentation for Perl command at point in other window.		

Description	<u>Keystroke</u>	Function	<u>Note</u>
Help on symbol at point	C-c C-h v	(cperi-get-help)	Get one-line docs on the symbol at the point.  • The data for these docs is a little bit obsolete and may be in fact longer than a line.
Insert matching parens	• ( • < • [	(cperl-electric-paren ARG)	Insert an opening parenthesis or a matching pair of parentheses.  Controlled by 'cperl-electric-parens' and 'cperl-hairy' user-options.
(toggle with C-c C-e)	• )	(cperl-electric-rparen ARG)	Insert a matching pair of parentheses if marking is active.  If not, or if we are not at the end of marking range, would self-insert.  Controlled by 'cperl-electric-parens' and 'cperl-hairy' user-options.
Insert : and indent	:	(cperl-electric-terminator ARG)	Insert character and correct line's indentation.
Insert; and indent	;	(cperl-electric-semi ARG)	Insert character and correct line's indentation.
Insert { and indent	{	(cperl-electric-lbrace ARG &optional END)	Insert character, correct line's indentation, correct quoting by space.
Insert } and indent	}	(cperl-electric-brace ARG &optional ONLY-BEFORE)	Insert character and correct line's indentation.  If ONLY-BEFORE and 'cperl-auto-newline', will insert newline before the place (even in empty line), but not after. If after ")" and the inserted char is "{", insert extra newline before only if 'cperl-extra-newline-before-brace'.
Deleted and possibly untabify	DEL	(cperl-electric-backspace ARG)	Backspace, or remove whitespace around the point inserted by an electric key.  • Will untabify if 'cperl-electric-backspace-untabify' is non-nil.
Indent Perl code	TAB	(cperl-indent-command &optional WHOLE-EXP)	Indent current line as Perl code, or in some cases insert a tab character.  • If 'cperl-tab-always-indent' is non-nil (the default), always indent current line. Otherwise, indent the current line only if point is at the left margin or in the line's indentation; otherwise insert a tab.  • A numeric argument, regardless of its value, means indent rigidly all the lines of the expression starting after point so that this line becomes properly indented. The relative indentation among the lines of the expression are preserved.
Newline and indent	с-ј	(newline-and-indent)	Insert a newline, then indent according to major mode.  Indentation is done using the value of 'indent-line-function'.  In programming language modes, this is the same as TAB.
Indent	С-м-q	(cperl-indent-exp)	Simple variant of indentation of continued-sexp.  Will not indent comment if it starts at 'comment-indent' or looks like continuation of the comment on the previous line.  If 'cperl-indent-region-fix-constructs', will improve spacing on conditional/loop constructs.
Indent	C-M-\	(cperl-indent-region START END)	Simple variant of indentation of region in CPerl mode.  Should be slow. Will not indent comment if it starts at 'comment-indent' or looks like continuation of the comment on the previous line.  Indents all the lines whose first character is between START and END inclusive.  If 'cperl-indent-region-fix-constructs', will improve spacing on conditional/loop constructs.
Lineup	C-M-	(cperl-lineup BEG END &optional STEP MINSHIFT)	Lineup construction in a region.  Beginning of region should be at the start of a construction.  All first occurrences of this construction in the lines that are partially contained in the region are lined up at the same column.  MINSHIFT is the minimal amount of space to insert before the construction.  STEP is the tabwidth to position constructions.  If STEP is nil, 'cperl-lineup-step' will be used (or 'cperl-indent-level', if 'cperl-lineup-step' is nil).  Will not move the position at the start to the left.

## Emacs & Perl — References

Document	Notes