Inserting Text

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Inserting Text Greek letter File/Directory name Software License To-do note Date/Time Automatic Time Stamping Automatic Copyright note Commented lines Smart Dash mode Smartparens mode Text tempo skeletons Yasnippet	Customization to co Simple command PEL specialized co The lice extern The smart-da The smartpar Specialized temple PEL tempo skele The yasnippe The yasnippe Hydra-based inser	ntrol automatic insertion of time based text insertions: ommands to insert formatted to nal package activated by path external package activated activates activate-based text insertion: actions based templates for generate external package activated activa	ext like time stamps, file path , file name, copyright notice, Greek letters, commented lines, etc ext like time stamps, file path , file name, copyright notice, Greek letters, commented lines, etc ext like time stamps, file path , file name, copyright notice, Greek letters, commented lines, etc extended by pel-use-smart-dash, used to automatically convert dash into underscore when typing. extend by pel-use-smartparens to provide automatic insertion of balanced block pairs for code. extended by pel-use-smartparens to provide automatic insertion header, document section header. d by pel-use-yasnippet to insert code from predefined snippets. activated by pel-use-yasnippet-snippets which provides a large amount of snippets.
Open this PDF file. See also: <u>National Help/Info</u>	• <f11> i <f1> • <f11> y <f1> • <f11> _ <f1></f1></f11></f1></f11></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the \(\subseteq \text{Inserting Text} \) local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
<u>> Customize</u> PEL Text Insertions control	<f11> i <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL text insertion support: lice, smart-dash, smartparens, tempo, time-stamp, yasnippet. Also pel-activate-f9-for-greek (see below). • If OTHER-WINDOW is non-nil (use C-u), display in other window.
∑ Customize Emacs Text Insertions control	<f11> i <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs text insertion support: lice, smart-dash, tempo, time-stamp, yasnippet
Insert Greek Letter See also: ∑ Input Method In macOS you can also: add Greek as a Keyboard Input Sources and temporary select it to enter Greek characters directly. Start pel-∑greek Hydra	• <f9> % • <f6> g % <f7> <f6> <f6> <f6> = <</f6></f6></f6></f7></f6></f9>	Examples: <f9> a inserts 0 • The insertions work everyw • Use <f9> C-h or which- The <f9> key binding is of The <f6> g binding is al This is not a command bo Start the Greek letter Hydra.</f6></f9></f9></f9>	there insert is allowed, including in response to prompts. key mode and type <f9> to see all keys. only available when the pel-activate-f9-for-greek user-option is turned on. lways available. und to a key: it's an additional set of bindings added to Emacs key-translation-map.</f9>
Quickly type succession of Greek characters See also: Input Method		character to insert them, late In terminal mode the cursor Requires the hydra extern Exit the hydra by typing <free <free="" active:="" all="" auto="" by="" can="" control="" cut="" exit="" hydra="" hydra,="" in="" is="" meta.="" mode="" no="" prefix="" terminal="" th="" the="" the<="" this="" to="" typing="" with="" you="" μπορείτε="" πλήκτρα=""><th>rools Defs Lisp-Interaction Help type Greek text by pressing the Meta keys. ε να πληκτρολογήσετε ελληνικό κείμενο πατώντας τα digit keys can be typed: 0123456789 ailable: use ``<f11> u u`` instead. ursor keys may not work though. Use C-b, C-f, C-n, C-p instead.</f11></th></free>	rools Defs Lisp-Interaction Help type Greek text by pressing the Meta keys. ε να πληκτρολογήσετε ελληνικό κείμενο πατώντας τα digit keys can be typed: 0123456789 ailable: use `` <f11> u u`` instead. ursor keys may not work though. Use C-b, C-f, C-n, C-p instead.</f11>
Insert file/directory name	The following comman		r directory of the current file or file in specified window.
Insert, at point, name of: current filename by default name of file in window identified by command numeric argument	• <f11> i f • <f6> f</f6></f11>	(pel-insert-filename &optional N USE-TILDE DIR-ONLY)	Insert the file name of the currently edited file at point. • By default, or with 1, insert filename of current buffer with complete absolute path. • With a numeric argument: identify the window where the file name is taken: • 8: up, 2: down, 4: left, 6: right. Any other number identifies the current window. • When the numeric argument is positive the file with complete absolute path is inserted, • With negative numeric argument the path is omitted. Same as above but also append a colon and a line number, followed by a line end.
Append line number of point in visited file	• <f6> F</f6>	line &optional N)	Useful for manually building a list of files inside a buffer. Later use the pel-open-at-point command M-<£6> (see <u>▼ File-mngt</u>) to open that file and move point to that line.
If file is in user home, use ~ at the beginning Insert, at point, name of:	• <f11> i M-f • <f6> M-f • <f11> i C-f</f11></f6></f11>	(pel-insert-filename-wtilde &optional N) (pel-insert-dirname	Same as first command above, except that if the file is located in the current user home, insert the Unix-style tilde character ~ in place of the user home directory name. Insert the directory path name of the currently edited file at point.
current dirname by default dirname of file in window identified by command numeric argument	• <ff> C-f</ff>	&optional N USE-TILDE)	 By default, or with 1, insert directory name of file in current buffer. With a numeric argument: identify the window where the directory name is taken: 8: up, 2: down, 4: left, 6: right. Any other number identifies the current window. When the numeric argument is positive the file with complete absolute path is inserted.
If file is in user home, use ~ at the beginning	• <f11> i C-M-f • <f6> C-M-f</f6></f11>	(pel-insert-dirname-wtilde &optional N)	Same as the above command, except that <i>if the file is located in the current user home</i> , insert the Unix-style tilde character ~ in place of the user home directory name.
Insert software license Insert software license text	• <f11> i L • <f6> L</f6></f11>	(lice NAME)	Insert license and headers at point. Prompts for license NAME, which is a license template name like "mit", "gpl-3.0", etc The list is available with TAB completion: hit TAB on prompt to get the complete list of templates. PEL activates it if pel-use-lice user option is t.
Insert to-do note		te format is: [:todo (DA' serts the date and user name	TE), by (USER):] e. Other popular prefixes can be used: TODO: and TO-DO: are just a few.
Insert To-Do note	• <f11> i n • <f6> n</f6></f11>	(pel-insert-todo-note &optional UTC)	Insert a to-do note template comment. The format is configured by the pel-todo-note-text and the pel-todo-note-date-format user options. • If "(USER") is repent in pel-todo-note-text, it is replaced by the user name. If it has "(DATE)", it is replaced by the date using the format specified pel-todo-note-date-format. By default the local date is entered. Use the C-u prefix to use UTC instead. • Point is placed one character before the end of the inserted text, where the text should be typed.
Customize to-do note format	<f11> i <f4> n</f4></f11>	(pel-customize-todo-note)	Open the customize buffer to change the to-do note format user options.

Description Insert date & time	Keystroke The following comman	Function ds insert time stamps of specif	Note	
misert date & time	Format	ds insert time stamps of specif	Date & Week-day Date & Time Date, Week-day & Time	
	User-selected	-	Date & Week-day Date & Time Date, Week-day & Time	
	<u>ISO-8601</u> forma	t <f11> i M-d </f11>	<f11> i M-D <f11> i M-t <f11> i M-T</f11></f11></f11>	
	 Each of these commands insert the local date/time by default. Use the C-u prefix to insert the UTC date/time instead. User-selected formats are specified by custom variables. Use <f11> i <f4> to access the relevant customize buffer. The docstring show the string generated by the format selected at the time PEL was last byte-compiled.</f4></f11> 			
Customize date/time format	<f11> i <f4> d</f4></f11>	(pel-customize-insert-date-time)	Open the customize buffer to change the date/time insertion, allowing you to change the formats used for each of the following commands.	
Insert current date	<f11> i d</f11>	(pel-insert-current-date &optional UTC)	Insert current date (only, no week-day, no time) at point. Like: 2023-10-15 • Local by default, UTC if C-u prefix used.	
Insert current date and week day	<f11> i D</f11>	(pel-insert-current-date- wd &optional UTC)	Insert current date and week-day (no time) at point. Like: Sunday, October 15 2023 • Local by default, UTC if C-u prefix used.	
Insert current date & time	<f11> i t</f11>	(pel-insert-current-date- time &optional UTC)	Insert current date and time at point. Like: 2023-10-15 13:20:24 EDT • Local by default, UTC if C - u prefix used.	
Insert current date, week-day & time	<f11> i T</f11>	(pel-insert-current-date- time-wc &optional UTC)	Insert current date, week-day and time at point. Like: Sunday, October 15 2023 at 13:20:24 EDT • Local by default, UTC if C - u prefix used.	
Insert current ISO 8601 date	<f11> i M-d</f11>	(pel-insert-current-iso- date &optional UTC)	Insert ISO 8601 conforming abbreviated YYYY-MM-DD format date. Like: 2023-10-15 • Local by default, UTC if C-u prefix is used.	
Insert current ISO 8601 date and week day	<f11> i M-D</f11>	(pel-insert-current-iso-date-wd &optional UTC)	Insert ISO 8601 conforming abbreviated week-day format like: 2023-10-15-W41-7 • Local by default, UTC if C - u prefix is used.	
Insert current ISO 8601 date & time	<f11> i M-t</f11>	(pel-insert-current-iso- date-time &optional UTC)	Insert ISO 8601 conforming abbreviated date/time/zone format like: 2023-10-15T13:20:24-0400 • Local by default, UTC if C-u prefix is used. Example: 2023-10-15T17:20:24+0000	
Insert current ISO 8601 date, week-day & time	<f11> i M-T</f11>	(pel-insert-current-iso- date-time-wc &optional UTC)	Insert ISO 8601 conforming abbreviated week-day format, like: 2023-10-15T13:20:24-0400 W41-7 • Local by default, UTC if C-u prefix is used. Example: 2023-10-15T17:20:24+0000 W41-7	
Automatic File Time Stamp on file save	This can either be done	e via Emacs customization syst	tes. It must be activated by adding the time-stamp function to the before-save-hook variable. tem or explicitly inside your init file with the following code:	
	The time stamp will		-stamp) inside their first 8 lines, a line that looks like one of the following:	
References: • TimeStamps @ EmacsWiki • Change time stamp format	• Time-stamp: <> • Time-stamp: " " You can be used a facility and get Empers to undete all corts of time stamp formats, even inside course and attempted.			
in: • markdown file	Emacs cor	You can, however change these defaults and get Emacs to update all sorts of time stamp formats, even inside source code statements: Emacs controls automatic insertion of timestamp with the following variables:		
reStucturedText file	 time-stamp-pattern consists of 4 parts, each one controlled by a variable: time-stamp-line-limit: identifies where in the file the time stamp can be located. Defaults to 8: the first 8 lines. 			
See also: File mngt	 time-stamp-start: identifies the text pattern that precedes the time stamp. time-stamp-end: identifies the end of the time stamp. 			
	 time-stamp-format specifies the format of the time stamp. Something like "%:y-%02m-%02d %02H:%02M:%02S %u" to specify the date and time in ISO format, with the user login's name. 			
	time-stamp-time-zone specifies the time zone selection: nil : Emacs local time			
	t : Universal time wall : system wall clock time Transferred by a Transferred wariable.			
	 TZ : controlled by a TZ environment variable The time-stamp-format and time-stamp-time-zone variables can be set in your init file or via the Emacs customization system. They are defined in the time-stamp customization group. 			
	• 🕏 To change the format or the pattern preceding or after the automatically updated time stamp, it is best to use file local variables: this will			
	allow automatic time stamp updates in files with various formats. As an example, see the top and end of the <u>PEL manual raw format file</u> . By default, the time-stamp string must be placed within the first 8 lines of the file, otherwise it will not be updated automatically.			
	PEL provides the ex	If you want it located somewhere else in your file set the time-stamp-line-limit file local variable. PEL provides the extra user-option to control the automatic generation of time-stamps:		
	 pel-update-time-stamp user-option controls whether time-stamps are automatically update time stamps in all files where a valid time-stamp corresponding to Emacs settings as described above. Set it to t (the default) to allow automatic time stamp updates. Set it to nil to prevent them. You can also toggle it globally for the current editing session by using the <f11> f M-t key sequence.</f11> To insert a non-updatable time stamp, the PEL package provides a set of text insert commands which include inserting a time stamp. 			
Update file time stamp	<f11> f t</f11>	(time-stamp)	Force update the time stamp string(s) in the current buffer. • Updates a time stamp of format recognized by <i>Emacs current settings</i> even when automatic	
See also: <u>∑ File mngt</u>			 Opdates a time stamp of format recognized by <i>Emacs current settings</i> even when automatic time-stamp update is off. More information about the "<i>Emacs current settings</i>" in the description block above. 	
Toggle time stamp automatic update	<f11> f M-t</f11>	(time-stamp-toggle-active &optional ARG)	Toggle 'time-stamp-active', setting whether <f11> f t updates a buffer. • With ARG, turn time stamping on if and only if arg is positive.</f11>	
Inserting &	Emacs has built-in support for insertion and update of copyright notices inside files. Two commands, shown below, are provided to manually insert or update the file's copyright notice.			
Automatically Updating Copyrights	 The copyright notice can be automatically updated by adding the copyright-update function to the list of before-save-hook variable with the following code: (add-hook 'before-save-hook 'copyright-update) 			
	To be automatically updated, the copyright notice must be placed within an area at the beginning of the file specified by the value of the copyright-limit variable, normally defined as the first 2000 characters. This variable is customizable.			
Insert copyright notice See also: <u>File mngt</u>	<f11> i c</f11>	(copyright &optional STR ARG)	Insert a copyright by \$ORGANIZATION notice at cursor. • If the ORGANIZATION environment variable is not available, Emacs prompts for it.	
Update file's copyright notice	<f11> i M-c</f11>	(copyright-update &optional ARG	Update copyright notice to indicate the current year. • With prefix ARG, replace the years in the notice rather than adding the current year after them.	
		INTERACTIVEP)	If necessary, and 'copyright-current-gpl-version' is set, any copying permissions following the copyright are updated as well.	
 Only update exiting notice. Does not create one if it's missing. 	If you want auto Without PEL add	copyright-update does not warn if there is no copyright in the current buffer to update. It does not create a missing notice. copyright-update does not warn if there is no copyright in the current buffer to update. It does not create a missing notice. display and it is saved, set the pel-update-copyright user option to t. Without PEL add the following inside your init.el file:		
	(add-hook '	before-save-hook 'copyr	right-update)	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Insert Commented Lines	adornment level used identified comment st	for reStructuredText sections.	s or just underlines the current line of text using the character corresponding to one of the The strings are commented according to the major mode of the current buffer. If the buffer has no or them the first time it is used in that type of buffer. nments table.
Insert commented line See also: • <u>∑ Comments</u> • <u>∑ Filling/Justification</u>	• <f11> i 1 • <f6> 1</f6></f11>	(pel-insert-line &optional LINELEN)	Insert a (commented) line before/at current line. If point is at the beginning of the line insert it there. If point is in the middle of a line, move point at beginning of line before inserting it. The number of dash characters of the line is specified by LINELEN: If LINELEN is not specified the buffer's fill-column value is used. It supports several programming and markup language and uses the comment style identified by the file extension. If the comment style is unknown the command prompts for one. fill-column is customizable and can be used as a file or directory variable.
Comment-underline current line with level adornment 1-9	<f11> _ *</f11>	(pel-commented-adorn-1)	Insert a commented level-x reST line adornment at point. • (*) := 1 to 9 for levels 1 to 9
Comment-underline current line with level 10 adornment	<f11> _ 0</f11>	(pel-commented-adorn-10)	Insert a commented level-10 reST line adornment at point.
Smart Dash Mode	type. Unfortunately used. Typing under helps. You can inse More information is Requires the smart. To activate smart-	most programming languages (score requires hitting the Shift kert underscore in text by typing available in the author's page. t-dash external package.	knows that using dash as word separator instead of underscore is more natural and faster to (all non-Lisp?) have restrictions on the characters available in identifiers and underscore is often ey and it annoys some people that enjoyed writing Lisp code. This is where the smart-dash-mode the dash key without hitting the Shift key! A very useful mode. PEL activates it when pel-use-smart-dash is set to t. dash-mode to the pel- <mode>activates-minor-mode user-option for the specific mode.</mode>
Toggle smart-dash mode	for other modes,	add the mode name to the pel-	-modes-activating-smart-dash-mode user-option.
See also: •	to type all_lowercas While Smart-Dash is identifier character. If Smart-Dash modwill also activate Sr postfix-decrement at to or not. Note that Normally when small However, with PEL. In Numlock OFF. with no market. with area mart. In Numlock ON: with area mart. with area mart.	se_c_identifiers as comfortably a mode is active, you can type C-You might need to do this if yo e is activated while in a C-like mart-Dash-C mode, which trans aren't made more difficult by Sn this will necessitate that you ty nart-dash-mode is active the number, the behaviour of the keypad '-E: darea: instanted: kill ked with er/expand-region: kill with the command in the comma	sert an underscore after letter, number or underscore, dash otherwise hore the marked area; insert a dash at point duces the marked area semantically as controlled by er/expand-region d key support, see Numkeypad
Smartparens Mode • Smartparens manual See also: ∑x Smartparens	This uses the sma • Smartparents	rtparens external package.	rens minor mode. PEL binds a set of keys, described below, to toggle activation of that mode. PEL activates it when pel-use-smartparens is set to t. ain keys, namely those that are part of any pair or tag. smartparens-strict-mode: SP/s
Help on smartparens	<f11> (?</f11>	(sp-cheat-sheet &optional ARG)	Generate a cheat sheet of all the smartparens interactive functions. Shows inside Emacs buffer. • Without a prefix argument, print only the short documentation and examples. • With non-nil prefix argument ARG, show the full documentation for each function. • You can follow the links to the function or variable help page. • To get back to the full list, use M-x help-go-back. • You can use 'beginning-of-defun' and 'end-of-defun' to jump to the previous/next entry. • Examples are fontified using the 'font-lock-string-face' for better orientation.
Describe user system	<f11> (M-?</f11>	(sp-describe-system STARTERKIT)	Describe user's system. Prompt for starter kit: Evil, Spacemac, Vanilla. • The output of this function can be used in bug reports.
Toggle smartparens mode	<f11> ((</f11>	(smartparens-mode &optional ARG)	Toggle smartparens mode.
Toggle smartparens-strict mode	<f11> ()</f11>	(smartparens-strict-mode &optional ARG)	 Toggle the strict smartparens mode. When strict mode is active, 'delete-char', 'kill-word' and their backward variants will skip over the pair delimiters in order to keep the structure always valid (the same way as 'paredit-mode' does). This is accomplished by remapping them to 'sp-delete-char' and 'sp-kill-word'. There is also function 'sp-kill-symbol' that deletes symbols instead of words, otherwise working exactly the same (it is not bound to any key by default). When strict mode is active, this is indicated with "/s" after the smartparens indicator in the mode list
Toggle smartparens mode	<f11> (M-(</f11>	(smartparens-global-mode &optional ARG)	Toggle Smartparens mode in all buffers. • With prefix ARG, enable Smartparens-Global mode if ARG is positive; otherwise, disable it. • Smartparens mode is enabled in all buffers where 'turn-on-smartparens-mode' would do it.
Toggle smartparens-strict mode	<f11> (M-)</f11>	(smartparens-global-strict-mode &optional ARG)	Toggle Smartparens-Strict mode in all buffers. With prefix ARG, enable Smartparens-Global-Strict mode if ARG is positive; otherwise, disable it. Smartparens-Strict mode is enabled in all buffers where 'turn-on-smartparens-strict-mode' would do it.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Text and code skeletons			asy insertion of predefined text in Emacs.
tempo skeletons	 Emacs provides the built-in skeleton mechanism and the tempo skeletons. PEL supports both. They are used a little bit differently. PEL provides key bindings to the tempo skeletons: the generic code templates, accessible via the <f6> prefix key, and the language-specific code templates, accessible via the <f12> key prefix.</f12></f6> 		
Generic skeletons	PEL provides generic tempo skeletons as well as some specialized for specific programming languages. The generic skeletons are less powerful but often good enough for most types of files. They support all types of files recognized by Emacs as long as Emacs understands the way comments work for the file type which is normally the case. If Emacs does not know the file type the commands assume the file uses a comment start only and will prompt for that string.		
<u>∑ Customize</u> PEL Text Insertions control	<f6> <f2></f2></f6>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL generic tempo skeleton customization groups that control the format of the various skeletons including the generic skeleton used by the <f6> h key (se below). • If OTHER-WINDOW is non-nil (use C-u), display in other window.</f6>
Insert generic file module header block — Language	<f6> h</f6>	(pel-generic-file-header)	Insert a file header block at the top of the file. Works only for buffer visiting a file.
After inserting the template, navigate though areas that must be filled with: • tempo-forward-mark: C-c. • tempo-backward-mark: C-c, See examples in manual	Supports all text file types. Supports all programming and markup language files that have a dedicated major mode. It is also available in buffers for major modes explicitly supported by the <f12> <f12> key prefix. This way, those modes can use two different commands to insert file header blocks, each having its own different format. It supports several programming and markup language and uses the comment style identified by the file extension. If the comment style is unknown the command prompts for one. The layout of the entered text is controlled by user options. It is possible to create a user-specified skeleton this command will used instead of the one provided by PEL. Specify the format of the header via the user-options in the pel-pkg-generic-code-style customization group accessible via <f6> <f2> The files that have no extensions are often used in Unix-like OS shell scripts. These files are also supported as Emacs can recognize them if they are stored in a bin directory. PEL also has special support for them and is controlled by the pel-sh-script-skeleton-control customization group, which is accessible as a child of the main group. After inserting the template you can use the tempo-forward-mark and tempo-backward-mark to move point to the beginning of each section that must be filled. The command key binding <f6> h is available only 1 second after Emacs has started.</f6></f2></f6></f12></f12>		
Toggle pel-tempo-mode	<f6> SPC</f6>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set of keys are only available when Emacs runs in graphics mode. In the pel-generic-file-header command inserts the text using a tempo skeleton: the PEL tempo mode is automatically activated by typing <f6> h.</f6>
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.
Store PEL code template settings in .dir-locals.el to fine-tune layout of files in a directory tree	Emacs user options by default take effect globally. But by using file and directory variables (see File/Directory Variables) they can also be used to take effect on a single file or all files inside a directory tree. So by default, the user options that control the PEL tempo template take effect globally. If you want to change the behaviour for only one file, write the user option control block at the end of that file. If you want to control the behaviour of the PEL tempo templates for all files inside a directory tree create a .dir-locals file and store the values of the relevant options variables inside that file. This allows you to control the user options affecting the format of the tempo templates precisely.		
Example:	Although the default settings of pel-generic-skel-module-section-titles identifies the 3 sections "Module Description", "Dependencies" and "Code" you can keep this for other files but inside a directory you can force all shell-mode files to use 2 sections: "Description" and "Script" and ensure that all files have a 1-line copyright notice with the .dir-locals.el file containing the following code:		
	;;; Directory Local Variables		
	;;; For more information see (info "(emacs) Directory Variables") ((nil . ((pel-generic-skel-with-copyright . t)		
Entering Templated Text with Tempo Skeletons See also: • Major mode specific: • NI - C • NI - C++ • NI - Emacs Lisp • NI - Erlang • M reStructuredText	Emacs built-in support includes the tempo skeletons . PEL implements extension to the tempo skeleton Emacs built-in package under two prefix keys: The commands under the <f6> prefix keys insert template text that are adapted to each major mode. They are generic in nature, and dynamically adapt to the major mode and the comment style supported by the major mode. The layout of the templates is the same for every major mode, they differ only by the comment strings. The commands under the <f12> <f12> prefix key insert templates specialized for the programming or markup language of the major mode that support this key prefix. PEL attempts to use the same key bindings for equivalent concepts (such as file header block) inside each mode specific instance of the <f12> <f12> key maps as much as possible. The tempo skeletons provided by PEL can be quite complex and their formats are controlled by user options. PEL currently only support this key prefix with for the following major modes (more are planned): C, C++, Emacs Lisp, Erlang reStructuredText</f12></f12></f12></f12></f6>		
Major-mode specific Tempo Templates Prefix	<f12> <f12></f12></f12>	This command prefix is avaThe commands under this properties	t of tempo skeleton commands. iilable only for some major modes (see the list in the first column) of the section row above. prefix insert text specialized for their specific major mode, as opposed to the commands bound to nore information see the language specialized reference table.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Entering Templated Test with <u>Yasnippet</u> • See also: <u>▼ Customize</u>	PEL also supports the popular vasanippet external package which provides a large set of code snippets for a large set of major modes. • To use yasnippets, you must type the snippet abbreviation and then hit the TAB key to expand the text. • Requires vasanippet activated when pel-use-yasnippet is set to t or to use-from-start. • Requires vasanippet-snippets activated when pel-use-yasnippet-snippets is set to t. • Use the key first row). • The list of snippets available in the current buffer is listed in the menu bar (see menus menus) and can also be listed using the yas-describe-tables command (which PEL binds to f11> y t). PEL binds the following yasnippet commands to keys in the pel: key prefix, shown below.		
<u>∑ Customize</u> PEL yasnippet use	<f11> y <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Yasnippet text insertion support. • If OTHER-WINDOW is non-nil (use C-u), display in other window.
<u>∑ Customize</u> Emacs yasnippet control	<f11> y <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Yasnippet groups: yasnippet, yasnippet-snippets, yas-minor
Toggle YASnippet minor mode on/off	<f11> y y</f11>	(yas-minor-mode &optional ARG)	Toggle YaSnippet mode.
Toggle YASnippet global	With no argument, this command toggles the mode. Positive prefix argument turns on the mode. Negative prefix argument turns of YASnippet mode key bindings: key binding C-c & C-n yas-new-snippet C-c & C-s yas-insert-snippet C-c & C-v yas-visit-snippet-file Column		Toggle Yas minor mode in all buffers.
mode on/off	7 -	ARG)	With prefix ARG, enable Yas-Global mode if ARG is positive; otherwise, disable it.
Expand snippet whose name is just before point	TAB	(yas-expand &optional FIELD)	 Expand a snippet before point. If no snippet expansion is possible, do nothing. This key binding is only active when the YASnippet mode is active. Once the snippet was expanded the TAB key normal behaviour is restored.
Write a new snippet	• <f11> y n</f11>	(yas-new-snippet &optional NO-TEMPLATE)	 Pops a new buffer for writing a snippet. Expands a snippet-writing snippet, unless the optional prefix arg NO-TEMPLATE is non-nil.
•	• C-c & C-n	NO-TEIVII EATE)	
Prompt for snippet & insert it	• <f11> y s</f11>	(yas-insert-snippet &optional NO-CONDITION)	Choose a snippet to expand, pop-up a list of choices according to 'yas-prompt-functions'. • With prefix argument NO-CONDITION, bypass filtering of snippets by condition.
	• C-c & C-s		
Visit a snippet file	• <f11> y v</f11>	(yas-visit-snippet-file)	Choose a snippet to edit, selection like 'yas-insert-snippet'. • Only success if selected snippet was loaded from a file. Put the visited file in 'snippet-mode'.
	• C-c & C-v		Only Success in Science Shipper was loaded from a file. Fut the visited life in Shipper-Houe.
Display all snippets for current major mode	<f11> y t</f11>	(yas-describe-tables &optional WITH-	Display snippets for each table.
		NONACTIVE)	

Inserting Text — References

Topic & link	Description
GNU Emacs Manual: Time Stamps	
Smart-Dash Mode homepage	A description of this extremely useful mode and why it was created.