





**CHECK** 

GALAHAD

USER DOCUMENTATION

GALAHAD Optimization Library version 3.3

#### 1 SUMMARY

This package uses finite difference approximations to check the gradient of an objective function  $f(\mathbf{x})$ , the Jacobian matrix of a constraint function  $\mathbf{c}(\mathbf{x})$ , and the second derivative Hessian matrix of the Lagrangian function  $L(\mathbf{x}, \mathbf{y}) = f(\mathbf{x}) - \mathbf{c}(\mathbf{x})^T \mathbf{y}$ . These quantities are typically associated with a nonlinear optimization problem

minimize  $f(\mathbf{x})$ 

subject to the general linear constraints

$$a_i^l \leq \mathbf{a}_i^T \mathbf{x} \leq a_i^u, \quad i = 1, \dots, m_a,$$

general nonlinear constraints

$$c_i^l \leq c_i(\mathbf{x}) \leq c_i^u, \quad i = 1, \dots, m,$$

and simple bound constraints

$$x_i^l \le x_i \le x_i^u$$
,  $j = 1, \dots, n$ ,

where the vectors  $\mathbf{a}_i$ ,  $\mathbf{a}^l$ ,  $\mathbf{a}^u$ ,  $\mathbf{c}^l$ ,  $\mathbf{c}^u$ ,  $\mathbf{x}^l$ , and  $\mathbf{x}^u$  are given, and the vectors  $\mathbf{x} \in \mathbb{R}^n$  and  $\mathbf{y} \in \mathbb{R}^m$  are known as the primal and dual (Lagrange multiplier) vectors, respectively. The user may choose to perform a "cheap" verification of the requested derivatives, or a more detailed and "expensive" check. Function values can be supplied via internal subroutine evaluation or reverse communication.

ATTRIBUTES — Versions: GALAHAD\_CHECK\_single and GALAHAD\_CHECK\_double. Uses: GALAHAD\_SYMBOLS, GALAHAD\_SPECFILE, GALAHAD\_SPACE, GALAHAD\_MOP, GALAHAD\_SMT, and GALAHAD\_NLPT. **Date:** September 2010. **Origin:** D. P. Robinson, University of Oxford, UK, and N. I. M. Gould, Rutherford Appleton Laboratory. **Language:** Fortran 95 + TR 15581 or Fortran 2003.

# 2 HOW TO USE THE PACKAGE

Access to the package requires a USE statement such as

Single precision version

USE GALAHAD\_CHECK\_single

Double precision version

USE GALAHAD\_CHECK\_double

If it is required to use both modules at the same time, the derived types SMT\_type, NLPT\_problem\_type, CHECK\_-control\_type, CHECK\_inform\_type, CHECK\_data\_type, CHECK\_reverse\_communication\_type and NLPT\_userdata\_type (Section 2.2), and the subroutines CHECK\_initialize, CHECK\_verify, CHECK\_terminate (Section 2.3), and CHECK\_read\_specfile (Section 2.7) must be renamed on one of the USE statements.

## 2.1 Matrix storage formats

The Jacobian matrix  $\mathbf{J} = \nabla_x \mathbf{c}(\mathbf{x})$  and the Hessian matrix  $\mathbf{H} = \nabla_{xx} L(\mathbf{x}, \mathbf{y})$  may be stored in a variety of input formats.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

CHECK GALAHAD

#### 2.1.1 Dense storage format

The matrix **J** is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. Component n\*(i-1)+j of the storage array J%val will hold the value  $j_{ij}$  for  $i=1,\ldots,m$  and  $j=1,\ldots,n$ . Since **H** is symmetric, only the lower triangular part (that is the part  $h_{ij}$  for  $1 \le j \le i \le n$ ) should be stored. In this case the lower triangle will be stored by rows, that is component i\*(i-1)/2+j of the storage array H%val will hold the value  $h_{ij}$  (and, by symmetry,  $h_{ji}$ ) for  $1 \le j \le i \le n$ .

### 2.1.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l-th entry of J, its row index i, column index j and value  $j_{ij}$  are stored in the l-th components of the integer arrays J%row, J%col and real array J%val. The order is unimportant, but the total number of entries J%ne is also required. Since H is symmetric, the same scheme is applicable, except that only the entries in the lower triangle should be stored.

#### 2.1.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row i+1. For the i-th row of  $\mathbf{J}$ , the i-th component of a integer array J%ptr holds the position of the first entry in this row, while J%ptr (m+1) holds the total number of entries plus one. The column indices j and values  $j_{ij}$  of the entries in the i-th row are stored in components l= J%ptr $(i),\ldots,$ J%ptr (i+1)-1 of the integer array J%col, and real array J%val, respectively. Since  $\mathbf{H}$  is symmetric, the same scheme is applicable, except that only the entries in the lower triangle should be stored.

For sparse matrices, this scheme almost always requires less storage than its predecessor.

# 2.1.4 Sparse column-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in column j appear directly before those in column j+1. For the j-th column of  $\mathbf{J}$ , the j-th component of the integer array J%ptr holds the position of the first entry in this column, while J%ptr (n+1) holds the total number of entries plus one. The row indices i and values  $j_{ij}$  of the entries in the j-th column are stored in components l = J%ptr $(j), \ldots, J$ %ptr (j+1)-1 of the integer array J%row, and real array J%val, respectively. Since  $\mathbf{H}$  is symmetric, the same scheme is applicable, except that only the entries in the lower triangle should be stored.

# 2.1.5 Diagonal storage format

If **J** is diagonal (i.e.,  $j_{ij} = 0$  for all  $1 \le i \ne j \le n$ ) only the diagonal entries  $j_{ii}$  for  $1 \le i \le n$  should be stored, and the first n components of the array J%val should be used for this purpose. The same holds for **H**.

#### 2.2 The derived data types

Seven derived data types are accessible from the package.

#### 2.2.1 The derived data type for holding matrices

The derived data type SMT\_TYPE is used to hold the Jacobian matrix J and the Hessian matrix H. The components of SMT\_TYPE used here are:

- m is a scalar component of type default INTEGER that holds the number of rows of the matrix.
- is a scalar component of type default INTEGER that holds the number of columns of the matrix.

- ne is a scalar variable of type default INTEGER that holds the number of matrix entries.
- type is a rank-one allocatable array of type default CHARACTER that is used to indicate the matrix storage scheme used. Its precise length and content depends on the type of matrix to be stored (see §2.2.2).
- is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) and dimension at least ne, that holds the values of the entries. Each pair of off-diagonal entries  $h_{ij} = h_{ji}$  for the *symmetric* matrix **H** is represented as a single entry (see §2.1.1–2.1.3). Any duplicated entries that appear in the sparse co-ordinate, row-wise, or column-wise schemes will be summed.
- row is a rank-one allocatable array of type default INTEGER, and dimension at least ne, that may hold the row indices of the entries (see §2.1.2).
- is a rank-one allocatable array of type default INTEGER, and dimension at least ne, that may hold the column indices of the entries (see §2.1.2–2.1.3).
- ptr is a rank-one allocatable array of type default INTEGER. If sparse row-wise storage is used (see  $\S 2.1.3$ ), then it must have dimension at least m + 1 and hold the pointers to the first entry in each row. If sparse column-wise storage is used (see  $\S 2.1.4$ ), then it must have dimension at least n + 1 and hold the pointers to the first entry in each column.

## 2.2.2 The derived data type for holding the problem

The derived data type NLPT\_problem\_type holds the problem. The relevant components of NLPT\_problem\_type are:

- m is a scalar variable of type default INTEGER that holds the number of nonlinear constraints m.
- n is a scalar variable of type default INTEGER that holds the number of optimization variables n.
- is scalar variable of type SMT\_TYPE that holds the Hessian matrix  $\mathbf{H} = \nabla_{xx} f(\mathbf{x})$ . The following components are used here:
  - H%type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of H%type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of H%type must contain the string COORDINATE, for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of H%type must contain the string SPARSE\_BY\_ROWS, for the sparse column-wise storage scheme (see Section 2.1.4), the first seventeen components of H%type must contain the string SPARSE\_BY\_COLUMNS, and for the diagonal storage scheme (see Section 2.1.5), the first eight components of H%type must contain the string DIAGONAL.

For convenience, the procedure SMT\_put may be used to allocate sufficient space and insert the required keyword into H%type. For example, if nlp is of derived type CHECK\_problem\_type and involves a Hessian we wish to store using the co-ordinate scheme, we may simply

```
CALL SMT_put( nlp%H%type, 'COORDINATE' )
```

See the documentation for the GALAHAD package SMT for further details on the use of SMT\_put.

- H%ne is a scalar variable of type default INTEGER, that holds the number of entries in the **lower triangular** part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for any of the other four schemes.
- H%val is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double), that holds the values of the entries of the **lower triangular** part of the Hessian matrix **H** in any of the storage schemes discussed in Section 2.1.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

H%row is a rank-one allocatable array of type default INTEGER, that holds the row indices of the **lower triangular** part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2) and the sparse column-wise scheme (see Section 2.1.4). It need not be allocated for any of the other three schemes.

- H%col is a rank-one allocatable array variable of type default INTEGER, that holds the column indices of the **lower triangular** part of **H** in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated for any of the other three schemes.
- H%ptr is a rank-one allocatable array of dimension n+1 and type default INTEGER that holds the starting position of each row of the **lower triangular** part of **H**, as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3), or the starting position of each column of the **lower triangular** part of **H**, as well as the total number of entries plus one, in the sparse column-wise storage scheme (see Section 2.1.4). It need not be allocated when the other schemes are used.
- J is scalar variable of type SMT\_TYPE that holds the Jacobian matrix  $\mathbf{J} = \nabla_x \mathbf{c}(\mathbf{x})$ . The following components are used here:
  - J\*type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of J\*type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of J\*type must contain the string COORDINATE, for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of J\*type must contain the string SPARSE\_BY\_ROWS, for the sparse column-wise storage scheme (see Section 2.1.4), the first seventeen components of J\*type must contain the string SPARSE\_BY\_COLUMNS, and for the diagonal storage scheme (see Section 2.1.5), the first eight components of J\*type must contain the string DIAGONAL.

For convenience, the procedure SMT\_put may be used to allocate sufficient space and insert the required keyword into J%type. For example, if nlp is of derived type CHECK\_problem\_type and involves a Jacobian we wish to store using the co-ordinate scheme, we may simply

```
CALL SMT_put( nlp%J%type, 'COORDINATE' )
```

See the documentation for the GALAHAD package SMT for further details on the use of SMT\_put.

- J%ne is a scalar variable of type default INTEGER that holds the number of entries in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for any of the other schemes.
- J%val is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the values of the entries of the Jacobian matrix **J** in any of the storage schemes discussed in Section 2.1.
- J%row is a rank-one allocatable array of type default INTEGER that holds the row indices of J in the sparse coordinate storage scheme discussed in Section 2.1.2 and the sparse column-wise storage scheme discussed in Section 2.1.4. It need not be allocated for any of the other three schemes.
- J%col is a rank-one allocatable array variable of type default INTEGER that holds the column indices of J in either the sparse co-ordinate scheme discussed in Section 2.1.2 or the sparse row-wise scheme discussed in Section 2.1.3. It need not be allocated for any of the other three schemes.
- J%ptr for the sparse row-wise storage scheme discussed in Section 2.1.3, it is a rank-one allocatable array of dimension m+1 and type default INTEGER that holds the starting position of each row of **J** as well as the total number of entries plus one. For the sparse column-wise storage scheme discussed in Section 2.1.4, it is a rank-one allocatable array of dimension n+1 and type default INTEGER that holds the starting position of each column of **J** as well as the total number of entries plus one. It need not be allocated for any of the other schemes.
- is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_CHECK\_double), that holds the gradient  $\mathbf{g}$  of the objective function. The j-th component of G,  $j = 1, \ldots, n$ , contains  $\mathbf{g}_j$ .



- is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the value of the constraint function. The j-th component of C, j = 1, ..., m, contains  $c_i$ .
- is a scalar variable of type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the value of the objective function.
- is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_CHECK\_double), that holds the values  $\mathbf{x}$  of the optimization variables. The j-th component of  $\mathbf{x}$ ,  $j=1,\ldots,n$ , contains  $x_j$ .
- $X_1$  is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the lower bounds on the optimization variables  $\mathbf{x}$ .
- X\_u is a rank-one allocatable array of dimension n and type default REAL (double precision in GALAHAD\_CHECK\_-double) that holds upper bounds on the optimization variables x.
- is a rank-one allocatable array of dimension m and type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the value y of the Lagrange multiplier estimate. The j-th component of Y, j = 1, ..., m, contains  $y_i$ .

#### 2.2.3 The derived data type for holding control parameters

The derived data type CHECK\_control\_type is used to hold controlling data. Default values may be obtained by calling CHECK\_initialize (see Section 2.3.1), while components may also be changed by calling GALAHAD\_CHECK\_read\_spec (see Section 2.7.1). The components of CHECK\_control\_type are:

- error is a scalar variable of type default INTEGER, that holds the stream number for error messages. Printing of error messages in CHECK\_verify and CHECK\_terminate is suppressed if error ≤ 0. The default is error = 6.
- out is a scalar variable of type default INTEGER, that holds the stream number for informational messages. Printing of informational messages in CHECK\_verify is suppressed if out  $\leq 0$ . The default is out = 6.
- print\_level is a scalar variable of type default INTEGER, that is used to control the amount of informational output which is required. No informational output will occur if print\_level  $\leq 0$ . If print\_level = 1, a brief summary of the derivative verification is provided. If print\_level  $\geq 2$ , this output will be increased to provide significant detail of each iteration (see Section 2.8 for more details). The default is print\_level = 0.
- verify\_level is a scalar variable of type default INTEGER that determines the detail of verification performed. A "cheap" check will be performed if  $verify_level = 1$ . If  $verify_level \ge 2$ , an "expensive"—but more detailed—verification of the derivatives is done. No checking is performed if  $verify_level \le 0$ . The default is  $verify_level = 2$ .
- f\_availability is a scalar variable of type default INTEGER that controls how the user is expected to supply objective function values, when required. The user should set f\_availability = 1 if an appropriate evaluation routine is supplied (see Section 2.4.1), and f\_availability = 2 if reverse communication will be used (see Section 2.5).
- c\_availability is a scalar variable of type default INTEGER that controls how the user is expected to supply constraint function values, when required. The user should set c\_availability = 1 if an appropriate evaluation routine is supplied (see Section 2.4.2), and c\_availability = 2 if reverse communication will be used (see Section 2.5). Any other value will result in an error message.
- g\_availability is a scalar variable of type default INTEGER that controls how the user is expected to supply the gradient of the objective function, when required. The user should set g\_availability = 1 if an appropriate evaluation routine is supplied (see Section 2.4.3), and g\_availability = 2 if reverse communication will be used (see Section 2.5). Any other value will result in an error message.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

CHECK GALAHAD

J\_availability is a scalar variable of type default INTEGER that controls how the user is expected to supply the Jacobian of the constraint function, when required. The user should set J\_availability = 1 if an appropriate evaluation routine is supplied (see Section 2.4.4), J\_availability = 2 if reverse communication will be used to obtain Jacobian values (see Section 2.5), J\_availability = 3 if an appropriate Jacobian-vector product routine is supplied (see Section 2.4.6), and J\_availability = 4 if reverse communication will be used to get Jacobian-vector products (see Section 2.5). Any other value will result in an error message.

- H\_availability is a scalar variable of type default INTEGER that controls how the user is expected to supply the Hessian of the Lagrangian function, when required. The user should set H\_availability = 1 if an appropriate evaluation routine is supplied (see Section 2.4.5), H\_availability = 2 if reverse communication will be used to obtain Hessian values (see Section 2.5), H\_availability = 3 if an appropriate Hessian-vector product routine is supplied (see Section 2.4.7), and H\_availability = 4 if reverse communication will be used to get Hessian-vector products (see Section 2.5). Any other value will result in an error message.
- checkG is a scalar variable of type default LOGICAL that should be set .TRUE. if the gradient of the objective function should be checked. Otherwise, it should be set .FALSE.. The default is <code>checkG=.TRUE.</code>.
- checkJ is a scalar variable of type default LOGICAL that should be set .TRUE. if the Jacobian of the constraint function should be checked. Otherwise, it should be set .FALSE.. The default is checkJ = .TRUE.
- checkH is a scalar variable of type default LOGICAL that should be set .TRUE. if the Hessian of the Lagrangian function should be checked. Otherwise, it should be set .FALSE.. The default is checkH=.TRUE..
- deallocate\_error\_fatal is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to terminate execution if a deallocation fails, and .FALSE. if an attempt to continue will be made. The default is deallocate\_error\_fatal = .FALSE..

# 2.2.4 The derived data type for holding informational parameters

The derived data type CHECK\_inform\_type is used to hold parameters that give information about the progress and needs of the algorithm. The components of CHECK\_inform\_type are:

- status is a scalar variable of type default INTEGER that gives the exit status of the algorithm. See Sections 2.5 and 2.6 for further details.
- alloc\_status is a scalar variable of type default INTEGER that gives the status of the last attempted array allocation or deallocation. This will be 0 if status = 0.
- bad\_alloc is a scalar variable of type default CHARACTER and length 80 that gives the name of the last internal array for which there was an allocation or deallocation error. This will be the null string if status = 0.
- numG\_wrong is a scalar variable of type default INTEGER that gives the number of components of the gradient of the objective function that appear to be wrong.
- numJ\_wrong is a scalar variable of type default INTEGER that gives the number of entries of the Jacobian of the constraint function that appear to be wrong.
- numH\_wrong is a scalar variable of type default INTEGER that gives the number of entries of the Hessian of the Lagrangian function that appear to be wrong.
- derivative\_ok is a scalar variable of type default LOGICAL that is .TRUE. if all derivatives appear to be correct, and set .FALSE. otherwise.



#### 2.2.5 The derived data type for holding problem data

The derived data type CHECK\_data\_type is used to hold all the data for a particular problem, or sequences of problems with the same structure, between calls of CHECK procedures. The only data that should be changed by the user from the initial call to CHECK\_initialize to the final call to CHECK\_terminate is the component RC of type CHECK\_reverse\_communication\_type (see Section 2.2.6), and this should be done only as directed from GALAH-AD\_CHECK\_verify with positive values of inform%status as described in Section 2.5.

### 2.2.6 The derived data type for holding reverse communication data

The derived data type CHECK\_reverse\_communication\_type is used to hold data for reverse communication, when needed. The components of CHECK\_reverse\_communication\_type are:

- X is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the values of the optimization variables at which the user must perform function computation.
- Y is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the values of the Lagrange multipliers that the user must use when evaluating the Hessian of the Lagrangian.
- F is a scalar variable of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the value of the objective function evaluated at X, when required (see Section 2.5).
- C is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the value of the constraint function evaluated at X, when required (see Section 2.5).
- G is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the gradient of the bejective function evaluated at X, when required (see Section 2.5).
- V is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) that holds the vector for which a matrix-vector product is required (see Section 2.5).
- U is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the result of any required matrix-vector product with the vector V from above (see Section 2.5).
- Jval is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the entries of the Jacobian matrix evaluated at X, when required (see Section 2.5).
- Hval is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double) in which the user places the **lower triangular** entries of the Hessian matrix of the Lagrangian evaluated at X and Y, when required (see Section 2.5).

# 2.2.7 The derived data type for holding user data

The derived data type NLPT\_userdata\_type is available to allow the user to pass data to and from user-supplied subroutines for function and derivative calculations (see Section 2.4). Components of variables of type NLPT\_userdata\_type may be allocated as necessary. The following components are available:

integer is a rank-one allocatable array of type default INTEGER.

real is a rank-one allocatable array of type default REAL (double precision in GALAHAD\_CHECK\_double)

complex is a rank-one allocatable array of type default COMPLEX (double precision complex in GALAHAD\_CHECK\_-double).

character is a rank-one allocatable array of type default CHARACTER.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

logical is a rank-one allocatable array of type default LOGICAL.

integer\_pointer is a rank-one pointer array of type default INTEGER.

real\_pointer is a rank-one pointer array of type default REAL (double precision in GALAHAD\_CHECK\_double)

complex\_pointer is a rank-one pointer array of type default COMPLEX (double precision complex in GALAHAD\_CHECK\_-double).

character\_pointer is a rank-one pointer array of type default CHARACTER.

logical\_pointer is a rank-one pointer array of type default LOGICAL.

# 2.3 Argument lists and calling sequences

There are three procedures for user calls (see Section 2.7 for further features):

- 1. The subroutine CHECK\_initialize is used to set default values, and initialize private data, before verifying the derivatives of one or more problems with the same sparsity and bound structure.
- 2. The subroutine CHECK\_verify is called to check the derivatives of the given problem.
- 3. The subroutine CHECK\_terminate is provided to allow the user to automatically deallocate array components of the private data, allocated by CHECK\_verify, at the end of the verification process. It is important to do this if the data object is re-used for another problem with a different structure since CHECK\_initialize cannot test for this situation, and any existing associated targets will subsequently become unreachable.

We use square brackets  $[\ ]$  to indicate  ${\tt OPTIONAL}$  arguments.

## 2.3.1 The initialization subroutine

Default values are provided as follows:

```
CALL CHECK_initialize( control )
```

control is a scalar INTENT (OUT) argument of type CHECK\_control\_type (see Section 2.2.3). On exit, control contains default values for the components as described in Section 2.2.3. These values should only be changed after calling CHECK\_initialize.

#### 2.3.2 The verification subroutine

The verification algorithm is called as follows:

```
CALL CHECK_verify( nlp, data, control, inform, userdata[, eval_F, eval_C, eval_G, eval_H, eval_Jv, eval_Hv])
```

nlp is a scalar INTENT (INOUT) argument of type NLPT\_problem\_type (see Section 2.2.2). It is used to hold data about the problem whose derivatives are being verified. For a new problem, the user must allocate all the array components, and set values for nlp%m, nlp%n, and the required integer components of nlp%J and nlp%H that is determined by the values of checkJ and checkH as described in Section 2.2.3. Users are free to choose whichever of the matrix formats described in Section 2.1 is appropriate for J and H for their application.

The components nlp%X and nlp%Y must be set to initial values  $\mathbf{x}$  and  $\mathbf{y}$  of the primal and dual variables for the optimization problem. Prior to verification of the derivatives, the point nlp%X is modified internally to ensure feasibility with respect to the bound constraints  $\mathbf{x}^l$  and  $\mathbf{x}^u$ ; no modification of  $\mathbf{y}$  is performed. The requested derivatives are then checked at the point nlp%X and nlp%Y.

**Restrictions:** nlp%n > 0 and  $nlp%m \ge 0$ .



- data is a scalar INTENT (INOUT) argument of type CHECK\_data\_type (see Section 2.2.5). It is used to hold data about the problem derivatives being verified. With the possible exception of the component RC (see Sections 2.2.6 and 2.5), it must not have been altered by the user since the last call to CHECK\_initialize.
- control is a scalar INTENT (IN) argument of type CHECK\_control\_type (see Section 2.2.3). Default values may be assigned by calling CHECK\_initialize prior to the first call to CHECK\_solve.
- inform is a scalar INTENT (INOUT) argument of type CHECK\_inform\_type (see Section 2.2.4). On initial entry, the component status must be set to the value 1. Other entries need not be set. A successful call to CHECK\_verify is indicated when the component status has the value 0. For other return values of status, see Sections 2.5 and 2.6.
- userdata is a scalar INTENT(INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the OPTIONAL subroutines eval\_F, eval\_C, eval\_G, eval\_J, eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- eval\_F is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the objective function  $f(\mathbf{x})$  at a given vector  $\mathbf{x}$ . See Section 2.4.1 for details. If f\_availability = 1 (see Section 2.2.3), then eval\_F must be present and declared EXTERNAL in the calling program. If f\_availability = 2, then GALAHAD\_CHECK\_verify will use reverse communication to obtain objective function values (see Section 2.5).
- eval\_C is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the constraint function  $\mathbf{c}(\mathbf{x})$  at a given vector  $\mathbf{x}$ . See Section 2.4.2 for details. If c\_availability = 1 (see Section 2.2.3), then eval\_C must be present and declared EXTERNAL in the calling program. If c\_availability = 2, then GALAHAD\_CHECK\_verify will use reverse communication to obtain constraint function values (see Section 2.5).
- eval\_G is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the gradient of the objective function  $\nabla_x f(\mathbf{x})$  at a given vector  $\mathbf{x}$ . See Section 2.4.3 for details. If g\_availability = 1 (see Section 2.2.3), then eval\_G must be present and declared EXTERNAL in the calling program. If g\_availability = 2, then GALAH-AD\_CHECK\_verify will use reverse communication to obtain gradient values (see Section 2.5).
- eval\_J is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the Jacobian of the objective function  $\nabla_{xx} f(\mathbf{x})$  at a given vector  $\mathbf{x}$ . See Section 2.4.5 for details. If J\_availability = 1 (see Section 2.2.3), then eval\_J must be present and declared EXTERNAL in the calling program. Otherwise, eval\_J need not be supplied.
- eval\_H is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the Hessian of the Lagrangian  $\nabla_{xx}L(\mathbf{x},\mathbf{y})$  at a given point  $(\mathbf{x},\mathbf{y})$ . See Section 2.4.5 for details. If H\_availability = 1 (see Section 2.2.3), then eval\_H must be present and declared EXTERNAL in the calling program. Otherwise, eval\_H need not be supplied.
- eval\_Jv is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the product of the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$  with a given vector  $\mathbf{v}$ . See Section 2.4.7 for details. If J\_availability = 3 (see Section 2.2.3), then eval\_Jv must be present and declared EXTERNAL in the calling program. Otherwise, eval\_Jv need not be supplied.
- eval\_Hv is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the product of the Hessian of the Lagrangian function  $\nabla_{xx}L(\mathbf{x},\mathbf{y})$  with a given vector  $\mathbf{v}$ . See Section 2.4.7 for details. If H\_availability = 3 (see Section 2.2.3), then eval\_Hv must be present and declared EXTERNAL in the calling program. Otherwise, eval\_Hv need not be supplied.

## 2.3.3 The termination subroutine

All previously allocated arrays are deallocated as follows:

CALL CHECK\_terminate( data, control, inform )

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

data is a scalar INTENT (INOUT) argument of type CHECK\_data\_type exactly as for CHECK\_verify, which must not have been altered by the user since the last call to CHECK\_initialize (except possibly data%RC as described in Section 2.5). On exit, array components will have been deallocated.

control is a scalar INTENT(IN) argument of type CHECK\_control\_type exactly as for CHECK\_verify.

inform is a scalar INTENT (OUT) argument of type CHECK\_inform\_type exactly as for CHECK\_verify. Only the component status will be set on exit, and a successful call to CHECK\_terminate is indicated when this component status has the value 0. For other return values of status see Section 2.6.

#### 2.4 Function and derivative values

#### 2.4.1 The objective function value via internal evaluation

If the control parameter f\_availability = 1 (see Section 2.2.3), then the argument eval\_F must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the value of the objective function  $f(\mathbf{x})$ . The routine must be specified as

```
SUBROUTINE eval_F( status, X, userdata, F )
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER, that should be set to 0 if the routine has been able to evaluate the objective function and to a non-zero value if the evaluation has not been possible.
- X is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector **x**.
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- is a scalar INTENT (OUT) argument of type default REAL (double precision in GALAHAD\_CHECK\_double) that should be set to the value of the objective function  $f(\mathbf{x})$  evaluated at the vector  $\mathbf{x}$  input in X.

#### 2.4.2 The constraint function value via internal evaluation

If the control parameter c\_availability = 1 (see Section 2.2.3), then the argument eval\_C must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the value of the constraint function  $\mathbf{c}(\mathbf{x})$ . The routine must be specified as

```
SUBROUTINE eval_C( status, X, userdata, C )
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER, that should be set to 0 if the routine has been able to evaluate the constraint function and to a non-zero value if the evaluation has not been possible.
- is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector **x**.
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- is a rank-one INTENT (OUT) argument of type default REAL (double precision in GALAHAD\_CHECK\_double) that should be set to the value of the constraint function  $\mathbf{c}(\mathbf{x})$  evaluated at the vector  $\mathbf{x}$  input in X.

#### 2.4.3 Gradient values via internal evaluation

If the control parameter g\_availability = 1 (see Section 2.2.3), then the argument eval\_G must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the value of the gradient the objective function  $\nabla_x f(\mathbf{x})$ . The routine must be specified as

```
SUBROUTINE eval G( status, X, userdata, G)
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER that should be set to 0 if the routine has been able to evaluate the gradient of the objective function and to a non-zero value if the evaluation has not been possible.
- is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector  $\mathbf{x}$ .
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- G is a rank-one INTENT (OUT) argument of type default REAL (double precision in GALAHAD\_CHECK\_double), whose components should be set to the values of the gradient of the objective function  $\nabla_x f(\mathbf{x})$  evaluated at the vector  $\mathbf{x}$  input in X.

# 2.4.4 Jacobian values via internal evaluation

If the control parameter J\_availability = 1 (see Section 2.2.3), then the argument eval\_J must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the values of the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$ . The routine must be specified as

```
SUBROUTINE eval_J( status, X, userdata, Jval )
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER that should be set to 0 if the routine has been able to evaluate the Jacobian of the constraint function and to a non-zero value if the evaluation has not been possible.
- INTERT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector **x**.
- userdata is a scalar INTENT(INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- Jval is a scalar INTENT (OUT) argument of type default REAL (double precision in GALAHAD\_CHECK\_double), whose components should be set to the values of the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$  evaluated at the vector  $\mathbf{x}$  input in X. The values should be input in the same order as that in which the array indices were given in nlp%J.

CHECK GALAHAD

#### 2.4.5 Hessian values via internal evaluation

If the control parameter H\_availability = 1 (see Section 2.2.3), then the argument eval\_H must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the values of the Hessian of the Lagrangian  $\nabla_{xx} L(\mathbf{x}, \mathbf{y})$ . The routine must be specified as

```
SUBROUTINE eval_H( status, X, Y, userdata, Hval )
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER, that should be set to 0 if the routine has been able to evaluate the Hessian of the Lagrangian and to a non-zero value if the evaluation has not been possible.
- X is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector  $\mathbf{x}$ .
- is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the dual vector y.
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- Hval is a scalar INTENT (OUT) argument of type default REAL (double precision in GALAHAD\_CHECK\_double), whose components should be set to the values of the Hessian of the Lagrangian  $\nabla_{xx}L(\mathbf{x},\mathbf{y})$  evaluated at the vector  $(\mathbf{x},\mathbf{y})$  input in X and Y. The values should be input in the same order as that in which the array indices were given in nlp%H.

## 2.4.6 Jacobian-vector products via internal evaluation

If the control parameter J\_availability = 3 (see Section 2.2.3), then the argument eval\_Jv must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to compute products of the Jacobian of the constraint function (and its transpose) of the form  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x}) \mathbf{v}$  and  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})^T \mathbf{v}$ . The routine must be specified as

```
SUBROUTINE eval Jv ( status, X, userdata, transpose, U, V )
```

whose arguments are as follows:

- status is a scalar INTENT (OUT) argument of type default INTEGER that should be set to 0 if the routine has been able to perform the required calculation (see transpose below) and to a non-zero value if the computation has not been possible.
- is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector  $\mathbf{x}$ .
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- transpose is a scalar INTENT (IN) argument of type default LOGICAL. If transpose = .FALSE., then the user should evaluate the sum  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})\mathbf{v}$ . If transpose = .TRUE., then the user should evaluate the sum  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})^T \mathbf{v}$ .



- is a rank-one INTENT (INOUT) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components on input contain the vector  $\mathbf{u}$  and on output contains either the sum  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x}) \mathbf{v}$  or  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})^T \mathbf{v}$  depending on the value of transpose given above.
- V is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector v.

### 2.4.7 Hessian-vector products via internal evaluation

If the control parameter H\_availability = 3 (see Section 2.2.3), then the argument eval\_Hv must be present when calling GALAHAD\_CHECK\_verify and the user must provide a subroutine of that name to evaluate the sum  $\mathbf{u} + \nabla_{xx} L(\mathbf{x}, \mathbf{y}) \mathbf{v}$  involving the product of the Hessian of the Lagrangian  $\nabla_{xx} L(\mathbf{x}, \mathbf{y})$ . The routine must be specified as

```
SUBROUTINE eval_Hv( status, X, Y, userdata, U, V )
```

whose arguments are as follows:

status is a scalar INTENT (OUT) argument of type default INTEGER that should be set to 0 if the routine has been able to perform the required calculation and to a non-zero value if the computation has not been possible.

- X is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector x.
- is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector **y**.
- userdata is a scalar INTENT (INOUT) argument of type NLPT\_userdata\_type whose components may be used to communicate user-supplied data to and from the subroutines eval\_F, eval\_C, eval\_G, eval\_J eval\_H, eval\_Jv, and eval\_Hv (see Section 2.2.7).
- is a rank-one INTENT (INOUT) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components on input contain the vector  $\mathbf{u}$  and on output the sum  $\mathbf{u} + \nabla_{xx} L(\mathbf{x}, \mathbf{y}) \mathbf{v}$ .
- V is a rank-one INTENT (IN) array argument of type default REAL (double precision in GALAHAD\_CHECK\_double) whose components contain the vector v.

#### 2.5 Reverse Communication Information

A positive value of inform%status on exit from CHECK\_verify indicates that GALAHAD\_CHECK\_verify is seeking further information—this will happen if the user has chosen not to evaluate function or derivative values internally (see Sections 2.2.3 and 2.4). The user should compute the required information and re-enter GALAHAD\_CHECK\_verify with all arguments (except those specifically mentioned below) unchanged.

Possible values of inform%status and the information required are

- 2. The user should compute the objective function value  $f(\mathbf{x})$  at the point  $\mathbf{x}$  indicated in data%RC%X. The required value should be set in data%RC%F. If the user is unable to evaluate  $f(\mathbf{x})$ —for instance, if the function is undefined at  $\mathbf{x}$ —the user need not set data%RC%F, but should then set inform%status to any negative value. Otherwise, the value of inform%status should remain unchanged.
- 3. The user should compute the constraint function value  $\mathbf{c}(\mathbf{x})$  at the point  $\mathbf{x}$  indicated in data%RC%X. The required value should be set in data%RC%C. If the user is unable to evaluate  $\mathbf{c}(\mathbf{x})$ —for instance, if the function is undefined at  $\mathbf{x}$ —the user need not set data%RC%C, but should then set inform%status to any negative value. Otherwise, the value of inform%status should remain unchanged.

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

CHECK GALAHAD

4. The user should compute the gradient of the objective function  $\nabla_x f(\mathbf{x})$  at the point  $\mathbf{x}$  indicated in data%RC%X. The value of the i-th component of the gradient should be set in data%RC%G(i) for  $i=1,\ldots,n$ . If the user is unable to evaluate a component of  $\nabla_x f(\mathbf{x})$ —for instance, if a component of the gradient is undefined at  $\mathbf{x}$ —the user need not set data%RC%G, but should then set inform%status to a negative value. Otherwise, the value of inform%status should remain unchanged.

- The user should compute the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$  at the point  $\mathbf{x}$  indicated in data%RC%X. The l-th component of the Jacobian stored according to the scheme used to input nlp%J (see Section 2.2.2) should be set in data%RC%Jval(1) for  $l=1,\ldots,$  nlp%J%ne. If the user is unable to evaluate a component of  $\nabla_x \mathbf{c}(\mathbf{x})$ —for instance, if a component of the Jacobian is undefined at  $\mathbf{x}$ —the user need not set data%RC%Jval, but should then set inform%status to a negative number. Otherwise, the value of inform%status should remain unchanged.
- 6. The user should compute the value  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})\mathbf{v}$ , which requires a product of the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$  at the point  $\mathbf{x}$  with the vector  $\mathbf{v}$ ; the vectors  $\mathbf{x}$ ,  $\mathbf{u}$ , and  $\mathbf{v}$  are contained in data%RC%X, data%RC%U, and data%RC%V, respectively. On exit, the resulting vector  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})\mathbf{v}$  should be stored in data%RC%U. If the user is unable to evaluate the product—for instance, if a component of the Jacobian is undefined at  $\mathbf{x}$ —the user need not set data%RC%U, but should then set inform%status to a negative value. Otherwise, the value of inform%status should remain unchanged.
- 7. The user should compute the value  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})^T \mathbf{v}$ , which requires a product of the transpose of the Jacobian of the constraint function  $\nabla_x \mathbf{c}(\mathbf{x})$  at the point  $\mathbf{x}$  with the vector  $\mathbf{v}$ ; the vectors  $\mathbf{x}$ ,  $\mathbf{u}$ , and  $\mathbf{v}$  are contained in data%RC%X, data%RC%U, and data%RC%V, respectively. On exit, the resulting vector  $\mathbf{u} + \nabla_x \mathbf{c}(\mathbf{x})^T \mathbf{v}$  should be stored in data%RC%U. If the user is unable to evaluate the product—for instance, if a component of the Jacobian is undefined at  $\mathbf{x}$ —the user need not set data%RC%U, but should then set inform%status to a negative value. Otherwise, the value of inform%status should remain unchanged.
- 8. The user should compute the Hessian of the Lagrangian  $\nabla_{xx}L(\mathbf{x},\mathbf{y})$  at the point  $(\mathbf{x},\mathbf{y})$  indicated in data%RC%X and data%RC%Y. The l-th component of the Hessian stored according to the scheme used to input nlp%H (see Section 2.2.2) should be set in data%RC%Hval(1) for  $l=1,\ldots,$  nlp%H%ne. If the user is unable to evaluate a component of  $\nabla_{xx}L(\mathbf{x},\mathbf{y})$ —for instance, if a component of the Hessian is undefined at  $(\mathbf{x},\mathbf{y})$ —the user need not set data%RC%Hval, but should then set inform%status to a negative value. Otherwise, the value of inform%status should remain unchanged.
- 9. The user should compute the value  $\mathbf{u} + \nabla_{xx} L(\mathbf{x}, \mathbf{y}) \mathbf{v}$ , which requires a product of the Hessian of the Lagrangian  $\nabla_{xx} L(\mathbf{x}, \mathbf{y})$  at the point  $(\mathbf{x}, \mathbf{y})$  with the vector  $\mathbf{v}$ ; the vectors  $\mathbf{x}$ ,  $\mathbf{y}$ ,  $\mathbf{u}$ , and  $\mathbf{v}$  are contained in data%RC%X, data%RC%Y, data%RC%Y, and data%RC%V, respectively. On exit, the resulting vector  $\mathbf{u} + \nabla_{xx} L(\mathbf{x}, \mathbf{y}) \mathbf{v}$  should be stored in data%RC%U. If the user is unable to evaluate the product—for instance, if a component of the Hessian is undefined at  $(\mathbf{x}, \mathbf{y})$ —the user need not set data%RC%U, but should then set inform%status to a negative value. Otherwise, the value of inform%status should remain unchanged.

# 2.6 Warning and error messages

A negative value of informstatus on exit from CHECK\_verify or CHECK\_terminate indicates that an error has occurred. No further calls should be made until the error has been corrected. Possible values are:

- -1. An allocation error occurred. A message indicating the offending array is written on unit control%error, and the returned allocation status and a string containing the name of the offending array are held in inform%alloc\_status and inform%bad\_alloc, respectively.
- -2. A deallocation error occurred. A message indicating the offending array is written on unit control%error and the returned allocation status and a string containing the name of the offending array are held in inform%alloc\_status and inform%bad\_alloc, respectively.



- -3. Either one of the restrictions nlp%n > 0 or nlp%m ≥ 0 is violated, or the requirement that nlp%J\_type and nlp%H\_type contain a relevant string 'DENSE', 'COORDINATE', 'SPARSE\_BY\_ROWS', 'SPARSE\_BY\_COLUMNS', or 'DIAGONAL' is not satisfied.
- -50. The user has called CHECK\_verify with inform%status < 0, which indicates that the user was not able to perform a requested computation needed during reverse communication.
- -51. The user has called CHECK\_verify with inform%status = 0, which should never happen. The user should only set inform%status in two situations: inform%status = 1 prior to the initial call to CHECK\_verify, and inform%status < 0 when reverse communication is being used and the user is unable to perform the required computation as indicated by the value of inform%status on return from CHECK\_verify (see Section 2.5). The user should not change inform%status for any other reason.
- -55. The user has input an invalid value for at least one of the control parameters f\_availability, c\_availability, g\_availability, or H\_availability as described in Section 2.2.3.
- -56. Based on the values of the control parameters f\_availability, c\_availability, g\_availability, J\_availability, and H\_availability (see Section 2.2.3), at least one optional dummy subroutine is missing in the call to CHECK\_verify.
- -57. At least one component of nlp%X\_l or nlp%X\_u is inappropriate (see Section 2.2.2).
- -58. A user supplied function (see Sections 2.4.1–2.4.7) returned inform%status  $\neq 0$ , implying that the function computation could not be performed at the required point.

# 2.7 Further features

In this section, we describe an alternative means of setting control parameters—that is components of the variable control of type CHECK\_control\_type (see Section 2.2.3)—by reading an appropriate data specification file using the subroutine CHECK\_read\_specfile. This facility is useful as it allows a user to change CHECK control parameters without editing and recompiling programs that call CHECK.

A specification file, or specfile, is a data file containing a number of "specification commands". Each command occurs on a separate line, and comprises a "keyword", which is a string (in a close-to-natural language) used to identify a control parameter, and an (optional) "value", which defines the value to be assigned to the given control parameter. All keywords and values are case insensitive, keywords may be preceded by one or more blanks but values must not contain blanks, and each value must be separated from its keyword by at least one blank. Values must not contain more than 30 characters, and each line of the specfile is limited to 80 characters, including the blanks separating keyword and value.

The portion of the specification file used by CHECK\_read\_specfile must start with a "BEGIN CHECK" command and end with an "END" command. The syntax of the specifile is thus defined as follows:

```
( .. lines ignored by CHECK_read_specfile .. )
BEGIN CHECK
   keyword value
    .....
   keyword value
END
( .. lines ignored by CHECK_read_specfile .. )
```

where keyword and value are two strings separated by (at least) one blank. The "BEGIN CHECK" and "END" delimiter command lines may contain additional (trailing) strings so long as such strings are separated by one or more blanks, so that lines such as

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

BEGIN CHECK SPECIFICATION

and

END CHECK SPECIFICATION

are acceptable. Furthermore, between the "BEGIN CHECK" and "END" delimiters, specification commands may occur in any order. Blank lines and lines whose first non-blank character is ! or \* are ignored. The content of a line after a ! or \* character is also ignored (as is the ! or \* character itself). This provides an easy manner to "comment out" some specification commands, or to comment specific values of certain control parameters.

The value of a control parameters may be of three different types, namely integer, logical, or real. Integer and real values may be expressed in any relevant Fortran integer and floating-point formats (respectively). Permitted values for logical parameters are "ON", "TRUE", ".TRUE.", "T", "YES", "Y", or "OFF", "NO", "N", "FALSE", ".FALSE." and "F". Empty values are also allowed for logical control parameters, and are interpreted as "TRUE".

The specification file must be open for input when CHECK\_read\_specfile is called, and the associated device number passed to the routine in device (see below). Note that the corresponding file is REWINDed, which makes it possible to combine the specifications for more than one program/routine. For the same reason, the file is not closed by CHECK\_read\_specfile.

# 2.7.1 To read control parameters from a specification file

Control parameters may be read from a file as follows:

```
CALL CHECK_read_specfile( control, device )
```

control is a scalar INTENT (INOUT) argument of type CHECK\_control\_type (see Section 2.2.3). Default values should have already been set, perhaps by calling CHECK\_initialize. On exit, individual components of control may have been changed according to the commands found in the specifile. Specifile commands and the components (see Section 2.2.3) of control that they affect are given in Table 2.1.

command	component of control	value type
error-printout-device	%error	integer
printout-device	%out	integer
print-level	%print_level	integer
verification-level	%verify_level	integer
f-availability	%f_availability	integer
c-availability	%c_availability	integer
g-availability	%G_availability	integer
J-availability	%J_availability	integer
H-availability	%H_availability	integer
check-gradient	%checkG	logical
check-Jacobian	%checkJ	logical
check-Hessian	%checkH	logical
deallocate-error-fatal	%deallocate_error_fatal	logical

Table 2.1: Specifle commands and associated components of control.

device is a scalar INTENT (IN) argument of type default INTEGER, that must be set to the unit number on which the specifile has been opened. If device is not open, control will not be altered and execution will continue, but an error message will be printed on unit control%error.



#### 2.8 Information printed

If control%print\_level is positive, information about the derivative verification will be printed on unit control%out, provided control%out > 0. If control%print\_level = 1, a basic summary of the derivative checking is produced. If control%print\_level = 2, then in addition to the above there is detailed output of the derivative verification, control parameters are printed, and basic matrix data is produced. If control%print\_level = 3, then in addition to the above, full matrix data is printed. Finally, control%print\_level  $\geq 4$  is used for debugging and in addition to the above also prints private data used during the verification process.

## 3 GENERAL INFORMATION

Use of common: None.

Workspace: Provided automatically by the module.

Other routines called directly: None.

Other modules used directly: CHECK\_verify and CHECK\_terminate call the GALAHAD packages GALAHAD\_MOP, and GALAHAD\_SPACE.

Input/output: Output is under control of the arguments control%error, control%out and control%print\_level.

**Restrictions:** nlp%n > 0 and  $nlp%m \ge 0$ .

**Portability:** ISO Fortran 95 + TR 15581 or Fortran 2003. The package is thread-safe.

# 4 METHOD

Finite difference approximations are used to numerically "verify" requested derivatives. If  $\operatorname{verify\_level} = 1$ , we perform a "cheap" check of the gradient of the objective function by comparing  $(f(\mathbf{x}) - f(\mathbf{x} + \alpha \mathbf{s}))/\alpha$  with  $\nabla_x f(\mathbf{x})^T \mathbf{s}$  for some appropriately chosen vector  $\mathbf{s}$  and scalar  $0 < \alpha \ll 1$ . Similarly, for the Jacobian of the constraints and the Hessian of the Lagrangian, we compare  $(\mathbf{c}(\mathbf{x}) - \mathbf{c}(\mathbf{x} + \alpha \mathbf{s}))/\alpha$  to  $\nabla_x \mathbf{c}(\mathbf{x})\mathbf{s}$  and  $(\nabla_x L(\mathbf{x},\mathbf{y}) - \nabla_x L(\mathbf{x} + \alpha \mathbf{s},\mathbf{y}))/\alpha$  to  $\nabla_{xx} L(\mathbf{x},\mathbf{y})\mathbf{s}$ , respectively. If  $\operatorname{verify\_level} = 2$ , we perform an "expensive" verification of the gradient of the objective function by comparing  $(f(\mathbf{x}) - f(\mathbf{x} + \alpha \mathbf{e}_i))/\alpha$  with  $[\nabla_x f(\mathbf{x})]_i$  for  $i = 1, \ldots, n$ , where  $\mathbf{e}_i$  is the ith coordinate vector. Similarly, for the Jacobian of the constraints and the Hessian of the Lagrangian, we compare  $[(\mathbf{c}(\mathbf{x}) - \mathbf{c}(\mathbf{x} + \alpha \mathbf{e}_j))]_i/\alpha$  to  $[\nabla_x \mathbf{c}(\mathbf{x})]_{ij}$  and  $[(\nabla_x L(\mathbf{x},\mathbf{y}) - \nabla_x L(\mathbf{x} + \alpha \mathbf{e}_j,\mathbf{y}))]_i/\alpha$  to  $[\nabla_x \mathbf{c}(\mathbf{x},\mathbf{y})]_{ij}$ , respectively.

# 5 EXAMPLES OF USE

Suppose we wish to perform an "expensive" check of the derivatives associated with the objective function  $f(\mathbf{x}) = x_1 + x_2^3/3$  and the constraint function  $\mathbf{c}(\mathbf{x}) = (x_1 + x_2^2 + x_3^3 + x_3x_2^2, -x_2^4)$  at the point  $\mathbf{x} = (4,3,2)$  and  $\mathbf{y} = (2,3)$ , with bounds  $\mathbf{x}^l = (-5,-5,-5)$  and  $\mathbf{x}^u = (5,5,5)$ . We may use the following code:

```
! THIS VERSION: GALAHAD 3.3 - 04/05/2021 AT 14:45 GMT.

PROGRAM GALAHAD_check_example

USE GALAHAD_SMT_double ! double precision version

USE GALAHAD_USERDATA_double ! double precision version

USE GALAHAD_NLPT_double ! double precision version

USE GALAHAD_MOP_double ! double precision version

USE GALAHAD_CHECK_double ! double precision version

IMPLICIT NONE

integer, parameter :: wp = KIND( 1.0D+0 ) ! Define the working precision
```

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

real (kind = wp), parameter :: one = 1.0\_wp, two = 2.0\_wp, three = 3.0\_wp

type( NLPT\_problem\_type ) :: nlp

type( CHECK\_data\_type ) :: data
type( CHECK\_control\_type ) :: control
type( CHECK\_inform\_type ) :: inform
integer :: stat, Jne, Hne, m, n

type ( GALAHAD\_userdata\_type ) :: userdata

```
GALAHAD <u></u>
```

```
real (kind = wp), parameter :: four = 4.0_wp, five = 5.0_wp
  external funF, funC, funG, funJ, funH
                                             ; n = nlp%n
 nlp%m = 2 ; nlp%n = 3 ; m = nlp%m
 nlp%J%m = 2; nlp%J%n = 3; nlp%J%ne = 4; Jne = nlp%J%ne nlp%H%m = 3; nlp%H%n = 3; nlp%H%ne = 3; Hne = nlp%H%ne
  call SMT_put( nlp%J%id, 'Toy 2x3 matrix', stat );
  call SMT_put( nlp%J%type, 'COORDINATE', stat )
 call SMT_put( nlp%H%id, 'Toy 3x3 hessian matrix', stat );
 call SMT_put( nlp%H%type, 'COORDINATE', stat )
 allocate ( \ nlp \$G (n) \ , \ nlp \$C (m) \ , \ nlp \$X (n) \ , \ nlp \$X \_l (n) \ , \ nlp \$X \_u (n) \ , \ nlp \$Y (m) \ )
 allocate( nlp%J%row(Jne), nlp%J%col(Jne), nlp%J%val(Jne) )
 allocate( nlp%H%row(Hne), nlp%H%col(Hne), nlp%H%val(Hne) )
 nlp%J%row = (/ 1, 1, 1, 2 /) ; nlp%J%col = (/ 1, 2, 3, 2 /)
 nlp%H%row = (/ 2, 3, 3 /); nlp%H%col = (/ 2, 2, 3 /)
 nlp%X = (/ four, three, two /); nlp%X_l = -five; nlp%X_u = five; nlp%Y = (/ two, three /)
 call CHECK_initialize( control ); control%print_level = 3
 inform%status = 1
 call CHECK_verify( nlp, data, control, inform, userdata, funF, funC, funG, funJ, funH)
  call CHECK_terminate( data, control, inform )
END PROGRAM GALAHAD_check_example
SUBROUTINE funF ( status, X, userdata, F )
 USE GALAHAD_USERDATA_double
  INTEGER, PARAMETER :: wp = KIND ( 1.0D+0 )
  INTEGER, INTENT( OUT ) :: status
  REAL ( kind = wp ), INTENT( IN ), DIMENSION( : ) :: X
 REAL ( kind = wp ), INTENT( OUT ) :: F
 TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
 F = X(1) + X(2) **3 / 3.0_wp
 status = 0
 RETURN
END SUBROUTINE funF
SUBROUTINE funC(status, X, userdata, C)
 USE GALAHAD_USERDATA_double
 INTEGER, PARAMETER :: wp = KIND ( 1.0D+0 )
 INTEGER, INTENT( OUT ) :: status
 REAL ( kind = wp ), INTENT( IN ), DIMENSION( : ) :: X
 REAL ( kind = wp ), DIMENSION( : ), INTENT( OUT ) :: C
 TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
 C(1) = X(1) + X(2)**2 + X(3)**3 + X(3)*X(2)**2
 C(2) = -X(2) **4
 status = 0
 RETURN
END SUBROUTINE funC
SUBROUTINE funG(status, X, userdata, G)
  USE GALAHAD_USERDATA_double
  INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
  INTEGER, INTENT( OUT ) :: status
```

```
REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X
 REAL ( KIND = wp ), DIMENSION( : ), INTENT( OUT ) :: G
 TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
 G(1) = 1.0_{wp}
 G(2) = X(2) **2
 G(3) = 0.0 wp
 status = 0
 RETURN
END SUBROUTINE funG
SUBROUTINE funJ(status, X, userdata, Jval)
 USE GALAHAD_USERDATA_double
 INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
 INTEGER, INTENT( OUT ) :: status
 REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X
 REAL ( KIND = wp ), DIMENSION( : ), INTENT( OUT ) :: Jval
 TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
 Jval(1) = 1.0_wp
 Jval(2) = 2.0_wp * X(2) * (1.0_wp + X(3))
 Jval(3) = 3.0_wp * X(3)**2 + X(2)**2
 Jval(4) = -4.0_wp * X(2) **3
 status = 0
 RETURN
END SUBROUTINE funJ
SUBROUTINE funH(status, X, Y, userdata, Hval)
 USE GALAHAD_USERDATA_double
 INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
 INTEGER, INTENT( OUT ) :: status
 REAL ( kind = wp ), DIMENSION( : ), INTENT( IN ) :: X
 REAL ( kind = wp ), DIMENSION( : ), INTENT( IN ) :: Y
 REAL ( kind = wp ), DIMENSION( : ), INTENT( OUT ) ::Hval
 TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
 Hval(1) = 2.0_{wp} * (X(2) - Y(1) - Y(1)*X(3) + 6.0_{wp}*Y(2)*X(2)**2)
 Hval(2) = -2.0_wp * Y(1) * X(2)
 Hval(3) = -6.0_wp * Y(1) * X(3)
 status = 0
 RETURN
END SUBROUTINE funH
```

The code produces the following output:

Component Ok Difference

```
----- BEGIN: CHECK_verify ------
```

EXPENSIVE VERIFICATION OF THE GRADIENT G(X)

Com	nponent	0k	Difference	Value	Error
G ( G ( G (	1) 2) 3)	OK OK OK	9.999999891E-01 9.000000276E+00 0.000000000E+00	1.00000000E+00 9.00000000E+00 0.00000000E+00	5.437063107E-09 2.755274155E-08 0.000000000E+00
		EXPEN	SIVE VERIFICATION O	F THE JACOBIAN C(X)	

All use is subject to the conditions of the GNU Lesser General Public License version 3. See http://galahad.rl.ac.uk/galahad-www/cou.html for full details.

GALAHAD CHECK (May 6, 2021) 19

Value

Error

CHECK GALAHAD **SALAHAD** 

```
J( 1, 1) OK 9.999999891E-01 1.00000000E+00 5.437063107E-09
J( 2, 1) OK 0.00000000E+00 0.0000000E+00 0.00000000E+00
J( 1, 2) OK 1.800000025E+01 1.800000000E+01 1.328101027E-08
J( 2, 2) OK -1.080000049E+02 -1.080000000E+02 4.540609994E-08
J( 1, 3) OK 2.100000052E+01 2.100000000E+01 2.356511149E-08
J( 2, 3) OK 0.000000000E+00 0.00000000E+00 0.00000000E+00
              EXPENSIVE VERIFICATION OF THE HESSIAN H(X,Y)
                                                        Error
  Component
             Ok
                     Difference
                                     Value
   1, 1) OK 0.00000000E+00 0.00000000E+00 0.00000000E+00 2, 1) OK 0.00000000E+00 0.00000000E+00 0.00000000E+00 0.00000000E+00 0.00000000E+00 0.00000000E+00 0.00000000E+00
H (
Н(
         2) OK 0.00000000E+00 0.0000000E+00 0.00000000E+00
   1,
Н(
         2) OK 3.180000098E+02 3.180000000E+02 3.083032558E-08
   2,
H (
         2) OK -1.200000017E+01 -1.20000000E+01 1.294047150E-08
Н(
   3,
   1, 3) OK 0.00000000E+00 0.00000000E+00 0.00000000E+00
H (
H( 2, 3) OK -1.200000017E+01 -1.200000000E+01 1.294047150E-08
H( 3, 3) OK -2.400000049E+01 -2.40000000E+01 1.943240311E-08
                        SUMMARY
                ( Verify : Expensive )
          THE GRADIENT OF THE OBJECTIVE FUNCTION IS ---- [OK]
          THE JACOBIAN OF THE CONSTRAINT FUNCTION IS --- [OK]
          THE HESSIAN OF THE LAGRANGIAN FUNCTION IS ---- [OK]
                      CONTROL PARAMETERS
         checkG = T f_available = 1 deall_error_fatal = F
         checkJ = T c_available = 1 print_level = 3
         checkH = T g_available = 1 verify_level = 2
error = 6 J_available = 1 out = 6
                    H_available = 1
                MATRIX DATA
           J%type --- COORDINATE
           J%id --- Toy 2x3 matrix
           H%type --- COORDINATE
           H%id --- Toy 3x3 hessian matrix
           ... =
n =
                   2
```

J%row	J%col	J%val
 1	1	1.000000000E+00
1	2	1.8000000571E+01
1	3	2.1000001142E+01
2	2	-1.080000000E+02
H%row	H%col	H%val
2	2	3.180000000E+02
3	2	-1.200000000E+01
3	3	-2.4000000000E+01
	EXIT STA	ATUS: 0
END		CCK_verify