A FAST VIEWER FOR AOE SIMULATION RESULT FILES

aoeViewer

Version 2.2.0

User and Reference Guide

The interface, the algorithms, the file format,
the C ABI and the scripting API

Paulo R. A. Gilz

This edition replaces the 2.0.0 guide and the 2.1.x addenda.

Contents

About this edition **4**

1 What changed since 2.0.0 **5**
1.1 In 2.1.0 . . . 5
1.2 In 2.2.0 . . . 5
1.3 In 2.2.0 . . . 6

2 What aoeViewer is **7**
2.1 The shape of the program . . . 7
2.2 What the program does . . . 7

3 Getting started **9**
3.1 What you need . . . 9
3.2 Building and running . . . 9
3.2.1 Sample data . . . 9
3.2.2 Where the library is looked for . . . 10
3.3 Command-line options . . . 10
3.4 Logging, and what to do when it will not start . . . 10
3.5 The first plot . . . 11

4 The window **12**
4.1 Anatomy . . . 12
4.2 The main toolbar . . . 12
4.3 Mouse modes . . . 13
4.4 The status bar . . . 14
4.5 Files that change underneath you . . . 14
4.6 Theme . . . 15
4.7 Interface size . . . 16

5 The twelve panels **17**
5.1 DATA — choosing runs . . . 17
5.2 Filtering the run list . . . 18
5.3 PARAMS — choosing the axes of a tile . . . 18
5.4 COMPUTE — channels the file does not contain . . . 19
5.5 ALIAS — a second name for a channel . . . 20
5.6 ISO — filtering runs by a value they hold constant . . . 20
5.6.1 Grouping values into intervals . . . 21
5.6.2 Two constraints, composed . . . 21
5.6.3 What a workspace keeps, and what it does when the data has moved on 22
5.7 STYLE — colour, line, marker and legend . . . 22
5.7.1 Two encodings, chosen separately . . . 23
5.7.2 What decides a curve's colour . . . 23
5.7.3 The two tables . . . 24
5.7.4 The legend . . . 24
5.7.5 Titles and axis captions . . . 25
5.8 SCALE — axis ranges and cross-tile constraints . . . 25

5.8.1 When two constraints meet on one axis . . . 25
5.9 3D — three channels against each other . . . 26
5.10 INSPECT — reading values off a curve . . . 27
5.11 AREA — shaded bands . . . 27
5.12 MARKERS — an instant, drawn two ways . . . 28
5.13 TEXT — captions on a tile . . . 28

6 Pages, grids and tiles **29**
6.1 The page and tile bar . . . 29
6.2 How a page is modelled . . . 30
6.3 What a tile remembers . . . 30
6.4 Robustness when the files change . . . 31

7 Exporting, and saving your work **32**
7.1 Image . . . 32
7.2 CSV . . . 32
7.3 Workspaces . . . 32
7.3.1 Save, and Save as . . . 32
7.3.2 Names given to files and runs . . . 33
7.3.3 Loading against data that has moved on . . . 33
7.4 Background work, and why the interface freezes when it does . . . 34

8 The AOE file format **35**
8.1 Overall shape . . . 35
8.2 Two header dialects . . . 35
8.3 How runs are delimited . . . 36
8.4 Records, rows and wrapped lines . . . 36
8.5 Numeric encoding . . . 37
8.6 File extensions . . . 37
8.7 SYNC — aligning the runs on an event . . . 37
8.8 Files that are not AOE: HDF5 . . . 39

9 How the data is read **41**
9.1 Memory mapping . . . 41
9.2 One index pass, then lazy parallel columns . . . 41
9.3 The inner loop . . . 42
9.4 What happens to malformed input . . . 42
9.5 The `.aoec` sidecar . . . 42
9.5.1 Layout . . . 43
9.5.2 Deciding whether it is still valid . . . 43
9.5.3 Where sidecars live . . . 43
9.5.4 What it buys . . . 44
9.6 The memory budget . . . 44

10 Computed parameters: the formula language **45**
10.1 How an expression is executed . . . 45
10.2 Operators . . . 45
10.3 Element-wise functions . . . 46
10.3.1 The three logarithms . . . 46
10.4 Whole-series functions . . . 47
10.5 Constants and the lookup form . . . 47
10.6 Worked examples . . . 48

10.7 Names, dependencies and errors . . . 48

11 The algorithms behind the plots 50
11.1 Decimation: drawing what the screen can show . . . 50
11.1.1 Selecting the visible window . . . 50
11.1.2 The pixel budget . . . 50
11.1.3 Statistics over the same window . . . 51
11.2 The redraw cache . . . 51
11.2.1 The resample key . . . 51
11.2.2 Adopting the drawn items . . . 51
11.2.3 The plot's own settings . . . 52
11.2.4 The drawn annotations . . . 52
11.3 ISO grouping . . . 52
11.3.1 Boundaries . . . 53
11.3.2 How values are written . . . 53
11.4 Legend order, and why it stopped shuffling . . . 53
11.5 Logarithmic axes . . . 54
11.6 The three-dimensional projection . . . 54

12 The C ABI 55
12.1 Handles, versioning and errors . . . 55
12.2 Thread safety . . . 55
12.3 Function reference . . . 56
12.4 Building against it . . . 58

13 The Python scripting API 59
13.1 The one rule . . . 59
13.2 Session . . . 59
13.3 Handles . . . 60
13.4 A worked script . . . 60

14 Performance, limits and troubleshooting 62
14.1 Where the time goes . . . 62
14.2 Getting the best out of it . . . 62
14.3 Troubleshooting . . . 63
14.3.1 The program will not start . . . 63
14.3.2 A file opens but shows nothing . . . 63
14.3.3 The curves look wrong on a phase plane . . . 63
14.3.4 A value I expected is missing or reads as nan . . . 63
14.3.5 A channel disappeared after I removed a computed parameter . . . 63
14.3.6 Colours changed when I opened another file . . . 64
14.3.7 I reopened a workspace and the plot is empty . . . 64
14.3.8 I swapped one study for another and the axes moved . . . 64

A Keyboard shortcuts and gestures 65

B Environment variables 66

C The workspace file 67

D Defaults at a glance 69

E Known limitations 70

About this edition

This is a single document. It replaces two: the *2.0.0 User and Reference Guide* and the *2.1.1 user-guide addendum*, which existed only because the guide had not been revised. Everything those two said is here. Where the 2.1.0 and 2.2.0 releases changed behaviour the 2.0.0 text described, the text has been rewritten rather than annotated, so nothing in this guide has to be read against a correction printed elsewhere.

Passages that describe behaviour introduced or changed after 2.0.0 are marked with a blue box naming the version, so a reader who knows 2.0.0 can find what moved without reading the whole guide again. Chapter 1 summarises the same ground in two pages.

Every label, default, range and limit quoted here was read from the source of version 2.2.0. Where the code and an earlier edition of this guide disagreed, the code won, and the discrepancy is recorded in a grey box. Where a genuine limitation exists, it is recorded in a red box. This edition carries no figures: it is a text reference, and the screenshots of the 2.0.0 edition described an interface that has since moved.

One version number is worth separating from the others before it causes confusion. **The application is at 2.2.0; the core library is still at 2.0.0**, which is what `aoe_version()` returns and what `-version` prints as the core version. Nothing in the C ABI changed across the 2.1 releases — every change was above the seam — so the core did not need a new number.

Chapter 1

What changed since 2.0.0

1.1 In 2.1.0

Dual encoding. A curve now carries two independent identities. *Colour by* — Parameter, Simulation or ISO — decides the colour and nothing else. *Style by* — None, File, Simulation or ISO — decides the dash pattern and the marker. *None* is the 2.0.0 behaviour, in which dash and marker hang off the colour key. See §5.7.

Two style tables. The single *Curves* table of 2.0.0 became two: *Colour*, with one row per coloured identity, and *Line*, with one row per styled identity. Both scroll.

Titles carry the names; axes do not. The captions beside Y and under X are blank. The tile title names every selected parameter, as `ALPHA, NZ = f(TIME)`, and wraps onto two lines rather than truncating.

PARAMS puts the selection first. On the active tile, the ticked Y parameters are listed before the rest, in the order they were ticked. The filter still only hides names.

Workspaces record more. The schema is still version 3, and files also carry `app_version` and, per tile, `style_mode` and `style_iso_param`.

1.2 In 2.2.0

Renamed files and runs survive a workspace. A name given in DATA is saved and restored. See §7.3.

***Style by ISO* reaches the legend.** Ticking *ISO* in the legend row now writes every ISO identity a curve carries, not only the colour's. Colouring by parameter while styling by ISO used to produce one row per parameter with no ISO value in it. See §5.7.4.

The ISO parameter checkbox selects values. It is a select-all over the values beneath it, tri-state, rather than the filter's own on/off flag — which moved to the row's context menu as *Use this filter*. See §5.6.

Unticking a parameter returns it to its place. It no longer stays at the top of the PARAMS list once it is no longer selected.

Legends are smaller. One point less, less padding inside the frame and less space between a swatch and its text. The row that reports a capped legend now names the cap instead of only counting what it left out.

Files are reloaded on request, not on a timer. The three-second disk poll and its *Files changed on disk* dialog are gone; *Reload* in the DATA tab re-reads what you ask it to. See §4.5.

A run keeps its identity across a reload. Run keys are built from the name a file was first given rather than from its current label, so renaming a file and then reloading it no longer detaches every colour and dash set for its runs.

Reusing a workspace against another study keeps the axes. Removing one file and adding another used to lose every tile's x axis on the way through zero open files. See §6.4.

Colour by Parameter is the default, and leads the row.

Rebuilds that change nothing cost less. The plot's own settings and the drawn annotations

are written only when they differ; the PARAMS filter waits for the typing to stop; a file of more than 200 runs opens closed in DATA. None of this changes what is drawn — see §11.2.

1.3 In 2.2.0

The interface has a size. Two buttons in the toolbar make the text and the spacing around it larger or smaller — everywhere: the tab rail, the panels, the bar itself, and the titles, axes and legends on the plots. The setting is saved with the workspace. See §4.7.

The panels scroll. Each one sits in a scroll area, so the window's minimum height no longer depends on the tallest panel. On a screen shorter than about 1000 usable pixels the window previously could be neither shrunk nor maximised.

The colour picker no longer paints itself in the colour being edited. Its OK, Cancel and two other buttons took the swatch's colour and disappeared into it on a light one.

***Fit* moved to the page and tile bar,** with the rest of what acts on the tiles. Ctrl+0 still works from anywhere in the window.

The light/dark toggle moved to the toolbar, out of the foot of the tab rail where it took vertical space from the tabs and selected no panel.

Building the executable writes `sample/`. Two 250 MB flight files and one small one, beside `build/` and `dist/`, generated once and never rewritten. See §3.2.1.

Chapter 2

What aoeViewer is

aoeViewer reads AOE simulation result files — plain-text tables of many runs against many channels, routinely hundreds of megabytes — and plots them interactively. It is built as a C++17 core under a Python and Qt interface, and the seam between them is a plain C ABI, so the core is one shared library that any CPython 3.8 or later can load through `ctypes` and that any language with a C foreign-function interface can drive equally well.

2.1 The shape of the program

Layer	Responsibility
`core/` (C++17)	Memory-maps the result file, builds a sample index, parses columns on demand across a thread pool, evaluates computed parameters, decimates series for display, buckets ISO values into intervals, and reads and writes the `.aoec` sidecar. Owns all sample memory and the cache budget.
`core/include/aoe/aoe_c_api.h`	The seam: an opaque-handle C ABI with a thread-local error string. Everything above this line is written without a C++ compiler.
`python/aoeviewer/_core.py`	Discovers and loads the shared library through `ctypes`, and wraps returned pointers in zero-copy NumPy views whose lifetime is pinned to the underlying block.
`python/aoeviewer/session.py`	A Pythonic façade — `Session`, `FileHandle`, `SimulationHandle`, `IsoGroup` — which is also the public scripting API.
`python/aoeviewer/model.py`	`AppState`: everything the core does not own. Pages, tiles, selections, ISO filter definitions, styles, annotations, scale constraints, and the workspace file format. Contains no Qt.
`python/aoeviewer/ui/`	The Qt layer: the main window, the twelve side panels, the plot grid and the plot tiles.

A rule visible throughout the source is that anything testable without a display lives in a Qt-free module. `model.py`, `scales.py`, `isogroups.py` and `projection.py` import no Qt, which is why the decimation budget, the log-axis conversion, the interval arithmetic and the orthographic projection can all be tested headlessly, and are.

2.2 What the program does

Five ideas account for most of the interface.

A page of tiles. The plotting area is a grid of up to twenty-five independent tiles, arranged from 1×1 to 5×5, and there may be any number of pages. Each tile is a complete plot definition: its own x channel, its own set of y channels, its own legend, its own axis locks, its own colouring and styling rules, and optionally its own three-dimensional projection.

Two independent constraints on what is drawn. The DATA tab chooses runs by name. The ISO tab chooses runs by the value some parameter holds constant across a run — a mass, a Mach number, a configuration. The two compose with a logical AND: a curve is drawn if and only if its run is ticked in DATA and admitted by every active ISO filter. Neither tab ever writes into the other's state.

Two independent encodings of what is drawn. Colour names one identity and the dash pattern names another, chosen separately per tile. Several files of the same parameters on one tile is the case this exists for: colour by parameter, style by file, and the eye reads both at once.

Channels that need not exist in the file. A computed parameter is an expression over the channels that are there — `deriv(THETA, TIME)`, `NZ / max(NZ)`, `ALTITUDE[TIME=last] - ALTITUDE[TIME=first]` — evaluated in the core, per run, and thereafter indistinguishable from a channel the file carried. An alias is a second name for an existing channel, so a cryptic column can be given a readable one without touching the data.

Drawing what the screen can show, exporting what the data says. A tile with twenty-five runs of five hundred thousand samples does not hand two and a half million points to Qt. It asks the core for a min/max decimation of exactly the visible window at roughly two points per horizontal pixel, so that narrow spikes survive but the item count stays in the low thousands. The CSV export does the opposite and writes every sample, because a plot is a picture and an export is data.

Chapter 3

Getting started

3.1 What you need

Building the core requires nothing but a C++ compiler — GCC 8 or later, Clang 7 or later, MSVC 2019, or MinGW-w64 — and GNU make (or `mingw32-make.exe` on Windows). CMake is supported as an alternative but is not required. Running the graphical application additionally needs three Python packages: `numpy`, for array views over the core's buffers; `PySide6-Essentials` together with `shiboken6`, for the Qt widgets; and `pyqtgraph`, for the plotting canvas. Building the standalone executable adds `PyInstaller`.

3.2 Building and running

```
# 1. Build the core
./build.sh                  # Linux and macOS
build.bat                   # Windows (MinGW)

# 2. Check that it works
./build.sh test             # or: build.bat test

# 3. Run
PYTHONPATH=python python -m aoeviewer               # Linux and macOS
set PYTHONPATH=python && python -m aoeviewer        # Windows
```

The build produces `build/libaoecore.so` on Linux, `build/libaoecore.dylib` on macOS and `build/aoecore.dll` on Windows. Two directories are generated rather than kept in the repository: `build/`, holding the compiled core and the PyInstaller work files, and `dist/`, holding the frozen executable.

To try the program without real data, generate a sample:

```
python tools/gen_sample.py sample.aoe --sims 6 --rows 40000
PYTHONPATH=python python -m aoeviewer sample.aoe
```

3.2.1 Sample data

New in 2.2.0

Building the executable also writes `sample/`, beside `build/` and `dist/`: two flight files of about 250 MB with twenty-five runs each, and one of 12 MB for a quick look.

The sizes are the point. A few megabytes exercises none of what this program is built around: the `.aoec` sidecar is not written below 8 MB, decimation has nothing to decimate, and a six-run file has no sweep for ISO to filter. Two large files rather than one, so that *Colour by Parameter* with *Style by File* has something to show.

Only the files that are missing are generated, and one already there is never rewritten — these take minutes to integrate, and someone who has trimmed one down or replaced it with their own data should not find it overwritten by a rebuild. Each is written under a temporary

name and moved into place, so an interrupted run leaves nothing that looks finished; without that, a Ctrl+C halfway through would count as "already there" on the next build and the viewer would open a truncated file.

Failure here never fails the build: a sample file is a convenience, not part of the product, so a read-only checkout or a full disk prints a reason and the executable is produced anyway. `--no-samples` skips the step.

The generator is `tools/gen_flight_data.py`, which integrates a longitudinal rigid-body model with a pitch-rate autopilot rather than emitting noise — test data made of sine waves lets a viewer look correct while being wrong in the ways that matter, since it has no transients that decimation must preserve and no per-run constants for ISO to key on.

3.2.2 Where the library is looked for

`_core.library_path()` searches in a fixed order, most specific first: the environment variable `AOEVIEWER_CORE` (which may name either a file or a directory); `sys._MEIPASS` and `sys._MEIPASS/aoeviewer`, which is where a PyInstaller bundle unpacks; the directory of the executable when frozen; the package directory; `<project>/build`; and finally the working directory. If none of them yields a loadable library, the raised `CoreError` lists every directory that was searched and suggests building the core first. On Windows a load failure that looks like a missing dependency adds a hint to run `objdump -p "<path>" | findstr "DLL Name"`.

3.3 Command-line options

Four options are recognised, and two of them are diagnostic tools worth knowing before you need them.

Option	Effect
`files...`	Result files to open at startup, given as positional arguments.
`-version`	Prints the application version (2.2.0), the core version (2.0.0), the path of the core library actually loaded, the worker count and the log path.
`-selftest`	Imports `numpy`, `PySide6`, `PySide6.QtWidgets` and `pyqtgraph` one at a time, loads the core through `ctypes`, then constructs a `QApplication`, falling back to the offscreen platform when there is no display. Prints `OK` or `FAIL` per component, then either *All checks passed.* or a count of failures. This is the first thing to run when the program will not start.
`-memory-limit MB`	Cap on cached sample data, default `2048.0`, floored at 64 MB. Columns beyond the cap are dropped least-recently-used first and re-read on demand.

3.4 Logging, and what to do when it will not start

The logger is named `aoeviewer` and writes `aoeviewer.log` through a rotating handler of 2 MB with three backups. The directory is chosen in order: the environment variable `AOEVIEWER_LOG_DIR`; the directory of the executable when frozen, or the project root when running from source; `~/.aoeviewer`; and the working directory. On startup the log records the application and core versions, the core library path, the Python and platform versions, the worker count and the PySide6, pyqtgraph and NumPy versions — which between them identify almost every environment problem.

The application installs `sys.excepthook`, `threading.excepthook` and a Qt message handler, so an unhandled exception anywhere, including inside a Qt callback, reaches the log

rather than the void. If construction of the main window fails, the traceback is logged and printed, and a dialog titled *aoeViewer could not start* appears with the log path as its informative text and the traceback as its detail.

3.5 The first plot

When the program opens with no arguments the window is empty: a grid of one tile labelled *empty tile*, and a DATA tab with nothing in it.

Getting to a plot takes two steps. Press *Add files* in the DATA tab and choose one or more result files; each appears as a top-level row with its runs beneath it, and every run is ticked by default. Then open the PARAMS tab, where the x axis has already defaulted to the first channel whose name begins with `TIME`, and tick one or more y channels. The tile draws as soon as it has both an x channel and at least one y channel.

Opening a file of any size is done on a worker thread, and for files of 8 MB or more the same task also writes an `.aoec` sidecar beside the result file. That happens once; subsequent opens of the same file skip the index scan entirely and are several times faster. Chapter 9 describes the mechanism.

Chapter 4

The window

4.1 Anatomy

The window has six regions. Across the top is the main toolbar, holding workspace load, save and save-as, the two exports, the auto-fit button and — pushed to the right edge — the four mouse modes. The title bar above it names the workspace currently open, with a leading asterisk while there are unsaved changes. Down the left edge runs the tab rail, a 21-pixel strip of vertically painted labels which selects which of the twelve panels is shown beside it. It holds tabs and nothing else: up to 2.1.1 the light/dark toggle was pinned to its foot, where it competed with the tabs for the one dimension a short screen is short of, and where it was the only button in the column that selected no panel. The panel itself occupies a splitter pane that can be dragged between 230 and 600 pixels wide. To its right, the plot area is divided into the page and tile bar along its top and the grid of tiles below. The status bar along the bottom carries, from left to right, the description of any running background task or the standing summary of what is loaded, an indeterminate progress bar while a task runs, the crosshair readout, and the size of the sample cache.

The active tile is the one every per-tile control acts on, and it is marked by a two-pixel accent border rather than a one-pixel neutral one. Clicking any tile makes it active. That border is set through a guard that returns early when the state has not changed, which is not a micro-optimisation: `QWidget.setStyleSheet` performs no comparison of its own and repolishes the widget and all its children, and since a tile is a `QGraphicsView` that means a full scene repaint. Without the guard, one click on a 5×5 page would repaint twenty-five plots.

4.2 The main toolbar

Ten buttons in three groups: the workspace, the two exports, and the interface — then, pushed to the right edge, the four mouse modes. Every one of them is a labelled icon, and every icon is painted at request time rather than loaded from a file.

Button	Shortcut	What it does
Load workspace	Ctrl+L	Opens a saved `.aoews` workspace, replacing everything currently loaded.
Save workspace	Ctrl+S	Overwrites the current workspace, asking for a path only if there is not one yet. The tooltip names the file it would write.
Save workspace as…	Ctrl+Shift+S	Always asks for a path, then continues in the new file and leaves the old one as it was.
Image	—	Saves the active page as a PNG, exactly as displayed.
CSV	—	Writes the active tile's curves to a CSV file at full resolution.
Smaller	Ctrl+-	Interface size: smaller text, tighter spacing, everywhere.
Larger	Ctrl+=	Interface size: larger text, roomier spacing, everywhere.
Light / Dark	—	Switches the theme. Its label and icon name the theme a press would *give* — a sun while the dark theme is on — rather than the one already on screen.
Select	Ctrl+1	Mouse mode: click to activate a tile; drag annotations.
Inspect	Ctrl+2	Mouse mode: click a curve to read every channel; drag to measure a slope.
Pan	Ctrl+3	Mouse mode: drag to move the view.
Zoom	Ctrl+4	Mouse mode: wheel zooms, drag a rectangle to zoom into it.

There is deliberately no *Open* action: *Add files* in the DATA tab and *Load workspace* here already cover it.

The interface group sits behind its own rule and under its own caption — *Smaller*, *Larger* and the theme — because those three are the ones here that change nothing about the data or the view: everything to their left acts on the workspace or on the plots, and these act on the window itself.

The toolbar is permanent by construction. Its context menu is suppressed, its `toggleViewAction` is disabled and hidden, and `MainWindow.createPopupMenu` returns nothing, because hiding the only toolbar in a window that has no menu bar would leave no way to bring it back. Its icons are not image files: they are painted on demand by `ui/icons.py` onto a 100×100 canvas and cached by name, colour and size, so they follow the theme and survive a PyInstaller bundle that ships no assets.

4.3 Mouse modes

The four modes are exclusive, and the inactive ones are genuinely off rather than merely ignored — in Select and Inspect the view box has mouse interaction disabled on both axes, and the wheel event is swallowed. Switching mode writes a one-line hint into the status bar.

Switching into Inspect brings the INSPECT panel to the front, and clicking a curve brings it forward again every time, because that is where the answer appears. Leaving Inspect clears the inspection dot. A locked axis stays locked whatever the mode says: the limits are re-applied and per-axis mouse interaction disabled on every redraw, so no drag or wheel gesture can escape a range you have frozen.

Mode	Drag does	Wheel	Annotations
Select	Moves markers and the edges of shaded areas; moves the legend and text captions.	inert	movable
Inspect	Rubber-bands a slope line; a drag shorter than six pixels counts as a click and inspects instead.	inert	frozen
Pan	Pans the view. On a 3D tile: turns it; middle-drag or Shift+drag slides it; right-drag or Ctrl+drag zooms.	inert	frozen
Zoom	Rubber-bands a rectangle to zoom into.	zooms	frozen

Annotations are movable only in Select mode and only on a two-dimensional tile.

4.4 The status bar

The standing summary reads *N file(s), P run(s) plotted, M parameter(s)*. When an ISO filter is holding runs back it becomes more explicit — *4 file(s), 17 of 25 run(s) plotted, 8 held back by the ISO filter(s), 42 parameter(s)* — which is the shortest honest description of a state that would otherwise look like lost data.

The progress bar is deliberately indeterminate: it has range 0 to 0, a fixed width of 120 pixels and no text. The core reports no progress from inside a parse, and a fabricated percentage would be worse than an honest working. On the right, *cache NN MB* is the sample data the core is holding; its tooltip explains that columns are dropped automatically when the figure exceeds the limit and re-read when needed again.

4.5 Files that change underneath you

Changed in 2.2.0 — nothing polls the disk

Up to 2.1.0 a timer fired every three seconds, asked the core which open files had changed, and put up a dialog titled *Files changed on disk* offering to reload them.
It was wrong in both directions. It interrupted work that had nothing to do with the file it was asking about — the question arrives while you are reading a plot of something else, and answering it is the only way back. And it could not be trusted anyway: a solver halfway through rewriting its output is a file that has changed and must *not* be read, so the prompt's best case was asking a question it had no business asking, and its worst case was talking you into a half-written file.
Whether the data on disk is finished is a question only the person running the solver can answer. Now they answer it.

Reload, in the DATA tab, re-reads the selected file or files from disk; with nothing selected it re-reads every open file, which is what "the solver has just finished" usually calls for. Selecting a run means the file it belongs to — there is no such thing as reloading one run. The same action is on the row's right-click menu, named after the file it would re-read.

A reload drops every cached sample for those files and re-reads the index, so it costs a full parse and runs on the worker thread exactly as opening does; a sidecar the new contents have invalidated is rewritten in the same pass, which spends the parse the user is already waiting for rather than the next open's.

Names survive it. The file keeps the name you gave it, every run keeps its own, and so do their colours and dashes.

Why a reload used to lose the styles of a renamed file

A run's key is `<file>::<id>::<ordinal>`, and `reload()` re-opens the dataset and rebuilds every key. While the `<file>` part was the *display* name, renaming a file and then reloading it renamed every one of its run keys with it — and every colour, dash and marker the user had chosen was suddenly attached to a key nothing answered to.
It was invisible while reloading was something a timer occasionally offered. Making it a button people press on purpose is what brought it out. The key is built from the name the file was *first* given, which renaming does not touch and a reload does not change.

On closing, if anything has been modified, a three-way prompt titled *Unsaved changes* offers to save the workspace first; *Cancel* aborts the close. The application then waits up to thirty seconds for background work to finish before destroying the session, because tearing the core down while a worker is still inside it would write into freed memory.

4.6 Theme

The theme button is in the toolbar's interface group (§4.7), and flips the whole application: the plot canvases, the legend grounds, the painted toolbar icons and the text captions.

Changed in 2.2.0

It was at the foot of the tab rail, labelled *L / D*. Its label and icon now name the theme a press would give rather than the one already on screen — a sun while the dark theme is on — because a toggle labelled with its current state reads as a description, and a button is an offer.

The stylesheet sets every colour it depends on instead of inheriting from the desktop, because Qt's default palette differs enough between Linux and Windows that an application which is correct on one can be unreadable on the other. Two details are worth knowing. Check and radio indicators are drawn explicitly, including the ones inside tree, list and table views — those are drawn by the views rather than by `QCheckBox`, and they are the ticks beside a run in DATA, a parameter in PARAMS and a value in ISO. And the type scale exists only as a set: widget text is sized in pixels (10 px body, 9 px for hints, section titles and the status bar) while plot text is sized in points (7.5 pt tile titles, 7 pt axes, 6 pt legend rows, 6.5 pt readouts and captions), because a stylesheet that sets a pixel size makes `QFont.pointSizeF()` report -1 and any code that reads a font back would have to guess.

Changed in 2.2.0 — legend type

Legend rows were 7 pt, the same as the axes, until 2.2.0. They are 6 pt now, with less padding inside the legend's frame and less space between a row's swatch and its text. A legend is a key that is read once and glanced at thereafter, and at the axis size it was taking a visible corner out of every tile on a 3×3 page.

4.7 Interface size

New in 2.2.0

Smaller and *Larger* in the toolbar scale the whole interface, from 70 % to 160 % in steps of ten points. The setting is saved with the workspace, like the theme.

One knob rather than a set of them. Text set two pixels smaller inside unchanged padding looks shrunken rather than roomier, so the padding, the tick boxes, the scrollbars and the rail move with the type or none of it should. It reaches:

- the application stylesheet — every font size and every padding figure in §4.6 is a base size multiplied by the scale;
- the widgets that paint their own text, which measure it themselves and so are not reached by a stylesheet. The tab rail is the one that shows: its *width* is the height of its rotated labels, so it re-measures and the column grows or shrinks with them;
- the plots — tile titles, axis tick numbers, legend rows, the crosshair readout and the text captions are all sized in points handed to pyqtgraph, and the legend's own padding moves with them.

What it does not touch is anything measured in the data: curve widths, marker sizes and band opacities are choices about the plot rather than about the window, and they have their own controls in STYLE, MARKERS and AREA.

Each button disables itself at its end of the range. A button that silently does nothing is worse than one that says it cannot: the scale clamps, so without that the last press at either end reads as the window failing to respond.

Why this exists

The base sizes are one compromise, chosen for a 1080-high screen, and screens are not all that. This was reported from a 1400 × 1050 Linux session, where the window overflowed the screen and could not be maximised; a 4K screen at 100 % has the opposite problem. Scrollable panels (below) make the window fit on any screen; this makes it *comfortable* on one.

Chapter 5

The twelve panels

The tab rail selects one of twelve panels. Selecting a tab refreshes that panel immediately and marks the others stale, so they are refreshed lazily when next shown — which is why no panel is allowed to write application state while refreshing. Five of the panels act on the active tile only (PARAMS, STYLE, SCALE, 3D, TEXT); the rest are global.

New in 2.2.0 — the panels scroll

Each panel sits in a scroll area, and the reason is the window's minimum size rather than the panel's own.
A plain widget's minimum height is the sum of its children's, and STYLE is tall: four switches, two encodings with their combos and hints, two tables and a legend group. Added to the toolbar, the page bar and the status bar, the window's minimum height came out near 950 px — fine on a 1080-high screen, and taller than the usable area of a 1050-high one once a desktop panel takes its share. The window could then neither be shrunk nor maximised, because a maximise that cannot satisfy the minimum is refused outright.
A scroll area does not propagate its child's minimum height, so the window's minimum stops depending on the tallest panel. Nothing is hidden: a panel keeps its full height and scrolls only when the pane is shorter than it, which on any screen that fitted before never happens. Horizontal scrolling is off, so a control can never be parked off to the side where it cannot be found.

5.1 DATA — choosing runs

The panel is a tree with one top-level row per open file and one child row per run. *Add files* opens the file dialog, which filters on AOE result files (`*.aoe *.dat *.txt`). *Remove* unloads the selected files, and acts only on file rows — selecting a single run and pressing *Remove* must not unload the whole file it belongs to. *Clear all* unloads everything.

Ticking a run plots it. Ticking a file row plots every run in that file, and clearing it plots none of them; the box is tri-state, so a file with only some of its runs ticked shows the indeterminate mark. The same two operations are on the context menu by name — *Plot all 25 runs in flight_b.aoe* and *Plot no runs in flight_b.aoe* — along with *Rename…*, *Reload … from disk* and, on a file row, *Copy full path*. At the foot of the panel, *Plot all* and *Plot none* act across every loaded file, driven from the session rather than from the tree. *Reload*, beside *Rename*, re-reads files from disk; §4.5 describes what it does and why nothing does it on its own.

Changed in 2.2.0 — a very large file opens closed

A file of more than 200 runs arrives with its runs hidden until you open it. Expanding a node is what makes Qt lay out and build view items for its children, so a twelve-hundred-run study — the size the performance chapter measures — paid for all twelve hundred rows on load, before anyone had looked at one. Nobody scrolls through twelve hundred rows to find a run either.
Nothing is missing: every run is in the tree, its tick is in force, and *Plot all* still reaches it.

Whichever way you leave a file, open or closed, is remembered — by path, so it survives a reload and a rename.

Renaming, by double-click or from the menu, changes the display name only. The identity a style attaches to is a separate key that never changes, so recolouring does not follow a rename; the tooltip of a renamed run records what the file calls it.

New in 2.2.0 — names are saved

A name given here is written into the workspace and restored when it is loaded. Before 2.2.0 it lived only for the session, so a study whose files had been given readable names came back as `flight_b.aoe` the next morning. §7.3 describes how the names are keyed and what an older workspace does.

Why the list does not blink

The tree is rebuilt only when its structure changes — a signature over each file's index, name, path and the index, name and file-level identifier of each of its runs. Ticking a box leaves every widget in place and writes only the check states, so scroll position and expansion survive. Before this, selecting a run rebuilt the whole tree, which read as a flicker and lost your place in a twenty-five-run file.

A run that is ticked here but excluded by an ISO filter is painted grey, and its tooltip gains a sentence explaining that it is held back rather than unselected. That greying is the visible half of the two-constraint model described in §5.6.

5.2 Filtering the run list

New in 2.2.0

The box above the DATA tree.

Runs are often named `X.Y.Z` and often number in the hundreds, so the slow part of this panel is scrolling. Typing in the box hides what does not match.

A bare pattern matches any part of the name: `2.1` shows `2.1.3` and `1.2.1` alike, because the middle field is as often the interesting one as the first. A pattern containing a wildcard is matched against the whole name instead, so `2.*.3` means first field 2, last field 3. Matching ignores case, and a file whose own name matches keeps all of its runs — having asked for that file, hiding most of it would be perverse.

It is a view and nothing else: a hidden run keeps its tick and goes on being plotted, and clearing the box brings it back exactly as it was. While a filter is typed, *Plot all* and *Plot none* read *(shown)* and act only on the rows on screen; "show me 2.1*, then plot all of them" is the reason to have a filter at all.

5.3 PARAMS — choosing the axes of a tile

PARAMS sets the x channel and the y channels of the active tile, and nothing else; the legend, grid, log scale and marker settings that once lived here moved to STYLE. The x combo and the y list both display the channel's label — the name with its unit appended, as in `ALTITUDE [ft]`, when the file's dialect carries one — but both carry the bare name as their data, so a unit can never be mistaken for part of a name.

The filter box matches against the channel name, uppercased. If the text contains `*` or `?` it is treated as a wildcard pattern; otherwise it is a substring test. Non-matching rows are hidden rather than removed, so the ticks of channels you have filtered out of sight are still in force.

It refilters 400 ms after the last keystroke rather than on every one. These files carry hundreds of channels — 585 in one of the dialects this reads — so a letter is several hundred rows hidden or shown and a relayout of the list, and the answer between two letters of the same word is not one anybody reads. It is the same delay, for the same reason, that the TEXT panel uses before it commits a caption.

Right-clicking a channel offers *Create alias for NAME…*, *Use as X axis* and *Copy name*. The alias dialog is pre-filled with a readable guess made by replacing underscores with spaces and capitalising words.

Changed in 2.1.0 and 2.2.0 — the order of the list

In 2.0.0 the y list was in file order and the tile's y list took the channels in the order they appeared in the list, not the order you ticked them.
Since 2.1.0 the ticked channels of the active tile are listed *first*, in the order they were ticked, and the rest follow in file order. That order is also the tile's y list, so it is the order the title names them in and the order the legend and the CSV export use. The filter still only hides rows: a selected name that does not match stays selected and stays at the top, hidden until the filter lets it through.
2.2.0 fixed the other half of that. Unticking a channel now returns it to its place among the unselected ones. In 2.1.0 the promotion was applied to the list's own order, which has no way back — once a name had been moved to the top, "the order as given" *was* the promoted one — so an unticked channel stayed at the top until something else rebuilt the list. The promotion is recomputed from the file order on every tick now.

Displayed default versus committed default

Refreshing the panel displays a sensible x channel — the first whose name starts with `TIME`, otherwise the first channel — but does not write it to the tile. The default is committed once per redraw, by `AppState.apply_parameter_defaults()`, and only for tiles that already have a y or z channel. Blank tiles are left blank.

5.4 COMPUTE — channels the file does not contain

A computed parameter is a name and an expression. Type both and press *Create*; the expression is validated on every keystroke, and the line beneath the field reads *Valid* or carries the core's parse error. Validation evaluates nothing — it parses and resolves identifiers only — so it is cheap enough to run while you type.

Once created, the parameter behaves exactly like a channel read from the file. It appears in PARAMS, in ISO, in the INSPECT tables, in the CSV export, and it can be referenced by other formulas. *Edit selected* loads a definition back into the fields; the name field is disabled while editing, because renaming would orphan every expression that referred to it. Applying an edit re-evaluates the parameter everywhere. *Remove selected* removes it, and also removes everything that depended on it, saying which: *Removed MACH_SQ, and ENERGY which depended on it*.

The *Help* button opens the complete syntax reference, which is also reproduced in Chapter 10.

5.5 ALIAS — a second name for a channel

Choose a channel, type a display name, press *Add alias*. The new name appears everywhere a channel name can appear and resolves to the same data. Aliases are resolved in the core, chains are followed, and a cycle such as `A -> B -> A` is broken rather than hung. The defined list shows each alias with the name it resolves to, and *Remove selected* deletes one.

Aliases are saved, and survive data that has moved on

An alias is written into the workspace and restored with it. If the channel behind it is not in the files the workspace reopens with, the alias is kept rather than dropped — it costs nothing until it resolves, and the file it belongs to may be opened next — and the load reports it so that an axis plotting nothing has an explanation.

5.6 ISO — filtering runs by a value they hold constant

An ISO parameter is one whose value is constant within a run but differs between runs: the initial mass of a sweep, a Mach number, a configuration index. The ISO tab filters the runs by those values, and several ISO parameters can filter at once, combining with a logical AND so that each one narrows the set further.

Choose a parameter in the *Filter by* combo, which lists only parameters not already filtered on, and press *Add*. The parameter appears as a checkable node whose badge summarises the selection — *all 75*, *none of 75* or *2/3* — followed by *paused* when the filter is switched off, *grouped* when it is grouped, *not in the loaded files* when no open file carries it, or *N outside the groups* when some values fall outside every interval. Its children are the individual values, or the interval names once grouped, each separately checkable.

The tab is a **tree**: one collapsible node per parameter over its own values, so every filter and everything selected in it is on screen at once. It replaced a list of parameters above a list of the selected one's values, which could only ever show one filter's values at a time — with three active there was no way to see what was selected without clicking through them and remembering.

```
v MACH      3/12
    0.70
    0.75
    0.80
> WEIGHT    all 5   grouped
> INITIAL_MASS   2/3   paused   grouped
```

Changed in 2.2.0 — what a parameter's checkbox does

It is a **select-all over the values beneath it**. Ticking it ticks every value — or every interval, when the parameter is grouped — unticking it unticks them all, and it shows a partial tick when some but not all are on. That is the same thing the *All* and *None* buttons do to the selected parameter, reachable now from the row itself.

Up to 2.1.0 that box carried the filter's own on/off flag, so the obvious reading of a checkbox sitting above a list of checkboxes did something else entirely, and clicking it appeared to leave the values alone.

The on/off flag moved to the row's right-click menu, as *Use this filter*, where it is named rather than guessed at. Switching it off keeps the values you ticked — which is what makes "with and without this" a two-click comparison — and the row says *paused*, so a filter that is not narrowing anything still accounts for itself in the tree.

Four buttons act on the selected parameter: *Group…* opens the interval editor, *All* and *None* tick or untick every value, and *Remove* stops filtering by it. The context menu carries the same operations, plus *Ungroup* and *Use this filter*. Ungrouping keeps the intervals in state, so re-grouping returns to what you had set up.

Ticking an individual value also switches the filter on, since choosing what to show is a statement that the filter should be applied. Unticking everything does not switch it off, and does not switch it on either: it says nothing about whether the filter is paused, so a paused filter stays paused rather than being activated to admit nothing.

5.6.1 Grouping values into intervals

The header of the grouping dialog states how many distinct values there are and the range they span. The *Groups* spin box is bounded above by the number of values — there can never be more groups than values — and *Distribute evenly* splits the observed range into equal intervals, discarding boundaries edited by hand. The table is editable in its *Name*, *From* and *To* columns; *Values* is read-only.

The editing model is the reason overlapping intervals are impossible rather than merely rejected. N groups are stored as $N + 1$ sorted edges, so the *From* of one row and the *To* of the row above are the same number; editing either moves that single edge, clamped between its neighbours. Interior gaps and overlaps are therefore unrepresentable. The two outer edges may still be moved inward, which is how an outlier is deliberately excluded, and the note beneath the table then reports how many values fall outside every group. A comma is accepted as a decimal point, and a cell that cannot be parsed silently restores its previous value. Changing the group count clears hand-typed names and re-splits evenly; names you typed yourself are never regenerated.

Bounds are inclusive at both ends and the first claiming group wins, so a value sitting exactly on a shared edge belongs to the earlier interval.

5.6.2 Two constraints, composed

The decisive property of this panel is what it does not do: applying a filter never writes into the DATA selection. A run is drawn if and only if

$$\text{ticked in DATA} \;\wedge\; \text{admitted by every active ISO filter.}$$

Ticking a run whose ISO value is excluded therefore puts it on no tile, and changing an ISO filter never re-ticks the DATA tab. The panel's summary line says how many of the DATA tab's runs are being held back, and the status bar repeats it.

What this replaced

An earlier version wrote the filter result into the run selection. Applying a mass filter then silently re-ticked the DATA tab, and re-ticking a run in DATA appeared to widen the filter: two controls, one piece of state, each overwriting the other's answer. The intersection is now computed only where curves are actually drawn, and memoised, because every tile asks the same question on every rebuild.

Two details of the admission rule are worth stating. A run whose value for the parameter is not a number is never admitted — it has no value for that parameter, so no interval can claim it. And for an ungrouped filter, a value absent from the tick map counts as on, so a value that appears only after a new file is opened is shown rather than silently hidden.

5.6.3 What a workspace keeps, and what it does when the data has moved on

The filter definitions are saved: which parameters are filtered on, their intervals, and which values are ticked. What is not saved is the answer — which runs those filters admit describes the files the last workspace had open, and is rebuilt once the new ones are known.

A workspace outlives the run it was made from. The solver is re-run with fewer channels, a file is replaced, a parameter is renamed; none of that may raise, and none of it may quietly empty the plot. Three cases are distinguished, and the load reports each of them in one dialog titled *Workspace loaded with differences*.

Situation	What happens	Shown as
No open file carries the parameter	The filter constrains nothing: it cannot speak about a channel that is not there.	*not in the loaded files*
The parameter is there, but no run falls in a ticked interval	The filter genuinely admits nothing, and the plot is correctly empty.	*no run satisfies it*
The column is there but a run's value is not a number	That run alone is excluded — the column exists and this run has no value for it.	greyed in DATA

A filter with nothing to say says nothing

The first row of that table used to read the other way: a filter on a parameter a file did not carry excluded every one of that file's runs. That is defensible read on its own and wrong in every case it actually arises. It made a filter on a parameter only some files carry hide every run of the others, and — once filters became part of a saved workspace — it made a workspace whose ISO parameter had since disappeared open to an empty plot with nothing at all to explain it.

Entries that cannot be read at all are skipped individually rather than failing the load: a value that is not a number, an interval with non-numeric bounds, an entry that is not an object. A reversed interval is normalised rather than refused, and a grouped filter whose intervals did not survive is demoted to ungrouped rather than left in a state the tab would have to invent intervals for.

Very long value lists are truncated in the tree at four hundred children, with a non-checkable row reading *…and N more, still filtered on*. The ticks for those values live in the state, so the filter still applies to them; only the rows are omitted, because laying out several thousand tree items is slow enough to be felt. A parameter's checkbox acts on *every* value, including the ones past that cap.

5.7 STYLE — colour, line, marker and legend

The panel opens with four per-tile switches — *Legend*, *Grid*, *Log Y* and *Points* — whose defaults are on, on, off and off. *Points* draws a circular marker on every curve of the tile that has no marker of its own; a per-curve marker overrides it.

5.7.1 Two encodings, chosen separately

New in 2.1.0 — Colour by and Style by

In 2.0.0 there was one choice, *Colour by*, and the dash pattern and marker hung off whatever key it produced. A curve therefore had one identity, and a tile showing the same three channels from three files could distinguish the channels or the files but not both. There are two choices now, made independently on each tile.

Colour by — *Parameter*, *Simulation* or *ISO* — sets the colour and nothing else. *Parameter* is the default, and leads the row: a tile is nearly always asked which quantity a line is, and colouring by run answers a different question — one that a twenty-five-run study answers with twenty-five colours that name nothing the user chose. Each radio is identified by its mode rather than by its place in the row, which is also what a workspace stores, so the row can be reordered without re-labelling a saved tile. Choosing *ISO* reveals an *ISO parameter* combo. If the tile has no ISO parameter yet, the combo displays the default without writing it, and selecting the radio commits that choice immediately — so that the table below is built from the same parameter the plot will use. Getting this wrong was a real defect: the table was built from the old choice and showed the wrong rows until something else forced a refresh.

Style by — *None*, *File*, *Simulation* or *ISO* — sets the dash pattern and the marker. *None* is the 2.0.0 behaviour: dash and marker follow the colour key. Choosing *ISO* reveals a second combo, *Style ISO*, which need not name the same parameter the colour does.

The pairing this exists for is several files of the same parameters on one tile: *Colour by Parameter* and *Style by File*. The colour says which quantity, the dash says which file, and the two read at once.

Colour by	One colour per	Key
Parameter	y channel of the tile (the default)	`param::<name>`
Simulation	plotted run	`sim::<run key>`
ISO	value or interval of the chosen ISO parameter	`iso::<param>::<label>`

Style by	One dash per	Key
None	—	the colour key above
File	open file	`file::<path>`
Simulation	plotted run	`sim::<run key>`
ISO	value or interval of the *Style ISO* parameter	`iso::<param>::<label>`

The two key namespaces are the same, which is deliberate: a tile that colours and styles by the same thing gets the same key from both, and a curve keeps one identity rather than two that could drift apart.

Apply encoding to all tiles copies all four choices — both modes and both ISO parameters — onto every tile of every page, hidden tiles included.

Dash patterns are handed out in order of first use from `solid`, `dash`, `dot`, `dashdot`; past the fourth distinct identity the cycle repeats and a marker is added from the ten shapes, so a fifth file is still told apart from the first.

5.7.2 What decides a curve's colour

A colour, once allocated, is kept for the session. The palette has twelve entries and the registry hands them out in order of first use, so the first three curves on a tile are always red, then blue,

then dark green, whatever the colouring mode — allocation depends on the order keys are first seen, not on what they describe. Three curves is the common case, and a set of figures whose three colours mean the same three things throughout is easier to read than one whose first colour depends on how many curves happened to be on the tile. There is deliberately no cyan near the front: cyan and a light green are the same colour once a line is one pixel wide. The remaining entries are ordered for separation. Loading another file therefore never recolours what is already on screen.

Re-assign palette deliberately forgets the current assignments so the next redraw allocates afresh, and *Reset widths* drops per-curve widths so all follow the global setting. Two global spin boxes set the line width, from 0.1 to 10.0 with a default of 1.6, and the marker size, from 1.0 to 20.0 with a default of 6.0.

5.7.3 The two tables

Changed in 2.1.0 — one table became two

The single *Curves* table of 2.0.0 is now a *Colour* table and a *Line* table, because the two encodings have different row sets: three parameters and four files is three colour rows and four line rows, not twelve of anything. Both scroll when the list is long.

Colour has one row per coloured identity in the current *Colour by* mode, with a swatch that opens a colour dialog. *Line* has one row per styled identity in the current *Style by* mode, with a dash combo over `solid`, `dash`, `dot` and `dashdot`, and a marker combo over eleven shapes from *none* to *hexagon*. With *Style by* set to *None* the Line table shows a single unselectable row reading *Style by is None — dash follows colour*; when nothing is plotted, both show *Nothing plotted yet*.

5.7.4 The legend

A legend row is assembled from up to four parts, each switched separately: *Parameter* (on by default), *ISO*, *File* and *Simulation*, joined by vertical bars. The dash pattern and marker are never spelled out in words, because the legend already draws a sample of the curve.

With *File* and *Simulation* off, rows whose text is identical are merged. That merging is the point of the switches: twenty-five runs sharing three ISO intervals produce three rows rather than twenty-five saying the same thing.

Fixed in 2.2.0 — ISO and *Style by ISO*

Ticking *ISO* writes every ISO identity the curve carries, not only the colour's.
Before 2.2.0 only the *Colour by* parameter's label was consulted. On a tile colouring by parameter and styling by ISO that label is empty — colour is not keying on ISO, so no ISO labels were looked up at all — so *ISO* wrote nothing, every row came out as just the parameter name, and the rows, being identical, were merged into one. A tile whose dashes carried the whole sweep had a legend that could not explain it.
It reads `ALT | MACH = 0.75` now, one row per value, ordered by value — or by interval, when the parameter is grouped — exactly as the colour path already was. When *Colour by* and *Style by* name the same ISO parameter it is written once, not twice.

Beyond sixty rows the legend stops adding them and appends a pen-less entry reading *…and N more (legend caps at 60 rows)*. The cap is what keeps a large study viewable: pyqtgraph lays out two graphics items per row, and a thousand-run study froze the application here before it existed. The row names the cap rather than only counting what it left out, because a bare count reads as missing data — every curve those rows would have named is drawn, and

turning *File* and *Simulation* off merges the identical rows, which usually brings the count back under the cap by itself.

The *Corner* combo snaps the legend to any of the four corners. Dragging the legend on the plot puts it anywhere, switches the corner to *custom* and keeps the position, including in a saved workspace. *Apply legend to all tiles* copies this tile's whole legend configuration — whether it is shown, its corner or dragged position, and which parts make up a row — onto every tile of every page, and reports how many tiles changed or says that every tile already had it.

5.7.5 Titles and axis captions

Changed in 2.1.0 — the title carries the names

The captions beside Y and under X are blank. The tile's title names every selected parameter and the x channel, as `ALPHA, NZ = f(TIME)`, and a long list wraps onto a second line rather than being truncated.
A caption beside the axis repeated what the title already said and spent a strip of a tile that is often one ninth of a page. The unit reaches the reader through the tick values and the INSPECT tables instead.

A tile with nothing to draw says so in the same place: *empty tile*, *no parameter selected (x: TIME)*, *ALTITUDE (no x axis selected)*, or *3D tile — choose X, Y and Z*. A three-dimensional tile reads `ALTITUDE = f(EAST, NORTH)`.

5.8 SCALE — axis ranges and cross-tile constraints

While an axis is unlocked, its two boxes follow the plot as you pan and zoom, so ticking *Lock X range* or *Lock Y range* is a one-click way to freeze exactly what you are looking at. Locked, the boxes are the range: they are enabled, and typing in one moves the frame. The boxes span $\pm 10^{12}$ with six decimals and do not commit per keystroke — a value takes effect on Enter or when the field loses focus. A minimum typed above its maximum is normalised rather than allowed to blank the plot.

A locked range is a hard bound, not a starting point: the view's limits are set and per-axis mouse interaction disabled, so no drag or wheel can leave it. A degenerate range is refused, because a view frozen at zero width looks exactly like a crash.

The two *Apply* buttons attach a range to the variable rather than to the tile. *Apply X range to every tile with the same X axis* gives every plot against that x channel, on every page, the same horizontal scale, so they can be compared directly. *Apply Y range to every tile sharing a parameter* does the same for any tile showing any of this tile's y channels. Because these constraints are re-applied on every redraw, they also govern tiles that acquire the parameter later — which is the whole point, and which the first implementation got wrong by walking only the tiles that existed when the button was pressed.

5.8.1 When two constraints meet on one axis

A tile has one y axis and may draw several channels on it, so it can be asked for two different vertical windows at once. Consider three tiles: the first draws `ALTITUDE`, the second draws `ALTITUDE` and `MACH`, the third draws `MACH`. Constrain `ALTITUDE` from the first tile and `MACH` from the third, and the second tile now carries two incompatible demands.

No arithmetic satisfies both, so none is invented. Parameters that ask for the same window are applied normally. Parameters that disagree leave the tile exactly as you had it — free, and therefore auto-fitting to show all of its data — and the SCALE tab says so, naming the

parameters and their ranges, with the offending entries marked in the *Constrained variables* list. A button, *Use the range that covers both*, then offers the compromise as something you choose rather than something you are given; it locks this tile, not the variables, so the tiles whose scales the constraints were set to fix keep them.

Why not simply take the union?

Taking the smallest window containing both is the obvious answer, and it is what the program used to do. It is wrong twice over. A union is a superset of both ranges and therefore honours neither, which defeats the entire purpose of the feature: the point of constraining a variable is that two tiles showing it can be compared directly, and under a union they cannot. And when the two ranges differ in magnitude the union destroys the smaller channel — `ALTITUDE` at $[0, 13000]$ unioned with `MACH` at $[0, 1]$ leaves Mach occupying 0.008 % of the axis height, a flat line along the bottom edge, with nothing on screen to explain it. Which parameter survived depended on its magnitude rather than on any decision the user had made.

The x axis cannot fail this way. A tile has exactly one x channel, so the lookup returns at most one range however many x constraints are declared; the conflict is not representable. The same channel may carry one window as an x axis and a different one as a y axis, which is correct — they are different axes — and the *Constrained variables* list labels every entry with the axis it belongs to.

Three-dimensional tiles are skipped entirely. Their frame is the projection's own centre and zoom, and the two-dimensional ranges describe data extents that mean nothing to a projection; locking them did no visible harm but left a tile mysteriously locked if it was ever switched back to two dimensions.

The *Constrained variables* list shows every such constraint, and *Clear all variable constraints* removes them while leaving per-tile locks alone. *Unlock both and auto-fit* releases this tile and also pops its parameters out of the variable-wide constraints — without which the next redraw would simply re-lock it.

When the frame moves

A tile is fitted once, when it first acquires data. After that the frame moves only on *Fit*, on a double-click, or when SCALE changes something. An ordinary redraw — restyling a curve, ticking a run, toggling the grid — never moves the frame. Locking x on a tile whose y is free is the one exception: the y axis is re-fitted inside the new x window, computed by a single pass in the core that understands a non-monotonic x, because otherwise a windowed manoeuvre sits as a flat line at the bottom of the tile.

5.9 3D — three channels against each other

Ticking *Draw the active tile in 3D* turns the active tile into an orthographic projection of three channels, filling in plausible axes if the tile has none. The three combos set x, y and z; a 3D tile uses exactly one y channel. *Rotation* sweeps the azimuth from 0 to 359 degrees and *Tilt* the elevation from -89 to $+89$, clamped rather than wrapped because past straight up or down the projection turns inside out. Four presets — *Iso*, *Top*, *Front*, *Side* — set the pair directly, and *Apply these axes to every 3D tile* copies axes and view onto every other tile already in 3D.

Two switches control the depth cues. *Orientation axes (X, Y, Z)* draws the fixed-size triad in the corner, coloured by the universal convention — x red, y green, z blue — and hovering it names the channel on each axis and its range. *Reference grid and tick values* draws the back-wall

grid and its numbers; without them the projection has no depth cue and no numeric scale, but on a very dense trajectory they can be turned off.

Each channel is normalised independently onto $[-0.5, 0.5]$, so three channels with unrelated units stay readable together; a channel that never moves collapses to the middle of the cube, which is the honest picture of a constant. In Pan mode a drag turns the object, middle-drag or Shift+drag slides it and right-drag or Ctrl+drag zooms; in Zoom mode the wheel zooms. Double-click or Ctrl+0 frames everything again.

Both encodings apply here. Colour and dash are resolved exactly as on a two-dimensional tile, so *Style by File* distinguishes the trajectories of two files in one cube. A projection has no legend, so the legend switches do nothing on a 3D tile.

Markers and areas are not drawn on a 3D tile

A vertical line is not a plane, and the indices a marker dot would use refer to the thinned, projected arrays rather than to samples. Annotations are therefore restricted to two-dimensional tiles.

5.10 INSPECT — reading values off a curve

Switch the mouse to Inspect and click a curve. The header names the file, the run and the x value at the click; the *At a point* tab then lists every channel of that run at that sample, with its unit, printed to six significant figures and with a dash where a value is not a number. *Copy to clipboard* writes the header and one tab-separated line per visible row — visible meaning after the channel filter, which accepts the same wildcards as PARAMS.

The nearest curve is found in pixels, not in data units. The two axes carry unrelated scales, so a distance measured in data space would always pick the channel with the larger numbers.

The *Statistics* tab gives minimum, maximum, mean, standard deviation and sample count for every combination of plotted run and y channel of the active tile. By default it reports over the visible x window and follows pan and zoom; *Whole channel instead of the visible range* widens it. Its header states the scope exactly, including the mixed case that arises when some runs have an x channel shorter than their y channel and therefore cannot be windowed at all. Both tables copy to the clipboard tab-separated.

Dragging in Inspect mode measures a gradient instead. A dashed line follows the pointer with the running figure beside it, and on release the panel reports the slope, the two deltas, both endpoints and the inverse. A purely vertical drag reports the change in y over no change in x rather than an infinity. A drag shorter than six pixels is treated as a click, so a slightly unsteady hand still inspects a point.

5.11 AREA — shaded bands

Add places a band across the middle of what the active tile currently shows — from 40 % to 60 % of the visible x span — using that tile's x channel. The editor beneath sets visibility, the x channel, the two bounds, the colour and the opacity, which runs from 0.02 to 1.0 with a default of 0.20. The bounds are normalised on commit, and the two buttons *Show all* and *Hide all* act on every band at once.

Bands are global: they appear on every page, on every tile whose axes can express them. They are drawn *over* the curves, because a band underneath them lost its edges wherever a curve crossed one.

In Select mode the edges of a band can be dragged directly on the plot, and the panel follows. There is deliberately no caption field: a caption typed here rebuilt the tile on every keystroke, deleting the very item being edited. Name a band with a TEXT note placed over it.

5.12 MARKERS — an instant, drawn two ways

A marker is a value of one channel — `TIME = 707.35`, say. *Add* places one at the midpoint of the active tile's x window. The editor sets visibility, the channel, the position, the colour and the dot size, which runs from 2.0 to 30.0 with a default of 9.0.

The dual rendering is the feature. On a tile whose x axis is the marker's channel the marker is a dashed vertical line, draggable in Select mode. On any other tile it becomes a dot on each curve, at the sample where the condition holds — which says something a vertical stripe could not: on a plot of angle of attack against altitude, where the aircraft was at that instant.

A marker that falls outside a run's range is refused rather than clamped to the last sample, because a clamped dot would silently claim the condition had been met. The band's equivalent rendering redraws the matching stretch of every curve in the band's colour, with separate passes through the band left unjoined.

5.13 TEXT — captions on a tile

Captions belong to the active tile — the deliberate opposite of markers and areas — and are positioned as a fraction of it, from 0.0 to 1.0 in each direction with $y = 0$ at the top. *Add text* appends a note reading *Note*, staggered downward from any notes already there. The editor sets visibility, the text (several lines are fine), the position, the point size from 4 to 72, bold, and the colour, which starts as the current theme's text colour. Nine *Place* buttons are corner and edge presets. *Copy to all tiles* deep-copies this tile's captions onto every visible tile of every page.

Typing does not commit on every keystroke: a 400 ms idle timer fires after you stop, or the caption commits when the field loses focus, or immediately on *Update text now*. Committing per keystroke used to flicker the tile and steal the caret. Notes can also be dragged directly on the plot in Select mode, and the spin boxes follow; clicking outside every note passes the click through, so empty space still selects the tile.

Chapter 6

Pages, grids and tiles

New in 2.2.0

Duplicate copies the whole page, tiles and all: the copy is named `<name> (2)`, inserted straight after the original and made active, since a duplicate is nearly always the start of a variation on the page it came from. Duplicating a duplicate gives `(3)` rather than `(2) (2)`.
The **remove** button now asks before removing a page, and says how many configured tiles are on it. It is one character wide and sits beside Add; a mis-click used to take a page of work with no way back.
Double-clicking a tile makes it active, fits it *and* brings PARAMS forward — three things from the gesture that means "this tile, now".

6.1 The page and tile bar

The bar immediately above the grid governs layout. On the left, a combo switches page, flanked by previous and next buttons, and a name field renames the current page on Enter or when it loses focus. Four small buttons add a page, remove the current one, and move it earlier or later in the order. Removing the last remaining page is refused.

In the middle, the *Grid* button drops a five-by-five matrix in the manner of a word processor's table picker. Sweeping the pointer highlights the layout and the caption underneath reads, for example, *2 x 3 (6 tiles)*; releasing chooses it. Cells whose layout would exceed twenty-five tiles are painted faint and cannot be chosen.

To its right, *Tile N* names the active tile and four arrows swap it with its neighbour to the left, above, below or right; each arrow is enabled only when that move is possible, and the active index follows the tile so the move is its own inverse. Then *Copy*, *Cut*, *Paste* and *Clear* act on the active tile's whole configuration. Pasting installs an independent deep copy, so pasting twice gives two tiles that can then diverge. This clipboard lives in the process only and is not saved to a workspace.

Last, behind its own rule, *Fit* (Ctrl+0) auto-scales every tile, honouring axis locks; double-clicking one plot fits just that one.

Changed in 2.2.0

Fit was in the main toolbar, among the workspace and export actions. It acts on the tiles, and you pick a tile by clicking it, so it belongs within a few pixels of them — the same reason the rest of this bar is here. Behind its own rule because it moves no tile and copies nothing: it re-frames what is already there.
The shortcut is unchanged and still works from anywhere in the window. An action that is on no widget has no shortcut at all, so it is registered on the window rather than on a bar.

6.2 How a page is modelled

Every page always carries twenty-five tile objects regardless of its grid, and the visible count is the product of rows and columns, capped at twenty-five. Shrinking a grid therefore hides tiles rather than destroying them, and they return unchanged when it grows again. Only the visible tiles are written to a workspace; loading pads the list back up to twenty-five.

The tile widgets themselves are recreated only when the shape of the grid changes. Constructing a pyqtgraph plot widget costs tens of milliseconds, so a fresh 5×5 page costs most of a second; switching between two pages of the same shape reuses the widgets and merely redraws them.

6.3 What a tile remembers

Field	Meaning	Default
`x_param`, `y_params`	the channels drawn; a 3D tile adds `z_param`	empty
`show_legend`	legend visible	on
`legend_position`	corner, or `custom` once dragged	`top-left`
`legend_x`, `legend_y`	dragged position as a fraction of the view	0.02, 0.02
`legend_show_param`	the channel name appears in a legend row	on
`legend_show_iso`	every ISO identity of the curve appears	off
`legend_show_file`	the file name appears	off
`legend_show_sim`	the run's own identifier appears	off
`legend_show_style`	withdrawn; read for compatibility, never drawn	off
`lock_x`, `lock_y`	the axis is frozen at the stored range	off
`x_min`, `x_max`	horizontal range, in data units	0.0, 1.0
`y_min`, `y_max`	vertical range, in data units even in log mode	0.0, 1.0
`view_initialised`	this tile has been fitted once already	off
`log_y`	logarithmic y axis	off
`show_grid`	grid lines	on
`show_points`	fallback circular marker on every curve	off
`color_mode`	parameter, simulation or ISO	parameter
`color_iso_param`	the ISO parameter that colours the tile	empty
`style_mode`	none, file, simulation or ISO	none
`style_iso_param`	the ISO parameter that dashes the tile	empty
`plot3d`	draw as an orthographic projection	off
`azimuth`, `elevation`	view angles in degrees	45.0, 25.0
`show_3d_axes`, `show_3d_grid`	triad and back-wall grid	on, on
`view3d_cx`, `view3d_cy`, `view3d_half`	3D pan centre and zoom half-width	0.0, 0.0, 0.95
`texts`	the tile's captions	empty

All of it is saved in a workspace. `style_mode` and `style_iso_param` are the two fields 2.1.0 added; a workspace written by 2.0.0 carries neither and opens with *Style by* set to *None*, which is exactly the behaviour it was written under.

Why `legend_show_style` is still there

It was offered in an early build as *Line style marker* and never read by anything that draws: the legend shows a sample of the curve itself, dash pattern and marker included, so spelling those out in the text said nothing the row was not already showing. The field is

retained so that a workspace written while it existed still loads.

The tile's title is generated from this state and states plainly when something is missing. With several y channels it names them all and wraps onto two lines; see §5.7.

Two 3D view fields deserve a note. The pan centre and zoom half-width are kept separately from the two-dimensional ranges, because those describe data ranges and mean nothing for a projection. The default half-width of 0.95 is chosen because the normalised cube's half-diagonal is $\sqrt{3}/2 \approx 0.866$, so 0.95 frames the whole box at any rotation with a small margin.

6.4 Robustness when the files change

When the set of open files changes, the application re-points anything that no longer resolves and reports what it did in the status bar — for example *page 2, tile 3: x axis VTAS -> TIME*. A missing z channel and a missing colour-by or style-by ISO parameter are cleared; a missing x axis falls back to the default. A missing y channel is deliberately left named: it plots nothing today and comes back when the file is reopened, which is friendlier when a study is loaded one file at a time.

With no file open at all, none of that happens. Closing a study does not destroy a layout, and reusing one workspace against another study — remove the old file, add the new one — keeps every tile's axes.

Fixed in 2.2.0 — swapping studies lost the x axis

Closing a study leaves its computed parameters and aliases defined. That is deliberate: opening the next study should not throw away the formulas and the readable names set up for it. What it also did was convince this step that something was still loaded. `Session.parameters` is the union of file headers, computed channels and aliases, so with nothing open it came back *non-empty* — and the guard here tested whether that list was empty rather than whether a file was open.

So removing `sample1.aoe` re-pointed every tile's x axis at whichever alias or formula sorted first, and adding `sample2.aoe` found that name perfectly valid and left it alone. `TIME` was gone from every tile and nothing said why.

The two questions have two answers now. `parameters` answers "what names may the user write", and still lists everything. `plottable_parameters` answers "what can carry an axis", and is empty while no file is open — a formula over columns that are not loaded evaluates to nothing, and an alias resolves to a channel no file carries. Everything that chooses a channel on the user's behalf reads the second.

A tile whose x channel is genuinely absent from the new study is still re-pointed, and the status bar still says so.

Chapter 7

Exporting, and saving your work

7.1 Image

Image writes the active page as a PNG, grabbing the plot grid widget exactly as displayed: every visible tile with its legend, markers, shaded areas and captions, at screen resolution, without the toolbar, rail or panels. The extension is appended if you omit it. This is the way to get a figure out of the program and into a report.

7.2 CSV

CSV writes the active tile's curves at full resolution, on a worker thread. The header row is `file`, `run`, `parameter`, the name of the tile's x channel, and `value`; note that the fourth column header is the channel's name rather than a literal. There is then one row per sample per combination of plotted run and y channel, in the order the runs are plotted and then the order of the tile's y list, with both numbers written to nine significant figures. Runs whose x or y channel is empty are skipped, and the status bar reports the sample count written.

Why the export is not what you see

The plot is decimated to roughly two points per horizontal pixel. The export is not: silently handing someone twelve hundred of their five hundred thousand points would be a trap. If the tile is empty or nothing is plotted, the button says so rather than writing an empty file.

7.3 Workspaces

A workspace is a single JSON file with the extension `.aoews`. It carries the list of open files by absolute path, the names you gave those files and their runs, every computed parameter, every alias, every ISO filter with its intervals and ticks, every page with its visible tiles and their complete state — both encodings included — the run selection, the whole style registry, the markers, the shaded areas, the variable-wide scale constraints, the theme and the mouse mode. What it deliberately does not carry is any derived answer — which runs the ISO filters admit describes the files that were open when it was written, and is recomputed against whatever is open when it is read.

The schema is at version 3. Files also record `app_version`, which is the build that wrote them and is informational only.

7.3.1 Save, and Save as

There are two buttons, not one with a modifier, because which file is being written is the thing that gets got wrong. *Save workspace* (Ctrl+S) overwrites the current workspace, asking for a path only if there is not one yet. *Save workspace as…* (Ctrl+Shift+S) always asks, and then continues in the new file — leaving the one you came from exactly as it was on disk. That is how a variant is made.

Three places say which file you are in. The window title carries its name, with a leading asterisk while there are unsaved changes. The *Save* tooltip names the file it would overwrite in full, or says that there is no workspace file yet and it will ask. And the status line after a save repeats the path and what went with it — *Workspace saved to C:\study\sweep.aoews (including 2 formula(s), 1 alias(es), 4 renamed run(s), 3 ISO filter(s))*.

7.3.2 Names given to files and runs

New in 2.2.0

A file or run renamed in DATA (§5.1) comes back under that name when the workspace is loaded. Before 2.2.0 the name lived only for the session.

The names ride in two optional keys, `file_names` and `sim_names`. Both are keyed by identity rather than by position — a file by its path, a run by the core's `<file>::<id>::<ordinal>` key — because a workspace is routinely opened against files that have since gained a run or lost one, and a name pinned to "the seventh run" would then land on whichever run happens to sit there. A name whose file or run is not in the data is dropped without comment; there is nothing for it to label.

Runs are written only where the name differs from the identifier the file itself carries, so a thousand-run study does not write a thousand entries saying nothing. A file's name is always written, because the automatic one already depends on what else is open — two files of the same basename make the second *out.aoe (2)*.

Neither key is written when nothing was renamed. A workspace from 2.1.0 or earlier carries neither and loads exactly as before, with each file and run under the name its own contents give it. Both are extra keys rather than a schema bump for that reason: nothing older needs to understand them to keep working, and nothing newer is confused by their absence.

The names are applied on the worker thread, immediately after the files are opened and before anything reads a name, so the first paint already shows them.

7.3.3 Loading against data that has moved on

Loading reads the file, then does everything that touches the core on a worker thread: clears the session, opens each file, builds any missing sidecars, applies the saved display names, installs the aliases, and re-creates the computed parameters.

Aliases are installed before the formulas, since a formula may be written in terms of one. The formulas are then installed in as many passes as it takes, repeating until a pass installs nothing new. A single pass is not enough: a JSON object has no dependency order, so a formula defined in terms of another would be refused — correctly, as an unknown name — and silently dropped. Repeating settles any acyclic chain, and what is left over genuinely cannot be defined against this data.

Nothing here stops the workspace loading. Whatever resolves is in place, and one dialog titled *Workspace loaded with differences* then lists what could not be: files that could not be opened, formulas that could not be defined and why, aliases whose channel is absent (kept, in case it returns), ISO filters on parameters none of these files carry, and ISO filters that no run satisfies.

JSON was chosen over an ad-hoc delimited format because such a format breaks the moment a file path or a parameter name contains the delimiter, and cannot be extended without a version bump nobody implements. The loader is tolerant by design: it sets only the attributes it recognises and ignores the rest, which is how workspaces written when markers and bands still had a caption field continue to load, and how a 2.0.0 workspace loads into the two-encoding model with *Style by* at *None*.

What a workspace still does not carry

The active tile index, the tile clipboard, the memory limit, the window geometry, and the hidden tiles of a shrunken grid. The `"version"` key is written but nothing branches on it; the loader's tolerance of unknown keys is what stands in for version handling.

7.4 Background work, and why the interface freezes when it does

Anything that touches the core runs on a worker thread: opening files, building sidecars, loading a workspace, reading channels, reading every channel of a clicked run, and writing a CSV. This works because `ctypes` releases the interpreter lock for the duration of every call, so a Python thread sitting inside a core function genuinely runs in parallel with the event loop — while the core is using all of its own worker threads inside that one call.

The governing constraint is that the core session is not internally synchronised, so only one thread may touch it at a time. Rather than take a lock, which would merely move the freeze from the paint loop to the click handler, the application disables the panels, the rail, the page bar and the grid while a task runs, and the tiles show a placeholder. Tasks queue rather than overlap, and for redraw work only the newest queued request is kept, since an older one is by then worthless. There is no cancellation: a running task cannot be interrupted.

Most redraws never reach a worker at all. Before dispatching, the application computes a signature of which channels each file must supply and which runs are plotted; when that matches what is already resident and no task is running, the grid is redrawn synchronously on the interface thread. Restyling a curve, toggling a grid or editing a limit is that kind of redraw, and routing it through a background task cost far more than the read it was meant to cover — starting a task disables and re-enables the panels, the rail and the whole grid, and every plot repaints on each of those transitions.

Chapter 8

The AOE file format

8.1 Overall shape

An AOE result file is plain ASCII text. There is no magic number, no preamble, no version field and no binary header; the only structure is a set of directive lines whose first non-blank character is an asterisk, with whitespace-separated decimal numbers between them.

```
*PARAMETRES
 'TIME'   'ALPHA'  'MACH'  'NZ'
*TABLEAU : SIM_001
 0.000 1.2340 0.7500 1.2500
 0.020 1.2350 0.7501 1.2499
*TABLEAU : SIM_002
 ...
*FIN
```

The parser recognises exactly two keywords, `*PARAMETRES` and `*TABLEAU` — note the French spelling of the first, without accent. A line is treated as a directive if and only if its first non-blank character is an asterisk; the keyword is then located by substring search within that line, which is why a form such as `*TABLEAU NUM SIMU: 1.2.0` is recognised as readily as `*TABLEAU : SIM_001`. Any other asterisk directive — `*FIN`, `*ENTITY`, a comment line — closes the open block and ends header reading. Nothing is required to terminate the file: `*FIN` is not special-cased, it is simply one more directive that closes the last block.

No magic bytes, and what that costs

Because nothing identifies the format, the only test of whether a file is an AOE file is whether parsing it yields at least one parameter. A file that maps successfully but contains no usable `*PARAMETRES` block is rejected; a file with headers but no `*TABLEAU` at all opens successfully with zero runs, because nothing rejects that case. Opening also fails if the file cannot be mapped, which deliberately includes a zero-length file.

8.2 Two header dialects

The `*PARAMETRES` block comes in two forms, and the parser chooses per line rather than per file.

The **packed** dialect puts several single-quoted names on one line and carries no units. Every non-empty quoted token on the line becomes a parameter, and its unit is the empty string.

```
*PARAMETRES
 'TIME'   'ALPHA'   'MACH'   'NZ'
```

The **indexed** dialect puts one parameter per line, prefixed by an ordinal and suffixed by a unit. The first quoted token is the name, the second — if present — is the unit, and anything further along the line is ignored.

```
*PARAMETRES
      1 'TIME' 's'
      2 'PARAMETER001'  ''
      3 'PARAMETER002'  'deg'
```

The test that distinguishes them is deliberately strict: digits, then only blanks, then a quote. A packed line begins with the quote itself and so can never match. The strictness matters more than it looks. Treating every quoted token on an indexed line as a name turns a 585-parameter file into 1156 parameters, puts `deg`, `ft` and `s` into the parameter list, and shifts every column index — so that asking for `TIME` silently returns another channel's samples. Correspondingly, quote extraction deliberately emits empty tokens, because the indexed dialect writes an absent unit as `''` and dropping it would shift the following line's unit onto the wrong parameter.

The header section is opened by the first `*PARAMETRES` encountered; a second block is ignored, which is what allows these files to repeat the header before every run. It is closed by whichever comes first: a line that yields no names once names have started, a blank line once names have started, or any asterisk directive.

8.3 How runs are delimited

A `*TABLEAU` line opens a run. Its identifier is everything after the first colon on the line, whitespace-trimmed; if there is no colon, or nothing after it, the identifier becomes `SIM_` followed by the run's one-based ordinal, without zero padding. The run's data begins at the start of the line following the marker, and its end offset is provisionally the end of the file and is rewritten the moment the next directive is met. That design — recording the end as the scan goes — is why the later parse tasks need neither a search nor a per-line terminator test.

Each run also carries a unique key of the form `flight_a.aoe::SIM_001::0`: the file's name, the identifier from the file, and the ordinal. Styles are attached to it and `sim_names` in a workspace is keyed on it, so it has to stay still under everything that is not an identity change.

Two things are not identity changes. Renaming a run does not touch it — the key is not derived from a run's display name. And renaming a *file* does not touch it either: the `<file>` part is the name the file was first given, which `Session` derives from the path before the file is parsed, not the label it currently carries.

Why the second of those had to be said out loud

The `<file>` part *was* the display name, and it went unnoticed because nothing rebuilt the keys. `reload()` does: it re-opens the dataset and builds every key again. So once reloading became something a user does on purpose (§4.5), renaming a file and then reloading it renamed every one of its run keys, and every colour, dash and marker chosen for those runs was left attached to keys nothing answered to.

8.4 Records, rows and wrapped lines

A logical record holds one value per header. Fortran writers wrap a record across several physical lines when it exceeds the format width, so the column counter carries across newlines and resets only after a full set of columns has been read. During the index scan the parser records how many values appeared on the first data line inside a run; only when that equals the column count is the file known to be one record per line, and only then may byte ranges be split at newlines for parallel parsing.

A data line is one whose first non-blank character is a digit, a minus, a plus or a full stop. Everything else inside a run's byte range — free text, blank lines — is skipped silently, and a skipped line does not reset the wrapped-record column counter.

Lines are split on the line-feed character, then trimmed on the right of any run of carriage returns, spaces and tabs, and on the left of whitespace. Both Unix and Windows line endings are therefore handled; classic Mac files, which use a lone carriage return, are not.

8.5 Numeric encoding

Values are decimal text, never binary. The reader accepts rather more than `strtod` would, because Fortran output requires it.

Form	Example	Notes
Plain	`1.5`, `-0.002`, `+3`	leading sign accepted
C exponent	`1.5e3`, `1.5E-3`	
Fortran double exponent	`1.234D+05`, `1.234d5`	`D` and `d` are read as `E`
Fortran bare-sign exponent	`1.234+05`	accepted only once mantissa digits have been seen
Non-numeric token	`NaN`, `Inf`, `*****`	becomes a quiet NaN — never zero

The last row is a design decision worth stating plainly: an unreadable value becomes not-a-number, so a gap in the data leaves a gap in the curve, rather than a spurious zero that would silently distort both the plot and any statistic computed over it.

Mantissa digits accumulate into a 64-bit integer up to nineteen significant digits with the decimal exponent tracked separately, and are scaled once at the end against an exactly-representable table of powers of ten. Digits beyond the nineteenth increment the exponent in the integer part or are dropped in the fractional part. If an exponent marker turns out not to be followed by digits the pointer is rewound, so `1.5e` reads as `1.5` and leaves the `e` to the caller. The result is computed as a double and narrowed to a float for storage.

8.6 File extensions

The core is entirely extension-agnostic: it takes a path, maps it, and parses the content. The only place a suffix appears is the cache-path builder, which appends `.aoec` to the full source name. The extension list lives solely in the file dialog's filter, which accepts `*.aoe`, `*.dat`, `*.txt`, `*.res` and `*.out`. Those are the same format under different customary names; the two real dialects are the packed and indexed header forms, and they are distinguished by content rather than by filename.

8.7 SYNC — aligning the runs on an event

New in 2.2.0

A thirteenth panel. Earlier versions could compare runs only against the clock they were recorded on.

A channel logged over several runs of the same manoeuvre carries that manoeuvre at a different place in each run, because each recording started at a different moment. Plotted against `TIME` the curves are the same shape smeared sideways, and comparing them means comparing the shapes rather than the clocks.

This panel shifts each run along the x axis so that a chosen event lands in the same place for all of them. Nothing in the file changes and no sample is altered; only where the curves are drawn.

The event

Condition	What it finds
first rises above	the first sample past a level you give
first falls below	the same, downwards
first crosses	either direction, judged against where the channel started
first starts to rise	no level needed: the first move of 2% of the channel's own range away from its first sample
first starts to fall	the same, downwards
reaches its maximum	the largest sample of the run
reaches its minimum	the smallest

The two *starts to* conditions take a threshold in percent of the channel's own span rather than an absolute level, which is what lets the same setting mean the same thing on a speed in m/s and an angle in radians.

Where it goes

Move the event to	Result
zero	the axis reads as time since the event
the first run's event	everything moves onto the first run drawn, which keeps the original axis values meaningful
a value I choose	for lining two tiles up on one reference

A car accelerating from rest, logged five times: choose `SPEED`, *first rises above*, `0.5`, and *zero*. Every run is then drawn with $x = 0$ at the moment it began to move.

What it does with the awkward cases

Three decisions worth knowing

The event is interpolated, not rounded to a sample. Two runs logged at different rates would otherwise align only to the sampling interval, which is visible as a step between them. Where the crossing itself falls inside a gap — `NaN`, which is what an unreadable token becomes — the first readable sample past the level is reported instead, because there is nothing to interpolate across.

A run in which the event never happens is left where it is, and counted. The panel reports "7 run(s) aligned, 1 left unaligned because the event was not found in them", and *List the events* names each run with the value found in it. Hiding such a run would lose data; shifting it by a guess would be a lie.

Markers and bands are evaluated in each run's own axis. They go on meaning "this instant in this run" and travel with the curve they mark, rather than being reinterpreted as an offset from the event.

The alignment belongs to the tile, so one page can hold the aligned comparison beside the raw one. *Apply to every tile on this page* copies it across. The title says so as well: `ALT = f(TIME)  [0 = SPEED event]`.

It is saved in the workspace. A workspace written before this existed carries none of these fields, which the loader reads as the default — off — so it opens exactly as it was saved. The schema version is unchanged, deliberately: bumping it would make the workspace unreadable by the version that wrote it.

8.8 Files that are not AOE: HDF5

A result file stored as HDF5 opens like any other. The channels, the runs and the samples are read; everything after that — decimation, ISO filtering, computed parameters, styles, workspaces — is the same code on the same data, because by the time it runs there is nothing to distinguish the two.

This route needs `h5py`, which is not part of the base install. Without it the file dialog still offers HDF5 files and opening one reports that the package is missing, which is the honest failure: nothing else in the program is affected.

Why there is no single HDF5 reader

HDF5 is a container, not a layout. It says how to store named arrays in a tree and nothing whatever about which array is a channel and which is a run, so two exporters writing the same simulation produce trees that share only the file signature. The axis they disagree about most is where a run's identity is written:

```
/RUN_1/ALTITUDE            a group per run, a dataset per channel
/ALTITUDE/ALTITUDE_1_2_0   a group per channel, a dataset per run, the
                           run spelled into the dataset name
/CASE_2/aero/ALTITUDE      the run further up the tree
/ALTITUDE                  a single run, nothing to disambiguate
```

Only one-dimensional numeric datasets are candidates, and only those of the length most of them share, so a short metadata vector sitting beside the channels is passed over rather than becoming a channel two samples long.

How the layout is chosen

Every convention above is tried. Those that do not partition the file consistently — two datasets claiming to be the same channel of the same run, or a run missing a channel another run has — are discarded outright. What survives is ranked on evidence taken from the tree itself:

- whether each channel's key is the name of the group its dataset sits in. `/ALFA/ALFA_1_2_0` read with the run in the leaf gives the channel `ALFA` inside the group `ALFA`; read as a single run it gives a channel called `ALFA_1_2_0` inside a group called `ALFA`, which no exporter writes on purpose.
- whether the run keys are the same beneath every group. A run identity is orthogonal to the tree: each channel has one dataset per run. A key appearing beneath only one group is part of that group's name.
- having found more than one run at all, as a tie-break only, since a file really can hold one.

T

he chosen convention is written to the log at INFO level, together with the runners-up and their scores. If a file ever opens with its runs and channels the wrong way round, that line is the first place to look.

Units come from a `units` or `unit` attribute on each dataset where one exists, and are left empty otherwise — the same position as the packed `.aoe` dialect, where the file declares none.

What is not read

Attributes carrying anything other than a unit — masses, inertias, configuration strings — are ignored. They are not channels, and there is no place in the interface where a per-run property belongs today.

How it reaches the core

The core has no HDF5 parser and gains no new compiled dependency. The file is read in Python and its columns handed down through four calls on the C ABI (`aoe_begin_arrays`, `aoe_add_arrays_sim`, `aoe_set_arrays_column`, `aoe_end_arrays`); what the core ends up holding is the same header table, run list and per-run columns that parsing an `.aoe` file would have produced.

That choice has two consequences worth knowing.

No sidecar. A `.aoec` is a rewrite of a parse of the source, and there is no parse here. None is written for an HDF5 file and none is looked for.
No lazy loading. A parsed file loads a column the first time a curve needs it; a pushed one arrives complete, so its samples are all resident from the moment it opens.

Reload (DATA panel) works and goes back through the reader rather than through the core, keeping the file's index and with it every style keyed on its runs.

Chapter 9

How the data is read

9.1 Memory mapping

The file is memory-mapped, read-only, in one view covering the whole file. There is no chunked or windowed mapping and no explicit page handling; demand paging is left entirely to the operating system, which is the right choice for a file that will be read column-by-column in an order the program cannot predict.

On POSIX the file is opened with `O_RDONLY | O_CLOEXEC`, sized with `fstat` — a size of zero or less is a failure — and mapped with `PROT_READ` and `MAP_PRIVATE`, with `madvise` asking for sequential access ahead of the index scan. On Windows the path is explicitly widened from UTF-8 to UTF-16 before `CreateFileW`, because the ANSI entry points failed silently on non-ASCII paths, and the share mode permits a solver to keep writing the file while it is open. There, asking for sequential access is a deliberate no-op: the flag would have to be set at open time and it measurably hurts the random column access that follows.

The modification time is read per platform — nanoseconds on POSIX, 100-nanosecond ticks on Windows — and returned as an opaque, monotonically increasing integer whose units differ between platforms and must never be interpreted. It is only ever compared for equality.

9.2 One index pass, then lazy parallel columns

Opening a file performs a single linear walk that records only the header names, the units, how many values appeared on the first data line of a run, and for each run its identifier, its unique key and the byte offsets at which its data begins and ends. No sample data is read. Opening a 578 MB file is therefore a scan, not a parse, and if a valid sidecar attaches the scan does not happen at all — headers, units, run identifiers, byte ranges and the values-per-line figure all come straight out of the sidecar's header.

Samples arrive later, per column and per run, the first time something asks for them. Each load maps the file afresh, clamps every recorded byte range to the file's current length — the solver this tool watches truncates and rewrites its output, so the index may have been built against a longer file — computes which columns are not already resident, divides the work into units, and dispatches them across the thread pool. Nothing already cached is re-read. Once parsed, the per-column chunks are stitched together outside the per-run locks, summarised in parallel, and published.

A byte range is split for parallelism only when the file is known to be one record per line, and only when the span exceeds 2 MiB; chunk boundaries are then advanced to the next line feed so that no line is ever split across two workers. The summary pass and the sidecar's copy path both run across the pool as well.

No SIMD, no OpenMP

It is worth saying explicitly, because it is often assumed of code this fast: there are no vector intrinsics and no OpenMP anywhere in the core. A search across the sources and build files for `immintrin`, `__m128`, `__m256`, `-mavx`, `-msse`, `-march=` and `-fopenmp` returns nothing. The parallelism is an ordinary thread pool; the only vector-like trick is scalar

SWAR in the token skipper.

9.3 The inner loop

The innermost loop of the program is the one that turns bytes into floats, and it is written accordingly. A flat vector maps column index to output slot, because a hash lookup per token was measurably too slow. Output vectors are pre-reserved from the observed bytes-per-line of the first line rather than grown. The column counter is declared outside the line loop, which is what carries a wrapped record across newlines. Wanted columns go through the float parser; unwanted columns go through a much cheaper token skipper. Slack is returned to the allocator only when there is enough of it to be worth a reallocation.

Text-to-number conversion is hand-rolled rather than delegated to `strtod`, `strtof` or `std::from_chars`. The reasons are recorded in the header: `strtof` is correctly rounded but locale-aware and roughly an order of magnitude slower, and `std::from_chars` for floating-point types is missing from libstdc++ before version 11 and from older libc++. (`strtod` is used, but only for numeric literals in the formula parser, where performance is irrelevant.)

The token skipper uses the classic SWAR has-zero idiom over a 64-bit word loaded by `memcpy` rather than by a cast — a `reinterpret_cast` there is undefined behaviour that some compilers do miscompile at `-O3` — and locates the first separator byte with a count-trailing-zeros intrinsic. Big-endian builds fall back to a plain byte loop. The measured effect on a 500 MB file is about 2 GB/s against about 1.1 GB/s for a byte-at-a-time skip.

9.4 What happens to malformed input

The core throws no exceptions for malformed data and logs nothing. Every failure mode has a defined, quiet behaviour.

Situation	Behaviour
Non-numeric token	becomes a quiet NaN, token consumed; never zero
The float parser cannot advance	the rest of the line is abandoned
A line that does not start with a digit, sign or point	skipped; the column counter is not reset
A blank line inside a run	skipped
Wrong number of values on a wrapped record	the column counter drifts, and columns silently misalign from there on
The file shrank since it was indexed	byte ranges are clamped to the current length
The file cannot be mapped at load time	columns are marked loaded with an empty block, so the interface does not retry every frame and the channel reads as absent rather than as a line of zeros
Empty or zero-length file	mapping fails, so opening fails
No `*PARAMETRES` block	opening fails
More units than headers	the unit list is resized to the header count
The sidecar disagrees with the dataset's shape	the sidecar is ignored and the text parse takes over

9.5 The `.aoec` sidecar

The first time a file of 8 MB or more is opened, the same background task that opened it also writes a sidecar beside it. Thereafter opening that file skips the index scan and loading a column becomes a copy out of a mapping.

9.5.1 Layout

The file begins with a fixed 128-byte header, followed by one 16-byte record per column, one 24-byte record per run, then the sample data aligned to a 64-byte cache line. The header carries the magic `"AOECACHE"` — eight bytes, not NUL-terminated — a format version of 1, a byte-order mark of `0x01020304`, the column and run counts, the values-per-line figure, and the source fingerprint. What is stored is column-major `float32` sample arrays, plus the complete index — headers, units, run identifiers, run byte ranges in the source, values per line — plus per-parameter-per-run summary statistics: minimum, maximum, whether any value is finite, whether there are gaps, and whether the channel is monotonic. No text is stored, no decimated form, and no formula results.

9.5.2 Deciding whether it is still valid

Three independent properties are compared for exact equality, and all three must match.

Field	Catches	Would miss on its own
size	truncation, extension, append	an in-place rewrite of the same length
modification time	an in-place rewrite	anything that restores timestamps: `rsync --times`, a restore from backup, some build systems
content hash	a rewrite that preserved both of the above	nothing — it is the backstop

The hash is 64-bit FNV-1a, chosen explicitly for being verifiable at a glance: it guards against a file changing underneath the program, not against an adversary crafting a collision. It is seeded with the file's length, so a file that is a strict prefix of another cannot collide with it, and the length is taken from the same open handle that the bytes are read through, so length and content always describe the same file. Files of 4 MiB or less are hashed in full. Larger files are sampled: sixty-four evenly spaced windows of 64 KiB, the first at offset zero and the last ending at the end of the file, with each window's offset folded into the hash before its bytes so that identical blocks moved to a different place in a rearranged file do not cancel out. The cost of validating a sidecar is therefore capped at about 4 MiB of reading however large the source is — which is exactly why the advantage of a sidecar widens as files grow.

9.5.3 Where sidecars live

Two locations are tried, nearest first. Beside the source, the sidecar is the full source name with `.aoec` appended — `run.aoe` becomes `run.aoe.aoec`, keeping the original extension so it can never collide with a differently-suffixed file of the same stem. Failing that, a per-user cache directory is used, with the full source path hashed into the filename so that two files called `results.aoe` in different directories do not share a cache.

Platform	Per-user cache directory
Windows	`%LOCALAPPDATA%\aoeViewer\cache`, falling back to `%APPDATA%`, then `%TEMP%`
macOS	`$HOME/Library/Caches/aoeviewer`
Linux and others	`$XDG_CACHE_HOME/aoeviewer`, else `$HOME/.cache/aoeviewer`

`AOE_CACHE_DIR` overrides that fallback location entirely. Each candidate is tried in turn and the first that both opens and matches is used; one that fails to match is skipped rather than treated as fatal, because the other location may hold a current one. Caching can be switched off entirely by setting `AOE_CACHE` to `0`, `false`, `no` or `off`; the variable is read once per process, because an environment lookup on Windows is a system call.

9.5.4 What it buys

On a 73 MB generated file of 1200 runs by 1000 rows by 6 channels, measured end to end:

Operation	From text	From sidecar
Open (index)	213 ms	22 ms
Preload 2 channels across 1200 runs	81 ms	7 ms
Fetch 1200 curves	6 ms	5 ms
ISO scan	7 ms	0.3 ms
Total	**306 ms**	**32 ms**

Roughly a tenfold improvement. Writing the sidecar took 0.24 s once, and it occupies 27.7 MB against a 73.1 MB source — `float32` is more compact than the decimal text it came from. The two structural wins are that opening does not scan, and that loading a column becomes a copy out of a mapping plus a copy of the precomputed summary, so the summarising pass does not run at all.

The 8 MB threshold lives in the interface, not the core

`MainWindow.CACHE_THRESHOLD_BYTES` is `8 * 1024 * 1024`, and the decision to write a sidecar is made there. Below that size, parsing is quick enough that a sidecar would save nothing measurable and would only leave an extra file beside the results. The consequence is that a script using the Python API gets no sidecar unless it calls `build_cache()` itself. Every reason to skip is silent: a read-only share, a full disk, caching switched off.

9.6 The memory budget

The core owns all sample memory and reports how much it is holding. When that figure exceeds the configured limit — 2048 MB by default, floored at 64 MB — the interface asks the core to trim to 80 % of the cap, which gives the eviction some hysteresis instead of trimming on every redraw. Eviction is least-recently-used by column, and is always safe: an evicted column is simply re-read the next time something asks for it.

Eviction can never free a buffer a visible curve is reading from. Arrays handed to Python are read-only views of the core's memory rather than copies, and each carries a pin object as its NumPy base which keeps the underlying block alive for as long as any view exists. That is also why an eviction invalidates the fast redraw path: what was resident before says nothing about what is resident now, so the next redraw re-checks.

Chapter 10

Computed parameters: the formula language

A computed parameter is a named expression over the channels that exist, evaluated in the core, per run, and thereafter indistinguishable from a channel the file carried. This chapter is the complete language reference.

10.1 How an expression is executed

An expression is compiled once into a flat bytecode and evaluated by a stack machine vectorised over rows. It is deliberately not an abstract syntax tree walked per sample. Compilation happens once per formula rather than once per run; the bytecode stores variable slots and data is bound at evaluation time, so no pointer can dangle when a later column load reallocates a vector. There is no per-node allocation and no virtual call.

The evaluator tracks whether each stack entry is a broadcast scalar or a real buffer, so `2 * 9.81` collapses to a single float rather than filling a million-element array, and buffers are drawn from a reused pool so that a deep expression allocates a handful of buffers rather than one per operator.

10.2 Operators

Level	Operators	Associativity	Meaning
1 (lowest)	`||`	left	logical or
2	`&&`	left	logical and
3	`== !=`	left	equality
4	`<= >= < >`	left	comparison
5	`+ -`	left	addition
6	`* / %`	left	multiplication, division, remainder
7	unary `- + !`	right	sign and logical not
8 (highest)	`^`	right	power

Because `^` is right-associative, `2^3^2` is 512 rather than 64.

Three behaviours are worth knowing before they surprise you. Division by zero yields not-a-number, never an infinity: the reason is stated twice in the source, that an infinity silently destroys the plot's y range whereas a NaN simply breaks the line where the data is bad. The same applies to `%` and to `mod`. Comparisons yield exactly 1.0 or 0.0, so they can be multiplied into arithmetic. And the logical operators do not short-circuit — both sides are always evaluated — which matters only in that a costly right-hand side is not skipped.

The power operator binds tighter than unary minus on its left, so `-2^2` is $-(2^2)$, matching engineering calculators, while `2^-3` still works because the exponent side is parsed as a unary expression. Logical not never swallows an inequality, and `!NaN` is `0.0`.

10.3 Element-wise functions

These operate one sample at a time.

Function	Behaviour
`abs(v)`	absolute value
`sqrt(v)`	NaN for a negative argument
`sin cos tan`	as the C library
`asin(v) acos(v)`	NaN outside $[-1, 1]$
`atan(v)`	arctangent
`exp(v)`	exponential
`log(v) ln(v)`	natural logarithm; both names map to the same operation, and a non-positive argument gives NaN
`log10(v)`	base-10 logarithm; non-positive gives NaN
`floor ceil round`	as the C library
`sign(v)`	-1, 0 or $+1$; NaN gives 0
`deg(v)`	radians to degrees
`rad(v)`	degrees to radians
`min(a,b) max(a,b)`	per-sample smaller or larger; NaN if either is NaN
`atan2(a,b)`	two-argument arctangent
`pow(a,b)`	as `a^b`
`mod(a,b)`	remainder; NaN when `b` is zero
`hypot(a,b)`	$\sqrt{a^2 + b^2}$ without intermediate overflow
`clamp(x, lo, hi)`	constrains `x`; NaN stays NaN
`if(cond, a, b)`	`a` when `cond` is non-zero and not NaN, else `b`. A NaN condition takes the false branch, and both branches are always evaluated

10.3.1 The three logarithms

Which logarithm a name gives is the easiest thing in this language to assume wrongly, since a pocket calculator's `log` is base ten and this one is not. There are two functions under three names.

Name	What it computes
`log(x)`	The natural logarithm, base $e = 2.71828\ldots$ — *not* base ten. This follows C and Fortran rather than a calculator keypad.
`ln(x)`	Exactly the same function as `log`, under the name most engineering texts use. Write whichever reads better; the two give identical results.
`log10(x)`	The base-ten logarithm. This is the one for decibels, orders of magnitude, and anything you would read off a logarithmic axis.

All three return NaN for an argument that is zero or negative rather than an infinity, for the reason given above: a NaN breaks the line where the data is out of domain, an infinity would destroy the plot's y range. The inverse of `log` and `ln` is `exp(x)`; the inverse of `log10` is `pow(10, x)`.

```
DECIBELS = 20 * log10(AMPLITUDE / AMP_REF)
DECADES  = log10(ALTITUDE)
TAU      = -1 / deriv(ln(ENERGY), TIME)
```

Taking a logarithm is not the same as drawing on one

The *Log Y* checkbox in STYLE draws an existing channel on a base-ten axis and leaves the data untouched. Use that to look at a channel logarithmically. Use these functions when you want the logarithm itself as a channel — to take a slope off it, say.

10.4 Whole-series functions

These cannot be evaluated one sample at a time — a derivative needs its neighbours, a filter needs its own previous output — so they operate on the finished buffer.

Function	Behaviour
`deriv(Y, X)`	dY/dX by central differences, one-sided at the two ends, accumulated in double precision. A zero step gives NaN rather than an infinity. A single sample gives zero
`integ(Y, X)`	cumulative trapezoidal integral starting at zero. NaN steps contribute nothing but the running total is still written out
`lowpass(Y, X, fc)`	first-order recursive low pass with the cutoff in hertz. The timestep is taken from `X` at every sample, so uneven sampling is handled correctly. A non-positive cutoff performs no filtering at all rather than dividing by zero
`highpass(Y, X, fc)`	the matching first-order high pass; the first output sample is zero
`movavg(Y, N)`	centred moving average over `N` samples, computed by prefix sum so the cost is independent of the window size. NaN samples are excluded from both the sum and the count; an all-NaN window gives NaN
`delta(Y)`	`Y` minus its first sample, so a leading NaN makes the whole channel NaN
`min(Y) max(Y) mean(Y)`	reductions to one number, accumulated in double and ignoring NaN and infinity, then held flat across every sample so the result combines with per-sample channels by ordinary arithmetic

Overload resolution is by argument count, not by name. `max(NZ)` is the run's peak; `max(NZ, NY)` is the per-sample larger of two channels. Each run is reduced separately, which is what makes `NZ / max(NZ)` normalise every run against its own peak. If a name exists but no definition has that arity, the error names the counts that would have worked — *min() takes 1 or 2 arguments, not 3*.

Passing a scalar where a series function expects its `X` argument fills the result with NaN, because a constant x would make every step zero.

10.5 Constants and the lookup form

Three constants are recognised, case-insensitively: `pi`, `e` and `nan`. There is no `inf`, and no `true` or `false` — comparisons already yield one and zero.

The lookup form reads one channel at the moment another channel satisfies a condition, and broadcasts that single value across the whole series:

```
NAME[COND=value]    # NAME at the sample where COND is closest to value
NAME[COND=first]    # NAME at the first sample where both are real
NAME[COND=last]     # NAME at the last sample where both are real
```

For a numeric target the sample minimising the absolute difference wins; samples whose condition is NaN are skipped, though a NaN value at the winning condition is returned as it stands. For `first` and `last` the scan runs from the respective end looking for the first index at which both the condition and the value are real numbers, so leading and trailing gaps are skipped and the lookup returns an actual sample rather than NaN. If nothing is found the result is NaN.

10.6 Worked examples

```
LOAD_FACTOR  = NZ * 9.80665
PITCH_RATE   = deriv(THETA, TIME)
DISTANCE     = integ(VTAS, TIME)
CLIMB_RATE   = deriv(ALTITUDE, TIME)
ALPHA_SMOOTH = lowpass(ALPHA, TIME, 2.0)
ALPHA_NOISE  = highpass(ALPHA, TIME, 5.0)
DRIFT        = HEADING - HEADING[TIME=first]
ALT_GAINED   = ALTITUDE[TIME=last] - ALTITUDE[TIME=first]
HIGH_MACH    = if(MACH > 0.8, ALPHA, nan)
ENERGY       = 0.5 * MASS * (VX^2 + VY^2)
NZ_NORM      = NZ / max(NZ)
NZ_ENVELOPE  = max(NZ, NY)
ALPHA_EXCESS = ALPHA - mean(ALPHA)
```

`HIGH_MACH` is worth a second look: substituting NaN for the samples you do not want breaks the line there, which is how you isolate a flight phase without editing the data.

10.7 Names, dependencies and errors

Any identifier that is not a call, a lookup or one of the three constants becomes a variable. Names are resolved after alias resolution, and a name must be either a physical column of some open file or another computed channel — otherwise the definition is refused with *unknown parameter 'X'*.

Formulas may reference other computed parameters, and the dependency graph is checked at definition time rather than discovered at plot time. The new definition is installed tentatively, the graph is walked with a depth limit of 32, and on detection the previous definition is restored and the error reads *'NAME' would depend on itself*. Exceeding the depth limit is reported the same way. Removing a parameter removes everything defined in terms of it, and the interface reports which.

Every variable is bound once, up front; a variable that resolves to nothing is a hard failure reading *no data for parameter 'X'*. The sample count is the shortest of the bound channels, and is never allowed to exceed it — the engine never reads past the shortest channel involved. A formula with no variables at all, such as `pi` or `2 + 3 * 4`, would otherwise have no length to fill, so the run's first column is consulted for a row count, falling back to a single row.

Validation, which is what runs as you type in the COMPUTE tab, compiles the expression and checks every variable against the set of known names without touching any data. The distinct compile-time messages are *empty expression*, *unexpected trailing text*, *expected ')'*, *malformed number*, *unexpected character*, *expected ',' or ')' in function arguments*, *unknown function 'X'*, the arity message, four specific lookup messages, and *invalid expression* as a last resort. The lookup messages are unusually helpful and worth quoting:

```
expected a parameter name inside [ ]
expected '=' in lookup, e.g. SPEED[TIME=0.5]
```

```
expected a number, 'first' or 'last' in lookup,
    e.g. SPEED[TIME=0.5] or SPEED[TIME=last]
expected ']' in lookup
```

Two consequences of caching

Results are cached per run and per name, and failures are cached too, as an empty block. Without that the interface would retry the same doomed evaluation on every repaint; and the tempting alternative — substituting a zero — would turn a channel that could not be computed into a flat line that looks like data.
A computed channel also carries no unit. Deriving one through a formula would mean dimensional analysis, and a wrong unit on an axis is worse than none.

Chapter 11

The algorithms behind the plots

11.1 Decimation: drawing what the screen can show

A tile with twenty-five runs of half a million samples cannot hand two and a half million points to a plotting library and stay interactive. Nor can it keep every thousandth sample: stride sampling silently deletes every spike between the samples it keeps, and on flight-test data that is exactly the part an engineer is looking for. aoeViewer therefore uses min/max bucketing.

The visible index span is divided into exactly `max_points` buckets by index, so bucket sizes differ by at most one sample. Within each bucket the minimum and maximum y are found, skipping NaN, and both are emitted in x order — swapped if necessary so the polyline never doubles back. Where a bucket's extremes coincide, one point is emitted; where a bucket is entirely NaN, a single NaN is emitted at the bucket's first x, so the line breaks visibly instead of interpolating across missing data. The output is therefore at most $2 \times$ `max_points` points. Below a count of twice the budget there is nothing to gain, and the span is copied through verbatim.

What the guarantee is, and is not

Every bucket's extremes survive, so the drawn envelope is pixel-accurate: no peak or trough can be lost at any zoom level, because it is either the minimum or the maximum of whatever bucket it falls into. What is not preserved is the shape between extremes within a bucket, nor the exact ordering of intermediate samples. NaN gaps are preserved as gaps, at bucket granularity.

11.1.1 Selecting the visible window

Before bucketing, the visible x window must be turned into an index span, and this is where a subtlety lives. When x is known to be non-decreasing, two binary searches find the span in logarithmic time. When it is not — and a phase-plane plot such as Mach against altitude over a climb and descent is not — a full scan finds the outermost indices whose x falls inside the window and keeps everything between them.

The reason is a real defect the scan fixes. On a climb-and-descend trajectory x rises and then falls, so a binary search brackets only the first crossing and the entire descending half of the trajectory silently disappears — differently depending on where you have panned to. One sample is also kept on each side of the window, so the curve is drawn to the plot border rather than stopping just short of it.

11.1.2 The pixel budget

The front end asks for roughly two points per horizontal pixel — one for each bucket's high and low — so a 600-pixel tile draws about 1200 points whether the channel holds ten thousand samples or ten million. A second ceiling of 1 500 000 points applies across all the curves of one tile together, so that a page with many curves cannot overwhelm Qt.

That second ceiling is a named function rather than an inline expression for a reason recorded in the source: written as a bare division it acted as a floor at moderate curve counts,

raising the target from 1800 to 10 000 at seventy-five curves and pushing one and a half million points into Qt on every pan.

The visible window is padded by five per cent on each side so the curve stays drawn to the tile's edges while panning. The quoted end-to-end effect on a heavy page is a sixty-fold reduction: 15.9 million samples become 266 thousand drawn points across 225 curves.

11.1.3 Statistics over the same window

The statistics shown in INSPECT use Welford's one-pass method rather than accumulating a sum of squares, because a sum of squares loses precision on a channel with a large offset — altitude in feet, squared, overflows single precision quickly. The reported standard deviation is the sample standard deviation and is zero for a single sample. NaN and infinite samples are skipped. On a non-monotonic x with a window given, every sample is tested individually rather than bracketing a span, for exactly the phase-plane reason above.

11.2 The redraw cache

Most rebuilds do not change a single drawn point. Toggling the grid, restyling one colour, dragging a marker, editing the legend, coming back to a page — all of them arrive at `rebuild()`, and all of them used to throw away every item and re-decimate every curve from full resolution for an answer identical to the one already on screen. Four caches now stand between a rebuild and the work it would otherwise do.

11.2.1 The resample key

The decimation result for a group of curves is tagged with a resample key: the quantised lower edge of the view, the span rounded to twelve significant figures, the point target, and whether the axis is logarithmic. A group whose key is unchanged is skipped entirely.

Both halves of that key are necessary. Quantising only the endpoints hides every zoom whose lower edge scales with its width — the windows $0 \ldots 1$ and $0 \ldots 0.25$ quantise into the same bucket — so zooming in around the origin gained no resolution. Rounding to twelve significant figures is needed because a view range read back from a plot wobbles in the last bits of a double, which would otherwise invalidate the cache on every mouse move.

11.2.2 Adopting the drawn items

Each group records a signature over its curves: the curve's identity, and the address and length of the x and y buffers behind it. A reloaded file, or a column that was evicted by the memory cap and re-read, lands at a different address and so compares unequal. When the signature matches, the existing graphics item is adopted and merely restyled; the group keeps its resample key, so no points are recomputed either.

Comparing addresses is sound only because the previous groups are still alive and still referencing those buffers while the comparison runs — a buffer that is still referenced cannot have been freed and another put at its address. That is why `rebuild()` holds the old groups rather than dropping them first.

One item per pen

Curves that share a pen cannot be told apart on screen, so they are concatenated into a single polyline with one NaN between consecutive runs and drawn with a connect rule that breaks the line there. Twelve hundred runs times two parameters — 2400 graphics items — becomes about twelve. Everything except painting is still per curve: the crosshair

readout, click-to-inspect, marker dots, area segments and the CSV export all need to know which run and which parameter a sample belongs to.

11.2.3 The plot's own settings

New in 2.2.0

Grid, log mode, axis captions and the title are written only when one of them differs from what was last written.

They were re-applied on every rebuild, and most rebuilds change none of them. `setLogMode` is what made that expensive rather than merely redundant: pyqtgraph propagates it to every data item on the plot, which invalidates each curve's cached display data, and then re-enables auto-range — which the tile then has to undo in its own view restoration. A rebuild the two caches above had just arranged to cost nothing threw away the transformed points of every curve on the tile and moved the frame, twice, for a setting nobody had touched.

The title is guarded in the same comparison rather than separately: it is a pure function of the tile's parameters and the theme's foreground colour, so one comparison answers for all of it. A placeholder message writes over the title, so showing one forgets the comparison — without that, a tile that showed *loading…* while a file opened kept the placeholder as its heading.

11.2.4 The drawn annotations

New in 2.2.0

Markers and shaded bands keep their items unless the annotations, the tile's x channel, whether they can be dragged, or the curves have changed.

This is the same idea applied to the overlay pass, and it matters for the same reason the item adoption does. The dot form of a marker searches each curve for the sample where the condition holds, and the band form redraws a stretch of every curve it crosses, so a thousand-run tile paid for both on every rebuild — including the rebuilds that changed neither a curve nor an annotation.

The curves are part of that comparison because the dot sits *on* a curve and the band *is* a stretch of one; they are compared by buffer address, with the same soundness argument as above.

One ordering detail is load-bearing. The overlay list is shared with the 3D data box and its tick values, which the 3D rebuild draws before the overlay pass runs. So the pass returns early on a 3D tile *before* clearing anything, and the 3D rebuild owns the clear on the way in — which is also what takes away two-dimensional markers that have no meaning in a projection.

11.3 ISO grouping

Automatic grouping divides the observed range of the distinct values into evenly spaced intervals. The extremes are found ignoring NaN and infinity; the step is computed in double precision; and the last interval's upper bound is set to the observed maximum exactly, rather than recomputed, so accumulated floating-point error cannot leave the largest sample outside every group. A sweep with a single distinct value yields one group whose bounds are equal, rather than several degenerate empty ones.

11.3.1 Boundaries

Every interval except the last is half-open, $[\min, \max)$; the last is fully closed, $[\min, \max]$. A value that is not a number belongs to no group. Two clamping fallbacks catch a value sitting a hair outside the extreme bounds through rounding — without them the maximum sample of a sweep can vanish — while a value between two non-adjacent manual intervals still belongs to none.

A documented inconsistency

The core header describes group bounds as inclusive at both ends, and the Python-side helpers implement inclusive-at-both-ends with the first claiming group winning. The core's own `iso_group_index` is half-open except for the last interval. The two agree on every value except one sitting exactly on a shared edge, which the core assigns to the later interval and the interface to the earlier one. In practice this is invisible — the edge is a value no sample holds, because the edges are derived from the observed range rather than from the samples — but it is a genuine discrepancy.

Where grouping is configured but the interval list is empty, nothing is filtered. Nothing sorts the interval list after the user has edited it, so overlapping manual bounds are resolved by the first match in the order given.

When a new file is opened, an automatically grouped parameter is rebuilt over the new range and the active flags are carried across by position, so deselections survive. A manually grouped parameter keeps its bounds, and only names that still look automatically generated — empty, or containing the exact separator `" - "` — are refreshed, so hand-typed labels are preserved.

11.3.2 How values are written

ISO values are formatted to two decimals with trailing zeros trimmed, so `0.750000` becomes `0.75` and `3.000000` becomes `3`. Values that round to zero, and values of a million or more, are written as a power of ten with a compacted exponent: `1.20e+06` becomes `1.2e6`. A negative zero is normalised to `0`.

The small-end boundary is decided by rounding rather than by a threshold, and the reasoning is worth knowing because it affects the labels you see. A value arrives as a single-precision float, so the literal `0.01` is stored as `0.00999999978`; comparing that against 10^{-2} would send `0.01` itself to scientific notation — the one value a Mach or tolerance sweep is most likely to contain. Asking instead whether the rounded form is still non-zero puts the boundary where it belongs. The large end genuinely is a threshold, and it is about label length: past a million the integer part alone is longer than the value written as a power of ten.

11.4 Legend order, and why it stopped shuffling

A legend row is ranked by an intrinsic property of what it describes, not by the order the curves happened to be walked in. In ISO mode a grouped label ranks by its position in the grouping and an ungrouped label by the value itself; the lowest rank wins when two runs share a label. Groups are then sorted by a tuple: ISO rank, parameter order, file, run when colouring by ISO; parameter order, style-ISO rank, file, run when colouring by parameter; file, run, style-ISO rank, parameter order when colouring by simulation.

Before this, the order was the order in which each group was first seen while walking the selection, so unticking a single run could reshuffle 0–10, 10–15, 15–20 into 15–20, 0–10, 10–15. Nothing about the data had changed; only the walk had.

The style-ISO rank joined the tuple in 2.2.0, with the legend text that made it necessary: a tile coloured by parameter and dashed by ISO now emits one row per ISO value (§5.7.4), and without an intrinsic rank for those rows they came out in the order the runs were walked — the same reshuffling this section exists to have ranked away.

11.5 Logarithmic axes

pyqtgraph's logarithmic mode does not scale the axis: it plots the base-10 logarithm of the samples on a linear axis and relabels the ticks. Everything crossing the view boundary is therefore in log units, while a tile's stored minimum and maximum are, and must remain, in data units. A dedicated module owns that conversion, and it exists because of a specific defect: ticking *Log Y* on a channel spanning 1 to 1000 framed the view at log-space 1 to 1000 — data 10^1 to 10^{1000} — while the curve sat at log values 0 to 3. The tile looked empty, double-clicking recomputed the same answer, and those mixed numbers then propagated as a variable-wide limit onto tiles that were not in logarithmic mode at all.

Converting a value to view space returns nothing at all when the value is non-positive, so the caller must decide what to do rather than being handed a silently wrong number. When the low end of a requested range has no logarithm, the frame is taken as three decades below the high end rather than refusing to frame at all. At draw time non-positive samples are blanked to NaN so the drawable part of the curve still shows.

11.6 The three-dimensional projection

The projection is orthographic, and deliberately so: these plots exist to have values read off them, and under perspective the same interval covers different distances depending on where it sits in the frame.

Each of the three channels is normalised independently onto $[-0.5, 0.5]$, so channels with unrelated units stay readable together; a degenerate or non-finite range collapses to zero, which puts a channel that never moves in the middle of the cube. The path is then rotated about the vertical axis by the azimuth, tilted by the elevation, and depth is dropped:

$$r_x = x\cos A - y\sin A, \qquad r_y = x\sin A + y\cos A,$$
$$\text{screen}_x = r_x, \qquad \text{screen}_y = z\cos E - r_y\sin E,$$

with depth $z\sin E + r_y\cos E$ retained only for ordering what is drawn in front of what.

A projected path cannot be min/max decimated, because that needs a monotonic x and a trajectory through space is monotonic in none of the three axes. Plain striding is the honest option here, and it is what is used, against a budget derived from the tile width as in the two-dimensional case.

Rotating does not rebuild the tile. Only the grid, the triad and the projection are redone; the channel reads, the bounds and the thinning are left alone, which is what makes dragging to rotate smooth rather than a sequence of full reloads.

The back-wall grid picks, for each axis, the face lying behind the data from the current viewpoint, so the grid never draws over the trajectory and swaps faces as you turn it. Its tick values are chosen in steps of 1, 2, 2.5 or 5 times a power of ten, counted rather than accumulated so they cannot drift outside the box, and the whole grid is drawn as a single graphics item. The orientation triad is parented to the view box rather than to the data, so panning and zooming never reach it and it keeps a constant size; its axes follow the universal convention of red, green and blue for x, y and z, and are painted back to front by depth.

Chapter 12

The C ABI

Everything above the core is written without a C++ compiler, and the reason is this interface: sixty exported functions taking only C types and opaque handles. It is declared in `core/include/aoe/aoe_c_api.h`.

Nothing in it changed across the 2.1 releases. `aoe_version()` returns `"2.0.0"`, which is the core's version and not the application's (2.2.0); `-version` prints both.

12.1 Handles, versioning and errors

```
typedef struct aoe_session aoe_session;   /* opaque; the API's whole context */
typedef struct aoe_pin     aoe_pin;       /* opaque; keeps a block alive */
```

A pin holds the sample block itself, not a path back to the session, so releasing one after the session has been destroyed is well defined. That matters because on the Python side pins are released by the garbage collector, in its own order and at its own time.

The only version marker is `aoe_version()`, which returns a string. There is no numeric ABI-version symbol and no version macro in the header.

Errors are reported per session. `aoe_last_error()` returns the message from the most recent failure, or the empty string. It is cleared at the start of every mutating call but not by read-only calls, so it means the last failure since the last mutating call rather than strictly the last call. Failure is signalled by a sentinel that depends on the return type: -1 for a function returning an index, 0 for a boolean or a count, an empty string — never a null pointer — for a string, a null pointer for a float array, and zero for a size. Index arguments out of range are errors rather than crashes, and a null session pointer is handled without being dereferenced.

Exceptions never cross the boundary

Every session-taking entry point funnels through a guard that catches `std::exception`, putting its message into the session's error slot, and any other exception as *unknown error*. Unwinding out of a C function is undefined behaviour, and with `ctypes` on the other side it would take the interpreter down.

12.2 Thread safety

The session carries a reader/writer lock — an `SRWLOCK` on Windows, a `pthread_rwlock_t` elsewhere. Read-only entry points take it shared, so many concurrent readers are allowed; mutating ones take it exclusively and clear the error string. The mutating set is: adding, removing, clearing and reloading files; setting a file or run display name; setting and removing aliases; setting and removing computed parameters; building and discarding a cache; and the two calls that write into the session's scratch string, `aoe_resolve` and `aoe_iso_format`, which are logically reads but take the write lock because of that scratch.

The pure-mathematics functions — decimation, the series helpers, nearest-index, and the ISO grouping arithmetic — take no session at all and are fully re-entrant on caller-owned buffers. Below the ABI, each run has its own mutex guarding its column vector and its map

of computed results, which is what lets the thread pool fill different runs concurrently; an attached cache file is immutable once open and needs no locking.

One concurrency caveat in the source

`aoe_cache_path` takes only the shared lock yet writes the session's scratch string. Two concurrent readers can therefore each invalidate the other's returned pointer. Copy returned strings immediately — which `ctypes` does automatically when the result type is declared as a C string, so the Python layer is not exposed to this.

12.3 Function reference

In the table below, *lock* is the lock the call takes; *session* in a note means memory owned by the session and valid until the next call that changes the thing it came from; *core buffer* means a zero-copy alias of a column buffer.

Function	Lock	Returns, and what to know
Library		
`aoe_version()`	—	`const char*`, a static literal, always valid. The *core*'s version.
`aoe_worker_count()`	—	`int`.
Session		
`aoe_session_create()`	—	`aoe_session*`; caller owns. `NULL` on failure.
`aoe_session_destroy(s)`	—	consumes the handle; `NULL` safe.
`aoe_last_error(s)`	—	session; valid until the next call. `""` on failure.
Files		
`aoe_add_file(s, path)`	write	`int` index. `-1` and the error set on failure.
`aoe_remove_file(s, file)`	write	invalidates every pointer from that file.
`aoe_clear_files(s)`	write	invalidates all file-derived pointers; aliases and computed definitions survive.
`aoe_file_count(s)`	read	`int`.
`aoe_file_name(s, file)`	read	session. The display name. `""` on failure.
`aoe_file_path(s, file)`	read	session. `""` on failure.
`aoe_stale_files(s, out, max)`	read	`int` count; writes $\leq$ `max` into `out`. `out=NULL` just counts. Returns the full count.
`aoe_reload_file(s, file)`	write	`1/0`; drops cached samples and computed results for that file and re-reads the index. Run keys survive it.
`aoe_set_file_name(s, file, name)`	write	display only; empty or `NULL` ignored. Run keys are not rebuilt from it.
`aoe_set_sim_name(s, file, sim, name)`	write	display only; `unique_key` untouched, so colours survive.
Runs		
`aoe_sim_count(s, file)`	read	`int`.
`aoe_sim_id(s, file, sim)`	read	session; what the file calls it.
`aoe_sim_name(s, file, sim)`	read	session; falls back to the id when the display name is empty.
`aoe_sim_key(s, file, sim)`	read	session; the identity styles and workspaces are built on.
Channels and names		
`aoe_header_count(s, file)`	read	`int`.
`aoe_header(s, file, i)`	read	session.
`aoe_header_unit(s, file, i)`	read	session; parallel to `aoe_header`; never `NULL`.

Function	Lock	Returns, and what to know
`aoe_param_unit(s, name)`	read	session; searches every open file, follows aliases; `""` for computed.
`aoe_param_count(s)`	read	`int`; union of headers, computed and aliases, sorted.
`aoe_param(s, i)`	read	session.
`aoe_set_alias(s, alias, target)`	write	no-op if either is empty or they are equal.
`aoe_remove_alias(s, alias)`	write	—
`aoe_resolve(s, name)`	write	session *scratch* — invalidated by the next scratch-writing call.
Computed parameters		
`aoe_set_computed(s, name, expr)`	write	`1/0`; clears cached computed results in every file. `0` and the error set on failure.
`aoe_remove_computed(s, name)`	write	`int` count; removes transitively, names readable through the next entry.
`aoe_removed_name(s, i)`	read	session; valid until the next `aoe_remove_computed`.
`aoe_is_computed(s, name)`	read	`1/0`; resolves aliases first.
`aoe_computed_source(s, name)`	read	session; the stored expression text.
`aoe_validate_formula(s, expr)`	read	`1/0`; parses and checks variables, evaluates nothing.
Samples		
`aoe_channel(s, file, sim, name, *count)`	read	core buffer, zero-copy. Valid only until the next eviction — anything that keeps it must pin. `NULL` on failure.
`aoe_channel_pinned(s, file, sim, name, *count, **pin)`	read	as above, and the caller owns `*pin`: the samples stay alive regardless of the memory cap until released.
`aoe_pin_release(pin)`	—	frees the pin; `NULL` safe.
`aoe_pin_sorted(pin)`	—	`1` when the samples are non-decreasing. Precomputed at parse time — free.
`aoe_pin_bounds(pin, *min, *max)`	—	precomputed extent; what autoscaling needs without rescanning a million samples per curve per replot.
`aoe_pin_count(pin)`	—	`size_t`.
`aoe_preload(s, file, sims, n, names, n)`	read	loads every physical column the names need in one parallel pass; `sims=NULL` means all.
Pure mathematics — no session, fully re-entrant		
`aoe_decimate(x, y, count, x_min, x_max, max_points, out_x, out_y)`	—	`size_t` written; caller owns all buffers, `out` needs $\geq 2\times$`max_points`. Uses the whole series when `!(x_min < x_max)`.
`aoe_decimate_ex(..., x_sorted, ...)`	—	as above plus `x_sorted`: `1` sorted, `0` not, `-1` detect. Pass `0` for phase planes.
`aoe_series_sorted(values, count)`	—	`1/0`.
`aoe_series_bounds(values, count, *min, *max)`	—	`1/0`.
`aoe_nearest_index(x, count, target)`	—	`size_t`; returns `0` for an empty series, indistinguishable from a genuine hit at index 0.
`aoe_series_stats(x, y, count, x_min, x_max, out)`	—	writes 7 doubles: min, max, mean, stddev, first, last, count. `x=NULL` or an empty window means the whole series.
`aoe_series_stats_ex(..., x_sorted, out)`	—	same `x_sorted` contract as `aoe_decimate_ex`.
Memory		
`aoe_resident_bytes(s)`	read	`size_t` of sample data cached across every open file.

Function	Lock	Returns, and what to know
`aoe_trim_memory(s, keep_bytes)`	read	frees LRU columns until at or below `keep_bytes`; returns the total afterwards. Always safe — evicted data is re-read on demand.
Sidecar		
`aoe_cache_enabled()`	—	`0` when `AOE_CACHE` switches caching off.
`aoe_cache_active(s, file)`	read	`1` when a valid sidecar is attached and serving reads.
`aoe_cache_path(s, file)`	read	session *scratch* — see the caveat above.
`aoe_build_cache(s, file)`	write	costs a full parse — call off the UI thread. Memory bounded to one parameter across every run.
`aoe_discard_cache(s, file)`	write	detaches and deletes every candidate sidecar; `1` when none remains.
ISO		
`aoe_iso_values(s, file, name, out, max)`	read	`int` count; writes $\leq$ `max`, returns the full count; NaN where absent.
`aoe_iso_distinct(s, name, out, max)`	read	ascending, NaN-free, de-duplicated across every open file; `out=NULL` to learn the count first.
`aoe_iso_auto_group(values, count, n, out_bounds, max)`	—	`out_bounds` receives 2 floats per group.
`aoe_iso_group_index(value, bounds, n)`	—	`int`; `-1` on failure.
`aoe_iso_format(s, value)`	write	session *scratch*; valid until the next call on this session.

Three of these — `aoe_stale_files`, `aoe_iso_values` and `aoe_iso_distinct` — return the full count rather than the number actually written, so a caller can size a buffer with one call and fill it with a second.

Two functions worth singling out

`aoe_channel` hands back a zero-copy pointer into a column buffer which is valid only until the next eviction; anything that intends to keep the samples must use `aoe_channel_pinned` and release the pin when done. And a pin answers two questions for free, because both were computed at parse time: whether the samples are non-decreasing — the precondition of any binary search over x — and what their extent is, which is what autoscaling needs without rescanning a million samples per curve per replot.

12.4 Building against it

The core is built as a shared library with optimisation on and no dependency beyond the C++ standard library and the platform's mapping and threading calls. The export macro resolves to `__declspec(dllexport)` on Windows and to a default-visibility attribute elsewhere when building shared, and to nothing when building statically. The artefact is `aoecore.dll`, `libaoecore.dylib` or `libaoecore.so` according to platform. Because the header declares only C types, any language with a C foreign-function interface can drive it; the Python binding in this repository is one client rather than a privileged one.

Chapter 13

The Python scripting API

Everything the interface can read, a script can read, through the same core and with the same performance. Importing the package is deliberately cheap: the exports are lazy, so importing `aoeviewer` pulls in neither NumPy nor the core library, which is what lets `-version`, `-help` and `-selftest` work on a machine where the core has not been built.

```
from aoeviewer import Session, FileHandle, SimulationHandle, IsoGroup, CoreError
```

13.1 The one rule

Arrays returned by `channel()` are read-only *views* of C++ memory, not copies. They are fast because of that. They carry a pin object as their NumPy base, which keeps the underlying block alive for as long as any view exists — so the memory cap can never free a buffer a script is still reading from — but they stop being meaningful when the owning file is reloaded or removed. Copy explicitly if you need to outlive that.

Asking twice for the same channel gives back the same buffer at the same address. Two caches in the plot tile are built on exactly that (§11.2), so it is a property of the API rather than an accident of it.

13.2 Session

A `Session` is created with no arguments, raises `CoreError` if the core cannot be initialised, and is a context manager. Its `last_error` property exposes the core's message.

An absent channel yields an empty array rather than an error, and callers should treat that as nothing to plot: different files in one study legitimately hold different channels. In the stats dictionary, `ranged` is true only when the x window was actually applied — a run whose x channel is shorter than its y channel cannot be windowed, and the figures are then whole-channel.

Method or property	Meaning
`add_file(path) -> FileHandle`	opens a result file; raises `CoreError` on failure
`remove_file(index)`, `clear()`	unload one file, or all of them
`file_count`, `files`, `file(index)`	the open files
`stale_files() -> List[int]`	indices of files changed on disk since they were read
`parameters -> List[str]`	every name: headers, computed channels and aliases
`plottable_parameters -> List[str]`	the same list, but empty while no file is open. Use it wherever a channel is being *chosen* on the user's behalf
`set_alias(alias, target)`, `remove_alias(alias)`, `resolve(name)`	aliases
`unit(name)`, `label(name)`	the unit, and `"ALTITUDE [ft]"` — one place decides how a channel is labelled

Method or property	Meaning
`set_computed(name, expr)`	defines a computed channel; raises `CoreError` carrying the parse message
`remove_computed(name) -> List[str]`	the name plus every dependant removed
`is_computed(name)`, `computed_source(name)`	interrogate a definition
`validate_formula(expr) -> (ok, message)`	parses and checks names, evaluates nothing
`channel(file, sim, name) -> ndarray`	read-only zero-copy view; an empty array when the channel is absent
`preload(file, sims, names)`	turns N lazy single-column loads into one batched, multi-threaded read; an empty `sims` means all
`decimate(x, y, max_points, x_range=None)`	min/max bucketing, at most 2×`max_points` points
`Session.bounds(values)`	static; extent ignoring NaN and infinity
`Session.nearest_index(x, target)`	static
`Session.stats(y, x=None, x_range=None)`	static; a dict of min, max, mean, std, first, last, count, ranged
`resident_bytes`, `trim_memory(keep_bytes)`	the cache, and LRU eviction that is always safe because columns are re-read
`cache_enabled`, `cache_active(file)`, `cache_path(file)`	sidecar state
`build_cache(file)`, `discard_cache(file)`	write or delete a sidecar; building costs a full parse
`iso_values(file, name)`	one value per run, NaN where absent
`iso_distinct(name)`	sorted distinct values across every open file
`iso_auto_group(values, n)`, `iso_group_index(value, groups)`	interval arithmetic
`format_value(value)`	the same formatting the lists show

13.3 Handles

A `FileHandle` carries its index and exposes `name`, `path`, `headers`, `units` — parallel to the headers, with empty strings where the dialect carries none, so the two can always be zipped — `simulation_count` and `simulations`. It can `rename(name)`, which changes the display name only, and `reload()`, which re-reads the file from disk and leaves every run's key as it was. The simulation list is cached on the session, because building one handle costs three ABI calls and a thousand-run file would otherwise cost three thousand on every access.

A `SimulationHandle` carries `file_index`, `index`, `sim_id` — what the file calls it — `name`, which is what the user sees, and `key`, the identity styles attach to, which never changes. It can `rename(name)` and `channel(name)`.

An `IsoGroup` is a named interval: `name`, `low`, `high`, `active`, and `contains(value)`.

13.4 A worked script

```
import numpy as np
from aoeviewer import Session, CoreError

with Session() as session:
    handle = session.add_file("study/sweep.aoe")

    # A derived channel, checked before it is relied on.
    ok, message = session.validate_formula("deriv(THETA, TIME)")
    if not ok:
        raise SystemExit(message)
```

```
session.set_computed("PITCH_RATE", "deriv(THETA, TIME)")

# One batched, multi-threaded read for everything we are about to touch.
session.preload(handle.index, [], ["TIME", "ALPHA", "PITCH_RATE"])

# Bucket the runs by their Mach number.
machs = session.iso_distinct("MACH")
groups = session.iso_auto_group(machs, 3)

for sim in handle.simulations:
    value = float(session.iso_values(handle.index, "MACH")[sim.index])
    bucket = session.iso_group_index(value, groups)

    t = sim.channel("TIME")           # read-only view, zero copy
    q = sim.channel("PITCH_RATE")
    stats = Session.stats(q, t, (5.0, 25.0))   # over 5 s .. 25 s only
    if stats is None:
        continue
    print("{0} MACH={1} group={2} peak q={3:.4g} ranged={4}".format(
        sim.sim_id, session.format_value(value),
        groups[bucket].name if bucket >= 0 else "-",
        stats["max"], stats["ranged"]))

# What a tile would actually draw for a 900 px wide plot.
t = handle.simulations[0].channel("TIME")
a = handle.simulations[0].channel("ALPHA")
dx, dy = session.decimate(t, a, max_points=1800, x_range=(0.0, 60.0))

print(session.label("ALPHA"), dx.size, "points drawn of", t.size)
print("cache", session.resident_bytes // (1024 * 1024), "MB")
session.trim_memory(256 * 1024 * 1024)
```

Two habits are worth adopting. Call `preload` once for everything a loop will touch, rather than letting each `channel()` trigger its own load — the batched read uses the whole thread pool and one mapping. And for a file of any size, call `build_cache()` once; the graphical application does this automatically above 8 MB, but a script gets no sidecar unless it asks.

Useful extras in `_core`

Beyond the façade, `aoeviewer._core` exposes `library_path()`, the `Pin` type with its `sorted` flag and `bounds()`, `pin_of(array)` to recover the pin behind a view, the array adapters, and the module-level `VERSION` and `WORKER_COUNT`.

Chapter 14

Performance, limits and troubleshooting

14.1 Where the time goes

Three costs dominate, and each has its own mitigation. Parsing text into floats is paid once per column per run, in parallel, and is avoided entirely on the second and subsequent opens by the sidecar. Deciding what to draw is paid on every pan and zoom, and is bounded by the pixel budget rather than by the size of the data. Creating graphics items is paid when a tile's shape changes, and is minimised by concatenating curves that share a pen into one polyline and by adopting existing items whenever the data behind them is unchanged.

A fourth cost, which is neither of those, is deciding to do work that was already done. Chapter 11 lists the four caches that stand between a rebuild and the work it would otherwise repeat, and the panels carry the same idea: each is rebuilt only when its *rows* change, and a refresh that changes only which boxes are ticked writes the boxes in place.

Limit	Value and meaning
Tiles per page	25, a 5×5 grid. Every page always holds 25 tile objects; shrinking a grid hides them rather than destroying them
Points per pixel	2 — one for each bucket's high and low
Points per tile	1 500 000 across all its curves, as a second ceiling
Legend rows	60, after which the remainder is summarised as *…and N more (legend caps at 60 rows)*
ISO value rows	400 per parameter in the tree; the ticks for the rest still apply, and a parameter's checkbox still acts on all of them
ISO values named in a tooltip	8, then *+N more*
DATA auto-expand	200 runs. A larger file opens closed; every run is still there, and the choice you make is remembered
Sample cache	2048 MB by default, floored at 64 MB, trimmed to 80 % of the cap on overflow
Sidecar threshold	8 MB; below it, parsing is quick enough that a sidecar would save nothing measurable
Formula dependency depth	32, beyond which the definition is reported as cyclic
Redraw coalescing	25 ms, so a drag produces one resample at its end rather than one per pixel
Caption commit delay	400 ms of idle typing
PARAMS filter delay	400 ms of idle typing
Interface size	70 % to 160 % of the base type scale, in steps of 10
Shutdown wait	30 s for background work to finish

The file-change poll that appeared in this table up to 2.1.0 is gone; see §4.5.

14.2 Getting the best out of it

Open each large file once and let the sidecar be written; the cost is paid on the first open and never again, and the status message says when it is happening. Prefer fewer, larger pages over

many sparsely filled ones, since a fresh 5×5 page costs most of a second to build its widgets while switching between pages of the same shape merely redraws. Where a tile shows many runs of the same channel, turn the legend's *File* and *Simulation* parts off so identical rows merge — sixty rows of legend cost more to lay out than the curves do. And if the cache figure in the status bar is climbing towards the cap on a machine with plenty of memory, raise the cap with `-memory-limit`: eviction is safe, but a column that is evicted and re-read is a column parsed twice.

14.3 Troubleshooting

14.3.1 The program will not start

Run `python -m aoeviewer -selftest`. It checks each dependency separately and then the core, so the first `FAIL` names the problem. If the core is the failure, the error lists every directory that was searched; build it, or point `AOEVIEWER_CORE` at the library. On Windows, a load failure that looks like a missing dependency suggests running `objdump -p` against the DLL to see what it wants. Whatever happens, the traceback is in `aoeviewer.log`, whose location is reported by `-version`.

14.3.2 A file opens but shows nothing

Opening succeeds as long as the file has a usable `*PARAMETRES` block, so a file with headers and no `*TABLEAU` opens with zero runs — the DATA tab will show the file with nothing beneath it. If runs are present but no curve appears, check in order: that runs are ticked in DATA — on a file of more than 200 runs the node opens closed, so click it open to see them; that no ISO filter is holding them back, which the status bar states explicitly; and that the tile has both an x channel and at least one y channel, which the tile's own title says in words.

14.3.3 The curves look wrong on a phase plane

A plot whose x channel is not monotonic — Mach against altitude over a climb and descent, for instance — needs the unsorted path through the decimator. The application always requests detection, so this is handled; but a script calling `decimate()` on such data should be aware that the sorted fast path would bracket only the first crossing. There is a related caveat in `nearest_index`: its fast path is chosen by comparing the first and last samples, which is a heuristic rather than a sortedness test, so a phase-plane channel that happens to end above where it started can return a wrong index.

14.3.4 A value I expected is missing or reads as nan

An unreadable token becomes not-a-number rather than zero, by design, so a gap in the file is a gap in the curve. Division by zero and the out-of-domain cases of `sqrt`, `asin`, `acos` and the logarithms also yield NaN rather than an infinity, because an infinity would destroy the plot's y range. In INSPECT, NaN prints as a dash.

14.3.5 A channel disappeared after I removed a computed parameter

Removing a computed parameter removes everything defined in terms of it, and the status message names what went. Re-create the dependency first, then the dependants.

14.3.6 Colours changed when I opened another file

They should not: a colour is allocated on first use and kept for the session, keyed on an identity that survives renaming — including the renaming of the *file*, and including a reload. If they did change, something called *Re-assign palette*, which deliberately forgets the assignments so that the next redraw allocates afresh.

14.3.7 I reopened a workspace and the plot is empty

Both halves of what gets drawn are restored, so start by reading the status bar. If it says runs are held back by the ISO filters, open ISO: a filter whose node reads *no run satisfies it* is doing exactly what it was asked to and the data no longer contains anything in that band, so widen or untick it. A filter reading *not in the loaded files* is filtering nothing and is not the cause, and one reading *paused* is not applying at all.

If the status bar says no runs are plotted at all, the DATA tab has nothing ticked — the workspace records which runs were chosen by index, so opening it against a file with fewer runs leaves the missing ones simply absent.

The dialog shown at load time, *Workspace loaded with differences*, lists everything the workspace asked for that this data could not give: unopenable files, formulas that could not be defined and why, aliases whose channel is gone, and both ISO cases. If it did not appear, everything in the workspace resolved.

14.3.8 I swapped one study for another and the axes moved

They should not, since 2.2.0 — see §6.4. If a tile's x axis did move, the status bar says so by name (*page 2, tile 3: x axis VTAS -> TIME*), and it means the new files genuinely do not carry the channel that tile was plotting against.

Appendix A

Keyboard shortcuts and gestures

Keys or gesture	Action
Ctrl+L	Load workspace
Ctrl+S	Save workspace (overwrites the current file)
Ctrl+Shift+S	Save workspace as — asks, then continues in the new file
Ctrl+0	Auto-fit every tile
Ctrl+- / Ctrl+=	Interface size: smaller, larger
Light / Dark in the toolbar	Switch the theme (no shortcut)
Ctrl+1 … Ctrl+4	Mouse mode: Select, Inspect, Pan, Zoom
Click a tile	make it the active tile
Double-click a tile	auto-fit that tile alone
Double-click a row in DATA	rename that file or run
Double-click a row in COMPUTE	load that definition for editing
Click a file row's arrow in DATA	open or close its runs; the choice is remembered
Right-click in DATA	plot all or no runs of a file; rename; reload from disk; copy the full path
Right-click in PARAMS	create an alias; use as x axis; copy the name
Right-click in ISO	group, ungroup, select all or none, use this filter, remove the filter
Drag in Inspect	measure a slope (shorter than 6 px counts as a click)
Drag a marker or band edge in Select	move it
Drag the legend	place it freely; the corner becomes *custom*
Drag a caption in Select	move it within its tile
Drag on a 3D tile in Pan	rotate
Middle-drag or Shift+drag on a 3D tile	translate
Right-drag or Ctrl+drag on a 3D tile	zoom
Wheel on a 3D tile in Zoom	zoom

Appendix B

Environment variables

Variable	Effect
`AOEVIEWER_CORE`	Path to the core library, or to a directory containing it. Searched first, before every built-in location
`AOEVIEWER_LOG_DIR`	Directory for `aoeviewer.log`
`AOE_CACHE`	Set to `0`, `false`, `no` or `off` to disable sidecar caching entirely. Read once per process
`AOE_CACHE_DIR`	Overrides the per-user sidecar directory

Appendix C

The workspace file

A workspace is UTF-8 JSON with the extension `.aoews`, written with two-space indentation. The schema is at version 3.

```
{
  "version": 3,
  "app_version": "2.2.0",
  "files":    ["/abs/path/run_a.aoe"],
  "computed": {"LOAD_FACTOR": "NZ * 9.80665"},
  "aliases":  {"Angle of attack": "ALPHA"},
  "file_names": {"/abs/path/run_a.aoe": "Nominal climb"},
  "sim_names":  {"/abs/path/run_a.aoe":
                   {"run_a.aoe::SIM_001::0": "Cold day"}},
  "pages": [
    {"name": "Page 1", "rows": 2, "cols": 2, "tiles": [ ... ]}
  ],
  "active_page": 0,
  "selected_sims": [[0, 0], [0, 1]],
  "styles": {
    "colors":  {"param::ALPHA": "#e8232a"},
    "dashes":  {"file::/abs/path/run_a.aoe": "dash"},
    "symbols": {"param::ALPHA": "o"},
    "widths":  {"param::ALPHA": 2.0},
    "line_width": 1.6,
    "symbol_size": 6.0
  },
  "iso_states": [
    {"param": "INITIAL_MASS", "active": true, "grouped": true,
     "group_count": 3, "value_enabled": [],
     "groups": [["57236 - 64495", 57236.3, 64495.9, true],
                ["64495 - 71754", 64495.9, 71753.9, false]]}
  ],
  "markers": [
    {"x_param": "TIME", "position": 5.0, "visible": true,
     "color": "#ff3333", "dot_size": 9.0}
  ],
  "areas": [
    {"x_param": "TIME", "x_min": 10.0, "x_max": 20.0,
     "color": "#3380ff", "alpha": 0.2, "visible": true}
  ],
  "global_x_limits": {"TIME": [0.0, 60.0]},
  "global_y_limits": {},
  "dark_mode": true,
  "ui_scale": 1.0,
  "mouse_mode": 0
}
```

Each entry of `"tiles"` carries the complete tile state listed in Chapter 6, including its captions and both encodings. Only the visible tiles of a page are written; loading pads the list back up to twenty-five.

`ui_scale` is absent from every workspace written before 2.2.0, and from one written by hand; 1.0 is the size those were laid out at, and a value outside the range is clamped rather than refused so that a workspace from a future version with a wider range still opens.

`file_names` and `sim_names` are optional and written only when something was renamed (§7.3). `app_version` records which build wrote the file and is informational only.

`value_enabled` is a list of pairs rather than an object because JSON object keys are strings: round-tripping `0.75` through an object hands back `"0.75"`, which would silently stop matching the value it is about. Non-finite keys are dropped, so the file stays portable JSON.

The loader sets only the attributes it recognises and ignores the rest, which is how workspaces written when markers and bands still carried a caption field continue to load, how the withdrawn `legend_show_style` field is tolerated, and how a 2.0.0 workspace loads into the two-encoding model with *Style by* at *None*. The `"version"` key is written but nothing branches on it.

Not saved: the active tile index, the tile clipboard, the memory limit, the window geometry, and the hidden tiles of a shrunken grid.

Appendix D

Defaults at a glance

Setting	Where	Default
Window size	startup	1500 × 920
Theme	rail foot	dark
Interface size	toolbar	100 % (range 70–160 %, steps of 10)
Mouse mode	toolbar	Select
Grid	page bar	1 × 1
Legend, Grid	STYLE	on
Log Y, Points	STYLE	off
Colour by	STYLE	**Parameter**
Style by	STYLE	None
First three curve colours	STYLE	red, blue, dark green
Line width	STYLE	1.6 (range 0.1–10.0)
Marker size	STYLE	6.0 (range 1.0–20.0)
Legend corner	STYLE	top-left
Legend parts	STYLE	Parameter only
Axis locks	SCALE	off
ISO groups	ISO	3
Azimuth, tilt	3D	45°, 25°
3D triad, 3D grid	3D	on
3D zoom half-width	3D	0.95
Band opacity	AREA	0.20 (range 0.02–1.0)
Band colour	AREA	`#3380ff`
Marker dot size	MARKERS	9.0 (range 2.0–30.0)
Marker colour	MARKERS	`#ff3333`
Caption size	TEXT	10.0 pt (range 4–72)
Caption position	TEXT	0.05, 0.05
Memory limit	command line	2048 MB (floor 64 MB)

Colour by defaulted to *Simulation* up to 2.1.0. Existing workspaces are unaffected — every tile records its own mode.

Appendix E

Known limitations

The following are real shortcomings of this version, gathered here so they are easy to find.

An HDF5 file is read whole, and needs h5py. The samples are handed to the core rather than parsed by it, so there is no lazy per-column loading and no `.aoec` sidecar for such a file; see section 8.8. The layout is inferred from the tree, which is evidence rather than proof — a file following none of the known conventions opens with its runs and channels arranged wrongly or does not open at all, and the log says which convention was chosen.

Entries that appeared here in earlier editions and have since been fixed are not repeated: ISO filters and aliases missing from the workspace, the undocumented `ln`, an ISO filter on an absent parameter hiding every run, display names lost on save, and a run's identity moving when its file was renamed and reloaded.

The workspace version is not interpreted. A `"version"` of 3 is written and nothing reads it; there is no version-branching logic, so a future format change has no mechanism to fall back on. What stands in for it is the loader's tolerance of unknown keys and of missing ones.

Group boundaries differ by a hair between the two layers. The core treats every interval except the last as half-open; the interface helpers treat all of them as inclusive at both ends with the first claiming group winning. The two disagree only for a value sitting exactly on a shared edge.

`nearest_index` guesses at sortedness. Its fast path is chosen by comparing the first and last samples rather than by testing monotonicity, so a phase-plane channel that ends above where it started can return a wrong index.

`aoe_cache_path` writes shared state under a read lock. Two concurrent readers can invalidate each other's returned pointer. The Python layer is not exposed to it because `ctypes` copies the string immediately.

There is no cancellation. A running background task cannot be interrupted; the interface is disabled until it completes. What exists instead is coalescing — a newer queued request replaces an older one.

Markers and areas are not drawn on three-dimensional tiles. This is a deliberate restriction rather than an oversight, but it is a restriction.

Classic Mac line endings are not supported. Lines are split on the line feed, with carriage returns trimmed, so a file using lone carriage returns reads as a single line.

The DATA tree holds one widget item per run. A twelve-hundred-run file is twelve hundred of them. The cost is paid once per change to the set of open files rather than per interaction, and not auto-expanding a large file keeps Qt from laying them out — but the items are built either way, and a model-backed view is what would avoid that.

Decimation scans the whole visible window. That is what makes the min/max guarantee hold, but it means a fully zoomed-out view of a large study scans every sample of every drawn curve on each resample. A multi-resolution min/max pyramid stored in the sidecar would make that case cost what the screen can show instead; it would also change the sidecar format.