Activate the Remote Desktop Services license server Windows 2019


Install the RD licensing role

1. Sign into the server you want to use as the license server using an administrator

2. In Server Manager, select Manage > Add Roles and Features.




On the Select installation type page, select Role-based or feature-based installation.





- 4. Specify the server on which you'll install the licensing role.
- 5. On the **Server Roles** page, check the box for **Remote Desktop Services**, then select **Next** until you see the **Remote Desktop Services** page.

6. Select the roles you want to install. Make sure you include the **Remote Desktop Licensing** role.



- 7. In the Add Roles and Features Wizard dialog box, select Add Features.
- 8. Select **Next** until you see the **Confirmation** page, then select **Install**.







Activate the license server


- In Server Manager, select Remote Desktop Services > Servers. Right-click the server where you installed the Remote Desktop Licensing role and select RD Licensing Manager.
- 2. In the **RD Licensing Manager**, select the server, and then select **Action** > **Activate Server**.

- 3. Accept the remaining default values in the Activate Server Wizard until you see the **Company information** page, then enter your company information.
- 4. Accept the defaults for the remaining pages until the final page. Clear **Start Install Licenses Wizard now**, and then select **Finish**.
- 5. Select **Action** > **Review Configuration** > **Add to Group** > **OK** and enter credentials for a user in the AAD DC Administrators group, and register as SCP. This step might not work if you are using Microsoft Entra Domain Services, but you can ignore any warnings or errors.




Click on Next → Choose SPLA (service Provider License Agreement)






Enter your agreement number \rightarrow specify how many number of license you need and choose per userCALS and apply

Finally you will see the below data




Once Done you need to add few permissions to allow the users simultaneously


Run →gpedit.msc for group policy editing




Click on Administrative Template → Windows Component → Remote Desktop Services




Click on Remote Desktop Services → Remote Desktop Session Host



Click on Connections




Click on number of connections and enable like below → apply →ok




Then click on Restrict Remote Desktop Services users to a single Remote Desktop

Connections			
Restrict Remote Desktop Services	Setting	State	Comment
users to a single Remote Desktop Services session	Automatic reconnection	Not configured	No
	Allow users to connect remotely by using Remote Desktop S	Not configured	No
Edit policy setting	Deny logoff of an administrator logged in to the console ses	Not configured	No
	Configure keep-alive connection interval	Not configured	No
Requirements: At least Windows Server 2003	Limit number of connections	Enabled	No
	Suspend user sign-in to complete app registration	Not configured	No
Description:	Set rules for remote control of Remote Desktop Services use	Not configured	No
This policy setting allows you to restrict users to a single Remote Desktop Services session.	Select network detection on the server	Not configured	No
	Select RDP transport protocols	Not configured	No
	Restrict Remote Desktop Services users to a single Remote D	Disabled	No
If you enable this policy setting, users	Allow remote start of unlisted programs	Not configured	No
who log on remotely by using Remote Desktop Services will be restricted to a single session (either active or disconnected) on that server. If the user leaves the session in a disconnected state, the user automatically reconnects to that session at the next logon. If you disable this policy setting, users are allowed to make unlimited simultaneous remote connections by using Remote Desktop Services. If you do not configure this policy setting, this policy setting is not specified at the Group Policy level.	Turn off Fair Share CPU Scheduling	Not configured	No


Disable -- > apply → ok




Then again come back and click on Remote Desktop Session Host




Click on licensing







Click on Use the specified Remote Desktop license servers \rightarrow enable \rightarrow specify your server IP \rightarrow apply \rightarrow ok




Come back and click on Set the Remote Desktop licensing mode \rightarrow Enable \rightarrow under options \rightarrow choose Per User \rightarrow apply \rightarrow ok




Come back and Click on file explorer on your windows Server → This PC → Properties




Click on Addition settings




Click on Remote and Uncheck the Allow connections only \rightarrow apply \rightarrow ok




Adding Users to Remote Desktop → SelectUsers → add






Go to the Computer management


If you want to create new users and add it to RDP group follow the below steps



Click on Local user and groups → right click on user → New user




Enter the name of the user and click on create



Reshma


C-----

Come back and click on groups \rightarrow Choose Remote Desktop user properties \rightarrow and list of users you need to add for the RDP connection \rightarrow apply \rightarrow ok




Run the below command in your cmd


gpupdate /force




Refresh the page and click on tools



Remote Desktop Services → Remote Desktop License Diagnoser



You need to see the below data



These are the steps you need to follow to enable RDP for multiple users and multiple user accessing simultaneously.