

方法一：源文件安装（推荐安装）

在CentOS和Red Hat系统中，首先添加EPEL仓库，然后更新yum源，然后安装

```
1 sudo yum install epel-release
2 sudo yum update
3 sudo yum -y install redis
```

3、服务启动停止及状态查询

```
1 // 起
2 systemctl start redis
3 // 停
4 systemctl stop redis
5 // 查看状态
6 systemctl status redis
7 // 开机自己启动
8 system enable redis
9 // 开机禁用redis服务器
10 systemctl disable redis.service
```

配置远程连接

另外，为了可以使Redis能被远程连接，需要修改配置文件，路径为/etc/redis.conf

```
1 vi /etc/redis.conf
2 需要修改的地方：
3 首先，注释这一行：
4 #bind 127.0.0.1
5 另外，推荐给Redis设置密码，取消注释这一行：
6 #requirepass foobared
7 foobared即当前密码，可以自行修改为
8 requirepass 密码
9 然后重启Redis服务，使用的命令如下：
10 sudo systemctl restart redis
```

使用docker compose安装redis-sentinels

... docker-compose.yml 706B

```
1 cd ~/app/redis/redis
2 vim docker-compose.yml
3
4 version: '2'
5 services:
6   master:
7     image: redis          ## 镜像
8     container_name: redis-master
9     command: redis-server --requirepass 123456
10    ports:
11      - "6379:6379"
12  slave1:
13    image: redis            ## 镜像
14    container_name: redis-slave-1
15    ports:
16      - "6380:6379"        ## 暴露端口
17    command: redis-server --slaveof redis-master 6379 --requirepass 123456 --
masterauth 123456
18    depends_on:
19      - master
20  slave2:
21    image: redis            ## 镜像
22    container_name: redis-slave-2
23    ports:
24      - "6381:6379"        ## 暴露端口
25    command: redis-server --slaveof redis-master 6379 --requirepass 123456 --
masterauth 123456
26    depends_on:
27      - master
28
```

然后执行 docker-compose up -d

然后cd ~/app/redis/redis-sentinel/redis

先写docker-compose文件

```
1 version: '2'
2 services:
3   sentinel1:
4     image: redis          ## 镜像
5     container_name: redis-sentinel-1
6     ports:
7       - "26379:26379"
8     command: redis-sentinel /usr/local/etc/redis/sentinel.conf
9     volumes:
10      - "./sentinel1.conf:/usr/local/etc/redis/sentinel.conf"
11  sentinel2:
12    image: redis          ## 镜像
13    container_name: redis-sentinel-2
14    ports:
15      - "26380:26379"
16    command: redis-sentinel /usr/local/etc/redis/sentinel.conf
17    volumes:
18      - "./sentinel2.conf:/usr/local/etc/redis/sentinel.conf"
19  sentinel3:
20    image: redis          ## 镜像
21    container_name: redis-sentinel-3
22    ports:
23      - "26381:26379"
24    command: redis-sentinel /usr/local/etc/redis/sentinel.conf
25    volumes:
26      - "./sentinel3.conf:/usr/local/etc/redis/sentinel.conf"
```

再写三个配置文件（sentinel.conf,sentinel1.conf,sentinel2.conf,sentinel3.conf）文件内容如下

```
1 port 26379
2 dir /tmp
3 #172.18.0.3填写自己的主节点ip
4 sentinel monitor mymaster 192.168.134.26 6379 2
5 sentinel auth-pass mymaster 123456
6 sentinel down-after-milliseconds mymaster 30000
7 sentinel parallel-syncs mymaster 1
8 sentinel failover-timeout mymaster 10000
9 sentinel deny-scripts-reconfig yes
```

然后执行 `docker-compose up -d`