Stream: Internet Engineering Task Force (IETF)

RFC: 8676

Category: Standards Track
Published: November 2019
ISSN: 2070-1721

Authors: I. Farrer, Ed. M. Boucadair, Ed.

Deutsche Telekom AG Orange

RFC 8676

YANG Modules for IPv4-in-IPv6 Address plus Port (A+P) Softwires

Abstract

This document defines YANG modules for the configuration and operation of IPv4-in-IPv6 softwire Border Relays and Customer Premises Equipment for the Lightweight 4over6, Mapping of Address and Port with Encapsulation (MAP-E), and Mapping of Address and Port using Translation (MAP-T) softwire mechanisms.

Status of This Memo

This is an Internet Standards Track document.

This document is a product of the Internet Engineering Task Force (IETF). It represents the consensus of the IETF community. It has received public review and has been approved for publication by the Internet Engineering Steering Group (IESG). Further information on Internet Standards is available in Section 2 of RFC 7841.

Information about the current status of this document, any errata, and how to provide feedback on it may be obtained at https://www.rfc-editor.org/info/rfc8676.

Copyright Notice

Copyright (c) 2019 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to BCP 78 and the IETF Trust's Legal Provisions Relating to IETF Documents (https://trustee.ietf.org/license-info) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Simplified BSD License text as described in Section 4.e of the Trust Legal Provisions and are provided without warranty as described in the Simplified BSD License.

Table of Contents

- 1. Introduction
- 2. Terminology
- 3. Overview of the Modules
 - 3.1. Overall Structure
 - 3.2. Configuration for Additional Components
- 4. Softwire CE YANG Tree Diagram
 - 4.1. CE Tree Diagram
 - 4.2. Softwire CE Tree Diagram Description
- 5. Softwire BR YANG Tree Diagram
 - 5.1. BR Tree Diagram
 - 5.2. Softwire BR Tree Diagram Description
- 6. Softwire CE YANG Module
- 7. BR Softwire YANG Module
- 8. Common Softwire Element Groups YANG Module
- 9. Security Considerations
- 10. IANA Considerations
- 11. References
 - 11.1. Normative References
 - 11.2. Informative References

Appendix A. Configuration Examples

- A.1. Configuration Example for a lw4o6 BR Binding-Table
- A.2. Configuration Example for a MAP-E BR
- A.3. lw4o6 CE Configuration Example

Acknowledgements

Contributors

Authors' Addresses

1. Introduction

The IETF Softwire Working Group has developed several IPv4-in-IPv6 softwire mechanisms to address various deployment contexts and constraints. As a companion to the architectural specification documents, this document focuses on the provisioning of Address plus Port (A+P) softwire functional elements: Border Routers (BRs) and Customer Edge (CE) (called "Customer Premises Equipment (CPE)" in [RFC7596]). The softwire mechanisms covered in this document are Lightweight 4over6 (lw4o6) [RFC7596], Mapping of Address and Port with Encapsulation (MAP-E) [RFC7597], and Mapping of Address and Port using Translation (MAP-T) [RFC7599].

This document focuses on A+P mechanisms [RFC6346]; the reader can refer to [RFC8513] for a YANG module for Dual-Stack Lite (DS-Lite) [RFC6333].

This document defines YANG modules [RFC7950] that can be used to configure and manage A+P softwire elements using the NETCONF [RFC6241] or RESTCONF [RFC8040] protocols for:

- Configuration
- · Operational State
- Notifications

2. Terminology

The reader should be familiar with the concepts and terms defined in [RFC7596], [RFC7597], [RFC7599], and the YANG data modeling language defined in [RFC7950].

The YANG modules in this document adopt the Network Management Datastore Architecture (NMDA) [RFC8342]. The meanings of the symbols used in tree diagrams are defined in [RFC8340].

The document uses the abbreviation 'BR' as a general term for softwire tunnel concentrators, including both MAP Border Routers [RFC7597] and Lightweight 4over6 lwAFTRs [RFC7596].

For brevity, "algorithm" is used to refer to the "mapping algorithm" defined in [RFC7597].

A network element may support one or multiple instances of a softwire mechanism; each of these instances (i.e., binding instances, MAP-E instances, or MAP-T instances) may have its own configuration and parameters. The term 'algo-instance' is used to denote both MAP-E and MAP-T instances.

3. Overview of the Modules

3.1. Overall Structure

The document defines the following two YANG modules for the configuration and monitoring of softwire functional elements:

ietf-softwire-ce

Provides configuration and monitoring for softwire CE element. This module is defined as augments to the interface YANG module [RFC8343].

ietf-softwire-br

Provides configuration and monitoring for softwire BR element.

In addition, the following module is defined:

ietf-softwire-common

Contains groups of common functions that are imported into the CE and BR modules.

This approach has been taken so that the various modules can be easily extended to support additional softwire mechanisms, if required.

Within the BR and CE modules, the YANG "feature" statement is used to distinguish which of the different softwire mechanism(s) is relevant for a specific element's configuration. For each module, a choice statement 'ce-type' is included for either 'binding' or 'algorithm'. 'Binding' is used for configuring Lightweight 4over6, whereas 'algorithm' is used for configuring MAP-T or MAP-E.

In the 'algo-instances' container, a choice statement 'data-plane' is included to specify MAP-E (encapsulation) or MAP-T (translation). Table 1 shows how these choices are used to indicate the desired softwire mechanism:

S46 Mechanism	ce-type?	data-plane?
Lightweight 4over6	binding	n/a
MAP-E	algorithm	encapsulation
MAP-T	algorithm	translation

Table 1: Softwire Mechanism Choice Statement Enumeration

NETCONF notifications are also included.

Earlier draft versions of this specification combined the softwire mechanisms by their associated technologies rather than their function in the architecture. As the document was revised, it became apparent that dividing the modules by their role in the architecture (CE or BR) was a better approach as this follows the intended function and existing implementation approaches more closely.

3.2. Configuration for Additional Components

The softwire modules only aim to provide configuration relevant for softwires. In order to fully provision a CE element, the following may also be necessary:

- IPv6 forwarding and routing configuration, to enable the CE to obtain one or more IPv6 prefixes for softwire usage. A YANG module for routing management is described in [RFC8349].
- IPv4 routing configuration, to add one or more IPv4 destination prefix(es) reachable via the configured softwire. A YANG module for routing management is described in [RFC8349].
- Stateful NAT44/NAPT management, to optionally specify a port set (Port Set Identifier (PSID)) along with its length. A YANG module for NAT management is described in [RFC8512].
- Stateless NAT46 management, which is required by softwire-translation-based mechanisms (i.e., the assignment of a Network-Specific Prefix to use for IPv4/IPv6 translation). A YANG module for NAT management is described in [RFC8512].

As YANG modules for the above functions are already defined in other documents, their functionality is not duplicated here and they should be referred to, as needed. Appendix A.3 provides XML examples of how these modules can be used together.

The CE must already have minimal IPv6 configuration in place so it is reachable by the NETCONF client to obtain softwire configuration. If additional IPv6-specific configuration is necessary, the YANG modules defined in [RFC8344] and [RFC8349] may be used.

4. Softwire CE YANG Tree Diagram

4.1. CE Tree Diagram

The CE module provides configuration and monitoring for all of the softwire mechanisms covered in this document (i.e., Lightweight 4over6, MAP-E, and MAP-T).

This module augments "ietf-interfaces", defined in [RFC8343] with an entry for the softwire. This entry can be referenced to configure IPv4 forwarding features for the element. This entry is added only if tunnel type (Section 10) is set to 'aplusp'.

Figure 1 shows the tree structure of the softwire CE YANG module:

```
module: ietf-softwire-ce
  augment /if:interfaces/if:interface:
    +--rw softwire-payload-mtu? uint16
    +--rw softwire-path-mru?
    +--rw (ce-type)?
       +--: (binding) {binding-mode}?
       | +--rw binding-ipv6info?
                                       union
         +--rw br-ipv6-addr
                                       inet:ipv6-address
       +--:(algo) {map-e or map-t}?
          +--rw algo-instances
             +--rw algo-instance* [name]
               +--rw name
                                         string
               +--rw enable?
                                         boolean
                +--rw algo-versioning
                yang:date-and-time
+--rw (data-plane)?
                  +--rw version? uint64
                  +--:(encapsulation) {map-e}?
                  | +--rw br-ipv6-addr
                                               inet:ipv6-address
                   +--:(translation) {map-t}?
                    +--rw dmr-ipv6-prefix?
                                               inet:ipv6-prefix
                +--rw ea-len
                                         uint8
               +--rw rule-ipv6-prefix
                                         inet:ipv6-prefix
                +--rw rule-ipv4-prefix
                                         inet:ipv4-prefix
                +--rw forwarding
                                         boolean
  augment /if:interfaces/if:interface/if:statistics:
      +--ro sent-ipv4-packets?
       yang:zero-based-counter64
       +--ro sent-ipv4-bvtes?
             yang:zero-based-counter64
       +--ro sent-ipv6-packets?
             yang:zero-based-counter64
       +--ro sent-ipv6-bytes?
              yang:zero-based-counter64
       +--ro rcvd-ipv4-packets?
              yang:zero-based-counter64
       +--ro rcvd-ipv4-bytes?
             yang:zero-based-counter64
       +--ro rcvd-ipv6-packets?
              yang:zero-based-counter64
       +--ro rcvd-ipv6-bytes?
              yang:zero-based-counter64
       +--ro dropped-ipv4-packets?
              yang:zero-based-counter64
       +--ro dropped-ipv4-bytes?
              yang:zero-based-counter64
       +--ro dropped-ipv6-packets?
              yang:zero-based-counter64
       +--ro dropped-ipv6-bytes?
              yang:zero-based-counter64
       +--ro dropped-ipv4-fragments?
              yang:zero-based-counter64
       +--ro dropped-ipv4-fragment-bytes?
              yang:zero-based-counter64
       +--ro ipv6-fragments-reassembled?
          yang:zero-based-counter64
```

```
+--ro ipv6-fragments-bytes-reassembled?

| yang:zero-based-counter64
+--ro out-icmpv4-error-packets?
| yang:zero-based-counter64
+--ro out-icmpv4-error-bytes?
| yang:zero-based-counter64
+--ro out-icmpv6-error-packets?
| yang:zero-based-counter64
+--ro out-icmpv6-error-bytes?
yang:zero-based-counter64

notifications:
+--n softwire-ce-event {binding-mode}?
+--ro ce-binding-ipv6-addr-change inet:ipv6-address
```

Figure 1: Softwire CE YANG Tree Diagram

4.2. Softwire CE Tree Diagram Description

Additional information related to the operation of a CE element is provided below:

softwire-payload-mtu:

optionally used to set the IPv4 Maximum Transmission Unit (MTU) for the softwire. Needed if the softwire implementation is unable to correctly calculate the correct IPv4 MTU size automatically.

softwire-path-mru:

optionally used to set the maximum IPv6 softwire packet size that can be received, including the encapsulation/translation overhead. Needed if the softwire implementation is unable to correctly calculate the correct IPv4 payload Maximum Receive Unit (MRU) size automatically (see Section 3.2 of [RFC4213]).

ce-type:

provides a choice statement allowing the binding or algorithmic softwire mechanisms to be selected.

Further details relevant to binding softwire elements are as follows:

binding-ipv6info:

used to set the IPv6 binding prefix type to identify which IPv6 address to use as the tunnel source. It can be 'ipv6-prefix' or 'ipv6-address'.

br-ipv6-addr:

sets the IPv6 address of the remote BR.

Additional details relevant to some of the important algorithmic elements are provided below:

algo-versioning:

optionally used to associate a version number and/or timestamp to the algorithm. This can be used for logging/data retention purposes [RFC7422]. The version number is

selected to uniquely identify the algorithm configuration and a new value written whenever a change is made to the algorithm or a new algo-instance is created.

forwarding:

specifies whether the rule can be used as a Forwarding Mapping Rule (FMR). If not set, this rule is a Basic Mapping Rule (BMR) only and must not be used for forwarding. Refer to Section 4.1 of [RFC7598].

ea-len:

used to set the length of the Embedded-Address (EA), which is defined in the mapping rule for a MAP domain.

data-plane:

provides a choice statement for either encapsulation (MAP-E) or translation (MAP-T).

br-ipv6-addr:

defines the IPv6 address of the BR. This information is valid for MAP-E.

dmr-ipv6-prefix:

defines the Default Mapping Rule (DMR) IPv6 prefix of the BR. This information is valid for MAP-T.

Additional information on the notification node is listed below:

ce-binding-ipv6-addr-change:

if the CE's binding IPv6 address changes for any reason, the NETCONF client will be notified.

5. Softwire BR YANG Tree Diagram

5.1. BR Tree Diagram

The BR YANG module provides configuration and monitoring for all of the softwire mechanisms covered in this document (i.e., Lightweight 4over6, MAP-E, and MAP-T).

Figure 2 provides the tree structure of this module:

```
module: ietf-softwire-br
 +--rw br-instances
    +--rw (br-type)?
        +--:(binding) {binding-mode}?
          +--rw binding
             +--rw bind-instance* [name]
                +--rw name
                                                 string
                +--rw binding-table-versioning
                  +--rw version? uint64
                  +--rw date? yang:date-and-time
                +--rw softwire-num-max uint32
                +--rw softwire-payload-mtu uint16
                +--rw softwire-path-mru
                                                uint16
                +--rw enable-hairpinning?
                                                 boolean
                +--rw binding-table
                   +--rw binding-entry* [binding-ipv6info]
                      +--rw binding-ipv6info
                                                union
                      +--rw binding-ipv4-addr?
                              inet:ipv4-address
                      +--rw port-set
                        +--rw psid-offset? uint8
                         +--rw psid-len
                                            uint8
                         +--rw psid
                                             uint16
                      +--rw br-ipv6-addr?
                              inet:ipv6-address
                  --rw icmp-policy
                   +--rw icmpv4-errors
                      +--rw allow-incoming-icmpv4?
                                                     boolean
                      +--rw icmpv4-rate?
                                                     uint32
                     +--rw generate-icmpv4-errors?
                                                     boolean
                   +--rw icmpv6-errors
                      +--rw generate-icmpv6-errors?
                                                     boolean
                      +--rw icmpv6-rate?
                                                     uint32
                  --ro traffic-stat
                   +--ro discontinuity-time yang:date-and-time
                   +--ro sent-ipv4-packets?
                          yang:zero-based-counter64
                   +--ro sent-ipv4-bytes?
                          yang:zero-based-counter64
                   +--ro sent-ipv6-packets?
                          yang:zero-based-counter64
                   +--ro sent-ipv6-bytes?
                          yang:zero-based-counter64
                   +--ro rcvd-ipv4-packets?
                          yang:zero-based-counter64
                   +--ro rcvd-ipv4-bytes?
                          yang:zero-based-counter64
                   +--ro rcvd-ipv6-packets?
                          yang:zero-based-counter64
                   +--ro rcvd-ipv6-bytes?
                           yang:zero-based-counter64
                   +--ro dropped-ipv4-packets?
                          yang:zero-based-counter64
                   +--ro dropped-ipv4-bytes?
                           yang:zero-based-counter64
                   +--ro dropped-ipv6-packets?
                     yang:zero-based-counter64
```

```
+--ro dropped-ipv6-bytes?
                   vang:zero-based-counter64
            +--ro dropped-ipv4-fragments?
                   yang:zero-based-counter64
            +--ro dropped-ipv4-fragment-bytes?
                   yang:zero-based-counter64
            +--ro ipv6-fragments-reassembled?
                   yang:zero-based-counter64
            +--ro ipv6-fragments-bytes-reassembled?
                   yang:zero-based-counter64
             --ro out-icmpv4-error-packets?
                   yang:zero-based-counter64
            +--ro out-icmpv4-error-bytes?
                   yang:zero-based-counter64
            +--ro out-icmpv6-error-packets?
                   yang:zero-based-counter64
            +--ro out-icmpv6-error-bytes?
                   yang:zero-based-counter64
            +--ro dropped-icmpv4-packets?
                   yang:zero-based-counter64
            +--ro dropped-icmpv4-bytes?
                   yang:zero-based-counter64
            +--ro hairpin-ipv4-packets?
                   yang:zero-based-counter64
            +--ro hairpin-ipv4-bytes?
                  yang:zero-based-counter64
            +--ro active-softwire-num?
                   uint32
+--:(algo) {map-e or map-t}?
  +--rw algorithm
     +--rw algo-instance* [name]
        +--rw name
                                   string
        +--rw enable?
                                   boolean
        +--rw algo-versioning
           +--rw version? uint64
           +--rw date?
                            yang:date-and-time
          --rw (data-plane)?
           +--:(encapsulation) {map-e}?
            | +--rw br-ipv6-addr
                                         inet:ipv6-address
           +--:(translation) {map-t}?
             +--rw dmr-ipv6-prefix?
                                        inet:ipv6-prefix
         +--rw ea-len
                                  uint8
        +--rw rule-ipv6-prefix
                                  inet:ipv6-prefix
        +--rw rule-ipv4-prefix
                                  inet:ipv4-prefix
        +--rw forwarding
                                  boolean
        +--rw port-set
           +--rw psid-offset? uint8
           +--rw psid-len
                                uint8
           +--rw psid
                                uint16
          --ro traffic-stat
           +--ro discontinuity-time
                                      yang:date-and-time
           +--ro sent-ipv4-packets?
                   yang:zero-based-counter64
            +--ro sent-ipv4-bytes?
                  yang:zero-based-counter64
            +--ro sent-ipv6-packets?
                   yang:zero-based-counter64
            +--ro sent-ipv6-bytes?
```

```
yang:zero-based-counter64
                  +--ro rcvd-ipv4-packets?
                         yang:zero-based-counter64
                  +--ro rcvd-ipv4-bytes?
                         yang:zero-based-counter64
                  +--ro rcvd-ipv6-packets?
                         yang:zero-based-counter64
                  +--ro rcvd-ipv6-bytes?
                         yang:zero-based-counter64
                  +--ro dropped-ipv4-packets?
                         yang:zero-based-counter64
                  +--ro dropped-ipv4-bytes?
                         yang:zero-based-counter64
                  +--ro dropped-ipv6-packets?
                         yang:zero-based-counter64
                  +--ro dropped-ipv6-bytes?
                         yang:zero-based-counter64
                  +--ro dropped-ipv4-fragments?
                         yang:zero-based-counter64
                  +--ro dropped-ipv4-fragment-bytes?
                         yang:zero-based-counter64
                  +--ro ipv6-fragments-reassembled?
                         yang:zero-based-counter64
                  +--ro ipv6-fragments-bytes-reassembled?
                         yang:zero-based-counter64
                  +--ro out-icmpv4-error-packets?
                        yang:zero-based-counter64
                  +--ro out-icmpv4-error-bytes?
                        yang:zero-based-counter64
                  +--ro out-icmpv6-error-packets?
                       yang:zero-based-counter64
                  +--ro out-icmpv6-error-bytes?
                         yang:zero-based-counter64
notifications:
  +---n softwire-binding-instance-event {binding-mode}?
    +--ro bind-name?
           -> /br-instances/binding/bind-instance/name
    +--ro invalid-entry* leafref
+--ro added-entry* inet:ipv6-address
    +--ro added-entry*
    +--ro modified-entry* leafref
   ---n softwire-algorithm-instance-event {map-e, map-t}?
    +--ro algo-name
             -> /br-instances/algorithm/algo-instance/name
     +--ro invalid-entry-id*
            -> /br-instances/algorithm/algo-instance/name
     +--ro added-entry*
           -> /br-instances/algorithm/algo-instance/name
     +--ro modified-entry*
             -> /br-instances/algorithm/algo-instance/name
```

Figure 2: Softwire BR YANG Tree

5.2. Softwire BR Tree Diagram Description

The descriptions for leaves that are common with the CE module are provided in Section 4.2. Descriptions for additional elements are provided below:

binding-table-versioning:

optionally used to associate a version number and/or timestamp to the binding table. This can be used for logging or data retention purposes [RFC7422]. The version number is selected to uniquely identify the binding table configuration and a new timestamp value written whenever a change is made to the contents of the binding table or a new binding table list is created.

binding-entry:

used to define the binding relationship between 3-tuples {lwB4's IPv6 address/prefix, the allocated IPv4 address, restricted port-set}. For detailed information, please refer to [RFC7596].

softwire-num-max:

used to set the maximum number of softwire binding rules that can be created on the lw4o6 element simultaneously. This parameter must not be set to zero because this is equivalent to disabling the BR instance.

active-softwire-num:

holds the number of softwires currently provisioned on the BR element.

Additional information on some of the important notification nodes is listed below:

invalid-entry, added-entry, modified-entry:

used to notify the NETCONF client that a specific binding entry or MAP rule has expired, been invalidated, added, or modified.

6. Softwire CE YANG Module

This module imports the modules defined in [RFC6991], [RFC8343], and [RFC7224]. It also imports the 'ietf-softwire-common' and 'iana-tunnel-type' modules [RFC8675].

```
<CODE BEGINS> file "ietf-softwire-ce@2019-11-16.yang"
module ietf-softwire-ce {
  yang-version 1.1;
  namespace "urn:ietf:params:xml:ns:yang:ietf-softwire-ce";
  prefix softwire-ce;
  import ietf-inet-types {
    prefix inet;
    reference
      "RFC 6991: Common YANG Data Types, Section 4";
  import ietf-interfaces {
    prefix if;
    reference
      "RFC 8343: A YANG Data Model for Interface Management";
  import ietf-softwire-common {
    prefix softwire-common;
    reference
      "RFC 8676: YANG Modules for IPv4-in-IPv6 Address plus Port
      Softwires";
  import iana-tunnel-type {
    prefix iana-tunnel-type;
    reference
      "RFC 8675: A YANG Data Model for Tunnel Interface Types";
  }
  organization
    "IETF Softwire Working Group";
  contact
    "WG Web:
               <https://datatracker.ietf.org/wg/softwire/>
    WG List: <mailto:softwire@ietf.org>
              Qi Sun
     Author:
              <mailto:sunqi.ietf@gmail.com>
     Author:
              Linhui Sun
              <mailto:lh.sunlinh@gmail.com>
     Author:
              Yong Cui
              <mailto:yong@csnet1.cs.tsinghua.edu.cn>
     Editor:
              Ian Farrer
              <mailto:ian.farrer@telekom.de>
     Author:
              Sladjana Zoric
              <mailto:sladjana.zoric@telekom.de>
              Mohamed Boucadair
     Editor:
              <mailto:mohamed.boucadair@orange.com>
     Author: Rajiv Asati
               <mailto:rajiva@cisco.com>";
  description
    "This document defines a YANG module for the configuration and
```

```
management of A+P Softwire Customer Premises Equipment (CEs).
   It covers Lightweight 4over6, MAP-E, and MAP-T mechanisms.
   Copyright (c) 2019 IETF Trust and the persons identified as
   authors of the code. All rights reserved.
   Redistribution and use in source and binary forms, with or
  without modification, is permitted pursuant to, and subject
  to the license terms contained in, the Simplified BSD License
   set forth in Section 4.c of the IETF Trust's Legal Provisions
   Relating to IETF Documents
   (http://trustee.ietf.org/license-info).
  This version of this YANG module is part of RFC 8676; see
   the RFC itself for full legal notices.";
revision 2019-11-16 {
  description
    "Initial revision.";
  reference
    "RFC 8676: YANG Modules for IPv4-in-IPv6 Address plus Port
     (A+P) Softwires";
}
 * Features
feature binding-mode {
  description
    "Binding is used for configuring the Lightweight 4over6
    mechanism.
     Binding-based softwire mechanisms are IPv4-over-IPv6 tunneling
     transition mechanisms specifically intended for complete
     independence between the IPv6 subnet prefix (and IPv6 address)
     and IPv4 address, with or without IPv4 address sharing.
    This is accomplished by maintaining state for each softwire
     (per-subscriber state) in the central Border Relay (BR) and
    using a hub-and-spoke forwarding architecture. In order to
     delegate the NAPT function and achieve IPv4 address sharing,
     port-restricted IPv4 addresses needs to be allocated to CEs.
    This feature indicates that the network element can function
     as one or more binding-based softwire instances.";
  reference
    "RFC 7596: Lightweight 4over6: An Extension to the Dual-Stack
    Lite Architecture
    RFC 7597: Mapping of Address and Port with Encapsulation
    RFC 7599: Mapping of Address and Port using Translation
     (MAP-T)";
}
feature map-e {
 description
    "MAP-E is an IPv6 transition mechanism for transporting IPv4
```

```
packets across an IPv6 network using IP encapsulation. MAP-E
     allows for a reduction of the amount of centralized state
    using rules to express IPv4/IPv6 address mappings. This
     introduces an algorithmic relationship between the IPv6
     subnet and IPv4 address.
    This feature indicates that the network element can function
     as one or more MAP-E softwire instances.";
  reference
    "RFC 7597: Mapping of Address and Port with
    Encapsulation (MAP-E)":
feature map-t {
  description
    "MAP-T is an IPv6 transition mechanism for transporting IPv4
     packets across an IPv6 network using IP translation. It
     leverages a double stateless NAT64-based solution as well as
     the stateless algorithmic address and transport layer port
    mapping algorithm defined for MAP-E.
    This feature indicates that the network element can function
     as one or more MAP-T softwire instances.";
  reference
    "RFC 7599: Mapping of Address and Port using Translation
     (MAP-T)";
// Binding Entry
grouping binding-entry {
  description
    "The binding BR (Border Relay) maintains an address
     binding table that contains the binding between the CE's
     IPv6 address, the allocated IPv4 address, and the
     restricted port-set.";
  leaf binding-ipv6info {
    type union {
      type inet:ipv6-address;
      type inet:ipv6-prefix;
    description
      "The IPv6 information for a binding entry.
       When the IPv6 prefix type is used,
       the IPv6 source address of the CE is constructed
       according to the description in RFC 7596.
       If the IPv6 address type is used, the CE can use
       any valid /128 address from a prefix assigned to
       the CE.";
    reference
      "RFC 7596: Lightweight 4over6: An Extension
       to the Dual-Stack Lite Architecture, Section 5.1";
  leaf br-ipv6-addr {
    type inet:ipv6-address;
    mandatory true;
```

```
description
      "The IPv6 address of the binding BR.";
 }
}
// configuration and stateful parameters for softwire CE interface
augment "/if:interfaces/if:interface" {
 when "derived-from(if:type, 'iana-tunnel-type:aplusp')";
  description
    "Softwire CE interface configuration";
  leaf softwire-payload-mtu {
    type uint16;
    units "bytes";
    description
      "The payload IPv4 MTU for the softwire tunnel.";
  leaf softwire-path-mru {
   type uint16;
   units "bytes";
    description
      "The path MRU for the softwire (payload + encapsulation
       overhead).";
    reference
      "RFC 4213: Basic Transition Mechanisms for IPv6 Hosts and
       Routers";
  choice ce-type {
    description
      "Sets the softwire CE mechanism";
    case binding {
      if-feature "binding-mode";
      description
        "CE binding configuration";
      uses binding-entry;
    case algo {
      if-feature "map-e or map-t";
      description
        "CE algorithm configuration";
      container algo-instances {
        description
          "Collection of MAP-E/MAP-T parameters";
        list algo-instance {
          key "name";
          description
            "MAP forwarding rule instance for
             MAP-E/MAP-T";
          leaf name {
            type string;
            mandatory true;
            description
              "The name is used to uniquely identify an algorithm
               instance.
               This name can be automatically assigned
               or explicitly configured.";
```

```
uses softwire-common:algorithm-instance;
          }
       }
     }
    }
  augment "/if:interfaces/if:interface/if:statistics" {
    when "derived-from(../if:type, 'iana-tunnel-type:aplusp')";
    description
      "Softwire CE interface statistics.";
    uses softwire-common:traffic-stat;
   * Notifications
   */
  notification softwire-ce-event {
    if-feature "binding-mode";
    description
      "CE notification";
    leaf ce-binding-ipv6-addr-change {
      type inet:ipv6-address;
      mandatory true;
      description
        "This notification is generated whenever the CE's binding
         IPv6 address changes for any reason.";
  }
}
<CODE ENDS>
```

7. BR Softwire YANG Module

This module imports typedefs from [RFC6991]. It also imports the 'ietf-softwire-common' module.

```
<CODE BEGINS> file "ietf-softwire-br@2019-11-16.yang"
module ietf-softwire-br {
  yang-version 1.1;
  namespace "urn:ietf:params:xml:ns:yang:ietf-softwire-br";
  prefix softwire-br;
  import ietf-inet-types {
    prefix inet;
    reference
      "RFC 6991: Common YANG Data Types, Section 4";
  import ietf-yang-types {
    prefix yang;
    reference
      "RFC 6991: Common YANG Data Types, Section 3";
  import ietf-softwire-common {
    prefix softwire-common;
    reference
      "RFC 8676: YANG Modules for IPv4-in-IPv6 Address plus Port
       (A+P) Softwires";
  }
  organization
    "IETF Softwire Working Group";
  contact
               <https://datatracker.ietf.org/wg/softwire/>
    "WG Web:
    WG List: <mailto:softwire@ietf.org>
     Author:
              Qi Sun
              <mailto:sunqi.ietf@gmail.com>
     Author:
              Linhui Sun
              <mailto:lh.sunlinh@gmail.com>
     Author:
              Yong Cui
              <mailto:yong@csnet1.cs.tsinghua.edu.cn>
     Editor: Ian Farrer
              <mailto:ian.farrer@telekom.de>
     Author:
              Sladjana Zoric
              <mailto:sladjana.zoric@telekom.de>
     Editor:
              Mohamed Boucadair
              <mailto:mohamed.boucadair@orange.com>
     Author: Rajiv Asati
               <mailto:rajiva@cisco.com>";
  description
    "This document defines a YANG module for the configuration and
     management of A+P Softwire Border Routers. It covers
     Lightweight 4over6, MAP-E, and MAP-T mechanisms.
     Copyright (c) 2019 IETF Trust and the persons identified as
```

```
authors of the code. All rights reserved.
   Redistribution and use in source and binary forms, with or
  without modification, is permitted pursuant to, and subject
   to the license terms contained in, the Simplified BSD License
   set forth in Section 4.c of the IETF Trust's Legal Provisions
   Relating to IETF Documents
   (http://trustee.ietf.org/license-info).
   This version of this YANG module is part of RFC 8676; see
   the RFC itself for full legal notices.";
revision 2019-11-16 {
  description
    "Initial revision.";
  reference
    "RFC 8676: YANG Modules for IPv4-in-IPv6 Address plus Port
     (A+P) Softwires";
}
 * Groupings
grouping port-set {
  description
    "Describes a set of Layer 4 port numbers.
     This may be a simple port range, or use the Port Set
     Identifier (PSID) algorithm to represent a range of transport
     layer ports that will be used by a NAPT.";
  leaf psid-offset {
    type uint8 {
      range "0..16";
    description
      "The number of offset bits. In Lightweight 4over6, the default value is 0 for assigning one contiguous
       port range. In MAP-E/T, the default value is 6,
       which means the system ports (0-1023) are excluded by
       default and the assigned port ranges are distributed across
       the entire port space, depending on either psid-len or the
       number of contiguous ports.";
  leaf psid-len {
    type uint8 {
     range "0..15";
    mandatory true;
    description
      "The length of PSID, representing the sharing
       ratio for an IPv4 address. This, along with ea-len, can
       be used to calculate the number of contiguous ports per
       port range";
  leaf psid {
    type uint16;
    mandatory true;
```

```
description
      "Port Set Identifier (PSID) value, which
       identifies a set of ports algorithmically.";
 }
}
grouping binding-entry {
  description
    "The binding BR maintains an address binding table that
    contains the binding between the CE's IPv6 address,
     the allocated IPv4 address and restricted port-set.";
  leaf binding-ipv6info {
    type union {
      type inet:ipv6-address;
      type inet:ipv6-prefix;
    description
      "The IPv6 information for a CE binding entry.
       When the IPv6 prefix type is used,
       the IPv6 source address of the CE is constructed
       according to the description in RFC 7596;
       if the IPv6 address type is used, the CE can use
       any valid /128 address from a prefix assigned to
       the CE.";
    reference
      "RFC 7596: Lightweight 4over6: An Extension to the Dual-Stack
       Lite Architecture";
  leaf binding-ipv4-addr {
    type inet:ipv4-address;
    description
      "The IPv4 address assigned to the binding CE,
       which is used as the IPv4 external address
       for binding CE local NAPT44.";
  container port-set {
    description
      "For Lightweight 4over6, the default value
       for offset should be 0, to configure one contiguous
       port range.";
    uses port-set {
      refine "psid-offset" {
        default "0";
      }
    }
  leaf br-ipv6-addr {
    type inet:ipv6-address;
    description
      "The IPv6 address for binding BR.";
}
 * Features
 */
feature binding-mode {
```

```
description
    "Binding is used for configuring the Lightweight 4over6
    mechanism.
     Binding-based softwire mechanisms are IPv4-over-IPv6 tunneling
     transition mechanisms specifically intended for complete
     independence between the IPv6 subnet prefix (and IPv6 address)
     and IPv4 address, with or without IPv4 address sharing.
    This is accomplished by maintaining state for each softwire
     (per-subscriber state) in the central Border Relay (BR) and
     using a hub-and-spoke forwarding architecture. In order to
     delegate the NAPT function and achieve IPv4 address sharing,
     port-restricted IPv4 addresses needs to be allocated to CEs.
     This feature indicates that the network element can function
     as one or more binding-based softwire instances.";
  reference
    "RFC 7596: Lightweight 4over6: An Extension to the Dual-Stack
    Lite Architecture
     RFC 7597: Mapping of Address and Port with Encapsulation
     RFC 7599: Mapping of Address and Port using Translation
     (MAP-T)";
}
feature map-e {
  description
    "MAP-E is an IPv6 transition mechanism for transporting IPv4
    packets across an IPv6 network using IP encapsulation. MAP-E
    allows for a reduction of the amount of centralized state
    using rules to express IPv4/IPv6 address mappings. This
    introduces an algorithmic relationship between the IPv6 subnet
    and IPv4 address.
    This feature indicates that the network element can function
    as one or more MAP-E softwire instances.";
  reference
    "RFC 7597: Mapping of Address and Port with Encapsulation
     (MAP-E)";
}
feature map-t {
  description
    "MAP-T is an IPv6 transition mechanism for transporting IPv4
    packets across an IPv6 network using IP translation. It
     leverages a double stateless NAT64-based solution as well
    as the stateless algorithmic address and transport layer
    port mapping algorithm defined for MAP-E.
    This feature indicates that the network element can function
     as one or more MAP-T softwire instances.";
  reference
    "RFC 7599: Mapping of Address and Port using Translation
     (MAP-T)";
container br-instances {
```

```
description
  "BR instances enabled in a network element.";
choice br-type {
  description
    "Select binding or algorithmic BR functionality.";
 case binding {
  if-feature "binding-mode";
    container binding {
      description
        "binding mechanism (binding table) configuration.";
      list bind-instance {
        key "name";
        description
          "A set of binding instances to be configured.";
        leaf name {
          type string;
          mandatory true;
          description
            "The name for the binding BR. It is used to uniquely
             distinguish a binding instance by its name.";
        container binding-table-versioning {
          description
            "binding table's version";
          leaf version {
            type uint64;
            description
              "Version number for this binding table.";
          leaf date {
            type yang:date-and-time;
            description
              "Timestamp when the binding table was activated.
               A binding instance may be provided with binding
               entries that may change in time (e.g., increase
               the size of the port set). When a party who is
               the victim of abuse presents an external IP
               address/port, the version of the binding table
               is important because, depending on the version,
               a distinct customer may be identified.
               The timestamp is used as a key to find the
               appropriate binding table that was put into effect
               when an abuse occurred.";
            reference
              "RFC 7422: Deterministic Address Mapping to Reduce
               Logging in Carrier-Grade NAT Deployments";
          }
        leaf softwire-num-max {
          type uint32 {
            range "1..max";
          mandatory true;
          description
            "The maximum number of softwires that can be created
             on the binding BR.";
```

```
leaf softwire-payload-mtu {
  type uint16;
  units "bytes";
  mandatory true;
  description
    "The payload IPv4 MTU for binding softwire.";
leaf softwire-path-mru {
  type uint16;
  units "bytes";
  mandatory true;
  description
    "The path MRU for binding softwire";
  reference
    "RFC 4213: Basic Transition Mechanisms for IPv6 Hosts
               and Routers";
leaf enable-hairpinning {
  type boolean;
  default "true";
  description
    "Enables/disables support for locally forwarding
     (hairpinning) traffic between two CEs";
  reference
    "RFC 7596: Lightweight 4over6: An Extension to
     the Dual-Stack Lite Architecture, Section 6.2";
container binding-table {
  description
    "binding table";
  list binding-entry {
    key "binding-ipv6info";
    description
      "binding entry";
    uses binding-entry;
 }
}
container icmp-policy {
  description
    "The binding BR can be configured to process or drop
     incoming ICMP messages and to generate outgoing ICMP
     error messages.";
  container icmpv4-errors {
    description
      "ICMPv4 error processing configuration";
    leaf allow-incoming-icmpv4 {
      type boolean;
      default "true";
      description
        "Enables the processing of incoming ICMPv4
         packets.";
      reference
        "RFC 7596: Lightweight 4over6: An Extension to
         the Dual-Stack Lite Architecture";
    leaf icmpv4-rate {
      type uint32;
```

```
description
        "Rate limit threshold in messages per second
         for processing incoming ICMPv4 errors messages";
    leaf generate-icmpv4-errors {
      type boolean;
      default "true";
      description
        "Enables the generation of outgoing ICMPv4 error
         messages on receipt of an inbound IPv4 packet
         with no matching binding table entry.";
        "RFC 7596: Lightweight 4over6:
         An Extension to the Dual-Stack Lite
         Architecture, Section 5.2";
    }
  }
  container icmpv6-errors {
    description
      "ICMPv6 error processing configuration";
    leaf generate-icmpv6-errors {
      type boolean;
      default "true";
      description
        "Enables the generation of ICMPv6 error messages
         if no matching binding table entry is found for
         a received packet.";
      reference
        "RFC 7596: Lightweight 4over6:
         An Extension to the Dual-Stack Lite
         Architecture, Section 6.2";
    leaf icmpv6-rate {
      type uint32;
      description
        "Rate limit threshold in messages per second
         for sending ICMPv6 errors messages";
      reference
        "RFC 7596: Lightweight 4over6: An Extension
         to the Dual-Stack Lite Architecture, Section 9";
    }
  }
}
container traffic-stat {
  config false;
  description
    "Traffic statistics information for the BR.";
  leaf discontinuity-time {
    type yang:date-and-time;
    mandatory true;
    description
      "The time of the most recent occasion on which the
       BR instance suffered a discontinuity. This must
       be initialized when the BR instance is configured
       or rebooted.";
  uses softwire-common:traffic-stat;
  leaf dropped-icmpv4-packets {
```

```
type yang:zero-based-counter64;
  description
    "ICMPv4 packets that are dropped as a result
     of the ICMP policy. Typically, this can be any
     incoming ICMPv4 packets if ICMPv4 processing is
     disabled or incoming ICMPv4 packets that exceed
     the ICMPv4 rate-limit threshold.
     Discontinuities in the value of this counter can
     occur at re-initialization of the management
     system and at other times as indicated by
     the value of 'discontinuity-time'.";
leaf dropped-icmpv4-bytes {
  type yang:zero-based-counter64;
  description
    "ICMPv4 messages, in bytes, that are dropped as a result of the ICMP policy. Typically, it
     can be any incoming ICMPv4 packets if ICMPv4
     processing is disabled or incoming ICMPv4
     packets that exceed the ICMPv4 rate-limit
     threshold.
     Discontinuities in the value of this counter can
     occur at re-initialization of the management
     system and at other times as indicated by
     the value of 'discontinuity-time'.";
leaf hairpin-ipv4-packets {
  type yang:zero-based-counter64;
  description
    "IPv4 packets locally routed between two CEs
     (hairpinned).
     Discontinuities in the value of this counter can
     occur at re-initialization of the management
     system and at other times as indicated by
     the value of 'discontinuity-time'.";
leaf hairpin-ipv4-bytes {
  type yang:zero-based-counter64;
  description
    "IPv4 bytes locally routed between two CEs
     (hairpinned).
     Discontinuities in the value of this counter can
     occur at re-initialization of the management
     system and at other times as indicated by
     the value of 'discontinuity-time'.";
leaf active-softwire-num {
  type uint32;
  config false;
  description
    "The number of currently active softwires on the
     binding instance.
     Discontinuities in the value of this counter can
```

```
occur at re-initialization of the management
                 system and at other times as indicated by
                 the value of 'discontinuity-time'.";
           }
         }
       }
      }
    }
    case algo {
      if-feature "map-e or map-t";
      container algorithm {
        description
          "A set of parameters used for MAP-E/MAP-T";
        list algo-instance {
          key "name";
          description
            "Instances of algorithm";
          leaf name {
            type string;
            mandatory true;
            description
              "The name is used to uniquely identify an algorithm
               instance.
               This name can be automatically assigned
               or explicitly configured.";
          uses softwire-common:algorithm-instance;
          container port-set {
            description
              "Indicates a set of ports.";
            uses port-set;
          container traffic-stat {
            config false;
            description
              "Traffic statistics information for the BR.";
            leaf discontinuity-time {
              type yang:date-and-time;
              mandatory true;
              description
                "The time of the most recent occasion on which the
                 BR instance suffered a discontinuity. This must
                 be reset to the current date-and-time when the BR
                 instance is configured or rebooted.";
            uses softwire-common:traffic-stat;
       }
     }
   }
 }
}
 * Notifications
```

```
notification softwire-binding-instance-event {
  if-feature "binding-mode";
  description
    "Notifications for the binding instance when an entry is
     added, modified, or is not valid anymore.";
  leaf bind-name {
    type leafref {
      path "/br-instances/binding/bind-instance/name";
    description
      "The name of the binding-instance that
       generated the notification.";
  leaf-list invalid-entry {
    type leafref {
      path "/br-instances/binding/"
         + "bind-instance[name=current()/../bind-name]/"
         + "binding-table/binding-entry/binding-ipv6info";
    description
      "Notify the client that a specific binding entry has
       expired or is invalid. The binding-ipv6info identifies
       an entry.";
  leaf-list added-entry {
    type inet:ipv6-address;
    description
      "Notify the client that a binding entry has been added.
       The IPv6 address of that entry is the index. The client
       gets other information from the binding BR about the entry
       indexed by that ipv6 address.";
  leaf-list modified-entry {
    type leafref {
      path "/br-instances/binding/"
         + "bind-instance[name=current()/../bind-name]/"
         + "binding-table/binding-entry/binding-ipv6info";
    description
      "The binding table entry that has been modified.";
  }
notification softwire-algorithm-instance-event {
  if-feature "map-e or map-t";
  description
    "Notifications for an algorithm instance when an entry is
     added, modified, or is not valid anymore.";
  leaf algo-name {
    type leafref {
      path "/br-instances/algorithm/algo-instance/name";
    mandatory true;
    description
      "Algorithmic instance event.";
  leaf-list invalid-entry {
   type leafref {
     path "/br-instances/algorithm/algo-instance/name";
```

```
description
    "Invalid entry.";
}
leaf-list added-entry {
    type leafref {
        path "/br-instances/algorithm/algo-instance/name";
    }
    description
        "Added entry.";
}
leaf-list modified-entry {
    type leafref {
        path "/br-instances/algorithm/algo-instance/name";
    }
    description
        "Modified entry.";
}
```

8. Common Softwire Element Groups YANG Module

This module imports typedefs from [RFC6991].

The following YANG module contains definitions that are used by both the softwire CE and softwire BR YANG modules.

```
<CODE BEGINS> file "ietf-softwire-common@2019-11-16.yang"
module ietf-softwire-common {
  yang-version 1.1;
  namespace "urn:ietf:params:xml:ns:yang:ietf-softwire-common";
  prefix softwire-common;
  import ietf-inet-types {
    prefix inet;
    reference
      "RFC 6991: Common YANG Data Types, Section 4";
  import ietf-yang-types {
    prefix yang;
    reference
      "RFC 6991: Common YANG Data Types, Section 3";
  organization
    "IETF Softwire Working Group";
  contact
    "WG Web:
               <https://datatracker.ietf.org/wg/softwire/>
    WG List: <mailto:softwire@ietf.org>
     Author:
              Qi Sun
              <mailto:sunqi.ietf@gmail.com>
     Author: Linhui Sun
              <mailto:lh.sunlinh@gmail.com>
     Author:
              Yong Cui
              <mailto:yong@csnet1.cs.tsinghua.edu.cn>
     Editor: Ian Farrer
              <mailto:ian.farrer@telekom.de>
              Sladjana Zoric
     Author:
              <mailto:sladjana.zoric@telekom.de>
     Editor:
              Mohamed Boucadair
              <mailto:mohamed.boucadair@orange.com>
     Author: Rajiv Asati
               <mailto:rajiva@cisco.com>";
  description
    "This document defines a YANG module defining types
     common to all A+P modules.
     Copyright (c) 2019 IETF Trust and the persons identified as
     authors of the code. All rights reserved.
     Redistribution and use in source and binary forms, with or
     without modification, is permitted pursuant to, and subject
     to the license terms contained in, the Simplified BSD License
     set forth in Section 4.c of the IETF Trust's Legal Provisions
     Relating to IETF Documents
     (http://trustee.ietf.org/license-info).
```

```
This version of this YANG module is part of RFC 8676; see
   the RFC itself for full legal notices.";
revision 2019-11-16 {
  description
    "Initial revision.";
  reference
    "RFC 8676: YANG Modules for IPv4-in-IPv6 Address plus Port
               (A+P) Softwires";
}
feature map-e {
  description
    "MAP-E is an IPv6 transition mechanism for transporting IPv4
    packets across an IPv6 network using IP encapsulation. MAP-E
     allows for a reduction of the amount of centralized state
    using rules to express IPv4/IPv6 address mappings. This
     introduces an algorithmic relationship between the IPv6
     subnet and IPv4 address.
    This feature indicates that the network element can function
     as one or more MAP-E softwire instances.";
  reference
    "RFC 7597: Mapping of Address and Port with Encapsulation
feature map-t {
  description
    "MAP-T is an IPv6 transition mechanism for transporting IPv4
    packets across an IPv6 network using IP translation. It
     leverages a double stateless NAT64-based solution as well as
    the stateless algorithmic address and transport layer
    port mapping algorithm defined for MAP-E.
    This feature indicates that the network element can function
    as one or more MAP-T softwire instances.";
  reference
    "RFC 7599: Mapping of Address and Port using Translation
     (MAP-T)";
}
 * Groupings
grouping algorithm-instance {
  description
    "A collection of parameters that is used for MAP-E/MAP-T.";
  leaf enable {
    type boolean;
    description
      "Enable/disable an individual MAP-E or MAP-T rule.";
  container algo-versioning {
    description
      "Version number for this algorithm instance";
```

```
leaf version {
    type uint64;
    description
      "A version number for the mapping algorithm
       rules provided to the algorithm instance";
  leaf date {
    type yang:date-and-time;
   description
      "Timestamp when the algorithm instance was activated.
       An algorithm instance may be provided with mapping
       rules that may change in time (for example, increase
       the size of the port set). When a party who is the victim
       of abuse presents an external IP address/port, the version
       of the algorithm is important because depending on
       the version, a distinct customer may be identified.
       The timestamp is used as a key to find the appropriate
       algorithm that was put into effect when an abuse
       occurred.";
    reference
      "RFC 7422: Deterministic Address Mapping to Reduce
                Logging in Carrier-Grade NAT Deployments";
 }
}
choice data-plane {
  description
    "Selects MAP-E (encapsulation) or MAP-T
    (translation)";
  case encapsulation {
   if-feature "map-e";
   description
      "encapsulation for MAP-E";
    leaf br-ipv6-addr {
     type inet:ipv6-address;
      mandatory true;
     description
        "The IPv6 address of the MAP-E BR.";
   }
 }
 case translation {
   if-feature "map-t";
   description
      "translation for MAP-T";
    leaf dmr-ipv6-prefix {
      type inet:ipv6-prefix;
      description
        "The IPv6 prefix of the MAP-T BR.";
   }
 }
leaf ea-len {
 type uint8;
 mandatory true;
  description
    "Embedded Address (EA) bits are the IPv4 EA-bits in the IPv6
    address identifying an IPv4 prefix/address (or part thereof)
```

```
or a shared IPv4 address (or part thereof) and a port-set
       identifier. The length of the EA-bits is defined as part of
       a MAP rule for a MAP domain.";
  leaf rule-ipv6-prefix {
    type inet:ipv6-prefix;
    mandatory true;
    description
      "The Rule IPv6 prefix defined in the mapping rule.";
  leaf rule-ipv4-prefix {
    type inet:ipv4-prefix;
    mandatory true;
    description
      "The Rule IPv4 prefix defined in the mapping rule.";
  leaf forwarding {
    type boolean;
    mandatory true;
    description
      "This parameter specifies whether the rule may be used for
       forwarding; if set, this rule is used as a Forwarding
       Mapping Rule (FMR); if not set, this rule is a Basic
       Mapping Rule (BMR) only and must not be used for
       forwarding.";
  }
grouping traffic-stat {
  description
    "Traffic statistics":
  leaf sent-ipv4-packets {
    type yang:zero-based-counter64;
    description
      "Number of decapsulated and forwarded IPv4 packets.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system and at
       other times as indicated by the value of
       'discontinuity-time'.";
  leaf sent-ipv4-bytes {
    type yang:zero-based-counter64;
    description
      "Decapsulated/translated IPv4 traffic sent, in bytes.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system and at
       other times as indicated by the value of
       'discontinuity-time'.";
  leaf sent-ipv6-packets {
    type yang:zero-based-counter64;
    description
      "Number of encapsulated IPv6 packets sent.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system and at
```

```
other times as indicated by the value of
     'discontinuity-time'.";
leaf sent-ipv6-bytes {
 type yang:zero-based-counter64;
  description
    "Encapsulated IPv6 traffic sent, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf rcvd-ipv4-packets {
  type yang:zero-based-counter64;
  description
    "Number of IPv4 packets received.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf rcvd-ipv4-bytes {
  type yang:zero-based-counter64;
  description
    "IPv4 traffic received, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf rcvd-ipv6-packets {
  type yang:zero-based-counter64;
  description
    "Number of IPv4-in-IPv6 packets received.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf rcvd-ipv6-bytes {
 type yang:zero-based-counter64;
  description
    "IPv4-in-IPv6 traffic received, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv4-packets {
  type yang:zero-based-counter64;
  description
    "Number of IPv4 packets dropped at the
    Internet-facing interface.
```

```
Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv4-bytes {
  type yang:zero-based-counter64;
  description
    "IPv4 traffic dropped at the Internet-facing
    interface, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv6-packets {
 type yang:zero-based-counter64;
  description
    "Number of IPv4-in-IPv6 packets dropped.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv6-bytes {
  type yang:zero-based-counter64;
  description
    "IPv4-in-IPv6 traffic dropped, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv4-fragments {
  type yang:zero-based-counter64;
  description
    "Number of fragmented IPv4 packets dropped.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf dropped-ipv4-fragment-bytes {
 type yang:zero-based-counter64;
  description
    "Fragmented IPv4 traffic dropped, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf ipv6-fragments-reassembled {
```

```
type yang:zero-based-counter64;
  description
    "Number of IPv6 fragments successfully reassembled.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf ipv6-fragments-bytes-reassembled {
  type yang:zero-based-counter64;
  description
    "IPv6 fragments successfully reassembled, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf out-icmpv4-error-packets {
  type yang:zero-based-counter64;
  description
    "Internally generated ICMPv4 error packets.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf out-icmpv4-error-bytes {
  type yang:zero-based-counter64;
  description
    "Internally generated ICMPv4 error messages, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf out-icmpv6-error-packets {
  type yang:zero-based-counter64;
  description
    "Internally generated ICMPv6 error packets.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
leaf out-icmpv6-error-bytes {
  type yang:zero-based-counter64;
  description
    "Internally generated ICMPv6 error messages, in bytes.
    Discontinuities in the value of this counter can occur
    at re-initialization of the management system and at
    other times as indicated by the value of
     'discontinuity-time'.";
```

```
}
}
<CODE ENDS>
```

9. Security Considerations

The YANG modules defined in this document are designed to be accessed via network management protocols such as NETCONF [RFC6241] or RESTCONF [RFC8040]. The lowest NETCONF layer is the secure transport layer, and the mandatory-to-implement secure transport is Secure Shell (SSH) [RFC6242]. The lowest RESTCONF layer is HTTPS, and the mandatory-to-implement secure transport is TLS [RFC8446].

The Network Configuration Access Control Model (NACM) [RFC8341] provides the means to restrict access for particular NETCONF or RESTCONF users to a preconfigured subset of all available NETCONF or RESTCONF protocol operations and content.

All data nodes defined in the YANG modules which can be created, modified, and deleted (i.e., config true, which is the default) are considered sensitive. Write operations (e.g., edit-config) to these data nodes without proper protection can have a negative effect on network operations. An attacker who is able to access the BR can undertake various attacks, such as:

- Setting the value of 'br-ipv6-addr' on the CE to point to an illegitimate BR so that it can intercept all the traffic sent by a CE. Illegitimately intercepting users' traffic is an attack with severe implications on privacy.
- Setting the MTU to a low value, which may increase the number of fragments ('softwire-payload-mtu').
- Disabling hairpinning (i.e., setting 'enable-hairpinning' to 'false') to prevent communications between CEs.
- Setting 'softwire-num-max' to an arbitrary high value, which may be exploited by a misbehaving user to perform a DoS on the binding BR by mounting a massive number of softwires.
- Setting 'icmpv4-rate' or 'icmpv6-rate' to a low value, which may lead to the deactivation of ICMP messages handling.
- Instructing the BR to install entries, which, in turn, will induce a DDoS attack by means of the notifications generated by the BR. This DDoS can be softened by defining a notification interval, but given that this interval parameter can be disabled or set to a low value by the misbehaving entity, the same problem will be observed.

Some of the readable data nodes in this YANG module may be considered sensitive or vulnerable in some network environments. It is thus important to control read access (e.g., via get, get-config, or notification) to these data nodes. These subtrees and data nodes can be misused to track the activity of a host:

• the binding Table (/br-instances/binding/bind-instance/binding-table)

• the algorithm configuration (/br-instances/algorithm/algo-instance/)

Security considerations related to lw4o6, MAP-T, and MAP-E are discussed in [RFC7596], [RFC7597], and [RFC7599] respectively.

Security considerations given in [RFC7950] are also applicable here.

10. IANA Considerations

IANA has assigned the following new tunnel type under the tunnelType subregistry of the "ifType Definitions" registry maintained in the SMI Numbers registry [TUNNELTYPE-IANA-REGISTRY]:

Decimal: 18 Name: aplusp

Description: A+P encapsulation

Reference: [RFC6346]

IANA has registered the following in the "ns" subregistry within the "IETF XML Registry" [RFC3688]:

URI: urn:ietf:params:xml:ns:yang:ietf-softwire-ce

Registrant Contact: The IESG.

XML: N/A; the requested URI is an XML namespace.

URI: urn:ietf:params:xml:ns:yang:ietf-softwire-br

Registrant Contact: The IESG.

XML: N/A; the requested URI is an XML namespace.

URI: urn:ietf:params:xml:ns:yang:ietf-softwire-common

Registrant Contact: The IESG.

XML: N/A; the requested URI is an XML namespace.

IANA has registered the following YANG modules in the "YANG Module Names" subregistry [RFC6020] within the "YANG Parameters" registry.

name: ietf-softwire-ce

namespace: urn:ietf:params:xml:ns:yang:ietf-softwire-ce

prefix: softwire-ce reference: RFC 8676

name: ietf-softwire-br

namespace: urn:ietf:params:xml:ns:yang:ietf-softwire-br

prefix: softwire-br reference: RFC 8676

name: ietf-softwire-common

namespace: urn:ietf:params:xml:ns:yang:ietf-softwire-common

prefix: softwire-common reference: RFC 8676

11. References

11.1. Normative References

- [RFC3688] Mealling, M., "The IETF XML Registry", BCP 81, RFC 3688, DOI 10.17487/RFC3688, January 2004, https://www.rfc-editor.org/info/rfc3688>.
- [RFC6020] Bjorklund, M., Ed., "YANG A Data Modeling Language for the Network Configuration Protocol (NETCONF)", RFC 6020, DOI 10.17487/RFC6020, October 2010, https://www.rfc-editor.org/info/rfc6020.
- [RFC6241] Enns, R., Ed., Bjorklund, M., Ed., Schoenwaelder, J., Ed., and A. Bierman, Ed., "Network Configuration Protocol (NETCONF)", RFC 6241, DOI 10.17487/RFC6241, June 2011, https://www.rfc-editor.org/info/rfc6241.
- [RFC6242] Wasserman, M., "Using the NETCONF Protocol over Secure Shell (SSH)", RFC 6242, DOI 10.17487/RFC6242, June 2011, https://www.rfc-editor.org/info/rfc6242.
- [RFC6991] Schoenwaelder, J., Ed., "Common YANG Data Types", RFC 6991, DOI 10.17487/ RFC6991, July 2013, https://www.rfc-editor.org/info/rfc6991.
- [RFC7224] Bjorklund, M., "IANA Interface Type YANG Module", RFC 7224, DOI 10.17487/ RFC7224, May 2014, https://www.rfc-editor.org/info/rfc7224.
- [RFC7596] Cui, Y., Sun, Q., Boucadair, M., Tsou, T., Lee, Y., and I. Farrer, "Lightweight 4over6: An Extension to the Dual-Stack Lite Architecture", RFC 7596, DOI 10.17487/ RFC7596, July 2015, https://www.rfc-editor.org/info/rfc7596>.
- [RFC7597] Troan, O., Ed., Dec, W., Li, X., Bao, C., Matsushima, S., Murakami, T., and T. Taylor, Ed., "Mapping of Address and Port with Encapsulation (MAP-E)", RFC 7597, DOI 10.17487/RFC7597, July 2015, https://www.rfc-editor.org/info/rfc7597.
- [RFC7598] Mrugalski, T., Troan, O., Farrer, I., Perreault, S., Dec, W., Bao, C., Yeh, L., and X. Deng, "DHCPv6 Options for Configuration of Softwire Address and Port-Mapped Clients", RFC 7598, DOI 10.17487/RFC7598, July 2015, https://www.rfc-editor.org/info/rfc7598.
- [RFC7599] Li, X., Bao, C., Dec, W., Ed., Troan, O., Matsushima, S., and T. Murakami, "Mapping of Address and Port using Translation (MAP-T)", RFC 7599, DOI 10.17487/ RFC7599, July 2015, https://www.rfc-editor.org/info/rfc7599>.
- [RFC7950] Bjorklund, M., Ed., "The YANG 1.1 Data Modeling Language", RFC 7950, DOI 10.17487/RFC7950, August 2016, https://www.rfc-editor.org/info/rfc7950>.
- [RFC8040] Bierman, A., Bjorklund, M., and K. Watsen, "RESTCONF Protocol", RFC 8040, DOI 10.17487/RFC8040, January 2017, https://www.rfc-editor.org/info/rfc8040.

- [RFC8341] Bierman, A. and M. Bjorklund, "Network Configuration Access Control Model", STD 91, RFC 8341, DOI 10.17487/RFC8341, March 2018, https://www.rfc-editor.org/info/rfc8341.
- [RFC8343] Bjorklund, M., "A YANG Data Model for Interface Management", RFC 8343, DOI 10.17487/RFC8343, March 2018, https://www.rfc-editor.org/info/rfc8343.
- [RFC8446] Rescorla, E., "The Transport Layer Security (TLS) Protocol Version 1.3", RFC 8446, DOI 10.17487/RFC8446, August 2018, https://www.rfc-editor.org/info/rfc8446.
- [RFC8675] Boucadair, M., Farrer, I., and R. Asati, "A YANG Data Model for Tunnel Interface Types", RFC 8675, DOI 10.17487/RFC8675, November 2019, https://www.rfc-editor.org/info/rfc8675.
- [TUNNELTYPE-IANA-REGISTRY] IANA, "Structure of Management Information (SMI) Numbers (MIB Module Registrations)", https://www.iana.org/assignments/smi-numbers>.

11.2. Informative References

- [RFC4213] Nordmark, E. and R. Gilligan, "Basic Transition Mechanisms for IPv6 Hosts and Routers", RFC 4213, DOI 10.17487/RFC4213, October 2005, https://www.rfc-editor.org/info/rfc4213.
- [RFC6333] Durand, A., Droms, R., Woodyatt, J., and Y. Lee, "Dual-Stack Lite Broadband Deployments Following IPv4 Exhaustion", RFC 6333, DOI 10.17487/RFC6333, August 2011, https://www.rfc-editor.org/info/rfc6333.
- [RFC6346] Bush, R., Ed., "The Address plus Port (A+P) Approach to the IPv4 Address Shortage", RFC 6346, DOI 10.17487/RFC6346, August 2011, https://www.rfc-editor.org/info/rfc6346.
- [RFC7422] Donley, C., Grundemann, C., Sarawat, V., Sundaresan, K., and O. Vautrin, "Deterministic Address Mapping to Reduce Logging in Carrier-Grade NAT Deployments", RFC 7422, DOI 10.17487/RFC7422, December 2014, https://www.rfc-editor.org/info/rfc7422.
- [RFC8340] Bjorklund, M. and L. Berger, Ed., "YANG Tree Diagrams", BCP 215, RFC 8340, DOI 10.17487/RFC8340, March 2018, https://www.rfc-editor.org/info/rfc8340.
- [RFC8342] Bjorklund, M., Schoenwaelder, J., Shafer, P., Watsen, K., and R. Wilton, "Network Management Datastore Architecture (NMDA)", RFC 8342, DOI 10.17487/RFC8342, March 2018, https://www.rfc-editor.org/info/rfc8342.
- [RFC8344] Bjorklund, M., "A YANG Data Model for IP Management", RFC 8344, DOI 10.17487/RFC8344, March 2018, https://www.rfc-editor.org/info/rfc8344.
- [RFC8349] Lhotka, L., Lindem, A., and Y. Qu, "A YANG Data Model for Routing Management (NMDA Version)", RFC 8349, DOI 10.17487/RFC8349, March 2018, https://www.rfc-editor.org/info/rfc8349.

[RFC8512] Boucadair, M., Ed., Sivakumar, S., Jacquenet, C., Vinapamula, S., and Q. Wu, "A

YANG Module for Network Address Translation (NAT) and Network Prefix Translation (NPT)", RFC 8512, DOI 10.17487/RFC8512, January 2019, https://

www.rfc-editor.org/info/rfc8512>.

[RFC8513] Boucadair, M., Jacquenet, C., and S. Sivakumar, "A YANG Data Model for Dual-

Stack Lite (DS-Lite)", RFC 8513, DOI 10.17487/RFC8513, January 2019, https://

www.rfc-editor.org/info/rfc8513>.

Appendix A. Configuration Examples

The following sections provide examples of how the softwire YANG modules can be used for configuring softwire elements.

A.1. Configuration Example for a lw4o6 BR Binding-Table

The lwAFTR maintains an address binding table that contains the following 3-tuples:

- IPv6 Address for a single lwB4
- Public IPv4 Address
- · Restricted port-set

The entry has two functions: the IPv6 encapsulation of inbound IPv4 packets destined to the lwB4 and the validation of outbound IPv4-in-IPv6 packets received from the lwB4 for decapsulation.

Consider an example for the following lw4o6 binding table entry:

lwB4 Binding IPv6 Address: 2001:db8::1

lwB4 Binding IPv4 Address: 192.0.2.1

lwB4 PSID: 0x34

lwB4 PSID Length 8

BR IPv6 Address: 2001:db8:1::2

```
<br-instances>
  <br/>
<br/>
ding>
      <br/><bind-instance>
        <name>mybinding-instance</name>
        <br/>
<br/>
ding-table>
          <br/>
<br/>
ding-entry>
            <binding-ipv6info>2001:db8::1/binding-ipv6info>
            <binding-ipv4-addr>192.0.2.1/binding-ipv4-addr>
            <port-set>
              <psid>52</psid>
              <psid-len>8</psid-len>
            </port-set>
            <br-ipv6-addr>2001:db8:1::2
          </binding-entry>
        </binding-table>
        <softwire-num-max>1024</softwire-num-max>
        <softwire-path-mru>1540</softwire-path-mru>
        <softwire-payload-mtu>1500</softwire-payload-mtu>
      </bind-instance>
  </binding>
</br-instances>
```

Figure 3: lw4o6 Binding Table Configuration XML

A.2. Configuration Example for a MAP-E BR

A MAP-E BR is configured with forward mapping rules for the CEs it is serving. In this example (taken from [RFC7597], Appendix A, Example 2), the following parameters are required:

- Rule IPv6 Prefix
- Rule IPv4 Prefix
- Rule EA-bit bit length
- IPv6 Address of MAP-BR

The mapping rule has two functions: identifying the destination CE IPv6 address for encapsulating inbound IPv4 packets and the validation of outbound IPv4-in-IPv6 packets received from the CE for de-capsulation.

The transport type for the data plane also needs to be configured for encapsulation to enable MAP-E and forwarding needs to be enabled.

Consider an example for the following MAP-E Forwarding Mapping Rule:

Data plane: encapsulation
Rule IPv6 Prefix: 2001:db8::/40

Rule IPv4 Prefix: 192.0.2.0/24

Rule EA-bit Length: 16

BR IPv6 Address: 2001:db8:ffff::1

Figure 4 provides the example MAP-E BR configuration xml.

```
<br-instances>
 <algorithm>
   <algo-instance>
     <name>myalgo-instance</name>
     <encapsulation>
       <br-ipv6-addr>2001:db8:ffff::1
     </encapsulation>
     <ea-len>16</ea-len>
     <rule-ipv4-prefix>192.0.2.0/24</rule-ipv4-prefix>
     <rule-ipv6-prefix>2001:db8::/40</rule-ipv6-prefix>
     <forwarding>true</forwarding>
     <port-set>
       <psid-offset>6</psid-offset>
       <psid-len>8</psid-len>
      </port-set>
   </algo-instance>
 </algorithm>
</br-instances>
```

Figure 4: MAP-E FMR Configuration XML

A.3. lw4o6 CE Configuration Example

This section provides XML examples for configuring a lw4o6 CE. Examples for routing and NAT44 are also provided for convenience.

Consider an example for the following lw4o6 CE configuration:

lwB4 Binding IPv6 Address: 2001:db8::1

lwB4 Binding IPv4 Address: 192.0.2.1

lwB4 PSID: 0x34

lwB4 PSID Length 8

BR IPv6 Address: 2001:db8:1::2

Figure 5: lw4o6 CE Configuration XML

In the example depicted in Figure 5, the interface name is defined for the softwire tunnel. This name is then referenced by the routing configuration for the IPv4 route. Figure 6 provides an example configuration for the CE's IPv4 routing using the YANG module described in [RFC8349].

```
<config xmlns="urn:ietf:params:xml:ns:netconf:base:1.0">
  <routing xmlns="urn:ietf:params:xml:ns:yang:ietf-routing">
    <control-plane-protocols>
      <control-plane-protocol>
        <type>static</type>
        <name>v4</name>
        <static-routes>
          <ipv4
          xmlns="urn:ietf:params:xml:ns:yang:ietf-ipv4-unicas\
          t-routing">
            <route>
              <destination-prefix>0.0.0/0</destination-prefix>
              <next-hop>
                <outgoing-interface>lw4o6-wan</outgoing-interface>
              </next-hop>
            </route>
          </ipv4>
        </static-routes>
      </control-plane-protocol>
    </control-plane-protocols>
 </routing>
</config>
```

Figure 6: lw4o6 CE Routing Configuration XML

Figure 7 provides an example configuration for the CE's NAPT44 function using the YANG module described in [RFC8512].

```
<config xmlns="urn:ietf:params:xml:ns:netconf:base:1.0">
 <nat xmlns="urn:ietf:params:xml:ns:yang:ietf-nat">
  <instances>
    <instance>
      <id>1</id>
       <policy>
       <policy-id>1</policy-id>
       <external-ip-address-pool>
         <pool-id>1</pool-id>
         <external-ip-pool>192.0.2.1</external-ip-pool>
       </external-ip-address-pool>
       <port-set-restrict>
         <port-set-algo>
           <psid-offset>6</psid-offset>
           <psid-len>8</psid-len>
           <psid>52</psid>
         </port-set-algo>
       </port-set-restrict>
       <notify-pool-usage>
         <pool-id>1</pool-id>
         <high-threshold>80</high-threshold>
       </notify-pool-usage>
       </policy>
       <mapping-limits>
        <limit-per-protocol>
cprotocol-id>
         imit>8</limit>
         </limit-per-protocol>
         <limit-per-protocol>
         cprotocol-id>6
         imit>32</limit>
         </limit-per-protocol>
         <limit-per-protocol>
         col-id>17
         imit>16</limit>
         </limit-per-protocol>
        </mapping-limits>
       <mapping-table>
         <mapping-entry>
           <index>1</index>
           <external-src-address>
             192.0.2.1/32
           </external-src-address>
           <internal-src-address>
              192.168.1.0/24
           </internal-src-address>
           <transport-protocol>6</transport-protocol>
         </mapping-entry>
         <mapping-entry>
           <index>2</index>
           <external-src-address>
             192.0.2.1/32
           </external-src-address>
           <internal-src-address>
             192.168.1.0/24
           </internal-src-address>
           <transport-protocol>17</transport-protocol>
```

```
</mapping-entry>
          <mapping-entry>
            <index>3</index>
            <external-src-address>
              192.0.2.1/32
            </external-src-address>
            <internal-src-address>
              192.168.1.0/24
            </internal-src-address>
            <transport-protocol>1</transport-protocol>
          </mapping-entry>
        </mapping-table>
      </instance>
    </instances>
  </nat>
</config>
```

Figure 7: lw4o6 NAT Configuration XML

Acknowledgements

The authors would like to thank Lishan Li, Bert Wijnen, Giles Heron, Ole Troan, Andy Wingo, and Leo Tietz for their contributions to this work.

Thanks to Sheng Jiang for the review.

Special thanks to Tom Petch and Martin Bjorklund for the detailed review and suggestions.

Contributors

The following individuals are co-authors:

```
Yong Cui
Tsinghua University
China
Phone: +86-10-6260-3059
Email: cuiyong@tsinghua.edu.cn

Qi Sun
Tsinghua University
China
Phone: +86-10-6278-5822
Email: sunqi.ietf@gmail.com

Linhui Sun
Tsinghua University
China
Phone: +86-10-6278-5822
Email: lh.sunlinh@gmail.com
```

Sladjana Zechlin Deutsche Telekom AG

Germany

Email: sladjana.zechlin@telekom.de

Rajiv Asati Cisco Systems, Inc. United States of America Email: Rajiva@cisco.com

Hao Wang Tsinghua University

China

Phone: +86-10-6278-5822

Email: wangh13@mails.tsinghua.edu.cn

Authors' Addresses

Ian Farrer (EDITOR)

Deutsche Telekom AG CTO-ATI, Landgrabenweg 151 53227 Bonn

Germany

Email: ian.farrer@telekom.de

Mohamed Boucadair (EDITOR)

Orange 35000 Rennes France

Email: mohamed.boucadair@orange.com