Network Working Group Request for Comments: 2128 Category: Standards Track G. Roeck, Editor cisco Systems March 1997

Dial Control Management Information Base using SMIv2

## Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

#### Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects used for managing demand access circuits, including ISDN.

This document specifies a MIB module in a manner that is compliant to the SNMPv2 SMI. The set of objects is consistent with the SNMP framework and existing SNMP standards.

This document is a product of the ISDN MIB working group within the Internet Engineering Task Force. Comments are solicited and should be addressed to the working group's mailing list at isdn-mib@cisco.com and/or the author.

## Table of Contents

| 1 The SNMPv2 Network Management Framework | 2  |
|---|----|
| 1.1 Object Definitions                    | 2  |
| 2 Overview                                | 2  |
| 2.1 Structure of MIB                      | 2  |
| 2.2 Relationship to the Interfaces MIB    | 3  |
| 2.2.1 Layering Model and Virtual Circuits | 3  |
| 2.2.2 ifTestTable                         | 4  |
| 2.2.3 ifRcvAddressTable                   | 4  |
| 2.2.3.1 ifEntry for a single peer         | 5  |
| 2.3 Multilink and backup line support     | 5  |
| 2.4 Support for generic peers             | 5  |
| 3 Definitions                             | 6  |
| 3.1 Dial Control MIB                      | 6  |
| 4 Acknowledgments                         | 32 |
| 5 References                              | 33 |

Roeck Standards Track [Page 1]

| 6 | Security | Considerations | 33 |
|---|----------|----------------|----|
| 7 | Author's | Address        | 34 |

#### 1. The SNMPv2 Network Management Framework

The SNMPv2 Network Management Framework presently consists of three major components. They are:

- o the SMI, described in RFC 1902 [1] the mechanisms used for describing and naming objects for the purpose of management.
- o the MIB-II, STD 17, RFC 1213 [2] the core set of managed objects for the Internet suite of protocols.
- o the protocol, STD 15, RFC 1157 [3] and/or RFC 1905 [4], the protocol for accessing managed objects.

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

## 1.1. Object Definitions

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) defined in the SMI. In particular, each object type is named by an OBJECT IDENTIFIER, an administratively assigned name. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the descriptor, to refer to the object type.

#### 2. Overview

#### 2.1. Structure of MIB

Managing demand access circuits requires the following groups of information:

- o General configuration information.
- Information to describe peer configuration and peer statistics. In this respect, peer configuration means information on how to connect to peers on outgoing calls, how to identify peers on incoming calls, and other call related configuration information.
- o Information to store active call information.

Roeck Standards Track [Page 2]

o Information to retain call history.

The MIB, therefore, is structured into four groups.

- o The dialCtlConfiguration group is used to specify general configuration information.
- o The dialCtlPeer group is used to describe peer configuration and peer statistics.
- o The callActive group is used to store active call information.
- The callHistory group is used to store call history information. These calls could be circuit switched or they could be virtual circuits. History of each and every call is stored, of successful calls as well as unsuccessful and rejected calls. An entry will be created when a call is cleared.

## 2.2. Relationship to the Interfaces MIB

This section clarifies the relationship of this MIB to the Interfaces MIB [8]. Several areas of correlation are addressed in the following subsections. The implementor is referred to the Interfaces MIB document in order to understand the general intent of these areas.

## 2.2.1. Layering Model and Virtual Circuits


On an occasional access channel, there are a number of peer systems that are permitted to call or be called, all of which need to be treated as active from a routing viewpoint, but most of which have no call in progress at any given time.

On dialup interfaces, this is further complicated by the fact that calls to a given peer float from channel to channel. One cannot definitively say "I call this peer on that interface." It is necessary, therefore, to provide a mapping algorithm between the low-level interfaces, and the various logical interfaces supporting the peers. This is solved by creating a logical interface (ifEntry) for each peer and a logical interface (ifEntry) for each low-level interface. These are then correlated using the ifStackTable.

The low-level interfaces are either physical interfaces, e.g. modem interfaces, or logical interfaces, e.g. ISDN B channels, which then in turn are layered on top of physical ISDN interfaces.

Roeck Standards Track [Page 3]

The model, therefore, looks something like this, taking ISDN as an example:



Mapping of IP interfaces to Called Peers to B Channels

If Entries are maintained for each peer.

In this model, each peer is required to have an associated encapsulation layer interface. This interface can be of any kind, e.g. PPP or LAPB.

In order to specify the network address for a given peer, one would then usually add a routing/forwarding table entry, pointing to the encapsulation layer interface through which this peer can be reached.

## 2.2.2. ifTestTable

The ifTestTable usage is defined in the MIBs defining the encapsulation below the network layer. For example, if PPP encapsulation is being used, the ifTestTable is defined by PPP.

# 2.2.3. ifRcvAddressTable

The ifRcvAddressTable usage is defined in the MIBs defining the encapsulation below the network layer. For example, if PPP encapsulation is being used, the ifRcvAddressTable is defined by PPP.

Roeck Standards Track [Page 4]

## 2.2.3.1. if Entry for a single peer

IfEntries are defined in the MIBs defining the encapsulation below the network layer. For example, if PPP encapsulation is being used, the ifEntry is defined by PPP.

ifEntries will never be created by the Dial Control MIB. The Dial Control MIB always depends on some other ifIndex of some set of ifTypes. That is, to create an entry in the Dial Control MIB, the base ifEntry must already have been created through some other mechanism.

The Dial Control entry does have its own RowStatus, permitting the Dial Control supplementary information to come and go, but not otherwise disturbing the ifIndex to which it is attached. If in a given implementation the two are tightly bound, deleting the ifEntry may have the side effect of deleting the Dial Control entry.

## 2.3. Multilink and backup line support

In order to support multilink and backup procedures, there may be several entries for a single peer in the dialCtlPeerCfgTable.

A single peer is identified using the dialCtlPeerCfgId object of the dialCtlPeerCfgTable. There may be several entries in dialCtlPeerCfgTable with the same value of dialCtlPeerCfgId, but different ifIndex values. Each of those entries will then describe a possible connection to the same peer. Such entries can then be used to handle multilink as well as backup procedures, e.g. by bundling the attached ifEntries using PPP multilink.

# 2.4. Support for generic peers

Generic peers can for example be supported by permitting wild-card characters (e.g., '?' or '\*') in dialCtlPeerCfgAnswerAddress. A number to be accepted could then be defined as partly (e.g., '\*1234') or entirely generic (e.g., '\*').

A detailed specification of such a functionality is outside the scope of this document.

However, the implementor should be aware that supporting generic peers may cause a security hole. The user would not know where a call is from, which could potentially allow unauthorized access.

Roeck Standards Track [Page 5]

```
3. Definitions
3.1. Dial Control MIB
DIAL-CONTROL-MIB DEFINITIONS ::= BEGIN
IMPORTS
        MODULE-IDENTITY,
        NOTIFICATION-TYPE,
        OBJECT-TYPE,
        Unsigned32
                FROM SNMPv2-SMI
        TEXTUAL-CONVENTION,
        DisplayString,
        TimeStamp,
        RowStatus
                 FROM SNMPv2-TC
        MODULE-COMPLIANCE,
        OBJECT-GROUP,
        NOTIFICATION-GROUP
                FROM SNMPv2-CONF
        IANAifType
                FROM IANAifType-MIB
        ifOperStatus,
        ifIndex,
        InterfaceIndex,
        InterfaceIndexOrZero
                FROM IF-MIB
        transmission
                FROM RFC1213-MIB;
dialControlMib MODULE-IDENTITY
        LAST-UPDATED "9609231544Z" -- Sep 23, 1996 ORGANIZATION "IETF ISDN Working Group"
        CONTACT-INFO
                    Guenter Roeck
             Postal: cisco Systems
                      170 West Tasman Drive
                      San Jose, CA 95134
                      U.S.A.
             Phone: +1 408 527 3143
             E-mail: groeck@cisco.com"
        DESCRIPTION
             "The MIB module to describe peer information for
             demand access and possibly other kinds of interfaces."
        ::= { transmission 21 }
AbsoluteCounter32 ::= TEXTUAL-CONVENTION
```

Roeck Standards Track [Page 6]

```
STATUS
               current
       DESCRIPTION
            "Represents a Counter32-like value that starts at zero,
             does not decrease, and does not wrap. This may be used
             only in situations where wrapping is not possible or
             extremely unlikely. Should such a counter overflow,
             it locks at the maxium value of 4,294,967,295.
             The primary use of this type of counter is situations
             where a counter value is to be recorded as history
             and is thus no longer subject to reading for changing
             values."
        SYNTAX
                   Unsigned32
-- Dial Control Mib objects definitions
dialControlMibObjects OBJECT IDENTIFIER ::= { dialControlMib 1 }
-- General configuration group
dialCtlConfiguration OBJECT IDENTIFIER ::= { dialControlMibObjects 1 }
-- general configuration data/parameters
dialCtlAcceptMode OBJECT-TYPE
       SYNTAX INTEGER {
           acceptNone(1),
           acceptAll(2),
           acceptKnown(3)
        }
       MAX-ACCESS read-write
        STATUS
                   current
        DESCRIPTION
            "The security level for acceptance of incoming calls.
            acceptNone(1) - incoming calls will not be accepted
             acceptAll(2) - incoming calls will be accepted,
                             even if there is no matching entry
                             in the dialCtlPeerCfgTable
             acceptKnown(3) - incoming calls will be accepted only
                             if there is a matching entry in the
                              dialCtlPeerCfgTable
        ::= { dialCtlConfiguration 1 }
dialCtlTrapEnable OBJECT-TYPE
        SYNTAX INTEGER {
           enabled(1),
           disabled(2)
```

Roeck Standards Track [Page 7]

```
MAX-ACCESS read-write
                              STATUS current
                              DESCRIPTION
                                              "This object indicates whether dialCtlPeerCallInformation
                                                 and dialCtlPeerCallSetup traps should be generated for
                                                 all peers. If the value of this object is enabled(1),
                                                 traps will be generated for all peers. If the value
                                                 of this object is disabled(2), traps will be generated
                                                 only for peers having dialCtlPeerCfgTrapEnable set
                                                 to enabled(1)."
                                                                 { disabled }
                              ::= { dialCtlConfiguration 2 }
-- Peer group
dialCtlPeer OBJECT IDENTIFIER ::= { dialControlMibObjects 2 }
-- peer configuration table
dialCtlPeerCfgTable OBJECT-TYPE
                              SYNTAX SEQUENCE OF DialCtlPeerCfgEntry
                              MAX-ACCESS not-accessible
                              STATUS current
                              DESCRIPTION
                                              "The list of peers from which the managed device
                                                will accept calls or to which it will place them."
                           ::= { dialCtlPeer 1 }
dialCtlPeerCfgEntry OBJECT-TYPE
                              SYNTAX
                                                                      DialCtlPeerCfgEntry
                              MAX-ACCESS not-accessible
                              STATUS
                                                                          current
                              DESCRIPTION
                                             "Configuration data for a single Peer. This entry is
                                                 effectively permanent, and contains information
                                                 to identify the peer, how to connect to the peer,
                                                 how to identify the peer and its permissions.
                                                 The value of dialCtlPeerCfgOriginateAddress must be
                                                 specified before a new row in this table can become
                                                 active(1). Any writeable parameters in an existing entry
                                                 can be modified while the entry is active. The modification % \left( 1\right) =\left( 1\right) +\left( 1\right)
                                                 will take effect when the peer in question will be
                                                 called the next time.
                                                 An entry in this table can only be created if the
                                                associated if Entry already exists."
                                                                         { dialCtlPeerCfgId, ifIndex }
                              TNDEX
```

Roeck Standards Track [Page 8]

```
::= { dialCtlPeerCfgTable 1 }
DialCtlPeerCfgEntry ::= SEQUENCE {
             dialCtlPeerCfqId
                                                  INTEGER,
             dialCtlPeerCfgIfType
                                                  IANAifType,
             dialCtlPeerCfgLowerIf
                                                  InterfaceIndexOrZero,
             dialCtlPeerCfgOriginateAddress DisplayString,
             dialCtlPeerCfgAnswerAddress DisplayString,
dialCtlPeerCfgSubAddress DisplayString,
dialCtlPeerCfgClosedUserGroup DisplayString,
             dialCtlPeerCfgSpeed
                                                  INTEGER,
             dialCtlPeerCfgInfoType INTEGER,
dialCtlPeerCfgPermission INTEGER,
dialCtlPeerCfgInactivityTimer INTEGER,
dialCtlPeerCfgMinDuration INTEGER,
dialCtlPeerCfgMayDuration INTEGER,
             dialCtlPeerCfqMaxDuration
                                                   INTEGER,
             dialCtlPeerCfgCarrierDelay
                                                  INTEGER,
             dialCtlPeerCfgCallRetries
                                                  INTEGER,
             dialCtlPeerCfgRetryDelay
dialCtlPeerCfgFailureDelay
INTEGER,
INTEGER,
             dialCtlPeerCfgTrapEnable
             dialCtlPeerCfgStatus
                                                  RowStatus
         }
dialCtlPeerCfgId OBJECT-TYPE
         SYNTAX INTEGER (1..2147483647)
         MAX-ACCESS not-accessible
         STATUS current
         DESCRIPTION
              "This object identifies a single peer. There may
              be several entries in this table for one peer,
               defining different ways of reaching this peer.
               Thus, there may be several entries in this table
               with the same value of dialCtlPeerCfgId.
               Multiple entries for one peer may be used to support
               multilink as well as backup lines.
               A single peer will be identified by a unique value
               of this object. Several entries for one peer MUST
               have the same value of dialCtlPeerCfqId, but different
               if Entries and thus different values of if Index."
         ::= { dialCtlPeerCfgEntry 1 }
dialCtlPeerCfgIfType OBJECT-TYPE
         SYNTAX IANAifType
         MAX-ACCESS read-create
         STATUS current
         DESCRIPTION
              "The interface type to be used for calling this peer.
```

Roeck Standards Track [Page 9]

```
In case of ISDN, the value of isdn(63) is to be used."
       DEFVAL { other }
        ::= { dialCtlPeerCfgEntry 2 }
dialCtlPeerCfgLowerIf OBJECT-TYPE
        SYNTAX
                 InterfaceIndexOrZero
       MAX-ACCESS read-create
        STATUS current
        DESCRIPTION
            "ifIndex value of an interface the peer will have to be
            called on. For example, on an ISDN interface, this can be
            the ifIndex value of a D channel or the ifIndex value of a
            B channel, whatever is appropriate for a given peer.
            As an example, for Basic Rate leased lines it will be
            necessary to specify a B channel if Index, while for
            semi-permanent connections the D channel ifIndex has
            to be specified.
            If the interface can be dynamically assigned, this object
            has a value of zero."
        DEFVAL { 0 }
        ::= { dialCtlPeerCfgEntry 3 }
dialCtlPeerCfgOriginateAddress OBJECT-TYPE
        SYNTAX DisplayString
       MAX-ACCESS read-create
        STATUS
               current
        DESCRIPTION
            "Call Address at which the peer will be called.
            Think of this as the set of characters following 'ATDT'
            or the 'phone number' included in a D channel call request.
            The structure of this information will be switch type
             specific. If there is no address information required
             for reaching the peer, i.e., for leased lines,
            this object will be a zero length string."
        ::= { dialCtlPeerCfgEntry 4 }
dialCtlPeerCfgAnswerAddress OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-create
        STATUS
                   current
        DESCRIPTION
            "Calling Party Number information element, as for example
            passed in an ISDN SETUP message by a PBX or switch,
            for incoming calls.
            This address can be used to identify the peer.
            If this address is either unknown or identical
            to dialCtlPeerCfgOriginateAddress, this object will be
```

Roeck Standards Track [Page 10]

```
a zero length string."
       DEFVAL { "" }
       ::= { dialCtlPeerCfgEntry 5 }
dialCtlPeerCfgSubAddress OBJECT-TYPE
       SYNTAX
               DisplayString
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "Subaddress at which the peer will be called.
            If the subaddress is undefined for the given media or
           unused, this is a zero length string."
       DEFVAL { "" }
       ::= { dialCtlPeerCfgEntry 6 }
dialCtlPeerCfgClosedUserGroup OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-create
                  current
       STATUS
       DESCRIPTION
           "Closed User Group at which the peer will be called.
            If the Closed User Group is undefined for the given media
            or unused, this is a zero length string."
       REFERENCE
           "Q.931, chapter 4.6.1."
       DEFVAL { "" }
       ::= { dialCtlPeerCfgEntry 7 }
dialCtlPeerCfgSpeed OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-create
       STATUS
                   current
       DESCRIPTION
           "The desired information transfer speed in bits/second
            when calling this peer.
            The detailed media specific information, e.g. information
            type and information transfer rate for ISDN circuits,
            has to be extracted from this object.
            If the transfer speed to be used is unknown or the default
            speed for this type of interfaces, the value of this object
            may be zero."
                { 0 }
       ::= { dialCtlPeerCfgEntry 8 }
dialCtlPeerCfgInfoType OBJECT-TYPE
       SYNTAX INTEGER {
           other(1),
           speech(2),
```

Roeck Standards Track [Page 11]

```
unrestrictedDigital(3),
                                     -- 64k/s data
           unrestrictedDigital56(4), -- with 56k rate adaption
           restrictedDigital(5),
                                      -- 3.1 kHz audio
           audio31(6),
                                      -- 7 kHz audio
           audio7(7),
           video(8),
           packetSwitched(9),
           fax(10)
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "The Information Transfer Capability to be used when
            calling this peer.
            speech(2) refers to a non-data connection, whereas
            audio31(6) and audio7(7) refer to data mode
            connections."
       DEFVAL { other }
        ::= { dialCtlPeerCfgEntry 9 }
dialCtlPeerCfgPermission OBJECT-TYPE
       SYNTAX INTEGER {
           originate(1),
           answer(2),
           both(3),
                                -- both originate & answer
           callback(4),
           none(5)
        }
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "Applicable permissions. callback(4) either rejects the
            call and then calls back, or uses the 'Reverse charging'
            information element if it is available.
            Note that callback(4) is supposed to control charging, not
            security, and applies to callback prior to accepting a
            call. Callback for security reasons can be handled using
            PPP callback."
                   { both }
       DEFVAL
        ::= { dialCtlPeerCfgEntry 10 }
dialCtlPeerCfgInactivityTimer OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       UNITS
                   "seconds"
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
```

Roeck Standards Track [Page 12]

```
"The connection will be automatically disconnected
            if no longer carrying useful data for a time
            period, in seconds, specified in this object.
            Useful data in this context refers to forwarding
            packets, including routing information; it
            excludes the encapsulator maintenance frames.
            A value of zero means the connection will not be
            automatically taken down due to inactivity,
            which implies that it is a dedicated circuit."
       DEFVAL
                   { 0 }
        ::= { dialCtlPeerCfgEntry 11 }
dialCtlPeerCfgMinDuration OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-create
       STATUS
                   current
       DESCRIPTION
            "Minimum duration of a call in seconds, starting from the
            time the call is connected until the call is disconnected.
            This is to accomplish the fact that in most countries
            charging applies to units of time, which should be matched
            as closely as possible."
       DEFVAL
                   { 0 }
        ::= { dialCtlPeerCfgEntry 12 }
dialCtlPeerCfgMaxDuration OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "Maximum call duration in seconds. Zero means 'unlimited'."
       DEFVAL { 0 }
        ::= { dialCtlPeerCfgEntry 13 }
dialCtlPeerCfgCarrierDelay OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       UNITS
                   "seconds"
       MAX-ACCESS read-create
       STATUS
               current
       DESCRIPTION
            "The call timeout time in seconds. The default value
            of zero means that the call timeout as specified for
            the media in question will apply."
                 { 0 }
        ::= { dialCtlPeerCfgEntry 14 }
dialCtlPeerCfqCallRetries OBJECT-TYPE
       SYNTAX
                  INTEGER (0..2147483647)
```

Roeck Standards Track [Page 13]

```
MAX-ACCESS read-create
        STATUS current
        DESCRIPTION
            "The number of calls to a non-responding address
            that may be made. A retry count of zero means
            there is no bound. The intent is to bound
            the number of successive calls to an address
            which is inaccessible, or which refuses those calls.
            Some countries regulate the number of call retries
            to a given peer that can be made."
                 { 0 }
        ::= { dialCtlPeerCfgEntry 15 }
dialCtlPeerCfgRetryDelay OBJECT-TYPE
        SYNTAX INTEGER (0..2147483647)
        UNITS
                   "seconds"
       MAX-ACCESS read-create
        STATUS
                   current
        DESCRIPTION
            "The time in seconds between call retries if a peer
            cannot be reached.
            A value of zero means that call retries may be done
            without any delay."
                 { 0 }
        ::= { dialCtlPeerCfgEntry 16 }
dialCtlPeerCfgFailureDelay OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
        UNITS
                   "seconds"
       MAX-ACCESS read-create
        STATUS
                   current
        DESCRIPTION
            "The time in seconds after which call attempts are
            to be placed again after a peer has been noticed
            to be unreachable, i.e. after dialCtlPeerCfgCallRetries
            unsuccessful call attempts.
            A value of zero means that a peer will not be called
            again after dialCtlPeerCfgCallRetries unsuccessful call
            attempts."
       DEFVAL { 0 }
        ::= { dialCtlPeerCfgEntry 17 }
dialCtlPeerCfgTrapEnable OBJECT-TYPE
        SYNTAX INTEGER {
           enabled(1),
           disabled(2)
        }
```

Roeck Standards Track [Page 14]

```
MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "This object indicates whether dialCtlPeerCallInformation
            and dialCtlPeerCallSetup traps should be generated for
            this peer."
       DEFVAL { disabled }
        ::= { dialCtlPeerCfgEntry 18 }
dialCtlPeerCfgStatus OBJECT-TYPE
       SYNTAX RowStatus
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
           "Status of one row in this table."
        ::= { dialCtlPeerCfgEntry 19 }
-- Peer statistics table
dialCtlPeerStatsTable OBJECT-TYPE
       SYNTAX SEQUENCE OF DialCtlPeerStatsEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
           "Statistics information for each peer entry.
            There will be one entry in this table for each entry
            in the dialCtlPeerCfgTable."
       ::= { dialCtlPeer 2 }
dialCtlPeerStatsEntry OBJECT-TYPE
       SYNTAX DialCtlPeerStatsEntry
       MAX-ACCESS not-accessible
                  current
       STATUS
       DESCRIPTION
           "Statistics information for a single Peer. This entry
            is effectively permanent, and contains information
            describing the last call attempt as well as supplying
            statistical information."
       AUGMENTS { dialCtlPeerCfgEntry }
      ::= { dialCtlPeerStatsTable 1 }
DialCtlPeerStatsEntry ::=
       SEQUENCE {
                                        AbsoluteCounter32,
           dialCtlPeerStatsConnectTime
           dialCtlPeerStatsChargedUnits
                                             AbsoluteCounter32,
           dialCtlPeerStatsSuccessCalls
                                             AbsoluteCounter32,
           dialCtlPeerStatsFailCalls
                                             AbsoluteCounter32,
           dialCtlPeerStatsAcceptCalls
                                             AbsoluteCounter32,
```

```
AbsoluteCounter32,
           dialCtlPeerStatsRefuseCalls
           dialCtlPeerStatsLastDisconnectCause OCTET STRING,
           dialCtlPeerStatsLastDisconnectText DisplayString,
           dialCtlPeerStatsLastSetupTime
                                             TimeStamp
        }
dialCtlPeerStatsConnectTime OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       UNITS
                   "seconds"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "Accumulated connect time to the peer since system startup.
            This is the total connect time, i.e. the connect time
            for outgoing calls plus the time for incoming calls."
        ::= { dialCtlPeerStatsEntry 1 }
dialCtlPeerStatsChargedUnits OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The total number of charging units applying to this
            peer since system startup.
            Only the charging units applying to the local interface,
            i.e. for originated calls or for calls with 'Reverse
            charging' being active, will be counted here."
        ::= { dialCtlPeerStatsEntry 2 }
dialCtlPeerStatsSuccessCalls OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS
                  current
       DESCRIPTION
           "Number of completed calls to this peer."
        ::= { dialCtlPeerStatsEntry 3 }
dialCtlPeerStatsFailCalls OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of failed call attempts to this peer since system
            startup."
        ::= { dialCtlPeerStatsEntry 4 }
dialCtlPeerStatsAcceptCalls OBJECT-TYPE
       SYNTAX
                 AbsoluteCounter32
```

Roeck Standards Track [Page 16]

```
MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of calls from this peer accepted since system
            startup."
        ::= { dialCtlPeerStatsEntry 5 }
dialCtlPeerStatsRefuseCalls OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of calls from this peer refused since system
            startup."
        ::= { dialCtlPeerStatsEntry 6 }
dialCtlPeerStatsLastDisconnectCause OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE (0..4))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The encoded network cause value associated with the last
            call.
            This object will be updated whenever a call is started
            The value of this object will depend on the interface type
            as well as on the protocol and protocol version being
            used on this interface. Some references for possible cause
            values are given below."
       REFERENCE
            "- Bellcore SR-NWT-001953, Generic Guidelines for
              ISDN Terminal Equipment On Basic Access Interfaces,
              chapter 5.2.5.8.
            - Bellcore SR-NWT-002343, ISDN Primary Rate Interface
              Generic Guidelines for Customer Premises Equipment,
              chapter 8.2.5.8.
            - ITU-T Q.931, Appendix I.
            - ITU-T X.25, CAUSE and DIAGNOSTIC field values.
            - German Telekom FTZ 1TR6, chapter 3.2.3.4.4.4."
        ::= { dialCtlPeerStatsEntry 7 }
dialCtlPeerStatsLastDisconnectText OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-only
       STATUS current
            "ASCII text describing the reason for the last call
            termination.
```

Roeck Standards Track [Page 17]

```
This object exists because it would be impossible for
            a management station to store all possible cause values
            for all types of interfaces. It should be used only if
            a management station is unable to decode the value of
            dialCtlPeerStatsLastDisconnectCause.
            This object will be updated whenever a call is started
            or cleared."
        ::= { dialCtlPeerStatsEntry 8 }
dialCtlPeerStatsLastSetupTime OBJECT-TYPE
        SYNTAX
                 TimeStamp
       MAX-ACCESS read-only
       STATUS
                   current
       DESCRIPTION
            "The value of sysUpTime when the last call to this peer
            was started.
            For ISDN media, this will be the time when the setup
            message was received from or sent to the network.
            This object will be updated whenever a call is started
            or cleared."
        ::= { dialCtlPeerStatsEntry 9 }
-- the active call group
callActive OBJECT IDENTIFIER ::= { dialControlMibObjects 3 }
-- callActiveTable
-- Table to store active call information.
-- These calls could be circuit switched or they could
-- be virtual circuits.
-- An entry will be created when a call is started and deleted
-- when a call is cleared.
callActiveTable OBJECT-TYPE
       SYNTAX SEQUENCE OF CallActiveEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "A table containing information about active
            calls to a specific destination."
        ::= { callActive 1 }
callActiveEntry OBJECT-TYPE
       SYNTAX CallActiveEntry
       MAX-ACCESS not-accessible
```

Roeck Standards Track [Page 18]

```
STATUS current
       DESCRIPTION
           "The information regarding a single active Connection.
            An entry in this table will be created when a call is
            started. An entry in this table will be deleted when
            an active call clears."
        INDEX { callActiveSetupTime, callActiveIndex }
        ::= { callActiveTable 1 }
CallActiveEntry ::=
        SEQUENCE {
            callActiveSetupTime
                                                TimeStamp,
            callActiveIndex
                                                 INTEGER,
            callActivePeerAddress
                                                DisplayString,
            callActivePeerSubAddress
                                                DisplayString,
            callActivePeerId
                                                 INTEGER,
            callActivePeerIfIndex
                                                INTEGER,
           callActiveLogicalIfIndex
                                                InterfaceIndexOrZero,
            callActiveConnectTime
                                                TimeStamp,
            callActiveCallState
                                                INTEGER,
           callActiveCallOrigin
                                               INTEGER,
           {\tt callActiveChargedUnits}
                                               AbsoluteCounter32,
           callActiveInfoType
                                                INTEGER,
           callActiveTransmitPackets
callActiveTransmitBytes
callActiveReceivePackets
                                                AbsoluteCounter32,
                                               AbsoluteCounter32,
                                               AbsoluteCounter32,
           callActiveReceiveBytes
                                               AbsoluteCounter32
        }
callActiveSetupTime OBJECT-TYPE
        SYNTAX TimeStamp
       MAX-ACCESS not-accessible
                   current
        DESCRIPTION
            "The value of sysUpTime when the call associated to this
            entry was started. This will be useful for an NMS to
            retrieve all calls after a specific time. Also, this object
            can be useful in finding large delays between the time the
             call was started and the time the call was connected.
             For ISDN media, this will be the time when the setup
             message was received from or sent to the network."
        ::= { callActiveEntry 1 }
callActiveIndex OBJECT-TYPE
        SYNTAX INTEGER (1..'7ffffffff'h)
       MAX-ACCESS not-accessible
       STATUS
                  current
```

Roeck Standards Track [Page 19]

```
DESCRIPTION
           "Small index variable to distinguish calls that start in
            the same hundredth of a second."
        ::= { callActiveEntry 2 }
callActivePeerAddress OBJECT-TYPE
       SYNTAX DisplayString MAX-ACCESS read-only
               current
       STATUS
       DESCRIPTION
            "The number this call is connected to. If the number is
            not available, then it will have a length of zero."
        ::= { callActiveEntry 3 }
callActivePeerSubAddress OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The subaddress this call is connected to. If the subaddress
            is undefined or not available, this will be a zero length
            string."
        ::= { callActiveEntry 4 }
callActivePeerId OBJECT-TYPE
        SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "This is the Id value of the peer table entry
            to which this call was made. If a peer table entry
            for this call does not exist or is unknown, the value
            of this object will be zero."
        ::= { callActiveEntry 5 }
callActivePeerIfIndex OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-only
               current
       STATUS
       DESCRIPTION
            "This is the ifIndex value of the peer table entry
            to which this call was made. If a peer table entry
            for this call does not exist or is unknown, the value
            of this object will be zero."
        ::= { callActiveEntry 6 }
callActiveLogicalIfIndex OBJECT-TYPE
       SYNTAX
                  InterfaceIndexOrZero
```

Roeck Standards Track [Page 20]

```
MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "This is the ifIndex value of the logical interface through
            which this call was made. For ISDN media, this would be
            the ifIndex of the B channel which was used for this call.
            If the ifIndex value is unknown, the value of this object
            will be zero."
        ::= { callActiveEntry 7 }
callActiveConnectTime OBJECT-TYPE
       SYNTAX TimeStamp
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The value of sysUpTime when the call was connected.
            If the call is not connected, this object will have a
            value of zero."
       ::= { callActiveEntry 8 }
callActiveCallState OBJECT-TYPE
       SYNTAX INTEGER {
           unknown(1),
           connecting(2),
           connected(3),
           active(4)
       }
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The current call state.
                        - The call state is unknown.
            unknown(1)
            connecting(2) - A connection attempt (outgoing call)
                            is being made.
            connected(3) - An incoming call is in the process
                            of validation.
            active(4) - The call is active.
        ::= { callActiveEntry 9 }
callActiveCallOrigin OBJECT-TYPE
       SYNTAX INTEGER {
           originate(1),
           answer(2),
           callback(3)
       }
       MAX-ACCESS read-only
       STATUS
                  current
```

Roeck Standards Track [Page 21]

```
DESCRIPTION
         "The call origin."
        ::= { callActiveEntry 10 }
callActiveChargedUnits OBJECT-TYPE
       SYNTAX
                AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The number of charged units for this connection.
            For incoming calls or if charging information is
            not supplied by the switch, the value of this object
            will be zero."
        ::= { callActiveEntry 11 }
callActiveInfoType OBJECT-TYPE
       SYNTAX INTEGER {
           other(1),
                                      -- e.g. for non-isdn media
           speech(2),
           unrestrictedDigital(3),
                                     -- 64k/s data
           unrestrictedDigital56(4), -- with 56k rate adaption
           restrictedDigital(5),
                                      -- 3.1 kHz audio
           audio31(6),
                                      -- 7 kHz audio
           audio7(7),
           video(8),
           packetSwitched(9),
           fax(10)
       }
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The information type for this call."
        ::= { callActiveEntry 12 }
callActiveTransmitPackets OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
               current
       DESCRIPTION
           "The number of packets which were transmitted for this
            call."
        ::= { callActiveEntry 13 }
callActiveTransmitBytes OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
```

Roeck Standards Track [Page 22]

```
"The number of bytes which were transmitted for this
            call."
        ::= { callActiveEntry 14 }
callActiveReceivePackets OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The number of packets which were received for this
            call."
        ::= { callActiveEntry 15 }
callActiveReceiveBytes OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS
                   current
       DESCRIPTION
           "The number of bytes which were received for this call."
        ::= { callActiveEntry 16 }
-- the call history group
callHistory OBJECT IDENTIFIER ::= { dialControlMibObjects 4 }
callHistoryTableMaxLength OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
           "The upper limit on the number of entries that the
            callHistoryTable may contain. A value of 0
            will prevent any history from being retained. When
            this table is full, the oldest entry will be deleted
            and the new one will be created."
        ::= { callHistory 1 }
callHistoryRetainTimer OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
                  "minutes"
       UNITS
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
           "The minimum amount of time that an callHistoryEntry
            will be maintained before being deleted. A value of
            0 will prevent any history from being retained in the
```

Roeck Standards Track [Page 23]

```
callHistoryTable, but will neither prevent callCompletion
            traps being generated nor affect other tables."
        ::= { callHistory 2 }
-- callHistoryTable
-- Table to store the past call information. The Destination number
-- and the call connect and disconnect time, the disconnection cause
-- are stored. These calls could be circuit switched or they could
-- be virtual circuits. History of each and every call is stored,
-- of successful calls as well as of unsuccessful and rejected calls.
-- An entry will be created when a call is cleared.
callHistoryTable OBJECT-TYPE
       SYNTAX SEQUENCE OF CallHistoryEntry
       MAX-ACCESS not-accessible
       STATUS
                  current
       DESCRIPTION
           "A table containing information about specific
            calls to a specific destination."
        ::= { callHistory 3 }
callHistoryEntry OBJECT-TYPE
       SYNTAX CallHistoryEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
           "The information regarding a single Connection."
       INDEX { callActiveSetupTime, callActiveIndex }
        ::= { callHistoryTable 1 }
CallHistoryEntry ::=
       SEQUENCE {
           callHistoryPeerAddress
                                               DisplayString,
           callHistoryPeerSubAddress
                                              DisplayString,
           callHistoryPeerId
                                              INTEGER,
           callHistoryPeerIfIndex
                                              INTEGER,
           callHistoryLogicalIfIndex
                                              InterfaceIndex,
           callHistoryDisconnectCause
                                             OCTET STRING,
           callHistoryDisconnectText
                                              DisplayString,
           callHistoryConnectTime
                                              TimeStamp,
           callHistoryDisconnectTime
                                               TimeStamp,
           callHistoryCallOrigin
                                               INTEGER,
           callHistoryChargedUnits
                                              AbsoluteCounter32,
           callHistoryInfoType
                                              INTEGER,
                                             AbsoluteCounter32,
           callHistoryTransmitPackets
           callHistoryTransmitBytes
                                              AbsoluteCounter32,
           callHistoryReceivePackets
                                              AbsoluteCounter32,
```

```
callHistoryReceiveBytes
                                              AbsoluteCounter32
       }
callHistoryPeerAddress OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The number this call was connected to. If the number is
            not available, then it will have a length of zero."
        ::= { callHistoryEntry 1 }
callHistoryPeerSubAddress OBJECT-TYPE
       SYNTAX DisplayString
       MAX-ACCESS read-only
       STATUS
                  current
       DESCRIPTION
           "The subaddress this call was connected to. If the subaddress
            is undefined or not available, this will be a zero length
            string."
        ::= { callHistoryEntry 2 }
callHistoryPeerId OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-only
       STATUS
               current
       DESCRIPTION
           "This is the Id value of the peer table entry
            to which this call was made. If a peer table entry
            for this call does not exist, the value of this object
            will be zero."
       ::= { callHistoryEntry 3 }
callHistoryPeerIfIndex OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "This is the ifIndex value of the peer table entry
            to which this call was made. If a peer table entry
            for this call does not exist, the value of this object
            will be zero."
        ::= { callHistoryEntry 4 }
callHistoryLogicalIfIndex OBJECT-TYPE
       SYNTAX InterfaceIndex
       MAX-ACCESS read-only
       STATUS
                  current
```

Roeck Standards Track [Page 25]

# DESCRIPTION "This is the ifIndex value of the logical interface through which this call was made. For ISDN media, this would be the ifIndex of the B channel which was used for this call." ::= { callHistoryEntry 5 } callHistoryDisconnectCause OBJECT-TYPE SYNTAX OCTET STRING (SIZE (0..4)) MAX-ACCESS read-only STATUS current DESCRIPTION "The encoded network cause value associated with this call. The value of this object will depend on the interface type as well as on the protocol and protocol version being used on this interface. Some references for possible cause values are given below." REFERENCE "- Bellcore SR-NWT-001953, Generic Guidelines for ISDN Terminal Equipment On Basic Access Interfaces, chapter 5.2.5.8. - Bellcore SR-NWT-002343, ISDN Primary Rate Interface Generic Guidelines for Customer Premises Equipment, chapter 8.2.5.8. - ITU-T Q.931, Appendix I. - ITU-T X.25, CAUSE and DIAGNOSTIC field values. - German Telekom FTZ 1TR6, chapter 3.2.3.4.4.4." ::= { callHistoryEntry 6 } callHistoryDisconnectText OBJECT-TYPE SYNTAX DisplayString MAX-ACCESS read-only STATUS current DESCRIPTION "ASCII text describing the reason for call termination. This object exists because it would be impossible for a management station to store all possible cause values for all types of interfaces. It should be used only if a management station is unable to decode the value of dialCtlPeerStatsLastDisconnectCause." ::= { callHistoryEntry 7 } callHistoryConnectTime OBJECT-TYPE

Roeck Standards Track [Page 26]

SYNTAX TimeStamp
MAX-ACCESS read-only
STATUS current

DESCRIPTION

```
"The value of sysUpTime when the call was connected."
        ::= { callHistoryEntry 8 }
callHistoryDisconnectTime OBJECT-TYPE
       SYNTAX TimeStamp
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The value of sysUpTime when the call was disconnected."
        ::= { callHistoryEntry 9 }
callHistoryCallOrigin OBJECT-TYPE
       SYNTAX INTEGER {
           originate(1),
           answer(2),
           callback(3)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The call origin."
        ::= { callHistoryEntry 10 }
callHistoryChargedUnits OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The number of charged units for this connection.
            For incoming calls or if charging information is
            not supplied by the switch, the value of this object
            will be zero."
        ::= { callHistoryEntry 11 }
callHistoryInfoType OBJECT-TYPE
       SYNTAX
                INTEGER \{
           other(1),
                                      -- e.g. for non-isdn media
           speech(2),
           unrestrictedDigital(3), -- 64k/s data
           unrestrictedDigital56(4), -- with 56k rate adaption
           restrictedDigital(5),
           audio31(6),
                                       -- 3.1 kHz audio
           audio7(7),
                                       -- 7 kHz audio
           video(8),
           packetSwitched(9),
           fax(10)
        }
       MAX-ACCESS read-only
```

Roeck Standards Track [Page 27]

```
STATUS current
       DESCRIPTION
           "The information type for this call."
        ::= { callHistoryEntry 12 }
callHistoryTransmitPackets OBJECT-TYPE
       SYNTAX AbsoluteCounter32 MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of packets which were transmitted while this
            call was active."
        ::= { callHistoryEntry 13 }
callHistoryTransmitBytes OBJECT-TYPE
       SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of bytes which were transmitted while this
            call was active."
        ::= { callHistoryEntry 14 }
callHistoryReceivePackets OBJECT-TYPE
        SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of packets which were received while this
            call was active."
        ::= { callHistoryEntry 15 }
callHistoryReceiveBytes OBJECT-TYPE
        SYNTAX AbsoluteCounter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The number of bytes which were received while this
            call was active."
        ::= { callHistoryEntry 16 }
-- Traps related to Connection management
dialControlMibTrapPrefix OBJECT IDENTIFIER ::= { dialControlMib 2 }
dialControlMibTraps OBJECT IDENTIFIER ::= { dialControlMibTrapPrefix 0 }
dialCtlPeerCallInformation NOTIFICATION-TYPE
       OBJECTS {
```

Roeck Standards Track [Page 28]

```
callHistoryPeerId,
            callHistoryPeerIfIndex,
            callHistoryLogicalIfIndex,
            ifOperStatus,
            callHistoryPeerAddress,
            callHistoryPeerSubAddress,
            callHistoryDisconnectCause,
            callHistoryConnectTime,
            callHistoryDisconnectTime,
            callHistoryInfoType,
            callHistoryCallOrigin
        }
        STATUS
                   current
        DESCRIPTION
            "This trap/inform is sent to the manager whenever
             a successful call clears, or a failed call attempt
             is determined to have ultimately failed. In the
             event that call retry is active, then this is after
             all retry attempts have failed. However, only one such
             trap is sent in between successful call attempts;
             subsequent call attempts result in no trap.
             ifOperStatus will return the operational status of the
             virtual interface associated with the peer to whom
             this call was made to."
     ::= { dialControlMibTraps 1 }
dialCtlPeerCallSetup NOTIFICATION-TYPE
       OBJECTS {
            callActivePeerId,
            callActivePeerIfIndex,
            callActiveLogicalIfIndex,
            ifOperStatus,
            callActivePeerAddress,
            callActivePeerSubAddress,
            callActiveInfoType,
           callActiveCallOrigin
        }
        STATUS
                    current
       DESCRIPTION
            "This trap/inform is sent to the manager whenever
             a call setup message is received or sent.
             ifOperStatus will return the operational status of the
             virtual interface associated with the peer to whom
             this call was made to."
     ::= { dialControlMibTraps 2 }
-- conformance information
```

Roeck Standards Track [Page 29]

```
dialControlMibConformance OBJECT IDENTIFIER ::=
                               { dialControlMib 3 }
dialControlMibCompliances OBJECT IDENTIFIER ::=
                               { dialControlMibConformance 1 }
dialControlMibGroups
                         OBJECT IDENTIFIER ::=
                               { dialControlMibConformance 2 }
-- compliance statements
dialControlMibCompliance MODULE-COMPLIANCE
        STATUS current
        DESCRIPTION
            "The compliance statement for entities which
            implement the DIAL CONTROL MIB"
        MODULE -- this module
        MANDATORY-GROUPS
            { dialControlGroup, callActiveGroup, callHistoryGroup,
              callNotificationsGroup }
        ::= { dialControlMibCompliances 1 }
-- units of conformance
dialControlGroup OBJECT-GROUP
        OBJECTS {
            dialCtlAcceptMode,
            dialCtlTrapEnable,
            dialCtlPeerCfgIfType,
            dialCtlPeerCfgLowerIf,
            dialCtlPeerCfgOriginateAddress,
            dialCtlPeerCfgAnswerAddress,
            dialCtlPeerCfgSubAddress,
            dialCtlPeerCfgClosedUserGroup,
            dialCtlPeerCfgSpeed,
            dialCtlPeerCfgInfoType,
            dialCtlPeerCfgPermission,
            dialCtlPeerCfgInactivityTimer,
            dialCtlPeerCfgMinDuration,
            dialCtlPeerCfgMaxDuration,
            dialCtlPeerCfgCarrierDelay,
            dialCtlPeerCfgCallRetries,
            dialCtlPeerCfgRetryDelay,
            dialCtlPeerCfgFailureDelay,
            dialCtlPeerCfgTrapEnable,
            dialCtlPeerCfgStatus,
            dialCtlPeerStatsConnectTime,
            dialCtlPeerStatsChargedUnits,
            dialCtlPeerStatsSuccessCalls,
            dialCtlPeerStatsFailCalls,
```

Roeck Standards Track [Page 30]

```
dialCtlPeerStatsAcceptCalls,
            dialCtlPeerStatsRefuseCalls,
            dialCtlPeerStatsLastDisconnectCause,
            dialCtlPeerStatsLastDisconnectText,
            dialCtlPeerStatsLastSetupTime
        STATUS
                    current
        DESCRIPTION
            "A collection of objects providing the DIAL CONTROL
             capability."
        ::= { dialControlMibGroups 1 }
callActiveGroup OBJECT-GROUP
        OBJECTS {
            callActivePeerAddress,
            callActivePeerSubAddress,
            callActivePeerId,
            callActivePeerIfIndex,
            callActiveLogicalIfIndex,
            callActiveConnectTime,
            callActiveCallState,
            callActiveCallOrigin,
            callActiveChargedUnits,
            callActiveInfoType,
            callActiveTransmitPackets,
            callActiveTransmitBytes,
            callActiveReceivePackets,
            callActiveReceiveBytes
        }
        STATUS
                   current
        DESCRIPTION
            "A collection of objects providing the active call
             capability."
        ::= { dialControlMibGroups 2 }
callHistoryGroup OBJECT-GROUP
        OBJECTS {
            callHistoryTableMaxLength,
            callHistoryRetainTimer,
            callHistoryPeerAddress,
            callHistoryPeerSubAddress,
            callHistoryPeerId,
            callHistoryPeerIfIndex,
            callHistoryLogicalIfIndex,
            callHistoryDisconnectCause,
            callHistoryDisconnectText,
            callHistoryConnectTime,
            callHistoryDisconnectTime,
```

Roeck Standards Track [Page 31]

```
callHistoryCallOrigin,
            callHistoryChargedUnits,
            callHistoryInfoType,
            callHistoryTransmitPackets,
            callHistoryTransmitBytes,
            callHistoryReceivePackets,
            callHistoryReceiveBytes
        STATUS
                 current
        DESCRIPTION
            "A collection of objects providing the Call History
            capability."
        ::= { dialControlMibGroups 3 }
callNotificationsGroup NOTIFICATION-GROUP
   NOTIFICATIONS { dialCtlPeerCallInformation, dialCtlPeerCallSetup }
    STATUS
                 current
   DESCRIPTION
            "The notifications which a Dial Control MIB entity is
             required to implement."
    ::= { dialControlMibGroups 4 }
```

END

# 4. Acknowledgments

This document was produced by the ISDN MIB Working Group. Special thanks is due to the following persons:

Ed Alcoff Fred Baker Bibek A. Das Ken Grigg Jeffrey T. Johnson Glenn Kime Oliver Korfmacher Kedar Madineni Bill Miskovetz David M. Piscitello Lisa A. Phifer Randy Roberts Hascall H. Sharp Hongchi Shih Robert Snyder Bob Stewart Ron Stoughton James Watt

Roeck Standards Track [Page 32]

#### 5. References

- [1] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Structure of Management Information for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1902, January 1996.
- [2] McCloghrie, K., and M. Rose, Editors, "Management Information Base for Network Management of TCP/IP-based internets: MIB-II", STD 17, RFC 1213, Hughes LAN Systems, Performance Systems International, March 1991.
- [3] Case, J., Fedor, M., Schoffstall, M., and J. Davin, "A Simple Network Management Protocol (SNMP)", STD 15, RFC 1157, SNMP Research, Performance Systems International, MIT Lab for Computer Science, May 1990.
- [4] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Protocol Operations for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1905, January 1996.
- [5] ITU-T Recommendation "Digital subscriber Signalling System No. 1 (DSS 1) - ISDN user-network interface layer 3 specification for basic call control", Rec. Q.931(I.451), March 1993.
- [6] ITU-T Recommendation "Generic procedures for the control of ISDN supplementary services ISDN user-network interface layer 3 specification", Rec. Q.932(I.452).
- [7] ITU-T Recommendation "Digital subscriber Signalling System No. 1 (DSS 1) Signalling specification for frame-mode basic call control", Rec. Q.933.
- [8] McCloghrie, K. and F. Kastenholz, "Evolution of the Interfaces Group of MIB-II", RFC 1573, Hughes LAN Systems, FTP Software, January 1994.
- 6. Security Considerations

Information in this MIB may be used by upper protocol layers for security purpose.

The implementor should be aware that supporting generic peers as described in section 3.4 may cause a security hole. The user would not know where a call is from, which could potentially allow unauthorized access if there is no other authentication scheme, e.g. PPP authentication, available.

Roeck Standards Track [Page 33]

RFC 2128 Dial Control MIB March 1997

# 7. Author's Address

Guenter Roeck cisco Systems 170 West Tasman Drive San Jose, CA 95134 U.S.A.

Phone: +1 408 527 3143 EMail: groeck@cisco.com

Roeck Standards Track [Page 34]