StarPU Handbook

for StarPU 1.3.2

This manual documents the usage of StarPU version 1.3.2. Its contents was last updated on 14 June 2019.

Copyright © 2009-2018 Université de Bordeaux

Copyright © 2010-2018 CNRS Copyright © 2011-2018 Inria

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

Contents

| 1 | Intro | duction | 3 | | | |
|---|--------------------|---|---|--|--|--|
| | 1.1 | Motivation | 3 | | | |
| | 1.2 | StarPU in a Nutshell | 3 | | | |
| | | 1.2.1 Codelet and Tasks | 3 | | | |
| | | 1.2.2 StarPU Data Management Library | 4 | | | |
| | 1.3 | Application Taskification | 4 | | | |
| | 1.4 | Glossary | 4 | | | |
| | 1.5 | Research Papers | 4 | | | |
| | 1.6 | StarPU Applications | 4 | | | |
| | 1.7 | Further Reading | 5 | | | |
| i | Star | PU Basics | 7 | | | |
| 2 | Buile | 3 · · · · · · 3 · · · · · | 9 | | | |
| | 2.1 | 3 7 3 | 9 | | | |
| | 2.2 | 9 | 9 | | | |
| | | | 9 | | | |
| | | | 9 | | | |
| | | 2.2.3 Configuring StarPU | | | | |
| | | 2.2.4 Building StarPU | | | | |
| | | 2.2.5 Installing StarPU | | | | |
| | 2.3 | Setting up Your Own Code | | | | |
| | | 2.3.1 Setting Flags for Compiling, Linking and Running Applications | | | | |
| | | 2.3.2 Integrating StarPU in a Build System | | | | |
| | | 2.3.3 Running a Basic StarPU Application | | | | |
| | | 2.3.4 Running a Basic StarPU Application on Microsoft Visual C | | | | |
| | | 2.3.5 Kernel Threads Started by StarPU | | | | |
| | | 2.3.6 Enabling OpenCL | | | | |
| | 2.4 | Benchmarking StarPU | | | | |
| | | 2.4.1 Task Size Overhead | | | | |
| | | 2.4.2 Data Transfer Latency | | | | |
| | | 2.4.3 Matrix-Matrix Multiplication | | | | |
| | | 2.4.4 Cholesky Factorization | | | | |
| | | 2.4.5 LU Factorization | | | | |
| | | 2.4.6 Simulated benchmarks | 4 | | | |
| 3 | | E Examples 1 | | | | |
| | 3.1 | Hello World | | | | |
| | | 3.1.1 Required Headers | | | | |
| | | 3.1.2 Defining A Codelet | | | | |
| | | 3.1.3 Submitting A Task | | | | |
| | | 3.1.4 Execution Of Hello World | | | | |
| | | 3.1.5 Passing Arguments To The Codelet | | | | |
| | | 3.1.6 Defining A Callback | - | | | |
| | 0.0 | 3.1.7 Where To Execute A Codelet | | | | |
| | 3.2 Vector Scaling | | | | | |

iv CONTENTS

| | | 3.2.1 Source Code of Vector Scaling | 20 |
|-----|---|---|--|
| | | 3.2.2 Execution of Vector Scaling | 21 |
| | 3.3 | Vector Scaling on an Hybrid CPU/GPU Machine | 21 |
| | | 3.3.1 Definition of the CUDA Kernel | 21 |
| | | 3.3.2 Definition of the OpenCL Kernel | 21 |
| | | 3.3.3 Definition of the Main Code | 22 |
| | | 3.3.4 Execution of Hybrid Vector Scaling | 24 |
| II | Sta | rPU Quick Programming Guide | 25 |
| 4 | Adva | anced Examples | 27 |
| 5 | Che | ck List When Performance Are Not There | 29 |
| | 5.1 | Check Task Size | 29 |
| | 5.2 | Configuration Which May Improve Performance | 29 |
| | 5.3 | Data Related Features Which May Improve Performance | 29 |
| | 5.4 | Task Related Features Which May Improve Performance | 29 |
| | 5.5 | Scheduling Related Features Which May Improve Performance | 29 |
| | 5.6 | CUDA-specific Optimizations | 30 |
| | 5.7 | OpenCL-specific Optimizations | 31 |
| | 5.8 | Detecting Stuck Conditions | 31 |
| | 5.9 | How to Limit Memory Used By StarPU And Cache Buffer Allocations | 31 |
| | 5.10 | | 32 |
| | 5.11 | | 32 |
| | | Performance Model Calibration | 32 |
| | | Profiling | 34 |
| | 5.14 | Overhead Profiling | 34 |
| | | | |
| Ш | Sta | arPU Inside | 37 |
| ••• | | | 31 |
| 6 | Task | ks In StarPU | 39 |
| | 6.1 | Task Granularity | 39 |
| | 6.1 6.2 | Task Granularity | 39 39 |
| | 6.1 6.2 6.3 | Task Granularity | 39 39 39 |
| | 6.1 6.2 | Task Granularity | 39 39 39 39 |
| | 6.1 6.2 6.3 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency | 39 39 39 39 39 |
| | 6.1 6.2 6.3 6.4 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies | 39 39 39 39 39 40 |
| | 6.1 6.2 6.3 6.4 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task | 39 39 39 39 39 40 40 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task | 39 39 39 39 39 40 40 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet | 39 39 39 39 39 40 40 41 41 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities | 39 39 39 39 40 40 41 41 41 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility | 39 39 39 39 39 40 41 41 41 42 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children | 39 39 39 39 39 40 41 41 41 42 44 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks | 39 39 39 39 40 41 41 41 42 44 44 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks | 39 39 39 39 39 40 41 41 41 42 44 44 44 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks | 39 39 39 39 39 40 41 41 41 42 44 44 44 45 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance | 39 39 39 39 39 40 41 41 41 42 44 44 45 45 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers | 39 39 39 39 39 40 41 41 41 42 44 44 45 45 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks | 39 39 39 39 39 40 41 41 41 42 44 44 45 45 45 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers | 39 39 39 39 39 40 41 41 41 42 44 44 45 45 |
| | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 6.11 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks 6.11.6 Synchronization Tasks | 39 39 39 39 39 40 41 41 41 42 44 45 45 45 45 |
| 6 | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 6.11 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks 6.11.6 Synchronization Tasks a Management Data Interface | 39 39 39 39 39 40 40 41 41 41 42 44 45 45 45 45 46 |
| 6 | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 6.11 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks 6.11.6 Synchronization Tasks a Management Data Interface 7.1.1 Variable Data Interface | 39 39 39 39 40 41 41 42 44 45 45 45 45 46 |
| 6 | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 6.11 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks 6.11.6 Synchronization Tasks a Management Data Interface 7.1.1 Variable Data Interface 7.1.1 Variable Data Interface 7.1.2 Vector Data Interface | 39 39 39 39 40 41 41 41 44 45 45 45 45 46 47 47 |
| 6 | 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 6.10 6.11 | Task Granularity Task Submission Task Priorities Task Dependencies 6.4.1 Sequential Consistency 6.4.2 Tasks And Tags Dependencies Setting Many Data Handles For a Task Setting a Variable Number Of Data Handles For a Task Using Multiple Implementations Of A Codelet Enabling Implementation According To Capabilities Insert Task Utility Getting Task Children Parallel Tasks 6.11.1 Fork-mode Parallel Tasks 6.11.2 SPMD-mode Parallel Tasks 6.11.3 Parallel Tasks Performance 6.11.4 Combined Workers 6.11.5 Concurrent Parallel Tasks 6.11.6 Synchronization Tasks a Management Data Interface 7.1.1 Variable Data Interface | 39 39 39 39 40 41 41 42 44 45 45 45 45 46 |

CONTENTS

| | | 7.1.5 BCSR Data Interface | 48 |
|----|------|---|-----|
| | | 7.1.6 CSR Data Interface | 48 |
| | | 7.1.7 Data Interface with Variable Size | 48 |
| | 7.2 | Data Management | 49 |
| | 7.3 | Data Prefetch | 50 |
| | 7.4 | | 50 |
| | 7.5 | | 51 |
| | 7.6 | | 51 |
| | 7.7 | | 52 |
| | 7.8 | | 52 |
| | 7.9 | | 53 |
| | | | 54 |
| | | | 54 |
| | 7.11 | | 54 |
| | | | 54 |
| | 7 10 | | 55 |
| | | | |
| | | | 56 |
| | 7.14 | Specifying A Target Node For Task Data | 57 |
| 8 | Sche | duling | 59 |
| • | 8.1 | | 59 |
| | 8.2 | | 59 |
| | 8.3 | · · · · · · · · · · · · · · · · · · · | 60 |
| | 8.4 | | 60 |
| | 8.5 | | 61 |
| | 8.6 | | 61 |
| | 8.7 | | 62 |
| | 0.7 | Tieterophio | 02 |
| 9 | Sche | duling Contexts | 65 |
| | 9.1 | | 65 |
| | 9.2 | | 65 |
| | | · | 66 |
| | 9.3 | | 66 |
| | 9.4 | | 66 |
| | 9.5 | , , | 66 |
| | 9.6 | | 67 |
| | 9.7 | | 67 |
| | | 1.4.2 | |
| 10 | Sche | duling Context Hypervisor | 69 |
| | 10.1 | What Is The Hypervisor | 69 |
| | 10.2 | Start the Hypervisor | 69 |
| | 10.3 | Interrogate The Runtime | 69 |
| | 10.4 | Trigger the Hypervisor | 69 |
| | 10.5 | Resizing Strategies | 70 |
| | 10.6 | Defining A New Hypervisor Policy | 71 |
| | | | |
| 11 | | , | 73 |
| | | | 73 |
| | | | 73 |
| | | | 74 |
| | 11.4 | · · | 75 |
| | | | 75 |
| | | | 76 |
| | | | 78 |
| | | | 78 |
| | | | 79 |
| | 11.6 | Debugging Scheduling | 80 |
| 40 | D-1 | region Table | C-1 |
| 12 | Dept | igging Tools | 81 |

vi

| | 2.1 TroubleShooting In General 2.2 Using The Gdb Debugger 2.3 Using Other Debugging Tools 2.4 Using The Temanejo Task Debugger | 81 81 82 82 |
|----|---|----------------------|
| 13 | Online Performance Tools | 85 |
| | 3.1 On-line Performance Feedback | 85 |
| | 13.1.1 Enabling On-line Performance Monitoring | 85 |
| | 13.1.2 Per-task Feedback | 85 |
| | 13.1.3 Per-codelet Feedback | 85 |
| | 13.1.4 Per-worker Feedback | 85 |
| | 13.1.5 Bus-related Feedback | 86 |
| | 13.1.6 MPI-related Feedback | 87 |
| | 3.2 Task And Worker Profiling | 87 |
| | 3.3 Performance Model Example | 87 |
| | 3.4 Data trace and tasks length | 90 |
| 14 | Offline Performance Tools | 91 |
| • | 4.1 Off-line Performance Feedback | 91 |
| | 14.1.1 Generating Traces With FxT | 91 |
| | 14.1.2 Limiting The Scope Of The Trace | 93 |
| | 4.2 Performance Of Codelets | 94 |
| | 4.3 Trace Statistics | 98 |
| | 4.4 Theoretical Lower Bound On Execution Time | |
| | 4.5 Theoretical Lower Bound On Execution Time Example | 101 |
| | 4.6 Memory Feedback | 101 |
| | 4.7 Data Statistics | |
| 15 | Fraguently Asked Questions | 103 |
| 13 | Frequently Asked Questions 5.1 How To Initialize A Computation Library Once For Each Worker? | 103 |
| | 5.2 Using The Driver API | |
| | 5.3 On-GPU Rendering | |
| | 5.4 Using StarPU With MKL 11 (Intel Composer XE 2013) | |
| | 5.5 Thread Binding on NetBSD | |
| | 5.6 StarPU permanently eats 100% of all CPUs | |
| | 5.7 Interleaving StarPU and non-StarPU code | |
| | 5.8 When running with CUDA or OpenCL devices, I am seeing less CPU cores | |
| | 5.9 StarPU does not see my CUDA device | |
| | 5.10StarPU does not see my OpenCL device | |
| | 5.11I keep getting a "Incorrect performance model file" error | |
| | | |
| IV | StarPU Extensions | 109 |
| 16 | Out Of Core | 111 |
| | 6.1 Introduction | 111 |
| | 6.2 Use a new disk memory | 111 |
| | 6.3 Data Registration | 112 |
| | 6.4 Using Wont Use | |
| | 6.5 Examples: disk_copy | 112 |
| | 6.6 Examples: disk_compute | 114 |
| | 6.7 Performances | 116 |
| | 6.8 Feedback Figures | 116 |
| | 6.9 Disk functions | 116 |
| 17 | ADI Support | 117 |
| 17 | MPI Support 7.1 Example Used In This Documentation | 117 |
| | 7.1 EXAMPLE COCCUIT THIS DUCCHIERIATION | 11/ |
| | | 117 |
| | 7.2 About Not Using The MPI Support | |

CONTENTS vii

| | 17.4 How to Initialize StarPU-MPI | |
|----|--|-----|
| | 17.5 Point To Point Communication | |
| | 17.6 Exchanging User Defined Data Interface | |
| | 17.7 MPI Insert Task Utility | |
| | 17.8 Pruning MPI Task Insertion | |
| | 17.9 Temporary Data | |
| | 17.10Per-node Data | |
| | 17.11 Priorities | |
| | 17.12MPI Cache Support | |
| | 17.13MPI Data Migration | |
| | 17.14MPI Collective Operations | |
| | 17.15Make StarPU-MPI Progression Thread Execute Tasks | |
| | 17.16Debugging MPI | |
| | 17.17More MPI examples | |
| | 17.18 Notes about the Implementation | |
| | 17.19MPI Master Slave Support | 129 |
| 18 | FFT Support | 131 |
| | 18.1 Compilation | _ |
| | | |
| 19 | MIC Xeon Phi Support | 133 |
| | 19.1 Compilation | 133 |
| | 19.2 Porting Applications To MIC Xeon Phi | 133 |
| | 19.3 Launching Programs | 134 |
| 00 | Notice Fauture Company | 105 |
| 20 | Native Fortran Support | 135 |
| | 20.1 Implementation Details and Specificities | |
| | 20.1.1 Prerequisites | |
| | | |
| | 20.1.3 Examples | |
| | 20.1.4 Complining a Native Fortian Application | |
| | 20.3 Uses, Initialization and Shutdown | |
| | 20.4 Fortran Flavor of StarPU's Variadic Insert_task | |
| | 20.5 Functions and Subroutines Expecting Data Structures Arguments | |
| | 20.6 Additional Notes about the Native Fortran Support | |
| | 20.6.1 Using StarPU with Older Fortran Compilers | |
| | 20.6.2 Valid API Mixes and Language Mixes | |
| | | |
| 21 | SOCL OpenCL Extensions | 139 |
| 22 | SimGrid Support | 141 |
| | 22.1 Preparing Your Application For Simulation | 141 |
| | 22.2 Calibration | |
| | 22.3 Simulation | |
| | 22.4 Simulation On Another Machine | |
| | 22.5 Simulation Examples | |
| | 22.6 Simulations On Fake Machines | |
| | 22.7 Tweaking Simulation | |
| | 22.8 MPI Applications | 143 |
| | 22.9 Debugging Applications | |
| | 22.10Memory Usage | |
| | | |
| 23 | The StarPU OpenMP Runtime Support (SORS) | 145 |
| | 23.1 Implementation Details and Specificities | 145 |
| | 23.1.1 Main Thread | |
| | 23.1.2 Extended Task Semantics | |
| | 23.2 Configuration | |
| | 23.3 Uses, Initialization and Shutdown | 145 |

viii CONTENTS

| | 23.4 | Parallel Regions and Worksharing | 146 |
|---|---|--|--|
| | | 23.4.1 Parallel Regions | 146 |
| | | 23.4.2 Parallel For | 146 |
| | | 23.4.3 Sections | 147 |
| | | 23.4.4 Single | 147 |
| | 23.5 | Tasks | 148 |
| | | 23.5.1 Explicit Tasks | |
| | | 23.5.2 Data Dependencies | |
| | | 23.5.3 TaskWait and TaskGroup | |
| | 23.6 | Synchronization Support | |
| | _0.0 | 23.6.1 Simple Locks | |
| | | 23.6.2 Nestable Locks | |
| | | 23.6.3 Critical Sections | |
| | | 23.6.4 Barriers | |
| | | 25.0.4 Daniels | 131 |
| 24 | Clus | tering a Machine | 153 |
| | | General Ideas | 153 |
| | 24.2 | Creating Clusters | 153 |
| | | Example Of Constraining OpenMP | |
| | | Creating Custom Clusters | |
| | | Clusters With Scheduling | |
| | | | |
| 25 | Inter | operability Support | 157 |
| | 25.1 | StarPU Resource Management | 157 |
| | | 25.1.1 Linking a program with the starpurm module | 157 |
| | | 25.1.2 Uses, Initialization and Shutdown | 157 |
| | | 25.1.3 Default Context | 158 |
| | | 25.1.4 Temporary Contexts | 158 |
| | | | |
| | | | |
| | | | |
| ٧ | Sta | rPU Reference API | 159 |
| | | | |
| | Exec | cution Configuration Through Environment Variables | 161 |
| | Exe ct 26.1 | cution Configuration Through Environment Variables Configuring Workers | 161 161 |
| | Exec 26.1 26.2 | Cution Configuration Through Environment Variables Configuring Workers | 161 161 164 |
| | Exec 26.1 26.2 26.3 | Cution Configuration Through Environment Variables Configuring Workers | 161 161 164 164 |
| | 26.1 26.2 26.3 26.4 | Cution Configuration Through Environment Variables Configuring Workers | 161 161 164 164 165 |
| | 26.1 26.2 26.3 26.4 | Cution Configuration Through Environment Variables Configuring Workers | 161 161 164 164 165 |
| 26 | 26.1 26.2 26.3 26.4 26.5 | Configuring Workers | 161 161 164 164 165 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com | Configuration Through Environment Variables Configuring Workers | 161 164 164 165 169 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 | Configuring Workers | 161 161 164 164 165 169 171 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 | Configuration Through Environment Variables Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Configuring The Hypervisor Configuration Common Configuration Configuring Workers | 161 161 164 164 165 169 171 171 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 | Configuration Through Environment Variables Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Ipilation Configuration Common Configuration Configuring Workers Extension Configuration | 161 164 164 165 169 171 171 172 173 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 | Configuration Through Environment Variables Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Configuring The Hypervisor Configuration Common Configuration Configuring Workers | 161 164 164 165 169 171 171 172 173 |
| 26 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 | Configuration Through Environment Variables Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Ipilation Configuration Common Configuration Configuring Workers Extension Configuration | 161 164 164 165 169 171 171 172 173 |
| 26 27 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 | Configuring Workers | 161 164 164 165 169 171 172 173 173 |
| 26 27 28 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 | Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Apilation Configuration Common Configuration Configuring Workers Extension Configuration Advanced Configuration ule Index Modules | 161 164 164 165 169 171 172 173 173 177 |
| 26 27 28 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 | Configuring Workers | 161 164 164 165 169 171 172 173 173 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 | Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Inpilation Configuration Common Configuration Configuring Workers Extension Configuration Advanced Configuration ule Index Modules recated List | 161 164 164 165 169 171 172 173 173 177 177 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | cution Configuration Through Environment Variables Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor configuring The Hypervisor configuring Workers Extension Configuration Configuring Workers Extension Configuration Advanced Configuration ule Index Modules recated List ule Documentation a.k.a StarPU's API | 161 164 164 165 169 171 172 173 173 177 177 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | cution Configuration Through Environment Variables Configuring Workers | 161 164 164 165 169 171 171 172 173 173 177 177 179 181 181 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers | 161 164 164 165 169 171 171 172 173 173 177 177 179 181 181 181 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers. Configuring The Scheduling Engine. Extensions. Miscellaneous And Debug. Configuring The Hypervisor. Pipilation Configuration Common Configuration Configuring Workers. Extension Configuration Advanced Configuration ule Index Modules recated List ule Documentation a.k.a StarPU's API Versioning 30.1.1 Detailed Description 30.1.2 Macro Definition Documentation | 161 164 164 165 169 171 171 172 173 177 177 177 181 181 181 181 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers | 161 164 164 165 169 171 172 173 177 177 177 181 181 181 181 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers | 161 164 164 165 169 171 172 173 177 177 179 181 181 181 181 181 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Inpilation Configuration Common Configuration Comfiguration Configuring Workers Extension Configuration Advanced Configuration Inpilation Configuration Intelligible Documentation a.k.a StarPU's API Versioning 30.1.1 Detailed Description 30.1.2 Macro Definition Documentation Initialization and Termination 30.2.1 Detailed Description | 161 164 164 165 169 171 171 172 173 177 177 179 181 181 181 181 181 182 182 |
| 26272829 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Configuring The Hypervisor Configuring The Hypervisor Ipilation Configuration Common Configuration Configuring Workers Extension Configuration Advanced Configuration Lule Index Modules Recated List Ule Documentation a.k.a StarPU's API Versioning 30.1.1 Detailed Description 30.1.2 Macro Definition Documentation 30.1.3 Function Documentation Initialization and Termination 30.2.1 Detailed Description 30.2.2 Data Structure Documentation | 161 164 164 165 169 171 171 172 173 177 177 179 181 181 181 181 181 182 182 182 |
| 26 27 28 29 | 26.1 26.2 26.3 26.4 26.5 Com 27.1 27.2 27.3 27.4 Mod 28.1 Depr | Configuring Workers Configuring The Scheduling Engine Extensions Miscellaneous And Debug Configuring The Hypervisor Inpilation Configuration Common Configuration Comfiguration Configuring Workers Extension Configuration Advanced Configuration Inpilation Configuration Intelligible Documentation a.k.a StarPU's API Versioning 30.1.1 Detailed Description 30.1.2 Macro Definition Documentation Initialization and Termination 30.2.1 Detailed Description | 161 164 164 165 169 171 172 173 177 177 179 181 181 181 181 182 182 182 186 |

CONTENTS

| 30.3 | Standard Memory Library | |
|-------|--|-----|
| | 30.3.1 Detailed Description | |
| | 30.3.2 Macro Definition Documentation | 189 |
| | 30.3.3 Function Documentation | 190 |
| 30.4 | Toolbox | 193 |
| | 30.4.1 Detailed Description | |
| | 30.4.2 Macro Definition Documentation | 193 |
| 30.5 | Threads | 195 |
| | 30.5.1 Detailed Description | |
| | 30.5.2 Macro Definition Documentation | |
| | 30.5.3 Function Documentation | |
| 30.6 | Bitmap | |
| | 30.6.1 Detailed Description | |
| | 30.6.2 Function Documentation | |
| 30.7 | Workers' Properties | |
| | 30.7.1 Detailed Description | |
| | 30.7.2 Data Structure Documentation | |
| | 30.7.3 Macro Definition Documentation | |
| | 30.7.4 Enumeration Type Documentation | |
| | 30.7.5 Function Documentation | |
| 30.8 | Data Management | |
| | 30.8.1 Detailed Description | |
| | 30.8.2 Macro Definition Documentation | |
| | 30.8.3 Typedef Documentation | |
| | 30.8.4 Enumeration Type Documentation | |
| | 30.8.5 Function Documentation | |
| 30.9 | | |
| | 30.9.1 Detailed Description | |
| | 30.9.2 Data Structure Documentation | |
| | 30.9.3 Macro Definition Documentation | |
| | 30.9.4 Enumeration Type Documentation | |
| | 30.9.5 Function Documentation | |
| 30.10 | OData Partition | |
| | 30.10.1 Detailed Description | |
| | 30.10.2 Data Structure Documentation | |
| | 30.10.3 Function Documentation | |
| 30.11 | 1 Out Of Core | |
| | 30.11.1 Detailed Description | |
| | 30.11.2 Data Structure Documentation | |
| | 30.11.3 Macro Definition Documentation | |
| | 30.11.4 Function Documentation | |
| 00.40 | 30.11.5 Variable Documentation | |
| 30.12 | 2Codelet And Tasks | |
| | 30.12.1 Detailed Description | |
| | 30.12.2 Data Structure Documentation | |
| | 30.12.3 Macro Definition Documentation | |
| | 30.12.4 Typedef Documentation | |
| | 30.12.5 Enumeration Type Documentation | |
| 00.40 | 30.12.6 Function Documentation | |
| 30.13 | 3Task Insert Utility | |
| | 30.13.1 Detailed Description | |
| | 30.13.2 Data Structure Documentation | |
| | 30.13.3 Macro Definition Documentation | |
| 20.4 | 30.13.4 Function Documentation | |
| 30.14 | 4Explicit Dependencies | |
| | 30.14.1 Detailed Description | |
| | 30.14.2 Typedef Documentation | |
| | 30.14.3 Function Documentation | 3U3 |

CONTENTS

| 30.15Performance Model | 306 |
|--|-----|
| 30.15.1 Detailed Description | 308 |
| 30.15.2 Data Structure Documentation | 308 |
| 30.15.3 Enumeration Type Documentation | 311 |
| 30.15.4 Function Documentation | 312 |
| 30.15.5 Variable Documentation | 315 |
| 30.16 Profiling | 315 |
| 30.16.1 Detailed Description | 316 |
| 30.16.2 Data Structure Documentation | 316 |
| 30.16.3 Macro Definition Documentation | 317 |
| 30.16.4 Function Documentation | 317 |
| 30.17Theoretical Lower Bound on Execution Time | 319 |
| 30.17.1 Detailed Description | 319 |
| 30.17.2 Function Documentation | 319 |
| 30.18CUDA Extensions | 320 |
| 30.18.1 Detailed Description | 321 |
| 30.18.2 Macro Definition Documentation | 321 |
| 30.18.3 Function Documentation | 321 |
| 30.19OpenCL Extensions | |
| 30.19.1 Detailed Description | 324 |
| 30.19.2 Data Structure Documentation | 324 |
| 30.19.3 Macro Definition Documentation | 324 |
| 30.19.4 Function Documentation | 325 |
| 30.20 OpenMP Runtime Support | 329 |
| 30.20.1 Detailed Description | 332 |
| 30.20.2 Data Structure Documentation | |
| 30.20.3 Macro Definition Documentation | 334 |
| 30.20.4 Enumeration Type Documentation | |
| 30.20.5 Function Documentation | 335 |
| 30.21 MIC Extensions | 353 |
| 30.21.1 Detailed Description | |
| 30.21.2 Macro Definition Documentation | |
| 30.21.3 Typedef Documentation | |
| 30.21.4 Function Documentation | |
| 30.22Miscellaneous Helpers | |
| 30.22.1 Detailed Description | |
| 30.22.2 Macro Definition Documentation | 354 |
| 30.22.3 Function Documentation | 355 |
| 30.23FxT Support | 356 |
| 30.23.1 Detailed Description | |
| 30.23.2 Data Structure Documentation | |
| 30.23.3 Function Documentation | |
| 30.24FFT Support | |
| 30.24.1 Detailed Description | |
| 30.24.2 Function Documentation | 358 |
| 30.25MPI Support | |
| 30.25.1 Detailed Description | |
| 30.25.2 Macro Definition Documentation | |
| 30.25.3 Typedef Documentation | |
| 30.25.4 Function Documentation | 364 |
| 30.26Task Bundles | 376 |
| 30.26.1 Detailed Description | 376 |
| 30.26.2 Typedef Documentation | 376 |
| 30.26.3 Function Documentation | 376 |
| 30.27Task Lists | 377 |
| 30.27.1 Detailed Description | 378 |
| 30.27.2 Data Structure Documentation | |
| 30.27.3 Function Documentation | 378 |

CONTENTS xi

| | 30.28 Parallel Tasks | 379 |
|-----------|---|-----|
| | 30.28.1 Detailed Description | 380 |
| | 30.28.2 Function Documentation | |
| | 30.29 Running Drivers | 381 |
| | 30.29.1 Detailed Description | |
| | 30.29.2 Data Structure Documentation | |
| | 30.29.3 Function Documentation | |
| | 30.30 Expert Mode | |
| | 30.30.1 Detailed Description | |
| | 30.30.2 Function Documentation | |
| | | |
| | 30.31 Scheduling Contexts | |
| | 30.31.1 Detailed Description | |
| | 30.31.2 Macro Definition Documentation | |
| | 30.31.3 Function Documentation | |
| | 30.32Scheduling Policy | |
| | 30.32.1 Detailed Description | |
| | 30.32.2 Data Structure Documentation | 392 |
| | 30.32.3 Macro Definition Documentation | 394 |
| | 30.32.4 Function Documentation | 394 |
| | 30.33Tree | 399 |
| | 30.33.1 Detailed Description | 399 |
| | 30.33.2 Data Structure Documentation | |
| | 30.34Scheduling Context Hypervisor - Building a new resizing policy | |
| | 30.34.1 Detailed Description | |
| | 30.34.2 Data Structure Documentation | |
| | 30.34.3 Macro Definition Documentation | |
| | 30.34.4 Function Documentation | |
| | | |
| | 30.35 Scheduling Context Hypervisor - Regular usage | |
| | 30.35.1 Detailed Description | |
| | 30.35.2 Data Structure Documentation | |
| | 30.35.3 Function Documentation | |
| | 30.35.4 Variable Documentation | |
| | 30.36 Scheduling Context Hypervisor - Linear Programming | |
| | 30.36.1 Detailed Description | |
| | 30.36.2 Function Documentation | |
| | 30.37 Modularized Scheduler Interface | 418 |
| | 30.37.1 Detailed Description | 421 |
| | 30.37.2 Data Structure Documentation | 421 |
| | 30.37.3 Macro Definition Documentation | 426 |
| | 30.37.4 Enumeration Type Documentation | 427 |
| | 30.37.5 Function Documentation | |
| | 30.38 Clustering Machine | 433 |
| | 30.38.1 Detailed Description | 434 |
| | 30.38.2 Enumeration Type Documentation | 434 |
| | 30.39Interoperability Support | _ |
| | 30.39.1 Detailed Description | |
| | 30.39.2 Enumeration Type Documentation | |
| | 30.39.3 Function Documentation | |
| | 50.59.5 Function Documentation | 437 |
| 31 | File Index | 447 |
| 31 | 31.1 File List | 447 |
| | ST.1 FILE LIST | 447 |
| 32 | File Documentation | 449 |
| 52 | 32.1 starpu.h File Reference | 449 |
| | 32.2 starpu_bitmap.h File Reference | 449 |
| | \cdot – \cdot | 450 |
| | 32.3 starpu_bound.h File Reference | |
| | 32.4 starpu_clusters.h File Reference | 451 |
| | 32.5 starpu_config.h File Reference | 451 |
| | 32.6 starpu_cublas.h File Reference | 454 |

xii CONTENTS

| | 32.7 starpu_cusparse.h File Reference | 454 |
|-----|---|-----|
| | 32.8 starpu_cuda.h File Reference | |
| | 32.9 starpu_data.h File Reference | |
| | 32.10starpu_data_filters.h File Reference | |
| | 32.11starpu_data_interfaces.h File Reference | |
| | 32.12starpu_deprecated_api.h File Reference | |
| | 32.13starpu_disk.h File Reference | |
| | 32.14starpu_driver.h File Reference | |
| | 32.15starpu_expert.h File Reference | |
| | $\cdot = \cdot$ | |
| | 32.16starpu_fxt.h File Reference | |
| | 32.17starpu_hash.h File Reference | |
| | 32.18starpu_mic.h File Reference | |
| | 32.19starpu_mod.f90 File Reference | |
| | 32.20starpu_mpi.h File Reference | |
| | 32.21starpu_mpi_lb.h File Reference | |
| | 32.22starpu_opencl.h File Reference | |
| | 32.23starpu_openmp.h File Reference | |
| | 32.24starpu_perfmodel.h File Reference | 471 |
| | 32.25starpu_profiling.h File Reference | 473 |
| | 32.26starpu_rand.h File Reference | 474 |
| | 32.27starpu_sched_component.h File Reference | |
| | 32.28starpu_sched_ctx.h File Reference | |
| | 32.29starpu sched ctx hypervisor.h File Reference | |
| | 32.29.1 Function Documentation | |
| | 32.30starpu_scheduler.h File Reference | |
| | 32.31starpu_simgrid_wrap.h File Reference | |
| | 32.32starpu_sink.h File Reference | |
| | 32.33starpu_stdlib.h File Reference | |
| | 32.34starpu_task.h File Reference | |
| | | |
| | 32.35starpu_task_bundle.h File Reference | |
| | 32.36starpu_task_list.h File Reference | |
| | 32.37starpu_task_util.h File Reference | |
| | 32.38starpu_thread.h File Reference | |
| | 32.38.1 Data Structure Documentation | |
| | 32.39starpu_thread_util.h File Reference | |
| | 32.40starpu_tree.h File Reference | |
| | 32.41starpu_util.h File Reference | |
| | 32.42starpu_worker.h File Reference | 491 |
| | 32.43starpufft.h File Reference | 493 |
| | 32.44sc_hypervisor.h File Reference | 494 |
| | 32.45sc_hypervisor_config.h File Reference | 495 |
| | 32.45.1 Data Structure Documentation | 495 |
| | 32.46sc_hypervisor_lp.h File Reference | 496 |
| | 32.47sc_hypervisor_monitoring.h File Reference | |
| | 32.47.1 Data Structure Documentation | |
| | 32.48sc_hypervisor_policy.h File Reference | |
| | 32.49starpurm.h File Reference | |
| | | 550 |
| 33 | Deprecated List | 503 |
| | | |
| ١/١ | Annondiv | EOF |
| VI | Appendix | 505 |
| 34 | Full Source Code for the 'Scaling a Vector' Example | 507 |
| | 34.1 Main Application | 507 |
| | 34.2 CPU Kernel | |
| | 34.3 CUDA Kernel | |
| | 34.4 OpenCL Kernel | |
| | 34.4.1 Invoking the Kernel | |
| | C | 503 |

| CONTENTS | | |
|---|-----|--|
| 34.4.2 Source of the Kernel | 510 | |
| 35 The GNU Free Documentation License | 511 | |
| 35.1 ADDENDUM: How to use this License for your documents | 515 | |
| VII Index | 517 | |

519

Index

2 CONTENTS

Chapter 1

Introduction

1.1 Motivation

The use of specialized hardware such as accelerators or coprocessors offers an interesting approach to overcome the physical limits encountered by processor architects. As a result, many machines are now equipped with one or several accelerators (e.g. a GPU), in addition to the usual processor(s). While a lot of efforts have been devoted to offload computation onto such accelerators, very little attention as been paid to portability concerns on the one hand, and to the possibility of having heterogeneous accelerators and processors to interact on the other hand. StarPU is a runtime system that offers support for heterogeneous multicore architectures, it not only offers a unified view of the computational resources (i.e. CPUs and accelerators at the same time), but it also takes care of efficiently mapping and executing tasks onto an heterogeneous machine while transparently handling low-level issues such as data transfers in a portable fashion.

1.2 StarPU in a Nutshell

StarPU is a software tool aiming to allow programmers to exploit the computing power of the available CPUs and GPUs, while relieving them from the need to specially adapt their programs to the target machine and processing units

At the core of StarPU is its runtime support library, which is responsible for scheduling application-provided tasks on heterogeneous CPU/GPU machines. In addition, StarPU comes with programming language support, in the form of an OpenCL front-end (SOCL OpenCL Extensions).

StarPU's runtime and programming language extensions support a task-based programming model. Applications submit computational tasks, with CPU and/or GPU implementations, and StarPU schedules these tasks and associated data transfers on available CPUs and GPUs. The data that a task manipulates are automatically transferred among accelerators and the main memory, so that programmers are freed from the scheduling issues and technical details associated with these transfers.

StarPU takes particular care of scheduling tasks efficiently, using well-known algorithms from the literature (Task Scheduling Policies). In addition, it allows scheduling experts, such as compiler or computational library developers, to implement custom scheduling policies in a portable fashion (How To Define A New Scheduling Policy).

The remainder of this section describes the main concepts used in StarPU.

1.2.1 Codelet and Tasks

One of the StarPU primary data structures is the **codelet**. A codelet describes a computational kernel that can possibly be implemented on multiple architectures such as a CPU, a CUDA device or an OpenCL device.

Another important data structure is the **task**. Executing a StarPU task consists in applying a codelet on a data set, on one of the architectures on which the codelet is implemented. A task thus describes the codelet that it uses, but also which data are accessed, and how they are accessed during the computation (read and/or write). StarPU tasks are asynchronous: submitting a task to StarPU is a non-blocking operation. The task structure can also specify a **callback** function that is called once StarPU has properly executed the task. It also contains optional fields that the application may use to give hints to the scheduler (such as priority levels).

By default, task dependencies are inferred from data dependency (sequential coherency) by StarPU. The application can however disable sequential coherency for some data, and dependencies can be specifically expressed. A task

4 Introduction

may be identified by a unique 64-bit number chosen by the application which we refer as a **tag**. Task dependencies can be enforced either by the means of callback functions, by submitting other tasks, or by expressing dependencies between tags (which can thus correspond to tasks that have not yet been submitted).

1.2.2 StarPU Data Management Library

Because StarPU schedules tasks at runtime, data transfers have to be done automatically and "just-in-time" between processing units, relieving application programmers from explicit data transfers. Moreover, to avoid unnecessary transfers, StarPU keeps data where it was last needed, even if was modified there, and it allows multiple copies of the same data to reside at the same time on several processing units as long as it is not modified.

1.3 Application Taskification

TODO

1.4 Glossary

A **codelet** records pointers to various implementations of the same theoretical function.

A memory node can be either the main RAM, GPU-embedded memory or a disk memory.

A **bus** is a link between memory nodes.

A **data handle** keeps track of replicates of the same data (**registered** by the application) over various memory nodes. The data management library manages to keep them coherent.

The **home** memory node of a data handle is the memory node from which the data was registered (usually the main memory node).

A task represents a scheduled execution of a codelet on some data handles.

A **tag** is a rendez-vous point. Tasks typically have their own tag, and can depend on other tags. The value is chosen by the application.

A worker execute tasks. There is typically one per CPU computation core and one per accelerator (for which a whole CPU core is dedicated).

A **driver** drives a given kind of workers. There are currently CPU, CUDA, and OpenCL drivers. They usually start several workers to actually drive them.

A **performance model** is a (dynamic or static) model of the performance of a given codelet. Codelets can have execution time performance model as well as energy consumption performance models.

A data **interface** describes the layout of the data: for a vector, a pointer for the start, the number of elements and the size of elements; for a matrix, a pointer for the start, the number of elements per row, the offset between rows, and the size of each element; etc. To access their data, codelet functions are given interfaces for the local memory node replicates of the data handles of the scheduled task.

Partitioning data means dividing the data of a given data handle (called **father**) into a series of **children** data handles which designate various portions of the former.

A **filter** is the function which computes children data handles from a father data handle, and thus describes how the partitioning should be done (horizontal, vertical, etc.)

Acquiring a data handle can be done from the main application, to safely access the data of a data handle from its home node, without having to unregister it.

1.5 Research Papers

Research papers about StarPU can be found at http://starpu.gforge.inria.fr/publications/.
A good overview is available in the research report at http://hal.archives-ouvertes.fr/inria-00467677.

1.6 StarPU Applications

You can first have a look at the chapters Basic Examples and Advanced Examples. A tutorial is also installed in the directory share/doc/starpu/tutorial/.

 $\label{lem:many-examples} \textbf{Many-examples are also available in the StarPU sources in the directory \verb|examples|/. Simple examples include: \\$

incrementer/ Trivial incrementation test.

1.7 Further Reading 5

basic_examples/ Simple documented Hello world and vector/scalar product (as shown in Basic Examples), matrix product examples (as shown in Performance Model Example), an example using the blocked matrix data interface, an example using the variable data interface, and an example using different formats on CPUs and GPUs.

matvecmult/ OpenCL example from NVidia, adapted to StarPU.

axpy/ AXPY CUBLAS operation adapted to StarPU.

native_fortran/ Example of using StarPU's native Fortran support.

fortran90/ Example of Fortran 90 bindings, using C marshalling wrappers.

fortran/ Example of Fortran 77 bindings, using C marshalling wrappers.

More advanced examples include:

filters/ Examples using filters, as shown in Partitioning Data.

lu/ LU matrix factorization, see for instance xlu_implicit.c

cholesky Cholesky matrix factorization, see for instance cholesky_implicit.c.

1.7 Further Reading

The documentation chapters include

- · Part 1: StarPU Basics
 - Building and Installing StarPU
 - Basic Examples
- · Part 2: StarPU Quick Programming Guide
 - Advanced Examples
 - Check List When Performance Are Not There
- Part 3: StarPU Inside
 - Tasks In StarPU
 - Data Management
 - Scheduling
 - Scheduling Contexts
 - Scheduling Context Hypervisor
 - How To Define A New Scheduling Policy
 - Debugging Tools
 - Online Performance Tools
 - Offline Performance Tools
 - Frequently Asked Questions
- · Part 4: StarPU Extensions
 - Out Of Core
 - MPI Support
 - FFT Support
 - MIC Xeon Phi Support
 - The StarPU Native Fortran Support
 - SOCL OpenCL Extensions

6 Introduction

- SimGrid Support
- The StarPU OpenMP Runtime Support (SORS)
- Clustering A Machine
- Part 5: StarPU Reference API
 - Execution Configuration Through Environment Variables
 - Compilation Configuration
 - Module Documentation
 - File Documentation
 - Deprecated List
- Part: Appendix
 - Full source code for the 'Scaling a Vector' example
 - The GNU Free Documentation License

Make sure to have had a look at those too!

Part I StarPU Basics

Chapter 2

Building and Installing StarPU

2.1 Installing a Binary Package

One of the StarPU developers being a Debian Developer, the packages are well integrated and very uptodate. To see which packages are available, simply type:

```
$ apt-cache search starpu
```

To install what you need, type for example:

```
$ sudo apt-get install libstarpu-1.3 libstarpu-dev
```

2.2 Installing from Source

StarPU can be built and installed by the standard means of the GNU autotools. The following chapter is intended to briefly remind how these tools can be used to install StarPU.

2.2.1 Optional Dependencies

The hwloc (http://www.open-mpi.org/software/hwloc) topology discovery library is not mandatory to use StarPU but strongly recommended. It allows for topology aware scheduling, which improves performance. libhwloc is available in major free operating system distributions, and for most operating systems.

If libhwloc is installed in a standard location, no option is required, it will be detected automatically, otherwise --with-hwloc=<directory> should be used to specify its location.

If libhwloc is not available on your system, the option --without-hwloc should be explicitly given when calling the configure script.

2.2.2 Getting Sources

StarPU's sources can be obtained from the download page of the StarPU website (http://starpu. \leftarrow gforge.inria.fr/files/).

All releases and the development tree of StarPU are freely available on Inria's gforge under the LGPL license. Some releases are available under the BSD license.

The latest release can be downloaded from the Inria's gforge (http://gforge.inria.fr/frs/?group \leftarrow _id=1570) or directly from the StarPU download page (http://starpu.gforge.inria.fr/files/). The latest nightly snapshot can be downloaded from the StarPU gforge website (http://starpu.gforge. \leftarrow inria.fr/testing/).

```
\$ \ wget \ http://starpu.gforge.inria.fr/testing/starpu-nightly-latest.tar.gz
```

And finally, current development version is also accessible via git. It should only be used if you need the very latest changes (i.e. less than a day old!).

```
\$ \  \, \text{git clone https://scm.gforge.inria.fr/anonscm/git/starpu/starpu.git}
```

2.2.3 Configuring StarPU

Running autogen.sh is not necessary when using the tarball releases of StarPU. However when using the source code from the git repository, you first need to generate the configure scripts and the Makefiles. This requires the availability of autoconf and automake >= 2.60.

```
$ ./autogen.sh
```

You then need to configure StarPU. Details about options that are useful to give to configure are given in Compilation Configuration.

```
$ ./configure
```

If configure does not detect some software or produces errors, please make sure to post the contents of the file config.log when reporting the issue.

By default, the files produced during the compilation are placed in the source directory. As the compilation generates a lot of files, it is advised to put them all in a separate directory. It is then easier to cleanup, and this allows to compile several configurations out of the same source tree. To do so, simply enter the directory where you want the compilation to produce its files, and invoke the configure script located in the StarPU source directory.

```
$ mkdir build
$ cd build
$ ../configure
```

By default, StarPU will be installed in /usr/local/bin, /usr/local/lib, etc. You can specify an installation prefix other than /usr/local using the option -prefix, for instance:

```
$ ../configure --prefix=$HOME/starpu
```

2.2.4 Building StarPU

\$ make

Once everything is built, you may want to test the result. An extensive set of regression tests is provided with Star PU. Running the tests is done by calling make check. These tests are run every night and the result from the main profile is publicly available (http://starpu.gforge.inria.fr/testing/).

```
$ make check
```

2.2.5 Installing StarPU

In order to install StarPU at the location which was specified during configuration:

```
$ make install
```

Libtool interface versioning information are included in libraries names (libstarpu-1.3.so, libstarpumpi $-1.\leftrightarrow$ 3.so and libstarpufft-1.3.so).

2.3 Setting up Your Own Code

2.3.1 Setting Flags for Compiling, Linking and Running Applications

StarPU provides a pkg-config executable to obtain relevant compiler and linker flags. As compiling and linking an application against StarPU may require to use specific flags or libraries (for instance CUDA or libspe2). If StarPU was not installed at some standard location, the path of StarPU's library must be specified in the environment variable PKG_CONFIG_PATH to allow pkg-config to find it. For example if StarPU was installed in \$STARPU_PATH:

```
$ export PKG_CONFIG_PATH=$PKG_CONFIG_PATH:$STARPU_PATH/lib/pkgconfig
```

The flags required to compile or link against StarPU are then accessible with the following commands:

```
$ pkg-config --cflags starpu-1.3 # options for the compiler
$ pkg-config --libs starpu-1.3 # options for the linker
```

Note that it is still possible to use the API provided in the version 1.0 of StarPU by calling pkg-config with the starpu-1.0 package. Similar packages are provided for starpumpi-1.0 and starpufft-1.0. It is also possible to use the API provided in the version 0.9 of StarPU by calling pkg-config with the libstarpu package. Similar packages are provided for libstarpumpi and libstarpufft.

Make sure that pkg-config -libs starpu-1.3 actually produces some output before going further: $PK \leftarrow G_CONFIG_PATH$ has to point to the place where starpu-1.3.pc was installed during make install. Also pass the option -static if the application is to be linked statically.

It is also necessary to set the environment variable LD_LIBRARY_PATH to locate dynamic libraries at runtime.

```
$ export LD_LIBRARY_PATH=$STARPU_PATH/lib:$LD_LIBRARY_PATH
```

And it is useful to get access to the StarPU tools:

```
$ export PATH=$PATH:$STARPU_PATH/bin
```

It is then useful to check that StarPU executes correctly and finds your hardware:

```
$ starpu_machine_display
```

If it does not, please check the output of lstopo from hwloc and report the issue to the hwloc project, since this is what StarPU uses to detect the hardware.

2.3.2 Integrating StarPU in a Build System

2.3.2.1 Integrating StarPU in a Make Build System

When using a Makefile, the following lines can be added to set the options for the compiler and the linker:

```
CFLAGS += $$(pkg-config --cflags starpu-1.3)
LDLIBS += $$(pkg-config --libs starpu-1.3)
```

If you have a test-starpu.c file containing for instance:

You can build it with make test-starpu and run it with ./test-starpu

2.3.2.2 Integrating StarPU in a CMake Build System

This section shows a minimal example integrating StarPU in an existing application's CMake build system. Let's assume we want to build an executable from the following source code using CMake:

```
#include <starpu.h>
#include <stdio.h>
int main(void)
{
   int ret;
   ret = starpu_init(NULL);
   if (ret != 0)
   {
      return 1;
   }
   printf("%d CPU coress\n", starpu_worker_get_count_by_type(
      STARPU_CPU_WORKER));
```

```
printf("%d CUDA GPUs\n", starpu_worker_get_count_by_type(
    STARPU_CUDA_WORKER));
printf("%d OpenCL GPUs\n", starpu_worker_get_count_by_type(
    STARPU_OPENCL_WORKER));
starpu_shutdown();
return 0;
```

The CMakeLists.txt file below uses the Pkg-Config support from CMake to autodetect the StarPU installation and library dependences (such as libhwloc) provided that the PKG_CONFIG_PATH variable is set, and is sufficient to build a statically-linked executable. This example has been successfully tested with CMake 3.2, though it may work with earlier CMake 3.x versions.

```
{File CMakeLists.txt}
cmake_minimum_required (VERSION 3.2)
project (hello_starpu)

find_package(PkgConfig)
pkg_check_modules(STARPU REQUIRED starpu-1.3)
if (STARPU_FOUND)
   include_directories (${STARPU_INCLUDE_DIRS})
   link_directories (${STARPU_STATIC_LIBRARY_DIRS})
   ink_libraries (${STARPU_STATIC_LIBRARIES})

else (STARPU_FOUND)
   message(FATAL_ERROR "StarPU not found")
endif()

add_executable(hello_starpu hello_starpu.c)
```

The following CMakeLists.txt implements an alternative, more complex strategy, still relying on Pkg-Config, but also taking into account additional flags. While more complete, this approach makes CMake's build types (Debug, Release, ...) unavailable because of the direct affectation to variable CMAKE_C_FLAGS. If both the full flags support and the build types support are needed, the CMakeLists.txt below may be altered to work with CMAKE_C_FLAGS_RELEASE, CMAKE_C_FLAGS_DEBUG, and others as needed. This example has been successfully tested with CMake 3.2, though it may work with earlier CMake 3.x versions.

```
{File CMakeLists.txt}
cmake_minimum_required (VERSION 3.2)
project (hello_starpu)
find_package(PkgConfig)
pkg_check_modules(STARPU REQUIRED starpu-1.3)
# This section must appear before 'add_executable'
if (STARPU FOUND)
    # CFLAGS other than -I
    foreach(CFLAG ${STARPU_CFLAGS_OTHER})
       set (CMAKE_C_FLAGS "${CMAKE_C_FLAGS} ${CFLAG}")
    endforeach()
    # Static LDFLAGS other than -L
    foreach(LDFLAG ${STARPU_STATIC_LDFLAGS_OTHER})
        set (CMAKE_EXE_LINKER_FLAGS "${CMAKE_EXE_LINKER_FLAGS} ${LDFLAG}")
    endforeach()
    # -L directories
    link_directories(${STARPU_STATIC_LIBRARY_DIRS})
else (STARPU_FOUND)
    message(FATAL_ERROR "StarPU not found")
add executable(hello starpu hello starpu.c)
# This section must appear after 'add_executable'
if (STARPU_FOUND)

↓ -I directories

    target_include_directories(hello_starpu PRIVATE ${STARPU_INCLUDE_DIRS})
    target_link_libraries(hello_starpu PRIVATE ${STARPU_STATIC_LIBRARIES})
endif()
```

2.3.3 Running a Basic StarPU Application

Basic examples using StarPU are built in the directory examples/basic_examples/ (and installed in \$ST ~ ARPU_PATH/lib/starpu/examples/). You can for example run the example vector_scal.

```
$ ./examples/basic_examples/vector_scal
```

```
BEFORE: First element was 1.000000 AFTER: First element is 3.140000
```

When StarPU is used for the first time, the directory \$STARPU_HOME/.starpu/is created, performance models will be stored in this directory (STARPU_HOME).

Please note that buses are benchmarked when StarPU is launched for the first time. This may take a few minutes, or less if libhwloc is installed. This step is done only once per user and per machine.

2.3.4 Running a Basic StarPU Application on Microsoft Visual C

Batch files are provided to run StarPU applications under Microsoft Visual C. They are installed in \$STARPU_P← ATH/bin/msvc.

To execute a StarPU application, you first need to set the environment variable STARPU_PATH.

```
c:\....> cd c:\cygwin\home\ci\starpu\
c:\....> set STARPU_PATH=c:\cygwin\home\ci\starpu\
c:\....> cd bin\msvc
c:\....> starpu_open.bat starpu_simple.c
```

The batch script will run Microsoft Visual C with a basic project file to run the given application.

The batch script starpu_clean.bat can be used to delete all compilation generated files.

The batch script starpu_exec.bat can be used to compile and execute a StarPU application from the command prompt.

```
c:\....> cd c:\cygwin\home\ci\starpu\
c:\....> set STARPU_PATH=c:\cygwin\home\ci\starpu\
c:\....> cd bin\msvc
c:\....> starpu_exec.bat ..\..\..\examples\basic_examples\hello_world.c

MSVC StarPU Execution
...
/out:hello_world.exe
...
Hello world (params = {1, 2.00000})
Callback function got argument 0000042
c:\....>
```

2.3.5 Kernel Threads Started by StarPU

StarPU automatically binds one thread per CPU core. It does not use SMT/hyperthreading because kernels are usually already optimized for using a full core, and using hyperthreading would make kernel calibration rather random.

Since driving GPUs is a CPU-consuming task, StarPU dedicates one core per GPU.

While StarPU tasks are executing, the application is not supposed to do computations in the threads it starts itself, tasks should be used instead.

If the application needs to reserve some cores for its own computations, it can do so with the starpu_conf::reserve — _ncpus field, get the core IDs with starpu_get_next_bindid(), and bind to them with starpu_bind_thread_on().

Another option is for the application to put the whole StarPU on pause with starpu_pause() before performing its own computations, and let StarPU resume executing tasks with starpu_resume().

2.3.6 Enabling OpenCL

When both CUDA and OpenCL drivers are enabled, StarPU will launch an OpenCL worker for NVIDIA GPUs only if CUDA is not already running on them. This design choice was necessary as OpenCL and CUDA can not run at the same time on the same NVIDIA GPU, as there is currently no interoperability between them.

To enable OpenCL, you need either to disable CUDA when configuring StarPU:

```
$ ./configure --disable-cuda
or when running applications:
```

\$ STARPU_NCUDA=0 ./application

OpenCL will automatically be started on any device not yet used by CUDA. So on a machine running 4 GPUS, it is therefore possible to enable CUDA on 2 devices, and OpenCL on the 2 other devices by doing so:


```
STARPU_NCUDA=2 ./application
```

2.4 Benchmarking StarPU

Some interesting benchmarks are installed among examples in \$STARPU_PATH/lib/starpu/examples/. Make sure to try various schedulers, for instance STARPU_SCHED=dmda.

2.4.1 Task Size Overhead

This benchmark gives a glimpse into how long a task should be (in μ s) for StarPU overhead to be low enough to keep efficiency. Running tasks_size_overhead.sh generates a plot of the speedup of tasks of various sizes, depending on the number of CPUs being used.



2.4.2 Data Transfer Latency

local_pingpong performs a ping-pong between the first two CUDA nodes, and prints the measured latency.

2.4.3 Matrix-Matrix Multiplication

sgemm and dgemm perform a blocked matrix-matrix multiplication using BLAS and cuBLAS. They output the obtained GFlops.

2.4.4 Cholesky Factorization

 $\verb|cholesky| x perform a Cholesky factorization (single precision). They use different dependency primitives.$

2.4.5 LU Factorization

lu_* perform an LU factorization. They use different dependency primitives.

2.4.6 Simulated benchmarks

It can also be convenient to try simulated benchmarks, if you want to give a try at CPU-GPU scheduling without actually having a GPU at hand. This can be done by using the simgrid version of StarPU: first install the simgrid simulator from http://simgrid.gforge.inria.fr/ (we tested with simgrid from 3.11 to 3.16, and 3.18 to 3.22, other versions may have compatibility issues, 3.17 notably does not build at all. MPI simulation does not

work with version 3.22), then configure StarPU with --enable-simgrid and rebuild and install it, and then you can simulate the performance for a few virtualized systems shipped along StarPU: attila, mirage, idgraf, and sirocco. For instance:

```
$ export STARPU_PERF_MODEL_DIR=$STARPU_PATH/share/starpu/perfmodels/sampling
$ export STARPU_HOSTNAME=attila
$ $STARPU_PATH/lib/starpu/examples/cholesky_implicit -size $((960*20)) -nblocks 20
```

Will show the performance of the cholesky factorization with the attila system. It will be interesting to try with different matrix sizes and schedulers.

Performance models are available for <code>cholesky_*</code>, lu_* , *gemm, with block sizes 320, 640, or 960 (plus 1440 for sirocco), and for <code>stencil</code> with block size 128x128x128, 192x192x192, and 256x256x256.

Chapter 3

Basic Examples

3.1 Hello World

This section shows how to implement a simple program that submits a task to StarPU.

3.1.1 Required Headers

The header starpu.h should be included in any code using StarPU.

```
#include <starpu.h>
```

3.1.2 Defining A Codelet

A codelet is a structure that represents a computational kernel. Such a codelet may contain an implementation of the same kernel on different architectures (e.g. CUDA, x86, ...). For compatibility, make sure that the whole structure is properly initialized to zero, either by using the function starpu_codelet_init(), or by letting the compiler implicitly do it as examplified below.

The field starpu_codelet::nbuffers specifies the number of data buffers that are manipulated by the codelet: here the codelet does not access or modify any data that is controlled by our data management library.

We create a codelet which may only be executed on CPUs. When a CPU core will execute a codelet, it will call the function <code>cpu_func</code>, which <code>must</code> have the following prototype:

```
void (*cpu_func)(void *buffers[], void *cl_arg);
```

In this example, we can ignore the first argument of this function which gives a description of the input and output buffers (e.g. the size and the location of the matrices) since there is none. We also ignore the second argument which is a pointer to optional arguments for the codelet.

```
void cpu_func(void *buffers[], void *cl_arg)
{
    printf("Hello world\n");
}
struct starpu_codelet cl =
{
    .cpu_funcs = { cpu_func },
    .nbuffers = 0
};
```

3.1.3 Submitting A Task

Before submitting any tasks to StarPU, starpu_init() must be called. The NULL argument specifies that we use the default configuration. Tasks can then be submitted until the termination of StarPU – done by a call to starpu_ shutdown().

In the example below, a task structure is allocated by a call to starpu_task_create(). This function allocates and fills the task structure with its default settings, it does not submit the task to StarPU.

The field starpu_task::cl is a pointer to the codelet which the task will execute: in other words, the codelet structure describes which computational kernel should be offloaded on the different architectures, and the task structure is a wrapper containing a codelet and the piece of data on which the codelet should operate.

18 Basic Examples

If the field starpu_task::synchronous is non-zero, task submission will be synchronous: the function starpu_task __submit() will not return until the task has been executed. Note that the function starpu_shutdown() does not guarantee that asynchronous tasks have been executed before it returns, starpu_task_wait_for_all() can be used to this effect, or data can be unregistered (starpu_data_unregister()), which will implicitly wait for all the tasks scheduled to work on it, unless explicitly disabled thanks to starpu_data_set_default_sequential_consistency_flag() or starpu_data_set_sequential_consistency_flag().

```
int main(int argc, char **argv)
{
    /* initialize StarPU */
    starpu_init(NULL);

    struct starpu_task *task = starpu_task_create();

    task->cl = &cl; /* Pointer to the codelet defined above */

    /* starpu_task_submit will be a blocking call. If unset,
    starpu_task_wait() needs to be called after submitting the task. */
    task->synchronous = 1;

    /* submit the task to StarPU */
    starpu_task_submit(task);

    /* terminate StarPU */
    starpu_shutdown();

    return 0;
}
```

3.1.4 Execution Of Hello World

```
$ make hello_world
cc $(pkg-config --cflags starpu-1.3) hello_world.c -o hello_world $(pkg-config --libs starpu-1.3)
$ ./hello_world
Hello world
```

3.1.5 Passing Arguments To The Codelet

The optional field starpu_task::cl_arg_size) with some parameters for the kernel described by the codelet. For instance, if a codelet implements a computational kernel that multiplies its input vector by a constant, the constant could be specified by the means of this buffer, instead of registering it as a StarPU data. It must however be noted that StarPU avoids making copy whenever possible and rather passes the pointer as such, so the buffer which is pointed at must be kept allocated until the task terminates, and if several tasks are submitted with various parameters, each of them must be given a pointer to their own buffer.

```
struct params
{
    int i;
    float f;
};

void cpu_func(void *buffers[], void *cl_arg)
{
    struct params *params = cl_arg;
    printf("Hello world (params = {%i, %f} )\n", params->i, params->f);
}
```

As said before, the field starpu_codelet::nbuffers specifies the number of data buffers which are manipulated by the codelet. It does not count the argument — the parameter cl_arg of the function cpu_func — since it is not managed by our data management library, but just contains trivial parameters.

Be aware that this may be a pointer to a *copy* of the actual buffer, and not the pointer given by the programmer: if the codelet modifies this buffer, there is no guarantee that the initial buffer will be modified as well: this for instance implies that the buffer cannot be used as a synchronization medium. If synchronization is needed, data has to be registered to StarPU, see Vector Scaling.

```
int main(int argc, char **argv)
{
    /* initialize StarPU */
    starpu_init(NULL);

    struct starpu_task *task = starpu_task_create();

    task->cl = &cl; /* Pointer to the codelet defined above */
```

3.1 Hello World

```
struct params params = { 1, 2.0f };
task->cl_arg = &params;
task->cl_arg_size = sizeof(params);

/* starpu_task_submit will be a blocking call */
task->synchronous = 1;

/* submit the task to StarPU */
starpu_task_submit(task);

/* terminate StarPU */
starpu_shutdown();

return 0;
}

$ make hello_world
cc $(pkg-config --cflags starpu-1.3) hello_world.c -o hello_world $(pkg-config --libs starpu-1.3)
$ ./hello_world
Hello world (params = {1, 2.000000})
```

3.1.6 Defining A Callback

Once a task has been executed, an optional callback function starpu_task::callback_func is called when defined. While the computational kernel could be offloaded on various architectures, the callback function is always executed on a CPU. The pointer starpu_task::callback_arg is passed as an argument of the callback function. The prototype of a callback function must be:

```
void (*callback_function) (void *);
void callback func (void *callback arg)
    printf("Callback function (arg %x)\n", callback_arg);
int main(int argc, char **argv)
    /* initialize StarPU */
    starpu_init(NULL);
    struct starpu_task *task = starpu_task_create();
    task->cl = &cl: /* Pointer to the codelet defined above */
    task->callback_func = callback_func;
    task->callback_arg = 0x42;
    /* starpu_task_submit will be a blocking call */
    task->synchronous = 1;
    /* submit the task to StarPU */
    starpu_task_submit(task);
    /* terminate StarPU */
    starpu_shutdown();
    return 0;
}
$ make hello_world
cc $(pkg-config --cflags starpu-1.3) hello_world.c -o hello_world $(pkg-config --libs starpu-1.3)
$ ./hello_world
Hello world
Callback function (arg 42)
```

3.1.7 Where To Execute A Codelet

```
struct starpu_codelet cl =
{
    .where = STARPU_CPU,
    .cpu_funcs = { cpu_func },
    .cpu_funcs_name = { "cpu_func" },
    .nbuffers = 0
};
```

We create a codelet which may only be executed on the CPUs. The optional field starpu_codelet::where is a bitmask which defines where the codelet may be executed. Here, the value STARPU_CPU means that only CPUs

20 Basic Examples

can execute this codelet. When the optional field starpu_codelet::where is unset, its value is automatically set based on the availability of the different fields XXX_funcs.

TODO: explain starpu_codelet::cpu_funcs_name

3.2 Vector Scaling

The previous example has shown how to submit tasks. In this section, we show how StarPU tasks can manipulate data.

The full source code for this example is given in Full source code for the 'Scaling a Vector' example.

3.2.1 Source Code of Vector Scaling

Programmers can describe the data layout of their application so that StarPU is responsible for enforcing data coherency and availability across the machine. Instead of handling complex (and non-portable) mechanisms to perform data movements, programmers only declare which piece of data is accessed and/or modified by a task, and StarPU makes sure that when a computational kernel starts somewhere (e.g. on a GPU), its data are available locally.

Before submitting those tasks, the programmer first needs to declare the different pieces of data to StarPU using the functions starpu_*_data_register. To ease the development of applications for StarPU, it is possible to describe multiple types of data layout. A type of data layout is called an **interface**. There are different predefined interfaces available in StarPU: here we will consider the **vector interface**.

The following lines show how to declare an array of NX elements of type float using the vector interface:

The first argument, called the **data handle**, is an opaque pointer which designates the array within StarPU. This is also the structure which is used to describe which data is used by a task. The second argument is the node number where the data originally resides. Here it is STARPU_MAIN_RAM since the array vector is in the main memory. Then comes the pointer vector where the data can be found in main memory, the number of elements in the vector and the size of each element. The following shows how to construct a StarPU task that will manipulate the vector and a constant factor.

Since the factor is a mere constant float value parameter, it does not need a preliminary registration, and can just be passed through the pointer starpu_task::cl_arg like in the previous example. The vector parameter is described by its handle. starpu_task::handles should be set with the handles of the data, the access modes for the data are defined in the field starpu_task::handles should be set with the handles of the data, the access modes for the data are defined in the field starpu_codelet::modes (STARPU_R for read-only, STARPU_W for write-only and STARPU_RW for read and write access).

The definition of the codelet can be written as follows:

```
void scal_cpu_func(void *buffers[], void *cl_arg)
{
    unsigned i;
    float *factor = cl_arg;

    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* CPU copy of the vector pointer */
    float *val = (float *)STARPU_VECTOR_GET_PTR(buffers[0]);
    for (i = 0; i < n; i++)
        val[i] *= *factor;
}
struct starpu_codelet cl =</pre>
```

```
{
    .cpu_funcs = { scal_cpu_func },
    .cpu_funcs_name = { "scal_cpu_func" },
    .nbuffers = 1,
    .modes = { STARPU_RW }
}:
```

The first argument is an array that gives a description of all the buffers passed in the array starpu_task::handles. The size of this array is given by the field starpu_codelet::nbuffers. For the sake of genericity, this array contains pointers to the different interfaces describing each buffer. In the case of the **vector interface**, the location of the vector (resp. its length) is accessible in the starpu_vector_interface::ptr (resp. starpu_vector_interface::nx) of this interface. Since the vector is accessed in a read-write fashion, any modification will automatically affect future accesses to this vector made by other tasks.

The second argument of the function scal_cpu_func contains a pointer to the parameters of the codelet (given in starpu_task::cl_arg), so that we read the constant factor from this pointer.

3.2.2 Execution of Vector Scaling

```
$ make vector_scal
cc $(pkg-config --cflags starpu-1.3) vector_scal.c -o vector_scal $(pkg-config --libs starpu-1.3)
$ ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

3.3 Vector Scaling on an Hybrid CPU/GPU Machine

Contrary to the previous examples, the task submitted in this example may not only be executed by the CPUs, but also by a CUDA device.

3.3.1 Definition of the CUDA Kernel

The CUDA implementation can be written as follows. It needs to be compiled with a CUDA compiler such as nvcc, the NVIDIA CUDA compiler driver. It must be noted that the vector pointer returned by STARPU_VECTOR_GET PTR is here a pointer in GPU memory, so that it can be passed as such to the kernel call vector_mult_cuda.

3.3.2 Definition of the OpenCL Kernel

The OpenCL implementation can be written as follows. StarPU provides tools to compile a OpenCL kernel stored in a file.

```
__kernel void vector_mult_opencl(int nx, __global float* val, float factor)
{
      const int i = get_global_id(0);
      if (i < nx)
      {
            val[i] *= factor;
      }
}</pre>
```

22 Basic Examples

Contrary to CUDA and CPU, STARPU_VECTOR_GET_DEV_HANDLE has to be used, which returns a cl_mem (which is not a device pointer, but an OpenCL handle), which can be passed as such to the OpenCL kernel. The difference is important when using partitioning, see Partitioning Data.

```
#include <starpu.h>
extern struct starpu_opencl_program programs;
void scal_opencl_func(void *buffers[], void *_args)
    float *factor = _args;
   int id, devid, err;
                                         /* OpenCL specific code */
   cl_kernel kernel;
                                         /* OpenCL specific code */
   cl_command_queue queue;
                                         /* OpenCL specific code */
                                         /* OpenCL specific code */
   cl_event event;
   /* length of the vector */
   unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* OpenCL copy of the vector pointer */
   cl_mem val = (cl_mem)STARPU_VECTOR_GET_DEV_HANDLE(buffers[0]);
   { /* OpenCL specific code */
        id = starpu_worker_get_id();
        devid = starpu_worker_get_devid(id);
        devid):
        if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
        err = clSetKernelArg(kernel, 0, sizeof(n), &n);
        err |= clSetKernelArg(kernel, 1, sizeof(val), &val);
        err |= clSetKernelArg(kernel, 2, sizeof(*factor), factor);
if (err) STARPU_OPENCL_REPORT_ERROR(err);
       /* OpenCL specific code */
       size_t global=n;
       size_t local;
       size t s:
       cl device id device;
       starpu_opencl_get_device(devid, &device);
       err = clGetKernelWorkGroupInfo (kernel, device, CL_KERNEL_WORK_GROUP_SIZE, sizeof(local), &local, &
     s);
if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
       if (local > global) local=global;
       err = clEnqueueNDRangeKernel(queue, kernel, 1, NULL, &global, &local, 0, NULL, &event);
        if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
      /* OpenCL specific code */
        clFinish (queue);
        starpu_opencl_collect_stats(event);
        clReleaseEvent(event);
        starpu_opencl_release_kernel(kernel);
   }
}
```

3.3.3 Definition of the Main Code

The CPU implementation is the same as in the previous section.

Here is the source of the main application. You can notice that the fields starpu_codelet::cuda_funcs and starpu← _codelet::opencl_funcs are set to define the pointers to the CUDA and OpenCL implementations of the task.

```
/*
 * This example demonstrates how to use StarPU to scale an array by a factor.
 * It shows how to manipulate data with StarPU's data management library.
 * 1- how to declare a piece of data to StarPU (starpu_vector_data_register)
 * 2- how to describe which data are accessed by a task (task->handles[0])
 * 3- how a kernel can manipulate the data (buffers[0].vector.ptr)
 */
#include <starpu.h>

#define NX 2048

extern void scal_cpu_func(void *buffers[], void *_args);
extern void scal_cuda_func(void *buffers[], void *_args);
extern void scal_cuda_func(void *buffers[], void *_args);
extern void scal_opencl_func(void *buffers[], void *_args);
```

```
static struct starpu_codelet cl =
    .where = STARPU_CPU | STARPU_CUDA | STARPU_OPENCL,
    /\star CPU implementation of the codelet \star/
    .cpu_funcs = { scal_cpu_func, scal_sse_func },
.cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
#ifdef STARPU_USE_CUDA
    /\star CUDA implementation of the codelet \star/
    .cuda_funcs = { scal_cuda_func },
#endif
#ifdef STARPU USE OPENCL
   /* OpenCL implementation of the codelet */
    .opencl funcs = { scal opencl func },
#endif
    .nbuffers = 1,
    .modes = { STARPU_RW }
};
#ifdef STARPU_USE_OPENCL
struct starpu_opencl_program programs;
int main(int argc, char **argv)
    /* We consider a vector of float that is initialized just as any of C
      * data */
    float vector[NX];
    unsigned i;
    for (i = 0; i < NX; i++)</pre>
        vector[i] = 1.0f;
    fprintf(stderr, "BEFORE: First element was f^n, vector[0]);
    /\star Initialize StarPU with default configuration \star/
    starpu_init(NULL);
#ifdef STARPU USE OPENCL
    starpu_opencl_load_opencl_from_file("
      examples/basic_examples/vector_scal_opencl_kernel.cl", &programs, NULL);
#endif
    /* Tell StaPU to associate the "vector" vector with the "vector_handle"
     \star identifier. When a task needs to access a piece of data, it should
     * refer to the handle that is associated to it.
* In the case of the "vector" data interface:
         the first argument of the registration method is a pointer to the
         handle that should describe the data
     \star\, - the second argument is the memory node where the data (ie. "vector")
          resides initially: STARPU_MAIN_RAM stands for an address in main memory, as
          opposed to an adress on a GPU for instance.
     \star - the third argument is the adress of the vector in RAM
     \star - the fourth argument is the number of elements in the vector
        - the fifth argument is the size of each element.
    starpu_data_handle_t vector_handle;
    starpu vector data register(&vector handle, STARPU MAIN RAM,
      (uintptr_t) vector, NX, sizeof(vector[0]));
    float factor = 3.14;
    /* create a synchronous task: any call to starpu_task_submit will block
      * until it is terminated */
    struct starpu_task *task = starpu_task_create();
    task->synchronous = 1;
    task->cl = &cl;
    /\star the codelet manipulates one buffer in RW mode \star/
    task->handles[0] = vector handle;
    /\star an argument is passed to the codelet, beware that this is a
     \star READ-ONLY buffer and that the codelet may be given a pointer to a
     \star COPY of the argument \star/
    task->cl_arg = &factor;
    task->cl arg size = sizeof(factor);
    /\star execute the task on any eligible computational ressource \star/
    starpu_task_submit(task);
    /* StarPU does not need to manipulate the array anymore so we can stop
      * monitoring it */
    starpu_data_unregister(vector_handle);
#ifdef STARPU_USE_OPENCL
    starpu_opencl_unload_opencl(&programs);
#endif
```

24 Basic Examples

```
/* terminate StarPU, no task can be submitted after */
starpu_shutdown();

fprintf(stderr, "AFTER First element is %f\n", vector[0]);

return 0;
}
```

3.3.4 Execution of Hybrid Vector Scaling

The Makefile given at the beginning of the section must be extended to give the rules to compile the CUDA source code. Note that the source file of the OpenCL kernel does not need to be compiled now, it will be compiled at run-time when calling the function starpu_opencl_load_opencl_from_file().

```
CFLAGS += $(shell pkg-config --cflags starpu-1.3)
LDLIBS += $(shell pkg-config --libs starpu-1.3)
         = qcc
vector_scal: vector_scal.o vector_scal_cpu.o vector_scal_cuda.o vector_scal_opencl.o
%.o: %.cu
       nvcc $(CFLAGS) $< -c $@
clean:
       rm -f vector_scal *.o
$ make
and to execute it, with the default configuration:
$ ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
or for example, by disabling CPU devices:
$ STARPU_NCPU=0 ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
or by disabling CUDA devices (which may permit to enable the use of OpenCL, see Enabling OpenCL):
$ STARPU_NCUDA=0 ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

Part II StarPU Quick Programming Guide

Chapter 4

Advanced Examples

TODO

28 Advanced Examples

Chapter 5

Check List When Performance Are Not There

TODO: improve!

To achieve good performance, we give below a list of features which should be checked.

For a start, you can use Offline Performance Tools to get a Gantt chart which will show roughly where time is spent, and focus correspondingly.

5.1 Check Task Size

Make sure that your tasks are not too small, because the StarPU runtime overhead is not completely zero. You can run the tasks_size_overhead.sh script to get an idea of the scalability of tasks depending on their duration (in μ s), on your own system.

Typically, 10µs-ish tasks are definitely too small, the CUDA overhead itself is much bigger than this.

1ms-ish tasks may be a good start, but will not necessarily scale to many dozens of cores, so it's better to try to get 10ms-ish tasks.

Tasks durations can easily be observed when performance models are defined (see Performance Model Example) by using the starpu_perfmodel_plot or starpu_perfmodel_display tool (see Performance Of Codelets)

When using parallel tasks, the problem is even worse since StarPU has to synchronize the execution of tasks.

5.2 Configuration Which May Improve Performance

The --enable-fast configure option disables all assertions. This makes StarPU more performant for really small tasks by disabling all sanity checks. Only use this for measurements and production, not for development, since this will drop all basic checks.

5.3 Data Related Features Which May Improve Performance

link to Data Management link to Data Prefetch

5.4 Task Related Features Which May Improve Performance

link to Task Granularity link to Task Submission link to Task Priorities

5.5 Scheduling Related Features Which May Improve Performance

link to Task Scheduling Policies

link to Task Distribution Vs Data Transfer

link to Energy-based Scheduling

link to Static Scheduling

5.6 CUDA-specific Optimizations

For proper overlapping of asynchronous GPU data transfers, data has to be pinned by CUDA. Data allocated with starpu_malloc() is always properly pinned. If the application is registering to StarPU some data which has not been allocated with starpu_malloc(), it should use starpu_memory_pin() to pin it.

Due to CUDA limitations, StarPU will have a hard time overlapping its own communications and the codelet computations if the application does not use a dedicated CUDA stream for its computations instead of the default stream, which synchronizes all operations of the GPU. StarPU provides one by the use of starpu_cuda_get_local_stream() which can be used by all CUDA codelet operations to avoid this issue. For instance:

```
func <<<grid,block,0,starpu_cuda_get_local_stream()>>> (foo, bar);
cudaStreamSynchronize(starpu_cuda_get_local_stream());
```

as well as the use of cudaMemcpyAsync(), etc. for each CUDA operation one needs to use a version that takes the a stream parameter.

Unfortunately, some CUDA libraries do not have stream variants of kernels. This will seriously lower the potential for overlapping. If some CUDA calls are made without specifying this local stream, synchronization needs to be explicited with cudaThreadSynchronize() around these calls, to make sure that they get properly synchronized with the calls using the local stream. Notably, <code>cudaMemcpy()</code> and <code>cudaMemset()</code> are actually asynchronous and need such explicit synchronization! Use <code>cudaMemcpyAsync()</code> and <code>cudaMemsetAsync()</code> instead.

Calling starpu_cublas_init() makes StarPU already do appropriate calls for the CUBLAS library. Some libraries like Magma may however change the current stream of CUBLAS v1, one then has to call cublasSetKernel Stream(starpu_cuda_get_local_stream()) at the beginning of the codelet to make sure that CUBLAS is really using the proper stream. When using CUBLAS v2, starpu_cublas_get_local_handle() can be called to queue CU BLAS kernels with the proper configuration.

Similarly, calling starpu_cusparse_init() makes StarPU create CUSPARSE handles on each CUDA device, starpucusparse get local handle() can then be used to queue CUSPARSE kernels with the proper configuration.

If the kernel can be made to only use this local stream or other self-allocated streams, i.e. the whole kernel submission can be made asynchronous, then one should enable asynchronous execution of the kernel. This means setting the flag STARPU_CUDA_ASYNC in the corresponding field starpu_codelet::cuda_flags, and dropping the cudaStreamSynchronize() call at the end of the cuda_func function, so that it returns immediately after having queued the kernel to the local stream. That way, StarPU will be able to submit and complete data transfers while kernels are executing, instead of only at each kernel submission. The kernel just has to make sure that StarPU can use the local stream to synchronize with the kernel startup and completion.

If the kernel uses its own non-default stream, one can synchronize this stream with the StarPU-provided stream this way:

```
cudaEvent_t event;
call_kernel_with_its_own_stream()
cudaEventCreateWithFlags(&event, cudaEventDisableTiming);
cudaEventRecord(event, get_kernel_stream());
cudaStreamWaitEvent(starpu_cuda_get_local_stream(), event, 0);
cudaEventDestroy(event);
```

This code makes the StarPU-provided stream wait for a new event, which will be triggered by the completion of the kernel

Using the flag STARPU_CUDA_ASYNC also permits to enable concurrent kernel execution, on cards which support it (Kepler and later, notably). This is enabled by setting the environment variable STARPU_NWORKER_PER_C UDA to the number of kernels to execute concurrently. This is useful when kernels are small and do not feed the whole GPU with threads to run.

Concerning memory allocation, you should really not use ${\tt cudaMalloc/cudaFree}$ within the kernel, since ${\tt cudaFree}$ introduces a awfully lot of synchronizations within CUDA itself. You should instead add a parameter to the codelet with the STARPU_SCRATCH mode access. You can then pass to the task a handle registered with the desired size but with the NULL pointer, that handle can even be the shared between tasks, StarPU will allocate per-task data on the fly before task execution, and reuse the allocated data between tasks.

See examples/pi/pi_redux.c for an example of use.

5.7 OpenCL-specific Optimizations

If the kernel can be made to only use the StarPU-provided command queue or other self-allocated queues, i.e. the whole kernel submission can be made asynchronous, then one should enable asynchronous execution of the kernel. This means setting the flag STARPU_OPENCL_ASYNC in the corresponding field starpu_codelet::opencl flags and dropping the clfinish() and starpu_opencl_collect_stats() calls at the end of the kernel, so that it returns immediately after having queued the kernel to the provided queue. That way, StarPU will be able to submit and complete data transfers while kernels are executing, instead of only at each kernel submission. The kernel just has to make sure that StarPU can use the command queue it has provided to synchronize with the kernel startup and completion.

5.8 Detecting Stuck Conditions

It may happen that for some reason, StarPU does not make progress for a long period of time. Reason are sometimes due to contention inside StarPU, but sometimes this is due to external reasons, such as stuck MPI driver, or CUDA driver, etc.

```
export STARPU_WATCHDOG_TIMEOUT=10000 (STARPU_WATCHDOG_TIMEOUT)
```

allows to make StarPU print an error message whenever StarPU does not terminate any task for 10ms, but lets the application continue normally. In addition to that,

```
export STARPU_WATCHDOG_CRASH=1 (STARPU_WATCHDOG_CRASH)
```

raises SIGABRT in this condition, thus allowing to catch the situation in gdb. It can also be useful to type handle SIGABRT nopass in gdb to be able to let the process continue, after inspecting the state of the process.

5.9 How to Limit Memory Used By StarPU And Cache Buffer Allocations

By default, StarPU makes sure to use at most 90% of the memory of GPU devices, moving data in and out of the device as appropriate and with prefetch and writeback optimizations. Concerning the main memory, by default it will not limit its consumption, since by default it has nowhere to push the data to when memory gets tight. This also means that by default StarPU will not cache buffer allocations in main memory, since it does not know how much of the system memory it can afford.

In the case of GPUs, the STARPU_LIMIT_CUDA_MEM, STARPU_LIMIT_CUDA_devid_MEM, STARPU_LIMIT ← _OPENCL_MEM, and STARPU_LIMIT_OPENCL_devid_MEM environment variables can be used to control how much (in MiB) of the GPU device memory should be used at most by StarPU (their default values are 90% of the available memory).

In the case of the main memory, the STARPU_LIMIT_CPU_MEM environment variable can be used to specify how much (in MiB) of the main memory should be used at most by StarPU for buffer allocations. This way, StarPU will be able to cache buffer allocations (which can be a real benefit if a lot of bufferes are involved, or if allocation fragmentation can become a problem), and when using Out Of Core, StarPU will know when it should evict data out to the disk.

It should be noted that by default only buffer allocations automatically done by StarPU are accounted here, i.e. allocations performed through starpu_malloc_on_node() which are used by the data interfaces (matrix, vector, etc.). This does not include allocations performed by the application through e.g. malloc(). It does not include allocations performed through starpu_malloc() either, only allocations performed explicitly with the STARPU_MALLOC_CO UNT flag, i.e. by calling

```
starpu_malloc_flags(STARPU_MALLOC_COUNT)
```

are taken into account. If the application wants to make StarPU aware of its own allocations, so that StarPU knows precisely how much data is allocated, and thus when to evict allocation caches or data out to the disk, starpu_\to\text{memory_allocate()} can be used to specify an amount of memory to be accounted for. starpu_memory_deallocate() can be used to account freed memory back. Those can for instance be used by data interfaces with dynamic data buffers: instead of using starpu_malloc_on_node(), they would dynamically allocate data with malloc/realloc, and notify starpu of the delta thanks to starpu_memory_allocate() and starpu_memory_deallocate() calls.

starpu_memory_get_total() and starpu_memory_get_available() can be used to get an estimation of how much memory is available. starpu_memory_wait_available() can also be used to block until an amount of memory becomes available, but it may be preferrable to call

```
starpu_memory_allocate(STARPU_MEMORY_WAIT)
```

to reserve this amount immediately.

5.10 How To Reduce The Memory Footprint Of Internal Data Structures

It is possible to reduce the memory footprint of the task and data internal structures of StarPU by describing the shape of your machine and/or your application at the configure step.

To reduce the memory footprint of the data internal structures of StarPU, one can set the --enable-maxcpus, --enable-maxnumanodes, --enable-maxcudadev, --enable-maxopencidev and --enable-maxnodes configure parameters to give StarPU the architecture of the machine it will run on, thus tuning the size of the structures to the machine.

To reduce the memory footprint of the task internal structures of StarPU, one can set the --enable-maxbuffers configure parameter to give StarPU the maximum number of buffers that a task can use during an execution. For example, in the Cholesky factorization (dense linear algebra application), the GEMM task uses up to 3 buffers, so it is possible to set the maximum number of task buffers to 3 to run a Cholesky factorization on StarPU.

The size of the various structures of StarPU can be printed by tests/microbenchs/display_← structures_size.

It is also often useless to submit *all* the tasks at the same time. One can make the starpu_task_submit() function block when a reasonable given number of tasks have been submitted, by setting the STARPU_LIMIT_MIN_SUB
MITTED_TASKS and STARPU_LIMIT_MAX_SUBMITTED_TASKS environment variables, for instance:

```
export STARPU_LIMIT_MAX_SUBMITTED_TASKS=10000
export STARPU_LIMIT_MIN_SUBMITTED_TASKS=9000
```

To make StarPU block submission when 10000 tasks are submitted, and unblock submission when only 9000 tasks are still submitted, i.e. 1000 tasks have completed among the 10000 which were submitted when submission was blocked. Of course this may reduce parallelism if the threshold is set too low. The precise balance depends on the application task graph.

An idea of how much memory is used for tasks and data handles can be obtained by setting the STARPU_MAX — _MEMORY_USE environment variable to 1.

5.11 How To Reuse Memory

When your application needs to allocate more data than the available amount of memory usable by StarPU (given by starpu_memory_get_available()), the allocation cache system can reuse data buffers used by previously executed tasks. For this system to work with MPI tasks, you need to submit tasks progressively instead of as soon as possible, because in the case of MPI receives, the allocation cache check for reusing data buffers will be done at submission time, not at execution time.

You have two options to control the task submission flow. The first one is by controlling the number of submitted tasks during the whole execution. This can be done whether by setting the environment variables STARPU_\Limit_LIMIT_MAX_SUBMITTED_TASKS and STARPU_LIMIT_MIN_SUBMITTED_TASKS to tell StarPU when to stop submitting tasks and when to wake up and submit tasks again, or by explicitely calling starpu_task_wait_for_n\Limits_submitted() in your application code for finest grain control (for example, between two iterations of a submission loop).

The second option is to control the memory size of the allocation cache. This can be done in the application by using jointly starpu_memory_get_available() and starpu_memory_wait_available() to submit tasks only when there is enough memory space to allocate the data needed by the task, i.e when enough data are available for reuse in the allocation cache.

5.12 Performance Model Calibration

Most schedulers are based on an estimation of codelet duration on each kind of processing unit. For this to be possible, the application programmer needs to configure a performance model for the codelets of the application (see Performance Model Example for instance). History-based performance models use on-line calibration. StarPU will automatically calibrate codelets which have never been calibrated yet, and save the result in \$STARPU_HO ME/.starpu/sampling/codelets. The models are indexed by machine name.

By default, StarPU stores separate performance models according to the hostname of the system. To avoid having to calibrate performance models for each node of a homogeneous cluster for instance, the model can be shared by using export STARPU_HOSTNAME=some_global_name (STARPU_HOSTNAME), where some_global — name is the name of the cluster for instance, which thus overrides the hostname of the system.

By default, StarPU stores separate performance models for each GPU. To avoid having to calibrate performance models for each GPU of a homogeneous set of GPU devices for instance, the model can be shared

by setting export STARPU_PERF_MODEL_HOMOGENEOUS_CUDA=1 (STARPU_PERF_MODEL_HOMOG← ENEOUS_CUDA), export STARPU_PERF_MODEL_HOMOGENEOUS_OPENCL=1 (STARPU_PERF_MOD← EL_HOMOGENEOUS_OPENCL), export STARPU_PERF_MODEL_HOMOGENEOUS_MIC=1 (STARPU_P← ERF_MODEL_HOMOGENEOUS_MIC), export STARPU_PERF_MODEL_HOMOGENEOUS_MPI_MS=1 (S← TARPU_PERF_MODEL_HOMOGENEOUS_MPI_MS) depending on your GPU device type.


To force continuing calibration, use <code>export STARPU_CALIBRATE=1</code> (STARPU_CALIBRATE). This may be necessary if your application has not-so-stable performance. StarPU will force calibration (and thus ignore the current result) until 10 (<code>_STARPU_CALIBRATION_MINIMUM</code>) measurements have been made on each architecture, to avoid badly scheduling tasks just because the first measurements were not so good. Details on the current performance model status can be obtained from the tool <code>starpu_perfmodel_display</code>: the <code>-l</code> option lists the available performance models, and the <code>-s</code> option permits to choose the performance model to be displayed. The result looks like:


```
$ starpu_perfmodel_display -s starpu_slu_lu_model_11
performance model for cpu_impl_0
# hash
         size
                  flops
                               mean
                                              dev
914f3bef
         1048576
                  0.000000e+00
                                2.503577e+04
                                              1.982465e+02
                  0.000000e+00 5.527003e+02
3e921964 65536
                                              1.848114e+01
e5a07e31 4096
                  0.000000e+00 1.717457e+01 5.190038e+00
```

Which shows that for the LU 11 kernel with a 1MiB matrix, the average execution time on CPUs was about 25ms, with a 0.2ms standard deviation, over 8 samples. It is a good idea to check this before doing actual performance measurements.

A graph can be drawn by using the tool starpu_perfmodel_plot:

```
$ starpu_perfmodel_plot -s starpu_slu_lu_model_11
4096 16384 65536 262144 1048576 4194304
$ gnuplot starpu_starpu_slu_lu_model_11.gp
$ gv starpu_starpu_slu_lu_model_11.eps
```





If a kernel source code was modified (e.g. performance improvement), the calibration information is stale and should be dropped, to re-calibrate from start. This can be done by using export STARPU_CALIBRATE=2 (STARPU_CALIBRATE).

Note: history-based performance models get calibrated only if a performance-model-based scheduler is chosen. The history-based performance models can also be explicitly filled by the application without execution, if e.g. the application already has a series of measurements. This can be done by using starpu_perfmodel_update_history(), for instance:

```
static struct starpu_perfmodel perf_model =
    .type = STARPU_HISTORY_BASED,
    .symbol = "my_perfmodel",
struct starpu_codelet cl =
    .cuda_funcs = { cuda_func1, cuda_func2 },
    .nbuffers = 1,
    .modes = {STARPU_W},
    .model = &perf_model
void feed(void)
    struct my_measure *measure;
    struct starpu_task task;
    starpu_task_init(&task);
    task.cl = &cl:
    for (measure = &measures[0]; measure < measures[last]; measure++)</pre>
        starpu_data_handle_t handle;
        starpu_vector_data_register(&handle, -1, 0, measure->size, sizeof(float)
        task.handles[0] = handle;
        starpu_perfmodel_update_history(&perf_model, &task,
      STARPU_CUDA_DEFAULT + measure->cudadev, 0, measure->implementation, measure->time);
        starpu_task_clean(&task);
        starpu_data_unregister(handle);
```

Measurement has to be provided in milliseconds for the completion time models, and in Joules for the energy consumption models.

5.13 Profiling

A quick view of how many tasks each worker has executed can be obtained by setting <code>export STARPU_WO</code>CHER_STATS=1 (STARPU_WORKER_STATS). This is a convenient way to check that execution did happen on accelerators, without penalizing performance with the profiling overhead.

A quick view of how much data transfers have been issued can be obtained by setting export STARPU_BUS← _STATS=1 (STARPU BUS STATS).

More detailed profiling information can be enabled by using <code>export STARPU_PROFILING=1</code> (STARPU_P ROFILING) or by calling starpu_profiling_status_set() from the source code. Statistics on the execution can then be obtained by using <code>export STARPU_BUS_STATS=1</code> and <code>export STARPU_WORKER_STATS=1</code>. More details on performance feedback are provided in the next chapter.

5.14 Overhead Profiling

Offline Performance Tools can already provide an idea of to what extent and which part of StarPU bring overhead on the execution time. To get a more precise analysis of the parts of StarPU which bring most overhead, <code>gprof</code> can be used.

First, recompile and reinstall StarPU with gprof support:

```
./configure --enable-perf-debug --disable-shared --disable-build-tests --disable-build-examples
```

Make sure not to leave a dynamic version of StarPU in the target path: remove any remaining libstarpu-*.so Then relink your application with the static StarPU library, make sure that running ldd on your application does not mention any libstarpu (i.e. it's really statically-linked).

```
gcc test.c -o test $(pkg-config --cflags starpu-1.3) $(pkg-config --libs starpu-1.3)
```

5.14 Overhead Profiling 35

Now you can run your application, and a gmon.out file should appear in the current directory, you can process it by running gprof on your application:

gprof ./test

This will dump an analysis of the time spent in StarPU functions.

Part III StarPU Inside

Chapter 6

Tasks In StarPU

6.1 Task Granularity

Like any other runtime, StarPU has some overhead to manage tasks. Since it does smart scheduling and data management, this overhead is not always neglectable. The order of magnitude of the overhead is typically a couple of microseconds, which is actually quite smaller than the CUDA overhead itself. The amount of work that a task should do should thus be somewhat bigger, to make sure that the overhead becomes neglectible. The offline performance feedback can provide a measure of task length, which should thus be checked if bad performance are observed. To get a grasp at the scalability possibility according to task size, one can run tests/microbenchs/tasks_csize_overhead.sh which draws curves of the speedup of independent tasks of very small sizes.

The choice of scheduler also has impact over the overhead: for instance, the scheduler <code>dmda</code> takes time to make a decision, while <code>eager</code> does not. <code>tasks_size_overhead.sh</code> can again be used to get a grasp at how much impact that has on the target machine.

6.2 Task Submission

To let StarPU make online optimizations, tasks should be submitted asynchronously as much as possible. Ideally, all the tasks should be submitted, and mere calls to starpu_data_unregister() be done to wait for termination. StarPU will then be able to rework the whole schedule, overlap computation with communication, manage accelerator local memory usage, etc.

6.3 Task Priorities

By default, StarPU will consider the tasks in the order they are submitted by the application. If the application programmer knows that some tasks should be performed in priority (for instance because their output is needed by many other tasks and may thus be a bottleneck if not executed early enough), the field starpu_task::priority should be set to transmit the priority information to StarPU.

6.4 Task Dependencies

6.4.1 Sequential Consistency

By default, task dependencies are inferred from data dependency (sequential coherency) by StarPU. The application can however disable sequential coherency for some data, and dependencies can be specifically expressed. Setting (or unsetting) sequential consistency can be done at the data level by calling starpu_data_set_sequential consistency_flag() for a specific data or starpu_data_set_default_sequential_consistency_flag() for all datas. Setting (or unsetting) sequential consistency can also be done at task level by setting the field starpu_task ::sequential consistency to 0.

Sequential consistency can also be set (or unset) for each handle of a specific task, this is done by using the field starpu_task::handles_sequential_consistency. When set, its value should be a array with the number of elements being the number of handles for the task, each element of the array being the sequential consistency for the i-th

40 Tasks In StarPU

handle of the task. The field can easily be set when calling starpu_task_insert() with the flag STARPU_HANDLE ← S SEQUENTIAL CONSISTENCY

The internal algorithm used by StarPU to set up implicit dependency is as follows:

```
if (sequential_consistency(task) == 1)
    for (i=0; i<STARPU_TASK_GET_NBUFFERS(task); i++)
    if (sequential_consistency(i-th data, task) == 1)
    if (sequential_consistency(i-th data) == 1)
        create_implicit_dependency(...)</pre>
```

6.4.2 Tasks And Tags Dependencies

One can explicitely set dependencies between tasks using starpu_task_declare_deps() or starpu_task_declare← _deps_array(). Dependencies between tasks can be expressed through tags associated to a tag with the field starpu_task::tag_id and using the function starpu_tag_declare_deps() or starpu_tag_declare_deps_array().

The termination of a task can be delayed through the function starpu_task_end_dep_add() which specifies the number of calls to the function starpu_task_end_dep_release() needed to trigger the task termination. One can also use starpu_task_declare_end_deps() or starpu_task_declare_end_deps_array() to delay the termination of a task until the termination of other tasks.

6.5 Setting Many Data Handles For a Task

The maximum number of data a task can manage is fixed by the environment variable STARPU_NMAXBUFS which has a default value which can be changed through the configure option --enable-maxbuffers.

However, it is possible to define tasks managing more data by using the field starpu_task::dyn_handles when defining a task and the field starpu_codelet::dyn_modes when defining the corresponding codelet.

```
enum starpu_data_access_mode modes[STARPU_NMAXBUFS+1] =
        STARPU_R, STARPU_R, ...
} ;
struct starpu codelet dummy big cl =
        .cuda_funcs = { dummy_big_kernel },
        .opencl_funcs = { dummy_big_kernel },
        .cpu_funcs = { dummy_big_kernel },
.cpu_funcs_name = { "dummy_big_kernel" },
        .nbuffers = STARPU_NMAXBUFS+1,
        .dyn_modes = modes
};
task = starpu_task_create();
task->cl = &dummy_big_cl;
task->dyn_handles = malloc(task->cl->nbuffers * sizeof(starpu_data_handle_t));
for(i=0; i<task->cl->nbuffers; i++)
        task->dyn_handles[i] = handle;
starpu_task_submit(task);
starpu data handle t *handles = malloc(dummy big cl.nbuffers * sizeof(
      starpu_data_handle_t));
for(i=0; i<dummy_big_cl.nbuffers; i++)</pre>
        handles[i] = handle;
starpu_task_insert(&dummy_big_cl,
                   STARPU_VALUE, &dummy_big_cl.nbuffers, sizeof(dummy_big_cl.nbuffers
      ),
                   STARPU_DATA_ARRAY, handles, dummy_big_cl.nbuffers,
```

The whole code for this complex data interface is available in the directory examples/basic_← examples/dynamic_handles.c.

6.6 Setting a Variable Number Of Data Handles For a Task

Normally, the number of data handles given to a task is fixed in the starpu_codelet::nbuffers codelet field. This field can however be set to STARPU_VARIABLE_NBUFFERS, in which case the starpu_task::nbuffers task field must be set, and the starpu_task::modes field (or starpu_task::dyn_modes field, see Setting Many Data Handles For a Task) should be used to specify the modes for the handles.

6.7 Using Multiple Implementations Of A Codelet

One may want to write multiple implementations of a codelet for a single type of device and let StarPU choose which one to run. As an example, we will show how to use SSE to scale a vector. The codelet can be written as follows:

```
#include <xmmintrin.h>
void scal_sse_func(void *buffers[], void *cl_arg)
    float *vector = (float *) STARPU_VECTOR_GET_PTR(buffers[0]);
unsigned int n = STARPU_VECTOR_GET_NX(buffers[0]);
    unsigned int n_iterations = n/4;
    if (n % 4 != 0)
        n_iterations++;
    __m128 *VECTOR = (__m128*) vector;
      _m128 factor __attribute__((aligned(16)));
    factor = _mm_set1_ps(*(float *) cl_arg);
    unsigned int i;
    for (i = 0; i < n_iterations; i++)</pre>
        VECTOR[i] = _mm_mul_ps(factor, VECTOR[i]);
struct starpu_codelet cl =
    .cpu_funcs = { scal_cpu_func, scal_sse_func },
    .cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
    .nbuffers = 1.
    .modes = { STARPU_RW }
```

Schedulers which are multi-implementation aware (only dmda and pheft for now) will use the performance models of all the implementations it was given, and pick the one which seems to be the fastest.

6.8 Enabling Implementation According To Capabilities

Some implementations may not run on some devices. For instance, some CUDA devices do not support double floating point precision, and thus the kernel execution would just fail; or the device may not have enough shared memory for the implementation being used. The field starpu_codelet::can_execute permits to express this. For instance:

```
static int can_execute(unsigned workerid, struct starpu_task *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) == STARPU_CPU_WORKER)
    return 1:
  /* Cuda device */
 props = starpu_cuda_get_device_properties(workerid);
     (props->major >= 2 || props->minor >= 3)
      At least compute capability 1.3, supports doubles \star/
  /* Old card, does not support doubles */
  return 0:
struct starpu_codelet cl =
    .can_execute = can_execute,
    .cpu_funcs = { cpu_func },
    .cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { gpu_func }
    .nbuffers = 1,
    .modes = { STARPU_RW }
```

This can be essential e.g. when running on a machine which mixes various models of CUDA devices, to take benefit from the new models without crashing on old models.

42 Tasks In StarPU

Note: the function starpu_codelet::can_execute is called by the scheduler each time it tries to match a task with a worker, and should thus be very fast. The function starpu_cuda_get_device_properties() provides a quick access to CUDA properties of CUDA devices to achieve such efficiency.

Another example is to compile CUDA code for various compute capabilities, resulting with two CUDA functions, e.g. $scal_gpu_13$ for compute capability 1.3, and $scal_gpu_20$ for compute capability 2.0. Both functions can be provided to StarPU by using starpu_codelet::cuda_funcs, and starpu_codelet::can_execute can then be used to rule out the $scal_gpu_20$ variant on a CUDA device which will not be able to execute it:

```
static int can_execute(unsigned workerid, struct starpu_task *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) == STARPU_CPU_WORKER)
    return 1;
  /* Cuda device */
  if (nimpl == 0)
    /\star Trying to execute the 1.3 capability variant, we assume it is ok in all cases. \star/
    return 1:
  /\star Trying to execute the 2.0 capability variant, check that the card can do it. \star/
  props = starpu_cuda_get_device_properties(workerid);
if (props->major >= 2 || props->minor >= 0)
    /\star At least compute capability 2.0, can run it \star/
    return 1:
  /\star Old card, does not support 2.0, will not be able to execute the 2.0 variant. \star/
  return 0;
struct starpu codelet cl =
    .can_execute = can_execute,
    .cpu_funcs = { cpu_func },
.cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { scal_gpu_13, scal_gpu_20 },
    .nbuffers = 1,
    .modes = { STARPU_RW }
```

Another example is having specialized implementations for some given common sizes, for instance here we have a specialized implementation for 1024x1024 matrices:

```
static int can_execute(unsigned workerid, struct starpu_task *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) == STARPU_CPU_WORKER)
    return 1;
  /* Cuda device */
  switch (nimpl)
     /\star Trying to execute the generic capability variant.
    case 1:
      /* Trying to execute the size == 1024 specific variant. */
      struct starpu_matrix_interface *interface = starpu_data_get_interface_on_node
      (task->handles[0]);
         urn STARPU_MATRIX_GET_NX(interface) == 1024 && STARPU_MATRIX_GET_NY
      (interface == 1024);
 }
struct starpu_codelet cl =
    .can_execute = can_execute,
    .cpu_funcs = { cpu_func },
.cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { potrf_gpu_generic, potrf_gpu_1024 },
    .nbuffers = 1,
    .modes = { STARPU_RW }
```

Note: the most generic variant should be provided first, as some schedulers are not able to try the different variants.

6.9 Insert Task Utility

StarPU provides the wrapper function starpu_task_insert() to ease the creation and submission of tasks. Here the implementation of the codelet:

6.9 Insert Task Utility 43

```
void func_cpu(void *descr[], void *_args)
        int *x0 = (int *)STARPU_VARIABLE_GET_PTR(descr[0]);
        float *x1 = (float *)STARPU_VARIABLE_GET_PTR(descr[1]);
        int ifactor:
        float ffactor:
        starpu_codelet_unpack_args(_args, &ifactor, &ffactor);
        *x0 = *x0 * ifactor;
        *x1 = *x1 * ffactor;
struct starpu codelet mycodelet =
        .cpu_funcs = { func_cpu },
        .cpu_funcs_name = { "func_cpu" },
        .nbuffers = 2.
        .modes = { STARPU_RW, STARPU_RW }
};
And the call to the function starpu_task_insert():
starpu task insert(&mycodelet,
                    STARPU_VALUE, &ifactor, sizeof(ifactor),
                   STARPU_VALUE, &ffactor, sizeof(ffactor),
                   STARPU_RW, data_handles[0],
                   STARPU_RW, data_handles[1],
```

The call to starpu_task_insert() is equivalent to the following code:

Here a similar call using ::STARPU_DATA_ARRAY.

If some part of the task insertion depends on the value of some computation, the macro STARPU_DATA_AC \leftarrow QUIRE_CB can be very convenient. For instance, assuming that the index variable i was registered as handle A_handle[i]:

The macro STARPU_DATA_ACQUIRE_CB submits an asynchronous request for acquiring data i for the main application, and will execute the code given as third parameter when it is acquired. In other words, as soon as the value of i computed by the codelet which_index can be read, the portion of code passed as third parameter of STARPU_DATA_ACQUIRE_CB will be executed, and is allowed to read from i to use it e.g. as an index. Note that this macro is only avaible when compiling StarPU with the compiler gcc.

StarPU also provides a utility function starpu_codelet_unpack_args() to retrieve the STARPU_VALUE arguments passed to the task. There is several ways of calling this function starpu_codelet_unpack_args().

```
void func_cpu(void *descr[], void *_args)
{
    int ifactor;
    float ffactor;

    starpu_codelet_unpack_args(_args, &ifactor, &ffactor);
}
```

44 Tasks In StarPU

```
void func_cpu(void *descr[], void *_args)
{
    int ifactor;
    float ffactor;

    starpu_codelet_unpack_args(_args, &ifactor, 0);
    starpu_codelet_unpack_args(_args, &ifactor, &ffactor);
}

void func_cpu(void *descr[], void *_args)
{
    int ifactor;
    float ffactor;
    char buffer[100];

    starpu_codelet_unpack_args_and_copyleft(_args, buffer, 100, &ifactor, 0);
    starpu_codelet_unpack_args(buffer, &ffactor);
}
```

6.10 Getting Task Children

It may be interesting to get the list of tasks which depend on a given task, notably when using implicit dependencies, since this list is computed by StarPU. starpu task get task succs() provides it. For instance:

```
struct starpu_task *tasks[4];
ret = starpu_task_get_task_succs(task, sizeof(tasks)/sizeof(*tasks), tasks);
```

6.11 Parallel Tasks

StarPU can leverage existing parallel computation libraries by the means of parallel tasks. A parallel task is a task which gets worked on by a set of CPUs (called a parallel or combined worker) at the same time, by using an existing parallel CPU implementation of the computation to be achieved. This can also be useful to improve the load balance between slow CPUs and fast GPUs: since CPUs work collectively on a single task, the completion time of tasks on CPUs become comparable to the completion time on GPUs, thus relieving from granularity discrepancy concerns. hwloc support needs to be enabled to get good performance, otherwise StarPU will not know how to better group cores.

Two modes of execution exist to accomodate with existing usages.

6.11.1 Fork-mode Parallel Tasks

In the Fork mode, StarPU will call the codelet function on one of the CPUs of the combined worker. The codelet function can use starpu_combined_worker_get_size() to get the number of threads it is allowed to start to achieve the computation. The CPU binding mask for the whole set of CPUs is already enforced, so that threads created by the function will inherit the mask, and thus execute where StarPU expected, the OS being in charge of choosing how to schedule threads on the corresponding CPUs. The application can also choose to bind threads by hand, using e.g. sched_getaffinity to know the CPU binding mask that StarPU chose.

For instance, using OpenMP (full source is available in examples/openmp/vector_scal.c):

```
void scal_cpu_func(void *buffers[], void *_args)
    unsigned i:
    float *factor = _args;
    struct starpu_vector_interface *vector = buffers[0];
    unsigned n = STARPU_VECTOR_GET_NX(vector);
    float *val = (float *)STARPU_VECTOR_GET_PTR(vector);
#pragma omp parallel for num threads(starpu combined worker get size())
    for (i = 0; i < n; i++)
        val[i] *= *factor;
static struct starpu_codelet cl =
    .modes = { STARPU_RW },
    .where = STARPU_CPU,
    .type = STARPU_FORKJOIN,
    .max_parallelism = INT_MAX,
    .cpu_funcs = {scal_cpu_func},
.cpu_funcs_name = {"scal_cpu_func"},
    .nbuffers = 1,
};
```

6.11 Parallel Tasks 45

Other examples include for instance calling a BLAS parallel CPU implementation (see examples/mult/xgemm. c).

6.11.2 SPMD-mode Parallel Tasks

In the SPMD mode, StarPU will call the codelet function on each CPU of the combined worker. The codelet function can use starpu_combined_worker_get_size() to get the total number of CPUs involved in the combined worker, and thus the number of calls that are made in parallel to the function, and starpu_combined_worker_get_rank() to get the rank of the current CPU within the combined worker. For instance:

```
static void func(void *buffers[], void *args)
    unsigned i;
    float *factor = _args;
    struct starpu_vector_interface *vector = buffers[0];
    unsigned n = STARPU_VECTOR_GET_NX(vector);
    float *val = (float *)STARPU_VECTOR_GET_PTR(vector);
    /\star Compute slice to compute \star/
    unsigned m = starpu_combined_worker_get_size();
    unsigned j = starpu_combined_worker_get_rank();
    unsigned slice = (n+m-1)/m;
    for (i = j * slice; i < (j+1) * slice && i < n; i++)</pre>
        val[i] *= *factor;
}
static struct starpu codelet cl =
    .modes = { STARPU_RW },
    .type = STARPU_SPMD,
    .max_parallelism = INT_MAX,
    .cpu_funcs = { func },
.cpu_funcs_name = { "func" },
    .nbuffers = 1,
```

Of course, this trivial example will not really benefit from parallel task execution, and was only meant to be simple to understand. The benefit comes when the computation to be done is so that threads have to e.g. exchange intermediate results, or write to the data in a complex but safe way in the same buffer.

6.11.3 Parallel Tasks Performance

To benefit from parallel tasks, a parallel-task-aware StarPU scheduler has to be used. When exposed to codelets with a flag STARPU_FORKJOIN or STARPU_SPMD, the schedulers pheft (parallel-heft) and peager (parallel eager) will indeed also try to execute tasks with several CPUs. It will automatically try the various available combined worker sizes (making several measurements for each worker size) and thus be able to avoid choosing a large combined worker if the codelet does not actually scale so much.

6.11.4 Combined Workers

By default, StarPU creates combined workers according to the architecture structure as detected by hwloc. It means that for each object of the hwloc topology (NUMA node, socket, cache, ...) a combined worker will be created. If some nodes of the hierarchy have a big arity (e.g. many cores in a socket without a hierarchy of shared caches), StarPU will create combined workers of intermediate sizes. The variable STARPU_SYNTHESIZE_ARI \leftarrow TY_COMBINED_WORKER permits to tune the maximum arity between levels of combined workers.

The combined workers actually produced can be seen in the output of the tool starpu_machine_display (the environment variable STARPU_SCHED has to be set to a combined worker-aware scheduler such as pheft or peager).

6.11.5 Concurrent Parallel Tasks

Unfortunately, many environments and librairies do not support concurrent calls.

For instance, most OpenMP implementations (including the main ones) do not support concurrent pragma omp parallel statements without nesting them in another pragma omp parallel statement, but StarPU does not yet support creating its CPU workers by using such pragma.

Other parallel libraries are also not safe when being invoked concurrently from different threads, due to the use of global variables in their sequential sections for instance.

46 Tasks In StarPU

The solution is then to use only one combined worker at a time. This can be done by setting the field starpu_conf⇔ ::single_combined_worker to 1, or setting the environment variable STARPU_SINGLE_COMBINED_WORKER to 1. StarPU will then run only one parallel task at a time (but other CPU and GPU tasks are not affected and can be run concurrently). The parallel task scheduler will however still try varying combined worker sizes to look for the most efficient ones.

6.11.6 Synchronization Tasks

For the application conveniency, it may be useful to define tasks which do not actually make any computation, but wear for instance dependencies between other tasks or tags, or to be submitted in callbacks, etc.

The obvious way is of course to make kernel functions empty, but such task will thus have to wait for a worker to become ready, transfer data, etc.

A much lighter way to define a synchronization task is to set its starpu_task::cl field to NULL. The task will thus be a mere synchronization point, without any data access or execution content: as soon as its dependencies become available, it will terminate, call the callbacks, and release dependencies.

An intermediate solution is to define a codelet with its starpu_codelet::where field set to STARPU_NOWHERE, for instance:

```
struct starpu_codelet cl =
{
          .where = STARPU_NOWHERE,
          .nbuffers = 1,
          .modes = { STARPU_R },
}

task = starpu_task_create();
task->cl = &cl;
task->handles[0] = handle;
starpu_task_submit(task);
```

will create a task which simply waits for the value of handle to be available for read. This task can then be depended on, etc.

Chapter 7

Data Management

TODO: intro which mentions consistency among other things

7.1 Data Interface

StarPU provides several data interfaces for programmers to describe the data layout of their application. There are predefined interfaces already available in StarPU. Users can define new data interfaces as explained in Defining A New Data Interface. All functions provided by StarPU are documented in Data Interfaces. You will find a short list below.

7.1.1 Variable Data Interface

A variable is a given size byte element, typically a scalar. Here an example of how to register a variable data to StarPU by using starpu_variable_data_register().

7.1.2 Vector Data Interface

A vector is a fixed number of elements of a given size. Here an example of how to register a vector data to StarPU by using starpu_vector_data_register().

7.1.3 Matrix Data Interface

To register 2-D matrices with a potential padding, one can use the matrix data interface. Here an example of how to register a matrix data to StarPU by using starpu_matrix_data_register().

7.1.4 Block Data Interface

To register 3-D blocks with potential paddings on Y and Z dimensions, one can use the block data interface. Here an example of how to register a block data to StarPU by using starpu_block_data_register().

48 Data Management

7.1.5 BCSR Data Interface

BCSR (Blocked Compressed Sparse Row Representation) sparse matrix data can be registered to StarPU using the bcsr data interface. Here an example on how to do so by using starpu bcsr data register().

```
* We use the following matrix:
     1 0
           1 0 0 1
                0
                    0 1
        2
            3
                   11
 * nzval = [0, 1, 2, 3] ++ [4, 5, 6, 7] ++ [8, 9, 10, 11]
 * colind = [0, 0, 1]
 * rowptr = [0, 1, 3]
 \star r = c = 2
/\star Size of the blocks \star/
int R = 2;
int C = 2;
int NROWS = 2;
int NNZ_BLOCKS = 3;
                     /* out of 4 */
int NZVAL_SIZE = (R*C*NNZ_BLOCKS);
int nzval[NZVAL SIZE] =
                       /* First block */
                        /* Second block */
        8, 9, 10, 11 /* Third block */
uint32 t colind[NNZ BLOCKS] =
        0, /* block-column index for first block in nzval */
        0, /* block-column index for second block in nzval */
          /* block-column index for third block in nzval */
uint32_t rowptr[NROWS+1] =
        0, / \star block-index in nzval of the first block of the first row. \star/
        1, / \star block-index in nzval of the first block of the second row. \star/
        NNZ_BLOCKS /\star number of blocks, to allow an easier element's access for the kernels \star/
};
starpu data handle t bcsr handle;
starpu_bcsr_data_register(&bcsr_handle,
                           NNZ_BLOCKS,
                           NROWS,
                           (uintptr t) nzval.
                           colind,
                           rowptr,
                           0, /* firstentry */
                           sizeof(nzval[0]));
```

StarPU provides an example on how to deal with such matrices in examples/spmv.

7.1.6 CSR Data Interface

TODO

7.1.7 Data Interface with Variable Size

Tasks are actually allowed to change the size of data interfaces.

The simplest case is just changing the amount of data actually used within the allocated buffer. This is for instance implemented for the matrix interface: one can set the new NX/NY values with STARPU_MATRIX_SET_NX(), STAGE RPU_MATRIX_SET_NY(), and STARPU_MATRIX_SET_LD() at the end of the task implementation. Data transfers achieved by StarPU will then use these values instead of the whole allocated size. The values of course need to be set within the original allocation. To reserve room for increasing the NX/NY values, one can use starpu_cmatrix_data_register_allocsize() instead of starpu_matrix_data_register(), to specify the allocation size to be used instead of the default NX*NY*ELEMSIZE. To support this, the data interface has to implement the starpu_data_cmatrix_data_register.

7.2 Data Management 49

interface_ops::alloc_footprint and starpu_data_interface_ops::alloc_compare methods, for proper StarPU allocation management.

A more involved case is changing the amount of allocated data. The task implementation can just reallocate the buffer during its execution, and set the proper new values in the interface structure, e.g. nx, ny, ld, etc. so that the StarPU core knows the new data layout. The starpu_data_interface_ops structure however then needs to have the starpu_data_interface_ops::dontcache field set to 1, to prevent StarPU from trying to perform any cached allocation, since the allocated size will vary. An example is available in tests/datawizard/variable_size.c

7.2 Data Management

When the application allocates data, whenever possible it should use the starpu_malloc() function, which will ask CUDA or OpenCL to make the allocation itself and pin the corresponding allocated memory, or to use the starpu-memory_pin() function to pin memory allocated by other ways, such as local arrays. This is needed to permit asynchronous data transfer, i.e. permit data transfer to overlap with computations. Otherwise, the trace will show that the DriverCopyAsync state takes a lot of time, this is because CUDA or OpenCL then reverts to synchronous transfers.

The application can provide its own allocation function by calling starpu_malloc_set_hooks(). StarPU will then use them for all data handle allocations in the main memory.

By default, StarPU leaves replicates of data wherever they were used, in case they will be re-used by other tasks, thus saving the data transfer time. When some task modifies some data, all the other replicates are invalidated, and only the processing unit which ran this task will have a valid replicate of the data. If the application knows that this data will not be re-used by further tasks, it should advise StarPU to immediately replicate it to a desired list of memory nodes (given through a bitmask). This can be understood like the write-through mode of CPU caches.

```
starpu_data_set_wt_mask(img_handle, 1<<0);
```

will for instance request to always automatically transfer a replicate into the main memory (node 0), as bit 0 of the write-through bitmask is being set.

```
starpu_data_set_wt_mask(img_handle, ~0U);
```

will request to always automatically broadcast the updated data to all memory nodes.

Setting the write-through mask to $\sim 0\,\mathrm{U}$ can also be useful to make sure all memory nodes always have a copy of the data, so that it is never evicted when memory gets scarse.

Implicit data dependency computation can become expensive if a lot of tasks access the same piece of data. If no dependency is required on some piece of data (e.g. because it is only accessed in read-only mode, or because write accesses are actually commutative), use the function starpu_data_set_sequential_consistency_flag() to disable implicit dependencies on this data.

In the same vein, accumulation of results in the same data can become a bottleneck. The use of the mode STA RPU_REDUX permits to optimize such accumulation (see Data Reduction). To a lesser extent, the use of the flag STARPU_COMMUTE keeps the bottleneck (see Commute Data Access), but at least permits the accumulation to happen in any order.

Applications often need a data just for temporary results. In such a case, registration can be made without an initial value, for instance this produces a vector data:

```
starpu_vector_data_register(&handle, -1, 0, n, sizeof(float));
```

StarPU will then allocate the actual buffer only when it is actually needed, e.g. directly on the GPU without allocating in main memory.

In the same vein, once the temporary results are not useful any more, the data should be thrown away. If the handle is not to be reused, it can be unregistered:

```
starpu_data_unregister_submit(handle);
```

actual unregistration will be done after all tasks working on the handle terminate.

If the handle is to be reused, instead of unregistering it, it can simply be invalidated:

```
starpu_data_invalidate_submit(handle);
```

the buffers containing the current value will then be freed, and reallocated only when another task writes some value to the handle.

50 Data Management

7.3 Data Prefetch

The scheduling policies heft, dmda and pheft perform data prefetch (see STARPU_PREFETCH): as soon as a scheduling decision is taken for a task, requests are issued to transfer its required data to the target processing unit, if needed, so that when the processing unit actually starts the task, its data will hopefully be already available and it will not have to wait for the transfer to finish.

The application may want to perform some manual prefetching, for several reasons such as excluding initial data transfers from performance measurements, or setting up an initial statically-computed data distribution on the machine before submitting tasks, which will thus guide StarPU toward an initial task distribution (since StarPU will try to avoid further transfers).

This can be achieved by giving the function starpu_data_prefetch_on_node() the handle and the desired target memory node. The starpu_data_idle_prefetch_on_node() variant can be used to issue the transfer only when the bus is idle.

Conversely, one can advise StarPU that some data will not be useful in the close future by calling starpu_data_\(Limin \) wont use(). StarPU will then write its value back to its home node, and evict it from GPUs when room is needed.

7.4 Partitioning Data

An existing piece of data can be partitioned in sub parts to be used by different tasks, for instance:

The task submission then uses the function starpu_data_get_sub_data() to retrieve the sub-handles to be passed as tasks parameters.

```
/* Submit a task on each sub-vector */
for (i=0; i<starpu_data_get_nb_children(handle); i++)
{
    /* Get subdata number i (there is only 1 dimension) */
    starpu_data_handle_t sub_handle = starpu_data_get_sub_data(
        handle, 1, i);
    struct starpu_task *task = starpu_task_create();

    task->handles[0] = sub_handle;
    task->cl = &cl;
    task->synchronous = 1;
    task->cl_arg = &factor;
    task->cl_arg_size = sizeof(factor);

    starpu_task_submit(task);
}
```

Partitioning can be applied several times, see examples/basic_examples/mult.c and examples/filters/. Wherever the whole piece of data is already available, the partitioning will be done in-place, i.e. without allocating new buffers but just using pointers inside the existing copy. This is particularly important to be aware of when using OpenCL, where the kernel parameters are not pointers, but cl_mem handles. The kernel thus needs to be also passed the offset within the OpenCL buffer:

```
void opencl_func(void *buffers[], void *cl_arg)
{
    cl_mem vector = (cl_mem) STARPU_VECTOR_GET_DEV_HANDLE(buffers[0]);
    unsigned offset = STARPU_BLOCK_GET_OFFSET(buffers[0]);
    ...
    clSetKernelArg(kernel, 0, sizeof(vector), &vector);
    clSetKernelArg(kernel, 1, sizeof(offset), &offset);
    ...
}
```

And the kernel has to shift from the pointer passed by the OpenCL driver:

```
__kernel void opencl_kernel(__global int *vector, unsigned offset)
{
    block = (__global void *)block + offset;
    ...
}
```

When the sub-data is not of the same type as the original data, the starpu_data_filter::get_child_ops field needs to be set appropriately for StarPU to know which type should be used.

StarPU provides various interfaces and filters for matrices, vectors, etc., but applications can also write their own data interfaces and filters, see <code>examples/interface</code> and <code>examples/filters/custom_mf</code> for an example, and see Defining A New Data Interface and Defining A New Data Filter for documentation.

7.5 Asynchronous Partitioning

The partitioning functions described in the previous section are synchronous: starpu_data_partition() and starpu← _data_unpartition() both wait for all the tasks currently working on the data. This can be a bottleneck for the application.

An asynchronous API also exists, it works only on handles with sequential consistency. The principle is to first plan the partitioning, which returns data handles of the partition, which are not functional yet. When submitting tasks, one can mix using the handles of the partition, of the whole data. One can even partition recursively and mix using handles at different levels of the recursion. Of course, StarPU will have to introduce coherency synchronization.

fmultiple_submit_implicit is a complete example using this technique. One can also look at fmultiple_submit_readonly which contains the explicit coherency synchronization which are automatically introduced by StarPU for fmultiple_submit_implicit.

In short, we first register a matrix and plan the partitioning:

starpu_data_partition_plan() returns the handles for the partition in vert_handle.

One can then submit tasks working on the main handle, and tasks working on vert_handle handles. Between using the main handle and vert_handle handles, StarPU will automatically call starpu_data_partition_submit() and starpu_data_unpartition_submit().

All this code is asynchronous, just submitting which tasks, partitioning and unpartitioning will be done at runtime. Planning several partitioning of the same data is also possible, StarPU will unpartition and repartition as needed when mixing accesses of different partitions. If data access is done in read-only mode, StarPU will allow the different partitioning to coexist. As soon as a data is accessed in read-write mode, StarPU will automatically unpartition everything and activate only the partitioning leading to the data being written to.

For instance, for a stencil application, one can split a subdomain into its interior and halos, and then just submit a task updating the whole subdomain, then submit MPI sends/receives to update the halos, then submit again a task updating the whole subdomain, etc. and StarPU will automatically partition/unpartition each time.

7.6 Manual Partitioning

One can also handle partitioning by hand, by registering several views on the same piece of data. The idea is then to manage the coherency of the various views through the common buffer in the main memory. $fmultiple_{\leftarrow}$ manual is a complete example using this technique.

In short, we first register the same matrix several times:

52 Data Management

Since StarPU is not aware that the two handles are actually pointing to the same data, we have a danger of inadvertently submitting tasks to both views, which will bring a mess since StarPU will not guarantee any coherency between the two views. To make sure we don't do this, we invalidate the view that we will not use:

Then we can safely work on handle.

When we want to switch to the vertical slice view, all we need to do is bring coherency between them by running an empty task on the home node of the data:

The execution of the switch task will get back the matrix data into the main memory, and thus the vertical slices will get the updated value there.

Again, we prefer to make sure that we don't accidentally access the matrix through the whole-matrix handle:

```
starpu_data_invalidate_submit(handle);
```

And now we can start using vertical slices, etc.

7.7 Defining A New Data Filter

StarPU provides a series of predefined filters in Data Partition, but additional filters can be defined by the application. The principle is that the filter function just fills the memory location of the i-th subpart of a data. Examples are provided in src/datawizard/interfaces/*_filters.c, and see starpu_data_filter::filter_func for the details. The starpu_filter_nparts_compute_chunk_size_and_offset() helper can be used to compute the division of pieces of data.

7.8 Data Reduction

In various cases, some piece of data is used to accumulate intermediate results. For instances, the dot product of a vector, maximum/minimum finding, the histogram of a photograph, etc. When these results are produced along the whole machine, it would not be efficient to accumulate them in only one place, incurring data transmission each and access concurrency.

StarPU provides a mode STARPU_REDUX, which permits to optimize this case: it will allocate a buffer on each memory node, and accumulate intermediate results there. When the data is eventually accessed in the normal mode STARPU_R, StarPU will collect the intermediate results in just one buffer.

For this to work, the user has to use the function starpu_data_set_reduction_methods() to declare how to initialize these buffers, and how to assemble partial results.

For instance, cg uses that to optimize its dot product: it first defines the codelets for initialization and reduction:

7.9 Commute Data Access 53

```
{
    double *v_dst = (double *)STARPU_VARIABLE_GET_PTR(descr[0]);
    double *v_src = (double *)STARPU_VARIABLE_GET_PTR(descr[1]);
    cublasaxpy(1, (double)1.0, v_src, 1, v_dst, 1);
    cudaStreamSynchronize(starpu_cuda_get_local_stream());
}

struct starpu_codelet accumulate_variable_cl =
{
        .cpu_funcs = { accumulate_variable_cpu },
        .cpu_funcs_name = { "accumulate_variable_cpu" },
        .cuda_funcs = { accumulate_variable_cuda },
        .nbuffers = 1,
}

and attaches them as reduction methods for its handle dtq:
starpu_variable_data_register(&dtq_handle, -1, NULL, sizeof(type));
```

starpu_data_set_reduction_methods(dtq_handle, &accumulate_variable_cl, &

and dtq_handle can now be used in mode STARPU_REDUX for the dot products with partitioned vectors:

bzero variable cl):

During registration, we have here provided NULL, i.e. there is no initial value to be taken into account during reduction. StarPU will thus only take into account the contributions from the tasks dot_kernel_cl. Also, it will not allocate any memory for dtq_handle before tasks dot_kernel_cl are ready to run.

If another dot product has to be performed, one could unregister dtq_handle , and re-register it. But one can also call starpu_data_invalidate_submit() with the parameter dtq_handle , which will clear all data from the handle, thus resetting it back to the initial status register (NULL).

The example cg also uses reduction for the blocked gemv kernel, leading to yet more relaxed dependencies and more parallelism.

STARPU_REDUX can also be passed to starpu_mpi_task_insert() in the MPI case. This will however not produce any MPI communication, but just pass STARPU_REDUX to the underlying starpu_task_insert(). It is up to the application to call starpu_mpi_redux_data(), which posts tasks which will reduce the partial results among MPI nodes into the MPI node which owns the data. For instance, some hypothetical application which collects partial results into data res, then uses it for other computation, before looping again with a new reduction:

```
for (i = 0; i < 100; i++)
{
    starpu_mpi_task_insert(MPI_COMM_WORLD, &init_res, STARPU_W, res, 0);
    starpu_mpi_task_insert(MPI_COMM_WORLD, &work, STARPU_RW, A, STARPU_R, B,
        STARPU_REDUX, res, 0);
    starpu_mpi_redux_data(MPI_COMM_WORLD, res);
    starpu_mpi_task_insert(MPI_COMM_WORLD, &work2, STARPU_RW, B, STARPU_R,
        res, 0);
}</pre>
```

7.9 Commute Data Access

By default, the implicit dependencies computed from data access use the sequential semantic. Notably, write accesses are always serialized in the order of submission. In some applicative cases, the write contributions can actually be performed in any order without affecting the eventual result. In this case it is useful to drop the strictly sequential semantic, to improve parallelism by allowing StarPU to reorder the write accesses. This can be done by using the STARPU_COMMUTE data access flag. Accesses without this flag will however properly be serialized against accesses with this flag. For instance:

The two tasks running c12 will be able to commute: depending on whether the value of handle1 or handle2 becomes available first, the corresponding task running c12 will start first. The task running c11 will however always be run before them, and the task running c13 will always be run after them.

If a lot of tasks use the commute access on the same set of data and a lot of them are ready at the same time, it may become interesting to use an arbiter, see Concurrent Data Accesses.

54 Data Management

7.10 Concurrent Data Accesses

When several tasks are ready and will work on several data, StarPU is faced with the classical Dining Philosophers problem, and has to determine the order in which it will run the tasks.

Data accesses usually use sequential ordering, so data accesses are usually already serialized, and thus by default StarPU uses the Dijkstra solution which scales very well in terms of overhead: tasks will just acquire data one by one by data handle pointer value order.

When sequential ordering is disabled or the STARPU_COMMUTE flag is used, there may be a lot of concurrent accesses to the same data, and the Dijkstra solution gets only poor parallelism, typically in some pathological cases which do happen in various applications. In this case, one can use a data access arbiter, which implements the classical centralized solution for the Dining Philosophers problem. This is more expensive in terms of overhead since it is centralized, but it opportunistically gets a lot of parallelism. The centralization can also be avoided by using several arbiters, thus separating sets of data for which arbitration will be done. If a task accesses data from different arbiters, it will acquire them arbiter by arbiter, in arbiter pointer value order.

See the tests/datawizard/test_arbiter.cpp example.

Arbiters however do not support the STARPU_REDUX flag yet.

7.11 Temporary Buffers

There are two kinds of temporary buffers: temporary data which just pass results from a task to another, and scratch data which are needed only internally by tasks.

7.11.1 Temporary Data

Data can sometimes be entirely produced by a task, and entirely consumed by another task, without the need for other parts of the application to access it. In such case, registration can be done without prior allocation, by using the special memory node number -1, and passing a zero pointer. StarPU will actually allocate memory only when the task creating the content gets scheduled, and destroy it on unregistration.

In addition to this, it can be tedious for the application to have to unregister the data, since it will not use its content anyway. The unregistration can be done lazily by using the function starpu_data_unregister_submit(), which will record that no more tasks accessing the handle will be submitted, so that it can be freed as soon as the last task accessing it is over.

The following code examplifies both points: it registers the temporary data, submits three tasks accessing it, and records the data for automatic unregistration.

The application may also want to see the temporary data initialized on the fly before being used by the task. This can be done by using starpu data set reduction methods() to set an initialization codelet (no redux codelet is needed).

7.11.2 Scratch Data

Some kernels sometimes need temporary data to achieve the computations, i.e. a workspace. The application could allocate it at the start of the codelet function, and free it at the end, but this would be costly. It could also allocate one buffer per worker (similarly to How To Initialize A Computation Library Once For Each Worker?), but this would make them systematic and permanent. A more optimized way is to use the data access mode STA \leftarrow RPU_SCRATCH, as examplified below, which provides per-worker buffers without content consistency. The buffer is registered only once, using memory node -1, i.e. the application didn't allocate memory for it, and StarPU will allocate it on demand at task execution.

```
starpu_vector_data_register(&workspace, -1, 0, sizeof(float));
for (i = 0; i < N; i++)
    starpu_task_insert(&compute, STARPU_R, input[i], STARPU_SCRATCH
    , workspace, STARPU_W, output[i], 0);</pre>
```

StarPU will make sure that the buffer is allocated before executing the task, and make this allocation per-worker: for CPU workers, notably, each worker has its own buffer. This means that each task submitted above will actually have

its own workspace, which will actually be the same for all tasks running one after the other on the same worker. Also, if for instance memory becomes scarce, StarPU will notice that it can free such buffers easily, since the content does not matter.

The example examples/pi uses scratches for some temporary buffer.

7.12 The Multiformat Interface

It may be interesting to represent the same piece of data using two different data structures: one only used on CPUs, and one only used on GPUs. This can be done by using the multiformat interface. StarPU will be able to convert data from one data structure to the other when needed. Note that the scheduler dmda is the only one optimized for this interface. The user must provide StarPU with conversion codelets:

```
#define NX 1024
struct point array_of_structs[NX];
starpu_data_handle_t handle;
* The conversion of a piece of data is itself a task, though it is created,
 * submitted and destroyed by StarPU internals and not by the user. Therefore,
 * we have to define two codelets.
 \star Note that for now the conversion from the CPU format to the GPU format has to
 \star be executed on the GPU, and the conversion from the GPU to the CPU has to be
 * executed on the CPU.
#ifdef STARPU_USE_OPENCL
void cpu_to_opencl_opencl_func(void *buffers[], void *args);
struct starpu_codelet cpu_to_opencl_cl
    .where = STARPU_OPENCL,
    .opencl_funcs = { cpu_to_opencl_opencl_func },
    .nbuffers = 1,
    .modes = { STARPU_RW }
void opencl_to_cpu_func(void *buffers[], void *args);
struct starpu_codelet opencl_to_cpu_cl =
    .where = STARPU_CPU,
    .cpu_funcs = { opencl_to_cpu_func },
    .cpu_funcs_name = { "opencl_to_cpu_func" },
    .nbuffers = 1.
    .modes = { STARPU_RW }
#endif
struct starpu_multiformat_data_interface_ops format_ops =
#ifdef STARPU USE OPENCI
    .opencl elemsize = 2 * sizeof(float).
    .cpu_to_opencl_cl = &cpu_to_opencl_cl,
    .opencl_to_cpu_cl = &opencl_to_cpu_cl,
#endif
    .cpu_elemsize = 2 * sizeof(float),
starpu_multiformat_data_register(handle, STARPU_MAIN_RAM, &
      array_of_structs, NX, &format_ops);
```

Kernels can be written almost as for any other interface. Note that STARPU_MULTIFORMAT_GET_CPU_PTR shall only be used for CPU kernels. CUDA kernels must use STARPU_MULTIFORMAT_GET_CUDA_PTR, and OpenCL kernels must use STARPU_MULTIFORMAT_GET_OPENCL_PTR. STARPU_MULTIFORMAT_GET_NX may be used in any kind of kernel.

```
static void
multiformat_scal_cpu_func(void *buffers[], void *args)
{
    struct point *aos;
    unsigned int n;
    aos = STARPU_MULTIFORMAT_GET_CPU_PTR(buffers[0]);
    n = STARPU_MULTIFORMAT_GET_NX(buffers[0]);
    ...
}
extern "C" void multiformat_scal_cuda_func(void *buffers[], void *_args)
{
    unsigned int n;
    struct struct_of_arrays *soa;
```

56 Data Management

```
soa = (struct struct_of_arrays *) STARPU_MULTIFORMAT_GET_CUDA_PTR(
  buffers[0]);
n = STARPU_MULTIFORMAT_GET_NX(buffers[0]);
...
```

A full example may be found in examples/basic_examples/multiformat.c.

7.13 Defining A New Data Interface

Let's define a new data interface to manage complex numbers.

```
/* interface for complex numbers */
struct starpu_complex_interface
{
         double *real;
         double *imaginary;
         int nx;
};
```

Registering such a data to StarPU is easily done using the function starpu_data_register(). The last parameter of the function, interface_complex_ops, will be described below.

The starpu_complex_interface structure is here used just to store the parameters that the user provided to starpu_complex_data_register. starpu_data_register() will first allocate the handle, and then pass the starpu_complex_interface structure to the starpu_data_interface_ops::register_data_handle method, which records them within the data handle (it is called once per node by starpu_data_register()).

Different operations need to be defined for a data interface through the type $starpu_data_interface_ops$. We only define here the basic operations needed to run simple applications. The source code for the different functions can be found in the file $examples/interface/complex_interface$. c, the details of the hooks to be provided are documented in $starpu_data_interface_ops$.

```
static struct starpu_data_interface_ops interface_complex_ops =
{
    .register_data_handle = complex_register_data_handle,
    .allocate_data_on_node = complex_allocate_data_on_node,
    .copy_methods = &complex_copy_methods,
    .get_size = complex_get_size,
    .footprint = complex_footprint,
    .interfaceid = STARPU_UNKNOWN_INTERFACE_ID,
    .interface_size = sizeof(struct starpu_complex_interface),
};
```

Functions need to be defined to access the different fields of the complex interface from a StarPU data handle.

```
double *starpu_complex_get_real(starpu_data_handle_t handle)
{
    struct starpu_complex_interface *complex_interface =
        (struct starpu_complex_interface *) starpu_data_get_interface_on_node
    (handle, STARPU_MAIN_RAM);
    return complex_interface->real;
}
double *starpu_complex_get_imaginary(starpu_data_handle_t handle);
int starpu_complex_get_nx(starpu_data_handle_t handle);
```

Similar functions need to be defined to access the different fields of the complex interface from a void * pointer to be used within codelet implementations.

Complex data interfaces can then be registered to StarPU.

The whole code for this complex data interface is available in the directory examples/interface/.

7.14 Specifying A Target Node For Task Data

When executing a task on a GPU for instance, StarPU would normally copy all the needed data for the tasks on the embedded memory of the GPU. It may however happen that the task kernel would rather have some of the datas kept in the main memory instead of copied in the GPU, a pivoting vector for instance. This can be achieved by setting the starpu_codelet::specific_nodes flag to 1, and then fill the starpu_codelet::nodes array (or starpu_codelet::dyn_nodes when starpu_codelet::nbuffers is greater than STARPU_NMAXBUFS) with the node numbers where data should be copied to, or STARPU_SPECIFIC_NODE_LOCAL to let StarPU copy it to the memory node where the task will be executed.

::STARPU_SPECIFIC_NODE_CPU can also be used to request data to be put in CPU-accessible memory (and let StarPU choose the NUMA node). ::STARPU_SPECIFIC_NODE_FAST and ::STARPU_SPECIFIC_NODE_SLOW can also be used

For instance, with the following codelet:

```
struct starpu_codelet cl =
{
          .cuda_funcs = { kernel },
          .nbuffers = 2,
          .modes = {STARPU_RW, STARPU_RW},
          .specific_nodes = 1,
          .nodes = {STARPU_SPECIFIC_NODE_CPU, STARPU_SPECIFIC_NODE_LOCAL},
};
```

the first data of the task will be kept in the CPU memory, while the second data will be copied to the CUDA GPU as usual. A working example is available in tests/datawizard/specific_node.c With the following codelet:

```
struct starpu_codelet cl =
{
          .cuda_funcs = { kernel },
          .nbuffers = 2,
          .modes = {STARPU_RW, STARPU_RW},
          .specific_nodes = 1,
          .nodes = {STARPU_SPECIFIC_NODE_LOCAL, STARPU_SPECIFIC_NODE_SLOW},
};
```

The first data will be copied into fast (but probably size-limited) local memory while the second data will be left in slow (but large) memory. This makes sense when the kernel does not make so many accesses to the second data, and thus data being remote e.g. over a PCI bus is not a performance problem, and avoids filling the fast local memory with data which does not need the performance.

58 Data Management

Chapter 8

Scheduling

8.1 Task Scheduling Policies

The basics of the scheduling policy are the following:

- The scheduler gets to schedule tasks (push operation) when they become ready to be executed, i.e. they are not waiting for some tags, data dependencies or task dependencies.
- Workers pull tasks (pop operation) one by one from the scheduler.

This means scheduling policies usually contain at least one queue of tasks to store them between the time when they become available, and the time when a worker gets to grab them.

By default, StarPU uses the work-stealing scheduler 1 ws. This is because it provides correct load balance and locality even if the application codelets do not have performance models. Other non-modelling scheduling policies can be selected among the list below, thanks to the environment variable STARPU_SCHED. For instance <code>exportSTARPU_SCHED=dmda</code>. Use <code>help</code> to get the list of available schedulers.

Non Performance Modelling Policies:

The **eager** scheduler uses a central task queue, from which all workers draw tasks to work on concurrently. This however does not permit to prefetch data since the scheduling decision is taken late. If a task has a non-0 priority, it is put at the front of the queue.

The **random** scheduler uses a queue per worker, and distributes tasks randomly according to assumed worker overall performance.

The **ws** (work stealing) scheduler uses a queue per worker, and schedules a task on the worker which released it by default. When a worker becomes idle, it steals a task from the most loaded worker.

The **lws** (locality work stealing) scheduler uses a queue per worker, and schedules a task on the worker which released it by default. When a worker becomes idle, it steals a task from neighbour workers. It also takes into account priorities.

The **prio** scheduler also uses a central task queue, but sorts tasks by priority specified by the programmer (between -5 and 5).

The **heteroprio** scheduler uses different priorities for the different processing units. This scheduler must be configured to work correctly and to expect high-performance as described in the corresponding section.

8.2 Performance Model-Based Task Scheduling Policies

If (and only if) your application codelets have performance models (Performance Model Example), you should change the scheduler thanks to the environment variable STARPU_SCHED, to select one of the policies below, in order to take advantage of StarPU's performance modelling. For instance <code>export STARPU_SCHED=dmda</code>. Use <code>help</code> to get the list of available schedulers.

Note: Depending on the performance model type chosen, some preliminary calibration runs may be needed for the model to converge. If the calibration has not been done, or is insufficient yet, or if no performance model is specified for a codelet, every task built from this codelet will be scheduled using an **eager** fallback policy.

Troubleshooting: Configuring and recompiling StarPU using the --enable-verbose configure option displays some statistics at the end of execution about the percentage of tasks which have been scheduled by a DM* family policy using performance model hints. A low or zero percentage may be the sign that performance models are not converging or that codelets do not have performance models enabled.

60 Scheduling

Performance Modelling Policies:

The **dm** (deque model) scheduler takes task execution performance models into account to perform a HEFT-similar scheduling strategy: it schedules tasks where their termination time will be minimal. The difference with HEFT is that **dm** schedules tasks as soon as they become available, and thus in the order they become available, without taking priorities into account.

The dmda (deque model data aware) scheduler is similar to dm, but it also takes into account data transfer time.

The **dmdar** (deque model data aware ready) scheduler is similar to dmda, but it also privileges tasks whose data buffers are already available on the target device.

The **dmdas** (deque model data aware sorted) scheduler is similar to dmdar, except that it sorts tasks by priority order, which allows to become even closer to HEFT by respecting priorities after having made the scheduling decision (but it still schedules tasks in the order they become available).

The **dmdasd** (deque model data aware sorted decision) scheduler is similar to dmdas, except that when scheduling a task, it takes into account its priority when computing the minimum completion time, since this task may get executed before others, and thus the latter should be ignored.

The **heft** (heterogeneous earliest finish time) scheduler is a deprecated alias for **dmda**.

The **pheft** (parallel HEFT) scheduler is similar to dmda, it also supports parallel tasks (still experimental). Should not be used when several contexts using it are being executed simultaneously.

The **peager** (parallel eager) scheduler is similar to eager, it also supports parallel tasks (still experimental). Should not be used when several contexts using it are being executed simultaneously.

TODO: describe modular schedulers

8.3 Task Distribution Vs Data Transfer

Distributing tasks to balance the load induces data transfer penalty. StarPU thus needs to find a balance between both. The target function that the scheduler <code>dmda</code> of StarPU tries to minimize is <code>alpha * T_execution + beta * T_data_transfer</code>, where <code>T_execution</code> is the estimated execution time of the codelet (usually accurate), and <code>T_data_transfer</code> is the estimated data transfer time. The latter is estimated based on bus calibration before execution start, i.e. with an idle machine, thus without contention. You can force bus re-calibration by running the tool <code>starpu_calibrate_bus</code>. The beta parameter defaults to 1, but it can be worth trying to tweak it by using <code>export STARPU_SCHED_BETA=2</code> (<code>STARPU_SCHED_BETA</code>) for instance, since during real application execution, contention makes transfer times bigger. This is of course imprecise, but in practice, a rough estimation already gives the good results that a precise estimation would give.

8.4 Energy-based Scheduling

If the application can provide some energy consumption performance model (through the field starpu_codelet ::energy_model), StarPU will take it into account when distributing tasks. The target function that the scheduler dmda minimizes becomes alpha * T_execution + beta * T_data_transfer + gamma * Consumption , where Consumption is the estimated task consumption in Joules. To tune this parameter, use export STARPU_SCHED_GAMMA=3000 (STARPU_SCHED_GAMMA) for instance, to express that each Joule (i.e kW during 1000us) is worth 3000us execution time penalty. Setting alpha and beta to zero permits to only take into account energy consumption.

This is however not sufficient to correctly optimize energy: the scheduler would simply tend to run all computations on the most energy-conservative processing unit. To account for the consumption of the whole machine (including idle processing units), the idle power of the machine should be given by setting $export\ STARPU_IDLE_PO\leftarrow\ WER=200\ (STARPU_IDLE_POWER)$ for 200W, for instance. This value can often be obtained from the machine power supplier.

The energy actually consumed by the total execution can be displayed by setting $export STARPU_PROFIL \leftarrow ING=1 STARPU_WORKER_STATS=1$.

For OpenCL devices, on-line task consumption measurement is currently supported through the CL_PROFILI \leftarrow NG_POWER_CONSUMED OpenCL extension, implemented in the MoviSim simulator.

For CUDA devices, on-line task consumption measurement is supported on V100 cards and beyond. This however only works for quite long tasks, since the measurement granularity is about 10ms.

Applications can however provide explicit measurements by using the function starpu_perfmodel_update_history() (examplified in Performance Model Example with the <code>energy_model</code> performance model). Fine-grain measurement is often not feasible with the feedback provided by the hardware, so the user can for instance run a given task a thousand times, measure the global consumption for that series of tasks, divide it by a thousand, repeat for varying

kinds of tasks and task sizes, and eventually feed StarPU with these manual measurements through starpu $_{\leftarrow}$ perfmodel_update_history(). For instance, for CUDA devices, nvidia-smi-q-d-POWER can be used to get the current consumption in Watt. Multiplying this value by the average duration of a single task gives the consumption of the task in Joules, which can be given to starpu_perfmodel_update_history().

61

Another way to provide the energy performance is to define a perfmodel with starpu_perfmodel::type STARPU_
PER_ARCH, and set the starpu_perfmodel::arch_cost_function field to a function which shall return the estimated consumption of the task in Joules. Such a function can for instance use starpu_task_expected_length() on the task (in µs), multiplied by the typical power consumption of the device, e.g. in W, and divided by 1000000. to get Joules.

8.5 Modularized Schedulers

StarPU provides a powerful way to implement schedulers, as documented in Defining A New Modular Scheduling Policy . It is currently shipped with the following pre-defined Modularized Schedulers :

- Eager-based Schedulers (with/without prefetching: modular-eager, modular-eager-prefetching):
 Naive scheduler, which tries to map a task on the first available resource it finds.
- Prio-based Schedulers (with/without prefetching: modular-prio, modular-prio-prefetching):
 Similar to Eager-Based Schedulers. Can handle tasks which have a defined priority and schedule them accordingly.
- Random-based Schedulers (with/without prefetching: modular-random, modular-random-prio, modular-random-prefetching, modular-random-prio-prefetching): Selects randomly a resource to be mapped on for each task.
- Work Stealing (modular-ws):
 Maps tasks to workers in round robin, but allows workers to steal work from other workers.
- HEFT Scheduler :

Maps tasks to workers using a heuristic very close to Heterogeneous Earliest Finish Time. It needs that every task submitted to StarPU have a defined performance model (Performance Model Calibration) to work efficiently, but can handle tasks without a performance model. modular-heft just takes tasks by priority order. modular-heft takes at most 5 tasks of the same priority and checks which one fits best. modular-heft-prio is similar to modular-heft, but only decides the memory node, not the exact worker, just pushing tasks to one central queue per memory node.

To use one of these schedulers, one can set the environment variable STARPU SCHED.

8.6 Static Scheduling

In some cases, one may want to force some scheduling, for instance force a given set of tasks to GPU0, another set to GPU1, etc. while letting some other tasks be scheduled on any other device. This can indeed be useful to guide StarPU into some work distribution, while still letting some degree of dynamism. For instance, to force execution of a task on CUDA0:

One can also specify a set worker(s) which are allowed to take the task, as an array of bit, for instance to allow workers 2 and 42:

```
task->workerids = calloc(2,sizeof(uint32_t));
task->workerids[2/32] |= (1 << (2\$32));
task->workerids[42/32] |= (1 << (42\$32));
task->workerids_len = 2;
```

62 Scheduling

One can also specify the order in which tasks must be executed by setting the starpu_task::workerorder field. If this field is set to a non-zero value, it provides the per-worker consecutive order in which tasks will be executed, starting from 1. For a given of such task, the worker will thus not execute it before all the tasks with smaller order value have been executed, notably in case those tasks are not available yet due to some dependencies. This eventually gives total control of task scheduling, and StarPU will only serve as a "self-timed" task runtime. Of course, the provided order has to be runnable, i.e. a task should should not depend on another task bound to the same worker with a bigger order.

Note however that using scheduling contexts while statically scheduling tasks on workers could be tricky. Be careful to schedule the tasks exactly on the workers of the corresponding contexts, otherwise the workers' corresponding scheduling structures may not be allocated or the execution of the application may deadlock. Moreover, the hypervisor should not be used when statically scheduling tasks.

8.7 Heteroprio

Within Heteroprio, one priority per processing unit type is assigned to each task, such that a task has several priorities. Each worker pops the task that has the highest priority for the hardware type it uses, which could be CPU or CUDA for example. Therefore, the priorities has to be used to manage the critical path, but also to promote the consumption of tasks by the more appropriate workers.

The tasks are stored inside buckets, where each bucket corresponds to a priority set. Then each worker uses an indirect access array to know the order in which it should access the buckets. Moreover, all the tasks inside a bucket must be compatible with all the processing units that may access it (at least).

As an example, see the following code where we have 5 types of tasks. CPU workers can compute all of them, but CUDA workers can only execute tasks of types 0 and 1, and is expected to go 20 and 30 time faster than the CPU, respectively.

```
#include <starpu_heteroprio.h>
struct starpu_conf conf;
starpu conf init(&conf);
conf.sched_policy_name = "heteroprio";
conf.sched_policy_init = &init_heteroprio;
starpu_init(&conf);
void init heteroprio(unsigned sched ctx) {
    CPU uses 5 buckets and visits them in the natural order
  starpu_heteroprio_set_nb_prios(ctx, STARPU_CPU_IDX, 5);
  // It uses direct mapping idx => idx
  for(unsigned idx = 0; idx < 5; ++idx) {
    starpu_heteroprio_set_mapping(ctx, STARPU_CPU_IDX, idx, idx);
      If there is no CUDA worker we must tell that CPU is faster
    starpu_heteroprio_set_faster_arch(ctx, STARPU_CPU_IDX, idx);
  if (starpu_cuda_worker_get_count()) {
    // CUDA is enabled and uses 2 buckets
    starpu_heteroprio_set_nb_prios(ctx, STARPU_CUDA_IDX, 2);
    // CUDA will first look at bucket 1
    starpu_heteroprio_set_mapping(ctx, STARPU_CUDA_IDX, 0, 1);
    // CUDA will then look at bucket 2
    starpu_heteroprio_set_mapping(ctx, STARPU_CUDA_IDX, 1, 2);
    // For bucket 1 CUDA is the fastest
    starpu_heteroprio_set_faster_arch(ctx, STARPU_CUDA_IDX, 1);
     / And CPU is 30 times slower
    starpu_heteroprio_set_arch_slow_factor(ctx, STARPU_CPU_IDX, 1, 30.0f);
    // For bucket 0 CUDA is the fastest
    starpu_heteroprio_set_faster_arch(ctx, STARPU_CUDA_IDX, 0);
    // And CPU is 20 times slower
    starpu_heteroprio_set_arch_slow_factor(ctx, STARPU_CPU_IDX, 0, 20.0f);
```

Then, when a task is inserted the priority of the task will be used to select in which bucket is has to be stored. So, in the given example, the priority of a task will be between 0 and 4 included. However, tasks of priorities 0-1

63 8.7 Heteroprio must provide CPU and CUDA kernels, and tasks of priorities 2-4 must provide CPU kernels (at least).

64 Scheduling

Chapter 9

Scheduling Contexts

TODO: improve!

9.1 General Ideas

Scheduling contexts represent abstracts sets of workers that allow the programmers to control the distribution of computational resources (i.e. CPUs and GPUs) to concurrent kernels. The main goal is to minimize interferences between the execution of multiple parallel kernels, by partitioning the underlying pool of workers using contexts. Scheduling contexts additionally allow a user to make use of a different scheduling policy depending on the target resource set.

9.2 Creating A Context

By default, the application submits tasks to an initial context, which disposes of all the computation resources available to StarPU (all the workers). If the application programmer plans to launch several kernels simultaneously, by default these kernels will be executed within this initial context, using a single scheduler policy(see Task Scheduling Policies). Meanwhile, if the application programmer is aware of the demands of these kernels and of the specificity of the machine used to execute them, the workers can be divided between several contexts. These scheduling contexts will isolate the execution of each kernel and they will permit the use of a scheduling policy proper to each one of them.

Scheduling Contexts may be created in two ways: either the programmers indicates the set of workers corresponding to each context (providing he knows the identifiers of the workers running within StarPU), or the programmer does not provide any worker list and leaves the Hypervisor assign workers to each context according to their needs (Scheduling Context Hypervisor).

Both cases require a call to the function $starpu_sched_ctx_create()$, which requires as input the worker list (the exact list or a NULL pointer), the amount of workers (or -1 to designate all workers on the platform) and a list of optional parameters such as the scheduling policy, terminated by a 0. The scheduling policy can be a character list corresponding to the name of a StarPU predefined policy or the pointer to a custom policy. The function returns an identifier of the context created which you will use to indicate the context you want to submit the tasks to.

Note: Parallel greedy and parallel heft scheduling policies do not support the existence of several disjoint contexts on the machine. Combined workers are constructed depending on the entire topology of the machine, not only the one belonging to a context.

66 Scheduling Contexts

9.2.1 Creating A Context With The Default Behavior

If no scheduling policy is specified when creating the context, it will be used as another type of resource: a cluster. A cluster is a context without scheduler (eventually delegated to another runtime). For more information see Clustering A Machine. It is therefore mandatory to stipulate a scheduler to use the contexts in this traditional way. To create a context with the default scheduler, that is either controlled through the environment variable STARP U_SCHED or the StarPU default scheduler, one can explicitly use the option STARPU_SCHED_CTX_POLICY UNAME, "" as in the following example:

9.3 Creating A Context

The contexts can also be used to group set of SMs of an NVIDIA GPU in order to isolate the parallel kernels and allow them to coexecution on a specified partition of the GPU.

Each context will be mapped to a stream and the user can indicate the number of SMs. The context can be added to a larger context already grouping CPU cores. This larger context can use a scheduling policy that assigns tasks to both CPUs and contexts (partitions of the GPU) based on performance models adjusted to the number of SMs. The GPU implementation of the task has to be modified accordingly and receive as a parameter the number of SMs.

9.4 Modifying A Context

A scheduling context can be modified dynamically. The application may change its requirements during the execution and the programmer can add additional workers to a context or remove those no longer needed. In the following example we have two scheduling contexts $sched_ctx1$ and $sched_ctx2$. After executing a part of the tasks some of the workers of $sched_ctx1$ will be moved to context $sched_ctx2$.

```
/* the list of ressources that context 1 will give away */
int workerids[3] = {1, 3, 10};

/* add the workers to context 1 */
starpu_sched_ctx_add_workers(workerids, 3, sched_ctx2);

/* remove the workers from context 2 */
starpu_sched_ctx_remove_workers(workerids, 3, sched_ctx1);
```

9.5 Submitting Tasks To A Context

The application may submit tasks to several contexts either simultaneously or sequnetially. If several threads of submission are used the function starpu_sched_ctx_set_context() may be called just before starpu_task_submit(). Thus StarPU considers that the current thread will submit tasks to the coresponding context.

When the application may not assign a thread of submission to each context, the id of the context must be indicated by using the function starpu_task_submit_to_ctx() or the field STARPU_SCHED_CTX for starpu_task_insert().

9.6 Deleting A Context

When a context is no longer needed it must be deleted. The application can indicate which context should keep the resources of a deleted one. All the tasks of the context should be executed before doing this. Thus, the programmer may use either a barrier and then delete the context directly, or just indicate that other tasks will not be submitted later on to the context (such that when the last task is executed its workers will be moved to the inheritor) and delete the context at the end of the execution (when a barrier will be used eventually).

9.7 Emptying A Context

A context may have no resources at the begining or at a certain moment of the execution. Tasks can still be submitted to these contexts and they will be executed as soon as the contexts will have resources. A list of tasks pending to be executed is kept and will be submitted when workers are added to the contexts.

```
/* create a empty context */
unsigned sched_ctx_id = starpu_sched_ctx_create(NULL, 0, "ctx", 0);
/* submit a task to this context */
starpu_sched_ctx_set_context(&sched_ctx_id);
ret = starpu_task_insert(&codelet, 0);
STARPU_CHECK_RETURN_VALUE(ret, "starpu_task_insert");
/* add CPU workers to the context */
int procs[STARPU_NMAXWORKERS];
int nprocs = starpu_cpu_worker_get_count();
starpu_worker_get_ids_by_type(STARPU_CPU_WORKER, procs, nprocs);
starpu_sched_ctx_add_workers(procs, nprocs, sched_ctx_id);
/* and wait for the task termination */
starpu_task_wait_for_all();
```

However, if resources are never allocated to the context, the application will not terminate. If these tasks have low priority, the application can inform StarPU to not submit them by calling the function starpu_sched_ctx_stop_task←_submission().

68 Scheduling Contexts

Chapter 10

Scheduling Context Hypervisor

10.1 What Is The Hypervisor

StarPU proposes a platform to construct Scheduling Contexts, to delete and modify them dynamically. A parallel kernel, can thus be isolated into a scheduling context and interferences between several parallel kernels are avoided. If users know exactly how many workers each scheduling context needs, they can assign them to the contexts at their creation time or modify them during the execution of the program.

The Scheduling Context Hypervisor Plugin is available for users who do not dispose of a regular parallelism, who cannot know in advance the exact size of the context and need to resize the contexts according to the behavior of the parallel kernels.

The Hypervisor receives information from StarPU concerning the execution of the tasks, the efficiency of the resources, etc. and it decides accordingly when and how the contexts can be resized. Basic strategies of resizing scheduling contexts already exist but a platform for implementing additional custom ones is available.

10.2 Start the Hypervisor

The Hypervisor must be initialized once at the beginning of the application. At this point a resizing policy should be indicated. This strategy depends on the information the application is able to provide to the hypervisor as well as on the accuracy needed for the resizing procedure. For example, the application may be able to provide an estimation of the workload of the contexts. In this situation the hypervisor may decide what resources the contexts need. However, if no information is provided the hypervisor evaluates the behavior of the resources and of the application and makes a guess about the future. The hypervisor resizes only the registered contexts.

10.3 Interrogate The Runtime

The runtime provides the hypervisor with information concerning the behavior of the resources and the application. This is done by using the performance_counters which represent callbacks indicating when the resources are idle or not efficient, when the application submits tasks or when it becomes to slow.

10.4 Trigger the Hypervisor

The resizing is triggered either when the application requires it (sc_hypervisor_resize_ctxs()) or when the initials distribution of resources alters the performance of the application (the application is to slow or the resource are idle for too long time). If the environment variable SC_HYPERVISOR_TRIGGER_RESIZE is set to speed the monitored speed of the contexts is compared to a theoretical value computed with a linear program, and the resizing is triggered whenever the two values do not correspond. Otherwise, if the environment variable is set to idle the hypervisor triggers the resizing algorithm whenever the workers are idle for a period longer than the threshold indicated by the programmer. When this happens different resizing strategy are applied that target minimizing the total execution of the application, the instant speed or the idle time of the resources.

10.5 Resizing Strategies

The plugin proposes several strategies for resizing the scheduling context.

The **Application driven** strategy uses users's input concerning the moment when they want to resize the contexts. Thus, users tag the task that should trigger the resizing process. One can set directly the field starpu_task :: hypervisor_tag or use the macro :: STARPU_HYPERVISOR_TAG in the function starpu_task_insert().

Then users have to indicate that when a task with the specified tag is executed the contexts should resize.

```
sc_hypervisor_resize(sched_ctx, 2);
```

Users can use the same tag to change the resizing configuration of the contexts if they consider it necessary.

The **Idleness** based strategy moves workers unused in a certain context to another one needing them. (see Scheduling Context Hypervisor - Regular usage)

The **Gflops rate** based strategy resizes the scheduling contexts such that they all finish at the same time. The speed of each of them is computed and once one of them is significantly slower the resizing process is triggered. In order to do these computations users have to input the total number of instructions needed to be executed by the parallel kernels and the number of instruction to be executed by each task.

The number of flops to be executed by a context are passed as parameter when they are registered to the hypervisor,

```
sc_hypervisor_register_ctx(sched_ctx_id, flops)
```

and the one to be executed by each task are passed when the task is submitted. The corresponding field is starpu—task::flops and the corresponding macro in the function starpu_task_insert() is STARPU_FLOPS (Caution: but take care of passing a double, not an integer, otherwise parameter passing will be bogus). When the task is executed the resizing process is triggered.

The **Feft** strategy uses a linear program to predict the best distribution of resources such that the application finishes in a minimum amount of time. As for the **Gflops rate** strategy the programmers has to indicate the total number of flops to be executed when registering the context. This number of flops may be updated dynamically during the execution of the application whenever this information is not very accurate from the beginning. The function **sc_hypervisor_update_diff_total_flops()** is called in order to add or to remove a difference to the flops left to be executed. Tasks are provided also the number of flops corresponding to each one of them. During the execution of the application the hypervisor monitors the consumed flops and recomputes the time left and the number of resources to use. The speed of each type of resource is (re)evaluated and inserter in the linear program in order to better adapt to the needs of the application.

The **Teft** strategy uses a linear program too, that considers all the types of tasks and the number of each of them and it tries to allocates resources such that the application finishes in a minimum amount of time. A previous calibration of StarPU would be useful in order to have good predictions of the execution time of each type of task.

The types of tasks may be determines directly by the hypervisor when they are submitted. However there are applications that do not expose all the graph of tasks from the beginning. In this case in order to let the hypervisor know about all the tasks the function sc_hypervisor_set_type_of_task() will just inform the hypervisor about future tasks without submitting them right away.

The **Ispeed** strategy divides the execution of the application in several frames. For each frame the hypervisor computes the speed of the contexts and tries making them run at the same speed. The strategy requires less contribution from users as the hypervisor requires only the size of the frame in terms of flops.

The **Throughput** strategy focuses on maximizing the throughput of the resources and resizes the contexts such that the machine is running at its maximum efficiency (maximum instant speed of the workers).

10.6 Defining A New Hypervisor Policy

While Scheduling Context Hypervisor Plugin comes with a variety of resizing policies (see Resizing Strategies), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own resizing policy.

Here an example of how to define a new policy

```
struct sc_hypervisor_policy dummy_policy =
{
    .handle_poped_task = dummy_handle_poped_task,
    .handle_pushed_task = dummy_handle_pushed_task,
    .handle_idle_cycle = dummy_handle_idle_cycle,
    .handle_idle_end = dummy_handle_idle_end,
    .handle_post_exec_hook = dummy_handle_post_exec_hook,
    .custom = 1,
    .name = "dummy"
};
```

Chapter 11

How To Define a New Scheduling Policy

11.1 Introduction

StarPU provides two ways of defining a scheduling policy, a basic monolithic way, and a modular way.

The basic monolithic way is directly connected with the core of StarPU, which means that the policy then has to handle all performance details, such as data prefetching, task performance model calibration, worker locking, etc. examples/scheduler/dummy_sched.c is a trivial example which does not handle this, and thus e.g. does not achieve any data prefetching or smart scheduling.

The modular way allows to implement just one component, and reuse existing components to cope with all these details. examples/scheduler/dummy_modular_sched.c is a trivial example very similar to dummy_c sched.c, but implemented as a component, which allows to assemble it with other components, and notably get data prefetching support for free, and task performance model calibration is properly performed, which allows to easily extend it into taking task duration into account, etc.

11.2 Helper functions for defining a scheduling policy (Basic or modular)

Make sure to have a look at the Scheduling Policy section, which provides a complete list of the functions available for writing advanced schedulers.

This includes getting an estimation for a task computation completion with starpu_task_expected_length(), for the required data transfers with starpu_task_expected_data_transfer_time_for(), for the required energy with starpu—task_expected_energy(), etc. Other useful functions include starpu_transfer_bandwidth(), starpu_transfer_clatency(), starpu_transfer_predict(), ... One can also directly test the presence of a data handle with starpu—data_is_on_node(). Prefetches can be triggered by calling either starpu_prefetch_task_input_for(), starpu_idle—prefetch_task_input_for(), starpu_idle prefetch_task_input_for_prio(). The _prio versions allow to specify a priority for the transfer (instead of taking the task priority by default). These prefetches are only processed when there are no fetch data requests (i.e. a task is waiting for it) to process. The _idle versions queue the transfers on the idle prefetch queue, which is only processed when there are no non-idle prefetch to process. starpu_get_prefetch_flag() is a convenient helper for checking the value of the STARPU_PR EFETCH environment variable.

Usual functions can be used on tasks, for instance one can use the following to get the data size for a task.

Task queues can be implemented with the $starpu_task_list$ functions. Access to the hwloc topology is available with $starpu_worker_get_hwloc_obj()$.

11.3 Defining A New Basic Scheduling Policy

A full example showing how to define a new scheduling policy is available in the StarPU sources in examples/scheduler/dummy_sched.c.

The scheduler has to provide methods:

```
static struct starpu_sched_policy dummy_sched_policy =
{
    .init_sched = init_dummy_sched,
    .deinit_sched = deinit_dummy_sched,
    .add_workers = dummy_sched_add_workers,
    .remove_workers = dummy_sched_remove_workers,
    .push_task = push_task_dummy,
    .pop_task = pop_task_dummy,
    .policy_name = "dummy",
    .policy_description = "dummy scheduling strategy"
};
```

The idea is that when a task becomes ready for execution, the starpu_sched_policy::push_task method is called to give the ready task to the scheduler. When a worker is idle, the starpu_sched_policy::pop_task method is called to get a task from the scheduler. It is up to the scheduler to implement what is between. A simple eager scheduler is for instance to make starpu_sched_policy::push_task push the task to a global list, and make starpu_sched_colicy::pop_task pop from this list. A scheduler can also use starpu_push_local_task() to directly push tasks to a per-worker queue, and then starpu does not even need to implement starpu_sched_policy::pop_task. If there are no ready tasks within the scheduler, it can just return NULL, and the worker will sleep.

The starpu_sched_policy section provides the exact rules that govern the methods of the policy.

One can enumerate the workers with this iterator:

To provide synchronization between workers, a per-worker lock exists to protect the data structures of a given worker. It is acquired around scheduler methods, so that the scheduler does not need any additional mutex to protect its per-worker data.

In case the scheduler wants to access another scheduler's data, it should use starpu_worker_lock() and starpu_worker_unlock().

Calling

```
starpu_worker_lock(B)
```

from a worker $\mathbb A$ will however thus make worker $\mathbb A$ wait for worker $\mathbb B$ to complete its scheduling method. That may be a problem if that method takes a long time, because it is e.g. computing a heuristic or waiting for another mutex, or even cause deadlocks if worker $\mathbb B$ is calling

```
starpu_worker_lock(A)
```

at the same time. In such a case, worker $\ B$ must call starpu_worker_relax_on() and starpu_worker_relax_off() around the section which potentially blocks (and does not actually need protection). While a worker is in relaxed mode, e.g. between a pair of starpu_worker_relax_on() and starpu_worker_relax_off() calls, its state can be altered by other threads: for instance, worker $\ B$ can push tasks for worker $\ B$. In consequence, worker $\ B$ must re-assess its state after

```
starpu_worker_relax_off(B)
```

, such as taking possible new tasks pushed to its queue into account.


When the starpu_sched_policy::push_task method has pushed a task for another worker, one has to call starpu_\(-\) wake_worker_relax_light() so that the worker wakes up and picks it. If the task was pushed on a shared queue, one may want to only wake one idle worker. An example doing this is available in src/sched_policies/eager\(-\) _central_policy.c.

A pointer to one data structure specific to the scheduler can be set with starpu_sched_ctx_set_policy_data() and fetched with starpu_sched_ctx_get_policy_data(). Per-worker data structures can then be store in it by allocating a STARPU_NMAXWORKERS -sized array of structures indexed by workers.

A variety of examples of advanced schedulers can be read in $src/sched_policies$, for instance $random \leftarrow _policy.c$, $eager_central_policy.c$, $work_stealing_policy.c$ Code protected by if ($_\leftarrow starpu_get_nsched_ctxs() > 1$) can be ignored, this is for scheduling contexts, which is an experimental feature.

11.4 Defining A New Modular Scheduling Policy

StarPU's Modularized Schedulers are made of individual Scheduling Components Modularizedly assembled as a Scheduling Tree. Each Scheduling Component has an unique purpose, such as prioritizing tasks or mapping tasks over resources. A typical Scheduling Tree is shown below.



When a task is pushed by StarPU in a Modularized Scheduler, the task moves from a Scheduling Component to an other, following the hierarchy of the Scheduling Tree, and is stored in one of the Scheduling Components of the strategy. When a worker wants to pop a task from the Modularized Scheduler, the corresponding Worker Component of the Scheduling Tree tries to pull a task from its parents, following the hierarchy, and gives it to the worker if it succeeded to get one.

11.4.1 Interface

Each Scheduling Component must follow the following pre-defined Interface to be able to interact with other Scheduling Components.

- push_task (child_component, Task)
 The calling Scheduling Component transfers a task to its Child Component. When the Push function returns, the task no longer belongs to the calling Component. The Modularized Schedulers' model relies on this function to perform prefetching. See starpu_sched_component::push_task for more details
- pull_task (parent_component, caller_component) -> Task
 The calling Scheduling Component requests a task from its Parent Component. When the Pull function ends, the returned task belongs to the calling Component. See starpu_sched_component::pull_task for more details
- can_push (caller_component, parent_component)
 The calling Scheduling Component notifies its Parent Component that it is ready to accept new tasks. See starpu_sched_component::can_push for more details

 can_pull (caller_component, child_component)
 The calling Scheduling Component notifies its Child Component that it is ready to give new tasks. See starpu sched component::can pull for more details

The components also provide the following useful methods:

- · starpu_sched_component::estimated_load provides an estimated load of the component
- starpu_sched_component::estimated_end provides an estimated date of availability of workers behind the component, after processing tasks in the component and below. This is computed only if the estimated field of the tasks have been set before passing it to the component.

11.4.2 Building a Modularized Scheduler

11.4.2.1 Pre-implemented Components

StarPU is currently shipped with the following four Scheduling Components:

- Storage Components: Fifo, Prio
 Components which store tasks. They can also prioritize them if they have a defined priority. It is possible to
 define a threshold for those Components following two criterias: the number of tasks stored in the Compo nent, or the sum of the expected length of all tasks stored in the Component. When a push operation tries
 to queue a task beyond the threshold, the push fails. When some task leaves the queue (and thus possibly
 more tasks can fit), this component calls can push from ancestors.
- Resource-Mapping Components: Mct, Heft, Eager, Random, Work-Stealing
 "Core" of the Scheduling Strategy, those Components are the ones who make scheduling choices between their children components.
- Worker Components: Worker
 Each Worker Component modelizes a concrete worker, and copes with the technical tricks of interacting with the StarPU core. Modular schedulers thus usually have them at the bottom of their component tree.
- Special-Purpose Components: Perfmodel_Select, Best_Implementation
 Components dedicated to original purposes. The Perfmodel_Select Component decides which Resource
 Mapping Component should be used to schedule a task: a component that assumes tasks with a calibrated performance model; a component for non-yet-calibrated tasks, that will distribute them to get measurements done as quickly as possible; and a component that takes the tasks without performance models.

 The Best_Implementation Component chooses which implementation of a task should be used on the chosen resource.

11.4.2.2 Progression And Validation Rules

Some rules must be followed to ensure the correctness of a Modularized Scheduler:

- At least one Storage Component without threshold is needed in a Modularized Scheduler, to store incoming
 tasks from StarPU. It can for instance be a global component at the top of the tree, or one component per
 worker at the bottom of the tree, or intermediate assemblies. The important point is that the starpu_sched
 _component::push_task call at the top can not fail, so there has to be a storage component without threshold
 between the top of the tree and the first storage component with threshold, or the workers themselves.
- At least one Resource-Mapping Component is needed in a Modularized Scheduler. Resource-Mapping Components are the only ones which can make scheduling choices, and so the only ones which can have several child.

11.4.2.3 Locking in modularized schedulers

Most often, components do not need to take locks. This allows e.g. the push operation to be called in parallel when tasks get released in parallel from different workers which have completed different ancestor tasks.

When a component has internal information which needs to be kept coherent, the component can define its own lock at take it as it sees fit, e.g. to protect a task queue. This may however limit scalability of the scheduler. Conversely, since push and pull operations will be called concurrently from different workers, the component might prefer to use a central mutex to serialize all scheduling decisions to avoid pathological cases (all push calls decide to put their task on the same target)

11.4.2.4 Implementing a Modularized Scheduler

The following code shows how to implement a Tree-Eager-Prefetching Scheduler.

```
static void initialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
  /\star The eager component will decide for each task which worker will run it,
   \star and we want fifos both above and below the component \star/
  starpu_sched_component_initialize_simple_scheduler(
    starpu_sched_component_eager_create, NULL,
    STARPU_SCHED_SIMPLE_DECIDE_WORKERS
    STARPU_SCHED_SIMPLE_FIFO_ABOVE |
    STARPU_SCHED_SIMPLE_FIFOS_BELOW,
    sched_ctx_id);
/* Properly destroy the Scheduling Tree and all its Components */
static void deinitialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
  struct starpu sched tree * tree = (struct starpu sched tree*)
      starpu_sched_ctx_get_policy_data(sched_ctx_id);
  starpu_sched_tree_destroy(tree);
/\star \ \ \  \  Initializing \ the \ \  \  sched_policy \ \  \  struct \ \  \  associated \ \  to \ \  the \ \  Modularized
* Scheduler : only the init_sched and deinit_sched needs to be defined to * implement a Modularized Scheduler */
struct starpu_sched_policy _starpu_sched_tree_eager_prefetching_policy =
  .init_sched = initialize_eager_prefetching_center_policy,
  .deinit_sched = deinitialize_eager_prefetching_center_policy,
.add_workers = starpu_sched_tree_add_workers,
  .remove workers = starpu sched tree remove workers.
  .push_task = starpu_sched_tree_push_task,
  .pop_task = starpu_sched_tree_pop_task,
  .pre_exec_hook = starpu_sched_component_worker_pre_exec_hook,
  .post_exec_hook = starpu_sched_component_worker_post_exec_hook
  .pop every task = NULL,
  .policy_name = "tree-eager-prefetching",
.policy_description = "eager with prefetching tree policy"
```

starpu_sched_component_initialize_simple_scheduler() is a helper function which makes it very trivial to assemble a modular scheduler around a scheduling decision component as seen above (here, a dumb eager decision component). Most often a modular scheduler can be implemented that way.

A modular scheduler can also be constructed hierarchically with starpu_sched_component_composed_recipe_create().

That modular scheduler can also be built by hand in the following way:

```
#define _STARPU_SCHED_NTASKS_THRESHOLD_DEFAULT 2
#define _STARPU_SCHED_EXP_LEN_THRESHOLD_DEFAULT 1000000000.0
static void initialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
 unsigned ntasks_threshold = _STARPU_SCHED_NTASKS_THRESHOLD_DEFAULT;
double exp_len_threshold = _STARPU_SCHED_EXP_LEN_THRESHOLD_DEFAULT;
 starpu_sched_ctx_create_worker_collection
    (sched_ctx_id, STARPU_WORKER_LIST);
  /* Create the Scheduling Tree */
 struct starpu_sched_tree * t = starpu_sched_tree_create(
      sched_ctx_id);
  /* The Root Component is a Flow-control Fifo Component */
  t->root = starpu_sched_component_fifo_create(NULL);
 /* The Resource-mapping Component of the strategy is an Eager Component
  struct starpu_sched_component *eager_component =
      starpu_sched_component_eager_create(NULL);
 /\star Create links between Components : the Eager Component is the child
    of the Root Component */
  starpu sched component connect(t->root, eager component);
  /\star A task threshold is set for the Flow-control Components which will
  * be connected to Worker Components. By doing so, this Modularized
  \star Scheduler will be able to perform some prefetching on the resources
 struct starpu_sched_component_fifo_data fifo_data =
```

```
.ntasks_threshold = ntasks_threshold,
    .exp_len_threshold = exp_len_threshold,
  unsigned i:
  for(i = 0; i < starpu_worker_get_count() + starpu_combined_worker_get_count</pre>
    /\star Each Worker Component has a Flow-control Fifo Component as
     * father */
    struct starpu sched component * worker component =
     starpu_sched_component_worker_new(i);
    struct starpu_sched_component * fifo_component =
      starpu_sched_component_fifo_create(&fifo_data);
    starpu_sched_component_connect(fifo_component, worker_component);
    /* Each Flow-control Fifo Component associated to a Worker
    * Component is linked to the Eager Component as one of its
    starpu sched component connect (eager component, fifo component);
  starpu_sched_tree_update_workers(t);
 starpu_sched_ctx_set_policy_data(sched_ctx_id, (void*)t);
/* Properly destroy the Scheduling Tree and all its Components */
static void deinitialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
 struct starpu_sched_tree * tree = (struct starpu_sched_tree*)
     starpu_sched_ctx_get_policy_data(sched_ctx_id);
  starpu_sched_tree_destroy(tree);
  starpu_sched_ctx_delete_worker_collection(sched_ctx_id);
/\star Initializing the starpu_sched_policy struct associated to the Modularized
* Scheduler : only the init_sched and deinit_sched needs to be defined to
  implement a Modularized Scheduler */
struct starpu_sched_policy _starpu_sched_tree_eager_prefetching_policy =
  .init_sched = initialize_eager_prefetching_center_policy,
  .deinit_sched = deinitialize_eager_prefetching_center_policy,
  .add_workers = starpu_sched_tree_add_workers,
  .remove_workers = starpu_sched_tree_remove_workers,
  .push_task = starpu_sched_tree_push_task,
  .pop_task = starpu_sched_tree_pop_task,
  .pre_exec_hook = starpu_sched_component_worker_pre_exec_hook,
  .post_exec_hook = starpu_sched_component_worker_post_exec_hook
  .pop_every_task = NULL,
  .policy_name = "tree-eager-prefetching",
  .policy_description = "eager with prefetching tree policy"
```

Other modular scheduler examples can be seen in src/sched_policies/modular_*.c

For instance, modular-heft-prio needs performance models, decides memory nodes, uses prioritized fifos above and below, and decides the best implementation.

If unsure on the result of the modular scheduler construction, you can run a simple application with FxT enabled (see Generating Traces With FxT), and open the generated file trace.html in a web-browser.

11.4.3 Management of parallel task

At the moment, parallel tasks can be managed in modularized schedulers through combined workers: instead of connecting a scheduling component to a worker component, one can connect it to a combined worker component (i.e. a worker component created with a combined worker id). That component will handle creating task aliases for parallel execution and push them to the different workers components.

11.4.4 Writing a Scheduling Component

11.4.4.1 Generic Scheduling Component

Each Scheduling Component is instantiated from a Generic Scheduling Component, which implements a generic version of the Interface. The generic implementation of Pull, Can_Pull and Can_Push functions are recursive calls to their parents (respectively to their children). However, as a Generic Scheduling Component do not know how much children it will have when it will be instantiated, it does not implement the Push function.


11.4.4.2 Instantiation : Redefining the Interface

A Scheduling Component must implement all the functions of the Interface. It is so necessary to implement a Push function to instantiate a Scheduling Component. The implemented Push function is the "fingerprint" of a Scheduling Component. Depending on how functionalities or properties programmers want to give to the Scheduling Component they are implementing, it is possible to reimplement all the functions of the Interface. For example, a Flow-control Component reimplements the Pull and the Can_Push functions of the Interface, allowing to catch the generic recursive calls of these functions. The Pull function of a Flow-control Component can, for example, pop a task from the local storage queue of the Component, and give it to the calling Component which asks for it.

11.4.4.3 Detailed Progression and Validation Rules

- A Reservoir is a Scheduling Component which redefines a Push and a Pull function, in order to store tasks into it. A Reservoir delimit Scheduling Areas in the Scheduling Tree.
- A Pump is the engine source of the Scheduler: it pushes/pulls tasks to/from a Scheduling Component to an other. Native Pumps of a Scheduling Tree are located at the root of the Tree (incoming Push calls from StarPU), and at the leafs of the Tree (Pop calls coming from StarPU Workers). Pre-implemented Scheduling Components currently shipped with Pumps are Flow-Control Components and the Resource-Mapping Component Heft, within their defined Can_Push functions.
- · A correct Scheduling Tree requires a Pump per Scheduling Area and per Execution Flow.

The Tree-Eager-Prefetching Scheduler shown in Section Implementing a Modularized Scheduler follows the previous assumptions :



11.5 Graph-based Scheduling

For performance reasons, most of the schedulers shipped with StarPU use simple list-scheduling heuristics, assuming that the application has already set priorities. This is why they do their scheduling between when tasks become available for execution and when a worker becomes idle, without looking at the task graph.

Other heuristics can however look at the task graph. Recording the task graph is expensive, so it is not available by default, the scheduling heuristic has to set _starpu_graph_record to 1 from the initialization function, to make it available. Then the _starpu_graph* functions can be used.

src/sched_policies/graph_test_policy.cis an example of simple greedy policy which automatically computes priorities by bottom-up rank.

The idea is that while the application submits tasks, they are only pushed to a bag of tasks. When the application is finished with submitting tasks, it calls starpu_do_schedule() (or starpu_task_wait_for_all(), which calls starpu—do_schedule()), and the starpu_sched_policy::do_schedule method of the scheduler is called. This method calls _starpu_graph_compute_depths() to compute the bottom-up ranks, and then uses these ranks to set priorities over tasks.

It then has two priority queues, one for CPUs, and one for GPUs, and uses a dumb heuristic based on the duration of the task over CPUs and GPUs to decide between the two queues. CPU workers can then pop from the CPU priority queue, and GPU workers from the GPU priority queue.

11.6 Debugging Scheduling

All the Online Performance Tools and Offline Performance Tools can be used to get information about how well the execution proceeded, and thus the overall quality of the execution.

Precise debugging can also be performed by using the STARPU_TASK_BREAK_ON_PUSH, STARPU_TASK_← BREAK_ON_SCHED, STARPU_TASK_BREAK_ON_POP, and STARPU_TASK_BREAK_ON_EXEC environment variables. By setting the job_id of a task in these environment variables, StarPU will raise SIGTRAP when the task is being scheduled, pushed, or popped by the scheduler. This means that when one notices that a task is being scheduled in a seemingly odd way, one can just reexecute the application in a debugger, with some of those variables set, and the execution will stop exactly at the scheduling points of this task, thus allowing to inspect the scheduler state, etc.

Chapter 12

Debugging Tools

StarPU provides several tools to help debugging applications. Execution traces can be generated and displayed graphically, see Generating Traces With FxT.

12.1 TroubleShooting In General

Generally-speaking, if you have troubles, pass --enable-debug to configure to enable some checks which impact performance, but will catch common issues, possibly earlier than the actual problem you are observing, which may just be a consequence of a bug that happened earlier. Also, make sure not to have the --enable-fast configure option which drops very useful catchup assertions. If your program is valgrind-safe, you can use it, see Using Other Debugging Tools.

Depending on your toolchain, it might happen that you get undefined reference to `__stack_chk chk cycle guard' errors. In that case, use the -disable-fstack-protector-all option to avoid the issue. Then, if your program crashes with an assertion error, a segfault, etc. you can send us the result of

```
thread apply all bt
```

run in gdb at the point of the crash.

In case your program just hangs, but it may also be useful in case of a crash too, it helps to source gdbinit as described in the next section to be able to run and send us the output of the following commands:

```
starpu-workers
starpu-tasks
starpu-print-requests
starpu-print-frrequests
starpu-print-irrequests
starpu-print-irrequests
```

To give us an idea of what is happening within StarPU. If the outputs are not too long, you can even run

```
starpu-all-tasks
starpu-print-all-tasks
starpu-print-datas-summary
starpu-print-datas
```

12.2 Using The Gdb Debugger

Some gdb helpers are provided to show the whole StarPU state:

```
(gdb) source tools/gdbinit
(gdb) help starpu
```

For instance,

- one can print all tasks with starpu-print-all-tasks,
- print all datas with starpu-print-datas,

82 Debugging Tools

• print all pending data transfers with starpu-print-prequests, starpu-print-requests, starpu-print-frequests, starpu-print-irequests,

• print pending MPI requests with starpu-mpi-print-detached-requests

Some functions can only work if --enable-debug was passed to configure (because they impact performance)

12.3 Using Other Debugging Tools


Valgrind can be used on StarPU: valgrind.h just needs to be found at configure time, to tell valgrind about some known false positives and disable host memory pinning. Other known false positives can be suppressed by giving the suppression files in tools/valgrind/*.suppr to valgrind's -suppressions option.

The environment variable STARPU_DISABLE_KERNELS can also be set to 1 to make StarPU does everything (schedule tasks, transfer memory, etc.) except actually calling the application-provided kernel functions, i.e. the computation will not happen. This permits to quickly check that the task scheme is working properly.

12.4 Using The Temanejo Task Debugger

StarPU can connect to Temanejo >= 1.0 rc2 (see http://www.hlrs.de/temanejo), to permit nice visual task debugging. To do so, build Temanejo's libayudame.so, install Ayudame.h to e. \leftarrow g. /usr/local/include, apply the tools/patch-ayudame to it to fix C build, re-configure, make sure that it found it, rebuild StarPU. Run the Temanejo GUI, give it the path to your application, any options you want to pass it, the path to libayudame.so.

It permits to visualize the task graph, add breakpoints, continue execution task-by-task, and run gdb on a given task, etc.



Make sure to specify at least the same number of CPUs in the dialog box as your machine has, otherwise an error will happen during execution. Future versions of Temanejo should be able to tell StarPU the number of CPUs to use.

| 12.4 Using The Temanejo Task Debugger | 83 |
|--|----------------|
| Tag numbers have to be below 4000000000000000000000000000000000000 | to distinguish |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |

84 Debugging Tools

Chapter 13

Online Performance Tools

13.1 On-line Performance Feedback

13.1.1 Enabling On-line Performance Monitoring

In order to enable online performance monitoring, the application can call starpu_profiling_status_set() with the parameter STARPU_PROFILING_ENABLE. It is possible to detect whether monitoring is already enabled or not by calling starpu_profiling_status_get(). Enabling monitoring also reinitialize all previously collected feedback. The environment variable STARPU_PROFILING can also be set to 1 to achieve the same effect. The function starpu—profiling_init() can also be called during the execution to reinitialize performance counters and to start the profiling if the environment variable STARPU_PROFILING is set to 1.

Likewise, performance monitoring is stopped by calling starpu_profiling_status_set() with the parameter STARPU — PROFILING_DISABLE. Note that this does not reset the performance counters so that the application may consult them later on.

More details about the performance monitoring API are available in Profiling.

13.1.2 Per-task Feedback

If profiling is enabled, a pointer to a structure starpu_profiling_task_info is put in the field starpu_task::profiling_info when a task terminates. This structure is automatically destroyed when the task structure is destroyed, either automatically or by calling starpu_task_destroy().

The structure starpu_profiling_task_info indicates the date when the task was submitted (starpu_profiling_task_info::submit_time), started (starpu_profiling_task_info::start_time), and terminated (starpu_profiling_task_info::end_time), relative to the initialization of StarPU with starpu_init(). It also specifies the identifier of the worker that has executed the task (starpu_profiling_task_info::workerid). These date are stored as timespec structures which the user may convert into micro-seconds using the helper function starpu_timing_timespec_to_us().

It it worth noting that the application may directly access this structure from the callback executed at the end of the task. The structure starpu_task associated to the callback currently being executed is indeed accessible with the function starpu_task_get_current().

13.1.3 Per-codelet Feedback

The field starpu_codelet::per_worker_stats is an array of counters. The i-th entry of the array is incremented every time a task implementing the codelet is executed on the i-th worker. This array is not reinitialized when profiling is enabled or disabled.

13.1.4 Per-worker Feedback

The second argument returned by the function starpu_profiling_worker_get_info() is a structure starpu_profiling_ worker_info that gives statistics about the specified worker. This structure specifies when StarPU started collecting profiling information for that worker (starpu_profiling_worker_info::start_time), the duration of the profiling measurement interval (starpu_profiling_worker_info::total_time), the time spent executing kernels (starpu_profiling_worker info::executing_time), the time spent sleeping because there is no task to execute at all (starpu_profiling_worker info::sleeping_time), and the number of tasks that were executed while profiling was enabled. These values give

86 Online Performance Tools

an estimation of the proportion of time spent do real work, and the time spent either sleeping because there are not enough executable tasks or simply wasted in pure StarPU overhead.

Calling starpu_profiling_worker_get_info() resets the profiling information associated to a worker.

To easily display all this information, the environment variable STARPU_WORKER_STATS can be set to 1 (in addition to setting STARPU_PROFILING to 1). A summary will then be displayed at program termination:

```
Worker stats:
CUDA 0.0 (4.7 GiB)
480 task(s)
total: 1574.82 ms executing: 1510.72 ms sleeping: 0.00 ms overhead 64.10 ms
325.217970 GFlop/s
CPU 0
22 task(s)
total: 1574.82 ms executing: 1364.81 ms sleeping: 0.00 ms overhead 210.01 ms
7.512057 GFlop/s
CPU 1
14 \, \text{task}(s)
total: 1574.82 ms executing: 1500.13 ms sleeping: 0.00 ms overhead 74.69 ms
6.675853 GFlop/s
CPU 2
14 task(s)
total: 1574.82 ms executing: 1553.12 ms sleeping: 0.00 ms overhead 21.70 ms
7.152886 GFlop/s
```

The number of GFlops is available because the starpu_task::flops field of the tasks were filled (or STARPU_FLOPS used in starpu_task insert()).

When an FxT trace is generated (see Generating Traces With FxT), it is also possible to use the tool $starpu_ \leftarrow workers_activity$ (see Monitoring Activity) to generate a graphic showing the evolution of these values during the time, for the different workers.

13.1.5 Bus-related Feedback

The bus speed measured by StarPU can be displayed by using the tool starpu_machine_display, for instance:

```
StarPU has found:
       3 CUDA devices
              CUDA 0 (Tesla C2050 02:00.0)
               CUDA 1 (Tesla C2050 03:00.0)
               CUDA 2 (Tesla C2050 84:00.0)
                                    to CUDA 1
     to RAM
                      to CUDA 0
                                                     to CUDA 2
from
RAM
       0.000000
                      5176.530428
                                      5176.492994
                                                     5191.710722
CUDA 0 4523.732446
                                      2414.074751
                                                     2417.379201
                      0.000000
CUDA 1 4523.718152
                      2414.078822
                                     0.000000
                                                     2417.375119
CUDA 2 4534.229519
                      2417.069025
                                     2417.060863
                                                     0.000000
```

Statistics about the data transfers which were performed and temporal average of bandwidth usage can be obtained by setting the environment variable STARPU_BUS_STATS to 1; a summary will then be displayed at program termination:

```
Data transfer stats:

RAM 0 -> CUDA 0 319.92 MB 213.10 MB/s (transfers : 91 - avg 3.52 MB)

CUDA 0 -> RAM 0 214.45 MB 142.85 MB/s (transfers : 61 - avg 3.52 MB)

RAM 0 -> CUDA 1 302.34 MB 201.39 MB/s (transfers : 86 - avg 3.52 MB)

CUDA 1 -> RAM 0 133.59 MB 88.99 MB/s (transfers : 38 - avg 3.52 MB)

CUDA 0 -> CUDA 1 144.14 MB 96.01 MB/s (transfers : 41 - avg 3.52 MB)

CUDA 1 -> CUDA 0 130.08 MB 86.64 MB/s (transfers : 37 - avg 3.52 MB)

RAM 0 -> CUDA 2 312.89 MB 208.42 MB/s (transfers : 89 - avg 3.52 MB)

CUDA 2 -> RAM 0 133.59 MB 88.99 MB/s (transfers : 38 - avg 3.52 MB)

CUDA 0 -> CUDA 2 151.17 MB 100.69 MB/s (transfers : 43 - avg 3.52 MB)

CUDA 2 -> CUDA 0 105.47 MB 70.25 MB/s (transfers : 30 - avg 3.52 MB)

CUDA 1 -> CUDA 2 175.78 MB 117.09 MB/s (transfers : 50 - avg 3.52 MB)

CUDA 2 -> CUDA 1 203.91 MB 135.82 MB/s (transfers : 58 - avg 3.52 MB)

Total transfers: 2.27 GB
```

13.1.6 MPI-related Feedback

Statistics about the data transfers which were performed over MPI can be obtained by setting the environment variable STARPU COMM STATS to 1; a summary will then be displayed at program termination:

```
[starpu_comm_stats][1] TOTAL: 456.000000 B 0.000435 MB 0.000188 B/s 0.000000 MB/s [starpu_comm_stats][1:0] 456.000000 B 0.000435 MB 0.000188 B/s 0.000000 MB/s [starpu_comm_stats][0] TOTAL: 456.000000 B 0.000435 MB 0.000188 B/s 0.000000 MB/s [starpu_comm_stats][0:1] 456.000000 B 0.000435 MB 0.000188 B/s 0.000000 MB/s
```

These statistics can be plotted as heatmaps using StarPU tool starpu_mpi_comm_matrix.py (see Debugging MPI).

13.2 Task And Worker Profiling

A full example showing how to use the profiling API is available in the StarPU sources in the directory examples/profiling/.

```
struct starpu_task *task = starpu_task_create();
task->cl = &cl;
task->synchronous = 1;
/\star We will destroy the task structure by hand so that we can
 \star query the profiling info before the task is destroyed. \star/
task->destroy = 0;
/\star Submit and wait for completion (since synchronous was set to 1) \star/
starpu_task_submit(task);
/* The task is finished, get profiling information */
struct starpu_profiling_task_info *info = task->profiling_info;
/* How much time did it take before the task started ? */
double delay += starpu_timing_timespec_delay_us(&info->submit_time
       , &info->start_time);
/\star How long was the task execution ? \star/
double length += starpu_timing_timespec_delay_us(&info->start_time
        . &info->end time):
/* We no longer need the task structure */
starpu_task_destroy(task);
/\star Display the occupancy of all workers during the test \star/
int worker:
for (worker = 0; worker < starpu_worker_get_count(); worker++)</pre>
          struct starpu_profiling_worker_info worker_info;
          int ret = starpu_profiling_worker_get_info(worker, &worker_info);
         STARPU ASSERT (!ret):
         double total time = starpu timing timespec to us(&worker info
          double executing_time = starpu_timing_timespec_to_us(&
       worker_info.executing_time);
         double sleeping_time = starpu_timing_timespec_to_us(&
       worker info.sleeping time);
          double overhead_time = total_time - executing_time - sleeping_time;
          float executing_ratio = 100.0*executing_time/total_time;
         float sleeping_ratio = 100.0*sleeping_time/total_time;
float overhead_ratio = 100.0 - executing_ratio - sleeping_ratio;
         char workername[128];
          starpu_worker_get_name(worker, workername, 128);
fprintf(stderr, "Worker %s:\n", workername);
fprintf(stderr, "\ttotal time: %.21f ms\n", total_time*1e-3);
         fprintf(stderr, "\texec time: %.21f ms (%.2f %%)\n", executing_time*1e-3, executing_ratio);
fprintf(stderr, "\text{time: %.21f ms (%.2f %%)\n", sleeping_time*1e-3, sleeping_ratio);
fprintf(stderr, "\toverhead time: %.21f ms (%.2f %%)\n", overhead_time*1e-3, overhead_ratio);
}
```

13.3 Performance Model Example

To achieve good scheduling, StarPU scheduling policies need to be able to estimate in advance the duration of a task. This is done by giving to codelets a performance model, by defining a structure starpu_perfmodel and providing

88 Online Performance Tools

its address in the field starpu_codelet::model. The fields starpu_perfmodel::symbol and starpu_perfmodel::type are mandatory, to give a name to the model, and the type of the model, since there are several kinds of performance models. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset(), or by letting the compiler implicitly do it as examplified below.

• Measured at runtime (model type STARPU_HISTORY_BASED). This assumes that for a given set of data input/output sizes, the performance will always be about the same. This is very true for regular kernels on GPUs for instance (<0.1% error), and just a bit less true on CPUs (~=1% error). This also assumes that there are few different sets of data input/output sizes. StarPU will then keep record of the average time of previous executions on the various processing units, and use it as an estimation. History is done per task size, by using a hash of the input and ouput sizes as an index. It will also save it in \$STAR← PU_HOME/.starpu/sampling/codelets for further executions, and can be observed by using the tool starpu_perfmodel_display, or drawn by using the tool starpu_perfmodel_plot (Performance Model Calibration). The models are indexed by machine name. To share the models between machines (e.g. for a homogeneous cluster), use export STARPU_HOSTNAME=some_global_name. Measurements are only done when using a task scheduler which makes use of it, such as dmda. Measurements can also be provided explicitly by the application, by using the function starpu_perfmodel_update_← history().

The following is a small code example.

If e.g. the code is recompiled with other compilation options, or several variants of the code are used, the symbol string should be changed to reflect that, in order to recalibrate a new model from zero. The symbol string can even be constructed dynamically at execution time, as long as this is done before submitting any task using it.

```
static struct starpu_perfmodel mult_perf_model =
{
    .type = STARPU_HISTORY_BASED,
    .symbol = "mult_perf_model"
};

struct starpu_codelet cl =
{
    .cpu_funcs = { cpu_mult },
    .cpu_funcs_name = { "cpu_mult" },
    .nbuffers = 3,
    .modes = { STARPU_R, STARPU_R, STARPU_W },
    /* for the scheduling policy to be able to use performance models */
    .model = &mult_perf_model
};
```

Measured at runtime and refined by regression (model types STARPU_REGRESSION_BASED and ST←
ARPU_NL_REGRESSION_BASED). This still assumes performance regularity, but works with various data
input sizes, by applying regression over observed execution times. STARPU_REGRESSION_BASED uses
an a*n^b regression form, STARPU_NL_REGRESSION_BASED uses an a*n^b+c (more precise than
STARPU_REGRESSION_BASED, but costs a lot more to compute).

For instance, tests/perfmodels/regression_based.c uses a regression-based performance model for the function memset().

Of course, the application has to issue tasks with varying size so that the regression can be computed. StarPU will not trust the regression unless there is at least 10% difference between the minimum and maximum observed input size. It can be useful to set the environment variable STARPU_CALIBRATE to 1 and run the application on varying input sizes with STARPU_SCHED set to dmda scheduler, so as to feed the performance model for a variety of inputs. The application can also provide the measurements explictly by using the function starpu_perfmodel_update_history(). The tools starpu_perfmodel_display and starpu_perfmodel_plot can be used to observe how much the performance model is calibrated (Performance Model Calibration); when their output look good, STARPU_CALIBRATE can be reset to 0 to let StarPU use the resulting performance model without recording new measures, and STARPU_SCHED can be set to dmda to benefit from the performance models. If the data input sizes vary a lot, it is really important to set STARPU_CALIBRATE to 0, otherwise StarPU will continue adding the measures, and result with a very big performance model, which will take time a lot of time to load and save.

For non-linear regression, since computing it is quite expensive, it is only done at termination of the application. This means that the first execution of the application will use only history-based performance model to perform scheduling, without using regression.

 Another type of model is STARPU_MULTIPLE_REGRESSION_BASED, which is based on multiple linear regression. In this model, the user defines both the relevant parameters and the equation for computing the task duration.

$$T_{kernel} = a + b(M^{\alpha_1} * N^{\beta_1} * K^{\gamma_1}) + c(M^{\alpha_2} * N^{\beta_2} * K^{\gamma_2}) + \dots$$

M,N,K are the parameters of the task, added at the task creation. These need to be extracted by the cleperf_func function, which should be defined by the user. α,β,γ are the exponents defined by the user in model->combinations table. Finally, coefficients a,b,c are computed automatically by the StarPU at the end of the execution, using least squares method of the dgels_LAPACK function.

examples/mlr/mlr.c example provides more details on the usage of STARPU_MULTIPLE_REGRE \leftarrow SSION BASED models.

Coefficients computation is done at the end of the execution, and the results are stored in standard codelet perfmodel files. Additional files containing the duration of task together with the value of each parameter are stored in .starpu/sampling/codelets/tmp/ directory. These files are reused when STARPU_ \leftarrow CALIBRATE environment variable is set to 1, to recompute coefficients based on the current, but also on the previous executions. Additionally, when multiple linear regression models are disabled (using --disable-mlr configure option) or when the model->combinations are not defined, StarPU will still write output files into .starpu/sampling/codelets/tmp/ to allow performing an analysis. This analysis typically aims at finding the most appropriate equation for the codelet and tools/starpu_mlr_analysis script provides an example of how to perform such study.

- Provided as an estimation from the application itself (model type STARPU_COMMON and field starpu_perfmodel::cost_function), see for instance examples/common/blas_model.h and examples/common/blas_model.c.
- Provided explicitly by the application (model type STARPU_PER_ARCH): either field starpu_perfmodel
 ::arch_cost_function, or the fields .per_arch[arch][nimpl].cost_function have to be filled with
 pointers to functions which return the expected duration of the task in micro-seconds, one per architecture,
 see for instance tests/datawizard/locality.c

For STARPU_HISTORY_BASED, STARPU_REGRESSION_BASED, and STARPU_NL_REGRESSION_BASED, the dimensions of task data (both input and output) are used as an index by default. STARPU_HISTORY_BASED uses a CRC hash of the dimensions as an index to distinguish histories, and STARPU_REGRESSION_BASED and STARPU_NL_REGRESSION_BASED use the total size as an index for the regression.

The starpu_perfmodel::size_base and starpu_perfmodel::footprint fields however permit the application to override that, when for instance some of the data do not matter for task cost (e.g. mere reference table), or when using sparse structures (in which case it is the number of non-zeros which matter), or when there is some hidden parameter such as the number of iterations, or when the application actually has a very good idea of the complexity of the algorithm, and just not the speed of the processor, etc. The example in the directory <code>examples/pi</code> uses this to include the number of iterations in the base size. <code>starpu_perfmodel::size_base</code> should be used when the variance of the actual performance is known (i.e. bigger return value is longer execution time), and thus particularly useful for <code>STARPU</code>—<code>REGRESSION_BASED</code> or <code>STARPU_NL_REGRESSION_BASED</code>. <code>starpu_perfmodel::footprint</code> can be used when the variance of the actual performance is unknown (irregular performance behavior, etc.), and thus only useful for <code>STARPU_HISTORY_BASED</code>. <code>starpu_task_data_footprint()</code> can be used as a base and combined with other parameters through <code>starpu_hash_crc32c_be()</code> for instance.

StarPU will automatically determine when the performance model is calibrated, or rather, it will assume the performance model is calibrated until the application submits a task for which the performance can not be predicted. For STARPU_HISTORY_BASED, StarPU will require 10 (STARPU_CALIBRATE_MINIMUM) measurements for a given size before estimating that an average can be taken as estimation for further executions with the same size. For STARPU_REGRESSION_BASED and STARPU_NL_REGRESSION_BASED, StarPU will require 10 (STAR←PU_CALIBRATE_MINIMUM) measurements, and that the minimum measured data size is smaller than 90% of the maximum measured data size (i.e. the measurement interval is large enough for a regression to have a meaning). Calibration can also be forced by setting the STARPU_CALIBRATE environment variable to 1, or even reset by setting it to 2.

How to use schedulers which can benefit from such performance model is explained in Task Scheduling Policies. The same can be done for task energy consumption estimation, by setting the field starpu_codelet::energy_

model the same way as the field starpu_codelet::model. Note: for now, the application has to give to the energy consumption performance model a name which is different from the execution time performance model.

90 Online Performance Tools

The application can request time estimations from the StarPU performance models by filling a task structure as usual without actually submitting it. The data handles can be created by calling any of the functions $starpu_*_\leftarrow data_register$ with a NULL pointer and -1 node and the desired data sizes, and need to be unregistered as usual. The functions $starpu_task_expected_length()$ and $starpu_task_expected_energy()$ can then be called to get an estimation of the task cost on a given arch. $starpu_task_footprint()$ can also be used to get the footprint used for indexing history-based performance models. $starpu_task_destroy()$ needs to be called to destroy the dummy task afterwards. See $tests/perfmodels/regression_based.c$ for an example.


The application can also request an on-the-fly XML report of the performance model, by calling starpu_perfmodel dump xml() to print the report to a FILE*.

13.4 Data trace and tasks length

It is possible to get statistics about tasks length and data size by using:

```
$ starpu_fxt_data_trace filename [codelet1 codelet2 ... codeletn]
```

Where filename is the FxT trace file and codeletX the names of the codelets you want to profile (if no names are specified, starpu_fxt_data_trace will profile them all). This will create a file, data_trace.gp which can be executed to get a .eps image of these results. On the image, each point represents a task, and each color corresponds to a codelet.



Chapter 14

Offline Performance Tools

To get an idea of what is happening, a lot of performance feedback is available, detailed in this chapter. The various informations should be checked for.

- · What does the Gantt diagram look like? (see Creating a Gantt Diagram)
 - If it's mostly green (tasks running in the initial context) or context specific color prevailing, then the
 machine is properly utilized, and perhaps the codelets are just slow. Check their performance, see
 Performance Of Codelets.
 - If it's mostly purple (FetchingInput), tasks keep waiting for data transfers, do you perhaps have far more communication than computation? Did you properly use CUDA streams to make sure communication can be overlapped? Did you use data-locality aware schedulers to avoid transfers as much as possible?
 - If it's mostly red (Blocked), tasks keep waiting for dependencies, do you have enough parallelism? It
 might be a good idea to check what the DAG looks like (see Creating a DAG With Graphviz).
 - If only some workers are completely red (Blocked), for some reason the scheduler didn't assign tasks
 to them. Perhaps the performance model is bogus, check it (see Performance Of Codelets). Do all your
 codelets have a performance model? When some of them don't, the schedulers switches to a greedy
 algorithm which thus performs badly.

You can also use the Temanejo task debugger (see Using The Temanejo Task Debugger) to visualize the task graph more easily.

14.1 Off-line Performance Feedback

14.1.1 Generating Traces With FxT

StarPU can use the FxT library (see https://savannah.nongnu.org/projects/fkt/) to generate traces with a limited runtime overhead.

You can get a tarball from http://download.savannah.gnu.org/releases/fkt/

Compiling and installing the FxT library in the \$FXTDIR path is done following the standard procedure:

```
$ ./configure --prefix=$FXTDIR
$ make
$ make install
```

In order to have StarPU to generate traces, StarPU should be configured with the option --with-fxt:

```
$ ./configure --with-fxt=$FXTDIR
```

Or you can simply point the PKG_CONFIG_PATH to \$FXTDIR/lib/pkgconfig and pass --with-fxt to configure

When FxT is enabled, a trace is generated when StarPU is terminated by calling starpu_shutdown(). The trace is a binary file whose name has the form $prof_file_XXX_YYY$ where XXX is the user name, and YYY is the pid of the process that used StarPU. This file is saved in the /tmp/ directory by default, or by the directory specified by the environment variable STARPU_FXT_PREFIX.

92 Offline Performance Tools

The additional configure option --enable-fxt-lock can be used to generate trace events which describes the locks behaviour during the execution. It is however very heavy and should not be used unless debugging StarPU's internal locking.

The environment variable STARPU_FXT_TRACE can be set to 0 to disable the generation of the $prof_file_{\leftarrow}$ XXX_YYY file.

When the FxT trace file prof_file_something has been generated, it is possible to generate different trace formats by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

Or alternatively, setting the environment variable STARPU_GENERATE_TRACE to 1 before application execution will make StarPU do it automatically at application shutdown.

One can also set the environment variable STARPU_GENERATE_TRACE_OPTIONS to specify options, see starpu fxt tool -help, for example:

```
$ export STARPU_GENERATE_TRACE=1
$ export STARPU_GENERATE_TRACE_OPTIONS="-no-acquire"
```

When running a MPI application, STARPU_GENERATE_TRACE will not work as expected (each node will try to generate trace files, thus mixing outputs...), you have to collect the trace files from the MPI nodes, and specify them all on the command starpu_fxt_tool, for instance:

```
$ starpu_fxt_tool -i /tmp/prof_file_something*
```

By default, the generated trace contains all informations. To reduce the trace size, various -no-foo options can be passed to $starpu_fxt_tool$, see $starpu_fxt_tool$ -help.

14.1.1.1 Creating a Gantt Diagram

One of the generated files is a trace in the Paje format. The file, located in the current directory, is named paje. \leftarrow trace. It can be viewed with ViTE (http://vite.gforge.inria.fr/) a trace visualizing open-source tool. To open the file paje.trace with ViTE, use the following command:

```
$ vite paje.trace
```

Tasks can be assigned a name (instead of the default unknown) by filling the optional starpu_codelet::name, or assigning them a performance model. The name can also be set with the field starpu_task::name or by using STARPU NAME when calling starpu_task insert().

Tasks are assigned default colors based on the worker which executed them (green for CPUs, yellow/orange/red for CUDAs, blue for OpenCLs, red for MICs, ...). To use a different color for every type of task, one can specify the option -c to $starpu_fxt_tool$ or in STARPU_GENERATE_TRACE_OPTIONS. Tasks can also be given a specific color by setting the field $starpu_codelet::color$ or the $starpu_task::color$. Colors are expressed with the following format 0xRRGGBB (e.g 0xFF0000 for red). See $basic_examples/task_insert_color$ for examples on how to assign colors.

To identify tasks precisely, the application can also set the field starpu_task::tag_id or setting STARPU_TAG_ONLY when calling starpu_task_insert("). The value of the tag will then show up in the trace.

One can also introduce user-defined events in the diagram thanks to the starpu_fxt_trace_user_event_string() function.

One can also set the iteration number, by just calling starpu_iteration_push() at the beginning of submission loops and starpu_iteration_pop() at the end of submission loops. These iteration numbers will show up in traces for all tasks submitted from there.

Coordinates can also be given to data with the starpu_data_set_coordinates() or starpu_data_set_coordinates_
array() function. In the trace, tasks will then be assigned the coordinates of the first data they write to.

Traces can also be inspected by hand by using the tool fxt_print, for instance:

```
$ fxt_print -o -f /tmp/prof_file_something
```

Timings are in nanoseconds (while timings as seen in ViTE are in milliseconds).

14.1.1.2 Creating a DAG With Graphviz

Another generated trace file is a task graph described using the DOT language. The file, created in the current directory, is named dag.dot file in the current directory. It is possible to get a graphical output of the graph by using the graphviz library:

```
$ dot -Tpdf dag.dot -o output.pdf
```

14.1.1.3 Getting Task Details

Another generated trace file gives details on the executed tasks. The file, created in the current directory, is named tasks.rec. This file is in the recutils format, i.e. Field: value lines, and empty lines to separate each task. This can be used as a convenient input for various ad-hoc analysis tools. By default it only contains information about the actual execution. Performance models can be obtained by running starpu_tasks_rec_complete on it:

```
$ starpu_tasks_rec_complete tasks.rec tasks2.rec
```

which will add EstimatedTime lines which contain the performance model-estimated time (in μs) for each worker starting from 0. Since it needs the performance models, it needs to be run the same way as the application execution, or at least with $\texttt{STARPU_HOSTNAME}$ set to the hostname of the machine used for execution, to get the performance models of that machine.

Another possibility is to obtain the performance models as an auxiliary perfmodel.rec file, by using the starpu_perfmodel_recdump utility:

```
$ starpu_perfmodel_recdump tasks.rec -o perfmodel.rec
```

14.1.1.4 Monitoring Activity

Another generated trace file is an activity trace. The file, created in the current directory, is named $activity. \leftarrow data$. A profile of the application showing the activity of StarPU during the execution of the program can be generated:

```
$ starpu_workers_activity activity.data
```

This will create a file named activity.eps in the current directory. This picture is composed of two parts. The first part shows the activity of the different workers. The green sections indicate which proportion of the time was spent executed kernels on the processing unit. The red sections indicate the proportion of time spent in StartPU: an important overhead may indicate that the granularity may be too low, and that bigger tasks may be appropriate to use the processing unit more efficiently. The black sections indicate that the processing unit was blocked because there was no task to process: this may indicate a lack of parallelism which may be alleviated by creating more tasks when it is possible.

The second part of the picture activity.eps is a graph showing the evolution of the number of tasks available in the system during the execution. Ready tasks are shown in black, and tasks that are submitted but not schedulable yet are shown in grey.

14.1.1.5 Getting Modular Schedular Animation

When using modular schedulers (i.e. schedulers which use a modular architecture, and whose name start with "modular-"), the call to starpu_fxt_tool will also produce a trace.html file which can be viewed in a javascript-enabled web browser. It shows the flow of tasks between the components of the modular scheduler.

14.1.2 Limiting The Scope Of The Trace

For computing statistics, it is useful to limit the trace to a given portion of the time of the whole execution. This can be achieved by calling

```
starpu_fxt_autostart_profiling(0)
```

before calling starpu_init(), to prevent tracing from starting immediately. Then

```
starpu_fxt_start_profiling();
and
starpu_fxt_stop_profiling();
```

can be used around the portion of code to be traced. This will show up as marks in the trace, and states of workers will only show up for that portion.

Offline Performance Tools

14.2 Performance Of Codelets

The performance model of codelets (see Performance Model Example) can be examined by using the tool starpu_perfmodel_display:

```
$ starpu_perfmodel_display -1
file: <malloc_pinned.hannibal>
file: <starpu_slu_lu_model_21.hannibal>
file: <starpu_slu_lu_model_11.hannibal>
file: <starpu_slu_lu_model_22.hannibal>
file: <starpu_slu_lu_model_12.hannibal>
```

Here, the codelets of the example 1u are available. We can examine the performance of the kernel 22 (in microseconds), which is history-based:

```
$ starpu_perfmodel_display -s starpu_slu_lu_model_22
performance model for cpu
# hash size
                 mean
         19660800 2.851069e+05 1.829369e+04 109
57618ab0
performance model for cuda_0
# hash size
                                dev
                 mean
57618ab0
          19660800 1.164144e+04 1.556094e+01 315
performance model for cuda_1
# hash size
                   mean
                                 dev
57618ab0 19660800 1.164271e+04 1.330628e+01 360
performance model for cuda_2
                                 dev
# hash
          size
                    mean
57618ab0
          19660800 1.166730e+04 3.390395e+02 456
```

We can see that for the given size, over a sample of a few hundreds of execution, the GPUs are about 20 times faster than the CPUs (numbers are in us). The standard deviation is extremely low for the GPUs, and less than 10% for CPUs.


This tool can also be used for regression-based performance models. It will then display the regression formula, and in the case of non-linear regression, the same performance log as for history-based performance models:

```
$ starpu_perfmodel_display -s non_linear_memset_regression_based
performance model for cpu_impl_0
Regression : #sample = 1400
Linear: y = alpha size ^ beta
alpha = 1.335973e-03
beta = 8.024020e-01
Non-Linear: y = a size ^b + c
a = 5.429195e-04
b = 8.654899e-01
c = 9.009313e-01
# hash size mean stddev n
a3d3725e 4096 4.763200e+00 7.650928e-01
                                     2.037181e-01
870a30aa 8192
                       1.827970e+00
                                                       100
48e988e9 16384
                        2.652800e+00
                                       1.876459e-01
                                                       100
                       4.255530e+00 3.518025e-01
961e65d2 32768
                                                       100
```

The same can also be achieved by using StarPU's library API, see Performance Model and notably the function starpu_perfmodel_load_symbol(). The source code of the tool starpu_perfmodel_display can be a useful example.

An $X\dot{M}L$ output can also be printed by using the -x option:

The tool $starpu_perfmodel_plot$ can be used to draw performance models. It writes a .gp file in the current directory, to be run with the tool gnuplot, which shows the corresponding curve.




When the field starpu_task::flops is set (or STARPU_FLOPS is passed to starpu_task_insert()), starpu_\circ} perfmodel_plot can directly draw a GFlops curve, by simply adding the -f option:

```
$ starpu_perfmodel_plot -f -s chol_model_11
```

This will however disable displaying the regression model, for which we can not compute GFlops.


Offline Performance Tools



When the FxT trace file $prof_file_something$ has been generated, it is possible to get a profiling of each codelet by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
$ starpu_codelet_profile distrib.data codelet_name
```


This will create profiling data files, and a distrib.data.gp file in the current directory, which draws the distribution of codelet time over the application execution, according to data input size.



This is also available in the tool starpu_perfmodel_plot, by passing it the fxt trace:

\$ starpu_perfmodel_plot -s non_linear_memset_regression_based -i /tmp/prof_file_foo_0

It will produce a .gp file which contains both the performance model curves, and the profiling measurements.




98 Offline Performance Tools

If you have the statistical tool R installed, you can additionally use

```
$ starpu_codelet_histo_profile distrib.data
```

Which will create one .pdf file per codelet and per input size, showing a histogram of the codelet execution time distribution.

Histogram of val[val > quantile(val, 0.01) & val < quantile(val, 0.99)]



14.3 Trace Statistics

More than just codelet performance, it is interesting to get statistics over all kinds of StarPU states (allocations, data transfers, etc.). This is particularly useful to check what may have gone wrong in the accurracy of the simgrid simulation.

This requires the R statistical tool, with the plyr, ggplot2 and data.table packages. If your system distribution does not have packages for these, one can fetch them from CRAN:

```
$ R
> install.packages("plyr")
> install.packages("ggplot2")
> install.packages("data.table")
> install.packages("knitr")
```

14.3 Trace Statistics 99

The pj_dump tool from pajeng is also needed (see https://github.com/schnorr/pajeng)
One can then get textual or .csv statistics over the trace states:

```
$ starpu_paje_state_stats -v native.trace simgrid.trace
"Value" "Events_native.csv" "Duration_native.csv" "Events_simgrid.csv"
"Callback" 220 0.075978 220 0
"chol_model_11" 10 565.176 10 572.8695
"chol_model_21" 45 9184.828 45 9170.719
"chol_model_22" 165 64712.07 165 64299.203
$ starpu_paje_state_stats native.trace simgrid.trace
```

An other way to get statistics of StarPU states (without installing R and pj_dump) is to use the $starpu_trace \leftarrow _state_stats.py$ script which parses the generated trace.rec file instead of the paje.trace file. The output is similar to the previous script but it doesn't need any dependencies.

The different prefixes used in trace.rec are:

```
E: Event type
N: Event name
C: Event category
W: Worker ID
T: Thread ID
S: Start time
```

Here's an example on how to use it:


starpu_trace_state_stats.py can also be used to compute the different efficiencies. Refer to the usage description to show some examples.

And one can plot histograms of execution times, of several states for instance:

```
$ starpu_paje_draw_histogram -n chol_model_11,chol_model_21,chol_model_22 native.trace simgrid.trace
```

and see the resulting pdf file:

100 Offline Performance Tools



A quick statistical report can be generated by using:

\$ starpu_paje_summary native.trace simgrid.trace

it includes gantt charts, execution summaries, as well as state duration charts and time distribution histograms. Other external Paje analysis tools can be used on these traces, one just needs to sort the traces by timestamp order (which not guaranteed to make recording more efficient):

\$ starpu_paje_sort paje.trace

14.4 Theoretical Lower Bound On Execution Time

StarPU can record a trace of what tasks are needed to complete the application, and then, by using a linear system, provide a theoretical lower bound of the execution time (i.e. with an ideal scheduling).

The computed bound is not really correct when not taking into account dependencies, but for an application which have enough parallelism, it is very near to the bound computed with dependencies enabled (which takes a huge lot more time to compute), and thus provides a good-enough estimation of the ideal execution time.

Theoretical Lower Bound On Execution Time Example provides an example on how to use this.

14.5 Theoretical Lower Bound On Execution Time Example

For kernels with history-based performance models (and provided that they are completely calibrated), StarPU can very easily provide a theoretical lower bound for the execution time of a whole set of tasks. See for instance $examples/lu/lu_example.c$: before submitting tasks, call the function $starpu_bound_start()$, and after complete execution, call $starpu_bound_stop()$. $starpu_bound_print_p()$ or $starpu_bound_print_mps()$ can then be used to output a Linear Programming problem corresponding to the schedule of your tasks. Run it through lp_solve or any other linear programming solver, and that will give you a lower bound for the total execution time of your tasks. If StarPU was compiled with the library glpk installed, $starpu_bound_compute()$ can be used to solve it immediately and get the optimized minimum, in ms. Its parameter integer allows to decide whether integer resolution should be computed and returned

The deps parameter tells StarPU whether to take tasks, implicit data, and tag dependencies into account. Tags released in a callback or similar are not taken into account, only tags associated with a task are. It must be understood that the linear programming problem size is quadratic with the number of tasks and thus the time to solve it will be very long, it could be minutes for just a few dozen tasks. You should probably use lp_solve_t -timeout 1 test.pl -wmps test.mps to convert the problem to MPS format and then use a better solver, glpsol might be better than lp_solve_t for instance (the -pcost option may be useful), but sometimes doesn't manage to converge. cbc might look slower, but it is parallel. For lp_solve_t , be sure to try at least all the -B options. For instance, we often just use lp_solve_t -cc -B1 -Bb -Bg -Bp -Bf -Br -BG -Bd -Bs -Be -Bo -Bc -Bi , and the -gr option can also be quite useful. The resulting schedule can be observed by using the tool starpu_lp2paje, which converts it into the Paje format.

Data transfer time can only be taken into account when deps is set. Only data transfers inferred from implicit data dependencies between tasks are taken into account. Other data transfers are assumed to be completely overlapped.

Setting deps to 0 will only take into account the actual computations on processing units. It however still properly takes into account the varying performances of kernels and processing units, which is quite more accurate than just comparing StarPU performances with the fastest of the kernels being used.

The prio parameter tells StarPU whether to simulate taking into account the priorities as the StarPU scheduler would, i.e. schedule prioritized tasks before less prioritized tasks, to check to which extend this results to a less optimal solution. This increases even more computation time.

14.6 Memory Feedback

It is possible to enable memory statistics. To do so, you need to pass the option --enable-memory-stats when running configure. It is then possible to call the function starpu_data_display_memory_stats() to display statistics about the current data handles registered within StarPU.

Moreover, statistics will be displayed at the end of the execution on data handles which have not been cleared out. This can be disabled by setting the environment variable STARPU_MEMORY_STATS to 0.

For example, if you do not unregister data at the end of the complex example, you will get something similar to:

```
$ STARPU_MEMORY_STATS=0 ./examples/interface/complex
Complex[0] = 45.00 + 12.00 i
Complex[0] = 78.00 + 78.00 i
Complex[0] = 45.00 + 12.00 i
Complex[0] = 45.00 + 12.00 i
$ STARPU_MEMORY_STATS=1 ./examples/interface/complex
Complex[0] = 45.00 + 12.00 i
Complex[0] = 78.00 + 78.00 i
Complex[0] = 45.00 + 12.00 i
Complex[0] = 45.00 + 12.00 i
Memory stats:
Data on Node #3
#----
Data : 0x553ff40
Size: 16
Data access stats
/!\ Work Underway
```

```
Node #0
Direct access : 4
Loaded (Owner) : 0
Loaded (Shared) : 0
Invalidated (was Owner) : 0
Node #3
Direct access : 0
Loaded (Owner) : 0
Loaded (Shared) : 1
Invalidated (was Owner) : 0
Data : 0x5544710
Size : 16
Data access stats
/!\ Work Underway
Node #0
Direct access: 2
Loaded (Owner) : 0
Loaded (Shared) : 1
Invalidated (was Owner): 1
Node #3
Direct access : 0
Loaded (Owner) : 1
Loaded (Shared) : 0
Invalidated (was Owner) : 0
```

14.7 Data Statistics

Different data statistics can be displayed at the end of the execution of the application. To enable them, you need to define the environment variable STARPU_ENABLE_STATS. When calling starpu_shutdown() various statistics will be displayed, execution, MSI cache statistics, allocation cache statistics, and data transfer statistics. The display can be disabled by setting the environment variable STARPU_STATS to 0.

```
$ ./examples/cholesky/cholesky_tag
Computation took (in ms)
518.16
Synthetic GFlops : 44.21
#-----
MSI cache stats :
TOTAL MSI stats hit 1622 (66.23 %) miss 827 (33.77 %)
...
$ STARPU_STATS=0 ./examples/cholesky/cholesky_tag
Computation took (in ms)
518.16
Synthetic GFlops : 44.21
```

Chapter 15

Frequently Asked Questions

15.1 How To Initialize A Computation Library Once For Each Worker?

Some libraries need to be initialized once for each concurrent instance that may run on the machine. For instance, a C++ computation class which is not thread-safe by itself, but for which several instanciated objects of that class can be used concurrently. This can be used in StarPU by initializing one such object per worker. For instance, the libstarpufft example does the following to be able to use FFTW on CPUs. Some global array stores the instanciated objects:

```
fftw_plan plan_cpu[STARPU_NMAXWORKERS];
```

At initialisation time of libstarpu, the objects are initialized:

```
int workerid;
for (workerid = 0; workerid < starpu_worker_get_count(); workerid++)
{
    switch (starpu_worker_get_type(workerid))
    {
        case STARPU_CPU_WORKER:
            plan_cpu[workerid] = fftw_plan(...);
            break;
    }
}</pre>
```

And in the codelet body, they are used:

```
static void fft(void *descr[], void *_args)
{
   int workerid = starpu_worker_get_id();
   fftw_plan plan = plan_cpu[workerid];
   ...
   ffttw_execute(plan, ...);
}
```

This however is not sufficient for FFT on CUDA: initialization has to be done from the workers themselves. This can be done thanks to starpu_execute_on_each_worker(). For instance libstarpufft does the following.

```
static void fft_plan_gpu(void *args)
{
    plan plan = args;
    int n2 = plan->n2[0];
    int workerid = starpu_worker_get_id();

    cufftPlan1d(&plan->plans[workerid].plan_cuda, n, _CUFFT_C2C, 1);
    cufftSetStream(plan->plans[workerid].plan_cuda, starpu_cuda_get_local_stream());
}
void starpufft_plan(void)
{
    starpu_execute_on_each_worker(fft_plan_gpu, plan, STARPU_CUDA);
}
```

15.2 Using The Driver API

Running Drivers

```
int ret;
struct starpu_driver =
{
    .type = STARPU_CUDA_WORKER,
    .id.cuda_id = 0
};
ret = starpu_driver_init(&d);
if (ret != 0)
    error();
while (some_condition)
{
    ret = starpu_driver_run_once(&d);
    if (ret != 0)
        error();
}
ret = starpu_driver_deinit(&d);
if (ret != 0)
    error();
```

To add a new kind of device to the structure starpu driver, one needs to:

- 1. Add a member to the union starpu driver::id
- 2. Modify the internal function _starpu_launch_drivers() to make sure the driver is not always launched.
- 3. Modify the function starpu_driver_run() so that it can handle another kind of architecture.
- 4. Write the new function _starpu_run_foobar() in the corresponding driver.

15.3 On-GPU Rendering

Graphical-oriented applications need to draw the result of their computations, typically on the very GPU where these happened. Technologies such as OpenGL/CUDA interoperability permit to let CUDA directly work on the Open←GL buffers, making them thus immediately ready for drawing, by mapping OpenGL buffer, textures or renderbuffer objects into CUDA. CUDA however imposes some technical constraints: peer memcpy has to be disabled, and the thread that runs OpenGL has to be the one that runs CUDA computations for that GPU.

To achieve this with StarPU, pass the option --disable-cuda-memcpy-peer to configure (TODO: make it dynamic), OpenGL/GLUT has to be initialized first, and the interoperability mode has to be enabled by using the field starpu_conf::cuda_opengl_interoperability, and the driver loop has to be run by the application, by using the field starpu_conf::not_launched_drivers to prevent StarPU from running it in a separate thread, and by using starpu_cdriver_run() to run the loop. The examples gl_interop and gl_interop_idle show how it articulates in a simple case, where rendering is done in task callbacks. The former uses glutMainLoopEvent to make GLUT progress from the StarPU driver loop, while the latter uses glutIdleFunc to make StarPU progress from the GLUT main loop.

Then, to use an OpenGL buffer as a CUDA data, StarPU simply needs to be given the CUDA pointer at registration, for instance:

and display it e.g. in the callback function.

15.4 Using StarPU With MKL 11 (Intel Composer XE 2013)

Some users had issues with MKL 11 and StarPU (versions 1.1rc1 and 1.0.5) on Linux with MKL, using 1 thread for MKL and doing all the parallelism using StarPU (no multithreaded tasks), setting the environment variable $MKL_\leftarrow NUM_THREADS$ to 1, and using the threaded MKL library, with iomp5.

Using this configuration, StarPU only uses 1 core, no matter the value of STARPU_NCPU. The problem is actually a thread pinning issue with MKL.

The solution is to set the environment variable KMP_AFFINITY to disabled (http://software.intel. ← com/sites/products/documentation/studio/composer/en-us/2011Update/compiler ← _c/optaps/common/optaps_openmp_thread_affinity.htm).

15.5 Thread Binding on NetBSD

When using StarPU on a NetBSD machine, if the topology discovery library hwloc is used, thread binding will fail. To prevent the problem, you should at least use the version 1.7 of hwloc, and also issue the following call:

```
$ sysctl -w security.models.extensions.user_set_cpu_affinity=1
Or add the following line in the file /etc/sysctl.conf
security.models.extensions.user_set_cpu_affinity=1
```

15.6 StarPU permanently eats 100% of all CPUs

Yes, this is on purpose.

By default, StarPU uses active polling on task queues, so as to minimize wake-up latency for better overall performance.

If eating CPU time is a problem (e.g. application running on a desktop), pass option --enable-blocking-drivers to configure. This will add some overhead when putting CPU workers to sleep or waking them, but avoid eating 100% CPU permanently.

15.7 Interleaving StarPU and non-StarPU code

If your application only partially uses StarPU, and you do not want to call starpu_init() / starpu_shutdown() at the beginning/end of each section, StarPU workers will poll for work between the sections. To avoid this behavior, you can "pause" StarPU with the starpu_pause() function. This will prevent the StarPU workers from accepting new work (tasks that are already in progress will not be frozen), and stop them from polling for more work.

Note that this does not prevent you from submitting new tasks, but they won't execute until starpu_resume() is called. Also note that StarPU must not be paused when you call starpu_shutdown(), and that this function pair works in a push/pull manner, i.e you need to match the number of calls to these functions to clear their effect. One way to use these functions could be:

```
starpu_init(NULL);
starpu_pause(); // To submit all the tasks without a single one executing
submit_some_tasks();
starpu_resume(); // The tasks start executing

starpu_task_wait_for_all();
starpu_pause(); // Stop the workers from polling

starpu_resume();
starpu_resume();
```

15.8 When running with CUDA or OpenCL devices, I am seeing less CPU cores

Yes, this is on purpose.

Since GPU devices are way faster than CPUs, StarPU needs to react quickly when a task is finished, to feed the GPU with another task (StarPU actually submits a couple of tasks in advance so as to pipeline this, but filling the

pipeline still has to be happening often enough), and thus it has to dedicate threads for this, and this is a very CPU-consuming duty. StarPU thus dedicates one CPU core for driving each GPU by default.

Such dedication is also useful when a codelet is hybrid, i.e. while kernels are running on the GPU, the codelet can run some computation, which thus be run by the CPU core instead of driving the GPU.

One can choose to dedicate only one thread for all the CUDA devices by setting the STARPU_CUDA_THREAD_
PER_DEV environment variable to 1. The application however should use STARPU_CUDA_ASYNC on its CUDA codelets (asynchronous execution), otherwise the execution of a synchronous CUDA codelet will monopolize the thread, and other CUDA devices will thus starve while it is executing.

15.9 StarPU does not see my CUDA device

First make sure that CUDA is properly running outside StarPU: build and run the following program with <code>-lcudart</code> .

```
#include <stdio.h>
#include <cuda.h>
#include <cuda_runtime.h>
int main (void)
        int n, i, version;
       cudaError_t err;
       err = cudaGetDeviceCount(&n);
        if (err)
        {
                fprintf(stderr, "cuda error %d\n", err);
                exit(1);
        cudaDriverGetVersion(&version);
       printf("driver version %d\n", version);
        cudaRuntimeGetVersion(&version);
       printf("runtime version %d\n", version);
       printf("\n");
        for (i = 0; i < n; i++)
                struct cudaDeviceProp props;
                printf("CUDA%d\n", i);
                err = cudaGetDeviceProperties(&props, i);
                {
                        fprintf(stderr, "cuda error %d\n", err);
                        continue:
                printf("%s\n", props.name);
                printf("\$0.3f GB\n", (float) props.totalGlobalMem / (1<<30));
                printf("%u MP\n", props.multiProcessorCount);
                printf("\n");
        return 0;
```

If that program does not find your device, the problem is not at the StarPU level, but the CUDA drivers, check the documentation of your CUDA setup.

15.10 StarPU does not see my OpenCL device

First make sure that OpenCL is properly running outside StarPU: build and run the following program with $-1 \leftarrow OpenCL$:

```
#include <CL/cl.h>
#include <stdio.h>
#include <assert.h>

int main(void)
{
    cl_device_id did[16];
    cl_int err;
    cl_platform_id pid, pids[16];
    cl_uint nbplat, nb;
    char buf[128];
    size_t size;
    int i, j;
```

```
err = clGetPlatformIDs(sizeof(pids)/sizeof(pids[0]), pids, &nbplat);
assert(err == CL_SUCCESS);
printf("%u platforms\n", nbplat);
for (j = 0; j < nbplat; j++)</pre>
    pid = pids[j];
    printf(" platform %d\n", j);
err = clGetPlatformInfo(pid, CL_PLATFORM_VERSION, sizeof(buf)-1, buf, &size);
    assert(err == CL_SUCCESS);
    buf[size] = 0;
    printf("
                    platform version %s\n", buf);
    err = clGetDeviceIDs(pid, CL_DEVICE_TYPE_ALL, sizeof(did)/sizeof(did[0]), did, &nb);
    assert (err == CL_SUCCESS);
    printf("%d devices\n", nb);
    for (i = 0; i < nb; i++)
        err = clGetDeviceInfo(did[i], CL_DEVICE_VERSION, sizeof(buf)-1, buf, &size);
        buf[size] = 0;
                    device %d version %s\n", i, buf);
        printf("
}
return 0;
```

If that program does not find your device, the problem is not at the StarPU level, but the OpenCL drivers, check the documentation of your OpenCL implementation.

15.11 I keep getting a "Incorrect performance model file" error

The performance model file, used by StarPU to record the performance of codelets, seem to have been corrupted. Perhaps a previous run of StarPU stopped abruptly, and thus could not save it properly. You can have a look at the file if you can fix it, but the simplest way is to just remove the file and run again, StarPU will just have to re-perform calibration for the corresponding codelet.

Part IV StarPU Extensions

Chapter 16

Out Of Core

16.1 Introduction

When using StarPU, one may need to store more data than what the main memory (RAM) can store. This part describes the method to add a new memory node on a disk and to use it.

Similarly to what happens with GPUs (it's actually exactly the same code), when available main memory becomes scarse, StarPU will evict unused data to the disk, thus leaving room for new allocations. Whenever some evicted data is needed again for a task, StarPU will automatically fetch it back from the disk.

The principle is that one first registers a disk location, seen by StarPU as a <code>void*</code>, which can be for instance a Unix path for the <code>stdio</code>, <code>unistdorunistdo-direct</code> backends, or a leveldb database for the <code>leveldb</code> backend, an HDF5 file path for the <code>HDF5</code> backend, etc. The <code>disk</code> backend opens this place with the plug() method. StarPU can then start using it to allocate room and store data there with the disk write method, without user intervention.

The user can also use starpu_disk_open() to explicitly open an object within the disk, e.g. a file name in the stdio or unistd cases, or a database key in the leveldb case, and then use starpu_*_register functions to turn it into a StarPU data handle. StarPU will then use this file as external source of data, and automatically read and write data as appropriate.

In any case, the user also needs to set STARPU_LIMIT_CPU_MEM to the amount of data that StarPU will be allowed to afford. By default StarPU will use the machine memory size, but part of it is taken by the kernel, the system, daemons, and the application's own allocated data, whose size can not be predicted. That is why the user needs to specify what StarPU can afford.

Some Out-of-core tests are worth giving a read, see tests/disk/*.c

16.2 Use a new disk memory

To use a disk memory node, you have to register it with this function:

Here, we use the unistd library to realize the read/write operations, i.e. fread/fwrite. This structure must have a path where to store files, as well as the maximum size the software can afford storing on the disk. Don't forget to check if the result is correct!

This can also be achieved by just setting environment variables STARPU_DISK_SWAP, STARPU_DISK_SWAP ← __BACKEND and STARPU_DISK_SWAP_SIZE :

```
export STARPU_DISK_SWAP=/tmp
export STARPU_DISK_SWAP_BACKEND=unistd
export STARPU_DISK_SWAP_SIZE=200
```

The backend can be set to stdio (some caching is done by libc and the kernel), unistd (only caching in the kernel), unistd_o_direct (no caching), leveldb, or hdf5.

It is important to understand that when the backend is not set to unistd_o_direct, some caching will occur at the kernel level (the page cache), which will also consume memory... STARPU_LIMIT_CPU_MEM might need to be set to less that half of the machine memory just to leave room for the kernel's page cache, otherwise the kernel

112 Out Of Core

will struggle to get memory. Using unistd_o_direct avoids this caching, thus allowing to set STARPU_LIM UT_CPU_MEM to the machine memory size (minus some memory for normal kernel operations, system daemons, and application data).

When the register call is made, StarPU will benchmark the disk. This can take some time.

Warning: the size thus has to be at least STARPU_DISK_SIZE_MIN bytes!

StarPU will then automatically try to evict unused data to this new disk. One can also use the standard StarPU memory node API to prefetch data etc., see the Standard Memory Library and the Data Interfaces.

The disk is unregistered during the starpu_shutdown().

16.3 Data Registration

StarPU will only be able to achieve Out-Of-Core eviction if it controls memory allocation. For instance, if the application does the following:

StarPU will not be able to release the corresponding memory since it's the application which allocated it, and StarPU can not know how, and thus how to release it. One thus have to use the following instead:

```
starpu_matrix_data_register(&h, -1, NULL, 1024, 1024, 1024, sizeof(float));
starpu_task_insert(cl_fill_with_data, STARPU_W, h, 0);
```

Which makes StarPU automatically do the allocation when the task running cl_fill_with_data gets executed. And then if its needs to, it will be able to release it after having pushed the data to the disk. Since no initial buffer is provided to starpu_matrix_data_register(), the handle does not have any initial value right after this call, and thus the very first task using the handle needs to use the STARPU_R or STARPU_R or STARPU_R or STARPU_R would not make sense.

By default, StarPU will try to push any data handle to the disk. To specify whether a given handle should be pushed to the disk, starpu_data_set_ooc_flag() should be used.

16.4 Using Wont Use

By default, StarPU uses a Least-Recently-Used (LRU) algorithm to determine which data should be evicted to the disk. This algorithm can be hinted by telling which data will no be used in the coming future thanks to starpu_color: blue, color: blue, color:

```
starpu_task_insert(&cl_work, STARPU_RW, h, 0);
starpu_data_wont_use(h);
```

StarPU will mark the data as "inactive" and tend to evict to the disk that data rather than others.

16.5 Examples: disk_copy

```
setenv("STARPU_LIMIT_CPU_MEM", "160", 1);
         /* Initialize StarPU with default configuration */
        int ret = starpu_init(NULL);
         if (ret == -ENODEV) goto enodev;
         /* register a disk */
      int new_dd = starpu_disk_register(&starpu_disk_unistd_ops
, (void *) "/tmp/", 1024*1024*200);
         /* can't write on /tmp/ */
        if (new dd == -ENOENT) goto enoent;
         /* allocate two memory spaces */
        starpu_malloc_flags((void **)&A, NX*sizeof(double), STARPU_MALLOC_COUNT
        starpu_malloc_flags((void **)&F, NX*sizeof(double), STARPU_MALLOC_COUNT
      );
        FPRINTF(stderr, "TEST DISK MEMORY \n");
        unsigned int j;
         /\star initialization with bad values \star/
        for(j = 0; j < NX; ++j)
                 A[j] = j;
                 F[j] = -j;
        starpu_data_handle_t vector_handleA, vector_handleB, vector_handleC,
      vector handleD, vector handleE, vector handleF;
         /* register vector in starpu */
        \verb|starpu_vector_data_register(&vector_handleA, STARPU_MAIN_RAM||
      , (uintptr_t)A, NX, sizeof(double));
         starpu_vector_data_register(&vector_handleB, -1, (uintptr_t) NULL, NX,
      sizeof(double));
        starpu_vector_data_register(&vector_handleC, -1, (uintptr_t) NULL, NX,
      sizeof(double));
         starpu_vector_data_register(&vector_handleD, -1, (uintptr_t) NULL, NX,
      sizeof(double));
        starpu_vector_data_register(&vector_handleE, -1, (uintptr_t) NULL, NX,
      sizeof(double));
starpu_vector_data_register(&vector_handleF, STARPU_MAIN_RAM
      , (uintptr_t)F, NX, sizeof(double));
         /* copy vector A->B, B->C... */
        starpu_data_cpy(vector_handleB, vector_handleA, 0, NULL, NULL);
        starpu_data_cpy(vector_handleC, vector_handleB, 0, NULL, NULL);
starpu_data_cpy(vector_handleD, vector_handleC, 0, NULL, NULL);
        starpu_data_cpy(vector_handleE, vector_handleD, 0, NULL, NULL);
        starpu_data_cpy(vector_handleF, vector_handleE, 0, NULL, NULL);
        /\star StarPU does not need to manipulate the array anymore so we can stop
         * monitoring it */
        /* free them */
        starpu_data_unregister(vector_handleA);
         starpu_data_unregister(vector_handleB);
        starpu_data_unregister(vector_handleC);
        starpu_data_unregister(vector_handleD);
        starpu_data_unregister(vector_handleE);
        starpu_data_unregister(vector_handleF);
         /* check if computation is correct */
        int try = 1;
for (j = 0; j < NX; ++j)
                 if (A[j] != F[j])
                 {
                          printf("Fail A %f != F %f n", A[j], F[j]);
                          try = 0;
                  }
        /* free last vectors */
        starpu_free_flags(A, NX*sizeof(double), STARPU_MALLOC_COUNT); starpu_free_flags(F, NX*sizeof(double), STARPU_MALLOC_COUNT);
         /\star terminate StarPU, no task can be submitted after \star/
        starpu_shutdown();
        if(try)
                 FPRINTF(stderr, "TEST SUCCESS\n");
                 FPRINTF(stderr, "TEST FAIL\n");
         return (try ? EXIT_SUCCESS : EXIT_FAILURE);
enodev:
```

114 Out Of Core

```
return 77;
enoent:
return 77;
```

16.6 Examples: disk_compute

```
/* Try to write into disk memory
* Use mechanism to push datas from main ram to disk ram
#include <starpu.h>
#include <stdlib.h>
#include <stdio.h>
#include <sys/types.h>
#include <unistd.h>
#include <math.h>
#define NX (1024)
int main(int argc, char **argv)
{
         /\star Initialize StarPU with default configuration \star/
         int ret = starpu_init(NULL);
         if (ret == -ENODEV) goto enodev;
         /* Initialize path and name */
         char pid_str[16];
         int pid = getpid();
         snprintf(pid_str, sizeof(pid_str), "%d", pid);
         const char *name_file_start = "STARPU_DISK_COMPUTE_DATA_";
const char *name_file_end = "STARPU_DISK_COMPUTE_DATA_RESULT_";
         char * path_file_start = malloc(strlen(base) + 1 + strlen(name_file_start) + 1);
         strcpy(path_file_start, base);
strcat(path_file_start, "/");
strcat(path_file_start, name_file_start);
         char * path_file_end = malloc(strlen(base) + 1 + strlen(name_file_end) + 1);
         strcpy(path_file_end, base);
strcat(path_file_end, "/");
         strcat(path_file_end, name_file_end);
         /* register a disk */
         int new_dd = starpu_disk_register(&starpu_disk_unistd_ops
       , (void *) base, 1024*1024*1);
         /* can't write on /tmp/ */
if (new_dd == -ENOENT) goto enoent;
         unsigned dd = (unsigned) new_dd;
         printf("TEST DISK MEMORY \n");
         /\star Imagine, you want to compute datas \star/
         int *A;
int *C;
         starpu_malloc_flags((void **)&A, NX*sizeof(int), STARPU_MALLOC_COUNT
         starpu_malloc_flags((void **)&C, NX*sizeof(int), STARPU_MALLOC_COUNT
       );
         unsigned int j;
         /\star you register them in a vector \star/
         for(j = 0; j < NX; ++j)
                  A[j] = j;
C[j] = 0;
         /* you create a file to store the vector ON the disk */ FILE * f = fopen(path_file_start, "wb+");
         if (f == NULL)
                  goto encent2;
         /\star store it in the file \star/
         fwrite(A, sizeof(int), NX, f);
         /* close the file */
         fclose(f);
```

```
/* create a file to store result */
f = fopen(path_file_end, "wb+");
        if (f == NULL)
                goto enoent2;
        /* replace all datas by 0 */
        fwrite(C, sizeof(int), NX, f);
        /* close the file */
        fclose(f);
        /\star And now, you want to use your datas in StarPU \star/ /\star Open the file ON the disk \star/
        void * data = starpu_disk_open(dd, (void *) name_file_start, NX*sizeof(int));
        void * data_result = starpu_disk_open(dd, (void *) name_file_end, NX*sizeof(int));
        starpu data handle t vector handleA, vector handleC;
        /* register vector in starpu */
        starpu_vector_data_register(&vector_handleA, dd, (uintptr_t) data, NX,
      sizeof(int));
        /\star and do what you want with it, here we copy it into an other vector \star/
        starpu_vector_data_register(&vector_handleC, dd, (uintptr_t) data_result
      , NX, sizeof(int));
        starpu_data_cpy(vector_handleC, vector_handleA, 0, NULL, NULL);
        /* free them */
        starpu_data_unregister(vector_handleA);
        starpu_data_unregister(vector_handleC);
        /* close them in StarPU */
        starpu_disk_close(dd, data, NX*sizeof(int));
        starpu_disk_close(dd, data_result, NX*sizeof(int));
        /* check results */
        f = fopen(path_file_end, "rb+");
        if (f == NULL)
                goto encent;
        /* take datas */
        int size = fread(C, sizeof(int), NX, f);
        /* close the file */
        fclose(f);
        int try = 1;
for (j = 0; j < NX; ++j)</pre>
                 if (A[j] != C[j])
                 {
                         printf("Fail A %d != C %d \n", A[j], C[j]);
        starpu_free_flags(A, NX*sizeof(int), STARPU_MALLOC_COUNT);
        starpu_free_flags(C, NX*sizeof(int), STARPU_MALLOC_COUNT);
        unlink(path_file_start);
        unlink(path_file_end);
        free(path_file_start);
        free (path_file_end);
        /\star terminate StarPU, no task can be submitted after \star/
        starpu_shutdown();
        if(try)
                 printf("TEST SUCCESS\n");
        else
                 printf("TEST FAIL\n");
        return (try ? EXIT_SUCCESS : EXIT_FAILURE);
enodev:
        return 77:
enoent2:
        starpu_free_flags(A, NX*sizeof(int), STARPU_MALLOC_COUNT);
        starpu_free_flags(C, NX*sizeof(int), STARPU_MALLOC_COUNT);
enoent:
        unlink(path_file_start);
        unlink (path_file_end);
        free(path_file_start);
        free (path_file_end);
        starpu_shutdown();
return 77;
```

}

116 Out Of Core

16.7 Performances

Scheduling heuristics for Out-of-core are still relatively experimental. The tricky part is that you usually have to find a compromise between privileging locality (which avoids back and forth with the disk) and privileging the critical path, i.e. taking into account priorities to avoid lack of parallelism at the end of the task graph.

It is notably better to avoid defining different priorities to tasks with low priority, since that will make the scheduler want to schedule them by levels of priority, at the depense of locality.

The scheduling algorithms worth trying are thus \mathtt{dmdar} and \mathtt{lws} , which privilege data locality over priorities. There will be work on this area in the coming future.

16.8 Feedback Figures

Beyond pure performance feedback, some figures are interesting to have a look at.

Using export STARPU_BUS_STATS=1 gives an overview of the data transfers which were needed. The values can also be obtained at runtime by using $starpu_bus_get_profiling_info()$. An example can be read in $src/profiling/profiling_helpers.c$.

```
#------
Data transfer speed for /tmp/sthibault-disk-DJzhAj (node 1):
0 -> 1: 99 MB/s
1 -> 0: 99 MB/s
0 -> 1: 23858 µs
1 -> 0: 23858 µs

#-------
TEST DISK MEMORY

#-------
Data transfer stats:
Disk 0 -> NUMA 0 0.0000 GB 0.0000 MB/s (transfers : 0 - avg -nan MB)
NUMA 0 -> Disk 0 0.0625 GB 63.6816 MB/s (transfers : 2 - avg 32.0000 MB)
Total transfers: 0.0625 GB
```

Using export STARPU_ENABLE_STATS=1 gives information for each memory node on data miss/hit and allocation miss/hit.

16.9 Disk functions

There are various ways to operate a disk memory node, described by the structure starpu_disk_ops. For instance, the variable starpu_disk_unistd_ops uses read/write functions.

All structures are in Out Of Core.

Chapter 17

MPI Support

The integration of MPI transfers within task parallelism is done in a very natural way by the means of asynchronous interactions between the application and StarPU. This is implemented in a separate <code>libstarpumpi</code> library which basically provides "StarPU" equivalents of <code>MPI_*</code> functions, where <code>void</code> * buffers are replaced with <code>starpu_</code> data_handle_t, and all GPU-RAM-NIC transfers are handled efficiently by StarPU-MPI. The user has to use the usual <code>mpirun</code> command of the MPI implementation to start StarPU on the different MPI nodes.

An MPI Insert Task function provides an even more seamless transition to a distributed application, by automatically issuing all required data transfers according to the task graph and an application-provided distribution.

17.1 Example Used In This Documentation

The example below will be used as the base for this documentation. It initializes a token on node 0, and the token is passed from node to node, incremented by one on each step. The code is not using StarPU yet.

17.2 About Not Using The MPI Support

Although StarPU provides MPI support, the application programmer may want to keep his MPI communications as they are for a start, and only delegate task execution to StarPU. This is possible by just using starpu_data_acquire(), for instance:

```
for (loop = 0; loop < nloops; loop++)
{
   int tag = loop*size + rank;

   /* Acquire the data to be able to write to it */
   starpu_data_acquire(token_handle, STARPU_W);
   if (loop == 0 && rank == 0)
   {
     token = 0;</pre>
```

```
fprintf(stdout, "Start with token value %d\n", token);
else
{
   MPI_Recv(&token, 1, MPI_INT, (rank+size-1)%size, tag, MPI_COMM_WORLD);
   starpu_data_release(token_handle);
/\star Task delegation to StarPU to increment the token. The execution might
 \star be performed on a CPU, a GPU, etc. \star/
increment_token();
/* Acquire the update data to be able to read from it */
starpu_data_acquire(token_handle, STARPU_R);
if (loop == last_loop && rank == last_rank)
    fprintf(stdout, "Finished: token value %d\n", token);
}
else
   MPI_Send(&token, 1, MPI_INT, (rank+1)%size, tag+1, MPI_COMM_WORLD);
   starpu_data_release(token_handle);
```

In that case, libstarpumpi is not needed. One can also use MPI_Isend() and MPI_Irecv(), by calling starpu_data_release() after MPI_Wait() or MPI_Test() have notified completion.

It is however better to use <code>libstarpumpi</code>, to save the application from having to synchronize with <code>starpu</code>—<code>data_acquire()</code>, and instead just submit all tasks and communications asynchronously, and wait for the overall completion.

17.3 Simple Example

The flags required to compile or link against the MPI layer are accessible with the following commands:

```
$ pkg-config --cflags starpumpi-1.3 # options for the compiler
$ pkg-config --libs starpumpi-1.3
                                           # options for the linker
void increment_token(void)
    struct starpu_task *task = starpu_task_create();
    task->cl = &increment_cl;
    task->handles[0] = token_handle;
    starpu_task_submit(task);
int main(int argc, char **argv)
    int rank, size;
    starpu_mpi_init_conf(&argc, &argv, 1, MPI_COMM_WORLD, NULL);
starpu_mpi_comm_rank(MPI_COMM_WORLD, &rank);
    starpu_mpi_comm_size(MPI_COMM_WORLD, &size);
    starpu_vector_data_register(&token_handle, STARPU_MAIN_RAM, (
      uintptr_t)&token, 1, sizeof(unsigned));
    unsigned nloops = NITER;
    unsigned loop;
    unsigned last_loop = nloops - 1;
unsigned last_rank = size - 1;
    for (loop = 0; loop < nloops; loop++)</pre>
        int tag = loop*size + rank;
         if (loop == 0 && rank == 0)
             starpu_data_acquire(token_handle, STARPU_W);
token = 0;
             fprintf(stdout, "Start with token value %d\n", token);
             starpu_data_release(token_handle);
        else
             starpu_mpi_irecv_detached(token_handle, (rank+size-1)%size, tag,
      MPI_COMM_WORLD, NULL, NULL);
```

```
increment_token();

if (loop == last_loop && rank == last_rank)
{
    starpu_data_acquire(token_handle, STARPU_R);
    fprintf(stdout, "Finished: token value %d\n", token);
    starpu_data_release(token_handle);
}
else
{
    starpu_mpi_isend_detached(token_handle, (rank+1)%size, tag+1,
    MPI_COMM_WORLD, NULL, NULL);
}

starpu_task_wait_for_all();

starpu_mpi_shutdown();

if (rank == last_rank)
{
    fprintf(stderr, "[%d] token = %d == %d * %d ?\n", rank, token, nloops, size);
    STARPU_ASSERT(token == nloops*size);
}
```

We have here replaced MPI_Recv() and MPI_Send() with starpu_mpi_irecv_detached() and starpu_mpi—isend_detached(), which just submit the communication to be performed. The implicit sequential consistency dependencies provide synchronization between mpi reception and emission and the corresponding tasks. The only remaining synchronization with starpu_data_acquire() is at the beginning and the end.

17.4 How to Initialize StarPU-MPI

As seen in the previous example, one has to call starpu_mpi_init_conf() to initialize StarPU-MPI. The third parameter of the function indicates if MPI should be initialized by StarPU or if the application did it itself. If the application initializes MPI itself, it must call MPI_Init_thread() with MPI_THREAD_SERIALIZED or MPI_THREAD —MULTIPLE, since StarPU-MPI uses a separate thread to perform the communications. MPI_THREAD_MULT — IPLE is necessary if the application also performs some MPI communications.

17.5 Point To Point Communication

The standard point to point communications of MPI have been implemented. The semantic is similar to the MPI one, but adapted to the DSM provided by StarPU. A MPI request will only be submitted when the data is available in the main memory of the node submitting the request.

There are two types of asynchronous communications: the classic asynchronous communications and the detached communications. The classic asynchronous communications (starpu_mpi_isend() and starpu_mpi_irecv()) need to be followed by a call to starpu_mpi_wait() or to starpu_mpi_test() to wait for or to test the completion of the communication. Waiting for or testing the completion of detached communications is not possible, this is done internally by StarPU-MPI, on completion, the resources are automatically released. This mechanism is similar to the pthread detach state attribute which determines whether a thread will be created in a joinable or a detached state.

For send communications, data is acquired with the mode STARPU_R. When using the configure option --enable-mpi-pedantic-isend, the mode STARPU_RW is used to make sure there is no more than 1 concurrent MPI_Isend() call accessing a data.

Internally, all communication are divided in 2 communications, a first message is used to exchange an envelope describing the data (i.e its tag and its size), the data itself is sent in a second message. All MPI communications submitted by StarPU uses a unique tag which has a default value, and can be accessed with the functions starpu_\circ mpi_get_communication_tag() and starpu_mpi_set_communication_tag(). The matching of tags with corresponding requests is done within StarPU-MPI.

For any userland communication, the call of the corresponding function (e.g starpu_mpi_isend()) will result in the creation of a StarPU-MPI request, the function starpu_data_acquire_cb() is then called to asynchronously request StarPU to fetch the data in main memory; when the data is ready and the corresponding buffer has already been received by MPI, it will be copied in the memory of the data, otherwise the request is stored in the early requests list. Sending requests are stored in the ready requests list.

While requests need to be processed, the StarPU-MPI progression thread does the following:

1. it polls the ready requests list. For all the ready requests, the appropriate function is called to post the corresponding MPI call. For example, an initial call to starpu_mpi_isend() will result in a call to MPI_

Isend(). If the request is marked as detached, the request will then be added in the detached requests list.

- 2. it posts a MPI_Irecv() to retrieve a data envelope.
- 3. it polls the *detached requests list*. For all the detached requests, it tests its completion of the MPI request by calling MPI_Test(). On completion, the data handle is released, and if a callback was defined, it is called.
- 4. finally, it checks if a data envelope has been received. If so, if the data envelope matches a request in the *early requests list* (i.e the request has already been posted by the application), the corresponding MPI call is posted (similarly to the first step above).

If the data envelope does not match any application request, a temporary handle is created to receive the data, a StarPU-MPI request is created and added into the *ready requests list*, and thus will be processed in the first step of the next loop.

MPIPtpCommunication gives the list of all the point to point communications defined in StarPU-MPI.

17.6 Exchanging User Defined Data Interface

New data interfaces defined as explained in Defining A New Data Interface can also be used within StarPU-MPI and exchanged between nodes. Two functions needs to be defined through the type starpu_data_interface_ops. The function starpu_data_interface_ops::pack_data takes a handle and returns a contiguous memory buffer allocated with

```
starpu_malloc_flags(ptr, size, 0)
```

along with its size where data to be conveyed to another node should be copied. The reversed operation is implemented in the function starpu_data_interface_ops::unpack_data which takes a contiguous memory buffer and recreates the data handle.

```
static int complex_pack_data(starpu_data_handle_t handle, unsigned node, void **ptr,
               ssize_t *count)
     STARPU_ASSERT(starpu_data_test_if_allocated_on_node(handle, node));
     struct starpu_complex_interface *complex_interface = (struct starpu_complex_interface *)
               starpu_data_get_interface_on_node(handle, node);
     *count = complex_get_size(handle);
     starpu_malloc_flags(ptr, *count, 0);
    memcpy(*ptr, complex_interface->real, complex_interface->nx*sizeof(double));
    memcpy(*ptr+complex_interface->nx*sizeof(double), complex_interface->imaginary, complex_interface->nx*
               sizeof(double));
static int complex_unpack_data(starpu_data_handle_t handle, unsigned node, void *ptr,
               size t count)
     STARPU_ASSERT(starpu_data_test_if_allocated_on_node(handle, node));
     struct starpu_complex_interface *complex_interface = (struct starpu_complex_interface *)
                starpu_data_get_interface_on_node(handle, node);
    memcpy(complex_interface->real, ptr, complex_interface->nx*sizeof(double));
    \verb|memcpy| (complex_interface->inx*sizeof(double), complex_interface->nx*sizeof(double), complex_interface-
     return 0;
static struct starpu_data_interface_ops interface_complex_ops =
     .pack_data = complex_pack_data,
     .unpack_data = complex_unpack_data
```

Instead of defining pack and unpack operations, users may want to attach a MPI type to their user defined data interface. The function starpu_mpi_datatype_register() allows to do so. This function takes 3 parameters: the data

handle for which the MPI datatype is going to be defined, a function's pointer that will create the MPI datatype, and a function's pointer that will free the MPI datatype.

The functions to create and free the MPI datatype are defined as follows.

```
void starpu complex interface datatype allocate(starpu data handle t handle,
     MPI_Datatype *mpi_datatype)
        int ret;
       int blocklengths[2];
       MPI_Aint displacements[2];
       MPI_Datatype types[2] = {MPI_DOUBLE, MPI_DOUBLE};
        struct starpu_complex_interface *complex_interface = (struct starpu_complex_interface *)
      starpu_data_get_interface_on_node(handle, STARPU_MAIN_RAM);
       MPI_Get_address(complex_interface, displacements);
       MPI_Get_address(&complex_interface->imaginary, displacements+1);
       displacements[1] -= displacements[0];
        displacements[0] = 0;
       blocklengths[0] = complex_interface->nx;
       blocklengths[1] = complex_interface->nx;
        ret = MPI_Type_create_struct(2, blocklengths, displacements, types, mpi_datatype);
       STARPU_ASSERT_MSG(ret == MPI_SUCCESS, "MPI_Type_contiguous failed");
        ret = MPI_Type_commit(mpi_datatype);
       STARPU_ASSERT_MSG(ret == MPI_SUCCESS, "MPI_Type_commit failed");
void starpu_complex_interface_datatype_free(MPI_Datatype *mpi_datatype)
        MPI_Type_free(mpi_datatype);
}
```

Note that it is important to make sure no communication is going to occur before the function starpu_mpi_datatype — register() is called. This would produce an undefined result as the data may be received before the function is called, and so the MPI datatype would not be known by the StarPU-MPI communication engine, and the data would be processed with the pack and unpack operations.

17.7 MPI Insert Task Utility

To save the programmer from having to explicit all communications, StarPU provides an "MPI Insert Task Utility". The principe is that the application decides a distribution of the data over the MPI nodes by allocating it and notifying StarPU of this decision, i.e. tell StarPU which MPI node "owns" which data. It also decides, for each handle, an MPI tag which will be used to exchange the content of the handle. All MPI nodes then process the whole task graph, and StarPU automatically determines which node actually execute which task, and trigger the required MPI transfers. The list of functions is described in MPIInsertTask.

Here an stencil example showing how to use starpu_mpi_task_insert(). One first needs to define a distribution function which specifies the locality of the data. Note that the data needs to be registered to MPI by calling starpu-mpi_data_register(). This function allows to set the distribution information and the MPI tag which should be used when communicating the data. It also allows to automatically clear the MPI communication cache when unregistering the data.

```
/* Returns the MPI node number where data is */
int my_distrib(int x, int y, int nb_nodes)
{
   /* Block distrib */
   return ((int)(x / sqrt(nb_nodes) + (y / sqrt(nb_nodes)) * sqrt(nb_nodes))) % nb_nodes;
   // /* Other examples useful for other kinds of computations */
```

```
// /* / distrib */
// return (x+y) % nb_nodes;

// /* Block cyclic distrib */
// unsigned side = sqrt(nb_nodes);
// return x % side + (y % side) * size;
}
```

Now the data can be registered within StarPU. Data which are not owned but will be needed for computations can be registered through the lazy allocation mechanism, i.e. with a home_node set to -1. StarPU will automatically allocate the memory when it is used for the first time.

One can note an optimization here (the else if test): we only register data which will be needed by the tasks that we will execute.

```
unsigned matrix[X][Y];
starpu_data_handle_t data_handles[X][Y];
for(x = 0; x < X; x++)
   for (y = 0; y < Y; y++)
      int mpi_rank = my_distrib(x, y, size);
      if (mpi_rank == my_rank)
           Owning data */
         starpu_variable_data_register(&data_handles[x][y], STARPU_MAIN_RAM
    , (uintptr_t) & (matrix[x][y]), sizeof(unsigned));
      starpu_variable_data_register(&data_handles[x][y], -1, (uintptr_t)
    NULL, sizeof(unsigned));
         /* I know it's useless to allocate anything for this */
         data_handles[x][y] = NULL;
      if (data_handles[x][y])
         starpu_mpi_data_register(data_handles[x][y], x*X+y, mpi_rank);
}
```

Now starpu_mpi_task_insert() can be called for the different steps of the application.

I.e. all MPI nodes process the whole task graph, but as mentioned above, for each task, only the MPI node which owns the data being written to (here, $data_handles[x][y]$) will actually run the task. The other MPI nodes will automatically send the required data.

To tune the placement of tasks among MPI nodes, one can use STARPU_EXECUTE_ON_NODE or STARPU_EXECUTE_ON_DATA to specify an explicit node, or the node of a given data (e.g. one of the parameters), or use starpu_mpi_node_selection_register_policy() and STARPU_NODE_SELECTION_POLICY to provide a dynamic policy.

A function starpu_mpi_task_build() is also provided with the aim to only construct the task structure. All MPI nodes need to call the function, which posts the required send/recv on the various nodes which have to. Only the node which is to execute the task will then return a valid task structure, others will return NULL. This node must submit the task. All nodes then need to call the function starpu_mpi_task_post_build() – with the same list of arguments as starpu_mpi_task_build() – to post all the necessary data communications meant to happen after the task execution.

17.8 Pruning MPI Task Insertion

Making all MPI nodes process the whole graph can be a concern with a growing number of nodes. To avoid this, the application can prune the task for loops according to the data distribution, so as to only submit tasks on nodes which have to care about them (either to execute them, or to send the required data).

A way to do some of this quite easily can be to just add an if like this:

This permits to drop the cost of function call argument passing and parsing.

If the my distrib function can be inlined by the compiler, the latter can improve the test.

If the size can be made a compile-time constant, the compiler can considerably improve the test further.

If the distribution function is not too complex and the compiler is very good, the latter can even optimize the for loops, thus dramatically reducing the cost of task submission.

To estimate quickly how long task submission takes, and notably how much pruning saves, a quick and easy way is to measure the submission time of just one of the MPI nodes. This can be achieved by running the application on just one MPI node with the following environment variables:

```
export STARPU_DISABLE_KERNELS=1
export STARPU_MPI_FAKE_RANK=2
export STARPU_MPI_FAKE_SIZE=1024
```

Here we have disabled the kernel function call to skip the actual computation time and only keep submission time, and we have asked StarPU to fake running on MPI node 2 out of 1024 nodes.

17.9 Temporary Data

To be able to use starpu_mpi_task_insert(), one has to call starpu_mpi_data_register(), so that StarPU-MPI can know what it needs to do for each data. Parameters of starpu_mpi_data_register() are normally the same on all nodes for a given data, so that all nodes agree on which node owns the data, and which tag is used to transfer its value.

It can however be useful to register e.g. some temporary data on just one node, without having to register a dumb handle on all nodes, while only one node will actually need to know about it. In this case, nodes which will not need the data can just pass NULL to starpu_mpi_task_insert():

Here, nodes whose rank is not 0 will simply not take care of the data, and consider it to be on another node.

This can be mixed various way, for instance here node 1 determines that it does not have to care about data0, but knows that it should send the value of its data1 to node 0, which owns data and thus will need the value of data1 to execute the task:

```
starpu_data_handle_t data0 = NULL, data1, data;
if (rank == 0)
{
    starpu_variable_data_register(&data0, STARPU_MAIN_RAM,
    (uintptr_t) &val0, sizeof(val0));
    starpu_mpi_data_register(data0, -1, rank);
```

17.10 Per-node Data

Further than temporary data on just one node, one may want per-node data, to e.g. replicate some computation because that is less expensive than communicating the value over MPI:

```
starpu_data_handle pernode, data0, data1;
starpu_variable_data_register(&pernode, -1, 0, sizeof(val));
starpu_mpi_data_register(pernode, -1, STARPU_MPI_PER_NODE);
/* Normal data: one on node0, one on node1 */
if (rank == 0)
          starpu_variable_data_register(&data0, STARPU_MAIN_RAM,
       (uintptr_t) &val0, sizeof(val0));
         starpu_variable_data_register(&data1, -1, 0, sizeof(val1));
else if (rank == 1)
         starpu_variable_data_register(&data0, -1, 0, sizeof(val1));
starpu_variable_data_register(&data1, STARPU_MAIN_RAM,
        (uintptr_t) &val1, sizeof(val1));
starpu_mpi_data_register(data0, 42, 0);
starpu_mpi_data_register(data1, 43, 1);
starpu_mpi_task_insert(MPI_COMM_WORLD, &cl, STARPU_W, pernode, 0); /* Will be
        replicated on all nodes */
starpu_mpi_task_insert(MPI_COMM_WORLD, &cl2, STARPU_RW, data0, STARPU_R,
pernode); /* Will execute on node 0, using its own pernode*/
starpu mpi task insert(MPI COMM WORLD, &cl2, STARPU RW, data1, STARPU R,
       pernode); /* Will execute on node 1, using its own pernode*/
```

One can turn a normal data into pernode data, by first broadcasting it to all nodes:

The data can then be used just like pernode above.

17.11 Priorities

All send functions have a _prio variant which takes an additional priority parameter, which allows to make Star PU-MPI change the order of MPI requests before submitting them to MPI. The default priority is 0.

When using the starpu_mpi_task_insert() helper, STARPU_PRIORITY defines both the task priority and the MPI requests priority.

To test how much MPI priorities have a good effect on performance, you can set the environment variable STAR← PU_MPI_PRIORITIES to 0 to disable the use of priorities in StarPU-MPI.

17.12 MPI Cache Support

StarPU-MPI automatically optimizes duplicate data transmissions: if an MPI node $\mathbb B$ needs a piece of data $\mathbb D$ from MPI node $\mathbb A$ for several tasks, only one transmission of $\mathbb D$ will take place from $\mathbb A$ to $\mathbb B$, and the value of $\mathbb D$ will be kept on $\mathbb B$ as long as no task modifies $\mathbb D$.

If a task modifies D, B will wait for all tasks which need the previous value of D, before invalidating the value of D. As a consequence, it releases the memory occupied by D. Whenever a task running on B needs the new value of D, allocation will take place again to receive it.

Since tasks can be submitted dynamically, StarPU-MPI can not know whether the current value of data D will again be used by a newly-submitted task before being modified by another newly-submitted task, so until a task is submitted to modify the current value, it can not decide by itself whether to flush the cache or not. The application can however explicitly tell StarPU-MPI to flush the cache by calling starpu_mpi_cache_flush() or starpu_mpi_cache_ flush_all_data(), for instance in case the data will not be used at all any more (see for instance the cholesky example in mpi/examples/matrix_decomposition), or at least not in the close future. If a newly-submitted task actually needs the value again, another transmission of D will be initiated from A to B. A mere starpu_mpi_cache flush_all_data() can for instance be added at the end of the whole algorithm, to express that no data will be reused after this (or at least that it is not interesting to keep them in cache). It may however be interesting to add fine-graph starpu_mpi_cache_flush() calls during the algorithm; the effect for the data deallocation will be the same, but it will additionally release some pressure from the StarPU-MPI cache hash table during task submission.

One can determine whether a piece of is cached with starpu_mpi_cached_receive() and starpu_mpi_cached_ send().

The whole caching behavior can be disabled thanks to the STARPU_MPI_CACHE environment variable. The variable STARPU_MPI_CACHE_STATS can be set to 1 to enable the runtime to display messages when data are added or removed from the cache holding the received data.

17.13 MPI Data Migration

The application can dynamically change its mind about the data distribution, to balance the load over MPI nodes for instance. This can be done very simply by requesting an explicit move and then change the registered rank. For instance, we here switch to a new distribution function my_distrib2: we first register any data which wasn't registered already and will be needed, then migrate the data, and register the new location.

From then on, further tasks submissions will use the new data distribution, which will thus change both MPI communications and task assignments.

Very importantly, since all nodes have to agree on which node owns which data so as to determine MPI communications and task assignments the same way, all nodes have to perform the same data migration, and at the same point among task submissions. It thus does not require a strict synchronization, just a clear separation of task submissions before and after the data redistribution.

Before data unregistration, it has to be migrated back to its original home node (the value, at least), since that is where the user-provided buffer resides. Otherwise the unregistration will complain that it does not have the latest value on the original home node.

```
{
    int mpi_rank = my_distrib(x, y, size);
    /* Get back data to original place where the user-provided buffer is. */
    starpu_mpi_get_data_on_node_detached(MPI_COMM_WORLD,

    data_handles[x][y], mpi_rank, NULL, NULL);
    /* And unregister it */
        starpu_data_unregister(data_handles[x][y]);
    }
}
```

17.14 MPI Collective Operations

The functions are described in MPICollectiveOperations.

```
if (rank == root)
    /* Allocate the vector */
    vector = malloc(nblocks * sizeof(float *));
    for(x=0 ; x < nblocks ; x++)
        starpu_malloc((void **)&vector[x], block_size*sizeof(float));
/\star Allocate data handles and register data to StarPU \star/
data_handles = malloc(nblocks*sizeof(starpu_data_handle_t *));
for (x = 0; x < nblocks; x++)
    int mpi_rank = my_distrib(x, nodes);
         starpu_vector_data_register(&data_handles[x], STARPU_MAIN_RAM
        (uintptr_t)vector[x], blocks_size, sizeof(float));
    else if ((mpi_rank == rank) || ((rank == mpi_rank+1 || rank == mpi_rank-1)))
         /\star I own this index, or i will need it for my computations \star/
        starpu_vector_data_register(&data_handles[x], -1, (uintptr_t)NULL,
      block_size, sizeof(float));
    else
         /\star I know it's useless to allocate anything for this \star/
        data_handles[x] = NULL;
    if (data_handles[x])
        starpu_mpi_data_register(data_handles[x], x*nblocks+y, mpi_rank);
/* Scatter the matrix among the nodes */
starpu_mpi_scatter_detached(data_handles, nblocks, root, MPI_COMM_WORLD, NULL,
      NULL, NULL, NULL);
/* Calculation */
for(x = 0; x < nblocks; x++)
    if (data_handles[x])
        int owner = starpu_data_get_rank(data_handles[x]);
if (owner == rank)
             starpu_task_insert(&cl, STARPU_RW, data_handles[x], 0);
    }
/* Gather the matrix on main node */
starpu_mpi_gather_detached(data_handles, nblocks, 0, MPI_COMM_WORLD, NULL, NULL,
      NULL, NULL);
```

Other collective operations would be easy to define, just ask starpu-devel for them!

17.15 Make StarPU-MPI Progression Thread Execute Tasks

The default behaviour of StarPU-MPI is to spawn an MPI thread to take care only of MPI communications in an active fashion (i.e the StarPU-MPI thread sleeps only when there is no active request submitted by the application),

17.16 Debugging MPI 127

with the goal of being as reactive as possible to communications. Knowing that, users usually leave one free core for the MPI thread when starting a distributed execution with StarPU-MPI. However, this could result in a loss of performance for applications that does not require an extreme reactivity to MPI communications.

The starpu_mpi_init_conf() routine allows the user to give the starpu_conf configuration structure of StarPU (usually given to the starpu_init() routine) to StarPU-MPI, so that StarPU-MPI reserves for its own use one of the CPU drivers of the current computing node, or one of the CPU cores, and then calls starpu_init() internally.

This allows the MPI communication thread to call a StarPU CPU driver to run tasks when there is no active requests to take care of, and thus recover the computational power of the "lost" core. Since there is a trade-off between executing tasks and polling MPI requests, which is how much the application wants to lose in reactivity to MPI communications to get back the computing power of the core dedicated to the StarPU-MPI thread, there are two environment variables to pilot the behaviour of the MPI thread so that users can tune this trade-off depending of the behaviour of the application.

The STARPU_MPI_DRIVER_CALL_FREQUENCY environment variable sets how many times the MPI progression thread goes through the MPI_Test() loop on each active communication request (and thus try to make communications progress by going into the MPI layer) before executing tasks. The default value for this environment variable is 0, which means that the support for interleaving task execution and communication polling is deactivated, thus returning the MPI progression thread to its original behaviour.

The STARPU_MPI_DRIVER_TASK_FREQUENCY environment variable sets how many tasks are executed by the MPI communication thread before checking all active requests again. While this environment variable allows a better use of the core dedicated to StarPU-MPI for computations, it also decreases the reactivity of the MPI communication thread as much.

17.16 Debugging MPI

Communication trace will be enabled when the environment variable STARPU_MPI_COMM is set to 1, and StarPU has been configured with the option --enable-verbose.

Statistics will be enabled for the communication cache when the environment variable STARPU_MPI_CACHE_ STATS is set to 1. It prints messages on the standard output when data are added or removed from the received communication cache.

When the environment variable STARPU_COMM_STATS is set to 1, StarPU will display at the end of the execution for each node the volume and the bandwidth of data sent to all the other nodes. Here an example of such a trace.

```
[starpu_comm_stats][3] TOTAL: 476.000000 B 0.000454 MB 0.000098 B/s 0.000000 MB/s [starpu_comm_stats][3:0] 248.000000 B 0.000237 MB 0.000051 B/s 0.000000 MB/s [starpu_comm_stats][3:2] 50.0000000 B 0.000217 MB 0.000047 B/s 0.000000 MB/s [starpu_comm_stats][2] TOTAL: 288.000000 B 0.000275 MB 0.000059 B/s 0.000000 MB/s [starpu_comm_stats][2:1] 70.000000 B 0.000103 MB 0.000022 B/s 0.000000 MB/s [starpu_comm_stats][2:3] 288.000000 B 0.000172 MB 0.000037 B/s 0.000000 MB/s [starpu_comm_stats][1:0] 80.000000 B 0.000179 MB 0.000038 B/s 0.000000 MB/s [starpu_comm_stats][1:0] 80.000000 B 0.000114 MB 0.000025 B/s 0.000000 MB/s [starpu_comm_stats][1:2] 188.000000 B 0.000114 MB 0.000025 B/s 0.000000 MB/s [starpu_comm_stats][1:2] 188.000000 B 0.000065 MB 0.000014 B/s 0.000000 MB/s [starpu_comm_stats][0] TOTAL: 376.000000 B 0.000359 MB 0.000077 B/s 0.000000 MB/s [starpu_comm_stats][0:1] 376.000000 B 0.000141 MB 0.000030 B/s 0.000000 MB/s [starpu_comm_stats][0:3] 10.000000 B 0.000117 MB 0.000047 B/s 0.000000 MB/s
```

These statistics can be plotted as heatmaps using StarPU tool starpu_mpi_comm_matrix.py, this will produce 2 PDF files, one plot for the bandwidth, and one plot for the data volume.




Figure 17.1 Bandwidth Heatmap




Figure 17.2 Data Volume Heatmap

17.17 More MPI examples

MPI examples are available in the StarPU source code in mpi/examples:

- comm shows how to use communicators with StarPU-MPI
- complex is a simple example using a user-define data interface over MPI (complex numbers),
- stencil5 is a simple stencil example using starpu_mpi_task_insert(),
- matrix_decomposition is a cholesky decomposition example using starpu_mpi_task_insert(). The non-distributed version can check for <algorithm correctness in 1-node configuration, the distributed version uses exactly the same source code, to be used over MPI,
- mpi_lu is an LU decomposition example, provided in three versions: plu_example uses explicit MPI data transfers, plu_implicit_example uses implicit MPI data transfers, plu_outofcore_example uses implicit MPI data transfers and supports data matrices which do not fit in memory (out-of-core).

17.18 Notes about the Implementation

StarPU-MPI is implemented directly on top of MPI.

Since the release 1.3.0, an implementation on top of NewMadeleine, an optimizing communication library for high-performance networks, is also provided. To use it, one needs to install NewMadeleine (see $http://pm2. \leftarrow gforge.inria.fr/newmadeleine/$) and enable the configure option --enable-nmad. Both implementations provide the same public API.

17.19 MPI Master Slave Support

StarPU provides an other way to execute applications across many nodes. The Master Slave support permits to use remote cores without thinking about data distribution. This support can be activated with the configure option --enable-mpi-master-slave. However, you should not activate both MPI support and MPI Master-Slave support.

The existing kernels for CPU devices can be used as such. They only have to be exposed through the name of the function in the starpu_codelet::cpu_funcs_name field. Functions have to be globally-visible (i.e. not static) for StarPU to be able to look them up, and rdynamic must be passed to gcc (or cexport-dynamic to ld) so that symbols of the main program are visible. Optionally, you can choose the use of another function on slaves thanks to the field starpu_codelet::mpi_ms_funcs.

By default, one core is dedicated on the master node to manage the entire set of slaves. If the implementation of MPI you are using has a good multiple threads support, you can use the configure option --with-mpi-master-slave-multiple-thread to dedicate one core per slave.

Choosing the number of cores on each slave device is done by setting the environment variable STARPU_NMPI← MSTHREADS=<number> with <number> being the requested number of cores. By default all the slave's cores are used.

Setting the number of slaves nodes is done by changing the -n parameter when executing the application with mpirun or mpiexec.

The master node is by default the node with the MPI rank equal to 0. To select another node, use the environment variable STARPU MPI MASTER NODE=<number> with <number> being the requested MPI rank node.

Chapter 18

FFT Support

StarPU provides libstarpufft, a library whose design is very similar to both fftw and cufft, the difference being that it takes benefit from both CPUs and GPUs. It should however be noted that GPUs do not have the same precision as CPUs, so the results may different by a negligible amount.

Different precisions are available, namely float, double and long double precisions, with the following fftw naming conventions:

- double precision structures and functions are named e.g. starpufft_execute()
- float precision structures and functions are named e.g. starpufftf_execute()
- long double precision structures and functions are named e.g. starpufftl_execute()

The documentation below is given with names for double precision, replace starpufft_with starpufftf_ or starpufftl_ as appropriate.

Only complex numbers are supported at the moment.

The application has to call starpu init() before calling starpufft functions.

Either main memory pointers or data handles can be provided.

- To provide main memory pointers, use starpufft_start() or starpufft_execute(). Only one FFT can be performed at a time, because StarPU will have to register the data on the fly. In the starpufft_start() case, starpufft_celeanup() needs to be called to unregister the data.
- To provide data handles (which is preferrable), use starpufft_start_handle() (preferred) or starpufft_execute ← _handle(). Several FFTs tasks can be submitted for a given plan, which permits e.g. to start a series of FFT with just one plan. starpufft_start_handle() is preferrable since it does not wait for the task completion, and thus permits to enqueue a series of tasks.

All functions are defined in FFT Support.

18.1 Compilation

The flags required to compile or link against the FFT library are accessible with the following commands:

```
$ pkg-config --cflags starpufft-1.3 # options for the compiler
$ pkg-config --libs starpufft-1.3 # options for the linker
```

Also pass the option -static if the application is to be linked statically.

132 FFT Support

MIC Xeon Phi Support

19.1 Compilation

MIC Xeon Phi support actually needs two compilations of StarPU, one for the host and one for the device. The PATH environment variable has to include the path to the cross-compilation toolchain, for instance /usr/linux-klom-4.7/bin. The SINK_PKG_CONFIG_PATH environment variable should include the path to the cross-compiled hwloc.pc. The script mic-configure can then be used to achieve the two compilations: it basically calls configure as appropriate from two new directories: $build_mic$ and $build_$

One can also run StarPU just natively on the Xeon Phi, i.e. it will only run directly on the Phi without any exchange with the host CPU. The binaries in build_mic can be run that way.

For MPI support, you will probably have to specify different MPI compiler path or option for the host and the device builds, for instance:

```
./mic-configure --with-mic-param=--with-mpicc="/.../mpiicc -mmic" \
    --with-host-param=--with-mpicc=/.../mpiicc
```

In case you have troubles with the coi or scif libraries (the Intel paths are really not standard, it seems...), you can still make a build in native mode only, by using mic-configure -enable-native-mic (and notably without -enable-mic since in that case we don't need mic offloading support).

19.2 Porting Applications To MIC Xeon Phi

The simplest way to port an application to MIC Xeon Phi is to set the field starpu_codelet::cpu_funcs_name, to provide StarPU with the function name of the CPU implementation, so for instance:

```
struct starpu_codelet cl =
{
    .cpu_funcs = {myfunc},
    .cpu_funcs_name = {"myfunc"},
    .nbuffers = 1,
}
```

StarPU will thus simply use the existing CPU implementation (cross-rebuilt in the MIC Xeon Phi case). The functions have to be globally-visible (i.e. not static) for StarPU to be able to look them up, and -rdynamic must be passed to gcc (or -export-dynamic to ld) so that symbols of the main program are visible.

If you have used the starpu_codelet::where field, you additionally need to add in it STARPU_MIC for the Xeon Phi. For non-native MIC Xeon Phi execution, the 'main' function of the application, on the sink, should call starpu_init() immediately upon start-up; the starpu_init() function never returns. On the host, the 'main' function may freely perform application related initialization calls as usual, before calling starpu_init().

For MIC Xeon Phi, the application may programmatically detect whether executing on the sink or on the host, by checking whether the STARPU_SINK environment variable is defined (on the sink) or not (on the host).

19.3 Launching Programs

MIC programs are started from the host. StarPU automatically starts the same program on MIC devices. It however needs to get the MIC-cross-built binary. It will look for the file given by the environment variable STARPU_MIC_ \hookleftarrow SINK_PROGRAM_NAME or in the directory given by the environment variable STARPU_MIC_SINK_PROGRA \hookleftarrow M_PATH, or in the field starpu_conf::mic_sink_program_path. It will also look in the current directory for the same binary name plus the suffix -mic or $_mic$.

The testsuite can be started by simply running <code>make check</code> from the top directory. It will recurse into both <code>build_host</code> to run tests with only the host, and into <code>build_mic</code> to run tests with both the host and the MIC devices. Single tests with the host and the MIC can be run by starting <code>./loader-cross.sh ./the_test</code> from <code>build_mic/tests</code>.

Native Fortran Support

StarPU provides the necessary routines and support to natively access most of its functionalities from Fortran 2008+codes

All symbols (functions, constants) are defined in fstarpu_mod.f90. Every symbol of the Native Fortran support API is prefixed by fstarpu_.

Note: Mixing uses of fstarpu_ and starpu_ symbols in the same Fortran code has unspecified behaviour. See Valid API Mixes and Language Mixes for a discussion about valid and unspecified combinations.

20.1 Implementation Details and Specificities

20.1.1 Prerequisites

The Native Fortran support relies on Fortran 2008 specific constructs, as well as on the support of interoperability of assumed-shape arrays introduced as part of Fortran's Technical Specification ISO/IEC TS 29113:2012, for which no equivalent are available in previous versions of the standard. It has currently been tested successfully with GNU GFortran 4.9, GFortran 5.x, GFortran 6.x and the Intel Fortran Compiler >= 2016. It is known not to work with GNU GFortran < 4.9, Intel Fortran Compiler < 2016.

See Section Using StarPU with Older Fortran Compilers on information on how to write StarPU Fortran code with older compilers.

20.1.2 Configuration

The Native Fortran API is enabled and its companion fstarpu_mod.f90 Fortran module source file is installed by default when a Fortran compiler is found, unless the detected Fortran compiler is known not to support the requirements for the Native Fortran API. The support can be disabled through the configure option --disable-fortran. Conditional compiled source codes may check for the availability of the Native Fortran Support by testing whether the preprocessor macro STARPU_HAVE_FC is defined or not.

20.1.3 Examples

Several examples using the Native Fortran API are provided in StarPU's examples/native_fortran/ examples directory, to showcase the Fortran flavor of various basic and more advanced StarPU features.

20.1.4 Compiling a Native Fortran Application

The Fortran module fstarpu_mod.f90 installed in StarPU's include/ directory provides all the necessary API definitions. It must be compiled with the same compiler (same vendor, same version) as the application itself, and the resulting fstarpu_mod.o object file must linked with the application executable.

Each example provided in StarPU's examples/native_fortran/ examples directory comes with its own dedicated Makefile for out-of-tree build. Such example Makefiles may be used as starting points for building application codes with StarPU.

20.2 Fortran Translation for Common StarPU API Idioms

All these examples assume that the standard Fortran module iso_c_binding is in use.

• Specifying a NULL pointer

```
type(c_ptr) :: my_ptr  ! variable to store the pointer
! [...]
my_ptr = c_null_ptr     ! assign standard constant for null ptr
```

· Obtaining a pointer to some object:

```
real(8), dimension(:), allocatable, target :: va
type(c_ptr) :: p_va ! variable to store a pointer to array va
! [...]
p_va = c_loc(va)
```

· Obtaining a pointer to some subroutine:

```
! pointed routine definition
recursive subroutine myfunc () bind(C)
! [...]
type(c_funptr) :: p_fun ! variable to store the routine pointer
! [...]
p_fun = c_funloc(my_func)
```

· Obtaining the size of some object:

```
real(8) :: a
integer(c_size_t) :: sz_a ! variable to store the size of a
! [...]
sz_a = c_sizeof(a)
```

• Obtaining the length of an array dimension:

```
real(8), dimension(:,:), allocatable, target :: vb intger(c_int) :: ln_vb_1 ! variable to store the length of vb's dimension 1 intger(c_int) :: ln_vb_2 ! variable to store the length of vb's dimension 2 ! [...] ln_vb_1 = 1+ubound(vb,1)-lbound(vb,1) ! get length of dimension 1 of vb ln_vb_2 = 1+ubound(vb,2)-lbound(vb,2) ! get length of dimension 2 of vb
```

· Specifying a string constant:

```
type(c_ptr) :: my_cl ! a StarPU codelet
! [...]
! set the name of a codelet to string 'my_codele't:
call fstarpu_codelet_set_name(my_cl, c_char_"my_codelet"//c_null_char)
! note: using the C_CHAR_ prefix and the //C_NULL_CHAR concatenation at the end ensures
! that the string constant is properly '\0' terminated, and compatible with StarPU's
! internal C routines
!
! note: plain Fortran string constants are not '\0' terminated, and as such, must not be
! passed to starpu routines.
```

Combining multiple flag constants with a bitwise 'or':

```
type(c_ptr) :: my_cl ! a pointer for the codelet structure
! [...]
! add a managed buffer to a codelet, specifying both the Read/Write access mode and the Locality hint
call fstarpu_codelet_add_buffer(my_cl, fstarpu_rw.ior.fstarpu_locality)
```

20.3 Uses, Initialization and Shutdown

The snippet below show an example of minimal StarPU code using the Native Fortran support. The program should use the standard module <code>iso_c_binding</code> as well as StarPU's <code>fstarpu_mod</code>. The StarPU runtime engine is initialized with a call to function <code>fstarpu_init</code>, which returns an integer status of 0 if successful or non-0 otherwise. Eventually, a call to <code>fstarpu_shutdown</code> ends the runtime engine and frees all internal StarPU data structures

```
program nf initexit
       use iso_c_binding
                              ! C interfacing module
        use fstarpu_mod
                                ! StarPU interfacing module
       implicit none
                                ! Fortran recommended best practice
       integer(c int) :: err ! return status for fstarpu init
        ! initialize StarPU with default settings
        err = fstarpu_init(c_null_ptr)
        if (err /= 0) then
               stop 1
                                ! StarPU initialization failure
        end if
        ! - add StarPU Native Fortran API calls here
        ! shut StarPU down
       call fstarpu_shutdown()
end program nf_initexit
```

20.4 Fortran Flavor of StarPU's Variadic Insert_task

Fortran does not have a construction similar to C variadic functions on which starpu_insert_task() relies at the time of this writing. However, Fortran's variable length arrays of <code>c_ptr</code> elements enable to emulate much of the convenience of C's variadic functions. This is the approach retained for implementing <code>fstarpu_insert_task</code>. The general syntax for using <code>fstarpu_insert_task</code> is as follows:

There is thus a unique array argument (/ ... /) passed to fstarpu_insert_task which itself contains the task settings. Each element of the array must be of type $type(c_ptr)$. The last element of the array must be C NULL PTR.

Example extracted from nf vector.f90:

20.5 Functions and Subroutines Expecting Data Structures Arguments

Several StarPU structures that are expected to be passed to the C API, are replaced by function/subroutine wrapper sets to allocate, set fields and free such structure. This strategy has been prefered over defining native Fortran equivalent of such structures using Fortran's derived types, to avoid potential layout mismatch between C and Fortran StarPU data structures. Examples of such data structures wrappers include fstarpu_conf_allocate and alike, fstarpu_codelet_allocate and alike, fstarpu_data_filter_allocate and alike. Here is an example of allocating, filling and deallocating a codelet structure:

```
! a pointer for the codelet structure
type(c ptr) :: cl vec
 [...]
  allocate an empty codelet structure
cl_vec = fstarpu_codelet_allocate()
! add a CPU implementation function to the codelet
call fstarpu_codelet_add_cpu_func(cl_vec, c_funloc(cl_cpu_func_vec))
! set the codelet name
call fstarpu_codelet_set_name(cl_vec, c_char_"my_vec_codelet"//c_null_char)
! add a Read-only mode data buffer to the codelet
call fstarpu_codelet_add_buffer(cl_vec, fstarpu_r)
! add a Read-Write mode data buffer to the codelet
call fstarpu_codelet_add_buffer(cl_vec, fstarpu_rw.ior.fstarpu_locality)
! [...]
! free codelet structure
call fstarpu_codelet_free(cl_vec)
```

20.6 Additional Notes about the Native Fortran Support

20.6.1 Using StarPU with Older Fortran Compilers

When using older compilers, Fortran applications may still interoperate with StarPU using C marshalling functions as exemplified in StarPU's examples/fortran/ and examples/fortran90/ example directories, though the process will be less convenient.

Basically, the main FORTRAN code calls some C wrapper functions to submit tasks to StarPU. Then, when StarPU starts a task, another C wrapper function calls the FORTRAN routine for the task.

Note that this marshalled FORTRAN support remains available even when specifying configure option --disable-fortran (which only disables StarPU's native Fortran layer).

20.6.2 Valid API Mixes and Language Mixes

Mixing uses of fstarpu_ and starpu_ symbols in the same Fortran code has unspecified behaviour. Using fstarpu_ symbols in C code has unspecified behaviour.

For multi-language applications using both C and Fortran source files:

- C source files must use starpu_symbols exclusively
- Fortran sources must uniformly use either fstarpu_symbols exclusively, or starpu_symbols exclusively. Every other combination has unspecified behaviour.

SOCL OpenCL Extensions

SOCL is an OpenCL implementation based on StarPU. It gives a unified access to every available OpenCL device: applications can now share entities such as Events, Contexts or Command Queues between several OpenCL implementations.

In addition, command queues that are created without specifying a device provide automatic scheduling of the submitted commands on OpenCL devices contained in the context to which the command queue is attached.

Setting the CL_QUEUE_OUT_OF_ORDER_EXEC_MODE_ENABLE flag on a command queue also allows StarPU to reorder kernels queued on the queue, otherwise they would be serialized and several command queues would be necessary to see kernels dispatched on the various OpenCL devices.

Note: this is still an area under development and subject to change.

When compiling StarPU, SOCL will be enabled if a valid OpenCL implementation is found on your system. To be able to run the SOCL test suite, the environment variable SOCL_OCL_LIB_OPENCL needs to be defined to the location of the file libOpenCL.so of the OCL ICD implementation. You should for example add the following line in your file .bashrc

```
export SOCL_OCL_LIB_OPENCL=/usr/lib/x86_64-linux-gnu/libOpenCL.so
```

You can then run the test suite in the directory socl/examples.

The environment variable OCL_ICD_VENDORS has to point to the directory where the socl.icd ICD file is installed. When compiling StarPU, the files are in the directory <code>socl/vendors</code>. With an installed version of StarPU, the files are installed in the directory <code>sprefix/share/starpu/opencl/vendors</code>.

To run the tests by hand, you have to call for example,

```
$ LD_PRELOAD=$SOCL_OCL_LIB_OPENCL OCL_ICD_VENDORS=socl/vendors/ socl/examples/clinfo/clinfo
Number of platforms: 2
Plaform Profile: FULL_PROFILE
Plaform Version: OpenCL 1.1 CUDA 4.2.1
Plaform Name: NVIDIA CUDA
Plaform Vendor: NVIDIA Corporation
Plaform Extensions: cl_khr_byte_addressable_store cl_khr_icd cl_khr_gl_sharing cl_nv_compiler_options cl_nv_
Plaform Profile: FULL_PROFILE
Plaform Version: OpenCL 1.0 SOCL Edition (0.1.0)
Plaform Name: SOCL Platform
Plaform Vendor: Inria
Plaform Extensions: cl_khr_icd
```

To enable the use of CPU cores via OpenCL, one can set the STARPU_OPENCL_ON_CPUS environment variable to 1 and STARPU_NCPUS to 0 (to avoid using CPUs both via the OpenCL driver and the normal CPU driver).

SimGrid Support

StarPU can use Simgrid in order to simulate execution on an arbitrary platform. This was tested with simgrid from 3.11 to 3.16, and 3.18 to 3.22. Other versions may have compatibility issues. 3.17 notably does not build at all. MPI simulation does not work with version 3.22.

22.1 Preparing Your Application For Simulation

There are a few technical details which need to be handled for an application to be simulated through Simgrid. If the application uses gettimeofday to make its performance measurements, the real time will be used, which will be bogus. To get the simulated time, it has to use starpu_timing_now() which returns the virtual timestamp in us.

For some technical reason, the application's .c file which contains main() has to be recompiled with starpucation_simgrid_wrap.h, which in the simgrid case will # define main() into starpu_main(), and it is libstarpu which will provide the real main() and will call the application's main().

To be able to test with crazy data sizes, one may want to only allocate application data if the macro STARPU_S← IMGRID is not defined. Passing a NULL pointer to starpu_data_register functions is fine, data will never be read/written to by StarPU in Simgrid mode anyway.

To be able to run the application with e.g. CUDA simulation on a system which does not have CUDA installed, one can fill the starpu_codelet::cuda_funcs with (void*)1, to express that there is a CUDA implementation, even if one does not actually provide it. StarPU will not actually run it in Simgrid mode anyway by default (unless the STARP U_CODELET_SIMGRID_EXECUTE_AND_INJECT flags are set in the codelet)

22.2 Calibration

The idea is to first compile StarPU normally, and run the application, so as to automatically benchmark the bus and the codelets.

```
$ ./configure && make
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
[starpu][_starpu_load_history_based_model] Warning: model matvecmult
   is not calibrated, forcing calibration for this run. Use the
    STARPU_CALIBRATE environment variable to control this.
$ ...
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
TEST PASSED
```

142 SimGrid Support

Note that we force to use the scheduler <code>dmda</code> to generate performance models for the application. The application may need to be run several times before the model is calibrated.

22.3 Simulation

Then, recompile StarPU, passing --enable-simgrid to configure. Make sure to keep all other configure options the same, and notably options such as -enable-maxcudadev.

```
$ ./configure --enable-simgrid
```

To specify the location of SimGrid, you can either set the environment variables SIMGRID_CFLAGS and SIMG← RID_LIBS, or use the configure options --with-simgrid-dir, --with-simgrid-include-dir and --with-simgrid-lib-dir, for example

```
$ ./configure --with-simgrid-dir=/opt/local/simgrid
```

You can then re-run the application.

```
$ make
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
TEST FAILED !!!
```

It is normal that the test fails: since the computation are not actually done (that is the whole point of SimGrid), the result is wrong, of course.

If the performance model is not calibrated enough, the following error message will be displayed

```
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
[starpu][_starpu_load_history_based_model] Warning: model matvecmult
    is not calibrated, forcing calibration for this run. Use the
    STARPU_CALIBRATE environment variable to control this.
[starpu][_starpu_simgrid_execute_job][assert failure] Codelet
    matvecmult does not have a perfmodel, or is not calibrated enough
```

The number of devices can be chosen as usual with STARPU_NCPU, STARPU_NCUDA, and STARPU_NOPE
NCL, and the amount of GPU memory with STARPU_LIMIT_CUDA_MEM, STARPU_LIMIT_CUDA_devid_MEM,
STARPU_LIMIT_OPENCL_MEM, and STARPU_LIMIT_OPENCL_devid_MEM.

22.4 Simulation On Another Machine

The SimGrid support even permits to perform simulations on another machine, your desktop, typically. To achieve this, one still needs to perform the Calibration step on the actual machine to be simulated, then copy them to your desktop machine (the \$STARPU_HOME/.starpu directory). One can then perform the Simulation step on the desktop machine, by setting the environment variable STARPU_HOSTNAME to the name of the actual machine, to make StarPU use the performance models of the simulated machine even on the desktop machine.

If the desktop machine does not have CUDA or OpenCL, StarPU is still able to use SimGrid to simulate execution with CUDA/OpenCL devices, but the application source code will probably disable the CUDA and OpenCL codelets in that case. Since during SimGrid execution, the functions of the codelet are actually not called by default, one can use dummy functions such as the following to still permit CUDA or OpenCL execution.

22.5 Simulation Examples

StarPU ships a few performance models for a couple of systems: attila, mirage, idgraf, and sirocco. See Section Simulated benchmarks for the details.

22.6 Simulations On Fake Machines

It is possible to build fake machines which do not exist, by modifying the platform file in $SSTARPU_HO \leftarrow ME/.starpu/sampling/bus/machine.platform.xml by hand: one can add more CPUs, add GPUs (but the performance model file has to be extended as well), change the available GPU memory size, PCI memory bandwidth, etc.$

22.7 Tweaking Simulation

The simulation can be tweaked, to be able to tune it between a very accurate simulation and a very simple simulation (which is thus close to scheduling theory results), see the STARPU_SIMGRID_TRANSFER_COST, STARPU_SIMGRID_CUDA_MALLOC_COST, STARPU_SIMGRID_CUDA_QUEUE_COST, STARPU_SIMGRID_TASK_SU← BMIT_COST, STARPU_SIMGRID_FETCHING_INPUT_COST and STARPU_SIMGRID_SCHED_COST environment variables.

22.8 MPI Applications

StarPU-MPI applications can also be run in SimGrid mode. It needs to be compiled with smpice, and run using the starpu_smpirun script, for instance:

```
$ STARPU_SCHED=dmda starpu_smpirun -platform cluster.xml -hostfile hostfile ./mpi/tests/pingpong
```

Where cluster.xml is a SimGrid-MPI platform description, and hostfile the list of MPI nodes to be used. StarPU currently only supports homogeneous MPI clusters: for each MPI node it will just replicate the architecture referred by STARPU HOSTNAME.

22.9 Debugging Applications

By default, SimGrid uses its own implementation of threads, which prevents gdb from being able to inspect stacks of all threads. To be able to fully debug an application running with SimGrid, pass the -cfg=contexts/factory:thread option to the application, to make SimGrid use system threads, which gdb will be able to manipulate as usual.

It is also worth noting SimGrid 3.21's new parameter <code>-cfg=simix/breakpoint</code> which allows to put a breakpoint at a precise (deterministic!) timing of the execution. If for instance in an execution trace we see that something odd is happening at time 19000ms, we can use <code>-cfg=simix/breakpoint:19.000</code> and <code>SIGTRAP</code> will be raised at that point, which will thus interrupt execution within <code>gdb</code>, allowing to inspect e.g. scheduler state, etc.

22.10 Memory Usage

Since kernels are not actually run and data transfers are not actually performed, the data memory does not actually need to be allocated. This allows for instance to simulate the execution of applications processing very big data on a small laptop.

The application can for instance pass 1 (or whatever bogus pointer) to starpu data registration functions, instead of allocating data. This will however require the application to take care of not trying to access the data, and will not work in MPI mode, which performs transfers.

Another way is to pass the STARPU_MALLOC_SIMULATION_FOLDED flag to the starpu_malloc_flags() function. This will make it allocate a memory area which one can read/write, but optimized so that this does not actually consume memory. Of course, the values read from such area will be bogus, but this allows the application to keep e.g. data load, store, initialization as it is, and also work in MPI mode.

Note however that notably Linux kernels refuse obvious memory overcommitting by default, so a single allocation can typically not be bigger than the amount of physical memory, see $https://www.kernel.org/doc/\leftarrow Documentation/vm/overcommit-accounting$ This prevents for instance from allocating a single huge matrix. Allocating a huge matrix in several tiles is not a problem, however. sysctl vm.overcommit_ \leftarrow memory=1 can also be used to allow such overcommit.

Note however that this folding is done by remapping the same file several times, and Linux kernels will also refuse to create too many memory areas. <code>sysctl vm.max_map_count</code> can be used to check and change the default (65535). By default, StarPU uses a 1MiB file, so it hopefully fits in the CPU cache. This however limits the amount of such folded memory to a bit below 64GiB. The <code>STARPU_MALLOC_SIMULATION_FOLD</code> environment variable can be used to increase the size of the file.

144 SimGrid Support

The StarPU OpenMP Runtime Support (SORS)

StarPU provides the necessary routines and support to implement an OpenMP (http://www.openmp.org/) runtime compliant with the revision 3.1 of the language specification, and compliant with the task-related data dependency functionalities introduced in the revision 4.0 of the language. This StarPU OpenMP Runtime Support (SORS) has been designed to be targetted by OpenMP compilers such as the Klang-OMP compiler. Most supported OpenMP directives can both be implemented inline or as outlined functions.

All functions are defined in OpenMP Runtime Support.

23.1 Implementation Details and Specificities

23.1.1 Main Thread

When using the SORS, the main thread gets involved in executing OpenMP tasks just like every other threads, in order to be compliant with the specification execution model. This contrasts with StarPU's usual execution model where the main thread submit tasks but does not take part in executing them.

23.1.2 Extended Task Semantics

The semantics of tasks generated by the SORS are extended with respect to regular StarPU tasks in that SO← RS' tasks may block and be preempted by SORS call, whereas regular StarPU tasks cannot. SORS tasks may coexist with regular StarPU tasks. However, only the tasks created using SORS API functions inherit from extended semantics.

23.2 Configuration

The SORS can be compiled into libstarpu through the configure option --enable-openmp. Conditional compiled source codes may check for the availability of the OpenMP Runtime Support by testing whether the C preprocessor macro STARPU_OPENMP is defined or not.

23.3 Uses, Initialization and Shutdown

The SORS needs to be executed/terminated by the starpu_omp_init() / starpu_omp_shutdown() instead of starpu—init() / starpu_shutdown(). This requirement is necessary to make sure that the main thread gets the proper execution environment to run OpenMP tasks. These calls will usually be performed by a compiler runtime. Thus, they can be executed from a constructor/destructor such as this:

```
__attribute__((constructor))
static void omp_constructor(void)
{
        int ret = starpu_omp_init();
        STARPU_CHECK_RETURN_VALUE(ret, "starpu_omp_init");
}
__attribute__((destructor))
static void omp_destructor(void)
{
```

```
starpu_omp_shutdown();
}
See also
    starpu_omp_init()
    starpu_omp_shutdown()
```

23.4 Parallel Regions and Worksharing

The SORS provides functions to create OpenMP parallel regions as well as mapping work on participating workers. The current implementation does not provide nested active parallel regions: Parallel regions may be created recursively, however only the first level parallel region may have more than one worker. From an internal point-of-view, the SORS' parallel regions are implemented as a set of implicit, extended semantics StarPU tasks, following the execution model of the OpenMP specification. Thus the SORS' parallel region tasks may block and be preempted, by SORS calls, enabling constructs such as barriers.

23.4.1 Parallel Regions

Parallel regions can be created with the function starpu_omp_parallel_region() which accepts a set of attributes as parameter. The execution of the calling task is suspended until the parallel region completes. The field starpu—omp_parallel_region_attr::cl is a regular StarPU codelet. However only CPU codelets are supported for parallel regions. Here is an example of use:

See also

```
struct starpu_omp_parallel_region_attr
starpu_omp_parallel_region()
```

23.4.2 Parallel For

OpenMP for loops are provided by the starpu_omp_for() group of functions. Variants are available for inline or outlined implementations. The SORS supports static, dynamic, and guided loop scheduling clauses. The auto scheduling clause is implemented as static. The runtime scheduling clause honors the scheduling mode selected through the environment variable OMP_SCHEDULE or the starpu_omp_set_schedule() function. For loops with the ordered clause are also supported. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

The canonical family of starpu_omp_for() functions provide each instance with the first iteration number and the number of iterations (possibly zero) to perform. The alternate family of starpu_omp_for_alt() functions provide each instance with the (possibly empty) range of iterations to perform, including the first and excluding the last.

The family of starpu_omp_ordered() functions enable to implement OpenMP's ordered construct, a region with a parallel for loop that is guaranteed to be executed in the sequential order of the loop iterations.

```
void for_g(unsigned long long i, unsigned long long nb_i, void *arg)
{
    (void) arg;
```

```
for (; nb_i > 0; i++, nb_i--)
                array[i] = 1;
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        starpu_omp_for(for_g, NULL, NB_ITERS, CHUNK, starpu_omp_sched_static
See also
     starpu_omp_for()
     starpu_omp_for_inline_first()
     starpu_omp_for_inline_next()
     starpu_omp_for_alt()
     starpu_omp_for_inline_first_alt()
     starpu_omp_for_inline_next_alt()
     starpu_omp_ordered()
     starpu_omp_ordered_inline_begin()
     starpu omp ordered inline end()
```

23.4.3 Sections

OpenMP sections worksharing constructs are supported using the set of starpu_omp_sections() variants. The general principle is either to provide an array of per-section functions or a single function that will redirect to execution to the suitable per-section functions. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

```
void parallel_region_f(void *buffers[], void *args)
{
    (void) buffers;
    (void) args;

    section_funcs[0] = f;
    section_funcs[1] = g;
    section_funcs[2] = h;
    section_funcs[3] = i;

    section_args[0] = arg_f;
    section_args[1] = arg_g;
    section_args[2] = arg_h;
    section_args[3] = arg_i;

    starpu_omp_sections(4, section_f, section_args, 0);
}

See also

starpu_omp_sections()
    starpu_omp_sections_combined()
```

23.4.4 Single

OpenMP single workharing constructs are supported using the set of starpu_omp_single() variants. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

```
void single_f(void *arg)
{
      (void) arg;
      pthread_t tid = pthread_self();
      int worker_id = starpu_worker_get_id();
      printf("[tid %p] task thread = %d -- single\n", (void *)tid, worker_id);
}

void parallel_region_f(void *buffers[], void *args)
{
      (void) buffers;
```

```
(void) args;
   starpu_omp_single(single_f, NULL, 0);
```

The SORS also provides dedicated support for single sections with copyprivate clauses through the starpu_omp_single_copyprivate() function variants. The OpenMP master directive is supported as well using the starpu_omp_master() function variants.

See also

```
starpu_omp_master()
starpu_omp_master_inline()
starpu_omp_single()
starpu_omp_single_inline()
starpu_omp_single_copyprivate()
starpu_omp_single_copyprivate_inline_begin()
starpu_omp_single_copyprivate_inline_end()
```

23.5 Tasks

The SORS implements the necessary support of OpenMP 3.1 and OpenMP 4.0's so-called explicit tasks, together with OpenMP 4.0's data dependency management.

23.5.1 Explicit Tasks

Explicit OpenMP tasks are created with the SORS using the starpu_omp_task_region() function. The implementation supports if, final, untied and mergeable clauses as defined in the OpenMP specification. Unless specified otherwise by the appropriate clause(s), the created task may be executed by any participating worker of the current parallel region.

The current SORS implementation requires explicit tasks to be created within the context of an active parallel region. In particular, an explicit task cannot be created by the main thread outside of a parallel region. Explicit OpenMP tasks created using starpu_omp_task_region() are implemented as StarPU tasks with extended semantics, and may as such be blocked and preempted by SORS routines.

The current SORS implementation supports recursive explicit tasks creation, to ensure compliance with the Open

MP specification. However, it should be noted that StarPU is not designed nor optimized for efficiently scheduling
of recursive task applications.

The code below shows how to create 4 explicit tasks within a parallel region.

```
void task_region_g(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        pthread tid = pthread_self();
        int worker_id = starpu_worker_get_id();
printf("[tid %p] task thread = %d: explicit task \"g\"\n", (void *)tid, worker_id);
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        struct starpu_omp_task_region_attr attr;
        memset(&attr, 0, sizeof(attr));
        attr.cl.cpu_funcs[0] = task_region_g;
                                = STARPU_CPU;
        attr.cl.where
        attr.if_clause
                               = 1;
        attr.final_clause
        attr.untied_clause
        attr.mergeable_clause = 0;
        starpu_omp_task_region(&attr);
        starpu_omp_task_region(&attr);
        starpu omp task region(&attr);
        starpu_omp_task_region(&attr);
```

See also

```
struct starpu_omp_task_region_attr
starpu_omp_task_region()
```

23.5 Tasks 149

23.5.2 Data Dependencies

The SORS implements inter-tasks data dependencies as specified in OpenMP 4.0. Data dependencies are expressed using regular StarPU data handles (starpu_data_handle_t) plugged into the task's attr.cl codelet. The family of starpu_vector_data_register() -like functions and the starpu_data_lookup() function may be used to register a memory area and to retrieve the current data handle associated with a pointer respectively. The testcase ./tests/openmp/task_02.c gives a detailed example of using OpenMP 4.0 tasks dependencies with the SORS implementation.

Note: the OpenMP 4.0 specification only supports data dependencies between sibling tasks, that is tasks created by the same implicit or explicit parent task. The current SORS implementation also only supports data dependencies between sibling tasks. Consequently the behaviour is unspecified if dependencies are expressed beween tasks that have not been created by the same parent task.

23.5.3 TaskWait and TaskGroup

The SORS implements both the taskwait and taskgroup OpenMP task synchronization constructs specified in OpenMP 4.0, with the starpu_omp_taskwait() and starpu_omp_taskgroup() functions respectively.

An example of starpu_omp_taskwait() use, creating two explicit tasks and waiting for their completion:

```
void task_region_g(void *buffers[], void *args)
        (void) buffers;
        (void) args;
       printf("Hello, World!\n");
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        struct starpu_omp_task_region_attr attr;
       memset(&attr, 0, sizeof(attr));
        attr.cl.cpu_funcs[0] = task_region_g;
                              = STARPU_CPU;
       attr.cl.where
        attr.if_clause
                             = 0;
        attr.final_clause
        attr.untied_clause
        attr.mergeable_clause = 0;
        starpu_omp_task_region(&attr);
        starpu_omp_task_region(&attr);
        starpu_omp_taskwait();
```

An example of starpu omp taskgroup() use, creating a task group of two explicit tasks:

```
void task_region_g(void *buffers[], void *args)
        (void) buffers;
        (void) args;
       printf("Hello, World!\n");
}
void taskgroup f(void *arg)
        (void)arg;
        struct starpu_omp_task_region_attr attr;
        memset(&attr, 0, sizeof(attr));
        attr.cl.cpu_funcs[0] = task_region_g;
                              = STARPU CPU:
        attr.cl.where
                             = 1;
       attr.if clause
       attr.final clause
        attr.untied_clause
        attr.mergeable_clause = 0;
        starpu_omp_task_region(&attr);
       starpu_omp_task_region(&attr);
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        starpu_omp_taskgroup(taskgroup_f, (void *)NULL);
```

See also

```
starpu_omp_task_region()
starpu_omp_taskwait()
starpu_omp_taskgroup()
starpu_omp_taskgroup_inline_begin()
starpu_omp_taskgroup_inline_end()
```

23.6 Synchronization Support

The SORS implements objects and method to build common OpenMP synchronization constructs.

23.6.1 Simple Locks

The SORS Simple Locks are opaque starpu_omp_lock_t objects enabling multiple tasks to synchronize with each others, following the Simple Lock constructs defined by the OpenMP specification. In accordance with such specification, simple locks may not by acquired multiple times by the same task, without being released in-between; otherwise, deadlocks may result. Codes requiring the possibility to lock multiple times recursively should use Nestable Locks (Nestable Locks). Codes NOT requiring the possibility to lock multiple times recursively should use Simple Locks as they incur less processing overhead than Nestable Locks.

See also

```
starpu_omp_lock_t
starpu_omp_init_lock()
starpu_omp_destroy_lock()
starpu_omp_set_lock()
starpu_omp_unset_lock()
starpu_omp_test_lock()
```

23.6.2 Nestable Locks

The SORS Nestable Locks are opaque starpu_omp_nest_lock_t objects enabling multiple tasks to synchronize with each others, following the Nestable Lock constructs defined by the OpenMP specification. In accordance with such specification, nestable locks may by acquired multiple times recursively by the same task without deadlocking. Nested locking and unlocking operations must be well parenthesized at any time, otherwise deadlock and/or undefined behaviour may occur. Codes requiring the possibility to lock multiple times recursively should use Nestable Locks. Codes NOT requiring the possibility to lock multiple times recursively should use Simple Locks (Simple Locks) instead, as they incur less processing overhead than Nestable Locks.

See also

```
starpu_omp_nest_lock_t
starpu_omp_init_nest_lock()
starpu_omp_destroy_nest_lock()
starpu_omp_set_nest_lock()
starpu_omp_unset_nest_lock()
starpu_omp_test_nest_lock()
```

23.6.3 Critical Sections

The SORS implements support for OpenMP critical sections through the family of starpu_omp_critical functions. Critical sections may optionally be named. There is a single, common anonymous critical section. Mutual exclusion only occur within the scope of single critical section, either a named one or the anonymous one.

See also

```
starpu_omp_critical()
starpu_omp_critical_inline_begin()
starpu_omp_critical_inline_end()
```

23.6.4 Barriers

The SORS provides the starpu_omp_barrier() function to implement barriers over parallel region teams. In accordance with the OpenMP specification, the starpu_omp_barrier() function waits for every implicit task of the parallel region to reach the barrier and every explicit task launched by the parallel region to complete, before returning.

See also

starpu_omp_barrier()

Clustering a Machine

24.1 General Ideas

Clusters are a concept introduced in this paper.

The granularity problem is tackled by using resource aggregation: instead of dynamically splitting tasks, resources are aggregated to process coarse grain tasks in a parallel fashion. This is built on top of scheduling contexts to be able to handle any type of parallel tasks.

This comes from a basic idea, making use of two levels of parallelism in a DAG. We keep the DAG parallelism but consider on top of it that a task can contain internal parallelism. A good example is if each task in the DAG is OpenMP enabled.

The particularity of such tasks is that we will combine the power of two runtime systems: StarPU will manage the DAG parallelism and another runtime (e.g. OpenMP) will manage the internal parallelism. The challenge is in creating an interface between the two runtime systems so that StarPU can regroup cores inside a machine (creating what we call a **cluster**) on top of which the parallel tasks (e.g. OpenMP tasks) will be run in a contained fashion.

The aim of the cluster API is to facilitate this process in an automatic fashion. For this purpose, we depend on the hwloc tool to detect the machine configuration and then partition it into usable clusters.

An example of code running on clusters is available in examples/sched_ctx/parallel_tasks_with ← _cluster_api.c.

Let's first look at how to create a cluster.

To enable clusters in StarPU, one needs to set the configure option --enable-cluster.

24.2 Creating Clusters

Partitioning a machine into clusters with the cluster API is fairly straightforward. The simplest way is to state under which machine topology level we wish to regroup all resources. This level is an hwloc object, of the type hwloc-obj_type_t. More information can be found in the hwloc documentation.

Once a cluster is created, the full machine is represented with an opaque structure starpu_cluster_machine. This can be printed to show the current machine state.

```
struct starpu_cluster_machine *clusters;
clusters = starpu_cluster_machine(HWLOC_OBJ_SOCKET, 0);
starpu_cluster_print(clusters);
/* submit some tasks with OpenMP computations */
starpu_uncluster_machine(clusters);
/* we are back in the default StarPU state */
```

The following graphic is an example of what a particular machine can look like once clusterized. The main difference is that we have less worker queues and tasks which will be executed on several resources at once. The execution of these tasks will be left to the internal runtime system, represented with a dashed box around the resources.

154 Clustering a Machine




Figure 24.1 StarPU using parallel tasks

Creating clusters as shown in the example above will create workers able to execute OpenMP code by default. The cluster creation function starpu_cluster_machine() takes optional parameters after the hwloc object (always terminated by the value 0) which allow to parametrize the cluster creation. These parameters can help creating clusters of a type different from OpenMP, or create a more precise partition of the machine.

This is explained in Section Creating Custom Clusters.

24.3 Example Of Constraining OpenMP

Clusters require being able to constrain the runtime managing the internal task parallelism (internal runtime) to the resources set by StarPU. The purpose of this is to express how StarPU must communicate with the internal runtime to achieve the required cooperation. In the case of OpenMP, StarPU will provide an awake thread from the cluster to execute this liaison. It will then provide on demand the process ids of the other resources supposed to be in the region. Finally, thanks to an OpenMP region we can create the required number of threads and bind each of them on the correct region. These will then be reused each time we encounter a #pragma omp parallel in the following computations of our program.

The following graphic is an example of what an OpenMP-type cluster looks like and how it represented in StarPU. We can see that one StarPU (black) thread is awake, and we need to create on the other resources the OpenMP threads (in pink).




Figure 24.2 StarPU with an OpenMP cluster

Finally, the following code shows how to force OpenMP to cooperate with StarPU and create the aforementioned OpenMP threads constrained in the cluster's resources set:

```
void starpu_openmp_prologue(void * sched_ctx_id)
{
  int sched_ctx = *(int*)sched_ctx_id;
  int *cpuids = NULL;
  int ncpuids = 0;
  int workerid = starpu_worker_get_id();
```

```
//we can target only CPU workers
if (starpu_worker_get_type(workerid) == STARPU_CPU_WORKER)
{
   //grab all the ids inside the cluster
   starpu_sched_ctx_get_available_cpuids(sched_ctx, &cpuids, &ncpuids);
   //set the number of threads
   omp_set_num_threads(ncpuids);
#pragma omp parallel
   {
        //bind each threads to its respective resource
        starpu_sched_ctx_bind_current_thread_to_cpuid(cpuids[omp_get_thread_num()]);
   }
   free(cpuids);
}
return;
```

This function is the default function used when calling starpu_cluster_machine() without extra parameter. Cluster are based on several tools and models already available within StarPU contexts, and merely extend contexts. More on contexts can be read in Section Scheduling Contexts.

24.4 Creating Custom Clusters

Clusters can be created either with the predefined types provided within StarPU, or with user-defined functions to bind another runtime inside StarPU.

The predefined cluster types provided by StarPU are STARPU_CLUSTER_OPENMP, STARPU_CLUSTER_IN ← TEL_OPENMP_MKL and STARPU_CLUSTER_GNU_OPENMP_MKL. The last one is only provided if StarPU is compiled with the MKL library. It uses MKL functions to set the number of threads which is more reliable when using an OpenMP implementation different from the Intel one.

The cluster type is set when calling the function starpu_cluster_machine() with the parameter ::STARPU_CLUS← TER_TYPE as in the example below, which is creating a MKL cluster.

Using the default type STARPU_CLUSTER_OPENMP is similar to calling starpu_cluster_machine() without any extra parameter.

Users can also define their own function.

Parameters that can be given to starpu_cluster_machine() are ::STARPU_CLUSTER_MIN_NB, ::STARPU_CLUSTER_VUSTER_MAX_NB, ::STARPU_CLUSTER_NB, ::STARPU_CLUSTER_POLICY_NAME, ::STARPU_CLUSTER_POLICY_STRUCT, ::STARPU_CLUSTER_KEEP_HOMOGENEOUS, ::STARPU_CLUSTER_PREFERE_MIN, ::← STARPU_CLUSTER_CREATE_FUNC, ::STARPU_CLUSTER_CREATE_FUNC_ARG, ::STARPU_CLUSTER_← TYPE, ::STARPU_CLUSTER_AWAKE_WORKERS, ::STARPU_CLUSTER_PARTITION_ONE, ::STARPU_CLU← STER_NEW and ::STARPU_CLUSTER_NCORES.

24.5 Clusters With Scheduling

As previously mentioned, the cluster API is implemented on top of Scheduling Contexts. Its main addition is to ease the creation of a machine CPU partition with no overlapping by using hwloc, whereas scheduling contexts can use any number of any type of resources.

It is therefore possible, but not recommended, to create clusters using the scheduling contexts API. This can be useful mostly in the most complex machine configurations where users have to dimension precisely clusters by hand using their own algorithm.

156 Clustering a Machine

```
/* the list of resources the context will manage */
int workerids[3] = {1, 3, 10};

/* indicate the list of workers assigned to it, the number of workers,
the name of the context and the scheduling policy to be used within
the context */
int id_ctx = starpu_sched_ctx_create(workerids, 3, "my_ctx", 0);

/* let StarPU know that the following tasks will be submitted to this context */
starpu_sched_ctx_set_task_context(id);

task->prologue_callback_pop_func=&runtime_interface_function_here;

/* submit the task to StarPU */
starpu_task_submit(task);
```

As this example illustrates, creating a context without scheduling policy will create a cluster. The interface function between StarPU and the other runtime must be specified through the field starpu_task::prologue_callback_pop_
func. Such a function can be similar to the OpenMP thread team creation one (see above).

Note that the OpenMP mode is the default mode both for clusters and contexts. The result of a cluster creation is a woken-up master worker and sleeping "slaves" which allow the master to run tasks on their resources. To create a cluster with woken-up workers, the flag STARPU_SCHED_CTX_AWAKE_WORKERS must be set when using the scheduling context API function starpu_sched_ctx_create(), or the flag ::STARPU_CLUSTER_AWAKE \(\to \) _WORKERS must be set when using the cluster API function starpu_cluster_machine().

Interoperability Support

In situations where multiple parallel software elements have to coexist within the same application, uncoordinated accesses to computing units may lead such parallel software elements to collide and interfere. The purpose of the Interoperability routines of StarPU, implemented along the definition of the Resource Management APIs of Project H2020 INTERTWinE, is to enable StarPU to coexist with other parallel software elements without resulting in computing core oversubscription or undersubscription. These routines allow the programmer to dynamically control the computing resources allocated to StarPU, to add or remove processor cores and/or accelerator devices from the pool of resources used by StarPU's workers to execute tasks. They also allow multiple libraries and applicative codes using StarPU simultaneously to select distinct sets of resources independently. Internally, the Interoperability Support is built on top of Scheduling Contexts (see Scheduling Contexts).

25.1 StarPU Resource Management

The starpurm module is a library built on top of the starpu library. It exposes a series of routines prefixed with starpurm_ defining the resource management API.

All functions are defined in Interoperability Support.

25.1.1 Linking a program with the starpurm module

The starpurm module must be linked explicitly with the applicative executable using it. Example Makefiles in the starpurm/dev/subdirectories show how to do so. If the pkg-config command is available and the $PKG_\leftarrow CONFIG_PATH$ environment variable is properly positioned, the proper settings may be obtained with the following Makefile snippet:

```
CFLAGS += $(shell pkg-config --cflags starpurm-1.3)
LDFLAGS+= $(shell pkg-config --libs-only-L starpurm-1.3)
LDLIBS += $(shell pkg-config --libs-only-l starpurm-1.3)
```

25.1.2 Uses, Initialization and Shutdown

The starpurm module is initialized with a call to starpurm_initialize() and must be finalized with a call to starpurm_shutdown(). The starpurm module supports CPU cores as well as devices. An integer ID is assigned to each supported device type. The ID assigned to a given device type can be queried with the starpurm_get_device __type_id() routine, which currently expects one of the following strings as argument and returns the corresponding ID:

- "cpu"
- "opencl"
- "cuda"
- "mic"

The cpu pseudo device type is defined for convenience and designates CPU cores. The number of units of each type available for computation can be obtained with a call to starpu_get_nb_devices_by_type().

Each CPU core unit available for computation is designated by its rank among the StarPU CPU worker threads and by its own CPUSET bit. Each non-CPU device unit can be designated both by its rank number in the type, and by the CPUSET bit corresponding to its StarPU device worker thread. The CPUSET of a computing unit or its associated worker can be obtained from its type ID and rank with starpurm_get_device_worker_cpuset(), which returns the corresponding HWLOC CPUSET.

25.1.3 Default Context

The starpurm module assumes a default, global context, manipulated through a series of routines allowing to assign and withdraw computing units from the main StarPU context. Assigning CPU cores can be done with starpurm_assign_cpu_to_starpu() and starpurm_assign_cpu_mask_to_starpu(), and assigning device units can be done with starpurm_assign_device_to_starpu() and starpurm_assign_device_mask_to_starpu(). Conversely, withdrawing CPU cores can be done with starpurm_withdraw_cpu_from_starpu() and starpurm_withdraw_cpu_cmask_from_starpu(), and withdrawing device units can be done with starpurm_withdraw_device_from_starpu() and starpurm_withdraw_device_mask_from_starpu(). These routine should typically be used to control resource usage for the main applicative code.

25.1.4 Temporary Contexts

Besides the default, global context, starpurm can create temporary contexts and launch the computation of kernels confined to these temporary contexts. The routine starpurm_spawn_kernel_on_cpus() can be used to do so: it allocates a temporary context and spawns a kernel within this context. The temporary context is subsequently freed upon completion of the kernel. The temporary context is set as the default context for the kernel throughout its lifespan. This routine should typically be used to control resource usage for a parallel kernel handled by an external library built on StarPU. Internally, it relies on the use of starpu_sched_ctx_set_context() to set the temporary context as default context for the parallel kernel, and then restore the main context upon completion. Note: the maximum number of temporary contexts allocated concurrently at any time should not exceed STARPU_NMAX_SCHED CTXS-2, otherwise, the call to starpurm_spawn_kernel_on_cpus() may block until a temporary context becomes available. The routine starpurm_spawn_kernel_on_cpus() returns upon the completion of the parallel kernel. An asynchronous variant is available with the routine starpurm_spawn_kernel_on_cpus_callback(). This variant returns immediately, however it accepts a callback function, which is subsequently called to notify the calling code about the completion of the parallel kernel.

Part V StarPU Reference API

Execution Configuration Through Environment Variables

The behavior of the StarPU library and tools may be tuned thanks to the following environment variables.

26.1 Configuring Workers

- **STARPU_NCPU** Specify the number of CPU workers (thus not including workers dedicated to control accelerators). Note that by default, StarPU will not allocate more CPU workers than there are physical CPUs, and that some CPUs are used to control the accelerators.
- **STARPU_RESERVE_NCPU** Specify the number of CPU cores that should not be used by StarPU, so the application can use starpu_get_next_bindid() and starpu_bind_thread_on() to bind its own threads.
 - This option is ignored if STARPU_NCPU or starpu_conf::ncpus is set.
- STARPU_NCPUS This variable is deprecated. You should use STARPU NCPU.
- **STARPU_NCUDA** Specify the number of CUDA devices that StarPU can use. If STARPU_NCUDA is lower than the number of physical devices, it is possible to select which CUDA devices should be used by the means of the environment variable STARPU_WORKERS_CUDAID. By default, StarPU will create as many CUDA workers as there are CUDA devices.
- **STARPU_NWORKER_PER_CUDA** Specify the number of workers per CUDA device, and thus the number of kernels which will be concurrently running on the devices. The default value is 1.
- STARPU_CUDA_THREAD_PER_WORKER Specify whether the cuda driver should use one thread per stream (1) or to use a single thread to drive all the streams of the device or all devices (0), and STARPU_CUDA_T← HREAD_PER_DEV determines whether is it one thread per device or one thread for all devices. The default value is 0. Setting it to 1 is contradictory with setting STARPU_CUDA_THREAD_PER_DEV.
- **STARPU_CUDA_THREAD_PER_DEV** Specify whether the cuda driver should use one thread per device (1) or to use a single thread to drive all the devices (0). The default value is 1. It does not make sense to set this variable if STARPU_CUDA_THREAD_PER_WORKER is set to to 1 (since STARPU_CUDA_THREAD_P ← ER_DEV is then meaningless).
- **STARPU_CUDA_PIPELINE** Specify how many asynchronous tasks are submitted in advance on CUDA devices. This for instance permits to overlap task management with the execution of previous tasks, but it also allows concurrent execution on Fermi cards, which otherwise bring spurious synchronizations. The default is 2. Setting the value to 0 forces a synchronous execution of all tasks.
- STARPU NOPENCL OpenCL equivalent of the environment variable STARPU NCUDA.
- **STARPU_OPENCL_PIPELINE** Specify how many asynchronous tasks are submitted in advance on OpenCL devices. This for instance permits to overlap task management with the execution of previous tasks, but it also allows concurrent execution on Fermi cards, which otherwise bring spurious synchronizations. The default is 2. Setting the value to 0 forces a synchronous execution of all tasks.

- **STARPU_OPENCL_ON_CPUS** By default, the OpenCL driver only enables GPU and accelerator devices. By setting the environment variable STARPU_OPENCL_ON_CPUS to 1, the OpenCL driver will also enable CPU devices.
- **STARPU_OPENCL_ONLY_ON_CPUS** By default, the OpenCL driver enables GPU and accelerator devices. By setting the environment variable STARPU_OPENCL_ONLY_ON_CPUS to 1, the OpenCL driver will ONLY enable CPU devices.
- **STARPU_NMIC** MIC equivalent of the environment variable STARPU_NCUDA, i.e. the number of MIC devices to use.
- STARPU NMICTHREADS Number of threads to use on the MIC devices.
- **STARPU_NMPI_MS** MPI Master Slave equivalent of the environment variable STARPU_NCUDA, i.e. the number of MPI Master Slave devices to use.
- **STARPU_NMPIMSTHREADS** Number of threads to use on the MPI Slave devices.
- **STARPU_MPI_MASTER_NODE** This variable allows to chose which MPI node (with the MPI ID) will be the master.
- **STARPU_WORKERS_NOBIND** Setting it to non-zero will prevent StarPU from binding its threads to CPUs. This is for instance useful when running the testsuite in parallel.
- STARPU_WORKERS_CPUID Passing an array of integers in STARPU_WORKERS_CPUID specifies on which logical CPU the different workers should be bound. For instance, if STARPU_WORKERS_CPUID = "0 1 4 5", the first worker will be bound to logical CPU #0, the second CPU worker will be bound to logical CPU #1 and so on. Note that the logical ordering of the CPUs is either determined by the OS, or provided by the library hwloc in case it is available. Ranges can be provided: for instance, STARPU_WORKERS_CPU← ID = "1-3 5" will bind the first three workers on logical CPUs #1, #2, and #3, and the fourth worker on logical CPU #5. Unbound ranges can also be provided: STARPU_WORKERS_CPUID = "1-" will bind the workers starting from logical CPU #1 up to last CPU.

Note that the first workers correspond to the CUDA workers, then come the OpenCL workers, and finally the CPU workers. For example if we have STARPU_NCUDA=1, STARPU_NOPENCL=1, STARPU_NCPU=2 and STARPU_WORKERS_CPUID = "0 2 1 3", the CUDA device will be controlled by logical CPU #0, the OpenCL device will be controlled by logical CPU #2, and the logical CPUs #1 and #3 will be used by the CPU workers.

If the number of workers is larger than the array given in STARPU_WORKERS_CPUID, the workers are bound to the logical CPUs in a round-robin fashion: if STARPU_WORKERS_CPUID = "0 1", the first and the third (resp. second and fourth) workers will be put on CPU #0 (resp. CPU #1).

This variable is ignored if the field starpu conf::use explicit workers bindid passed to starpu init() is set.

- **STARPU_MAIN_THREAD_BIND** When defined, this make StarPU bind the thread that calls starpu_initialize() to a reserved CPU, subtracted from the CPU workers.
- **STARPU_MAIN_THREAD_CPUID** When defined, this make StarPU bind the thread that calls starpu_initialize() to the given CPU ID.
- **STARPU_MPI_THREAD_CPUID** When defined, this make StarPU bind its MPI thread to the given CPU ID. Setting it to -1 (the default value) will use a reserved CPU, subtracted from the CPU workers.
- STARPU_WORKERS_CUDAID Similarly to the STARPU_WORKERS_CPUID environment variable, it is possible to select which CUDA devices should be used by StarPU. On a machine equipped with 4 GPUs, setting S← TARPU_WORKERS_CUDAID = "1 3" and STARPU_NCUDA=2 specifies that 2 CUDA workers should be created, and that they should use CUDA devices #1 and #3 (the logical ordering of the devices is the one reported by CUDA).
 - This variable is ignored if the field starpu_conf::use_explicit_workers_cuda_gpuid passed to starpu_init() is set.
- **STARPU_WORKERS_OPENCLID** OpenCL equivalent of the STARPU_WORKERS_CUDAID environment variable.
 - This variable is ignored if the field starpu_conf::use_explicit_workers_opencl_gpuid passed to starpu_init() is set.

- STARPU_WORKERS_MICID MIC equivalent of the STARPU_WORKERS_CUDAID environment variable.
 - This variable is ignored if the field starpu_conf::use_explicit_workers_mic_deviceid passed to starpu_init() is set.
- **STARPU_WORKER_TREE** Define to 1 to enable the tree iterator in schedulers.
- **STARPU_SINGLE_COMBINED_WORKER** If set, StarPU will create several workers which won't be able to work concurrently. It will by default create combined workers which size goes from 1 to the total number of CPU workers in the system. STARPU_MIN_WORKERSIZE and STARPU_MAX_WORKERSIZE can be used to change this default.
- **STARPU_MIN_WORKERSIZE** STARPU_MIN_WORKERSIZE permits to specify the minimum size of the combined workers (instead of the default 2)
- **STARPU_MAX_WORKERSIZE** STARPU_MAX_WORKERSIZE permits to specify the minimum size of the combined workers (instead of the number of CPU workers in the system)
- STARPU_SYNTHESIZE_ARITY_COMBINED_WORKER Let the user decide how many elements are allowed between combined workers created from hwloc information. For instance, in the case of sockets with 6 cores without shared L2 caches, if STARPU_SYNTHESIZE_ARITY_COMBINED_WORKER is set to 6, no combined worker will be synthesized beyond one for the socket and one per core. If it is set to 3, 3 intermediate combined workers will be synthesized, to divide the socket cores into 3 chunks of 2 cores. If it set to 2, 2 intermediate combined workers will be synthesized, to divide the the socket cores into 2 chunks of 3 cores, and then 3 additional combined workers will be synthesized, to divide the former synthesized workers into a bunch of 2 cores, and the remaining core (for which no combined worker is synthesized since there is already a normal worker for it).
 - The default, 2, thus makes StarPU tend to building a binary trees of combined workers.
- **STARPU_DISABLE_ASYNCHRONOUS_COPY** Disable asynchronous copies between CPU and GPU devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- **STARPU_DISABLE_ASYNCHRONOUS_CUDA_COPY** Disable asynchronous copies between CPU and CUDA devices.
- **STARPU_DISABLE_ASYNCHRONOUS_OPENCL_COPY** Disable asynchronous copies between CPU and OpenCL devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- **STARPU_DISABLE_ASYNCHRONOUS_MIC_COPY** Disable asynchronous copies between CPU and MIC devices.
- **STARPU_DISABLE_ASYNCHRONOUS_MPI_MS_COPY** Disable asynchronous copies between CPU and MPI Slave devices.
- **STARPU_ENABLE_CUDA_GPU_DIRECT** Enable (1) or Disable (0) direct CUDA transfers from GPU to GPU, without copying through RAM. The default is Enabled. This permits to test the performance effect of GPU-Direct.
- **STARPU_DISABLE_PINNING** Disable (1) or Enable (0) pinning host memory allocated through starpu_malloc, starpu_memory_pin and friends. The default is Enabled. This permits to test the performance effect of memory pinning.
- STARPU_MIC_SINK_PROGRAM_NAME todo
- STARPU_MIC_SINK_PROGRAM_PATH todo
- STARPU MIC PROGRAM PATH todo

26.2 Configuring The Scheduling Engine

STARPU_SCHED Choose between the different scheduling policies proposed by StarPU: work random, stealing, greedy, with performance models, etc.

Use STARPU_SCHED=help to get the list of available schedulers.

STARPU MIN PRIO Set the mininum priority used by priorities-aware schedulers.

STARPU_MAX_PRIO Set the maximum priority used by priorities-aware schedulers.

STARPU_CALIBRATE If this variable is set to 1, the performance models are calibrated during the execution. If it is set to 2, the previous values are dropped to restart calibration from scratch. Setting this variable to 0 disable calibration, this is the default behaviour.

Note: this currently only applies to dm and dmda scheduling policies.

- **STARPU_CALIBRATE_MINIMUM** Define the minimum number of calibration measurements that will be made before considering that the performance model is calibrated. The default value is 10.
- STARPU BUS CALIBRATE If this variable is set to 1, the bus is recalibrated during intialization.
- **STARPU_PREFETCH** Indicate whether data prefetching should be enabled (0 means that it is disabled). If prefetching is enabled, when a task is scheduled to be executed e.g. on a GPU, StarPU will request an asynchronous transfer in advance, so that data is already present on the GPU when the task starts. As a result, computation and data transfers are overlapped. Note that prefetching is enabled by default in StarPU.
- **STARPU_SCHED_ALPHA** To estimate the cost of a task StarPU takes into account the estimated computation time (obtained thanks to performance models). The alpha factor is the coefficient to be applied to it before adding it to the communication part.
- **STARPU_SCHED_BETA** To estimate the cost of a task StarPU takes into account the estimated data transfer time (obtained thanks to performance models). The beta factor is the coefficient to be applied to it before adding it to the computation part.
- STARPU SCHED GAMMA Define the execution time penalty of a joule (Energy-based Scheduling).
- **STARPU_IDLE_POWER** Define the idle power of the machine (Energy-based Scheduling).
- STARPU PROFILING Enable on-line performance monitoring (Enabling On-line Performance Monitoring).

26.3 Extensions

- **SOCL_OCL_LIB_OPENCL** THE SOCL test suite is only run when the environment variable SOCL_OCL_LIB_O \leftarrow PENCL is defined. It should contain the location of the file libOpenCL.so of the OCL ICD implementation.
- OCL_ICD_VENDORS When using SOCL with OpenCL ICD (https://forge.imag.fr/projects/ocl-icd/), this variable may be used to point to the directory where ICD files are installed. The default directory is /etc/OpenCL/vendors. StarPU installs ICD files in the directory \$prefix/share/starpu/opencl/vendors.
- **STARPU_COMM_STATS** Communication statistics for starpumpi (Debugging MPI) will be enabled when the environment variable STARPU COMM STATS is defined to an value other than 0.
- **STARPU_MPI_CACHE** Communication cache for starpumpi (MPI Support) will be disabled when the environment variable STARPU_MPI_CACHE is set to 0. It is enabled by default or for any other values of the variable S← TARPU_MPI_CACHE.
- **STARPU_MPI_COMM** Communication trace for starpumpi (MPI Support) will be enabled when the environment variable STARPU_MPI_COMM is set to 1, and StarPU has been configured with the option --enable-verbose.
- **STARPU_MPI_CACHE_STATS** When set to 1, statistics are enabled for the communication cache (MPI Support). For now, it prints messages on the standard output when data are added or removed from the received communication cache.

- **STARPU_MPI_PRIORITIES** When set to 0, the use of priorities to order MPI communications is disabled (MPI Support).
- **STARPU_MPI_FAKE_SIZE** Setting to a number makes StarPU believe that there are as many MPI nodes, even if it was run on only one MPI node. This allows e.g. to simulate the execution of one of the nodes of a big cluster without actually running the rest. It of course does not provide computation results and timing.
- **STARPU_MPI_FAKE_RANK** Setting to a number makes StarPU believe that it runs the given MPI node, even if it was run on only one MPI node. This allows e.g. to simulate the execution of one of the nodes of a big cluster without actually running the rest. It of course does not provide computation results and timing.
- STARPU_MPI_DRIVER_CALL_FREQUENCY When set to a positive value, activates the interleaving of the execution of tasks with the progression of MPI communications (MPI Support). The starpu_mpi_init_conf() function must have been called by the application for that environment variable to be used. When set to 0, the MPI progression thread does not use at all the driver given by the user, and only focuses on making MPI communications progress.
- STARPU_MPI_DRIVER_TASK_FREQUENCY When set to a positive value, the interleaving of the execution of tasks with the progression of MPI communications mechanism to execute several tasks before checking communication requests again (MPI Support). The starpu_mpi_init_conf() function must have been called by the application for that environment variable to be used, and the STARPU_MPI_DRIVER_CALL_FREQUE NCY environment variable set to a positive value.
- **STARPU_SIMGRID_TRANSFER_COST** When set to 1 (which is the default), data transfers (over PCI bus, typically) are taken into account in simgrid mode.
- **STARPU_SIMGRID_CUDA_MALLOC_COST** When set to 1 (which is the default), CUDA malloc costs are taken into account in simgrid mode.
- **STARPU_SIMGRID_CUDA_QUEUE_COST** When set to 1 (which is the default), CUDA task and transfer queueing costs are taken into account in simgrid mode.
- **STARPU_PCI_FLAT** When unset or set to 0, the platform file created for simgrid will contain PCI bandwidths and routes.
- **STARPU_SIMGRID_QUEUE_MALLOC_COST** When unset or set to 1, simulate within simgrid the GPU transfer queueing.
- STARPU_MALLOC_SIMULATION_FOLD Define the size of the file used for folding virtual allocation, in MiB. The default is 1, thus allowing 64GiB virtual memory when Linux's sysctl vm.max_map_count value is the default 65535.
- **STARPU_SIMGRID_TASK_SUBMIT_COST** When set to 1 (which is the default), task submission costs are taken into account in simgrid mode. This provides more accurate simgrid predictions, especially for the beginning of the execution.
- **STARPU_SIMGRID_FETCHING_INPUT_COST** When set to 1 (which is the default), fetching input costs are taken into account in simgrid mode. This provides more accurate simgrid predictions, especially regarding data transfers.
- **STARPU_SIMGRID_SCHED_COST** When set to 1 (0 is the default), scheduling costs are taken into account in simgrid mode. This provides more accurate simgrid predictions, and allows studying scheduling overhead of the runtime system. However, it also makes simulation non-deterministic.

26.4 Miscellaneous And Debug

- **STARPU_HOME** Specify the main directory in which StarPU stores its configuration files. The default is \$HOME on Unix environments, and \$USERPROFILE on Windows environments.
- **STARPU_PATH** Only used on Windows environments. Specify the main directory in which StarPU is installed (Running a Basic StarPU Application on Microsoft Visual C)

- **STARPU_PERF_MODEL_DIR** Specify the main directory in which StarPU stores its performance model files. The default is \$STARPU_HOME/.starpu/sampling.
- **STARPU_PERF_MODEL_HOMOGENEOUS_CPU** When this is set to 0, StarPU will assume that CPU devices do not have the same performance, and thus use different performance models for them, thus making kernel calibration much longer, since measurements have to be made for each CPU core.
- **STARPU_PERF_MODEL_HOMOGENEOUS_CUDA** When this is set to 1, StarPU will assume that all CUDA devices have the same performance, and thus share performance models for them, thus allowing kernel calibration to be much faster, since measurements only have to be once for all CUDA GPUs.
- **STARPU_PERF_MODEL_HOMOGENEOUS_OPENCL** When this is set to 1, StarPU will assume that all OPE → NCL devices have the same performance, and thus share performance models for them, thus allowing kernel calibration to be much faster, since measurements only have to be once for all OPENCL GPUs.
- **STARPU_PERF_MODEL_HOMOGENEOUS_MIC** When this is set to 1, StarPU will assume that all MIC devices have the same performance, and thus share performance models for them, thus allowing kernel calibration to be much faster, since measurements only have to be once for all MIC GPUs.
- **STARPU_PERF_MODEL_HOMOGENEOUS_MPI_MS** When this is set to 1, StarPU will assume that all M← PI Slave devices have the same performance, and thus share performance models for them, thus allowing kernel calibration to be much faster, since measurements only have to be once for all MPI Slaves.
- **STARPU_HOSTNAME** When set, force the hostname to be used when dealing performance model files. Models are indexed by machine name. When running for example on a homogeneous cluster, it is possible to share the models between machines by setting export STARPU HOSTNAME=some global name.
- STARPU_OPENCL_PROGRAM_DIR Specify the directory where the OpenCL codelet source files are located. The function starpu_opencl_load_program_source() looks for the codelet in the current directory, in the directory specified by the environment variable STARPU_OPENCL_PROGRAM_DIR, in the directory share/starpu/opencl of the installation directory of StarPU, and finally in the source directory of StarPU.
- **STARPU_SILENT** Allow to disable verbose mode at runtime when StarPU has been configured with the option --enable-verbose. Also disable the display of StarPU information and warning messages.
- **STARPU_LOGFILENAME** Specify in which file the debugging output should be saved to.
- **STARPU_FXT_PREFIX** Specify in which directory to save the trace generated if FxT is enabled. It needs to have a trailing '/' character.
- **STARPU_FXT_TRACE** Specify whether to generate (1) or not (0) the FxT trace in /tmp/prof_file_XXX_YYY . The default is 1 (generate it)
- **STARPU_LIMIT_CUDA_devid_MEM** Specify the maximum number of megabytes that should be available to the application on the CUDA device with the identifier devid. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory. When defined, the variable overwrites the value of the variable STARPU_LIMIT_CUDA_MEM.
- **STARPU_LIMIT_CUDA_MEM** Specify the maximum number of megabytes that should be available to the application on each CUDA devices. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory.
- **STARPU_LIMIT_OPENCL_devid_MEM** Specify the maximum number of megabytes that should be available to the application on the OpenCL device with the identifier devid. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory. When defined, the variable overwrites the value of the variable STARPU_LIMIT_OPENCL_MEM.
- **STARPU_LIMIT_OPENCL_MEM** Specify the maximum number of megabytes that should be available to the application on each OpenCL devices. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory.
- **STARPU_LIMIT_CPU_MEM** Specify the maximum number of megabytes that should be available to the application in the main CPU memory. Setting it enables allocation cache in main memory. Setting it to zero lets StarPU overflow memory.

- **STARPU_LIMIT_CPU_NUMA_devid_MEM** Specify the maximum number of megabytes that should be available to the application on the NUMA node with the OS identifier devid.
- **STARPU_MINIMUM_AVAILABLE_MEM** Specify the minimum percentage of memory that should be available in GPUs (or in main memory, when using out of core), below which a reclaiming pass is performed. The default is 0%.
- **STARPU_TARGET_AVAILABLE_MEM** Specify the target percentage of memory that should be reached in G← PUs (or in main memory, when using out of core), when performing a periodic reclaiming pass. The default is 0%.
- **STARPU_MINIMUM_CLEAN_BUFFERS** Specify the minimum percentage of number of buffers that should be clean in GPUs (or in main memory, when using out of core), below which asynchronous writebacks will be issued. The default is 5%.
- **STARPU_TARGET_CLEAN_BUFFERS** Specify the target percentage of number of buffers that should be reached in GPUs (or in main memory, when using out of core), when performing an asynchronous write-back pass. The default is 10%.
- **STARPU_DIDUSE_BARRIER** When set to 1, StarPU will never evict a piece of data if it has not been used by at least one task. This avoids odd behaviors under high memory pressure, but can lead to deadlocks, so is to be considered experimental only.
- STARPU DISK SWAP Specify a path where StarPU can push data when the main memory is getting full.
- **STARPU_DISK_SWAP_BACKEND** Specify the backend to be used by StarPU to push data when the main memory is getting full. The default is unistd (i.e. using read/write functions), other values are stdio (i.e. using fread/fwrite), unistd_o_direct (i.e. using read/write with O_DIRECT), leveldb (i.e. using a leveldb database), and hdf5 (i.e. using HDF5 library).
- **STARPU_DISK_SWAP_SIZE** Specify the maximum size in MiB to be used by StarPU to push data when the main memory is getting full. The default is unlimited.
- STARPU_LIMIT_MAX_SUBMITTED_TASKS Allow users to control the task submission flow by specifying to StarPU a maximum number of submitted tasks allowed at a given time, i.e. when this limit is reached task submission becomes blocking until enough tasks have completed, specified by STARPU_LIMIT_MIN_SU← BMITTED_TASKS. Setting it enables allocation cache buffer reuse in main memory.
- **STARPU_LIMIT_MIN_SUBMITTED_TASKS** Allow users to control the task submission flow by specifying to StarPU a submitted task threshold to wait before unblocking task submission. This variable has to be used in conjunction with STARPU_LIMIT_MAX_SUBMITTED_TASKS which puts the task submission thread to sleep. Setting it enables allocation cache buffer reuse in main memory.
- **STARPU_TRACE_BUFFER_SIZE** Set the buffer size for recording trace events in MiB. Setting it to a big size allows to avoid pauses in the trace while it is recorded on the disk. This however also consumes memory, of course. The default value is 64.
- **STARPU_GENERATE_TRACE** When set to 1, indicate that StarPU should automatically generate a Paje trace when starpu_shutdown() is called.
- **STARPU_GENERATE_TRACE_OPTIONS** When the variable STARPU_GENERATE_TRACE is set to 1 to generate a Paje trace, this variable can be set to specify options (see starpu_fxt_tool -help).
- **STARPU_ENABLE_STATS** When defined, enable gathering various data statistics (Data Statistics).
- **STARPU_MEMORY_STATS** When set to 0, disable the display of memory statistics on data which have not been unregistered at the end of the execution (Memory Feedback).
- **STARPU_MAX_MEMORY_USE** When set to 1, display at the end of the execution the maximum memory used by StarPU for internal data structures during execution.
- **STARPU_BUS_STATS** When defined, statistics about data transfers will be displayed when calling starpu_
 shutdown() (Profiling).

- **STARPU_WORKER_STATS** When defined, statistics about the workers will be displayed when calling starpu_ shutdown() (Profiling). When combined with the environment variable STARPU_PROFILING, it displays the energy consumption (Energy-based Scheduling).
- **STARPU_STATS** When set to 0, data statistics will not be displayed at the end of the execution of an application (Data Statistics).
- **STARPU_WATCHDOG_TIMEOUT** When set to a value other than 0, allows to make StarPU print an error message whenever StarPU does not terminate any task for the given time (in μs), but lets the application continue normally. Should be used in combination with STARPU_WATCHDOG_CRASH (see Detecting Stuck Conditions).
- **STARPU_WATCHDOG_CRASH** When set to a value other than 0, trigger a crash when the watch dog is reached, thus allowing to catch the situation in gdb, etc (see Detecting Stuck Conditions)
- **STARPU_WATCHDOG_DELAY** Delay the activation of the watchdog by the given time (in μs). This can be convenient for letting the application initialize data etc. before starting to look for idle time.
- **STARPU_TASK_BREAK_ON_PUSH** When this variable contains a job id, StarPU will raise SIGTRAP when the task with that job id is being pushed to the scheduler, which will be nicely catched by debuggers (see Debugging Scheduling)
- **STARPU_TASK_BREAK_ON_SCHED** When this variable contains a job id, StarPU will raise SIGTRAP when the task with that job id is being scheduled by the scheduler (at a scheduler-specific point), which will be nicely catched by debuggers. This only works for schedulers which have such a scheduling point defined (see Debugging Scheduling)
- **STARPU_TASK_BREAK_ON_POP** When this variable contains a job id, StarPU will raise SIGTRAP when the task with that job id is being popped from the scheduler, which will be nicely catched by debuggers (see Debugging Scheduling)
- **STARPU_TASK_BREAK_ON_EXEC** When this variable contains a job id, StarPU will raise SIGTRAP when the task with that job id is being executed, which will be nicely catched by debuggers (see Debugging Scheduling)
- **STARPU_DISABLE_KERNELS** When set to a value other than 1, it disables actually calling the kernel functions, thus allowing to quickly check that the task scheme is working properly, without performing the actual application-provided computation.
- **STARPU_HISTORY_MAX_ERROR** History-based performance models will drop measurements which are really far froom the measured average. This specifies the allowed variation. The default is 50 (%), i.e. the measurement is allowed to be x1.5 faster or /1.5 slower than the average.
- **STARPU_RAND_SEED** The random scheduler and some examples use random numbers for their own working. Depending on the examples, the seed is by default juste always 0 or the current time() (unless simgrid mode is enabled, in which case it is always 0). **STARPU_RAND_SEED** allows to set the seed to a specific value.
- **STARPU_IDLE_TIME** When set to a value being a valid filename, a corresponding file will be created when shutting down StarPU. The file will contain the sum of all the workers' idle time.
- **STARPU_GLOBAL_ARBITER** When set to a positive value, StarPU will create a arbiter, which implements an advanced but centralized management of concurrent data accesses (see Concurrent Data Accesses).
- **STARPU_USE_NUMA** When defined, NUMA nodes are taking into account by StarPU. Otherwise, memory is considered as only one node. This is experimental for now.
 - When enabled, STARPU_MAIN_MEMORY is a pointer to the NUMA node associated to the first CPU worker if it exists, the NUMA node associated to the first GPU discovered otherwise. If StarPU doesn't find any NUMA node after these step, STARPU_MAIN_MEMORY is the first NUMA node discovered by StarPU.
- **STARPU_IDLE_FILE** If the environment variable STARPU_IDLE_FILE is defined, a file named after its contents will be created at the end of the execution. The file will contain the sum of the idle times of all the workers.
- **STARPU_HWLOC_INPUT** If the environment variable STARPU_HWLOC_INPUT is defined to the path of an XML file, hwloc will be made to use it as input instead of detecting the current platform topology, which can save significant initialization time.
 - To produce this XML file, use lstopo file.xml

STARPU_CATCH_SIGNALS By default, StarPU catch signals SIGINT, SIGSEGV and SIGTRAP to perform final actions such as dumping FxT trace files even though the application has crashed. Setting this variable to a value other than 1 will disable this behaviour. This should be done on JVM systems which may use these signals for their own needs. The flag can also be set through the field starpu_conf::catch_signals.

26.5 Configuring The Hypervisor

- **SC_HYPERVISOR_POLICY** Choose between the different resizing policies proposed by StarPU for the hypervisor: idle, app_driven, feft_lp, teft_lp; ispeed_lp, throughput_lp etc.
 - Use SC_HYPERVISOR_POLICY=help to get the list of available policies for the hypervisor
- SC_HYPERVISOR_TRIGGER_RESIZE Choose how should the hypervisor be triggered: speed if the resizing algorithm should be called whenever the speed of the context does not correspond to an optimal precomputed value, idle it the resizing algorithm should be called whenever the workers are idle for a period longer than the value indicated when configuring the hypervisor.
- **SC_HYPERVISOR_START_RESIZE** Indicate the moment when the resizing should be available. The value correspond to the percentage of the total time of execution of the application. The default value is the resizing frame.
- SC_HYPERVISOR_MAX_SPEED_GAP Indicate the ratio of speed difference between contexts that should trigger the hypervisor. This situation may occur only when a theoretical speed could not be computed and the hypervisor has no value to compare the speed to. Otherwise the resizing of a context is not influenced by the the speed of the other contexts, but only by the the value that a context should have.
- **SC_HYPERVISOR_STOP_PRINT** By default the values of the speed of the workers is printed during the execution of the application. If the value 1 is given to this environment variable this printing is not done.
- SC_HYPERVISOR_LAZY_RESIZE By default the hypervisor resizes the contexts in a lazy way, that is workers are firstly added to a new context before removing them from the previous one. Once this workers are clearly taken into account into the new context (a task was poped there) we remove them from the previous one. However if the application would like that the change in the distribution of workers should change right away this variable should be set to 0
- SC_HYPERVISOR_SAMPLE_CRITERIA By default the hypervisor uses a sample of flops when computing the speed of the contexts and of the workers. If this variable is set to time the hypervisor uses a sample of time (10% of an aproximation of the total execution time of the application)

| Execution Configuration Through Environment Variables |
|--|
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |

170

Chapter 27

Compilation Configuration

The behavior of the StarPU library and tools may be tuned thanks to the following configure options.

27.1 Common Configuration

- -enable-debug Enable debugging messages.
- -enable-spinlock-check Enable checking that spinlocks are taken and released properly.
- **-enable-fast** Disable assertion checks, which saves computation time.
- -enable-verbose Increase the verbosity of the debugging messages. This can be disabled at runtime by setting the environment variable STARPU_SILENT to any value. -enable-verbose=extra increase even more the verbosity.

```
$ STARPU_SILENT=1 ./vector_scal
```

- **-enable-coverage** Enable flags for the coverage tool gcov.
- -enable-quick-check Specify tests and examples should be run on a smaller data set, i.e allowing a faster execution time
- **-enable-long-check** Enable some exhaustive checks which take a really long time.
- -enable-new-check Enable new testcases which are known to fail.
- -with-hwloc Specify hwloc should be used by StarPU. hwloc should be found by the means of the tool pkg-config.
- -with-hwloc=prefix Specify hwloc should be used by StarPU. hwloc should be found in the directory specified by prefix
- -without-hwloc Specify hwloc should not be used by StarPU.
- -disable-build-doc Disable the creation of the documentation. This should be done on a machine which does not have the tools doxygen and latex (plus the packages latex-xcolor and texlive-latex-extra).
- **-disable-icc** Disable the usage of the ICC compiler. When found, some specific ICC examples are compiled.

Additionally, the script configure recognize many variables, which can be listed by typing ./configure -help. For example, ./configure $NVCCFLAGS="-arch sm_20"$ adds a flag for the compilation of CUDA kernels, and $NVCC_CC=gcc-5$ allows to change the C++ compiler used by nvcc.

27.2 Configuring Workers

- **-enable-blocking-drivers** By default, StarPU keeps CPU workers awake permanently, for better reactivity. This option makes StarPU put CPU workers to real sleep when there are not enough tasks to compute.
- **-enable-worker-callbacks** If blocking drivers are enabled, enable callbacks to notify an external resource manager about workers going to sleep and waking up.
- -enable-maxcpus=count Use at most count CPU cores. This information is then available as the macro STARPU MAXCPUS.
- -enable-maxnumanodes=count Use at most count NUMA nodes. This information is then available as the macro STARPU_MAXNUMANODES.
- -disable-cpu Disable the use of CPUs of the machine. Only GPUs etc. will be used.
- -enable-maxcudadev=count Use at most count CUDA devices. This information is then available as the macro ::STARPU_MAXCUDADEVS.
- **-disable-cuda** Disable the use of CUDA, even if a valid CUDA installation was detected.
- -with-cuda-dir=prefix Search for CUDA under prefix, which should notably contain the file include/cuda. ← h.
- -with-cuda-include-dir=dir Search for CUDA headers under dir, which should notably contain the file cuda.h. This defaults to /include appended to the value given to --with-cuda-dir.
- -with-cuda-lib-dir=dir Search for CUDA libraries under dir, which should notably contain the CUDA shared libraries—e.g., libcuda.so. This defaults to /lib appended to the value given to --with-cuda-dir.
- **-disable-cuda-memcpy-peer** Explicitly disable peer transfers when using CUDA 4.0.
- -enable-maxopencidev=count Use at most count OpenCL devices. This information is then available as the macro STARPU_MAXOPENCLDEVS.
- **-disable-opencl** Disable the use of OpenCL, even if the SDK is detected.
- -with-opencl-dir=prefix Search for an OpenCL implementation under prefix, which should notably contain include/CL/cl.h (or include/OpenCL/cl.h on Mac OS).
- -with-opencl-include-dir=dir Search for OpenCL headers under dir, which should notably contain CL/cl.h (or OpenCL/cl.h on Mac OS). This defaults to /include appended to the value given to --with-opencl-dir
- -with-opencl-lib-dir=dir Search for an OpenCL library under dir, which should notably contain the OpenCL shared libraries—e.g. libOpenCL.so. This defaults to /lib appended to the value given to --with-opencl-dir
- -enable-opencl-simulator Enable considering the provided OpenCL implementation as a simulator, i.e. use the kernel duration returned by OpenCL profiling information as wallclock time instead of the actual measured real time. This requires simgrid support.
- **-enable-maximplementations=count** Allow for at most count codelet implementations for the same target device. This information is then available as the macro STARPU MAXIMPLEMENTATIONS macro.
- -enable-max-sched-ctxs=count Allow for at most count scheduling contexts This information is then available as the macro STARPU_NMAX_SCHED_CTXS.
- -disable-asynchronous-copy Disable asynchronous copies between CPU and GPU devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- -disable-asynchronous-cuda-copy Disable asynchronous copies between CPU and CUDA devices.
- -disable-asynchronous-opencl-copy Disable asynchronous copies between CPU and OpenCL devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.

- -enable-maxmicthreads Specify the maximum number of MIC threads
- -disable-asynchronous-mic-copy Disable asynchronous copies between CPU and MIC devices.
- -disable-asynchronous-mpi-master-slave-copy Disable asynchronous copies between CPU and MPI Slave devices.
- **-enable-maxnodes=count** Use at most count memory nodes. This information is then available as the macro STARPU_MAXNODES. Reducing it allows to considerably reduce memory used by StarPU data structures.

27.3 Extension Configuration

- -disable-mpi Disable the build of libstarpumpi. By default, it is enabled when MPI is found.
- **-with-mpicc=path** Use the compiler mpicc at path, for StarPU-MPI. (MPI Support).
- -enable-mpi-pedantic-isend Before performing any MPI communication, StarPU-MPI waits for the data to be available in the main memory of the node submitting the request. For send communications, data is acquired with the mode STARPU_R. When enabling the pedantic mode, data are instead acquired with the STARP← U_RW which thus ensures that there is not more than 1 concurrent MPI_Isend calls accessing the data.
- -enable-mpi-master-slave Enable the MPI Master-Slave support. By default, it is disabled.
- -with-mpi-master-slave-multiple-thread Create one thread per MPI Slave on the MPI master to manage communications.
- -enable-mpi-verbose Increase the verbosity of the MPI debugging messages. This can be disabled at runtime by setting the environment variable STARPU_SILENT to any value. -enable-mpi-verbose=extra increase even more the verbosity.

```
$ STARPU_SILENT=1 mpirun -np 2 ./insert_task
```

- **-enable-nmad** Enable the NewMadeleine implementation for StarPU-MPI.
- -disable-fortran Disable the fortran extension. By default, it is enabled when a fortran compiler is found.
- -disable-socl Disable the SOCL extension (SOCL OpenCL Extensions). By default, it is enabled when an Open← CL implementation is found.
- -with-coi-dir Specify the directory to the COI library for MIC support. The default value is /opt/intel/mic/coi
- -mic-host Specify the precise MIC architecture host identifier. The default value is x86_64-k1om-linux

27.4 Advanced Configuration

- -enable-perf-debug Enable performance debugging through gprof.
- -enable-model-debug Enable performance model debugging.
- **-enable-fxt-lock** Enable additional trace events which describes locks behaviour. This is however extremely heavy and should only be enabled when debugging insides of StarPU.
- **-enable-maxbuffers** Define the maximum number of buffers that tasks will be able to take as parameters, then available as the macro STARPU_NMAXBUFS.
- **-enable-allocation-cache** Enable the use of a data allocation cache to avoid the cost of it with CUDA. Still experimental.
- -enable-opengl-render Enable the use of OpenGL for the rendering of some examples.

- -enable-blas-lib=prefix Specify the blas library to be used by some of the examples. Librairies available:
 - · none [default]: no BLAS library is used
 - · atlas: use ATLAS library
 - · goto: use GotoBLAS library
 - · openblas: use OpenBLAS library
 - mkl: use MKL library (you may need to set specific CFLAGS and LDFLAGS with –with-mkl-cflags and –with-mkl-ldflags)
- -enable-leveldb Enable linking with LevelDB if available
- -disable-hdf5 Disable building HDF5 support.
- -with-hdf5-include-dir=path Specify the directory where is stored the header hdf5.h.
- -with-hdf5-lib-dir=path Specify the directory where is stored the hdf5 library.
- -disable-starpufft Disable the build of libstarpufft, even if fftw or cuffT is available.
- -enable-starpufft-examples Enable the compilation and the execution of the libstarpufft examples. By default, they are neither compiled nor checked.
- -with-fxt=prefix Search for FxT under prefix. FxT (http://savannah.nongnu.org/projects/fkt) is used to generate traces of scheduling events, which can then be rendered them using ViTE (Off-line Performance Feedback). prefix should notably contain include/fxt/fxt.h.
- -with-perf-model-dir=dir Store performance models under dir, instead of the current user's home.
- -with-goto-dir=prefix Search for GotoBLAS under prefix, which should notably contain libgoto.so or libgoto2.so.
- -with-atlas-dir=prefix Search for ATLAS under prefix, which should notably contain include/cblas. ←
 h.
- -with-mkl-cflags=cflags Use cflags to compile code that uses the MKL library.
- -with-mkl-ldflags=ldflags Use ldflags when linking code that uses the MKL library. Note that the MKL website (http://software.intel.com/en-us/articles/intel-mkl-link-line-advisor/) provides a script to determine the linking flags.
- **-disable-glpk** Disable the use of libglpk for computing area bounds.
- -disable-build-tests Disable the build of tests.
- **-disable-build-examples** Disable the build of examples.
- -disable-build-tests Disable the build of tests.
- -enable-sc-hypervisor Enable the Scheduling Context Hypervisor plugin (Scheduling Context Hypervisor). By default, it is disabled.
- -enable-memory-stats Enable memory statistics (Memory Feedback).
- **-enable-simgrid** Enable simulation of execution in simgrid, to allow easy experimentation with various numbers of cores and GPUs, or amount of memory, etc. Experimental.

The path to simgrid can be specified through the SIMGRID_CFLAGS and SIMGRID_LIBS environment variables, for instance:

```
export SIMGRID_CFLAGS="-I/usr/local/simgrid/include" export SIMGRID_LIBS="-L/usr/local/simgrid/lib -lsimgrid"
```

-with-simgrid-dir Similar to the option --enable-simgrid but also allows to specify the location to the SimGrid library.

- **-with-simgrid-include-dir** Similar to the option --enable-simgrid but also allows to specify the location to the SimGrid include directory.
- **-with-simgrid-lib-dir** Similar to the option --enable-simgrid but also allows to specify the location to the SimGrid lib directory.
- -with-smpirun=path Use the smpirun at path
- **-enable-simgrid-mc** Enable the Model Checker in simulation of execution in simgrid, to allow exploring various execution paths.
- -enable-calibration-heuristic Allows to set the maximum authorized percentage of deviation for the history-based calibrator of StarPU. A correct value of this parameter must be in [0..100]. The default value of this parameter is 10. Experimental.

Chapter 28

Module Index

28.1 Modules

| lere is a list of all modules: | |
|--|----|
| FFT Support | 58 |
| Threads | 95 |
| Versioning | 81 |
| Bitmap | 05 |
| Theoretical Lower Bound on Execution Time | 19 |
| Clustering Machine | 33 |
| CUDA Extensions | 20 |
| Data Partition | 60 |
| Data Management | 16 |
| Data Interfaces | 26 |
| Out Of Core | 70 |
| Running Drivers | 81 |
| Expert Mode | 82 |
| FxT Support | 56 |
| Initialization and Termination | 82 |
| Miscellaneous Helpers | 54 |
| MIC Extensions | 53 |
| OpenCL Extensions | 23 |
| OpenMP Runtime Support | 29 |
| Performance Model | 06 |
| Profiling | 15 |
| Random Functions | ?? |
| Modularized Scheduler Interface | 18 |
| Scheduling Contexts | 83 |
| Scheduling Policy | 90 |
| Sink | ?? |
| Standard Memory Library | 89 |
| Task Bundles | 76 |
| Codelet And Tasks | 74 |
| Explicit Dependencies | 02 |
| Task Lists | 77 |
| Task Insert Utility | 96 |
| Tree | 99 |
| Toolbox | 93 |
| Workers' Properties | 07 |
| Parallel Tasks | 79 |
| MPI Support | 60 |
| Scheduling Context Hypervisor - Regular usage | |
| Scheduling Context Hypervisor - Linear Programming | |
| | 99 |

| 1 | 78 | | | Module | Index |
|---|-------------------------|---|------|--------|-------|
| | Interoperability Suppor | t | | | 434 |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |

Chapter 29

Deprecated List

Global starpu codelet::cpu func

Optional field which has been made deprecated. One should use instead the field starpu codelet::cpu funcs.

Global starpu codelet::cuda func

Optional field which has been made deprecated. One should use instead the starpu_codelet::cuda_funcs field.

Global starpu_codelet::opencl_func

Optional field which has been made deprecated. One should use instead the starpu_codelet::opencl_funcs field.

Global starpu data free pinned if possible

Equivalent to starpu_free(). This macro is provided to avoid breaking old codes.

Global starpu_data_interface_ops::handle_to_pointer)(starpu_data_handle_t handle, unsigned node)

Use starpu_data_interface_ops::to_pointer instead. Return the current pointer (if any) for the handle on the given node.

Global starpu data malloc pinned if possible

Equivalent to starpu_malloc(). This macro is provided to avoid breaking old codes.

Global starpu_mpi_initialize (void)

This function has been made deprecated. One should use instead the function starpu_mpi_init(). This function does not call MPI_Init(), it should be called beforehand.

Global starpu mpi initialize extended (int *rank, int *world size)

This function has been made deprecated. One should use instead the function starpu_mpi_init(). MPI will be initialized by starpumpi by calling MPI_Init_Thread(argc, argv, MPI_THREAD_SERIALIZED, ...).

Global STARPU MULTIPLE CPU IMPLEMENTATIONS

Setting the field starpu_codelet::cpu_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::cpu_funcs.

Global STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS

Setting the field starpu_codelet::cuda_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::cuda_funcs.

Global STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS

Setting the field starpu_codelet::opencl_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::opencl __funcs.

180 Deprecated List

Chapter 30

Module Documentation a.k.a StarPU's API

30.1 Versioning

Macros

- #define STARPU_MAJOR_VERSION
- #define STARPU MINOR VERSION
- #define STARPU_RELEASE_VERSION

Functions

void starpu get version (int *major, int *minor, int *release)

30.1.1 Detailed Description

30.1.2 Macro Definition Documentation

30.1.2.1 STARPU_MAJOR_VERSION

```
#define STARPU_MAJOR_VERSION
```

Define the major version of StarPU. This is the version used when compiling the application.

30.1.2.2 STARPU_MINOR_VERSION

```
#define STARPU_MINOR_VERSION
```

Define the minor version of StarPU. This is the version used when compiling the application.

30.1.2.3 STARPU_RELEASE_VERSION

```
#define STARPU_RELEASE_VERSION
```

Define the release version of StarPU. This is the version used when compiling the application.

30.1.3 Function Documentation

30.1.3.1 starpu_get_version()

Return as 3 integers the version of StarPU used when running the application.

30.2 Initialization and Termination

Data Structures

· struct starpu_conf

Macros

• #define STARPU_THREAD_ACTIVE

Functions

- int starpu_conf_init (struct starpu_conf *conf)
- int starpu_init (struct starpu_conf *conf) STARPU_WARN_UNUSED_RESULT
- int starpu_initialize (struct starpu_conf *user_conf, int *argc, char ***argv)
- int starpu_is_initialized (void)
- void starpu_wait_initialized (void)
- · void starpu shutdown (void)
- void starpu_pause (void)
- void starpu_resume (void)
- unsigned starpu get next bindid (unsigned flags, unsigned *preferred, unsigned npreferred)
- int starpu_bind_thread_on (int cpuid, unsigned flags, const char *name)
- void starpu_topology_print (FILE *f)
- int starpu_asynchronous_copy_disabled (void)
- int starpu_asynchronous_cuda_copy_disabled (void)
- int starpu_asynchronous_opencl_copy_disabled (void)
- int starpu_asynchronous_mic_copy_disabled (void)
- · int starpu_asynchronous_mpi_ms_copy_disabled (void)
- void starpu_display_stats (void)

30.2.1 Detailed Description

30.2.2 Data Structure Documentation

30.2.2.1 struct starpu_conf

Structure passed to the starpu_init() function to configure StarPU. It has to be initialized with starpu_conf_init(). When the default value is used, StarPU automatically selects the number of processing units and takes the default scheduling policy. The environment variables overwrite the equivalent parameters.

Data Fields

- const char * sched_policy_name
- struct starpu sched policy * sched policy
- void(* sched_policy_init)(unsigned)
- · int ncpus
- · int reserve_ncpus
- int ncuda
- int nopencl
- int nmic
- int nmpi_ms
- unsigned use_explicit_workers_bindid
- unsigned workers_bindid [STARPU_NMAXWORKERS]
- unsigned use_explicit_workers_cuda_gpuid
- unsigned workers_cuda_gpuid [STARPU_NMAXWORKERS]
- · unsigned use explicit workers opencl gpuid
- unsigned workers_opencl_gpuid [STARPU_NMAXWORKERS]

- · unsigned use_explicit_workers_mic_deviceid
- unsigned workers_mic_deviceid [STARPU_NMAXWORKERS]
- · unsigned use explicit workers mpi ms deviceid
- unsigned workers_mpi_ms_deviceid [STARPU_NMAXWORKERS]
- · int bus calibrate
- · int calibrate
- int single_combined_worker
- char * mic_sink_program_path
- · int disable asynchronous copy
- int disable_asynchronous_cuda_copy
- int disable_asynchronous_opencl_copy
- int disable_asynchronous_mic_copy
- int disable_asynchronous_mpi_ms_copy
- unsigned * cuda_opengl_interoperability
- · unsigned n cuda opengl interoperability
- struct starpu_driver * not_launched_drivers
- unsigned n_not_launched_drivers
- unsigned trace_buffer_size
- int global_sched_ctx_min_priority
- int global_sched_ctx_max_priority
- void(* callback_worker_going_to_sleep)(unsigned workerid)
- void(* callback_worker_waking_up)(unsigned workerid)
- · int catch_signals

Private Attributes

· int magic

30.2.2.1.1 Field Documentation

```
30.2.2.1.1.1 magic
```

int starpu_conf::magic [private]

Will be initialized by starpu_conf_init(). Should not be set by hand.

30.2.2.1.1.2 sched_policy_name

 $\verb|const char* starpu_conf::sched_policy_name|\\$

Name of the scheduling policy. This can also be specified with the environment variable STARPU_SCHED. (default = NULL).

30.2.2.1.1.3 sched_policy

struct starpu_sched_policy* starpu_conf::sched_policy

30.2.2.1.1.4 ncpus

int starpu_conf::ncpus

Number of CPU cores that StarPU can use. This can also be specified with the environment variable STARPU_← NCPU. (default = -1)

30.2.2.1.1.5 reserve_ncpus

int starpu_conf::reserve_ncpus

Number of CPU cores to that StarPU should leave aside. They can then be used by application threads, by calling starpu_get_next_bindid()) to get their ID, and starpu_bind_thread_on()) to bind the current thread to them.

30.2.2.1.1.6 ncuda

int starpu_conf::ncuda

Number of CUDA devices that StarPU can use. This can also be specified with the environment variable STARP ← U NCUDA. (default = -1)

30.2.2.1.1.7 nopencl

int starpu_conf::nopencl

Number of OpenCL devices that StarPU can use. This can also be specified with the environment variable STA← RPU NOPENCL. (default = -1)

30.2.2.1.1.8 nmic

int starpu conf::nmic

Number of MIC devices that StarPU can use. This can also be specified with the environment variable STARPU ← _NMIC. (default = -1)

30.2.2.1.1.9 nmpi_ms

int starpu_conf::nmpi_ms

Number of MPI Master Slave devices that StarPU can use. This can also be specified with the environment variable STARPU_NMPI_MS. (default = -1)

30.2.2.1.1.10 use_explicit_workers_bindid

unsigned starpu_conf::use_explicit_workers_bindid

If this flag is set, the starpu_conf::workers_bindid array indicates where the different workers are bound, otherwise StarPU automatically selects where to bind the different workers. This can also be specified with the environment variable STARPU WORKERS CPUID. (default = 0)

30.2.2.1.1.11 workers_bindid

unsigned starpu_conf::workers_bindid[STARPU_NMAXWORKERS]

If the starpu_conf::use_explicit_workers_bindid flag is set, this array indicates where to bind the different workers. The i-th entry of the starpu_conf::workers_bindid indicates the logical identifier of the processor which should execute the i-th worker. Note that the logical ordering of the CPUs is either determined by the OS, or provided by the hwloc library in case it is available.

30.2.2.1.1.12 use_explicit_workers_cuda_gpuid

 $\verb"unsigned starpu_conf": \verb"use_explicit_workers_cuda_gpuid"$

If this flag is set, the CUDA workers will be attached to the CUDA devices specified in the starpu_conf::workers_cuda_gpuid array. Otherwise, StarPU affects the CUDA devices in a round-robin fashion. This can also be specified with the environment variable STARPU_WORKERS_CUDAID. (default = 0)

30.2.2.1.1.13 workers_cuda_gpuid

unsigned starpu_conf::workers_cuda_gpuid[STARPU_NMAXWORKERS]

If the starpu_conf::use_explicit_workers_cuda_gpuid flag is set, this array contains the logical identifiers of the C← UDA devices (as used by cudaGetDevice ()).

30.2.2.1.1.14 use_explicit_workers_opencl_gpuid

unsigned starpu_conf::use_explicit_workers_opencl_gpuid

If this flag is set, the OpenCL workers will be attached to the OpenCL devices specified in the starpu_conf

::workers_opencl_gpuid array. Otherwise, StarPU affects the OpenCL devices in a round-robin fashion. This can also be specified with the environment variable STARPU WORKERS OPENCLID. (default = 0)

30.2.2.1.1.15 workers_opencl_gpuid

unsigned starpu_conf::workers_opencl_gpuid[STARPU_NMAXWORKERS]

If the starpu_conf::use_explicit_workers_opencl_gpuid flag is set, this array contains the logical identifiers of the OpenCL devices to be used.

30.2.2.1.1.16 use explicit workers mic deviceid

unsigned starpu_conf::use_explicit_workers_mic_deviceid

If this flag is set, the MIC workers will be attached to the MIC devices specified in the array starpu_conf::workers __mic_deviceid. Otherwise, StarPU affects the MIC devices in a round-robin fashion. This can also be specified with the environment variable STARPU_WORKERS_MICID. (default = 0)

30.2.2.1.1.17 workers mic deviceid

unsigned starpu_conf::workers_mic_deviceid[STARPU_NMAXWORKERS]

If the flag starpu_conf::use_explicit_workers_mic_deviceid is set, the array contains the logical identifiers of the MIC devices to be used.

30.2.2.1.1.18 use_explicit_workers_mpi_ms_deviceid

unsigned starpu_conf::use_explicit_workers_mpi_ms_deviceid

If this flag is set, the MPI Master Slave workers will be attached to the MPI Master Slave devices specified in the array starpu_conf::workers_mpi_ms_deviceid. Otherwise, StarPU affects the MPI Master Slave devices in a round-robin fashion. (default = 0)

30.2.2.1.1.19 workers_mpi_ms_deviceid

unsigned starpu_conf::workers_mpi_ms_deviceid[STARPU_NMAXWORKERS]

If the flag starpu_conf::use_explicit_workers_mpi_ms_deviceid is set, the array contains the logical identifiers of the MPI Master Slave devices to be used.

30.2.2.1.1.20 bus calibrate

int starpu_conf::bus_calibrate

If this flag is set, StarPU will recalibrate the bus. If this value is equal to -1, the default value is used. This can also be specified with the environment variable STARPU_BUS_CALIBRATE. (default = 0)

30.2.2.1.1.21 calibrate

int starpu conf::calibrate

If this flag is set, StarPU will calibrate the performance models when executing tasks. If this value is equal to 1, the default value is used. If the value is equal to 1, it will force continuing calibration. If the value is equal to 2, the existing performance models will be overwritten. This can also be specified with the environment variable STARPU CALIBRATE. (default = 0)

30.2.2.1.1.22 single_combined_worker

int starpu_conf::single_combined_worker

By default, StarPU executes parallel tasks concurrently. Some parallel libraries (e.g. most OpenMP implementations) however do not support concurrent calls to parallel code. In such case, setting this flag makes StarPU only start one parallel task at a time (but other CPU and GPU tasks are not affected and can be run concurrently). The parallel task scheduler will however still try varying combined worker sizes to look for the most efficient ones. This can also be specified with the environment variable STARPU_SINGLE_COMBINED_WORKER. (default = 0)

30.2.2.1.1.23 mic_sink_program_path

char* starpu_conf::mic_sink_program_path

Path to the kernel to execute on the MIC device, compiled for MIC architecture. When set to \mathtt{NULL} , StarPU automatically looks next to the host program location. (default = \mathtt{NULL})

30.2.2.1.1.24 disable_asynchronous_copy

int starpu_conf::disable_asynchronous_copy

This flag should be set to 1 to disable asynchronous copies between CPUs and all accelerators. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_COPY. This can also be specified at compilation time by giving to the configure script the option --disable-asynchronous-copy. (default = 0)

30.2.2.1.1.25 disable_asynchronous_cuda_copy

int starpu_conf::disable_asynchronous_cuda_copy

This flag should be set to 1 to disable asynchronous copies between CPUs and CUDA accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_CUDA_COPY. This can also be specified at compilation time by giving to the configure script the option --disable-asynchronous-cuda-copy. (default = 0)

30.2.2.1.1.26 disable_asynchronous_opencl_copy

int starpu_conf::disable_asynchronous_opencl_copy

This flag should be set to 1 to disable asynchronous copies between CPUs and OpenCL accelerators. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_OPENCL_COPY. This can also be specified at compilation time by giving to the configure script the option --disable-asynchronous-opencl-copy. (default = 0)

30.2.2.1.1.27 disable_asynchronous_mic_copy

```
int starpu_conf::disable_asynchronous_mic_copy
```

This flag should be set to 1 to disable asynchronous copies between CPUs and MIC accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_MIC_COPY. This can also be specified at compilation time by giving to the configure script the option --disable-asynchronous-mic-copy. (default = 0).

30.2.2.1.1.28 disable_asynchronous_mpi_ms_copy

```
int starpu_conf::disable_asynchronous_mpi_ms_copy
```

This flag should be set to 1 to disable asynchronous copies between CPUs and MPI Master Slave devices. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_MPI_MS_COPY. This can also be specified at compilation time by giving to the configure script the option --disable-asynchronous-mpi-master-slave-copy. (default = 0).

30.2.2.1.1.29 cuda_opengl_interoperability

```
unsigned* starpu_conf::cuda_opengl_interoperability
```

Enable CUDA/OpenGL interoperation on these CUDA devices. This can be set to an array of CUDA device identifiers for which <code>cudaGLSetGLDevice()</code> should be called instead of <code>cudaSetDevice()</code>. Its size is specified by the <code>starpu_conf::n_cuda_opengl_interoperability</code> field below (default = <code>NULL</code>)

30.2.2.1.1.30 n_cuda_opengl_interoperability

```
unsigned starpu_conf::n_cuda_opengl_interoperability
```

Size of the array starpu_conf::cuda_opengl_interoperability

30.2.2.1.1.31 not_launched_drivers

```
struct starpu_driver* starpu_conf::not_launched_drivers
```

Array of drivers that should not be launched by StarPU. The application will run in one of its own threads. (default = NULL)

30.2.2.1.1.32 n_not_launched_drivers

```
unsigned starpu_conf::n_not_launched_drivers
```

The number of StarPU drivers that should not be launched by StarPU, i.e number of elements of the array starpu—conf::not_launched_drivers. (default = 0)

30.2.2.1.1.33 trace buffer size

```
unsigned starpu conf::trace buffer size
```

Specify the buffer size used for FxT tracing. Starting from FxT version 0.2.12, the buffer will automatically be flushed when it fills in, but it may still be interesting to specify a bigger value to avoid any flushing (which would disturb the trace).

30.2.2.1.1.34 catch_signals

```
int starpu_conf::catch_signals
```

Specify if StarPU should catch SIGINT, SIGSEGV and SIGTRAP signals to make sure final actions (e.g dumping FxT trace files) are done even though the application has crashed. By default (value = 1), signals are catched. It should be disabled on systems which already catch these signals for their own needs (e.g JVM) This can also be specified with the environment variable STARPU_CATCH_SIGNALS

30.2.3 Macro Definition Documentation

30.2.3.1 STARPU_THREAD_ACTIVE

```
#define STARPU THREAD ACTIVE
```

Value to be passed to starpu_get_next_bindid() and starpu_bind_thread_on() when binding a thread which will significantly eat CPU time, and should thus have its own dedicated CPU.

30.2.4 Function Documentation

30.2.4.1 starpu_conf_init()

Initialize the conf structure with the default values. In case some configuration parameters are already specified through environment variables, starpu_conf_init() initializes the fields of conf according to the environment variables. For instance if STARPU_CALIBRATE is set, its value is put in the field starpu_conf::calibrate of conf. Upon successful completion, this function returns 0. Otherwise, -EINVAL indicates that the argument was NULL.

30.2.4.2 starpu_init()

StarPU initialization method, must be called prior to any other StarPU call. It is possible to specify StarPU's configuration (e.g. scheduling policy, number of cores, ...) by passing a non-NULL conf. Default configuration is used if conf is NULL. Upon successful completion, this function returns 0. Otherwise, -ENODEV indicates that no worker was available (and thus StarPU was not initialized).

30.2.4.3 starpu_initialize()

Similar to starpu_init(), but also take the argc and argv as defined by the application. Do not call starpu_init() and starpu_initialize() in the same program.

30.2.4.4 starpu_is_initialized()

Return 1 if StarPU is already initialized.

30.2.4.5 starpu_wait_initialized()

Wait for starpu_init() call to finish.

30.2.4.6 starpu_shutdown()

```
void starpu_shutdown (
```

StarPU termination method, must be called at the end of the application: statistics and other post-mortem debugging information are not guaranteed to be available until this method has been called.

30.2.4.7 starpu_pause()

```
void starpu_pause (
     void )
```

Suspend the processing of new tasks by workers. It can be used in a program where StarPU is used during only a part of the execution. Without this call, the workers continue to poll for new tasks in a tight loop, wasting CPU time. The symmetric call to starpu resume() should be used to unfreeze the workers.

30.2.4.8 starpu_resume()

```
void starpu_resume (
     void )
```

Symmetrical call to starpu_pause(), used to resume the workers polling for new tasks.

30.2.4.9 starpu_get_next_bindid()

```
unsigned starpu_get_next_bindid (
          unsigned flags,
          unsigned * preferred,
          unsigned npreferred )
```

Return a PU binding ID which can be used to bind threads with starpu_bind_thread_on(). flags can be set to STARPU_THREAD_ACTIVE or 0. When npreferred is set to non-zero, preferred is an array of size npreferred in which a preference of PU binding IDs can be set. By default StarPU will return the first PU available for binding.

30.2.4.10 starpu_bind_thread_on()

Bind the calling thread on the given <code>cpuid</code> (which should have been obtained with starpu_get_next_bindid()).

Return -1 if a thread was already bound to this PU (but binding will still have been done, and a warning will have been printed), so the caller can tell the user how to avoid the issue.

name should be set to a unique string so that different calls with the same name for the same cpuid does not produce a warning.

30.2.4.11 starpu_topology_print()

Print a description of the topology on f.

30.2.4.12 starpu_asynchronous_copy_disabled()

Return 1 if asynchronous data transfers between CPU and accelerators are disabled.

30.2.4.13 starpu_asynchronous_cuda_copy_disabled()

Return 1 if asynchronous data transfers between CPU and CUDA accelerators are disabled.

30.2.4.14 starpu_asynchronous_opencl_copy_disabled()

Return 1 if asynchronous data transfers between CPU and OpenCL accelerators are disabled.

30.2.4.15 starpu_asynchronous_mic_copy_disabled()

```
\label{local_copy_disabled} \mbox{int starpu_asynchronous_mic_copy_disabled (} \\ \mbox{void )}
```

Return 1 if asynchronous data transfers between CPU and MIC devices are disabled.

30.2.4.16 starpu_asynchronous_mpi_ms_copy_disabled()

Return 1 if asynchronous data transfers between CPU and MPI Slave devices are disabled.

30.3 Standard Memory Library

Macros

- #define STARPU MALLOC PINNED
- #define STARPU MALLOC COUNT
- #define STARPU MALLOC NORECLAIM
- #define STARPU MEMORY WAIT
- #define STARPU MEMORY OVERFLOW
- #define STARPU MALLOC SIMULATION FOLDED
- #define starpu_data_malloc_pinned_if_possible
- #define starpu_data_free_pinned_if_possible

Typedefs

- typedef int(* starpu_malloc_hook) (unsigned dst_node, void **A, size_t dim, int flags)
- typedef int(* starpu_free_hook) (unsigned dst_node, void *A, size_t dim, int flags)

Functions

- void starpu malloc set align (size t align)
- int starpu malloc (void **A, size t dim)
- int starpu free (void *A)
- int starpu_malloc_flags (void **A, size_t dim, int flags)
- int starpu_free_flags (void *A, size_t dim, int flags)
- void starpu malloc set hooks (starpu malloc hook malloc hook, starpu free hook free hook)
- int starpu memory pin (void *addr, size t size)
- int starpu_memory_unpin (void *addr, size_t size)
- starpu ssize t starpu memory get total (unsigned node)
- starpu_ssize_t starpu_memory_get_available (unsigned node)
- starpu_ssize_t starpu_memory_get_total_all_nodes (void)
- starpu_ssize_t starpu_memory_get_available_all_nodes (void)
- int starpu_memory_allocate (unsigned node, size_t size, int flags)
- void starpu_memory_deallocate (unsigned node, size_t size)
- void starpu_memory_wait_available (unsigned node, size_t size)
- void starpu_usleep (float nb_micro_sec)

30.3.1 Detailed Description

30.3.2 Macro Definition Documentation

30.3.2.1 STARPU_MALLOC_PINNED

#define STARPU_MALLOC_PINNED

Value passed to the function starpu_malloc_flags() to indicate the memory allocation should be pinned.

30.3.2.2 STARPU_MALLOC_COUNT

#define STARPU_MALLOC_COUNT

Value passed to the function starpu_malloc_flags() to indicate the memory allocation should be in the limit defined by the environment variables STARPU_LIMIT_CUDA_devid_MEM, STARPU_LIMIT_CUDA_MEM, STARPU_LI→ MIT_OPENCL_devid_MEM, STARPU_LIMIT_OPENCL_MEM and STARPU_LIMIT_CPU_MEM (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations). If no memory is available, it tries to reclaim memory from StarPU. Memory allocated this way needs to be freed by calling the function starpu_free_flags() with the same flag.

30.3.2.3 STARPU_MALLOC_NORECLAIM

```
#define STARPU_MALLOC_NORECLAIM
```

Value passed to the function starpu_malloc_flags() along STARPU_MALLOC_COUNT to indicate that while the memory allocation should be kept in the limits defined for STARPU_MALLOC_COUNT, no reclaiming should be performed by starpu_malloc_flags() itself, thus potentially overflowing the memory node a bit. StarPU will reclaim memory after next task termination, according to the STARPU_MINIMUM_AVAILABLE_MEM, STARPU_TARGE ← T_AVAILABLE_MEM, STARPU_MINIMUM_CLEAN_BUFFERS, and STARPU_TARGET_CLEAN_BUFFERS environment variables. If STARPU_MEMORY_WAIT is set, no overflowing will happen, starpu_malloc_flags() will wait for other eviction mechanisms to release enough memory.

30.3.2.4 STARPU_MEMORY_WAIT

```
#define STARPU_MEMORY_WAIT
```

Value passed to starpu_memory_allocate() to specify that the function should wait for the requested amount of memory to become available, and atomically allocate it.

30.3.2.5 STARPU_MEMORY_OVERFLOW

```
#define STARPU_MEMORY_OVERFLOW
```

Value passed to starpu_memory_allocate() to specify that the function should allocate the amount of memory, even if that means overflowing the total size of the memory node.

30.3.2.6 STARPU_MALLOC_SIMULATION_FOLDED

```
#define STARPU MALLOC SIMULATION FOLDED
```

Value passed to the function starpu_malloc_flags() to indicate that when StarPU is using simgrid, the allocation can be "folded", i.e. a memory area is allocated, but its content is actually a replicate of the same memory area, to avoid having to actually allocate that much memory . This thus allows to have a memory area that does not actually consumes memory, to which one can read from and write to normally, but get bogus values.

```
30.3.2.7 starpu_data_malloc_pinned_if_possible
```

```
#define starpu_data_malloc_pinned_if_possible
```

Deprecated Equivalent to starpu_malloc(). This macro is provided to avoid breaking old codes.

30.3.2.8 starpu_data_free_pinned_if_possible

```
#define starpu_data_free_pinned_if_possible
```

Deprecated Equivalent to starpu_free(). This macro is provided to avoid breaking old codes.

30.3.3 Function Documentation

30.3.3.1 starpu_malloc_set_align()

Set an alignment constraints for starpu_malloc() allocations. align must be a power of two. This is for instance called automatically by the OpenCL driver to specify its own alignment constraints.

30.3.3.2 starpu_malloc()

```
int starpu_malloc (
     void ** A,
     size_t dim )
```

Allocate data of the given size dim in main memory, and return the pointer to the allocated data through A. It will also try to pin it in CUDA or OpenCL, so that data transfers from this buffer can be asynchronous, and thus permit data transfer and computation overlapping. The allocated buffer must be freed thanks to the starpu_free() function.

30.3.3.3 starpu_free()

```
int starpu_free (
     void * A )
```

Free memory which has previously been allocated with starpu_malloc().

30.3.3.4 starpu_malloc_flags()

Perform a memory allocation based on the constraints defined by the given flag.

30.3.3.5 starpu_free_flags()

```
int starpu_free_flags (
     void * A,
     size_t dim,
     int flags )
```

Free memory by specifying its size. The given flags should be consistent with the ones given to starpu_malloc_\circ flags() when allocating the memory.

30.3.3.6 starpu_malloc_set_hooks()

Set allocation functions to be used by StarPU. By default, StarPU will use malloc() (or cudaHostAlloc() if CUDA GPUs are used) for all its data handle allocations. The application can specify another allocation primitive by calling this. The malloc_hook should pass the allocated pointer through the A parameter, and return 0 on success. On allocation failure, it should return -ENOMEM. The flags parameter contains STARPU_MALLOC_PINNED if the memory should be pinned by the hook for GPU transfer efficiency. The hook can use starpu_memory_pin() to achieve this. The dst_node parameter is the starpu memory node, one can convert it to an hwloc logical id with starpu_memory_nodes_numa_id_to_hwloclogid() or to an OS NUMA number with starpu_memory_nodes_numa_devid_to_id().

30.3.3.7 starpu_memory_pin()

Pin the given memory area, so that CPU-GPU transfers can be done asynchronously with DMAs. The memory must be unpinned with starpu_memory_unpin() before being freed. Return 0 on success, -1 on error.

30.3.3.8 starpu_memory_unpin()

Unpin the given memory area previously pinned with starpu_memory_pin(). Return 0 on success, -1 on error.

30.3.3.9 starpu_memory_get_total()

```
starpu_ssize_t starpu_memory_get_total (  unsigned \ node \ )
```

If a memory limit is defined on the given node (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations), return the amount of total memory on the node. Otherwise return -1.

30.3.3.10 starpu_memory_get_available()

```
\label{lem:starpu_ssize_t starpu_memory_get_available (} \\ \text{unsigned } node \ )
```

If a memory limit is defined on the given node (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations), return the amount of available memory on the node. Otherwise return -1.

30.3.3.11 starpu_memory_get_total_all_nodes()

Return the amount of total memory on all memory nodes for whose a memory limit is defined (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations).

30.3.3.12 starpu_memory_get_available_all_nodes()

Return the amount of available memory on all memory nodes for whose a memory limit is defined (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations).

30.3.3.13 starpu_memory_allocate()

```
int starpu_memory_allocate (
          unsigned node,
          size_t size,
          int flags )
```

If a memory limit is defined on the given node (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations), try to allocate some of it. This does not actually allocate memory, but only accounts for it. This can be useful when the application allocates data another way, but want StarPU to be aware of the allocation size e.g. for memory reclaiming. By default, return <code>-ENOMEM</code> if there is not enough room on the given node. <code>flags</code> can be either <code>STARPU_MEMORY_WAIT</code> or <code>STARPU_MEMORY_OVERFLOW</code> to change this.

30.3.3.14 starpu_memory_deallocate()

```
void starpu_memory_deallocate (
          unsigned node,
          size_t size )
```

If a memory limit is defined on the given node (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations), free some of it. This does not actually free memory, but only accounts for it, like starpu_memory_\circ\ allocate(). The amount does not have to be exactly the same as what was passed to starpu_memory_allocate(), only the eventual amount needs to be the same, i.e. one call to starpu_memory_allocate() can be followed by several calls to starpu_memory_deallocate() to declare the deallocation piece by piece.

30.3.3.15 starpu_memory_wait_available()

```
void starpu_memory_wait_available (
          unsigned node,
          size_t size )
```

30.4 Toolbox 193

If a memory limit is defined on the given node (see Section How to Limit Memory Used By StarPU And Cache Buffer Allocations), this will wait for <code>size</code> bytes to become available on <code>node</code>. Of course, since another thread may be allocating memory concurrently, this does not necessarily mean that this amount will be actually available, just that it was reached. To atomically wait for some amount of memory and reserve it, <code>starpu_memory_allocate()</code> should be used with the <code>STARPU_MEMORY_WAIT</code> flag.

30.4 Toolbox

The following macros allow to make GCC extensions portable, and to have a code which can be compiled with any C compiler.

Macros

- #define STARPU GNUC PREREQ(maj, min)
- #define STARPU_UNLIKELY(expr)
- #define STARPU_LIKELY(expr)
- #define STARPU ATTRIBUTE UNUSED
- #define STARPU_ATTRIBUTE_NORETURN
- #define STARPU_ATTRIBUTE_INTERNAL
- #define STARPU_ATTRIBUTE_MALLOC
- #define STARPU_ATTRIBUTE_WARN_UNUSED_RESULT
- #define STARPU_ATTRIBUTE_PURE
- #define STARPU_ATTRIBUTE_ALIGNED(size)
- #define STARPU_ATTRIBUTE_FORMAT(type, string, first)
- #define STARPU_INLINE
- #define STARPU_ATTRIBUTE_CALLOC_SIZE(num, size)
- #define STARPU_ATTRIBUTE_ALLOC_SIZE(size)
- #define STARPU_WARN_UNUSED_RESULT
- #define STARPU BACKTRACE LENGTH
- #define STARPU_DUMP_BACKTRACE()
- #define STARPU_SIMGRID_ASSERT(x)
- #define STARPU ASSERT(x)
- #define STARPU_ASSERT_ACCESSIBLE(ptr)
- #define STARPU_ASSERT_MSG(x, msg, ...)
- #define _starpu_abort()
- #define STARPU ABORT()
- #define STARPU_ABORT_MSG(msg, ...)
- #define STARPU_CHECK_RETURN_VALUE(err, message, ...)
- #define STARPU_CHECK_RETURN_VALUE_IS(err, value, message, ...)
- #define STARPU ATOMIC SOMETHING(name, expr)
- #define STARPU_ATOMIC_SOMETHINGL(name, expr)
- #define STARPU RMB()
- #define STARPU_WMB()

30.4.1 Detailed Description

The following macros allow to make GCC extensions portable, and to have a code which can be compiled with any C compiler.

30.4.2 Macro Definition Documentation

```
30.4.2.1 STARPU_GNUC_PREREQ
#define STARPU_GNUC_PREREQ(
               maj,
               min )
Return true (non-zero) if GCC version maj.min or later is being used (macro taken from glibc.)
30.4.2.2 STARPU_UNLIKELY
#define STARPU_UNLIKELY(
               expr )
When building with a GNU C Compiler, allow programmers to mark an expression as unlikely.
30.4.2.3 STARPU_LIKELY
#define STARPU_LIKELY(
When building with a GNU C Compiler, allow programmers to mark an expression as likely.
30.4.2.4 STARPU_ATTRIBUTE_UNUSED
#define STARPU_ATTRIBUTE_UNUSED
When building with a GNU C Compiler, defined to __attribute__((unused))
30.4.2.5 STARPU_ATTRIBUTE_NORETURN
#define STARPU_ATTRIBUTE_NORETURN
When building with a GNU C Compiler, defined to __attribute__((noreturn))
30.4.2.6 STARPU_ATTRIBUTE_INTERNAL
#define STARPU_ATTRIBUTE_INTERNAL
When building with a GNU C Compiler, defined to __attribute__((visibility ("internal")))
30.4.2.7 STARPU ATTRIBUTE MALLOC
#define STARPU_ATTRIBUTE_MALLOC
When building with a GNU C Compiler, defined to __attribute__((malloc))
30.4.2.8 STARPU_ATTRIBUTE_WARN_UNUSED_RESULT
#define STARPU_ATTRIBUTE_WARN_UNUSED_RESULT
When building with a GNU C Compiler, defined to __attribute__((warn_unused_result))
30.4.2.9 STARPU_ATTRIBUTE_PURE
#define STARPU_ATTRIBUTE_PURE
When building with a GNU C Compiler, defined to __attribute__((pure))
30.4.2.10 STARPU_ATTRIBUTE_ALIGNED
#define STARPU_ATTRIBUTE_ALIGNED(
               size )
When building with a GNU C Compiler, defined to __attribute __((aligned(size)))
30.4.2.11 STARPU_ASSERT
```

Unless StarPU has been configured with the option --enable-fast, this macro will abort if the expression \boldsymbol{x} is false.

#define STARPU_ASSERT(

30.5 Threads 195

30.4.2.12 STARPU_ASSERT_MSG

Unless StarPU has been configured with the option --enable-fast, this macro will abort if the expression x is false. The string msg will be displayed.

30.4.2.13 STARPU_ABORT

```
#define STARPU_ABORT( )
Abort the program.
```

30.4.2.14 STARPU_ABORT_MSG

Print the string '[starpu][abort][name of the calling function:name of the file:line in the file]' followed by the given string msg and abort the program

30.4.2.15 STARPU_CHECK_RETURN_VALUE

Abort the program (after displaying message) if err has a value which is not 0.

30.4.2.16 STARPU_CHECK_RETURN_VALUE_IS

Abort the program (after displaying message) if err is different from value.

30.4.2.17 STARPU_RMB

```
#define STARPU_RMB( )
```

This macro can be used to do a synchronization.

30.4.2.18 STARPU_WMB

```
#define STARPU_WMB( )
```

This macro can be used to do a synchronization.

30.5 Threads

This section describes the thread facilities provided by StarPU. The thread function are either implemented on top of the pthread library or the Simgrid library when the simulated performance mode is enabled (SimGrid Support).

Macros

- #define STARPU_PTHREAD_CREATE_ON(name, thread, attr, routine, arg, where)
- #define STARPU_PTHREAD_CREATE(thread, attr, routine, arg)
- #define STARPU_PTHREAD_MUTEX_INIT(mutex, attr)

- #define STARPU_PTHREAD_MUTEX_DESTROY(mutex)
- #define STARPU PTHREAD MUTEX LOCK(mutex)
- #define STARPU_PTHREAD_MUTEX_UNLOCK(mutex)
- #define STARPU_PTHREAD_KEY_CREATE(key, destr)
- #define STARPU PTHREAD KEY DELETE(key)
- #define STARPU PTHREAD SETSPECIFIC(key, ptr)
- #define STARPU PTHREAD GETSPECIFIC(key)
- #define STARPU_PTHREAD_RWLOCK_INIT(rwlock, attr)
- #define STARPU PTHREAD RWLOCK RDLOCK(rwlock)
- #define STARPU PTHREAD RWLOCK WRLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_UNLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_DESTROY(rwlock)
- #define STARPU PTHREAD COND INIT(cond, attr)
- #define STARPU_PTHREAD_COND_DESTROY(cond)
- #define STARPU PTHREAD COND SIGNAL(cond)
- #define STARPU PTHREAD COND BROADCAST(cond)
- #define STARPU_PTHREAD_COND_WAIT(cond, mutex)
- #define STARPU PTHREAD BARRIER INIT(barrier, attr, count)
- #define STARPU_PTHREAD_BARRIER_DESTROY(barrier)
- #define STARPU PTHREAD BARRIER WAIT(barrier)
- #define STARPU PTHREAD MUTEX INITIALIZER
- #define STARPU PTHREAD COND INITIALIZER

Functions

- int starpu_pthread_create (starpu_pthread_t *thread, const starpu_pthread_attr_t *attr, void *(*start_
 routine)(void *), void *arg)
- int starpu pthread join (starpu pthread t thread, void **retval)
- int starpu pthread exit (void *retval) STARPU ATTRIBUTE NORETURN
- int starpu_pthread_attr_init (starpu_pthread_attr_t *attr)
- int starpu_pthread_attr_destroy (starpu_pthread_attr_t *attr)
- int starpu_pthread_attr_setdetachstate (starpu_pthread_attr_t *attr, int detachstate)
- int starpu_pthread_mutex_init (starpu_pthread_mutex_t *mutex, const starpu_pthread_mutexattr_
 t *mutexattr)
- int starpu pthread mutex destroy (starpu pthread mutex t *mutex)
- int starpu_pthread_mutex_lock (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_unlock (starpu_pthread_mutex_t *mutex)
- int starpu pthread mutex trylock (starpu pthread mutex t *mutex)
- int starpu_pthread_mutexattr_gettype (const starpu_pthread_mutexattr_t *attr, int *type)
- int starpu_pthread_mutexattr_settype (starpu_pthread_mutexattr_t *attr, int type)
- int starpu_pthread_mutexattr_destroy (starpu_pthread_mutexattr_t *attr)
- int starpu_pthread_mutexattr_init (starpu_pthread_mutexattr_t *attr)
- int starpu_pthread_key_create (starpu_pthread_key_t *key, void(*destr_function)(void *))
- int starpu_pthread_key_delete (starpu_pthread_key_t key)
- int starpu_pthread_setspecific (starpu_pthread_key_t key, const void *pointer)
- void * starpu_pthread_getspecific (starpu_pthread_key_t key)
- int starpu pthread cond init (starpu pthread cond t *cond, starpu pthread condattr t *cond attr)
- int starpu pthread cond signal (starpu pthread cond t *cond)
- int starpu_pthread_cond_broadcast (starpu_pthread_cond_t *cond)
- int starpu pthread cond wait (starpu pthread cond t *cond, starpu pthread mutex t *mutex)
- int starpu_pthread_cond_timedwait (starpu_pthread_cond_t *cond, starpu_pthread_mutex_t *mutex, const struct timespec *abstime)
- int starpu_pthread_cond_destroy (starpu_pthread_cond_t *cond)
- int starpu pthread rwlock init (starpu pthread rwlock t *rwlock, const starpu pthread rwlockattr t *attr)
- int starpu_pthread_rwlock_destroy (starpu_pthread_rwlock_t *rwlock)

30.5 Threads 197

- int starpu_pthread_rwlock_rdlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_tryrdlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_wrlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_trywrlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_unlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_barrier_init (starpu_pthread_barrier_t *barrier, const starpu_pthread_barrierattr_t *attr, unsigned count)
- int starpu_pthread_barrier_destroy (starpu_pthread_barrier_t *barrier)
- int starpu_pthread_barrier_wait (starpu_pthread_barrier_t *barrier)
- int starpu_pthread_spin_init (starpu_pthread_spinlock_t *lock, int pshared)
- int starpu pthread spin destroy (starpu pthread spinlock t *lock)
- int starpu_pthread_spin_lock (starpu_pthread_spinlock_t *lock)
- int starpu pthread spin trylock (starpu pthread spinlock t *lock)
- int starpu_pthread_spin_unlock (starpu_pthread_spinlock_t *lock)
- void starpu_sleep (float nb_sec)

30.5.1 Detailed Description

This section describes the thread facilities provided by StarPU. The thread function are either implemented on top of the pthread library or the Simgrid library when the simulated performance mode is enabled (SimGrid Support).

30.5.2 Macro Definition Documentation

30.5.2.1 STARPU_PTHREAD_CREATE_ON

Call starpu_pthread_create_on() and abort on error.

30.5.2.2 STARPU_PTHREAD_CREATE

Call starpu_pthread_create() and abort on error.

30.5.2.3 STARPU_PTHREAD_MUTEX_INIT

Call starpu_pthread_mutex_init() and abort on error.

30.5.2.4 STARPU_PTHREAD_MUTEX_DESTROY

Call starpu_pthread_mutex_destroy() and abort on error.

```
30.5.2.5 STARPU_PTHREAD_MUTEX_LOCK
#define STARPU_PTHREAD_MUTEX_LOCK(
              mutex )
Call starpu_pthread_mutex_lock() and abort on error.
30.5.2.6 STARPU_PTHREAD_MUTEX_UNLOCK
#define STARPU_PTHREAD_MUTEX_UNLOCK(
              mutex )
Call starpu_pthread_mutex_unlock() and abort on error.
30.5.2.7 STARPU_PTHREAD_KEY_CREATE
#define STARPU_PTHREAD_KEY_CREATE(
               key,
               destr )
Call starpu_pthread_key_create() and abort on error.
30.5.2.8 STARPU_PTHREAD_KEY_DELETE
#define STARPU_PTHREAD_KEY_DELETE(
               key )
Call starpu_pthread_key_delete() and abort on error.
30.5.2.9 STARPU_PTHREAD_SETSPECIFIC
#define STARPU_PTHREAD_SETSPECIFIC(
               key,
               ptr )
Call starpu_pthread_setspecific() and abort on error.
30.5.2.10 STARPU_PTHREAD_GETSPECIFIC
#define STARPU_PTHREAD_GETSPECIFIC(
               key )
Call starpu_pthread_getspecific() and abort on error.
30.5.2.11 STARPU_PTHREAD_RWLOCK_INIT
#define STARPU_PTHREAD_RWLOCK_INIT(
              rwlock,
               attr )
Call starpu_pthread_rwlock_init() and abort on error.
30.5.2.12 STARPU_PTHREAD_RWLOCK_RDLOCK
#define STARPU_PTHREAD_RWLOCK_RDLOCK(
               rwlock )
Call starpu_pthread_rwlock_rdlock() and abort on error.
30.5.2.13 STARPU_PTHREAD_RWLOCK_WRLOCK
```

Call starpu_pthread_rwlock_wrlock() and abort on error.

30.5 Threads 199

```
30.5.2.14 STARPU_PTHREAD_RWLOCK_UNLOCK
#define STARPU_PTHREAD_RWLOCK_UNLOCK(
              rwlock )
Call starpu_pthread_rwlock_unlock() and abort on error.
30.5.2.15 STARPU_PTHREAD_RWLOCK_DESTROY
#define STARPU_PTHREAD_RWLOCK_DESTROY(
               rwlock )
Call starpu_pthread_rwlock_destroy() and abort on error.
30.5.2.16 STARPU_PTHREAD_COND_INIT
#define STARPU_PTHREAD_COND_INIT(
              cond,
Call starpu pthread cond init() and abort on error.
30.5.2.17 STARPU_PTHREAD_COND_DESTROY
#define STARPU_PTHREAD_COND_DESTROY(
              cond )
Call starpu_pthread_cond_destroy() and abort on error.
30.5.2.18 STARPU_PTHREAD_COND_SIGNAL
#define STARPU_PTHREAD_COND_SIGNAL(
               cond )
Call starpu_pthread_cond_signal() and abort on error.
30.5.2.19 STARPU_PTHREAD_COND_BROADCAST
#define STARPU_PTHREAD_COND_BROADCAST(
Call starpu_pthread_cond_broadcast() and abort on error.
30.5.2.20 STARPU_PTHREAD_COND_WAIT
#define STARPU_PTHREAD_COND_WAIT(
              cond,
Call starpu_pthread_cond_wait() and abort on error.
30.5.2.21 STARPU_PTHREAD_BARRIER_INIT
#define STARPU_PTHREAD_BARRIER_INIT(
              barrier,
               attr,
               count )
Call starpu_pthread_barrier_init() and abort on error.
30.5.2.22 STARPU_PTHREAD_BARRIER_DESTROY
#define STARPU_PTHREAD_BARRIER_DESTROY(
              barrier )
```

Call starpu_pthread_barrier_destroy() and abort on error.

30.5.2.23 STARPU_PTHREAD_BARRIER_WAIT

Call starpu_pthread_barrier_wait() and abort on error.

30.5.2.24 STARPU PTHREAD MUTEX INITIALIZER

```
STARPU_PTHREAD_MUTEX_INITIALIZER
```

Initialize the mutex given in parameter.

30.5.2.25 STARPU_PTHREAD_COND_INITIALIZER

```
STARPU_PTHREAD_COND_INITIALIZER
```

Initialize the condition variable given in parameter.

30.5.3 Function Documentation

30.5.3.1 starpu_pthread_create()

Start a new thread in the calling process. The new thread starts execution by invoking start_routine; arg is passed as the sole argument of start_routine.

30.5.3.2 starpu_pthread_join()

Wait for the thread specified by thread to terminate. If that thread has already terminated, then the function returns immediately. The thread specified by thread must be joinable.

30.5.3.3 starpu_pthread_exit()

Terminate the calling thread and return a value via retval that (if the thread is joinable) is available to another thread in the same process that calls starpu pthread join().

30.5.3.4 starpu_pthread_attr_init()

Initialize the thread attributes object pointed to by attr with default attribute values.

Do not do anything when the simulated performance mode is enabled (SimGrid Support).

30.5.3.5 starpu_pthread_attr_destroy()

Destroy a thread attributes object which is no longer required. Destroying a thread attributes object has no effect on threads that were created using that object.

Do not do anything when the simulated performance mode is enabled (SimGrid Support).

30.5 Threads 201

30.5.3.6 starpu_pthread_attr_setdetachstate()

Set the detach state attribute of the thread attributes object referred to by attr to the value specified in detachstate. The detach state attribute determines whether a thread created using the thread attributes object attr will be created in a joinable or a detached state.

Do not do anything when the simulated performance mode is enabled (SimGrid Support).

30.5.3.7 starpu_pthread_mutex_init()

Initialize the mutex object pointed to by mutex according to the mutex attributes specified in mutexattr. If mutexattr is NULL, default attributes are used instead.

30.5.3.8 starpu_pthread_mutex_destroy()

```
int starpu_pthread_mutex_destroy ( starpu\_pthread\_mutex\_t \ * \ mutex \ )
```

Destroy a mutex object, and free the resources it might hold. The mutex must be unlocked on entrance.

30.5.3.9 starpu_pthread_mutex_lock()

Lock the given mutex. If mutex is currently unlocked, it becomes locked and owned by the calling thread, and the function returns immediately. If mutex is already locked by another thread, the function suspends the calling thread until mutex is unlocked.

This function also produces trace when the configure option --enable-fxt-lock is enabled.

30.5.3.10 starpu_pthread_mutex_unlock()

Unlock the given mutex. The mutex is assumed to be locked and owned by the calling thread on entrance to starpu_pthread_mutex_unlock().

This function also produces trace when the configure option --enable-fxt-lock is enabled.

30.5.3.11 starpu_pthread_mutex_trylock()

Behave identically to starpu_pthread_mutex_lock(), except that it does not block the calling thread if the mutex is already locked by another thread (or by the calling thread in the case of a "fast" mutex). Instead, the function returns immediately with the error code EBUSY.

This function also produces trace when the configure option --enable-fxt-lock is enabled.

30.5.3.12 starpu_pthread_mutexattr_gettype()

todo

30.5.3.13 starpu_pthread_mutexattr_settype()

todo

30.5.3.14 starpu_pthread_mutexattr_destroy()

todo

30.5.3.15 starpu_pthread_mutexattr_init()

30.5.3.16 starpu_pthread_key_create()

Allocate a new TSD key. The key is stored in the location pointed to by key.

30.5.3.17 starpu_pthread_key_delete()

Deallocate a TSD key. Do not check whether non- \mathtt{NULL} values are associated with that key in the currently executing threads, nor call the destructor function associated with the key.

30.5.3.18 starpu_pthread_setspecific()

Change the value associated with key in the calling thread, storing the given pointer instead.

30.5.3.19 starpu_pthread_getspecific()

Return the value associated with key on success, and NULL on error.

30.5.3.20 starpu_pthread_cond_init()

Initialize the condition variable cond, using the condition attributes specified in $cond_attr$, or default attributes if $cond_attr$ is NULL.

30.5.3.21 starpu_pthread_cond_signal()

Restart one of the threads that are waiting on the condition variable cond. If no threads are waiting on cond, nothing happens. If several threads are waiting on cond, exactly one is restarted, but it is not specified which.

30.5 Threads 203

30.5.3.22 starpu_pthread_cond_broadcast()

Restart all the threads that are waiting on the condition variable cond. Nothing happens if no threads are waiting on cond.

30.5.3.23 starpu_pthread_cond_wait()

Atomically unlock <code>mutex</code> (as per starpu_pthread_mutex_unlock()) and wait for the condition variable <code>cond</code> to be signaled. The thread execution is suspended and does not consume any CPU time until the condition variable is signaled. The mutex must be locked by the calling thread on entrance to <code>starpu_pthread_cond_wait()</code>. Before returning to the calling thread, the function re-acquires mutex (as per <code>starpu_pthread_mutex_lock())</code>.

This function also produces trace when the configure option --enable-fxt-lock is enabled.

30.5.3.24 starpu_pthread_cond_timedwait()

Atomicall unlocks mutex and wait on cond, as starpu_pthread_cond_wait() does, but also bound the duration of the wait with abstime.

30.5.3.25 starpu_pthread_cond_destroy()

Destroy a condition variable, freeing the resources it might hold. No threads must be waiting on the condition variable on entrance to the function.

```
30.5.3.26 starpu_pthread_rwlock_init()
```

30.5.3.27 starpu_pthread_rwlock_destroy()

```
int starpu_pthread_rwlock_destroy ( starpu\_pthread\_rwlock\_t \ * \ rwlock \ )
```

$Similar\ to\ starpu_pthread_mutex_destroy().$

30.5.3.28 starpu_pthread_rwlock_rdlock()

30.5.3.29 starpu_pthread_rwlock_tryrdlock()

todo

```
30.5.3.30 starpu_pthread_rwlock_wrlock()
int starpu_pthread_rwlock_wrlock (
              starpu_pthread_rwlock_t * rwlock )
Similar to starpu_pthread_mutex_lock().
30.5.3.31 starpu_pthread_rwlock_trywrlock()
int starpu_pthread_rwlock_trywrlock (
             starpu_pthread_rwlock_t * rwlock )
todo
30.5.3.32 starpu_pthread_rwlock_unlock()
int starpu_pthread_rwlock_unlock (
              \verb|starpu_pthread_rwlock_t * rwlock||
Similar to starpu_pthread_mutex_unlock().
30.5.3.33 starpu_pthread_barrier_init()
int starpu_pthread_barrier_init (
             starpu_pthread_barrier_t * barrier,
              const starpu_pthread_barrierattr_t * attr,
              unsigned count )
todo
30.5.3.34 starpu_pthread_barrier_destroy()
int starpu_pthread_barrier_destroy (
             starpu_pthread_barrier_t * barrier )
todo
30.5.3.35 starpu_pthread_barrier_wait()
int starpu_pthread_barrier_wait (
              starpu_pthread_barrier_t * barrier )
todo
30.5.3.36 starpu_pthread_spin_init()
int starpu_pthread_spin_init (
             starpu_pthread_spinlock_t * lock,
              int pshared )
todo
30.5.3.37 starpu_pthread_spin_destroy()
int starpu_pthread_spin_destroy (
              starpu_pthread_spinlock_t * lock )
todo
30.5.3.38 starpu_pthread_spin_lock()
int starpu_pthread_spin_lock (
              starpu_pthread_spinlock_t * lock)
todo
```

30.6 Bitmap 205

Similar to calling Unix' sleep function, except that it takes a float to allow sub-second sleeping, and when StarPU is compiled in simgrid mode it does not really sleep but just makes simgrid record that the thread has taken some time to sleep.

30.6 Bitmap

This is the interface for the bitmap utilities provided by StarPU.

Functions

- struct starpu_bitmap * starpu_bitmap_create (void) STARPU_ATTRIBUTE_MALLOC
- void starpu_bitmap_destroy (struct starpu_bitmap *b)
- void starpu_bitmap_set (struct starpu_bitmap *b, int e)
- void starpu_bitmap_unset (struct starpu_bitmap *b, int e)
- void starpu_bitmap_unset_all (struct starpu_bitmap *b)
- int starpu_bitmap_get (struct starpu_bitmap *b, int e)
- void starpu bitmap unset and (struct starpu bitmap *a, struct starpu bitmap *b, struct starpu bitmap *c)
- void starpu bitmap or (struct starpu bitmap *a, struct starpu bitmap *b)
- int starpu_bitmap_and_get (struct starpu_bitmap *b1, struct starpu_bitmap *b2, int e)
- int starpu_bitmap_cardinal (struct starpu_bitmap *b)
- int starpu_bitmap_first (struct starpu_bitmap *b)
- int starpu_bitmap_last (struct starpu_bitmap *b)
- int starpu_bitmap_next (struct starpu_bitmap *b, int e)
- int starpu_bitmap_has_next (struct starpu_bitmap *b, int e)

30.6.1 Detailed Description

This is the interface for the bitmap utilities provided by StarPU.

30.6.2 Function Documentation

```
30.6.2.2 starpu_bitmap_destroy()
void starpu_bitmap_destroy (
              struct starpu_bitmap * b )
free b
30.6.2.3 starpu_bitmap_set()
void starpu_bitmap_set (
              struct starpu_bitmap * b,
              int e )
set bit e in b
30.6.2.4 starpu_bitmap_unset()
void starpu_bitmap_unset (
              struct starpu_bitmap * b,
              int e)
unset bit e in b
30.6.2.5 starpu_bitmap_unset_all()
void starpu_bitmap_unset_all (
              struct starpu\_bitmap * b )
unset all bits in b
30.6.2.6 starpu_bitmap_get()
int starpu_bitmap_get (
              struct starpu_bitmap * b,
              int e)
return true iff bit e is set in b
30.6.2.7 starpu_bitmap_unset_and()
void starpu_bitmap_unset_and (
             struct starpu_bitmap * a,
              struct starpu_bitmap * b,
              struct starpu\_bitmap * c )
Basically compute starpu_bitmap_unset_all(a); a = b & c;
30.6.2.8 starpu_bitmap_or()
void starpu_bitmap_or (
             struct starpu_bitmap * a,
              struct starpu_bitmap * b )
Basically compute a |= b
30.6.2.9 starpu_bitmap_and_get()
int starpu_bitmap_and_get (
              struct starpu_bitmap * b1,
              struct starpu_bitmap * b2,
              int e )
return 1 iff e is set in b1 AND e is set in b2
30.6.2.10 starpu_bitmap_cardinal()
int starpu_bitmap_cardinal (
              struct starpu_bitmap * b )
```

return the number of set bits in b

```
30.6.2.11 starpu_bitmap_first()
int starpu_bitmap_first (
              struct starpu_bitmap * b )
return the index of the first set bit of b, -1 if none
30.6.2.12 starpu_bitmap_last()
int starpu_bitmap_last (
               struct starpu_bitmap * b )
return the position of the last set bit of b, -1 if none
30.6.2.13 starpu_bitmap_next()
int starpu_bitmap_next (
              struct starpu_bitmap * b,
               int e)
return the position of set bit right after e in b, -1 if none
30.6.2.14 starpu_bitmap_has_next()
int starpu_bitmap_has_next (
              struct starpu_bitmap * b,
              int e )
todo
```

30.7 Workers' Properties

Data Structures

- struct starpu_sched_ctx_iterator
- struct starpu_worker_collection

Macros

- #define starpu_worker_get_id_check()
- #define STARPU_NMAXWORKERS
- #define STARPU_MAXCPUS
- #define STARPU_MAXNUMANODES
- #define STARPU MAXNODES

Enumerations

- enum starpu_node_kind {
 STARPU_UNUSED, STARPU_CPU_RAM, STARPU_CUDA_RAM, STARPU_OPENCL_RAM,
 STARPU_DISK_RAM, STARPU_MIC_RAM, STARPU_MPI_MS_RAM }
- enum starpu_worker_archtype {
 STARPU_CPU_WORKER, STARPU_CUDA_WORKER, STARPU_OPENCL_WORKER, STARPU_MIC_
 WORKER,
 STARPU_MPI_MS_WORKER, STARPU_ANY_WORKER }
- enum starpu_worker_collection_type { STARPU_WORKER_TREE, STARPU_WORKER_LIST }

Functions

- unsigned starpu worker get count (void)
- unsigned starpu cpu worker get count (void)
- unsigned starpu_cuda_worker_get_count (void)
- unsigned starpu opencl worker get count (void)
- · unsigned starpu mic worker get count (void)
- unsigned starpu mpi ms worker get count (void)
- unsigned starpu_mic_device_get_count (void)
- int starpu_worker_get_id (void)
- unsigned starpu worker get id check (const char *f, int l)
- · int starpu worker get bindid (int workerid)
- · void starpu_sched_find_all_worker_combinations (void)
- enum starpu worker archtype starpu worker get type (int id)
- int starpu worker get count by type (enum starpu worker archtype type)
- unsigned starpu_worker_get_ids_by_type (enum starpu_worker_archtype type, int *workerids, unsigned maxsize)
- int starpu_worker_get_by_type (enum starpu_worker_archtype type, int num)
- int starpu_worker_get_by_devid (enum starpu_worker_archtype type, int devid)
- void starpu worker get name (int id, char *dst, size t maxlen)
- void starpu_worker_display_names (FILE *output, enum starpu_worker_archtype type)
- int starpu_worker_get_devid (int id)
- int starpu_worker_get_mp_nodeid (int id)
- struct starpu tree * starpu workers get tree (void)
- unsigned starpu_worker_get_sched_ctx_list (int worker, unsigned **sched_ctx)
- unsigned starpu_worker_is_blocked_in_parallel (int workerid)
- unsigned starpu_worker_is_slave_somewhere (int workerid)
- char * starpu_worker_get_type_as_string (enum starpu_worker_archtype type)
- int starpu bindid get workerids (int bindid, int **workerids)
- int starpu_worker_get_devids (enum starpu_worker_archtype type, int *devids, int num)
- int starpu_worker_get_stream_workerids (unsigned devid, int *workerids, enum starpu_worker_archtype type)
- unsigned starpu_worker_get_sched_ctx_id_stream (unsigned stream_workerid)
- hwloc_cpuset_t starpu_worker_get_hwloc_cpuset (int workerid)
- · hwloc obj t starpu worker get hwloc obj (int workerid)
- int starpu_memory_node_get_devid (unsigned node)
- unsigned starpu_worker_get_local_memory_node (void)
- unsigned starpu_worker_get_memory_node (unsigned workerid)
- unsigned starpu memory nodes get count (void)
- int starpu_memory_node_get_name (unsigned node, char *name, size_t size)
- int starpu_memory_nodes_get_numa_count (void)
- int starpu_memory_nodes_numa_id_to_devid (int osid)
- int starpu memory nodes numa devid to id (unsigned id)
- enum starpu_node_kind starpu_node_get_kind (unsigned node)

Variables

- · struct starpu_worker_collection worker_list
- · struct starpu worker collection worker_tree

Scheduling operations

- int starpu_worker_sched_op_pending (void)
- void starpu worker relax on (void)
- void starpu_worker_relax_off (void)
- int starpu_worker_get_relax_state (void)
- void starpu worker lock (int workerid)
- int starpu_worker_trylock (int workerid)
- void starpu_worker_unlock (int workerid)
- void starpu_worker_lock_self (void)
- void starpu_worker_unlock_self (void)
- void starpu_worker_set_going_to_sleep_callback (void(*callback)(unsigned workerid))
- void starpu_worker_set_waking_up_callback (void(*callback)(unsigned workerid))

30.7.1 Detailed Description

30.7.2 Data Structure Documentation

30.7.2.1 struct starpu_sched_ctx_iterator

Structure needed to iterate on the collection

Data Fields

| int | cursor | The index of the current worker in the collection, needed when iterating on the collection. |
|--------|-----------------------------|---|
| void * | value | |
| void * | possible_value | |
| char | visited[STARPU_NMAXWORKERS] | |
| int | possibly_parallel | |

30.7.2.2 struct starpu_worker_collection

A scheduling context manages a collection of workers that can be memorized using different data structures. Thus, a generic structure is available in order to simplify the choice of its type. Only the list data structure is available but further data structures(like tree) implementations are foreseen.

- int * workerids
- void * collection_private
- unsigned nworkers
- void * unblocked_workers
- unsigned nunblocked_workers
- void * masters
- · unsigned nmasters
- char present [STARPU NMAXWORKERS]
- char is unblocked [STARPU NMAXWORKERS]
- char is_master [STARPU_NMAXWORKERS]
- enum starpu_worker_collection_type type
- unsigned(* has_next)(struct starpu_worker_collection *workers, struct starpu_sched_ctx_iterator *it)
- int(* get_next)(struct starpu_worker_collection *workers, struct starpu_sched_ctx_iterator *it)
- int(* add)(struct starpu_worker_collection *workers, int worker)
- int(* remove)(struct starpu_worker_collection *workers, int worker)
- void(* init)(struct starpu worker collection *workers)
- void(* deinit)(struct starpu_worker_collection *workers)

- void(* init_iterator)(struct starpu_worker_collection *workers, struct starpu_sched_ctx_iterator *it)
- void(* init_iterator_for_parallel_tasks)(struct starpu_worker_collection *workers, struct starpu_sched_
 ctx_iterator *it, struct starpu_task *task)

30.7.2.2.1 Field Documentation

```
30.7.2.2.1.1 workerids
int* starpu_worker_collection::workerids
The workerids managed by the collection
30.7.2.2.1.2 nworkers
unsigned starpu_worker_collection::nworkers
The number of workers in the collection
30.7.2.2.1.3 type
enum starpu_worker_collection_type starpu_worker_collection::type
The type of structure
30.7.2.2.1.4 has_next
unsigned(* starpu_worker_collection::has_next) (struct starpu_worker_collection *workers,
struct starpu_sched_ctx_iterator *it)
Check if there is another element in collection
30.7.2.2.1.5 get_next
int(* starpu_worker_collection::get_next) (struct starpu_worker_collection *workers, struct
starpu_sched_ctx_iterator *it)
Return the next element in the collection
30.7.2.2.1.6 add
int(* starpu_worker_collection::add) (struct starpu_worker_collection *workers, int worker)
Add a new element in the collection
30.7.2.2.1.7 remove
int(* starpu_worker_collection::remove) (struct starpu_worker_collection *workers, int worker)
Remove an element from the collection
30.7.2.2.1.8 init
void(* starpu_worker_collection::init) (struct starpu_worker_collection *workers)
Initialize the collection
30.7.2.2.1.9 deinit
void(* starpu_worker_collection::deinit) (struct starpu_worker_collection *workers)
Deinitialize the colection
30.7.2.2.1.10 init_iterator
void(* starpu_worker_collection::init_iterator) (struct starpu_worker_collection *workers,
```

30.7.3 Macro Definition Documentation

struct starpu_sched_ctx_iterator *it)

Initialize the cursor if there is one

```
30.7.3.1 starpu_worker_get_id_check
unsigned starpu_worker_get_id_check(
```

void)

Similar to starpu_worker_get_id(), but abort when called from outside a worker (i.e. when starpu_worker_get_id() would return -1).

30.7.3.2 STARPU_NMAXWORKERS

#define STARPU_NMAXWORKERS

Define the maximum number of workers managed by StarPU.

30.7.3.3 STARPU_MAXCPUS

#define STARPU_MAXCPUS

Define the maximum number of CPU workers managed by StarPU. The default value can be modified at configure by using the option --enable-maxcpus.

30.7.3.4 STARPU_MAXNUMANODES

#define STARPU_MAXNUMANODES

Define the maximum number of NUMA nodes managed by StarPU. The default value can be modified at configure by using the option --enable-maxnumanodes.

30.7.3.5 STARPU_MAXNODES

#define STARPU MAXNODES

Define the maximum number of memory nodes managed by StarPU. The default value can be modified at configure by using the option --enable-maxnodes. Reducing it allows to considerably reduce memory used by StarPU data structures.

30.7.4 Enumeration Type Documentation

30.7.4.1 starpu_worker_archtype

enum starpu_worker_archtype

Worker Architecture Type

The value 4 which was used by the driver SCC is no longer used as renumbering workers would make unusable old performance model files.

Enumerator

| STARPU_CPU_WORKER | CPU core |
|----------------------|------------------------------------|
| STARPU_CUDA_WORKER | NVIDIA CUDA device |
| STARPU_OPENCL_WORKER | OpenCL device |
| STARPU_MIC_WORKER | Intel MIC device |
| STARPU_MPI_MS_WORKER | MPI Slave device |
| STARPU_ANY_WORKER | any worker, used in the hypervisor |

30.7.4.2 starpu_worker_collection_type

enum starpu_worker_collection_type

Types of structures the worker collection can implement

Enumerator

| STARPU_WORKER_TREE | The collection is a tree |
|--------------------|----------------------------|
| STARPU_WORKER_LIST | The collection is an array |

30.7.5 Function Documentation

30.7.5.1 starpu_worker_get_count()

Return the number of workers (i.e. processing units executing StarPU tasks). The return value should be at most STARPU_NMAXWORKERS.

30.7.5.2 starpu_cpu_worker_get_count()

Return the number of CPUs controlled by StarPU. The return value should be at most STARPU_MAXCPUS.

30.7.5.3 starpu_cuda_worker_get_count()

Return the number of CUDA devices controlled by StarPU. The return value should be at most STARPU_MAXC UDADEVS.

30.7.5.4 starpu_opencl_worker_get_count()

Return the number of OpenCL devices controlled by StarPU. The return value should be at most STARPU_MAX OPENCLDEVS.

30.7.5.5 starpu_mic_worker_get_count()

Return the number of MIC workers controlled by StarPU.

30.7.5.6 starpu_mpi_ms_worker_get_count()

Return the number of MPI Master Slave workers controlled by StarPU.

30.7.5.7 starpu_mic_device_get_count()

Return the number of MIC devices controlled by StarPU. The return value should be at most STARPU_MAXMIC ← DEVS.

30.7.5.8 starpu_worker_get_id()

Return the identifier of the current worker, i.e the one associated to the calling thread. The return value is either -1 if the current context is not a StarPU worker (i.e. when called from the application outside a task or a callback), or an integer between 0 and starpu_worker_get_count() - 1.

30.7.5.9 starpu_worker_get_type()

```
enum starpu_worker_archtype starpu_worker_get_type (
    int id )
```

Return the type of processing unit associated to the worker id. The worker identifier is a value returned by the function starpu_worker_get_id()). The return value indicates the architecture of the worker: STARPU_CPU_WO RKER for a CPU core, STARPU_CUDA_WORKER for a CUDA device, and STARPU_OPENCL_WORKER for a OpenCL device. The return value for an invalid identifier is unspecified.

30.7.5.10 starpu_worker_get_count_by_type()

Return the number of workers of type. A positive (or NULL) value is returned in case of success, -EINVAL indicates that type is not valid otherwise.

30.7.5.11 starpu_worker_get_ids_by_type()

Get the list of identifiers of workers of type. Fill the array workerids with the identifiers of the workers. The argument maxsize indicates the size of the array workerids. The return value gives the number of identifiers that were put in the array. -ERANGE is returned is maxsize is lower than the number of workers with the appropriate type: in that case, the array is filled with the maxsize first elements. To avoid such overflows, the value of maxsize can be chosen by the means of the function starpu_worker_get_count_by_type(), or by passing a value greater or equal to STARPU NMAXWORKERS.

30.7.5.12 starpu_worker_get_by_type()

Return the identifier of the num -th worker that has the specified type. If there is no such worker, -1 is returned.

30.7.5.13 starpu_worker_get_by_devid()

Return the identifier of the worker that has the specified type and device id devid (which may not be the n-th, if some devices are skipped for instance). If there is no such worker, -1 is returned.

30.7.5.14 starpu_worker_get_name()

Get the name of the worker id. StarPU associates a unique human readable string to each processing unit. This function copies at most the maxlen first bytes of the unique string associated to the worker id into the dst buffer. The caller is responsible for ensuring that dst is a valid pointer to a buffer of maxlen bytes at least. Calling this function on an invalid identifier results in an unspecified behaviour.

30.7.5.15 starpu_worker_display_names()

Display on output the list (if any) of all the workers of the given type.

30.7.5.16 starpu_worker_get_devid()

Return the device id of the worker id. The worker should be identified with the value returned by the $starpu_\leftarrow worker_get_id()$ function. In the case of a CUDA worker, this device identifier is the logical device identifier exposed by CUDA (used by the function cudaGetDevice() for instance). The device identifier of a CPU worker is the logical identifier of the core on which the worker was bound; this identifier is either provided by the OS or by the library hwloc in case it is available.

30.7.5.17 starpu_worker_get_type_as_string()

Return worker type as a string.

30.7.5.18 starpu_worker_get_hwloc_cpuset()

If StarPU was compiled with hwloc support, return a duplicate of the hwloc cpuset associated with the worker workerid. The returned cpuset is obtained from a hwloc_bitmap_dup() function call. It must be freed by the caller using $hwloc_bitmap_free()$.

30.7.5.19 starpu_worker_get_hwloc_obj()

If StarPU was compiled with hwloc support, return the hwloc object corresponding to the worker workerid.

30.7.5.20 starpu_worker_get_local_memory_node()

Return the memory node associated to the current worker

30.7.5.21 starpu_worker_get_memory_node()

Return the identifier of the memory node associated to the worker identified by workerid.

30.7.5.22 starpu_memory_nodes_numa_id_to_devid()

Return the identifier of the memory node associated to the NUMA node identified by osid by the Operating System.

30.7.5.23 starpu_memory_nodes_numa_devid_to_id()

Return the Operating System identifier of the memory node whose StarPU identifier is id.

30.7.5.24 starpu_node_get_kind()

Return the type of node as defined by ::starpu_node_kind. For example, when defining a new data interface, this function should be used in the allocation function to determine on which device the memory needs to be allocated.

30.7.5.25 starpu_worker_sched_op_pending()

Return ! 0 if current worker has a scheduling operation in progress, and 0 otherwise.

30.7.5.26 starpu_worker_relax_on()

Allow other threads and workers to temporarily observe the current worker state, even though it is performing a scheduling operation. Must be called by a worker before performing a potentially blocking call such as acquiring a mutex other than its own sched_mutex. This function increases state_relax_refcnt from the current worker. No more than UINT_MAX-1 nested starpu_worker_relax_on() calls should performed on the same worker. This function is automatically called by starpu_worker_lock() to relax the caller worker state while attempting to lock the target worker.

30.7.5.27 starpu_worker_relax_off()

Must be called after a potentially blocking call is complete, to restore the relax state in place before the corresponding starpu_worker_relax_on(). Decreases state_relax_refcnt. Calls to starpu_worker_relax_on() and starpu—worker_relax_off() must be properly paired. This function is automatically called by starpu_worker_unlock() after the target worker has been unlocked.

30.7.5.28 starpu_worker_get_relax_state()

Return !0 if the current worker state_relax_refcnt!=0 and 0 otherwise.

30.7.5.29 starpu_worker_lock()

Acquire the sched mutex of workerid. If the caller is a worker, distinct from workerid, the caller worker automatically enters a relax state while acquiring the target worker lock.

30.7.5.30 starpu_worker_trylock()

Attempt to acquire the sched mutex of workerid. Returns 0 if successful, !0 if workerid sched mutex is held or the corresponding worker is not in a relax state. If the caller is a worker, distinct from workerid, the caller worker automatically enters relax state if successfully acquiring the target worker lock.

30.7.5.31 starpu_worker_unlock()

Release the previously acquired sched mutex of workerid. Restore the relax state of the caller worker if needed.

If StarPU was compiled with blocking drivers support and worker callbacks support enabled, allow to specify an external resource manager callback to be notified about workers going to sleep.

If StarPU was compiled with blocking drivers support and worker callbacks support enabled, allow to specify an external resource manager callback to be notified about workers waking-up.

30.8 Data Management

Data management facilities provided by StarPU. We show how to use existing data interfaces in Data Interfaces, but developers can design their own data interfaces if required.

Typedefs

- typedef struct _starpu_data_state * starpu_data_handle_t
- typedef struct starpu_arbiter * starpu_arbiter_t

Enumerations

```
    enum starpu_data_access_mode {
        STARPU_NONE, STARPU_R, STARPU_W, STARPU_RW,
        STARPU_SCRATCH, STARPU_REDUX, STARPU_COMMUTE, STARPU_SSEND,
        STARPU_LOCALITY, STARPU_ACCESS_MODE_MAX }
```

Functions

- void starpu data set name (starpu data handle t handle, const char *name)
- void starpu_data_set_coordinates_array (starpu_data_handle_t handle, int dimensions, int dims[])
- void starpu_data_set_coordinates (starpu_data_handle_t handle, unsigned dimensions,...)
- · void starpu data unregister (starpu data handle t handle)
- void starpu_data_unregister_no_coherency (starpu_data_handle_t handle)
- void starpu data unregister submit (starpu data handle t handle)
- void starpu_data_invalidate (starpu_data_handle_t handle)
- · void starpu data invalidate submit (starpu data handle t handle)
- void starpu_data_advise_as_important (starpu_data_handle_t handle, unsigned is_important)

30.8 Data Management 217

- starpu_arbiter_t starpu_arbiter_create (void) STARPU_ATTRIBUTE_MALLOC
- void starpu_data_assign_arbiter (starpu_data_handle_t handle, starpu_arbiter_t arbiter)
- void starpu_arbiter_destroy (starpu_arbiter_t arbiter)
- int starpu_data_request_allocation (starpu_data_handle_t handle, unsigned node)
- int starpu_data_fetch_on_node (starpu_data_handle_t handle, unsigned node, unsigned async)
- int starpu_data_prefetch_on_node (starpu_data_handle_t handle, unsigned node, unsigned async)
- int starpu_data_prefetch_on_node_prio (starpu_data_handle_t handle, unsigned node, unsigned async, int prio)
- · int starpu data idle prefetch on node (starpu data handle t handle, unsigned node, unsigned async)
- int starpu_data_idle_prefetch_on_node_prio (starpu_data_handle_t handle, unsigned node, unsigned async, int prio)
- unsigned starpu_data_is_on_node (starpu_data_handle_t handle, unsigned node)
- void starpu data wont use (starpu data handle t handle)
- void starpu_data_set_wt_mask (starpu_data_handle_t handle, uint32_t wt_mask)
- void starpu_data_set_ooc_flag (starpu_data_handle_t handle, unsigned flag)
- unsigned starpu_data_get_ooc_flag (starpu_data_handle_t handle)
- void starpu_data_query_status (starpu_data_handle_t handle, int memory_node, int *is_allocated, int *is_valid, int *is_requested)
- void starpu_data_set_reduction_methods (starpu_data_handle_t handle, struct starpu_codelet *redux_cl, struct starpu_codelet *init_cl)
- struct starpu_data_interface_ops * starpu_data_get_interface_ops (starpu_data_handle_t handle)
- unsigned starpu_data_test_if_allocated_on_node (starpu_data_handle_t handle, unsigned memory_
 node)
- void starpu_memchunk_tidy (unsigned memory node)
- void starpu_data_set_user_data (starpu_data_handle_t handle, void *user_data)
- void * starpu_data_get_user_data (starpu_data_handle_t handle)

Access registered data from the application

- int starpu_data_acquire (starpu_data_handle_t handle, enum starpu_data_access_mode mode)
- int starpu_data_acquire_on_node (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode)
- int starpu_data_acquire_cb (starpu_data_handle_t handle, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg)
- int starpu_data_acquire_on_node_cb (starpu_data_handle_t handle, int node, enum starpu_data_access
 —mode mode, void(*callback)(void *), void *arg)
- int starpu_data_acquire_cb_sequential_consistency (starpu_data_handle_t handle, enum starpu_data_
 access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency)
- int starpu_data_acquire_on_node_cb_sequential_consistency (starpu_data_handle_t handle, int node, enum starpu_data_access mode mode, void(*callback)(void *), void *arg, int sequential_consistency)
- int starpu_data_acquire_on_node_cb_sequential_consistency_quick (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency, int quick)
- int starpu_data_acquire_on_node_cb_sequential_consistency_sync_jobids (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency, int quick, long *pre_sync_jobid, long *post_sync_jobid)
- int starpu_data_acquire_try (starpu_data_handle_t handle, enum starpu_data_access_mode mode)
- int starpu_data_acquire_on_node_try (starpu_data_handle_t handle, int node, enum starpu_data_access
 —mode mode)
- void starpu_data_release (starpu_data_handle_t handle)
- void starpu_data_release_on_node (starpu_data_handle_t handle, int node)
- #define STARPU ACQUIRE NO NODE
- #define STARPU ACQUIRE NO NODE LOCK ALL
- #define STARPU_DATA_ACQUIRE_CB(handle, mode, code)

Implicit Data Dependencies

In this section, we describe how StarPU makes it possible to insert implicit task dependencies in order to enforce sequential data consistency. When this data consistency is enabled on a specific data handle, any data access will appear as sequentially consistent from the application. For instance, if the application submits two tasks that access the same piece of data in read-only mode, and then a third task that access it in write mode, dependencies will be added between the two first tasks and the third one. Implicit data dependencies are also inserted in the case of data accesses from the application.

- void starpu_data_set_sequential_consistency_flag (starpu_data_handle_t handle, unsigned flag)
- · unsigned starpu data get sequential consistency flag (starpu data handle t handle)
- unsigned starpu_data_get_default_sequential_consistency_flag (void)
- void starpu_data_set_default_sequential_consistency_flag (unsigned flag)

30.8.1 Detailed Description

Data management facilities provided by StarPU. We show how to use existing data interfaces in Data Interfaces, but developers can design their own data interfaces if required.

30.8.2 Macro Definition Documentation

30.8.2.1 STARPU_ACQUIRE_NO_NODE

```
#define STARPU_ACQUIRE_NO_NODE
```

This macro can be used to acquire data, but not require it to be available on a given node, only enforce R/W dependencies. This can for instance be used to wait for tasks which produce the data, but without requesting a fetch to the main memory.

30.8.2.2 STARPU_ACQUIRE_NO_NODE_LOCK_ALL

```
#define STARPU_ACQUIRE_NO_NODE_LOCK_ALL
```

Similar to STARPU_ACQUIRE_NO_NODE, but will lock the data on all nodes, preventing them from being evicted for instance. This is mostly useful inside StarPU only.

30.8.2.3 STARPU_DATA_ACQUIRE_CB

STARPU_DATA_ACQUIRE_CB() is the same as starpu_data_acquire_cb(), except that the code to be executed in a callback is directly provided as a macro parameter, and the data handle is automatically released after it. This permits to easily execute code which depends on the value of some registered data. This is non-blocking too and may be called from task callbacks.

30.8.3 Typedef Documentation

30.8.3.1 starpu_data_handle_t

```
typedef struct _starpu_data_state* starpu_data_handle_t
```

StarPU uses starpu_data_handle_t as an opaque handle to manage a piece of data. Once a piece of data has been registered to StarPU, it is associated to a starpu_data_handle_t which keeps track of the state of the piece of data over the entire machine, so that we can maintain data consistency and locate data replicates for instance.

30.8 Data Management 219

30.8.3.2 starpu_arbiter_t

typedef struct starpu_arbiter* starpu_arbiter_t

This is an arbiter, which implements an advanced but centralized management of concurrent data accesses, see Concurrent Data Accesses for the details.

30.8.4 Enumeration Type Documentation

30.8.4.1 starpu_data_access_mode

enum starpu_data_access_mode

Describe a StarPU data access mode

Note: when adding a flag here, update _starpu_detect_implicit_data_deps_with_handle

Note: other STARPU_* values in include/starpu_task_util.h

Enumerator

| STARPU_NONE | todo |
|------------------------|---|
| STARPU_R | read-only mode |
| STARPU_W | write-only mode |
| STARPU_RW | read-write mode. Equivalent to STARPU_R STARPU_W |
| STARPU_SCRATCH | A temporary buffer is allocated for the task, but StarPU does not enforce data consistency—i.e. each device has its own buffer, independently from each other (even for CPUs), and no data transfer is ever performed. This is useful for temporary variables to avoid allocating/freeing buffers inside each task. Currently, no behavior is defined concerning the relation with the STARPU_R and STARPU_W modes and the value provided at registration — i.e., the value of the scratch buffer is undefined at entry of the codelet function. It is being considered for future extensions at least to define the initial value. For now, data to be used in STARPU_SCRATCH mode should be registered with node -1 and a NULL pointer, since the value of the provided buffer is simply ignored for now. |
| STARPU_REDUX | todo |
| STARPU_COMMUTE | STARPU_COMMUTE can be passed along STARPU_W or STARPU_RW to express that StarPU can let tasks commute, which is useful e.g. when bringing a contribution into some data, which can be done in any order (but still require sequential consistency against reads or non-commutative writes). |
| STARPU_SSEND | used in starpu_mpi_insert_task() to specify the data has to be sent using a synchronous and non-blocking mode (see starpu_mpi_issend()) |
| STARPU_LOCALITY | used to tell the scheduler which data is the most important for the task, and should thus be used to try to group tasks on the same core or cache, etc. For now only the ws and lws schedulers take this flag into account, and only when rebuild with USE_LOCALITY flag defined in the src/sched_policies/work_stealing_policy.c source code. |
| STARPU_ACCESS_MODE_MAX | todo |

30.8.5 Function Documentation

30.8.5.1 starpu_data_set_name()

Set the name of the data, to be shown in various profiling tools.

30.8.5.2 starpu_data_set_coordinates_array()

Set the coordinates of the data, to be shown in various profiling tools. dimensions is the size of the dims array. This can be for instance the tile coordinates within a big matrix.

30.8.5.3 starpu_data_set_coordinates()

Set the coordinates of the data, to be shown in various profiling tools. dimensions is the number of subsequent int parameters. This can be for instance the tile coordinates within a big matrix.

30.8.5.4 starpu_data_unregister()

Unregister a data handle from StarPU. If the data was automatically allocated by StarPU because the home node was -1, all automatically allocated buffers are freed. Otherwise, a valid copy of the data is put back into the home node in the buffer that was initially registered. Using a data handle that has been unregistered from StarPU results in an undefined behaviour. In case we do not need to update the value of the data in the home node, we can use the function starpu_data_unregister_no_coherency() instead.

30.8.5.5 starpu_data_unregister_no_coherency()

Similar to starpu_data_unregister(), except that StarPU does not put back a valid copy into the home node, in the buffer that was initially registered.

30.8.5.6 starpu_data_unregister_submit()

Destroy the data handle once it is no longer needed by any submitted task. No coherency is assumed.

30.8.5.7 starpu_data_invalidate()

Destroy all replicates of the data handle immediately. After data invalidation, the first access to handle must be performed in STARPU W mode. Accessing an invalidated data in STARPU R mode results in undefined behaviour.

30.8.5.8 starpu_data_invalidate_submit()

30.8 Data Management 221

Submit invalidation of the data handle after completion of previously submitted tasks.

30.8.5.9 starpu_data_advise_as_important()

Specify that the data handle can be discarded without impacting the application.

30.8.5.10 starpu_data_acquire()

The application must call this function prior to accessing registered data from main memory outside tasks. StarPU ensures that the application will get an up-to-date copy of handle in main memory located where the data was originally registered, and that all concurrent accesses (e.g. from tasks) will be consistent with the access mode specified with mode. starpu_data_release() must be called once the application no longer needs to access the piece of data. Note that implicit data dependencies are also enforced by starpu_data_acquire(), i.e. starpu_data_acquire() will wait for all tasks scheduled to work on the data, unless they have been disabled explictly by calling starpu_data_set_default_sequential_consistency_flag() or starpu_data_set_sequential_consistency_flag(). starpu_data_acquire() is a blocking call, so that it cannot be called from tasks or from their callbacks (in that case, starpu_data_acquire() returns -EDEADLK). Upon successful completion, this function returns 0.

30.8.5.11 starpu_data_acquire_on_node()

Similar to starpu_data_acquire(), except that the data will be available on the given memory node instead of main memory. STARPU_ACQUIRE_NO_NODE and STARPU_ACQUIRE_NO_NODE_LOCK_ALL can be used instead of an explicit node number.

30.8.5.12 starpu_data_acquire_cb()

Asynchronous equivalent of starpu_data_acquire(). When the data specified in handle is available in the access mode, the callback function is executed. The application may access the requested data during the execution of callback. The callback function must call starpu_data_release() once the application no longer needs to access the piece of data. Note that implicit data dependencies are also enforced by starpu_data_acquire_cb() in case they are not disabled. Contrary to starpu_data_acquire(), this function is non-blocking and may be called from task callbacks. Upon successful completion, this function returns 0.

30.8.5.13 starpu_data_acquire_on_node_cb()

Similar to starpu_data_acquire_cb(), except that the data will be available on the given memory node instead of main memory. STARPU_ACQUIRE_NO_NODE and STARPU_ACQUIRE_NO_NODE_LOCK_ALL can be used instead of an explicit node number.

30.8.5.14 starpu_data_acquire_cb_sequential_consistency()

Similar to starpu_data_acquire_cb() with the possibility of enabling or disabling data dependencies. When the data specified in handle is available in the access mode, the callback function is executed. The application may access the requested data during the execution of this callback. The callback function must call starpu_data_release() once the application no longer needs to access the piece of data. Note that implicit data dependencies are also enforced by starpu_data_acquire_cb_sequential_consistency() in case they are not disabled specifically for the given handle or by the parameter sequential_consistency. Similarly to starpu_data—acquire_cb(), this function is non-blocking and may be called from task callbacks. Upon successful completion, this function returns 0.

30.8.5.15 starpu_data_acquire_on_node_cb_sequential_consistency()

Similar to starpu_data_acquire_cb_sequential_consistency(), except that the data will be available on the given memory node instead of main memory. STARPU_ACQUIRE_NO_NODE and STARPU_ACQUIRE_NO_NODE LOCK ALL can be used instead of an explicit node number.

30.8.5.16 starpu data acquire on node cb sequential consistency sync jobids()

Similar to starpu_data_acquire_on_node_cb_sequential_consistency(), except that the *pre_sync_jobid* and *post*— _sync_jobid parameters can be used to retrieve the jobid of the synchronization tasks. *pre_sync_jobid* happens just before the acquisition, and *post_sync_jobid* happens just after the release.

30.8.5.17 starpu_data_acquire_try()

The application can call this function instead of starpu_data_acquire() so as to acquire the data like starpu_data_← acquire(), but only if all previously-submitted tasks have completed, in which case starpu_data_acquire_try() returns 0. StarPU will have ensured that the application will get an up-to-date copy of handle in main memory located where the data was originally registered. starpu_data_release() must be called once the application no longer needs to access the piece of data.

30.8 Data Management 223

30.8.5.18 starpu_data_acquire_on_node_try()

Similar to starpu_data_acquire_try(), except that the data will be available on the given memory node instead of main memory. STARPU_ACQUIRE_NO_NODE and STARPU_ACQUIRE_NO_NODE_LOCK_ALL can be used instead of an explicit node number.

```
30.8.5.19 starpu_data_release()
```

Release the piece of data acquired by the application either by starpu_data_acquire() or by starpu_data_acquire
_cb().

30.8.5.20 starpu_data_release_on_node()

Similar to starpu_data_release(), except that the data will be available on the given memory node instead of main memory. The node parameter must be exactly the same as the corresponding starpu_data_acquire_onc_node* call.

30.8.5.21 starpu_arbiter_create()

Create a data access arbiter, see Concurrent Data Accesses for the details

30.8.5.22 starpu_data_assign_arbiter()

Make access to handle managed by arbiter

30.8.5.23 starpu_arbiter_destroy()

Destroy the arbiter. This must only be called after all data assigned to it have been unregistered.

30.8.5.24 starpu_data_request_allocation()

Explicitly ask StarPU to allocate room for a piece of data on the specified memory node.

30.8.5.25 starpu_data_fetch_on_node()

Issue a fetch request for the data handle to node, i.e. requests that the data be replicated to the given node as soon as possible, so that it is available there for tasks. If async is 0, the call will block until the transfer is

achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

30.8.5.26 starpu_data_prefetch_on_node()

Issue a prefetch request for the data handle to node, i.e. requests that the data be replicated to node when there is room for it, so that it is available there for tasks. If async is 0, the call will block until the transfer is achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

30.8.5.27 starpu_data_idle_prefetch_on_node()

Issue an idle prefetch request for the data handle to node, i.e. requests that the data be replicated to node, so that it is available there for tasks, but only when the bus is really idle. If async is 0, the call will block until the transfer is achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

30.8.5.28 starpu_data_is_on_node()

Check whether a valid copy of handle is currently available on memory node node.

30.8.5.29 starpu_data_wont_use()

Advise StarPU that handle will not be used in the close future, and is thus a good candidate for eviction from GPUs. StarPU will thus write its value back to its home node when the bus is idle, and select this data in priority for eviction when memory gets low.

30.8.5.30 starpu_data_set_wt_mask()

Set the write-through mask of the data handle (and its children), i.e. a bitmask of nodes where the data should be always replicated after modification. It also prevents the data from being evicted from these nodes when memory gets scarse. When the data is modified, it is automatically transferred into those memory nodes. For instance a 1<<0 write-through mask means that the CUDA workers will commit their changes in main memory (node 0).

30.8.5.31 starpu_data_set_sequential_consistency_flag()

Set the data consistency mode associated to a data handle. The consistency mode set using this function has the priority over the default mode which can be set with starpu_data_set_default_sequential_consistency_flag().

30.8 Data Management 225

30.8.5.32 starpu_data_get_sequential_consistency_flag()

Get the data consistency mode associated to the data handle handle

30.8.5.33 starpu_data_get_default_sequential_consistency_flag()

Return the default sequential consistency flag

30.8.5.34 starpu_data_set_default_sequential_consistency_flag()

Set the default sequential consistency flag. If a non-zero value is passed, a sequential data consistency will be enforced for all handles registered after this function call, otherwise it is disabled. By default, StarPU enables sequential data consistency. It is also possible to select the data consistency mode of a specific data handle with the function starpu_data_set_sequential_consistency_flag().

30.8.5.35 starpu_data_set_ooc_flag()

Set whether this data should be elligible to be evicted to disk storage (1) or not (0). The default is 1.

30.8.5.36 starpu_data_get_ooc_flag()

Get whether this data was set to be elligible to be evicted to disk storage (1) or not (0).

30.8.5.37 starpu_data_query_status()

Query the status of handle on the specified memory_node.

30.8.5.38 starpu_data_set_reduction_methods()

Set the codelets to be used for handle when it is accessed in the mode STARPU_REDUX. Per-worker buffers will be initialized with the codelet init_cl, and reduction between per-worker buffers will be done with the codelet redux_cl.

30.8.5.39 starpu_data_set_user_data()

Set the field user_data for the handle to user_data. It can then be retrieved with starpu_data_get_user data(). user_data can be any application-defined value, for instance a pointer to an object-oriented container for the data.

30.8.5.40 starpu_data_get_user_data()

Retrieve the field user_data previously set for the handle.

30.9 Data Interfaces

Data management is done at a high-level in StarPU: rather than accessing a mere list of contiguous buffers, the tasks may manipulate data that are described by a high-level construct which we call data interface.

Data Structures

- · struct starpu_data_copy_methods
- · struct starpu data interface ops
- · struct starpu matrix interface
- · struct starpu coo interface
- struct starpu_block_interface
- struct starpu_vector_interface
- · struct starpu variable interface
- struct starpu_csr_interface
- struct starpu bcsr interface
- struct starpu_multiformat_data_interface_ops
- · struct starpu_multiformat_interface

Enumerations

enum starpu_data_interface_id {
 STARPU_UNKNOWN_INTERFACE_ID, STARPU_MATRIX_INTERFACE_ID, STARPU_BLOCK_INTER
 FACE_ID, STARPU_VECTOR_INTERFACE_ID,
 STARPU_CSR_INTERFACE_ID, STARPU_BCSR_INTERFACE_ID, STARPU_VARIABLE_INTERFACE
 _ ID, STARPU_VOID_INTERFACE_ID,
 STARPU_MULTIFORMAT_INTERFACE_ID, STARPU_COO_INTERFACE_ID, STARPU_MAX_INTERF
 ACE_ID }

Basic API

- void starpu_data_register (starpu_data_handle_t *handleptr, int home_node, void *data_interface, struct starpu_data_interface ops *ops)
- · void starpu data ptr register (starpu data handle t handle, unsigned node)
- void starpu_data_register_same (starpu_data_handle_t *handledst, starpu_data_handle_t handlesrc)
- void * starpu_data_handle_to_pointer (starpu_data_handle_t handle, unsigned node)
- int starpu_data_pointer_is_inside (starpu_data_handle_t handle, unsigned node, void *ptr)
- void * starpu_data_get_local_ptr (starpu_data_handle_t handle)
- void * starpu_data_get_interface_on_node (starpu_data_handle_t handle, unsigned memory_node)
- enum starpu_data_interface_id starpu_data_get_interface_id (starpu_data_handle_t handle)
- int starpu_data_pack (starpu_data_handle_t handle, void **ptr, starpu_ssize_t *count)
- int starpu_data_unpack (starpu_data_handle_t handle, void *ptr, size_t count)
- size t starpu data get size (starpu data handle t handle)
- size_t starpu_data_get_alloc_size (starpu_data_handle_t handle)
- starpu_data_handle_t starpu_data_lookup (const void *ptr)
- int starpu_data_get_home_node (starpu_data_handle_t handle)

- int starpu_data_interface_get_next_id (void)
- int starpu_interface_copy (uintptr_t src, size_t src_offset, unsigned src_node, uintptr_t dst, size_t dst_offset, unsigned dst_node, size_t size, void *async_data)
- void starpu_interface_start_driver_copy_async (unsigned src_node, unsigned dst_node, double *start)
- void starpu_interface_end_driver_copy_async (unsigned src_node, unsigned dst_node, double start)
- void starpu_interface_data_copy (unsigned src_node, unsigned dst_node, size_t size)
- uintptr t starpu malloc on node flags (unsigned dst node, size t size, int flags)
- uintptr_t starpu_malloc_on_node (unsigned dst_node, size_t size)
- void starpu free on node flags (unsigned dst node, uintptr t addr, size t size, int flags)
- void starpu free on node (unsigned dst node, uintptr t addr, size t size)
- void starpu_malloc_on_node_set_default_flags (unsigned node, int flags)

Accessing Matrix Data Interfaces

- · struct starpu data interface ops starpu interface matrix ops
- void starpu_matrix_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ld, uint32_t nx, uint32_t ny, size_t elemsize)
- void starpu_matrix_data_register_allocsize (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ld, uint32_t nx, uint32_t ny, size_t elemsize, size_t allocsize)
- uint32_t starpu_matrix_get_nx (starpu_data_handle_t handle)
- uint32_t starpu_matrix_get_ny (starpu_data_handle_t handle)
- uint32 t starpu matrix get local ld (starpu data handle t handle)
- uintptr_t starpu_matrix_get_local_ptr (starpu_data_handle_t handle)
- size t starpu matrix get elemsize (starpu data handle t handle)
- size_t starpu_matrix_get_allocsize (starpu_data_handle_t handle)
- #define STARPU_MATRIX_GET_PTR(interface)
- #define STARPU MATRIX GET DEV HANDLE(interface)
- #define STARPU_MATRIX_GET_OFFSET(interface)
- #define STARPU_MATRIX_GET_NX(interface)
- #define STARPU_MATRIX_GET_NY(interface)
- #define STARPU_MATRIX_GET_LD(interface)
- #define STARPU_MATRIX_GET_ELEMSIZE(interface)
- #define STARPU_MATRIX_GET_ALLOCSIZE(interface)
- #define STARPU_MATRIX_SET_NX(interface, newnx)
- #define STARPU_MATRIX_SET_NY(interface, newny)
- #define STARPU_MATRIX_SET_LD(interface, newld)

Accessing COO Data Interfaces

- · struct starpu data interface ops starpu interface coo ops
- void starpu_coo_data_register (starpu_data_handle_t *handleptr, int home_node, uint32_t nx, uint32_t ny, uint32_t n_values, uint32_t *columns, uint32_t *rows, uintptr_t values, size_t elemsize)
- #define STARPU_COO_GET_COLUMNS(interface)
- #define STARPU_COO_GET_COLUMNS_DEV_HANDLE(interface)
- #define STARPU_COO_GET_ROWS(interface)
- #define STARPU_COO_GET_ROWS_DEV_HANDLE(interface)
- #define STARPU_COO_GET_VALUES(interface)
- #define STARPU_COO_GET_VALUES_DEV_HANDLE(interface)
- #define STARPU COO GET OFFSET
- #define STARPU_COO_GET_NX(interface)
- #define STARPU COO GET NY(interface)
- #define STARPU COO GET NVALUES(interface)
- #define STARPU_COO_GET_ELEMSIZE(interface)

Block Data Interface

- struct starpu_data_interface_ops starpu_interface_block_ops
- void starpu_block_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ldy, uint32_t ldz, uint32_t nx, uint32_t nx, uint32_t nz, size_t elemsize)
- uint32_t starpu_block_get_nx (starpu_data_handle_t handle)
- uint32_t starpu_block_get_ny (starpu_data_handle_t handle)
- uint32 t starpu block get nz (starpu data handle t handle)
- uint32 t starpu block get local ldy (starpu data handle t handle)
- uint32 t starpu block get local ldz (starpu data handle t handle)
- uintptr t starpu block get local ptr (starpu data handle t handle)
- size t starpu block get elemsize (starpu data handle t handle)
- #define STARPU_BLOCK_GET_PTR(interface)
- #define STARPU_BLOCK_GET_DEV_HANDLE(interface)
- #define STARPU_BLOCK_GET_OFFSET(interface)
- #define STARPU BLOCK GET NX(interface)
- #define STARPU BLOCK GET NY(interface)
- #define STARPU BLOCK GET NZ(interface)
- #define STARPU BLOCK GET LDY(interface)
- #define STARPU_BLOCK_GET_LDZ(interface)
- #define STARPU BLOCK GET ELEMSIZE(interface)

Vector Data Interface

- struct starpu data interface ops starpu interface vector ops
- void starpu_vector_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t nx, size t elemsize)
- void starpu_vector_data_register_allocsize (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32 t nx, size t elemsize, size t allocsize)
- uint32 t starpu vector get nx (starpu data handle t handle)
- size_t starpu_vector_get_elemsize (starpu_data_handle_t handle)
- size_t starpu_vector_get_allocsize (starpu_data_handle_t handle)
- uintptr_t starpu_vector_get_local_ptr (starpu_data_handle_t handle)
- #define STARPU VECTOR GET PTR(interface)
- #define STARPU VECTOR GET DEV HANDLE(interface)
- #define STARPU_VECTOR_GET_OFFSET(interface)
- #define STARPU_VECTOR_GET_NX(interface)
- #define STARPU_VECTOR_GET_ELEMSIZE(interface)
- #define STARPU_VECTOR_GET_ALLOCSIZE(interface)
- #define STARPU_VECTOR_GET_SLICE_BASE(interface)
- #define STARPU_VECTOR_SET_NX(interface, newnx)

Variable Data Interface

- · struct starpu data interface ops starpu interface variable ops
- void starpu_variable_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, size_t size)
- void starpu_variable_ptr_register (starpu_data_handle_t handle, unsigned node, uintptr_t ptr, uintptr_t dev
 —handle, size_t offset)
- size_t starpu_variable_get_elemsize (starpu_data_handle_t handle)
- uintptr_t starpu_variable_get_local_ptr (starpu_data_handle_t handle)
- #define STARPU_VARIABLE_GET_PTR(interface)
- #define STARPU VARIABLE GET OFFSET(interface)
- #define STARPU_VARIABLE_GET_ELEMSIZE(interface)
- #define STARPU VARIABLE GET DEV HANDLE(interface)

Void Data Interface

- · struct starpu data interface ops starpu interface void ops
- void starpu_void_data_register (starpu_data_handle_t *handle)

CSR Data Interface

- · struct starpu data interface ops starpu interface csr ops
- void starpu_csr_data_register (starpu_data_handle_t *handle, int home_node, uint32_t nnz, uint32_t nrow, uintptr_t nzval, uint32_t *colind, uint32_t *rowptr, uint32_t firstentry, size_t elemsize)
- uint32 t starpu csr get nnz (starpu data handle t handle)
- uint32 t starpu csr get nrow (starpu data handle t handle)
- uint32 t starpu csr get firstentry (starpu data handle t handle)
- · uintptr t starpu csr get local nzval (starpu data handle t handle)
- uint32 t * starpu csr get local colind (starpu data handle t handle)
- uint32_t * starpu_csr_get_local_rowptr (starpu_data_handle_t handle)
- size_t starpu_csr_get_elemsize (starpu_data_handle_t handle)
- #define STARPU CSR GET NNZ(interface)
- #define STARPU_CSR_GET_NROW(interface)
- #define STARPU_CSR_GET_NZVAL(interface)
- #define STARPU CSR GET NZVAL DEV HANDLE(interface)
- #define STARPU CSR GET COLIND(interface)
- #define STARPU_CSR_GET_COLIND_DEV_HANDLE(interface)
- #define STARPU CSR GET ROWPTR(interface)
- #define STARPU CSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU CSR GET OFFSET
- #define STARPU_CSR_GET_FIRSTENTRY(interface)
- #define STARPU_CSR_GET_ELEMSIZE(interface)

BCSR Data Interface

- struct starpu_data_interface_ops starpu_interface_bcsr_ops
- void starpu_bcsr_data_register (starpu_data_handle_t *handle, int home_node, uint32_t nnz, uint32_t nrow, uintptr_t nzval, uint32_t *colind, uint32_t *rowptr, uint32_t firstentry, uint32_t r, uint32_t c, size_t elemsize)
- uint32_t starpu_bcsr_get_nnz (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_nrow (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_firstentry (starpu_data_handle_t handle)
- uintptr_t starpu_bcsr_get_local_nzval (starpu_data_handle_t handle)
- uint32_t * starpu_bcsr_get_local_colind (starpu_data_handle_t handle)
- uint32_t * starpu_bcsr_get_local_rowptr (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_r (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_c (starpu_data_handle_t handle)
- size_t starpu_bcsr_get_elemsize (starpu_data_handle_t handle)
- #define STARPU BCSR GET NNZ(interface)
- #define STARPU_BCSR_GET_NZVAL(interface)
- #define STARPU BCSR GET NZVAL DEV HANDLE(interface)
- #define STARPU_BCSR_GET_COLIND(interface)
- #define STARPU_BCSR_GET_COLIND_DEV_HANDLE(interface)
- #define STARPU_BCSR_GET_ROWPTR(interface)
- #define STARPU BCSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU_BCSR_GET_OFFSET

Multiformat Data Interface

- void starpu_multiformat_data_register (starpu_data_handle_t *handle, int home_node, void *ptr, uint32_t nobjects, struct starpu_multiformat_data_interface_ops *format_ops)
- #define STARPU_MULTIFORMAT_GET_CPU_PTR(interface)
- #define STARPU_MULTIFORMAT_GET_CUDA_PTR(interface)
- #define STARPU_MULTIFORMAT_GET_OPENCL_PTR(interface)
- #define STARPU MULTIFORMAT GET MIC PTR(interface)
- #define STARPU MULTIFORMAT GET NX(interface)
- uint32 t starpu hash crc32c be n (const void *input, size t n, uint32 t inputcrc)
- uint32_t starpu_hash_crc32c_be (uint32_t input, uint32_t inputcrc)
- uint32 t starpu hash crc32c string (const char *str, uint32 t inputcrc)

30.9.1 Detailed Description

Data management is done at a high-level in StarPU: rather than accessing a mere list of contiguous buffers, the tasks may manipulate data that are described by a high-level construct which we call data interface.

An example of data interface is the "vector" interface which describes a contiguous data array on a spefic memory node. This interface is a simple structure containing the number of elements in the array, the size of the elements, and the address of the array in the appropriate address space (this address may be invalid if there is no valid copy of the array in the memory node). More informations on the data interfaces provided by StarPU are given in Data Interfaces.

When a piece of data managed by StarPU is used by a task, the task implementation is given a pointer to an interface describing a valid copy of the data that is accessible from the current processing unit.

Every worker is associated to a memory node which is a logical abstraction of the address space from which the processing unit gets its data. For instance, the memory node associated to the different CPU workers represents main memory (RAM), the memory node associated to a GPU is DRAM embedded on the device. Every memory node is identified by a logical index which is accessible from the function starpu_worker_get_memory_node(). When registering a piece of data to StarPU, the specified memory node indicates where the piece of data initially resides (we also call this memory node the home node of a piece of data).

In the case of NUMA systems, functions starpu_memory_nodes_numa_devid_to_id() and starpu_memory_nodes __numa_id_to_devid() can be used to convert from NUMA node numbers as seen by the Operating System and NUMA node numbers as seen by StarPU.

There are several ways to register a memory region so that it can be managed by StarPU. StarPU provides data interfaces for vectors, 2D matrices, 3D matrices as well as BCSR and CSR sparse matrices.

Each data interface is provided with a set of field access functions. The ones using a void * parameter aimed to be used in codelet implementations (see for example the code in Vector Scaling).

Applications can provide their own interface as shown in Defining A New Data Interface.

30.9.2 Data Structure Documentation

30.9.2.1 struct starpu_data_copy_methods

Define the per-interface methods. If the starpu_data_copy_methods::any_to_any method is provided, it will be used by default if no specific method is provided. It can still be useful to provide more specific method in case of e.g. available particular CUDA or OpenCL support.

- int(* can_copy)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, unsigned handling node)
- int(* ram_to_ram)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* ram to cuda)(void *src interface, unsigned src node, void *dst interface, unsigned dst node)
- int(* ram to opencl)(void *src interface, unsigned src node, void *dst interface, unsigned dst node)
- int(* ram to mic)(void *src interface, unsigned src node, void *dst interface, unsigned dst node)
- int(* cuda_to_ram)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* cuda to cuda)(void *src interface, unsigned src node, void *dst interface, unsigned dst node)
- int(* cuda_to_opencl)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

- int(* opencl_to_ram)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* opencl_to_cuda)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* opencl_to_opencl)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* mic_to_ram)(void *src_interface, unsigned srd_node, void *dst_interface, unsigned dst_node)
- int(* ram_to_mpi_ms)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* mpi_ms_to_ram)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* mpi_ms_to_mpi_ms)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* ram_to_cuda_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, starpu cudaStream t stream)
- int(* cuda_to_ram_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, starpu_cudaStream_t stream)
- int(* cuda_to_cuda_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, starpu_cudaStream_t stream)
- int(* opencl_to_ram_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_← node, cl_event *event)
- int(* opencl_to_opencl_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst
 node, cl_event *event)

- int(* mpi_ms_to_mpi_ms_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, void *event)
- int(* ram_to_mic_async)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)
- int(* mic_to_ram_async)(void *src_interface, unsigned srd_node, void *dst_interface, unsigned dst_node)
- int(* any_to_any)(void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node, void *async_data)

30.9.2.1.1 Field Documentation

30.9.2.1.1.1 can_copy

int(* starpu_data_copy_methods::can_copy) (void *src_interface, unsigned src_node, void *dst_ \leftrightarrow interface, unsigned dst_node, unsigned handling_node)

If defined, allow the interface to declare whether it supports transferring from $src_interface$ on node src_{\leftarrow} node to $dst_interface$ on node dst_node , run from node $handling_node$. If not defined, it is assumed that the interface supports all transfers.

30.9.2.1.1.2 ram_to_ram

int(* starpu_data_copy_methods::ram_to_ram) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the dst_\leftrightarrow interface interface on the dst_node CPU node. Return 0 on success.

30.9.2.1.1.3 ram_to_cuda

int(* starpu_data_copy_methods::ram_to_cuda) (void *src_interface, unsigned src_node, void
*dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the $dst_interface$ interface on the dst_node CUDA node. Return 0 on success.

30.9.2.1.1.4 ram_to_opencl

int(* starpu_data_copy_methods::ram_to_opencl) (void *src_interface, unsigned src_node, void
*dst_interface, unsigned dst_node)

Define how to copy data from the src_interface interface on the src_node CPU node to the dst_\circ} interface interface on the dst_node OpenCL node. Return 0 on success.

30.9.2.1.1.5 ram_to_mic

int(* starpu_data_copy_methods::ram_to_mic) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the dst_{\leftarrow} interface interface on the dst_node MIC node. Return 0 on success.

30.9.2.1.1.6 cuda_to_ram

int(* starpu_data_copy_methods::cuda_to_ram) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the src_interface interface on the src_node CUDA node to the dst_\Limin interface interface on the dst_node CPU node. Return 0 on success.

30.9.2.1.1.7 cuda to cuda

int(* starpu_data_copy_methods::cuda_to_cuda) (void *src_interface, unsigned src_node, void
*dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CUDA node to the dst_{\leftarrow} interface interface on the dst_node CUDA node. Return 0 on success.

30.9.2.1.1.8 cuda_to_opencl

int(* starpu_data_copy_methods::cuda_to_opencl) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CUDA node to the $dst_interface$ interface interface on the dst_node OpenCL node. Return 0 on success.

30.9.2.1.1.9 opencl_to_ram

int(* starpu_data_copy_methods::opencl_to_ram) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the src_interface interface on the src_node OpenCL node to the dst_\Limin interface interface on the dst_node CPU node. Return 0 on success.

30.9.2.1.1.10 opencl_to_cuda

int(* starpu_data_copy_methods::opencl_to_cuda) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node OpenCL node to the $dst_interface$ interface interface on the dst_node CUDA node. Return 0 on success.

30.9.2.1.1.11 opencl_to_opencl

int(* starpu_data_copy_methods::opencl_to_opencl) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node OpenCL node to the $dst_interface$ interface interface on the dst_node OpenCL node. Return 0 on success.

30.9.2.1.1.12 mic_to_ram

int(* starpu_data_copy_methods::mic_to_ram) (void *src_interface, unsigned srd_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node MIC node to the dst_{\leftarrow} interface interface on the dst_node CPU node. Return 0 on success.

30.9.2.1.1.13 ram_to_mpi_ms

int(* starpu_data_copy_methods::ram_to_mpi_ms) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the $dst_interface$ interface interface on the dst_node MPI Slave node. Return 0 on success.

30.9.2.1.1.14 mpi_ms_to_ram

int(* starpu_data_copy_methods::mpi_ms_to_ram) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node MPI Slave node to the $dst_interface$ interface interface on the dst_node CPU node. Return 0 on success.

30.9.2.1.1.15 mpi_ms_to_mpi_ms

int(* starpu_data_copy_methods::mpi_ms_to_mpi_ms) (void *src_interface, unsigned src_node, void *dst_interface, unsigned dst_node)

Define how to copy data from the $src_interface$ interface on the src_node MPI Slave node to the $dst_interface$ interface interface on the dst_node MPI Slave node. Return 0 on success.

30.9.2.1.1.16 ram_to_cuda_async

int(* starpu_data_copy_methods::ram_to_cuda_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, starpu_cudaStream_t stream)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the $dst_interface$ interface interface on the dst_node CUDA node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.17 cuda_to_ram_async

int(* starpu_data_copy_methods::cuda_to_ram_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, starpu_cudaStream_t stream)

Define how to copy data from the $src_interface$ interface on the src_node CUDA node to the $dst_interface$ interface interface on the dst_node CPU node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.18 cuda_to_cuda_async

int(* starpu_data_copy_methods::cuda_to_cuda_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, starpu_cudaStream_t stream)

Define how to copy data from the $src_interface$ interface on the src_node CUDA node to the $dst_interface$ interface interface on the dst_node CUDA node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.19 ram_to_opencl_async

int(* starpu_data_copy_methods::ram_to_opencl_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, cl_event *event)

Define how to copy data from the src_interface interface on the src_node CPU node to the dst_\circ interface interface on the dst_node OpenCL node, by recording in event, a pointer to a cl_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.20 opencl_to_ram_async

int(* starpu_data_copy_methods::opencl_to_ram_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, cl_event *event)

Define how to copy data from the $src_interface$ interface on the src_node OpenCL node to the $dst_interface$ interface interface on the dst_node CPU node, by recording in event, a pointer to a cl_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.21 opencl_to_opencl_async

int(* starpu_data_copy_methods::opencl_to_opencl_async) (void *src_interface, unsigned src_←
node, void *dst_interface, unsigned dst_node, cl_event *event)

Define how to copy data from the $src_interface$ interface on the src_node OpenCL node to the $dst_\leftrightarrow interface$ interface on the dst_node OpenCL node, by recording in event, a pointer to a cl_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.22 ram_to_mpi_ms_async

int(* starpu_data_copy_methods::ram_to_mpi_ms_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, void *event)

Define how to copy data from the $src_interface$ interface on the src_node CPU node to the $dst_interface$ interface interface on the dst_node MPI Slave node, with the given even. Must return 0 if the transfer was

actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.23 mpi_ms_to_ram_async

```
int(* starpu_data_copy_methods::mpi_ms_to_ram_async) (void *src_interface, unsigned src_node,
void *dst_interface, unsigned dst_node, void *event)
```

Define how to copy data from the $src_interface$ interface on the src_node MPI Slave node to the $dst \leftarrow _interface$ interface interface on the dst_node CPU node, with the given event. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.24 mpi_ms_to_mpi_ms_async

```
int (* starpu_data_copy_methods::mpi_ms_to_mpi_ms_async) (void *src_interface, unsigned src\_\leftrightarrow node, void *dst_interface, unsigned dst_node, void *event)
```

Define how to copy data from the $src_interface$ interface on the src_node MPI Slave node to the $dst_interface$ interface interface on the dst_node MPI Slave node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

```
30.9.2.1.1.25 ram_to_mic_async
```

```
int(* starpu_data_copy_methods::ram_to_mic_async) (void *src_interface, unsigned src_node, void
*dst_interface, unsigned dst_node)
```

Define how to copy data from the src_interface interface on the src_node CPU node to the dst_cinterface interface interface on the dst_node MIC node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

30.9.2.1.1.26 mic_to_ram_async

```
int(* starpu_data_copy_methods::mic_to_ram_async) (void *src_interface, unsigned srd_node, void
*dst_interface, unsigned dst_node)
```

Define how to copy data from the $src_interface$ interface on the src_node MIC node to the $dst_interface$ interface interface on the dst_node CPU node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

```
30.9.2.1.1.27 any_to_any
```

```
int(* starpu_data_copy_methods::any_to_any) (void *src_interface, unsigned src_node, void
*dst_interface, unsigned dst_node, void *async_data)
```

Define how to copy data from the $src_interface$ interface on the src_node node to the $dst_interface$ interface on the dst_node node. This is meant to be implemented through the $starpu_interface_copy()$ helper, to which async_data should be passed as such, and will be used to manage asynchronicity. This must return $-EAG \leftarrow AIN$ if any of the $starpu_interface_copy()$ calls has returned -EAGAIN (i.e. at least some transfer is still ongoing), and return 0 otherwise.

This can only be implemented if the interface has ready-to-send data blocks. If the interface is more involved than this, i.e. it needs to collect pieces of data before transferring, starpu_data_interface_ops::pack_data and starpu_data_interface_ops::unpack_data should be implemented instead, and the core will just transfer the resulting data buffer.

30.9.2.2 struct starpu_data_interface_ops

Per-interface data management methods.

- void(* register_data_handle)(starpu_data_handle_t handle, unsigned home_node, void *data_interface)
- starpu_ssize_t(* allocate_data_on_node)(void *data_interface, unsigned node)
- void(* free data on node)(void *data interface, unsigned node)
- void(* init)(void *data_interface)
- const struct starpu_data_copy_methods * copy_methods

- void *(* handle_to_pointer)(starpu_data_handle_t handle, unsigned node)
- void *(* to_pointer)(void *data_interface, unsigned node)
- int(* pointer_is_inside)(void *data_interface, unsigned node, void *ptr)
- size_t(* get_size)(starpu_data_handle_t handle)
- size_t(* get_alloc_size)(starpu_data_handle_t handle)
- uint32_t(* footprint)(starpu_data_handle_t handle)
- uint32 t(* alloc footprint)(starpu data handle t handle)
- int(* compare)(void *data interface a, void *data interface b)
- int(* alloc_compare)(void *data_interface_a, void *data_interface_b)
- void(* display)(starpu_data_handle_t handle, FILE *f)
- starpu ssize t(* describe)(void *data interface, char *buf, size t size)
- · enum starpu data interface id interfaceid
- · size t interface size
- · char is multiformat
- · char dontcache
- struct starpu multiformat data interface ops *(* get mf ops)(void *data interface)
- int(* pack_data)(starpu_data_handle_t handle, unsigned node, void **ptr, starpu_ssize_t *count)
- int(* unpack_data)(starpu_data_handle_t handle, unsigned node, void *ptr, size_t count)
- char * name

30.9.2.2.1 Field Documentation

30.9.2.2.1.1 register data handle

```
void(* starpu_data_interface_ops::register_data_handle) (starpu_data_handle_t handle, unsigned
home_node, void *data_interface)
```

Register an existing interface into a data handle.

This iterates over all memory nodes to initialize all fields of the data interface on each of them. Since data is not allocated yet except on the home node, pointers should be left as NULL except on the home_node, for which the pointers should be copied from the given data_interface, which was filled with the application's pointers. This method is mandatory.

```
30.9.2.2.1.2 allocate_data_on_node
```

```
starpu_ssize_t(* starpu_data_interface_ops::allocate_data_on_node) (void *data_interface,
unsigned node)
```

Allocate data for the interface on a given node. This should use starpu_malloc_on_node() to perform the allocation(s), and fill the pointers in the data interface. It should return the size of the allocated memory, or -ENOMEM if memory could not be allocated.

Note that the memory node can be CPU memory, GPU memory, or even disk area. The result returned by starpu← _malloc_on_node() should be just stored as uintptr_t without trying to interpret it since it may be a GPU pointer, a disk descriptor, etc.

This method is mandatory to be able to support memory nodes.

```
30.9.2.2.1.3 free_data_on_node
```

```
void(* starpu_data_interface_ops::free_data_on_node) (void *data_interface, unsigned node)
```

Free data of the interface on a given node.

This method is mandatory to be able to support memory nodes.

```
30.9.2.2.1.4 init
```

```
void(* starpu_data_interface_ops::init) (void *data_interface)
```

Initialize the interface. This method is optional. It is called when initializing the handler on all the memory nodes.

```
30.9.2.2.1.5 copy_methods
```

```
\verb|const| struct| starpu\_data\_copy\_methods*| starpu\_data\_interface\_ops::copy\_methods*|
```

Struct with pointer to functions for performing ram/cuda/opencl synchronous and asynchronous transfers.

This field is mandatory to be able to support memory nodes, except disk nodes which can be supported by just implementing starpu_data_interface_ops::pack_data and starpu_data_interface_ops::unpack_data.

30.9.2.2.1.6 handle_to_pointer

void*(* starpu_data_interface_ops::handle_to_pointer) (starpu_data_handle_t handle, unsigned node)

Deprecated Use starpu_data_interface_ops::to_pointer instead. Return the current pointer (if any) for the handle on the given node.

This method is only required if starpu data interface ops::to pointer is not implemented.

30.9.2.2.1.7 to_pointer

```
void*(* starpu_data_interface_ops::to_pointer) (void *data_interface, unsigned node)
```

Return the current pointer (if any) for the given interface on the given node.

This method is only required for starpu_data_handle_to_pointer() and starpu_data_get_local_ptr(), and for disk support.

30.9.2.2.1.8 pointer_is_inside

```
int(* starpu_data_interface_ops::pointer_is_inside) (void *data_interface, unsigned node, void
*ptr)
```

Return whether the given ptr is within the data for the given interface on the given node. This method is optional, as it is only used for coherency checks.

```
30.9.2.2.1.9 get_size
```

```
size_t(* starpu_data_interface_ops::get_size) (starpu_data_handle_t handle)
```

Return an estimation of the size of data, for performance models and tracing feedback.

```
30.9.2.2.1.10 get_alloc_size
```

```
size_t(* starpu_data_interface_ops::get_alloc_size) (starpu_data_handle_t handle)
```

Return an estimation of the size of allocated data, for allocation management. If not specified, the starpu_data_
interface ops::get size method is used instead.

30.9.2.2.1.11 footprint

```
uint32_t(* starpu_data_interface_ops::footprint) (starpu_data_handle_t handle)
```

Return a 32bit footprint which characterizes the data size and layout (nx, ny, ld, elemsize, etc.), required for indexing performance models.

starpu_hash_crc32c_be() and alike can be used to produce this 32bit value from various types of values.

30.9.2.2.1.12 alloc_footprint

```
uint32_t(* starpu_data_interface_ops::alloc_footprint) (starpu_data_handle_t handle)
```

Return a 32bit footprint which characterizes the data allocation, to be used for indexing allocation cache. If not specified, the starpu_data_interface_ops::footprint method is used instead.

30.9.2.2.1.13 compare

```
int(* starpu_data_interface_ops::compare) (void *data_interface_a, void *data_interface_b)
```

Compare the data size and layout of two interfaces (nx, ny, ld, elemsize, etc.), to be used for indexing performance models. It should return 1 if the two interfaces size and layout match computation-wise, and 0 otherwise.

```
30.9.2.2.1.14 alloc_compare
```

```
int(* starpu_data_interface_ops::alloc_compare) (void *data_interface_a, void *data_interface↔
```

Compare the data allocation of two interfaces etc.), to be used for indexing allocation cache. It should return 1 if the two interfaces are allocation-compatible, i.e. basically have the same alloc_size, and 0 otherwise. If not specified, the starpu_data_interface_ops::compare method is used instead.

```
30.9.2.2.1.15 display
```

```
void(* starpu_data_interface_ops::display) (starpu_data_handle_t handle, FILE *f)
```

Dump the sizes of a handle to a file. This is required for performance models

```
30.9.2.2.1.16 describe
```

```
starpu_ssize_t(* starpu_data_interface_ops::describe) (void *data_interface, char *buf, size_t
size)
```

Describe the data into a string in a brief way, such as one letter to describe the type of data, and the data dimensions.

This is required for tracing feedback.

30.9.2.2.1.17 interfaceid

enum starpu_data_interface_id starpu_data_interface_ops::interfaceid

An identifier that is unique to each interface.

30.9.2.2.1.18 interface size

size_t starpu_data_interface_ops::interface_size

Size of the interface data descriptor.

30.9.2.2.1.19 dontcache

```
char starpu_data_interface_ops::dontcache
```

If set to non-zero, StarPU will never try to reuse an allocated buffer for a different handle. This can be notably useful for application-defined interfaces which have a dynamic size, and for which it thus does not make sense to reuse the buffer since will probably not have the proper size.

30.9.2.2.1.20 pack_data

```
int(* starpu_data_interface_ops::pack_data) (starpu_data_handle_t handle, unsigned node, void
**ptr, starpu_ssize_t *count)
```

Pack the data handle into a contiguous buffer at the address allocated with <code>starpu_malloc_flags(ptr, size, 0)</code> (and thus returned in <code>ptr</code>) and set the size of the newly created buffer in <code>count</code>. If <code>ptr</code> is <code>NULL</code>, the function should not copy the data in the buffer but just set count to the size of the buffer which would have been allocated. The special value -1 indicates the size is yet unknown.

This method (and starpu_data_interface_ops::unpack_data) is required for disk support if the starpu_data_copy ← _methods::any_to_any method is not implemented (because the in-memory data layout is too complex).

This is also required for MPI support if there is no registered MPI data type.

30.9.2.2.1.21 unpack_data

```
int(* starpu_data_interface_ops::unpack_data) (starpu_data_handle_t handle, unsigned node,
void *ptr, size_t count)
```

Unpack the data handle from the contiguous buffer at the address ptr of size count. The memory at the address ptr should be freed after the data unpacking operation.

30.9.2.2.1.22 name

char* starpu_data_interface_ops::name

Name of the interface

30.9.2.3 struct starpu_matrix_interface

Matrix interface for dense matrices

| enum starpu_data_interface_id | id | Identifier of the interface |
|-------------------------------|------------|--|
| uintptr_t | ptr | local pointer of the matrix |
| uintptr_t | dev_handle | device handle of the matrix |
| size_t | offset | offset in the matrix |
| uint32_t | nx | number of elements on the x-axis of the matrix |
| uint32_t | ny | number of elements on the y-axis of the matrix |
| uint32_t | ld | number of elements between each row of the matrix. Maybe be equal to starpu_matrix_interface::nx when there is no padding. |
| size_t | elemsize | size of the elements of the matrix |
| size_t | allocsize | size actually currently allocated |

30.9.2.4 struct starpu_coo_interface

COO Matrices

Data Fields

| enum starpu_data_interface_id | id | identifier of the interface |
|-------------------------------|----------|--|
| uint32_t * | columns | column array of the matrix |
| uint32_t * | rows | row array of the matrix |
| uintptr_t | values | values of the matrix |
| uint32_t | nx | number of elements on the x-axis of the matrix |
| uint32_t | ny | number of elements on the y-axis of the matrix |
| uint32_t | n_values | number of values registered in the matrix |
| size_t | elemsize | size of the elements of the matrix |

30.9.2.5 struct starpu_block_interface

Block interface for 3D dense blocks

Data Fields

| enum starpu_data_interface_id | id | identifier of the interface |
|-------------------------------|------------|--|
| uintptr_t | ptr | local pointer of the block |
| uintptr_t | dev_handle | device handle of the block. |
| size_t | offset | offset in the block. |
| uint32_t | nx | number of elements on the x-axis of the block. |
| uint32_t | ny | number of elements on the y-axis of the block. |
| uint32_t | nz | number of elements on the z-axis of the block. |
| uint32_t | ldy | number of elements between two lines |
| uint32_t | ldz | number of elements between two planes |
| size_t | elemsize | size of the elements of the block. |

30.9.2.6 struct starpu_vector_interface

Data Fields

| enum starpu_data_interface_id | id | Identifier of the interface |
|-------------------------------|------------|--|
| uintptr_t ptr | | local pointer of the vector |
| uintptr_t | dev_handle | device handle of the vector. |
| size_t | offset | offset in the vector |
| uint32_t | nx | number of elements on the x-axis of the vector |
| size_t | elemsize | size of the elements of the vector |
| uint32_t | slice_base | vector slice base, used by the StarPU OpenMP runtime support |
| size_t | allocsize | size actually currently allocated |

30.9.2.7 struct starpu_variable_interface

Variable interface for a single data (not a vector, a matrix, a list, ...)

| enum starpu_data_interface_id | id | Identifier of the interface |
|-------------------------------|----|-----------------------------|
|-------------------------------|----|-----------------------------|

Data Fields

| uintptr_t | ptr | local pointer of the variable |
|-----------|------------|--------------------------------|
| uintptr_t | dev_handle | device handle of the variable. |
| size_t | offset | offset in the variable |
| size_t | elemsize | size of the variable |

30.9.2.8 struct starpu_csr_interface

CSR interface for sparse matrices (compressed sparse row representation)

Data Fields

| enum starpu_data_interface_id | id | Identifier of the interface |
|-------------------------------|------------|---|
| uint32_t | nnz | number of non-zero entries |
| uint32_t nrow | | number of rows |
| uintptr_t | nzval | non-zero values |
| uint32_t * | colind | position of non-zero entries on the row |
| uint32_t * | rowptr | index (in nzval) of the first entry of the row |
| uint32_t | firstentry | k for k-based indexing (0 or 1 usually). also useful when partitionning the matrix. |
| size_t | elemsize | size of the elements of the matrix |

30.9.2.9 struct starpu_bcsr_interface

BCSR interface for sparse matrices (blocked compressed sparse row representation)

Data Fields

| enum starpu_data_interface_id | id | Identifier of the interface |
|-------------------------------|------------|--|
| uint32_t nnz | | number of non-zero BLOCKS |
| uint32_t | nrow | number of rows (in terms of BLOCKS) |
| uintptr_t | nzval | non-zero values |
| uint32_t * | colind | array of nnz elements, colind[i] is the block-column index for block i in nzval |
| uint32_t * | rowptr | array of nrow+1 elements, rowptr[i] is the block-index (in nzval) of the first block of row i. By convention, rowptr[nrow] is the number of blocks, this allows an easier access of the matrix's elements for the kernels. |
| uint32_t | firstentry | k for k-based indexing (0 or 1 usually). Also useful when partitionning the matrix. |
| uint32_t | r | height of the blocks |
| uint32_t | С | width of the blocks |
| size_t | elemsize | size of the elements of the matrix |

30.9.2.10 struct starpu_multiformat_data_interface_ops

Multiformat operations

| size_t cpu_elemsize | size of each element on CPUs |
|---------------------|------------------------------|
|---------------------|------------------------------|

Data Fields

| size_t | opencl_elemsize | size of each element on OpenCL devices |
|-------------------------|------------------|--|
| struct starpu_codelet * | cpu_to_opencl_cl | pointer to a codelet which converts from CPU to OpenCL |
| struct starpu_codelet * | opencl_to_cpu_cl | pointer to a codelet which converts from OpenCL to CPU |
| size_t | cuda_elemsize | size of each element on CUDA devices |
| struct starpu_codelet * | cpu_to_cuda_cl | pointer to a codelet which converts from CPU to CUDA |
| struct starpu_codelet * | cuda_to_cpu_cl | pointer to a codelet which converts from CUDA to CPU |
| size_t | mic_elemsize | size of each element on MIC devices |
| struct starpu_codelet * | cpu_to_mic_cl | pointer to a codelet which converts from CPU to MIC |
| struct starpu_codelet * | mic_to_cpu_cl | pointer to a codelet which converts from MIC to CPU |

30.9.2.11 struct starpu_multiformat_interface

Data Fields

| enum starpu_data_interface_id | id | |
|---|------------|--|
| void * | cpu_ptr | |
| void * | cuda_ptr | |
| void * | opencl_ptr | |
| void * | mic_ptr | |
| uint32_t | nx | |
| struct | | |
| starpu_multiformat_data_interface_ops * | ops | |

30.9.3 Macro Definition Documentation

30.9.3.1 STARPU_MATRIX_GET_PTR

Return a pointer to the matrix designated by interface, valid on CPUs and CUDA devices only. For OpenCL devices, the device handle and offset need to be used instead.

30.9.3.2 STARPU_MATRIX_GET_DEV_HANDLE

Return a device handle for the matrix designated by interface, to be used with OpenCL. The offset returned by STARPU_MATRIX_GET_OFFSET has to be used in addition to this.

30.9.3.3 STARPU_MATRIX_GET_OFFSET

Return the offset in the matrix designated by interface, to be used with the device handle.

30.9.3.4 STARPU_MATRIX_GET_NX

Return the number of elements on the x-axis of the matrix designated by interface.

30.9.3.5 STARPU_MATRIX_GET_NY

Return the number of elements on the y-axis of the matrix designated by interface.

30.9.3.6 STARPU_MATRIX_GET_LD

Return the number of elements between each row of the matrix designated by interface. May be equal to nx when there is no padding.

30.9.3.7 STARPU_MATRIX_GET_ELEMSIZE

Return the size of the elements registered into the matrix designated by interface.

30.9.3.8 STARPU_MATRIX_GET_ALLOCSIZE

Return the allocated size of the matrix designated by interface.

30.9.3.9 STARPU_MATRIX_SET_NX

Set the number of elements on the x-axis of the matrix designated by interface.

30.9.3.10 STARPU_MATRIX_SET_NY

Set the number of elements on the y-axis of the matrix designated by interface.

30.9.3.11 STARPU_MATRIX_SET_LD

Set the number of elements between each row of the matrix designated by interface. May be set to the same value as nx when there is no padding.

30.9.3.12 STARPU_COO_GET_COLUMNS

Return a pointer to the column array of the matrix designated by interface.

30.9.3.13 STARPU_COO_GET_COLUMNS_DEV_HANDLE

Return a device handle for the column array of the matrix designated by interface, to be used with OpenCL. The offset returned by STARPU_COO_GET_OFFSET has to be used in addition to this.

30.9.3.14 STARPU_COO_GET_ROWS

Return a pointer to the rows array of the matrix designated by interface.

30.9.3.15 STARPU_COO_GET_ROWS_DEV_HANDLE

Return a device handle for the row array of the matrix designated by interface, to be used on OpenCL. The offset returned by STARPU COO GET OFFSET has to be used in addition to this.

30.9.3.16 STARPU_COO_GET_VALUES

Return a pointer to the values array of the matrix designated by interface.

30.9.3.17 STARPU_COO_GET_VALUES_DEV_HANDLE

Return a device handle for the value array of the matrix designated by interface, to be used on OpenCL. The offset returned by STARPU COO GET OFFSET has to be used in addition to this.

30.9.3.18 STARPU_COO_GET_OFFSET

```
#define STARPU_COO_GET_OFFSET
```

Return the offset in the arrays of the COO matrix designated by interface.

30.9.3.19 STARPU_COO_GET_NX

Return the number of elements on the x-axis of the matrix designated by interface.

30.9.3.20 STARPU_COO_GET_NY

Return the number of elements on the y-axis of the matrix designated by interface.

30.9.3.21 STARPU_COO_GET_NVALUES

Return the number of values registered in the matrix designated by ${\tt interface}.$

30.9.3.22 STARPU_COO_GET_ELEMSIZE

Return the size of the elements registered into the matrix designated by interface.

30.9.3.23 STARPU_BLOCK_GET_PTR

Return a pointer to the block designated by interface.

30.9.3.24 STARPU_BLOCK_GET_DEV_HANDLE

Return a device handle for the block designated by interface, to be used on OpenCL. The offset returned by STARPU_BLOCK_GET_OFFSET has to be used in addition to this.

30.9.3.25 STARPU_BLOCK_GET_OFFSET

Return the offset in the block designated by interface, to be used with the device handle.

30.9.3.26 STARPU_BLOCK_GET_NX

Return the number of elements on the x-axis of the block designated by interface.

30.9.3.27 STARPU_BLOCK_GET_NY

Return the number of elements on the y-axis of the block designated by interface.

30.9.3.28 STARPU_BLOCK_GET_NZ

Return the number of elements on the z-axis of the block designated by interface.

30.9.3.29 STARPU_BLOCK_GET_LDY

Return the number of elements between each row of the block designated by interface. May be equal to nx when there is no padding.

30.9.3.30 STARPU_BLOCK_GET_LDZ

Return the number of elements between each z plane of the block designated by interface. May be equal to nx*ny when there is no padding.

30.9.3.31 STARPU_BLOCK_GET_ELEMSIZE

```
#define STARPU_BLOCK_GET_ELEMSIZE(
```

Return the size of the elements of the block designated by interface.

30.9.3.32 STARPU_VECTOR_GET_PTR

Return a pointer to the array designated by interface, valid on CPUs and CUDA only. For OpenCL, the device handle and offset need to be used instead.

30.9.3.33 STARPU_VECTOR_GET_DEV_HANDLE

Return a device handle for the array designated by interface, to be used with OpenCL. the offset returned by STARPU_VECTOR_GET_OFFSET has to be used in addition to this.

30.9.3.34 STARPU_VECTOR_GET_OFFSET

Return the offset in the array designated by interface, to be used with the device handle.

30.9.3.35 STARPU_VECTOR_GET_NX

Return the number of elements registered into the array designated by interface.

30.9.3.36 STARPU_VECTOR_GET_ELEMSIZE

Return the size of each element of the array designated by interface.

30.9.3.37 STARPU_VECTOR_GET_ALLOCSIZE

Return the size of each element of the array designated by interface.

30.9.3.38 STARPU_VECTOR_GET_SLICE_BASE

Return the OpenMP slice base annotation of each element of the array designated by interface.

30.9.3.39 STARPU_VECTOR_SET_NX

Set the number of elements registered into the array designated by ${\tt interface}.$

30.9.3.40 STARPU VARIABLE GET PTR

Return a pointer to the variable designated by interface.

30.9.3.41 STARPU_VARIABLE_GET_OFFSET

Return the offset in the variable designated by interface, to be used with the device handle.

30.9.3.42 STARPU_VARIABLE_GET_ELEMSIZE

Return the size of the variable designated by interface.

30.9.3.43 STARPU_VARIABLE_GET_DEV_HANDLE

Return a device handle for the variable designated by interface, to be used with OpenCL. The offset returned by STARPU_VARIABLE_GET_OFFSET has to be used in addition to this.

30.9.3.44 STARPU_CSR_GET_NNZ

Return the number of non-zero values in the matrix designated by interface.

30.9.3.45 STARPU_CSR_GET_NROW

Return the size of the row pointer array of the matrix designated by interface.

30.9.3.46 STARPU_CSR_GET_NZVAL

Return a pointer to the non-zero values of the matrix designated by interface.

30.9.3.47 STARPU_CSR_GET_NZVAL_DEV_HANDLE

Return a device handle for the array of non-zero values in the matrix designated by interface. The offset returned by STARPU CSR GET OFFSET has to used in addition to this.

30.9.3.48 STARPU_CSR_GET_COLIND

Return a pointer to the column index of the matrix designated by interface.

30.9.3.49 STARPU_CSR_GET_COLIND_DEV_HANDLE

Return a device handle for the column index of the matrix designated by interface. The offset returned by STARPU_CSR_GET_OFFSET has to be used in addition to this.

30.9.3.50 STARPU_CSR_GET_ROWPTR

```
#define STARPU_CSR_GET_ROWPTR(
```

Return a pointer to the row pointer array of the matrix designated by interface.

30.9.3.51 STARPU_CSR_GET_ROWPTR_DEV_HANDLE

Return a device handle for the row pointer array of the matrix designated by interface. The offset returned by STARPU_CSR_GET_OFFSET has to be used in addition to this.

30.9.3.52 STARPU_CSR_GET_OFFSET

```
#define STARPU_CSR_GET_OFFSET
```

Return the offset in the arrays (colind, rowptr, nzval) of the matrix designated by interface, to be used with the device handles.

30.9.3.53 STARPU_CSR_GET_FIRSTENTRY

Return the index at which all arrays (the column indexes, the row pointers...) of the interface start.

30.9.3.54 STARPU_CSR_GET_ELEMSIZE

Return the size of the elements registered into the matrix designated by interface.

30.9.3.55 STARPU_BCSR_GET_NNZ

Return the number of non-zero values in the matrix designated by interface.

30.9.3.56 STARPU_BCSR_GET_NZVAL

Return a pointer to the non-zero values of the matrix designated by interface.

30.9.3.57 STARPU_BCSR_GET_NZVAL_DEV_HANDLE

Return a device handle for the array of non-zero values in the matrix designated by interface. The offset returned by STARPU BCSR GET OFFSET has to be used in addition to this.

30.9.3.58 STARPU_BCSR_GET_COLIND

Return a pointer to the column index of the matrix designated by interface.

30.9.3.59 STARPU_BCSR_GET_COLIND_DEV_HANDLE

Return a device handle for the column index of the matrix designated by interface. The offset returned by STARPU BCSR GET OFFSET has to be used in addition to this.

30.9.3.60 STARPU_BCSR_GET_ROWPTR

Return a pointer to the row pointer array of the matrix designated by interface.

30.9.3.61 STARPU_BCSR_GET_ROWPTR_DEV_HANDLE

Return a device handle for the row pointer array of the matrix designated by interface. The offset returned by STARPU_BCSR_GET_OFFSET has to be used in addition to this.

30.9.3.62 STARPU BCSR GET OFFSET

```
#define STARPU_BCSR_GET_OFFSET
```

Return the offset in the arrays (coling, rowptr, nzval) of the matrix designated by interface, to be used with the device handles.

30.9.3.63 STARPU_MULTIFORMAT_GET_CPU_PTR

Return the local pointer to the data with CPU format.

30.9.3.64 STARPU_MULTIFORMAT_GET_CUDA_PTR

Return the local pointer to the data with CUDA format.

30.9.3.65 STARPU_MULTIFORMAT_GET_OPENCL_PTR

Return the local pointer to the data with OpenCL format.

30.9.3.66 STARPU_MULTIFORMAT_GET_MIC_PTR

Return the local pointer to the data with MIC format.

30.9.3.67 STARPU_MULTIFORMAT_GET_NX

Return the number of elements in the data.

30.9.4 Enumeration Type Documentation

30.9.4.1 starpu_data_interface_id

```
enum starpu_data_interface_id
```

Identifier for all predefined StarPU data interfaces

Enumerator

| STARPU_UNKNOWN_INTERFACE_ID | Unknown interface |
|-----------------------------|--|
| STARPU_MATRIX_INTERFACE_ID | Identifier for the matrix data interface |
| STARPU_BLOCK_INTERFACE_ID | Identifier for the block data interface |
| STARPU_VECTOR_INTERFACE_ID | Identifier for the vector data interface |
| STARPU_CSR_INTERFACE_ID | Identifier for the CSR data interface |

Enumerator

| STARPU_BCSR_INTERFACE_ID | Identifier for the BCSR data interface |
|---------------------------------|---|
| STARPU_VARIABLE_INTERFACE_ID | Identifier for the variable data interface |
| STARPU_VOID_INTERFACE_ID | Identifier for the void data interface |
| STARPU_MULTIFORMAT_INTERFACE_ID | Identifier for the multiformat data interface |
| STARPU_COO_INTERFACE_ID | Identifier for the COO data interface |
| STARPU_MAX_INTERFACE_ID | Maximum number of data interfaces |

30.9.5 Function Documentation

30.9.5.1 starpu_data_register()

Register a piece of data into the handle located at the handleptr address. The data_interface buffer contains the initial description of the data in the home_node. The ops argument is a pointer to a structure describing the different methods used to manipulate this type of interface. See starpu_data_interface_ops for more details on this structure. If home_node is -1, StarPU will automatically allocate the memory when it is used for the first time in write-only mode. Once such data handle has been automatically allocated, it is possible to access it using any access mode. Note that StarPU supplies a set of predefined types of interface (e.g. vector or matrix) which can be registered by the means of helper functions (e.g. starpu_vector_data_register()) or starpu_matrix_cdata_register()).

30.9.5.2 starpu_data_ptr_register()

Register that a buffer for handle on node will be set. This is typically used by starpu_*_ptr_register helpers before setting the interface pointers for this node, to tell the core that that is now allocated.

30.9.5.3 starpu_data_register_same()

Register a new piece of data into the handle handledst with the same interface as the handle handlesrc.

30.9.5.4 starpu_data_handle_to_pointer()

Return the pointer associated with handle on node node or NULL if handle's interface does not support this operation or data for this handle is not allocated on that node.

30.9.5.5 starpu_data_pointer_is_inside()

```
unsigned node,
void * ptr )
```

Return whether the given ptr is within the data for handle on node node (1) or not (0). If the handle interface does not support this operation, and thus the result is unknown, -1 is returned.

```
30.9.5.6 starpu_data_get_local_ptr()
```

Return the local pointer associated with handle or NULL if handle's interface does not have any data allocated locally.

30.9.5.7 starpu_data_get_interface_on_node()

Return the interface associated with handle on memory_node.

30.9.5.8 starpu_data_get_interface_id()

Return the unique identifier of the interface associated with the given handle.

30.9.5.9 starpu_data_pack()

Execute the packing operation of the interface of the data registered at handle (see starpu_data_interface_ops). This packing operation must allocate a buffer large enough at ptr and copy into the newly allocated buffer the data associated to handle. count will be set to the size of the allocated buffer. If ptr is NULL, the function should not copy the data in the buffer but just set count to the size of the buffer which would have been allocated. The special value -1 indicates the size is yet unknown.

30.9.5.10 starpu_data_unpack()

Unpack in handle the data located at ptr of size count as described by the interface of the data. The interface registered at handle must define a unpacking operation (see starpu_data_interface_ops).

30.9.5.11 starpu_data_get_size()

Return the size of the data associated with handle.

30.9.5.12 starpu_data_get_alloc_size()

Return the size of the allocated data associated with handle.

30.9.5.13 starpu_data_lookup()

Return the handle corresponding to the data pointed to by the ptr host pointer.

30.9.5.14 starpu_data_interface_get_next_id()

```
int starpu_data_interface_get_next_id (
```

Return the next available id for a newly created data interface (Defining A New Data Interface).

30.9.5.15 starpu_interface_copy()

Copy size bytes from byte offset src_offset of src on src_node to byte offset dst_offset of dst on dst_node. This is to be used in the starpu_data_copy_methods::any_to_any copy method, which is provided with async_data to be passed to starpu_interface_copy(). this returns -EAGAIN if the transfer is still ongoing, or 0 if the transfer is already completed.

30.9.5.16 starpu_interface_start_driver_copy_async()

When an asynchonous implementation of the data transfer is implemented, the call to the underlying CUDA, Open CL, etc. call should be surrounded by calls to starpu_interface_start_driver_copy_async() and starpu_interface end_driver_copy_async(), so that it is recorded in offline execution traces, and the timing of the submission is checked. start must point to a variable whose value will be passed unchanged to starpu_interface_end_driver copy_async().

30.9.5.17 starpu_interface_end_driver_copy_async()

See starpu_interface_start_driver_copy_async().

30.9.5.18 starpu_interface_data_copy()

```
void starpu_interface_data_copy (
          unsigned src_node,
          unsigned dst_node,
          size_t size )
```

Record in offline execution traces the copy of size bytes from node src_node to node dst_node

30.9.5.19 starpu_malloc_on_node_flags()

```
size_t size,
int flags )
```

Allocate size bytes on node dst_node with the given allocation flags. This returns 0 if allocation failed, the allocation method should then return -ENOMEM as allocated size. Deallocation must be done with starpu_free_
on node flags().

30.9.5.20 starpu_malloc_on_node()

Allocate size bytes on node dst_node with the default allocation flags. This returns 0 if allocation failed, the allocation method should then return -ENOMEM as allocated size. Deallocation must be done with $starpu_free_{\leftarrow}$ on node().

30.9.5.21 starpu_free_on_node_flags()

```
void starpu_free_on_node_flags (
          unsigned dst_node,
          uintptr_t addr,
          size_t size,
          int flags )
```

Free addr of size bytes on node dst_node which was previously allocated with starpu_malloc_on_node_
flags() with the given allocation flags.

30.9.5.22 starpu_free_on_node()

```
void starpu_free_on_node (
          unsigned dst_node,
          uintptr_t addr,
          size_t size )
```

Free addr of size bytes on node dst_node which was previously allocated with starpu_malloc_on_node().

30.9.5.23 starpu_malloc_on_node_set_default_flags()

Define the default flags for allocations performed by starpu_malloc_on_node() and starpu_free_on_node(). The default is STARPU_MALLOC_PINNED | STARPU_MALLOC_COUNT.

30.9.5.24 starpu_matrix_data_register()

Register the nx x ny 2D matrix of elemsize-byte elements pointed by ptr and initialize handle to represent it. 1d specifies the number of elements between rows. a value greater than nx adds padding, which can be useful for alignment purposes.

Here an example of how to use the function.

30.9.5.25 starpu_matrix_data_register_allocsize()

Similar to starpu_matrix_data_register, but additionally specifies which allocation size should be used instead of the initial nx*ny*elemsize.

30.9.5.26 starpu_matrix_ptr_register()

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev_handle and offset offset (for OpenCL, notably), with ld elements between rows.

30.9.5.27 starpu_matrix_get_nx()

Return the number of elements on the x-axis of the matrix designated by handle.

30.9.5.28 starpu_matrix_get_ny()

Return the number of elements on the y-axis of the matrix designated by handle.

30.9.5.29 starpu_matrix_get_local_ld()

Return the number of elements between each row of the matrix designated by handle. Maybe be equal to nx when there is no padding.

30.9.5.30 starpu_matrix_get_local_ptr()

Return the local pointer associated with handle.

30.9.5.31 starpu_matrix_get_elemsize()

Return the size of the elements registered into the matrix designated by handle.

30.9.5.32 starpu_matrix_get_allocsize()

Return the allocated size of the matrix designated by handle.

30.9.5.33 starpu_coo_data_register()

Register the nx x ny 2D matrix given in the COO format, using the columns, rows, values arrays, which must have n_values elements of size elemsize. Initialize handleptr.

30.9.5.34 starpu_block_data_register()

Register the $nx \ x \ ny \ x \ nz$ 3D matrix of elemsize byte elements pointed by ptr and initialize handle to represent it. Again, ldy and ldz specify the number of elements between rows and between z planes. Here an example of how to use the function.

30.9.5.35 starpu_block_ptr_register()

Register into the <code>handle</code> that to store data on node <code>node</code> it should use the buffer located at <code>ptr</code>, or device handle <code>dev_handle</code> and offset <code>offset</code> (for OpenCL, notably), with <code>ldy</code> elements between rows and <code>ldz</code> elements between z planes.

```
30.9.5.36 starpu_block_get_nx()
```

Return the number of elements on the x-axis of the block designated by handle.

30.9.5.37 starpu_block_get_ny()

Return the number of elements on the y-axis of the block designated by handle.

30.9.5.38 starpu_block_get_nz()

Return the number of elements on the z-axis of the block designated by handle.

30.9.5.39 starpu_block_get_local_ldy()

Return the number of elements between each row of the block designated by handle, in the format of the current memory node.

30.9.5.40 starpu_block_get_local_ldz()

Return the number of elements between each z plane of the block designated by handle, in the format of the current memory node.

30.9.5.41 starpu_block_get_local_ptr()

Return the local pointer associated with handle.

30.9.5.42 starpu_block_get_elemsize()

Return the size of the elements of the block designated by handle.

30.9.5.43 starpu_vector_data_register()

Register the nx elemsize-byte elements pointed to by ptr and initialize handle to represent it. Here an example of how to use the function.

30.9.5.44 starpu_vector_data_register_allocsize()

Similar to starpu_matrix_data_register, but additionally specifies which allocation size should be used instead of the initial nx*elemsize.

30.9.5.45 starpu_vector_ptr_register()

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev_handle and offset offset (for OpenCL, notably)

30.9.5.46 starpu_vector_get_nx()

Return the number of elements registered into the array designated by handle.

30.9.5.47 starpu_vector_get_elemsize()

Return the size of each element of the array designated by handle.

30.9.5.48 starpu_vector_get_allocsize()

Return the allocated size of the array designated by handle.

30.9.5.49 starpu_vector_get_local_ptr()

Return the local pointer associated with handle.

30.9.5.50 starpu_variable_data_register()

Register the size byte element pointed to by ptr, which is typically a scalar, and initialize handle to represent this data item.

Here an example of how to use the function.

30.9.5.51 starpu_variable_ptr_register()

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev_handle and offset offset (for OpenCL, notably)

30.9.5.52 starpu_variable_get_elemsize()

Return the size of the variable designated by handle.

30.9.5.53 starpu_variable_get_local_ptr()

Return a pointer to the variable designated by handle.

30.9.5.54 starpu_void_data_register()

Register a void interface. There is no data really associated to that interface, but it may be used as a synchronization mechanism. It also permits to express an abstract piece of data that is managed by the application internally: this makes it possible to forbid the concurrent execution of different tasks accessing the same <code>void</code> data in read-write concurrently.

30.9.5.55 starpu_csr_data_register()

Register a CSR (Compressed Sparse Row Representation) sparse matrix.

30.9.5.56 starpu_csr_get_nnz()

Return the number of non-zero values in the matrix designated by handle.

30.9.5.57 starpu_csr_get_nrow()

Return the size of the row pointer array of the matrix designated by handle.

30.9.5.58 starpu_csr_get_firstentry()

Return the index at which all arrays (the column indexes, the row pointers...) of the matrix designated by handle.

30.9.5.59 starpu_csr_get_local_nzval()

Return a local pointer to the non-zero values of the matrix designated by handle.

30.9.5.60 starpu_csr_get_local_colind()

Return a local pointer to the column index of the matrix designated by handle.

30.9.5.61 starpu_csr_get_local_rowptr()

Return a local pointer to the row pointer array of the matrix designated by handle.

30.9.5.62 starpu_csr_get_elemsize()

Return the size of the elements registered into the matrix designated by handle.

30.9.5.63 starpu_bcsr_data_register()

This variant of starpu_data_register() uses the BCSR (Blocked Compressed Sparse Row Representation) sparse matrix interface. Register the sparse matrix made of nnz non-zero blocks of elements of size elemsize stored in nzval and initializes handle to represent it. Blocks have size r*c. nrow is the number of rows (in terms of blocks), colind is an array of nnz elements, colind[i] is the block-column index for block i in nzval, rowptr is an array of nrow+1 elements, rowptr[i] is the block-index (in nzval) of the first block of row i. By convention, rowptr[nrow] is the number of blocks, this allows an easier access of the matrix's elements for the kernels. firstentry is the index of the first entry of the given arrays (usually 0 or 1).

Here an example with the following matrix:

```
| 0 1 0 0 |
| 2 3 0 0 |
| 4 5 8 9 |
| 6 7 10 11 |
```

```
nzval = [0, 1, 2, 3] ++ [4, 5, 6, 7] ++ [8, 9, 10, 11]
colind = [0, 0, 1]
rowptr = [0, 1, 3]
r = c = 2
which translates into the following code
int R = 2; // Size of the blocks
int NROWS = 2;
int NNZ_BLOCKS = 3;
                      // out of 4
int NZVAL_SIZE = (R*C*NNZ_BLOCKS);
int nzval[NZVAL_SIZE] =
  0, 1, 2, 3,
                  // First block
  4, 5, 6, 7,
8, 9, 10, 11
                  // Second block
                 // Third block
uint32_t colind[NNZ_BLOCKS] =
  0, // block-column index for first block in nzval
  \mathbf{0}\text{, } // \text{ block-column index for second block in nzval}
  1\ \ //\ {\tt block-column} index for third block in nzval
uint32_t rowptr[NROWS+1] =
  0, // block-index in nzval of the first block of the first row. 1, // block-index in nzval of the first block of the second row.
 NNZ_BLOCKS // number of blocks, to allow an easier element's access for the kernels
starpu_data_handle_t bcsr_handle;
starpu_bcsr_data_register(&bcsr_handle,
                   STARPU_MAIN_RAM,
                   NNZ BLOCKS.
                   NROWS,
                   (uintptr_t) nzval,
                   colind,
                   rowptr,
                   0, // firstentry
                   R,
                   sizeof(nzval[0]));
30.9.5.64 starpu_bcsr_get_nnz()
uint32_t starpu_bcsr_get_nnz (
               starpu_data_handle_t handle )
Return the number of non-zero elements in the matrix designated by handle.
30.9.5.65 starpu_bcsr_get_nrow()
uint32_t starpu_bcsr_get_nrow (
                starpu_data_handle_t handle )
Return the number of rows (in terms of blocks of size r*c) in the matrix designated by handle.
30.9.5.66 starpu_bcsr_get_firstentry()
uint32_t starpu_bcsr_get_firstentry (
               starpu_data_handle_t handle )
Return the index at which all arrays (the column indexes, the row pointers...) of the matrix desginated by handle.
30.9.5.67 starpu_bcsr_get_local_nzval()
uintptr_t starpu_bcsr_get_local_nzval (
               starpu_data_handle_t handle )
Return a pointer to the non-zero values of the matrix designated by handle.
```

30.9.5.68 starpu_bcsr_get_local_colind()

Return a pointer to the column index, which holds the positions of the non-zero entries in the matrix designated by handle.

```
30.9.5.69 starpu_bcsr_get_local_rowptr()
```

Return the row pointer array of the matrix designated by handle.

```
30.9.5.70 starpu_bcsr_get_r()
```

Return the number of rows in a block.

30.9.5.71 starpu_bcsr_get_c()

Return the number of columns in a block.

30.9.5.72 starpu_bcsr_get_elemsize()

Return the size of the elements in the matrix designated by handle.

30.9.5.73 starpu_multiformat_data_register()

Register a piece of data that can be represented in different ways, depending upon the processing unit that manipulates it. It allows the programmer, for instance, to use an array of structures when working on a CPU, and a structure of arrays when working on a GPU. nobjects is the number of elements in the data. format_ops describes the format.

30.9.5.74 starpu_hash_crc32c_be_n()

Compute the CRC of a byte buffer seeded by the inputere *current state*. The return value should be considered as the new *current state* for future CRC computation. This is used for computing data size footprint.

30.9.5.75 starpu_hash_crc32c_be()

Compute the CRC of a 32bit number seeded by the inputere current state. The return value should be considered as the new current state for future CRC computation. This is used for computing data size footprint.

30.9.5.76 starpu_hash_crc32c_string()

Compute the CRC of a string seeded by the inputoro *current state*. The return value should be considered as the new *current state* for future CRC computation. This is used for computing data size footprint.

30.10 Data Partition

Data Structures

· struct starpu_data_filter

Basic API

- void starpu_data_partition (starpu_data_handle_t initial_handle, struct starpu_data_filter *f)
- void starpu data unpartition (starpu data handle t root data, unsigned gathering node)
- starpu_data_handle_t starpu_data_get_child (starpu_data_handle_t handle, unsigned i)
- int starpu data get nb children (starpu data handle t handle)
- starpu_data_handle_t starpu_data_get_sub_data (starpu_data_handle_t root_data, unsigned depth,...)
- starpu_data_handle_t starpu_data_vget_sub_data (starpu_data_handle_t root_data, unsigned depth, va_list pa)
- void starpu data map filters (starpu data handle t root data, unsigned nfilters,...)
- void starpu_data_vmap_filters (starpu_data_handle_t root_data, unsigned nfilters, va_list pa)

Asynchronous API

- void starpu_data_partition_plan (starpu_data_handle_t initial_handle, struct starpu_data_filter *f, starpu_
 data_handle_t *children)
- void starpu_data_partition_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_
 handle t *children)
- void starpu_data_partition_readonly_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu
 __data_handle_t *children)
- void starpu_data_partition_readwrite_upgrade_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children)
- void starpu_data_unpartition_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_
 handle_t *children, int gathering_node)
- void starpu_data_unpartition_submit_r (starpu_data_handle_t initial_handle, int gathering_node)
- void starpu_data_unpartition_readonly_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int gathering_node)
- void starpu_data_partition_clean (starpu_data_handle_t root_data, unsigned nparts, starpu_data_handle_t *children)
- void starpu_data_unpartition_submit_sequential_consistency_cb (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int gather_node, int sequential_consistency, void(*callback
 _func)(void *), void *callback_arg)
- void starpu_data_partition_submit_sequential_consistency (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int sequential_consistency)
- void starpu_data_unpartition_submit_sequential_consistency (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int gathering_node, int sequential_consistency)
- void starpu_data_partition_not_automatic (starpu_data_handle_t handle)

30.10 Data Partition 261

Predefined BCSR Filter Functions

Predefined partitioning functions for BCSR data. Examples on how to use them are shown in Partitioning Data.

- void starpu_bcsr_filter_canonical_block (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)
- struct starpu_data_interface_ops * starpu_bcsr_filter_canonical_block_child_ops (struct starpu_data_filter *f, unsigned child)

Predefined CSR Filter Functions

Predefined partitioning functions for CSR data. Examples on how to use them are shown in Partitioning Data.

• void starpu_csr_filter_vertical_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)

Predefined Matrix Filter Functions

Predefined partitioning functions for matrix data. Examples on how to use them are shown in Partitioning Data.

- void starpu_matrix_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data_
 —
 filter *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_vertical_block (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_vertical_block_shadow (void *father_interface, void *child_interface, struct starpu
 __data_filter *f, unsigned id, unsigned nparts)

Predefined Vector Filter Functions

Predefined partitioning functions for vector data. Examples on how to use them are shown in Partitioning Data.

- void starpu_vector_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data_
 iller *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_list_long (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_list (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_divide_in_2 (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)

Predefined Block Filter Functions

Predefined partitioning functions for block data. Examples on how to use them are shown in Partitioning Data. An example is available in examples/filters/shadow3d.c

- void starpu_block_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)
- void starpu_block_filter_vertical_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_vertical_block_shadow (void *father_interface, void *child_interface, struct starpu
 __data_filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_depth_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)

- void starpu_block_filter_depth_block_shadow (void *father_interface, void *child_interface, struct starpu_
 data_filter *f, unsigned id, unsigned nparts)
- void starpu_filter_nparts_compute_chunk_size_and_offset (unsigned n, unsigned nparts, size_t elemsize, unsigned id, unsigned ld, unsigned *chunk size, size t *offset)

30.10.1 Detailed Description

30.10.2 Data Structure Documentation

30.10.2.1 struct starpu_data_filter

Describe a data partitioning operation, to be given to starpu_data_partition())

Data Fields

- void(* filter_func)(void *father_interface, void *child_interface, struct starpu_data_filter *, unsigned id, unsigned nparts)
- unsigned nchildren
- unsigned(* get_nchildren)(struct starpu_data_filter *, starpu_data_handle_t initial_handle)
- struct starpu_data_interface_ops *(* get_child_ops)(struct starpu_data_filter *, unsigned id)
- · unsigned filter arg
- void * filter_arg_ptr

30.10.2.1.1 Field Documentation

30.10.2.1.1.1 filter_func

void(* starpu_data_filter::filter_func) (void *father_interface, void *child_interface, struct starpu_data_filter *, unsigned id, unsigned nparts)

Fill the child_interface structure with interface information for the i -th child of the parent father_\Liminstate interface (among nparts). The filter structure is provided, allowing to inspect the starpu_data_filter\Liminstate interface and starpu_data_filter::filter_arg_ptr parameters. The details of what needs to be filled in child_\Liminstate interface vary according to the data interface, but generally speaking:

- id is usually just copied over from the father, when the sub data has the same structure as the father, e.g. a subvector is a vector, a submatrix is a matrix, etc. This is however not the case for instance when dividing a BCSR matrix into its dense blocks, which then are matrices.
- nx, ny and alike are usually divided by the number of subdata, depending how the subdivision is done (e.g. nx division vs ny division for vertical matrix division vs horizontal matrix division).
- 1d for matrix interfaces are usually just copied over: the leading dimension (ld) usually does not change.
- elemsize is usually just copied over.
- ptr, the pointer to the data, has to be computed according to i and the father's ptr, so as to point to the start of the sub data. This should however be done only if the father has ptr different from NULL: in the OpenCL case notably, the dev_handle and offset fields are used instead.
- dev_handle should be just copied over from the parent.
- offset has to be computed according to i and the father's offset, so as to provide the offset of the start of the sub data. This is notably used for the OpenCL case.

30.10.2.1.1.2 nchildren

unsigned starpu_data_filter::nchildren

Number of parts to partition the data into.

30.10 Data Partition 263

```
30.10.2.1.1.3 get_nchildren
```

```
unsigned(* starpu_data_filter::get_nchildren) (struct starpu_data_filter *, starpu_data_\leftarrow handle_t initial_handle)
```

Return the number of children. This can be used instead of starpu_data_filter::nchildren when the number of children depends on the actual data (e.g. the number of blocks in a sparse matrix).

```
30.10.2.1.1.4 get_child_ops
```

```
struct starpu_data_interface_ops*(* starpu_data_filter::get_child_ops) (struct starpu_data_← filter *, unsigned id)
```

When children use different data interface, return which interface is used by child number id.

```
30.10.2.1.1.5 filter_arg
```

```
unsigned starpu_data_filter::filter_arg
```

Additional parameter for the filter function

```
30.10.2.1.1.6 filter_arg_ptr
```

```
void* starpu_data_filter::filter_arg_ptr
```

Additional pointer parameter for the filter function, such as the sizes of the different parts.

30.10.3 Function Documentation

```
30.10.3.1 starpu_data_partition()
```

Request the partitioning of initial_handle into several subdata according to the filter f. Here an example of how to use the function.

```
struct starpu_data_filter f =
{
    .filter_func = starpu_matrix_filter_block,
    .nchildren = nslicesx
};
starpu_data_partition(A_handle, &f);
```

30.10.3.2 starpu_data_unpartition()

Unapply the filter which has been applied to root_data, thus unpartitioning the data. The pieces of data are collected back into one big piece in the gathering_node (usually STARPU_MAIN_RAM). Tasks working on the partitioned data will be waited for by starpu_data_unpartition().

Here an example of how to use the function.

```
starpu_data_unpartition(A_handle, STARPU_MAIN_RAM);
```

30.10.3.3 starpu_data_get_child()

Return the i -th child of the given handle, which must have been partitionned beforehand.

30.10.3.4 starpu_data_get_nb_children()

Return the number of children handle has been partitioned into.

30.10.3.5 starpu_data_get_sub_data()

After partitioning a StarPU data by applying a filter, starpu_data_get_sub_data() can be used to get handles for each of the data portions. root_data is the parent data that was partitioned. depth is the number of filters to traverse (in case several filters have been applied, to e.g. partition in row blocks, and then in column blocks), and the subsequent parameters are the indexes. The function returns a handle to the subdata. Here an example of how to use the function.

```
h = starpu_data_get_sub_data(A_handle, 1, taskx);
```

30.10.3.6 starpu_data_vget_sub_data()

Similar to starpu data get sub data() but use a va_list for the parameter list.

30.10.3.7 starpu_data_map_filters()

Apply nfilters filters to the handle designated by root_handle recursively. nfilters pointers to variables of the type starpu_data_filter should be given.

30.10.3.8 starpu_data_vmap_filters()

Apply nfilters to the handle designated by root_handle recursively. Use a va_list of pointers to variables of the type starpu data filter.

30.10.3.9 starpu_data_partition_plan()

Plan to partition initial_handle into several subdata according to the filter f. The handles are returned into the children array, which has to be the same size as the number of parts described in f. These handles are not immediately usable, starpu_data_partition_submit() has to be called to submit the actual partitioning. Here is an example of how to use the function:

```
starpu_data_handle_t children[nslicesx];
struct starpu_data_filter f =
```

30.10 Data Partition 265

```
.filter_func = starpu_matrix_filter_block,
.nchildren = nslicesx
};
starpu_data_partition_plan(A_handle, &f, children);
```

30.10.3.10 starpu_data_partition_submit()

Submit the actual partitioning of initial_handle into the nparts children handles. This call is asynchronous, it only submits that the partitioning should be done, so that the children handles can now be used to submit tasks, and initial_handle can not be used to submit tasks any more (to guarantee coherency). For instance,

```
starpu_data_partition_submit(A_handle, nslicesx, children);
```

30.10.3.11 starpu_data_partition_readonly_submit()

Similar to starpu_data_partition_submit(), but do not invalidate initial_handle. This allows to continue using it, but the application has to be careful not to write to initial_handle or children handles, only read from them, since the coherency is otherwise not guaranteed. This thus allows to submit various tasks which concurrently read from various partitions of the data.

When the application wants to write to initial_handle again, it should call starpu_data_unpartition_submit(), which will properly add dependencies between the reads on the children and the writes to be submitted. If instead the application wants to write to children handles, it should call starpu_data_partition_readwrite_\(\cup \) upgrade_submit(), which will correctly add dependencies between the reads on the initial_handle and the writes to be submitted.

30.10.3.12 starpu_data_partition_readwrite_upgrade_submit()

Assume that a partitioning of initial_handle has already been submited in readonly mode through starpu—data_partition_readonly_submit(), and will upgrade that partitioning into read-write mode for the children, by invalidating initial_handle, and adding the necessary dependencies.

30.10.3.13 starpu_data_unpartition_submit()

Assuming that initial_handle is partitioned into children, submit an unpartitionning of initial_\circ handle, i.e. submit a gathering of the pieces on the requested gathering_node memory node, and submit an invalidation of the children.

30.10.3.14 starpu_data_unpartition_readonly_submit()

Similar to starpu_data_partition_submit(), but do not invalidate initial_handle. This allows to continue using it, but the application has to be careful not to write to initial_handle or children handles, only read from them, since the coherency is otherwise not guaranteed. This thus allows to submit various tasks which concurrently read from various partitions of the data.

30.10.3.15 starpu_data_partition_clean()

Clear the partition planning established between root_data and children with starpu_data_partition_plan(). This will notably submit an unregister all the children, which can thus not be used any more afterwards.

30.10.3.16 starpu_data_unpartition_submit_sequential_consistency_cb()

Similar to starpu_data_unpartition_submit_sequential_consistency() but allow to specify a callback function for the unpartitiong task

30.10.3.17 starpu_data_partition_submit_sequential_consistency()

Similar to starpu_data_partition_submit() but also allow to specify the coherency to be used for the main data initial_handle through the parameter sequential_consistency.

30.10.3.18 starpu_data_unpartition_submit_sequential_consistency()

Similar to starpu_data_unpartition_submit() but also allow to specify the coherency to be used for the main data initial_handle through the parameter sequential_consistency.

30.10.3.19 starpu_data_partition_not_automatic()

30.10 Data Partition 267

Disable the automatic partitioning of the data handle for which a asynchronous plan has previously been submitted

```
30.10.3.20 starpu_bcsr_filter_canonical_block()
```

```
void starpu_bcsr_filter_canonical_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block-sparse matrix into dense matrices. starpu_data_filter::get_child_ops needs to be set to starpu_\(\lefta \) bcsr filter canonical block child ops()

30.10.3.21 starpu_bcsr_filter_canonical_block_child_ops()

Return the child_ops of the partition obtained with starpu_bcsr_filter_canonical_block().

30.10.3.22 starpu_csr_filter_vertical_block()

```
void starpu_csr_filter_vertical_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block-sparse matrix into vertical block-sparse matrices.

30.10.3.23 starpu_matrix_filter_block()

Partition a dense Matrix along the x dimension, thus getting (x/nparts ,y) matrices. If nparts does not divide x, the last submatrix contains the remainder.

30.10.3.24 starpu_matrix_filter_block_shadow()

```
void starpu_matrix_filter_block_shadow (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a dense Matrix along the x dimension, with a shadow border filter_arg_ptr, thus getting ((x-2*shadow)/nparts +2*shadow,y) matrices. If nparts does not divide x-2*shadow, the last submatrix contains the remainder.

IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. A usage example is available in examples/filters/shadow2d.c

30.10.3.25 starpu_matrix_filter_vertical_block()

```
void * child_interface,
struct starpu_data_filter * f,
unsigned id,
unsigned nparts )
```

Partition a dense Matrix along the y dimension, thus getting (x,y/nparts) matrices. If nparts does not divide y, the last submatrix contains the remainder.

30.10.3.26 starpu_matrix_filter_vertical_block_shadow()

Partition a dense Matrix along the y dimension, with a shadow border filter_arg_ptr, thus getting (x,(y-2*shadow)/nparts +2*shadow) matrices. If nparts does not divide y-2*shadow, the last submatrix contains the remainder.

IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. A usage example is available in examples/filters/shadow2d.c

30.10.3.27 starpu_vector_filter_block()

```
void starpu_vector_filter_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Return in child_interface the id th element of the vector represented by father_interface once partitioned in nparts chunks of equal size.

30.10.3.28 starpu_vector_filter_block_shadow()

```
void starpu_vector_filter_block_shadow (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Return in child_interface the id th element of the vector represented by father_interface once partitioned in nparts chunks of equal size with a shadow border filter_arg_ptr, thus getting a vector of size (n-2*shadow)/nparts+2*shadow. The filter_arg_ptr field of f must be the shadow size casted into void*.

IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. An usage example is available in examples/filters/shadow.c

30.10.3.29 starpu_vector_filter_list_long()

Return in child_interface the id th element of the vector represented by father_interface once partitioned into nparts chunks according to the filter_arg_ptr field of f. The filter_arg_ptr field must point to an array of nparts long elements, each of which specifies the number of elements in each chunk of the partition.

30.10 Data Partition 269

30.10.3.30 starpu_vector_filter_list()

```
void starpu_vector_filter_list (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Return in <code>child_interface</code> the <code>id</code> th element of the vector represented by <code>father_interface</code> once partitioned into <code>nparts</code> chunks according to the <code>filter_arg_ptr</code> field of <code>f</code>. The <code>filter_arg_ptr</code> field must point to an array of <code>nparts</code> uint32_t elements, each of which specifies the number of elements in each chunk of the partition.

30.10.3.31 starpu_vector_filter_divide_in_2()

```
void starpu_vector_filter_divide_in_2 (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Return in child_interface the id th element of the vector represented by father_interface once partitioned in 2 chunks of equal size, ignoring nparts. Thus, id must be 0 or 1.

30.10.3.32 starpu_block_filter_block()

```
void starpu_block_filter_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block along the X dimension, thus getting (x/nparts, y,z) 3D matrices. If nparts does not divide x, the last submatrix contains the remainder.

30.10.3.33 starpu_block_filter_block_shadow()

```
void starpu_block_filter_block_shadow (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block along the X dimension, with a shadow border filter_arg_ptr, thus getting ((x-2*shadow)/nparts +2*shadow,y,z) blocks. If nparts does not divide x, the last submatrix contains the remainder.

IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

30.10.3.34 starpu_block_filter_vertical_block()

```
void starpu_block_filter_vertical_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block along the Y dimension, thus getting (x,y/nparts,z) blocks. If nparts does not divide y, the last submatrix contains the remainder.

30.10.3.35 starpu_block_filter_vertical_block_shadow()

Partition a block along the Y dimension, with a shadow border filter_arg_ptr, thus getting (x,(y-2*shadow)/nparts +2*shadow,z) 3D matrices. If nparts does not divide y, the last submatrix contains the remainder.

IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

30.10.3.36 starpu_block_filter_depth_block()

```
void starpu_block_filter_depth_block (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block along the Z dimension, thus getting (x,y,z/nparts) blocks. If nparts does not divide z, the last submatrix contains the remainder.

30.10.3.37 starpu_block_filter_depth_block_shadow()

```
void starpu_block_filter_depth_block_shadow (
    void * father_interface,
    void * child_interface,
    struct starpu_data_filter * f,
    unsigned id,
    unsigned nparts )
```

Partition a block along the Z dimension, with a shadow border filter_arg_ptr, thus getting (x,y,(z-2*shadow)/nparts +2*shadow) blocks. If nparts does not divide z, the last submatrix contains the remainder. **IMPORTANT**: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

30.10.3.38 starpu_filter_nparts_compute_chunk_size_and_offset()

```
void starpu_filter_nparts_compute_chunk_size_and_offset (
    unsigned n,
    unsigned nparts,
    size_t elemsize,
    unsigned id,
    unsigned ld,
    unsigned * chunk_size,
    size t * offset )
```

Given an integer n, n the number of parts it must be divided in, id the part currently considered, determines the <code>chunk_size</code> and the <code>offset</code>, taking into account the size of the elements stored in the data structure <code>elemsize</code> and <code>ld</code>, the leading dimension, which is most often 1.

30.11 Out Of Core

Data Structures

struct starpu_disk_ops

Macros

• #define STARPU_DISK_SIZE_MIN

30.11 Out Of Core 271

Functions

- void starpu disk close (unsigned node, void *obj, size t size)
- void * starpu_disk_open (unsigned node, void *pos, size_t size)
- int starpu_disk_register (struct starpu_disk_ops *func, void *parameter, starpu_ssize_t size)

Variables

- · struct starpu disk ops starpu disk stdio ops
- struct starpu_disk_ops starpu_disk_hdf5_ops
- · struct starpu disk ops starpu disk unistd ops
- struct starpu_disk_ops starpu_disk_unistd_o_direct_ops
- struct starpu_disk_ops starpu_disk_leveldb_ops
- · int starpu_disk_swap_node

30.11.1 Detailed Description

30.11.2 Data Structure Documentation

30.11.2.1 struct starpu_disk_ops

Set of functions to manipulate datas on disk.

Data Fields

- void *(* plug)(void *parameter, starpu_ssize_t size)
- void(* unplug)(void *base)
- int(* bandwidth)(unsigned node, void *base)
- void *(* alloc)(void *base, size_t size)
- void(* free)(void *base, void *obj, size_t size)
- void *(* open)(void *base, void *pos, size_t size)
- void(* close)(void *base, void *obj, size_t size)
- int(* read)(void *base, void *obj, void *buf, off t offset, size t size)
- int(* write)(void *base, void *obj, const void *buf, off_t offset, size_t size)
- int(* full_read)(void *base, void *obj, void **ptr, size_t *size, unsigned dst_node)
- int(* full_write)(void *base, void *obj, void *ptr, size_t size)
- void *(* async write)(void *base, void *obj, void *buf, off t offset, size t size)
- void *(* async_read)(void *base, void *obj, void *buf, off_t offset, size_t size)
- void *(* async_full_read)(void *base, void *obj, void **ptr, size_t *size, unsigned dst_node)
- void *(* async_full_write)(void *base, void *obj, void *ptr, size_t size)
- void *(* copy)(void *base_src, void *obj_src, off_t offset_src, void *base_dst, void *obj_dst, off_t offset_dst, size_t size)
- void(* wait_request)(void *async_channel)
- int(* test_request)(void *async_channel)
- void(* free_request)(void *async_channel)

30.11.2.1.1 Field Documentation

```
30.11.2.1.1.1 plug
```

```
void*(* starpu_disk_ops::plug) (void *parameter, starpu_ssize_t size)
```

Connect a disk memory at location parameter with size size, and return a base as void*, which will be passed by StarPU to all other methods.

```
30.11.2.1.1.2 unplug
```

```
void(* starpu_disk_ops::unplug) (void *base)
```

Disconnect a disk memory base.

30.11.2.1.1.3 bandwidth

int(* starpu_disk_ops::bandwidth) (unsigned node, void *base)

Measure the bandwidth and the latency for the disk node and save it. Returns 1 if it could measure it.

30.11.2.1.1.4 alloc

void*(* starpu_disk_ops::alloc) (void *base, size_t size)

Create a new location for datas of size size. Return an opaque object pointer.

30.11.2.1.1.5 free

void(* starpu_disk_ops::free) (void *base, void *obj, size_t size)

Free a data obj previously allocated with starpu disk ops::alloc.

30.11.2.1.1.6 open

void*(* starpu_disk_ops::open) (void *base, void *pos, size_t size)

Open an existing location of datas, at a specific position pos dependent on the backend.

30.11.2.1.1.7 close

void(* starpu_disk_ops::close) (void *base, void *obj, size_t size)

Close, without deleting it, a location of datas obj.

30.11.2.1.1.8 read

int(* starpu_disk_ops::read) (void *base, void *obj, void *buf, off_t offset, size_t size)

Read size bytes of data from obj in base, at offset offset, and put into buf. Return the actual number of read bytes.

30.11.2.1.1.9 write

int(* starpu_disk_ops::write) (void *base, void *obj, const void *buf, off_t offset, size_←
t size)

Write size bytes of data to obj in base, at offset offset, from buf. Return 0 on success.

30.11.2.1.1.10 full_read

int(* starpu_disk_ops::full_read) (void *base, void *obj, void **ptr, size_t *size, unsigned
dst_node)

Read all data from obj of base, from offset 0. Returns it in an allocated buffer ptr, of size size

30.11.2.1.1.11 full_write

int(* starpu_disk_ops::full_write) (void *base, void *obj, void *ptr, size_t size)

Write data in ptr to obj of base, from offset 0, and truncate obj to size, so that a full_read will get it.

30.11.2.1.1.12 async_write

void*(* starpu_disk_ops::async_write) (void *base, void *obj, void *buf, off_t offset, size_t
size)

Asynchronously write size bytes of data to obj in base, at offset offset, from buf. Return a void* pointer that StarPU will pass to xxx_request methods for testing for the completion.

30.11.2.1.1.13 async_read

void*(* starpu_disk_ops::async_read) (void *base, void *obj, void *buf, off_t offset, size_← t size)

Asynchronously read size bytes of data from obj in base, at offset offset, and put into buf. Return a void* pointer that StarPU will pass to xxx request methods for testing for the completion.

30.11.2.1.1.14 async_full_read

void*(* starpu_disk_ops::async_full_read) (void *base, void *obj, void **ptr, size_t *size,
unsigned dst_node)

Read all data from obj of base, from offset 0. Return it in an allocated buffer ptr, of size size

30.11.2.1.1.15 async_full_write

void*(* starpu_disk_ops::async_full_write) (void *base, void *obj, void *ptr, size_t size)

Write data in ptr to obj of base, from offset 0, and truncate obj to size, so that a starpu_disk_ops::full_read will get it.

30.11 Out Of Core 273

30.11.2.1.1.16 copy

```
void*(* starpu_disk_ops::copy) (void *base_src, void *obj_src, off_t offset_src, void *base_↔ dst, void *obj_dst, off_t offset_dst, size_t size)
```

Copy from offset $offset_src$ of disk object obj_src in $base_src$ to offset $offset_dst$ of disk object obj_dst in $base_dst$. Return a void* pointer that StarPU will pass to $xxx_request$ methods for testing for the completion.

30.11.2.1.1.17 wait_request

```
void(* starpu_disk_ops::wait_request) (void *async_channel)
```

Wait for completion of request async_channel returned by a previous asynchronous read, write or copy.

30.11.2.1.1.18 test_request

```
int(* starpu_disk_ops::test_request) (void *async_channel)
```

Test for completion of request async_channel returned by a previous asynchronous read, write or copy. Return 1 on completion, 0 otherwise.

30.11.2.1.1.19 free_request

```
void(* starpu_disk_ops::free_request) (void *async_channel)
```

Free the request allocated by a previous asynchronous read, write or copy.

30.11.3 Macro Definition Documentation

30.11.3.1 STARPU_DISK_SIZE_MIN

```
#define STARPU_DISK_SIZE_MIN
```

Minimum size of a registered disk. The size of a disk is the last parameter of the function starpu_disk_register().

30.11.4 Function Documentation

30.11.4.1 starpu_disk_close()

```
void starpu_disk_close (
          unsigned node,
          void * obj,
          size_t size )
```

Close an existing data opened with starpu_disk_open().

30.11.4.2 starpu_disk_open()

```
void* starpu_disk_open (
          unsigned node,
          void * pos,
          size_t size )
```

Open an existing file memory in a disk node. size is the size of the file. pos is the specific position dependent on the backend, given to the open method of the disk operations. Return an opaque object pointer.

30.11.4.3 starpu_disk_register()

Register a disk memory node with a set of functions to manipulate datas. The plug member of func will be passed parameter, and return a base which will be passed to all func methods. SUCCESS: return the disk node.

FAIL: return an error code.

size must be at least STARPU_DISK_SIZE_MIN bytes! size being negative means infinite size.

30.11.5 Variable Documentation

```
30.11.5.1 starpu disk stdio ops
```

struct starpu_disk_ops starpu_disk_stdio_ops

Use the stdio library (fwrite, fread...) to read/write on disk.

Warning: It creates one file per allocation!

Do not support asynchronous transfers.

30.11.5.2 starpu_disk_hdf5_ops

struct starpu_disk_ops starpu_disk_hdf5_ops

Use the HDF5 library.

It doesn't support multiple opening from different processes.

You may only allow one process to write in the HDF5 file.

If HDF5 library is not compiled with -thread-safe you can't open more than one HDF5 file at the same time.

30.11.5.3 starpu_disk_unistd_ops

struct starpu_disk_ops starpu_disk_unistd_ops

Use the unistd library (write, read...) to read/write on disk.

Warning: It creates one file per allocation!

30.11.5.4 starpu_disk_unistd_o_direct_ops

struct starpu_disk_ops starpu_disk_unistd_o_direct_ops

Use the unistd library (write, read...) to read/write on disk with the O_DIRECT flag.

Warning: It creates one file per allocation!

Only available on Linux systems.

30.11.5.5 starpu_disk_leveldb_ops

```
struct starpu_disk_ops starpu_disk_leveldb_ops
```

Use the leveldb created by Google. More information at https://code.google.com/p/leveldb/ Do not support asynchronous transfers.

30.11.5.6 starpu_disk_swap_node

int starpu_disk_swap_node

Contain the node number of the disk swap, if set up through the STARPU_DISK_SWAP variable.

30.12 Codelet And Tasks

This section describes the interface to manipulate codelets and tasks.

Data Structures

- · struct starpu_codelet
- · struct starpu data descr
- struct starpu_task

30.12 Codelet And Tasks 275

Macros

- #define STARPU NMAXBUFS
- #define STARPU NOWHERE
- #define STARPU CPU
- #define STARPU CUDA
- #define STARPU_OPENCL
- #define STARPU MIC
- #define STARPU MPI MS
- #define STARPU CODELET SIMGRID EXECUTE
- #define STARPU CODELET SIMGRID EXECUTE AND INJECT
- #define STARPU_CODELET_NOPLANS
- #define STARPU_CUDA_ASYNC
- #define STARPU_OPENCL_ASYNC
- #define STARPU MAIN RAM
- #define STARPU MULTIPLE CPU IMPLEMENTATIONS
- #define STARPU MULTIPLE CUDA IMPLEMENTATIONS
- #define STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS
- #define STARPU VARIABLE NBUFFERS
- #define STARPU SPECIFIC NODE LOCAL
- #define STARPU SPECIFIC NODE CPU
- #define STARPU SPECIFIC NODE SLOW
- #define STARPU SPECIFIC NODE FAST
- #define STARPU TASK TYPE NORMAL
- #define STARPU TASK TYPE INTERNAL
- #define STARPU_TASK_TYPE_DATA_ACQUIRE
- #define STARPU_TASK_INITIALIZER
- #define STARPU TASK GET NBUFFERS(task)
- #define STARPU TASK GET HANDLE(task, i)
- #define STARPU_TASK_GET_HANDLES(task)
- #define STARPU TASK SET HANDLE(task, handle, i)
- #define STARPU_CODELET_GET_MODE(codelet, i)
- #define STARPU CODELET SET MODE(codelet, mode, i)
- #define STARPU_TASK_GET_MODE(task, i)
- #define STARPU TASK SET MODE(task, mode, i)
- #define STARPU_CODELET_GET_NODE(codelet, i)
- #define STARPU CODELET SET NODE(codelet, node, i)

Typedefs

- typedef void(* starpu_cpu_func_t) (void **, void *)
- typedef void(* starpu_cuda_func_t) (void **, void *)
- typedef void(* starpu opencl func t) (void **, void *)
- typedef void(* starpu_mic_kernel_t) (void **, void *)
- typedef starpu mic kernel t(* starpu mic func t) (void)
- typedef void(* starpu_mpi_ms_kernel_t) (void **, void *)
- typedef starpu_mpi_ms_kernel_t(* starpu_mpi_ms_func_t) (void)

Enumerations

- enum starpu codelet type { STARPU SEQ, STARPU SPMD, STARPU FORKJOIN }
- enum starpu task status {
 - STARPU TASK INVALID, STARPU TASK INVALID, STARPU TASK BLOCKED, STARPU TASK RE↔
 - STARPU TASK RUNNING, STARPU TASK FINISHED, STARPU TASK BLOCKED ON TAG, STAR↔ PU_TASK_BLOCKED_ON_TASK,
 - STARPU_TASK_BLOCKED_ON_DATA, STARPU_TASK_STOPPED }

Functions

- void starpu_task_init (struct starpu_task *task)
- void starpu task clean (struct starpu task *task)
- struct starpu_task * starpu_task_create (void) STARPU_ATTRIBUTE_MALLOC
- void starpu task destroy (struct starpu task *task)
- int starpu_task_submit (struct starpu_task *task) STARPU_WARN_UNUSED_RESULT
- int starpu task submit to ctx (struct starpu task *task, unsigned sched ctx id)
- int starpu task finished (struct starpu task *task) STARPU WARN UNUSED RESULT
- int starpu_task_wait (struct starpu_task *task) STARPU_WARN_UNUSED_RESULT
- int starpu_task_wait_array (struct starpu_task **tasks, unsigned nb_tasks) STARPU_WARN_UNUSED_←
 RESULT
- int starpu_task_wait_for_all (void)
- int starpu task wait for n submitted (unsigned n)
- int starpu task wait for all in ctx (unsigned sched ctx id)
- int starpu task wait for n submitted in ctx (unsigned sched ctx id, unsigned n)
- int starpu_task_wait_for_no_ready (void)
- int starpu_task_nready (void)
- int starpu_task_nsubmitted (void)
- void starpu iteration push (unsigned long iteration)
- void starpu_iteration_pop (void)
- · void starpu do schedule (void)
- void starpu codelet init (struct starpu codelet *cl)
- void starpu codelet display stats (struct starpu codelet *cl)
- struct starpu task * starpu task get current (void)
- int starpu_task_get_current_data_node (unsigned i)
- const char * starpu task get model name (struct starpu task *task)
- const char * starpu_task_get_name (struct starpu_task *task)
- struct starpu_task * starpu_task_dup (struct starpu_task *task)
- void starpu_task_set_implementation (struct starpu_task *task, unsigned impl)
- unsigned starpu_task_get_implementation (struct starpu_task *task)
- void starpu_create_sync_task (starpu_tag_t sync_tag, unsigned ndeps, starpu_tag_t *deps, void(*callback)(void *), void *callback arg)

30.12.1 Detailed Description

This section describes the interface to manipulate codelets and tasks.

30.12.2 Data Structure Documentation

30.12.2.1 struct starpu_codelet

The codelet structure describes a kernel that is possibly implemented on various targets. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset, or the function starpu_codelet_init(), or by letting the compiler implicitly do it in e.g. static storage case.

Data Fields

- · uint32 t where
- int(* can execute)(unsigned workerid, struct starpu task *task, unsigned nimpl)
- · enum starpu codelet type type
- · int max_parallelism
- starpu_cpu_func_t cpu_func
- starpu_cuda_func_t cuda_func
- starpu_opencl_func_t opencl_func
- starpu_cpu_func_t cpu_funcs [STARPU_MAXIMPLEMENTATIONS]
- starpu_cuda_func_t cuda_funcs [STARPU_MAXIMPLEMENTATIONS]

- char cuda_flags [STARPU_MAXIMPLEMENTATIONS]
- starpu opencl func topencl funcs [STARPU MAXIMPLEMENTATIONS]
- char opencl_flags [STARPU_MAXIMPLEMENTATIONS]
- starpu_mic_func_t mic_funcs [STARPU_MAXIMPLEMENTATIONS]
- starpu mpi ms func t mpi ms funcs [STARPU MAXIMPLEMENTATIONS]
- const char * cpu_funcs_name [STARPU_MAXIMPLEMENTATIONS]
- · int nbuffers
- enum starpu data access mode modes [STARPU NMAXBUFS]
- enum starpu_data_access_mode * dyn_modes
- unsigned specific_nodes
- int nodes [STARPU_NMAXBUFS]
- int * dyn nodes
- struct starpu_perfmodel * model
- struct starpu perfmodel * energy model
- unsigned long per_worker_stats [STARPU_NMAXWORKERS]
- const char * name
- · unsigned color
- int flags

30.12.2.1.1 Field Documentation

30.12.2.1.1.1 where

```
uint32_t starpu_codelet::where
```

Optional field to indicate which types of processing units are able to execute the codelet. The different values ST \leftarrow ARPU_CPU, STARPU_CUDA, STARPU_OPENCL can be combined to specify on which types of processing units the codelet can be executed. STARPU_CPU|STARPU_CUDA for instance indicates that the codelet is implemented for both CPU cores and CUDA devices while STARPU_OPENCL indicates that it is only available on OpenCL devices. If the field is unset, its value will be automatically set based on the availability of the XXX_funcs fields defined below. It can also be set to STARPU_NOWHERE to specify that no computation has to be actually done.

```
30.12.2.1.1.2 can execute
```

```
int(* starpu_codelet::can_execute) (unsigned workerid, struct starpu_task *task, unsigned
nimpl)
```

Define a function which should return 1 if the worker designated by workerid can execute the nimpl -th implementation of task, 0 otherwise.

```
30.12.2.1.1.3 type
```

```
enum starpu_codelet_type starpu_codelet::type
```

Optional field to specify the type of the codelet. The default is STARPU_SEQ, i.e. usual sequential implementation. Other values (STARPU_SPMD or STARPU_FORKJOIN) declare that a parallel implementation is also available. See Parallel Tasks for details.

```
30.12.2.1.1.4 max_parallelism
```

```
int starpu_codelet::max_parallelism
```

Optional field. If a parallel implementation is available, this denotes the maximum combined worker size that StarPU will use to execute parallel tasks for this codelet.

```
30.12.2.1.1.5 cpu_func
```

```
starpu_cpu_func_t starpu_codelet::cpu_func
```

30.12.2.1.1.6 cuda_func

starpu_cuda_func_t starpu_codelet::cuda_func

Deprecated Optional field which has been made deprecated. One should use instead the starpu_codelet::cuda ← funcs field.

30.12.2.1.1.7 opencl_func

starpu_opencl_func_t starpu_codelet::opencl_func

Deprecated Optional field which has been made deprecated. One should use instead the starpu_codelet::opencl ← __funcs field.

30.12.2.1.1.8 cpu_funcs

starpu_cpu_func_t starpu_codelet::cpu_funcs[STARPU_MAXIMPLEMENTATIONS]

Optional array of function pointers to the CPU implementations of the codelet. The functions prototype must be:

```
void cpu_func(void *buffers[], void *cl_arg)
```

The first argument being the array of data managed by the data management library, and the second argument is a pointer to the argument passed from the field starpu_task::cl_arg. If the field starpu_codelet::where is set, then the field tarpu_codelet::where, it must be non-NULL otherwise.

30.12.2.1.1.9 cuda_funcs

starpu_cuda_func_t starpu_codelet::cuda_funcs[STARPU_MAXIMPLEMENTATIONS]

Optional array of function pointers to the CUDA implementations of the codelet. The functions must be host-functions written in the CUDA runtime API. Their prototype must be:

```
void cuda_func(void *buffers[], void *cl_arg)
```

If the field starpu_codelet::where is set, then the field starpu_codelet::cuda_funcs is ignored if STARPU_CUDA does not appear in the field starpu_codelet::where, it must be non-NULL otherwise.

30.12.2.1.1.10 cuda_flags

char starpu_codelet::cuda_flags[STARPU_MAXIMPLEMENTATIONS]

Optional array of flags for CUDA execution. They specify some semantic details about CUDA kernel execution, such as asynchronous execution.

30.12.2.1.1.11 opencl_funcs

starpu_opencl_func_t starpu_codelet::opencl_funcs[STARPU_MAXIMPLEMENTATIONS]

Optional array of function pointers to the OpenCL implementations of the codelet. The functions prototype must be:

```
void opencl_func(void *buffers[], void *cl_arg)
```

If the field starpu_codelet::where field is set, then the field starpu_codelet::opencl_funcs is ignored if STARPU_ \leftarrow OPENCL does not appear in the field starpu_codelet::where, it must be non-NULL otherwise.

30.12.2.1.1.12 opencl_flags

```
char starpu_codelet::opencl_flags[STARPU_MAXIMPLEMENTATIONS]
```

Optional array of flags for OpenCL execution. They specify some semantic details about OpenCL kernel execution, such as asynchronous execution.

30.12.2.1.1.13 mic_funcs

```
starpu_mic_func_t starpu_codelet::mic_funcs[STARPU_MAXIMPLEMENTATIONS]
```

Optional array of function pointers to a function which returns the MIC implementation of the codelet. The functions prototype must be:

```
starpu_mic_kernel_t mic_func(struct starpu_codelet *cl, unsigned nimpl)
```

If the field starpu_codelet::where is set, then the field starpu_codelet::mic_funcs is ignored if STARPU_MIC does not appear in the field starpu_codelet::where. It can be <code>NULL</code> if starpu_codelet::cpu_funcs_name is non-<code>NULL</code>, in which case StarPU will simply make a symbol lookup to get the implementation.

```
30.12.2.1.1.14 mpi_ms_funcs
```

```
starpu_mpi_ms_func_t starpu_codelet::mpi_ms_funcs[STARPU_MAXIMPLEMENTATIONS]
```

Optional array of function pointers to a function which returns the MPI Master Slave implementation of the codelet. The functions prototype must be:

If the field starpu_codelet::where is set, then the field starpu_codelet::mpi_ms_funcs is ignored if STARPU_M PI_MS does not appear in the field starpu_codelet::where. It can be NULL if starpu_codelet::cpu_funcs_name is non-NULL, in which case StarPU will simply make a symbol lookup to get the implementation.

```
30.12.2.1.1.15 cpu_funcs_name
```

```
const char* starpu_codelet::cpu_funcs_name[STARPU_MAXIMPLEMENTATIONS]
```

Optional array of strings which provide the name of the CPU functions referenced in the array starpu_codelet::cpu _ funcs. This can be used when running on MIC devices for StarPU to simply look up the MIC function implementation through its name.

```
30.12.2.1.1.16 nbuffers
```

```
int starpu_codelet::nbuffers
```

Specify the number of arguments taken by the codelet. These arguments are managed by the DSM and are accessed from the <code>void *buffers[]</code> array. The constant argument passed with the field <code>starpu_task::cl_arg</code> is not counted in this number. This value should not be above <code>STARPU_NMAXBUFS</code>. It may be set to <code>STARPU_</code> VARIABLE_NBUFFERS to specify that the number of buffers and their access modes will be set in <code>starpu_task</code>::nbuffers and <code>starpu_task::modes</code> or <code>starpu_task::dyn_modes</code>, which thus permits to define codelets with a varying number of data.

```
30.12.2.1.1.17 modes
```

```
enum starpu_data_access_mode starpu_codelet::modes[STARPU_NMAXBUFS]
```

Is an array of starpu_data_access_mode. It describes the required access modes to the data needed by the codelet (e.g. STARPU_RW). The number of entries in this array must be specified in the field starpu_codelet ::nbuffers, and should not exceed STARPU_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers.

```
30.12.2.1.1.18 dyn_modes
```

```
enum starpu_data_access_mode* starpu_codelet::dyn_modes
```

Is an array of starpu_data_access_mode. It describes the required access modes to the data needed by the codelet (e.g. STARPU_RW). The number of entries in this array must be specified in the field starpu_codelet::nbuffers. This field should be used for codelets having a number of datas greater than STARPU_NMAXBUFS (see Setting Many Data Handles For a Task). When defining a codelet, one should either define this field or the field starpu_codelet ::modes defined above.

```
30.12.2.1.1.19 specific_nodes
```

```
unsigned starpu_codelet::specific_nodes
```

Default value is 0. If this flag is set, StarPU will not systematically send all data to the memory node where the task will be executing, it will read the starpu_codelet::nodes or starpu_codelet::dyn_nodes array to determine, for each data, whether to send it on the memory node where the task will be executing (-1), or on a specific node (!= -1).

```
30.12.2.1.1.20 nodes
```

```
int starpu_codelet::nodes[STARPU_NMAXBUFS]
```

Optional field. When starpu_codelet::specific_nodes is 1, this specifies the memory nodes where each data should be sent to for task execution. The number of entries in this array is starpu_codelet::nbuffers, and should not exceed STARPU_NMAXBUFS.

```
30.12.2.1.1.21 dyn_nodes
```

```
\verb"int* starpu_codelet::dyn_nodes"
```

Optional field. When starpu_codelet::specific_nodes is 1, this specifies the memory nodes where each data should be sent to for task execution. The number of entries in this array is starpu_codelet::nbuffers. This field should be used for codelets having a number of datas greater than STARPU_NMAXBUFS (see Setting Many Data Handles For a Task). When defining a codelet, one should either define this field or the field starpu_codelet::nodes defined above.

30.12.2.1.1.22 model

```
struct starpu_perfmodel* starpu_codelet::model
```

Optional pointer to the task duration performance model associated to this codelet. This optional field is ignored when set to NULL or when its field starpu perfmodel::symbol is not set.

```
30.12.2.1.1.23 energy_model
```

```
struct starpu_perfmodel* starpu_codelet::energy_model
```

Optional pointer to the task energy consumption performance model associated to this codelet. This optional field is ignored when set to <code>NULL</code> or when its field starpu_perfmodel::symbol is not set. In the case of parallel codelets, this has to account for all processing units involved in the parallel execution.

```
30.12.2.1.1.24 per_worker_stats
```

```
unsigned long starpu_codelet::per_worker_stats[STARPU_NMAXWORKERS]
```

Optional array for statistics collected at runtime: this is filled by StarPU and should not be accessed directly, but for example by calling the function starpu_codelet_display_stats() (See starpu_codelet_display_stats() for details).

```
30.12.2.1.1.25 name
```

```
const char* starpu_codelet::name
```

Optional name of the codelet. This can be useful for debugging purposes.

```
30.12.2.1.1.26 color
```

```
unsigned starpu_codelet::color
```

Optional color of the codelet. This can be useful for debugging purposes.

30.12.2.1.1.27 flags

```
int starpu_codelet::flags
```

Various flags for the codelet.

30.12.2.2 struct starpu_data_descr

Describe a data handle along with an access mode.

Data Fields

| starpu_data_handle_t | handle | data |
|------------------------------|--------|-------------|
| enum starpu_data_access_mode | mode | access mode |

30.12.2.3 struct starpu_task

Describe a task that can be offloaded on the various processing units managed by StarPU. It instantiates a codelet. It can either be allocated dynamically with the function starpu_task_create(), or declared statically. In the latter case, the programmer has to zero the structure starpu_task and to fill the different fields properly. The indicated default values correspond to the configuration of a task allocated with starpu_task create().

Data Fields

- const char * name
- struct starpu_codelet * cl
- · int32_t where
- · int nbuffers
- starpu_data_handle_t * dyn_handles
- void ** dyn_interfaces
- enum starpu_data_access_mode * dyn_modes
- starpu data handle t handles [STARPU NMAXBUFS]
- void * interfaces [STARPU NMAXBUFS]
- enum starpu data access mode modes [STARPU NMAXBUFS]
- unsigned char * handles_sequential_consistency

- void * cl_arg
- size_t cl_arg_size
- void(* callback_func)(void *)
- void * callback arg
- void(* prologue_callback_func)(void *)
- void * prologue_callback_arg
- void(* prologue_callback_pop_func)(void *)
- void * prologue_callback_pop_arg
- · starpu_tag_t tag_id
- · unsigned cl arg free:1
- unsigned callback_arg_free:1
- unsigned prologue_callback_arg_free:1
- unsigned prologue_callback_pop_arg_free:1
- unsigned use_tag:1
- · unsigned sequential_consistency:1
- unsigned synchronous:1
- unsigned execute_on_a_specific_worker:1
- unsigned detach:1
- · unsigned destroy:1
- · unsigned regenerate:1
- unsigned no_submitorder:1
- unsigned scheduled:1
- unsigned prefetched:1
- · unsigned workerid
- · unsigned workerorder
- uint32_t * workerids
- unsigned workerids_len
- · int priority
- enum starpu task status status
- unsigned type
- unsigned color
- unsigned sched ctx
- · int hypervisor_tag
- unsigned possibly_parallel
- starpu_task_bundle_t bundle
- struct starpu_profiling_task_info * profiling_info
- double flops
- double predicted
- double predicted_transfer
- double predicted_start
- void * sched_data

Private Attributes

- unsigned mf_skip:1
- int magic
- struct starpu task * prev
- struct starpu_task * next
- void * starpu_private
- struct starpu_omp_task * omp_task
- unsigned nb_termination_call_required

30.12.2.3.1 Field Documentation

30.12.2.3.1.1 name

const char* starpu_task::name

Optional name of the task. This can be useful for debugging purposes.

With starpu task insert() and alike this can be specified thanks to STARPU NAME followed by the const char *.

30.12.2.3.1.2 cl

struct starpu_codelet* starpu_task::cl

Pointer to the corresponding structure starpu_codelet. This describes where the kernel should be executed, and supplies the appropriate implementations. When set to <code>NULL</code>, no code is executed during the tasks, such empty tasks can be useful for synchronization purposes.

30.12.2.3.1.3 where

int32_t starpu_task::where

When set, specify where the task is allowed to be executed. When unset, take the value of starpu_codelet::where. With starpu_task_insert() and alike this can be specified thanks to STARPU_EXECUTE_WHERE followed by an unsigned long long.

30.12.2.3.1.4 nbuffers

int starpu_task::nbuffers

Specify the number of buffers. This is only used when starpu_codelet::nbuffers is STARPU_VARIABLE_NBUFF ← ERS.

With starpu task insert() and alike this is automatically computed when using ::STARPU DATA ARRAY and alike.

30.12.2.3.1.5 dyn_handles

starpu_data_handle_t* starpu_task::dyn_handles

Array of starpu_data_handle_t. Specify the handles to the different pieces of data accessed by the task. The number of entries in this array must be specified in the field starpu_codelet::nbuffers. This field should be used for tasks having a number of datas greater than STARPU_NMAXBUFS (see <a href="setting Many Data Handles For a Task). When defining a task, one should either define this field or the field starpu_task::handles defined below.

With starpu_task_insert() and alike this is automatically filled when using ::STARPU_DATA_ARRAY and alike.

30.12.2.3.1.6 dyn_interfaces

void** starpu_task::dyn_interfaces

Array of data pointers to the memory node where execution will happen, managed by the DSM. Is used when the field starpu_task::dyn_handles is defined.

This is filled by StarPU.

30.12.2.3.1.7 dyn_modes

enum starpu_data_access_mode* starpu_task::dyn_modes

Used only when starpu_codelet::nbuffers is STARPU_VARIABLE_NBUFFERS. Array of starpu_data_access_ ← mode which describes the required access modes to the data needed by the codelet (e.g. STARPU_RW). The number of entries in this array must be specified in the field starpu_codelet::nbuffers. This field should be used for codelets having a number of datas greater than STARPU_NMAXBUFS (see Setting Many Data Handles For a Task). When defining a codelet, one should either define this field or the field starpu_task::modes defined below. With starpu_task_insert() and alike this is automatically filled when using ::STARPU_DATA_MODE_ARRAY and alike.

30.12.2.3.1.8 handles

starpu_data_handle_t starpu_task::handles[STARPU_NMAXBUFS]

Array of starpu_data_handle_t. Specify the handles to the different pieces of data accessed by the task. The number of entries in this array must be specified in the field starpu_codelet::nbuffers, and should not exceed ST ARPU_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers. With starpu_task_insert() and alike this is automatically filled when using STARPU_R and alike.

30.12.2.3.1.9 interfaces

void* starpu_task::interfaces[STARPU_NMAXBUFS]

Array of Data pointers to the memory node where execution will happen, managed by the DSM. This is filled by StarPU.

30.12.2.3.1.10 modes

enum starpu_data_access_mode starpu_task::modes[STARPU_NMAXBUFS]

Used only when starpu_codelet::nbuffers is STARPU_VARIABLE_NBUFFERS. Array of starpu_data_access_ ← mode which describes the required access modes to the data neeeded by the codelet (e.g. STARPU_RW). The number of entries in this array must be specified in the field starpu_task::nbuffers, and should not exceed STAR ← PU_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers.

With starpu_task_insert() and alike this is automatically filled when using ::STARPU_DATA_MODE_ARRAY and alike.

30.12.2.3.1.11 handles_sequential_consistency

unsigned char* starpu_task::handles_sequential_consistency

Optional pointer to an array of characters which allows to define the sequential consistency for each handle for the current task.

With starpu_task_insert() and alike this can be specified thanks to STARPU_HANDLES_SEQUENTIAL_CONSI

STENCY followed by an unsigned char *

30.12.2.3.1.12 cl_arg

void* starpu task::cl arg

Optional pointer which is passed to the codelet through the second argument of the codelet implementation (e.g. starpu_codelet::cpu_func or starpu_codelet::cuda_func). The default value is NULL. starpu_codelet_pack_args() and starpu_codelet_unpack_args() are helpers that can can be used to respectively pack and unpack data into and from it, but the application can manage it any way, the only requirement is that the size of the data must be set in starpu_task::cl_arg_size.

With starpu_task_insert() and alike this can be specified thanks to STARPU_CL_ARGS followed by a void* and a size t.

30.12.2.3.1.13 cl_arg_size

size_t starpu_task::cl_arg_size

Optional field. For some specific drivers, the pointer starpu_task::cl_arg cannot not be directly given to the driver function. A buffer of size starpu_task::cl_arg_size needs to be allocated on the driver. This buffer is then filled with the starpu_task::cl_arg_size bytes starting at address starpu_task::cl_arg. In this case, the argument given to the codelet is therefore not the starpu_task::cl_arg pointer, but the address of the buffer in local store (LS) instead. This field is ignored for CPU, CUDA and OpenCL codelets, where the starpu_task::cl_arg pointer is given as such. With starpu_task insert() and alike this can be specified thanks to STARPU_CL_ARGS followed by a void* and a

With starpu_task_insert() and alike this can be specified thanks to STARPU_CL_ARGS followed by a void* and a size_t.

```
void(* starpu_task::callback_func) (void *)
```

Optional field, the default value is NULL. This is a function pointer of prototype void (*f) (void *) which specifies a possible callback. If this pointer is non-NULL, the callback function is executed on the host after the execution of the task. Tasks which depend on it might already be executing. The callback is passed the value contained in the starpu_task::callback_arg field. No callback is executed if the field is set to NULL.

With starpu_task_insert() and alike this can be specified thanks to STARPU_CALLBACK followed by the function pointer, or thanks to STARPU_CALLBACK_WITH_ARG followed by the function pointer and the argument.

30.12.2.3.1.15 callback_arg

```
void* starpu_task::callback_arg
```

Optional field, the default value is NULL. This is the pointer passed to the callback function. This field is ignored if the field starpu_task::callback_func is set to NULL.

With starpu_task_insert() and alike this can be specified thanks to STARPU_CALLBACK_ARG followed by the function pointer, or thanks to STARPU_CALLBACK_WITH_ARG followed by the function pointer and the argument.

30.12.2.3.1.16 prologue_callback_func

```
void(* starpu_task::prologue_callback_func) (void *)
```

Optional field, the default value is \mathtt{NULL} . This is a function pointer of prototype \mathtt{void} (*f) (\mathtt{void} *) which specifies a possible callback. If this pointer is non- \mathtt{NULL} , the callback function is executed on the host when the task becomes ready for execution, before getting scheduled. The callback is passed the value contained in the starpu task::prologue callback arg field. No callback is executed if the field is set to \mathtt{NULL} .

With starpu_task_insert() and alike this can be specified thanks to ::STARPU_PROLOGUE_CALLBACK followed by the function pointer.

30.12.2.3.1.17 prologue_callback_arg

void* starpu_task::prologue_callback_arg

Optional field, the default value is NULL. This is the pointer passed to the prologue callback function. This field is ignored if the field starpu_task::prologue_callback_func is set to NULL.

With starpu_task_insert() and alike this can be specified thanks to ::STARPU_PROLOGUE_CALLBACK followed by the function pointer.

30.12.2.3.1.18 tag_id

starpu_tag_t starpu_task::tag_id

Optional field. Contain the tag associated to the task if the field starpu_task::use_tag is set, ignored otherwise. With starpu_task insert() and alike this can be specified thanks to STARPU_TAG followed by a starpu_tag t.

30.12.2.3.1.19 cl_arg_free

unsigned starpu_task::cl_arg_free

Optional field. In case $starpu_task::cl_arg$ was allocated by the application through malloc(), setting $starpu_task::cl_arg_free$ to 1 makes StarPU automatically call $free(cl_arg)$ when destroying the task. This saves the user from defining a callback just for that. This is mostly useful when targetting MIC, where the codelet does not execute in the same memory space as the main thread.

With starpu_task_insert() and alike this is set to 1 when using STARPU_CL_ARGS.

30.12.2.3.1.20 callback_arg_free

unsigned starpu_task::callback_arg_free

Optional field. In case starpu_task::callback_arg was allocated by the application through malloc(), setting starpu_task::callback_arg_free to 1 makes StarPU automatically call free (callback_arg) when destroying the task.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.21 prologue_callback_arg_free

 $\verb"unsigned starpu_task::prologue_callback_arg_free"$

Optional field. In case starpu_task::prologue_callback_arg was allocated by the application through malloc(), setting starpu_task::prologue_callback_arg_free to 1 makes StarPU automatically call $free(prologue_callback_arg)$ when destroying the task.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.22 prologue_callback_pop_arg_free

unsigned starpu_task::prologue_callback_pop_arg_free

Optional field. In case $starpu_task::prologue_callback_pop_arg$ was allocated by the application through malloc(), $setting starpu_task::prologue_callback_pop_arg_free$ to 1 makes StarPU automatically call $free(prologue_callback_pop_arg)$ when destroying the task.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.23 use_tag

unsigned starpu_task::use_tag

Optional field, the default value is 0. If set, this flag indicates that the task should be associated with the tag contained in the starpu_task::tag_id field. Tag allow the application to synchronize with the task and to express task dependencies easily.

With starpu_task_insert() and alike this is set to 1 when using STARPU_TAG.

30.12.2.3.1.24 sequential_consistency

unsigned starpu_task::sequential_consistency

If this flag is set (which is the default), sequential consistency is enforced for the data parameters of this task for which sequential consistency is enabled. Clearing this flag permits to disable sequential consistency for this task, even if data have it enabled.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.25 synchronous

unsigned starpu_task::synchronous

If this flag is set, the function starpu_task_submit() is blocking and returns only when the task has been executed (or if no worker is able to process the task). Otherwise, starpu_task_submit() returns immediately.

With starpu_task_insert() and alike this can be specified thanks to STARPU_TASK_SYNCHRONOUS followed an int.

30.12.2.3.1.26 execute_on_a_specific_worker

unsigned starpu_task::execute_on_a_specific_worker

Default value is 0. If this flag is set, StarPU will bypass the scheduler and directly affect this task to the worker specified by the field starpu task::workerid.

With starpu task insert() and alike this is set to 1 when using STARPU EXECUTE ON WORKER.

30.12.2.3.1.27 detach

unsigned starpu task::detach

Optional field, default value is 1. If this flag is set, it is not possible to synchronize with the task by the means of starpu_task_wait() later on. Internal data structures are only guaranteed to be freed once starpu_task_wait() is called if the flag is not set.

With starpu_task_insert() and alike this is set to 1.

30.12.2.3.1.28 destroy

unsigned starpu_task::destroy

Optional value. Default value is 0 for starpu_task_create(). If this flag is set, the task structure will automatically be freed, either after the execution of the callback if the task is detached, or during starpu_task_wait() otherwise. If this flag is not set, dynamically allocated data structures will not be freed until starpu_task_destroy() is called explicitly. Setting this flag for a statically allocated task structure will result in undefined behaviour. The flag is set to 1 when the task is created by calling starpu_task_wait_for_all() will not free any task.

With starpu_task_insert() and alike this is set to 1.

30.12.2.3.1.29 regenerate

unsigned starpu_task::regenerate

Optional field. If this flag is set, the task will be re-submitted to StarPU once it has been executed. This flag must not be set if the flag starpu_task::destroy is set. This flag must be set before making another task depend on this one.

With starpu_task_insert() and alike this is set to 0.

30.12.2.3.1.30 mf_skip

unsigned starpu_task::mf_skip [private]

This is only used for tasks that use multiformat handle. This should only be used by StarPU.

30.12.2.3.1.31 no_submitorder

 $\verb"unsigned starpu_task::no_submitorder"$

do not allocate a submitorder id for this task

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.32 scheduled

unsigned starpu_task::scheduled

Whether the scheduler has pushed the task on some queue

Set by StarPU.

30.12.2.3.1.33 workerid

unsigned starpu_task::workerid

Optional field. If the field starpu_task::execute_on_a_specific_worker is set, this field indicates the identifier of the worker that should process this task (as returned by starpu_worker_get_id()). This field is ignored if the field starpu task::execute on a specific worker is set to 0.

With starpu_task_insert() and alike this can be specified thanks to STARPU_EXECUTE_ON_WORKER followed by an int.

30.12.2.3.1.34 workerorder

 $\verb"unsigned starpu_task:: \verb"worker" order"$

Optional field. If the field starpu_task::execute_on_a_specific_worker is set, this field indicates the per-worker

consecutive order in which tasks should be executed on the worker. Tasks will be executed in consecutive starpu—
_task::workerorder values, thus ignoring the availability order or task priority. See Static Scheduling for more details.
This field is ignored if the field starpu_task::execute_on_a_specific_worker is set to 0.

With starpu_task_insert() and alike this can be specified thanks to STARPU_WORKER_ORDER followed by an unsigned.

30.12.2.3.1.35 workerids

uint32_t* starpu_task::workerids

Optional field. If the field starpu_task::workerids_len is different from 0, this field indicates an array of bits (stored as uint32_t values) which indicate the set of workers which are allowed to execute the task. starpu_task::workerid takes precedence over this.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.36 workerids_len

unsigned starpu_task::workerids_len

Optional field. This provides the number of uint32_t values in the starpu_task::workerids array.

TODO: does not have a starpu_task_insert() equivalent

30.12.2.3.1.37 priority

int starpu_task::priority

Optional field, the default value is STARPU_DEFAULT_PRIO. This field indicates a level of priority for the task. This is an integer value that must be set between the return values of the function starpu_sched_get_min_priority() for the least important tasks, and that of the function starpu_sched_get_max_priority() for the most important tasks (included). The STARPU_MIN_PRIO and STARPU_MAX_PRIO macros are provided for convenience and respectively return the value of starpu_sched_get_min_priority() and starpu_sched_get_max_priority(). Default priority is STARPU_DEFAULT_PRIO, which is always defined as 0 in order to allow static task initialization. Scheduling strategies that take priorities into account can use this parameter to take better scheduling decisions, but the scheduling policy may also ignore it.

With starpu_task_insert() and alike this can be specified thanks to STARPU_PRIORITY followed by an unsigned long long.

30.12.2.3.1.38 status

enum starpu_task_status starpu_task::status

Current state of the task.

Set by StarPU.

30.12.2.3.1.39 magic

int starpu_task::magic [private]

This field is set when initializing a task. The function starpu_task_submit() will fail if the field does not have the correct value. This will hence avoid submitting tasks which have not been properly initialised.

30.12.2.3.1.40 type

unsigned starpu_task::type

Allow to get the type of task, for filtering out tasks in profiling outputs, whether it is really internal to StarPU (::ST← ARPU_TASK_TYPE_INTERNAL), a data acquisition synchronization task (::STARPU_TASK_TYPE_DATA_AC← QUIRE), or a normal task (::STARPU_TASK_TYPE_NORMAL) Set by StarPU.

30.12.2.3.1.41 color

unsigned starpu_task::color

color of the task to be used in dag.dot.

With starpu_task_insert() and alike this can be specified thanks to STARPU_TASK_COLOR followed by an int.

30.12.2.3.1.42 sched_ctx

unsigned starpu_task::sched_ctx

Scheduling context.

With starpu_task_insert() and alike this can be specified thanks to STARPU_SCHED_CTX followed by an unsigned.

```
30.12.2.3.1.43 hypervisor_tag
int starpu_task::hypervisor_tag
Help the hypervisor monitor the execution of this task.
With starpu task insert() and alike this can be specified thanks to ::STARPU HYPERVISOR TAG followed by an
30.12.2.3.1.44 possibly_parallel
unsigned starpu_task::possibly_parallel
TODO: related with sched contexts and parallel tasks
With starpu_task_insert() and alike this can be specified thanks to ::STARPU_POSSIBLY_PARALLEL followed by
an unsigned.
30.12.2.3.1.45 bundle
starpu_task_bundle_t starpu_task::bundle
Optional field. The bundle that includes this task. If no bundle is used, this should be NULL.
30.12.2.3.1.46 profiling info
struct starpu_profiling_task_info* starpu_task::profiling_info
Optional field. Profiling information for the task.
TODO: does not have a starpu_task_insert() equivalent
30.12.2.3.1.47 flops
double starpu_task::flops
This can be set to the number of floating points operations that the task will have to achieve. This is useful for easily
getting GFlops curves from the tool starpu perfmodel plot, and for the hypervisor load balancing.
With starpu_task_insert() and alike this can be specified thanks to STARPU_FLOPS followed by a double.
30.12.2.3.1.48 predicted
double starpu_task::predicted
Output field. Predicted duration of the task. This field is only set if the scheduling strategy uses performance models.
Set by StarPU.
30.12.2.3.1.49 predicted_transfer
double starpu_task::predicted_transfer
Output field. Predicted data transfer duration for the task in microseconds. This field is only valid if the scheduling
strategy uses performance models.
Set by StarPU.
30.12.2.3.1.50 prev
struct starpu_task* starpu_task::prev [private]
A pointer to the previous task. This should only be used by StarPU schedulers.
30.12.2.3.1.51 next
struct starpu_task* starpu_task::next [private]
A pointer to the next task. This should only be used by StarPU schedulers.
30.12.2.3.1.52 starpu_private
void* starpu_task::starpu_private [private]
This is private to StarPU, do not modify.
30.12.2.3.1.53 omp_task
struct starpu_omp_task* starpu_task::omp_task [private]
This is private to StarPU, do not modify.
30.12.2.3.1.54 nb_termination_call_required
```

30.12.2.3.1.55 sched data

This is private to StarPU, do not modify.

void* starpu_task::sched_data

unsigned starpu_task::nb_termination_call_required [private]

This field is managed by the scheduler, is it allowed to do whatever with it. Typically, some area would be allocated on push, and released on pop.

30.12.3 Macro Definition Documentation

30.12.3.1 STARPU_NMAXBUFS

#define STARPU_NMAXBUFS

Define the maximum number of buffers that tasks will be able to take as parameters. The default value is 8, it can be changed by using the configure option --enable-maxbuffers.

30.12.3.2 STARPU_NOWHERE

#define STARPU_NOWHERE

To be used when setting the field starpu_codelet::where to specify that the codelet has no computation part, and thus does not need to be scheduled, and data does not need to be actually loaded. This is thus essentially used for synchronization tasks.

30.12.3.3 STARPU_CPU

#define STARPU_CPU

To be used when setting the field starpu_codelet::where (or starpu_task::where) to specify the codelet (or the task) may be executed on a CPU processing unit.

30.12.3.4 STARPU_CUDA

#define STARPU_CUDA

To be used when setting the field starpu_codelet::where (or starpu_task::where) to specify the codelet (or the task) may be executed on a CUDA processing unit.

30.12.3.5 STARPU_OPENCL

#define STARPU_OPENCL

To be used when setting the field starpu_codelet::where (or starpu_task::where) to specify the codelet (or the task) may be executed on a OpenCL processing unit.

30.12.3.6 STARPU_MIC

#define STARPU_MIC

To be used when setting the field starpu_task::where) to specify the codelet (or the task) may be executed on a MIC processing unit.

30.12.3.7 STARPU_MPI_MS

#define STARPU_MPI_MS

To be used when setting the field starpu_codelet::where (or starpu_task::where) to specify the codelet (or the task) may be executed on a MPI Slave processing unit.

30.12.3.8 STARPU_CODELET_SIMGRID_EXECUTE

#define STARPU_CODELET_SIMGRID_EXECUTE

Value to be set in starpu_codelet::flags to execute the codelet functions even in simgrid mode.

30.12.3.9 STARPU_CODELET_SIMGRID_EXECUTE_AND_INJECT

#define STARPU_CODELET_SIMGRID_EXECUTE_AND_INJECT

Value to be set in starpu_codelet::flags to execute the codelet functions even in simgrid mode, and later inject the measured timing inside the simulation.

30.12.3.10 STARPU_CODELET_NOPLANS

#define STARPU_CODELET_NOPLANS

Value to be set in starpu_codelet::flags to make starpu_task_submit() not submit automatic asynchronous partitioning/unpartitioning.

30.12.3.11 STARPU_CUDA_ASYNC

#define STARPU_CUDA_ASYNC

Value to be set in starpu_codelet::cuda_flags to allow asynchronous CUDA kernel execution.

30.12.3.12 STARPU_OPENCL_ASYNC

#define STARPU_OPENCL_ASYNC

Value to be set in starpu_codelet::opencl_flags to allow asynchronous OpenCL kernel execution.

30.12.3.13 STARPU_MAIN_RAM

#define STARPU_MAIN_RAM

To be used when the RAM memory node is specified.

30.12.3.14 STARPU_MULTIPLE_CPU_IMPLEMENTATIONS

#define STARPU_MULTIPLE_CPU_IMPLEMENTATIONS

Deprecated Setting the field starpu_codelet::cpu_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu← codelet::cpu_funcs.

30.12.3.15 STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS

#define STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS

Deprecated Setting the field starpu_codelet::cuda_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::cuda_funcs.

30.12.3.16 STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS

#define STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS

Deprecated Setting the field starpu_codelet::opencl_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::opencl_funcs.

30.12.3.17 STARPU_VARIABLE_NBUFFERS

#define STARPU_VARIABLE_NBUFFERS

Value to set in starpu_codelet::nbuffers to specify that the codelet can accept a variable number of buffers, specified in starpu_task::nbuffers.

30.12.3.18 STARPU_SPECIFIC_NODE_LOCAL

#define STARPU_SPECIFIC_NODE_LOCAL

Value to be set in the field starpu_codelet::nodes to request StarPU to put the data in CPU-accessible memory (and let StarPU choose the NUMA node).

30.12.3.19 STARPU_TASK_INITIALIZER

```
#define STARPU_TASK_INITIALIZER
```

Value to be used to initialize statically allocated tasks. This is equivalent to initializing a structure starpu_task with the function starpu_task init().

30.12.3.20 STARPU_TASK_GET_NBUFFERS

Return the number of buffers for task, i.e. starpu_codelet::nbuffers, or starpu_task::nbuffers if the former is ST← ARPU VARIABLE NBUFFERS.

30.12.3.21 STARPU_TASK_GET_HANDLE

```
#define STARPU_TASK_GET_HANDLE(

task,

i )
```

Return the i -th data handle of task. If task is defined with a static or dynamic number of handles, will either return the i -th element of the field starpu_task::handles or the i -th element of the field starpu_task::dyn_handles (see Setting Many Data Handles For a Task)

30.12.3.22 STARPU_TASK_SET_HANDLE

Set the <code>i</code> -th data handle of <code>task</code> with <code>handle</code>. If <code>task</code> is defined with a static or dynamic number of handles, will either set the <code>i</code> -th element of the field <code>starpu_task::handles</code> or the <code>i</code> -th element of the field <code>starpu_task::dyn</code>—handles (see Setting Many Data Handles For a Task)

30.12.3.23 STARPU_CODELET_GET_MODE

Return the access mode of the <code>i</code> -th data handle of <code>codelet</code>. If <code>codelet</code> is defined with a static or dynamic number of handles, will either return the <code>i</code> -th element of the field <code>starpu_codelet::modes</code> or the <code>i</code> -th element of the field <code>starpu_codelet::dyn_modes</code> (see Setting Many Data Handles For a Task)

30.12.3.24 STARPU_CODELET_SET_MODE

Set the access mode of the i-th data handle of <code>codelet</code>. If <code>codelet</code> is defined with a static or dynamic number of handles, will either set the i-th element of the field starpu_codelet::modes or the i-th element of the field starpu_codelet::dyn_modes (see Setting Many Data Handles For a Task)

30.12.3.25 STARPU_TASK_GET_MODE

Return the access mode of the i-th data handle of task. If task is defined with a static or dynamic number of handles, will either return the i-th element of the field starpu_task::modes or the i-th element of the field starpu_task::dyn_modes (see Setting Many Data Handles For a Task)

30.12.3.26 STARPU_TASK_SET_MODE

Set the access mode of the <code>i</code> -th data handle of <code>task</code>. If <code>task</code> is defined with a static or dynamic number of handles, will either set the <code>i</code> -th element of the field <code>starpu_task::modes</code> or the <code>i</code> -th element of the field <code>starpu_cask::modes</code> or the <code>i</code> -th element of the field <code>starpu_cask::modes</code> (see Setting Many Data Handles For a Task)

30.12.3.27 STARPU_CODELET_GET_NODE

Return the target node of the <code>i</code> -th data handle of <code>codelet</code>. If <code>node</code> is defined with a static or dynamic number of handles, will either return the <code>i</code> -th element of the field <code>starpu_codelet::nodes</code> or the <code>i</code> -th element of the field <code>starpu_codelet::dyn_nodes</code> (see Setting Many Data Handles For a Task)

30.12.3.28 STARPU_CODELET_SET_NODE

Set the target node of the i-th data handle of <code>codelet</code>. If <code>codelet</code> is defined with a static or dynamic number of handles, will either set the i-th element of the field starpu_codelet::nodes or the i-th element of the field starpu_codelet::dyn_nodes (see Setting Many Data Handles For a Task)

30.12.4 Typedef Documentation

```
30.12.4.1 starpu_cpu_func_t
typedef void(* starpu_cpu_func_t) (void **, void *)
CPU implementation of a codelet.

30.12.4.2 starpu_cuda_func_t
typedef void(* starpu_cuda_func_t) (void **, void *)
CUDA implementation of a codelet.

30.12.4.3 starpu_opencl_func_t
typedef void(* starpu_opencl_func_t) (void **, void *)
OpenCL implementation of a codelet.

30.12.4.4 starpu_mic_kernel_t
typedef void(* starpu_mic_kernel_t) (void **, void *)
MIC implementation of a codelet.

30.12.4.5 starpu_mic_func_t
typedef starpu_mic_kernel_t(* starpu_mic_func_t) (void)
MIC kernel for a codelet
```

30.12.4.6 starpu_mpi_ms_kernel_t

typedef void(* starpu_mpi_ms_kernel_t) (void **, void *)

MPI Master Slave kernel for a codelet

30.12.4.7 starpu_mpi_ms_func_t

typedef starpu_mpi_ms_kernel_t(* starpu_mpi_ms_func_t) (void)

MPI Master Slave implementation of a codelet.

30.12.5 Enumeration Type Documentation

30.12.5.1 starpu_codelet_type

enum starpu_codelet_type

Describe the type of parallel task. See Parallel Tasks for details.

Enumerator

| STARPU_SEQ | (default) for classical sequential tasks. | |
|-----------------|---|--|
| STARPU_SPMD | for a parallel task whose threads are handled by StarPU, the code has to use | |
| | starpu_combined_worker_get_size() and starpu_combined_worker_get_rank() to | |
| | distribute the work. | |
| STARPU_FORKJOIN | for a parallel task whose threads are started by the codelet function, which has to use | |
| | starpu_combined_worker_get_size() to determine how many threads should be | |
| | started. | |

30.12.5.2 starpu_task_status

enum starpu_task_status

Enumerator

| STARPU_TASK_INVALID | The task has just been initialized. |
|-----------------------------|--|
| STARPU_TASK_INVALID | The task has just been initialized. |
| STARPU_TASK_BLOCKED | The task has just been submitted, and its dependencies has not been checked yet. |
| STARPU_TASK_READY | The task is ready for execution. |
| STARPU_TASK_RUNNING | The task is running on some worker. |
| STARPU_TASK_FINISHED | The task is finished executing. |
| STARPU_TASK_BLOCKED_ON_TAG | The task is waiting for a tag. |
| STARPU_TASK_BLOCKED_ON_TASK | The task is waiting for a task. |
| STARPU_TASK_BLOCKED_ON_DATA | The task is waiting for some data. |
| STARPU_TASK_STOPPED | The task is stopped. |
| | |

30.12.6 Function Documentation

```
30.12.6.1 starpu_task_init()
void starpu_task_init (
```

struct starpu task * task)

Initialize task with default values. This function is implicitly called by starpu_task_create(). By default, tasks initialized with starpu_task_init() must be deinitialized explicitly with starpu_task_clean(). Tasks can also be initialized statically, using STARPU_TASK_INITIALIZER.

```
30.12.6.2 starpu_task_clean()
```

Release all the structures automatically allocated to execute task, but not the task structure itself and values set by the user remain unchanged. It is thus useful for statically allocated tasks for instance. It is also useful when users want to execute the same operation several times with as least overhead as possible. It is called automatically by $starpu_task_destroy()$. It has to be called only after explicitly waiting for the task or after $starpu_shutdown()$ (waiting for the callback is not enough, since $starpu_shutdown()$) the callback is not enough.

```
30.12.6.3 starpu_task_create()
struct starpu_task* starpu_task_create (
```

void)

Allocate a task structure and initialize it with default values. Tasks allocated dynamically with starpu_task_create() are automatically freed when the task is terminated. This means that the task pointer can not be used any more once the task is submitted, since it can be executed at any time (unless dependencies make it wait) and thus freed at any time. If the field starpu_task::destroy is explicitly unset, the resources used by the task have to be freed by calling starpu_task_destroy().

Free the resource allocated during starpu_task_create() and associated with task. This function is called automatically after the execution of a task when the field starpu_task::destroy is set, which is the default for tasks created by starpu_task_create(). Calling this function on a statically allocated task results in an undefined behaviour.

```
30.12.6.5 starpu_task_submit()
```

Submit task to StarPU. Calling this function does not mean that the task will be executed immediately as there can be data or task (tag) dependencies that are not fulfilled yet: StarPU will take care of scheduling this task with respect to such dependencies. This function returns immediately if the field starpu_task::synchronous is set to 0, and block until the termination of the task otherwise. It is also possible to synchronize the application with asynchronous tasks by the means of tags, using the function starpu_tag_wait() function for instance. In case of success, this function returns 0, a return value of -ENODEV means that there is no worker able to process this task (e.g. there is no GPU available and this task is only implemented for CUDA devices). starpu_task_submit() can be called from anywhere, including codelet functions and callbacks, provided that the field starpu_task::synchronous is set to 0.

```
30.12.6.6 starpu_task_submit_to_ctx()
```

Submit task to the context $sched_ctx_id$. By default, $starpu_task_submit()$ submits the task to a global context that is created automatically by starPU.

30.12.6.7 starpu_task_wait()

Block until task has been executed. It is not possible to synchronize with a task more than once. It is not possible to wait for synchronous or detached tasks. Upon successful completion, this function returns 0. Otherwise, -EINVAL indicates that the specified task was either synchronous or detached.

30.12.6.8 starpu_task_wait_array()

Allow to wait for an array of tasks. Upon successful completion, this function returns 0. Otherwise, -EINVAL indicates that one of the tasks was either synchronous or detached.

30.12.6.9 starpu_task_wait_for_all()

Block until all the tasks that were submitted (to the current context or the global one if there is no current context) are terminated. It does not destroy these tasks.

30.12.6.10 starpu_task_wait_for_n_submitted()

```
int starpu_task_wait_for_n_submitted (  unsigned \ n \ )
```

Block until there are n submitted tasks left (to the current context or the global one if there is no current context) to be executed. It does not destroy these tasks.

30.12.6.11 starpu_task_wait_for_all_in_ctx()

```
int starpu_task_wait_for_all_in_ctx (
          unsigned sched_ctx_id )
```

Wait until all the tasks that were already submitted to the context sched_ctx_id have been terminated.

30.12.6.12 starpu_task_wait_for_n_submitted_in_ctx()

Wait until there are n tasks submitted left to be executed that were already submitted to the context $sched_ctx \leftarrow _id$.

30.12.6.13 starpu_task_wait_for_no_ready()

Wait until there is no more ready task.

30.12.6.14 starpu_task_nready()

Return the number of submitted tasks which are ready for execution are already executing. It thus does not include tasks waiting for dependencies.

30.12.6.15 starpu_task_nsubmitted()

Return the number of submitted tasks which have not completed yet.

30.12.6.16 starpu_iteration_push()

```
void starpu_iteration_push (
          unsigned long iteration )
```

Set the iteration number for all the tasks to be submitted after this call. This is typically called at the beginning of a task submission loop. This number will then show up in tracing tools. A corresponding starpu_iteration_pop() call must be made to match the call to starpu_iteration_push(), at the end of the same task submission loop, typically. Nested calls to starpu_iteration_push() and starpu_iteration_pop() are allowed, to describe a loop nest for instance, provided that they match properly.

30.12.6.17 starpu_iteration_pop()

Drop the iteration number for submitted tasks. This must match a previous call to starpu_iteration_push(), and is typically called at the end of a task submission loop.

30.12.6.18 starpu_codelet_init()

Initialize cl with default values. Codelets should preferably be initialized statically as shown in Defining A Codelet. However such a initialisation is not always possible, e.g. when using C++.

30.12.6.19 starpu_codelet_display_stats()

Output on stderr some statistics on the codelet cl.

30.12.6.20 starpu_task_get_current()

```
struct starpu_task* starpu_task_get_current (
```

Return the task currently executed by the worker, or NULL if it is called either from a thread that is not a task or simply because there is no task being executed at the moment.

30.12.6.21 starpu_task_get_current_data_node()

```
int starpu_task_get_current_data_node (  unsigned \ i \ )
```

Return the memory node number of parameter i of the task currently executed, or -1 if it is called either from a thread that is not a task or simply because there is no task being executed at the moment.

Usually, the returned memory node number is simply the memory node for the current worker. That may however be different when using e.g. starpu_codelet::specific_nodes.

30.12.6.22 starpu_task_get_model_name()

Return the name of the performance model of task.

30.12.6.23 starpu_task_get_name()

Return the name of task, i.e. either its starpu_task::name field, or the name of the corresponding performance model.

30.12.6.24 starpu_task_dup()

Allocate a task structure which is the exact duplicate of task.

30.12.6.25 starpu_task_set_implementation()

This function should be called by schedulers to specify the codelet implementation to be executed when executing task.

30.12.6.26 starpu_task_get_implementation()

```
unsigned starpu_task_get_implementation ( struct \ starpu\_task \ * \ task \ )
```

Return the codelet implementation to be executed when executing task.

30.12.6.27 starpu_create_sync_task()

Create (and submit) an empty task that unlocks a tag once all its dependencies are fulfilled.

30.13 Task Insert Utility

Data Structures

• struct starpu_codelet_pack_arg_data

Macros

- #define STARPU MODE SHIFT
- #define STARPU_VALUE
- #define STARPU_CALLBACK
- #define STARPU_CALLBACK_WITH_ARG
- #define STARPU_CALLBACK_ARG
- #define STARPU_PRIORITY
- #define STARPU_DATA_ARRAY
- #define STARPU_DATA_MODE_ARRAY
- #define STARPU TAG
- #define STARPU_HYPERVISOR_TAG
- #define STARPU FLOPS
- #define STARPU SCHED CTX
- #define STARPU_PROLOGUE_CALLBACK

30.13 Task Insert Utility 297

- #define STARPU PROLOGUE CALLBACK ARG
- #define STARPU_PROLOGUE_CALLBACK_POP
- #define STARPU PROLOGUE CALLBACK POP ARG
- #define STARPU EXECUTE ON WORKER
- #define STARPU EXECUTE WHERE
- #define STARPU TAG ONLY
- #define STARPU_POSSIBLY_PARALLEL
- #define STARPU WORKER ORDER
- #define STARPU NAME
- #define STARPU CL ARGS
- #define STARPU CL ARGS NFREE
- #define STARPU_TASK_DEPS_ARRAY
- #define STARPU TASK COLOR
- #define STARPU HANDLES SEQUENTIAL CONSISTENCY
- #define STARPU TASK SYNCHRONOUS
- #define STARPU TASK END DEPS ARRAY
- #define STARPU_TASK_END_DEP
- #define STARPU SHIFTED MODE MAX

Functions

- int starpu_task_set (struct starpu_task *task, struct starpu_codelet *cl,...)
- struct starpu task * starpu task build (struct starpu codelet *cl,...)
- int starpu task insert (struct starpu codelet *cl,...)
- int starpu insert task (struct starpu codelet *cl,...)
- void starpu_task_insert_data_make_room (struct starpu_codelet *cl, struct starpu_task *task, int *allocated buffers, int current buffer, int room)
- void starpu_task_insert_data_process_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated buffers, int *current buffer, int arg type, starpu data handle t handle)
- void starpu_task_insert_data_process_array_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated_buffers, int *current_buffer, int nb_handles, starpu_data_handle_t *handles)
- void starpu_task_insert_data_process_mode_array_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated_buffers, int *current_buffer, int nb_descrs, struct starpu_data_descr *descrs)
- void starpu_codelet_pack_args (void **arg_buffer, size_t *arg_buffer_size,...)
- void starpu codelet pack arg init (struct starpu codelet pack arg data *state)
- void starpu codelet pack arg (struct starpu codelet pack arg data *state, const void *ptr, size t ptr size)
- void starpu_codelet_pack_arg_fini (struct starpu_codelet_pack_arg_data *state, void **cl_arg, size_t *cl
 _arg_size)
- void starpu_codelet_unpack_args (void *cl_arg,...)
- void starpu_codelet_unpack_args_and_copyleft (void *cl_arg, void *buffer, size_t buffer_size,...)

30.13.1 Detailed Description

30.13.2 Data Structure Documentation

30.13.2.1 struct starpu_codelet_pack_arg_data

Data Fields

| char * | arg_buffer | |
|--------|-----------------|--|
| size_t | arg_buffer_size | |
| size_t | current_offset | |
| int | nargs | |

30.13.3 Macro Definition Documentation

30.13.3.1 STARPU_VALUE

#define STARPU_VALUE

Used when calling starpu_task_insert(), must be followed by a pointer to a constant value and the size of the constant

30.13.3.2 STARPU CALLBACK

#define STARPU_CALLBACK

Used when calling starpu_task_insert(), must be followed by a pointer to a callback function

30.13.3.3 STARPU_CALLBACK_WITH_ARG

#define STARPU_CALLBACK_WITH_ARG

Used when calling starpu_task_insert(), must be followed by two pointers: one to a callback function, and the other to be given as an argument to the callback function; this is equivalent to using both STARPU_CALLBACK and STARPU_CALLBACK_WITH_ARG.

30.13.3.4 STARPU_CALLBACK_ARG

#define STARPU_CALLBACK_ARG

Used when calling starpu_task_insert(), must be followed by a pointer to be given as an argument to the callback function

30.13.3.5 STARPU PRIORITY

#define STARPU_PRIORITY

Used when calling starpu_task_insert(), must be followed by a integer defining a priority level

30.13.3.6 STARPU_TAG

#define STARPU_TAG

Used when calling starpu_task_insert(), must be followed by a tag.

30.13.3.7 STARPU_FLOPS

#define STARPU_FLOPS

Used when calling starpu_task_insert(), must be followed by an amount of floating point operations, as a double. Users MUST explicitly cast into double, otherwise parameter passing will not work.

30.13.3.8 STARPU SCHED CTX

#define STARPU_SCHED_CTX

Used when calling starpu_task_insert(), must be followed by the id of the scheduling context to which to submit the task to.

30.13.3.9 STARPU_EXECUTE_ON_WORKER

#define STARPU_EXECUTE_ON_WORKER

Used when calling starpu_task_insert(), must be followed by an integer value specifying the worker on which to execute the task (as specified by starpu_task::execute on a specific worker)

30.13.3.10 STARPU_EXECUTE_WHERE

#define STARPU_EXECUTE_WHERE

Used when calling starpu_task_insert(), must be followed by an unsigned long long value specifying the mask of worker on which to execute the task (as specified by starpu_task::where)

30.13 Task Insert Utility 299

30.13.3.11 STARPU_TAG_ONLY

#define STARPU_TAG_ONLY

Used when calling starpu_task_insert(), must be followed by a tag stored in starpu_task::tag_id. Leave starpu_← task::use tag as 0.

30.13.3.12 STARPU WORKER ORDER

#define STARPU_WORKER_ORDER

used when calling starpu_task_insert(), must be followed by an integer value specifying the worker order in which to execute the tasks (as specified by starpu_task::workerorder)

30.13.3.13 STARPU_NAME

#define STARPU_NAME

Used when calling starpu_task_insert(), must be followed by a char * stored in starpu_task::name.

30.13.3.14 STARPU CL ARGS

#define STARPU CL ARGS

Used when calling starpu_task_insert(), must be followed by a memory buffer containing the arguments to be given to the task, and by the size of the arguments. The memory buffer should be the result of a previous call to starpu← codelet pack args(), and will be freed (i.e. starpu task::cl arg free will be set to 1)

30.13.3.15 STARPU_CL_ARGS_NFREE

#define STARPU_CL_ARGS_NFREE

Used when calling starpu_task_insert(), similarly to STARPU_CL_ARGS, must be followed by a memory buffer containing the arguments to be given to the task, and by the size of the arguments. The memory buffer should be the result of a previous call to starpu_codelet_pack_args(), and will NOT be freed (i.e. starpu_task::cl_arg_free will be set to 0)

30.13.3.16 STARPU_TASK_DEPS_ARRAY

#define STARPU_TASK_DEPS_ARRAY

Used when calling starpu_task_insert(), must be followed by a number of tasks as int, and an array containing these tasks. The function starpu_task_declare_deps_array() will be called with the given values.

30.13.3.17 STARPU_TASK_COLOR

#define STARPU_TASK_COLOR

Used when calling starpu task insert(), must be followed by an integer representing a color

30.13.3.18 STARPU_HANDLES_SEQUENTIAL_CONSISTENCY

#define STARPU_HANDLES_SEQUENTIAL_CONSISTENCY

Used when calling starpu_task_insert(), must be followed by an array of characters representing the sequential consistency for each buffer of the task.

30.13.3.19 STARPU_TASK_SYNCHRONOUS

#define STARPU_TASK_SYNCHRONOUS

Used when calling starpu task insert(), must be followed by an integer stating if the task is synchronous or not

30.13.3.20 STARPU_TASK_END_DEPS_ARRAY

#define STARPU_TASK_END_DEPS_ARRAY

Used when calling starpu_task_insert(), must be followed by a number of tasks as int, and an array containing these tasks. The function starpu_task_declare_end_deps_array() will be called with the given values.

30.13.3.21 STARPU_TASK_END_DEP

```
#define STARPU_TASK_END_DEP
```

Used when calling starpu_task_insert(), must be followed by an integer which will be given to starpu_task_end_ dep_add()

30.13.4 Function Documentation

30.13.4.1 starpu_task_set()

Set the given task corresponding to cl with the following arguments. The argument list must be zero-terminated. The arguments following the codelet are the same as the ones for the function $starpu_task_insert()$. If some arguments of type STARPU VALUE are given, the parameter $starpu_task::cl_arg$ free will be set to 1.

30.13.4.2 starpu_task_build()

Create a task corresponding to cl with the following arguments. The argument list must be zero-terminated. The arguments following the codelet are the same as the ones for the function starpu_task_insert(). If some arguments of type STARPU_VALUE are given, the parameter starpu_task::cl_arg_free will be set to 1.

30.13.4.3 starpu_task_insert()

Create and submit a task corresponding to cl with the following given arguments. The argument list must be zero-terminated.

The arguments following the codelet can be of the following types:

- STARPU_R, STARPU_W, STARPU_RW, STARPU_SCRATCH, STARPU_REDUX an access mode followed by a data handle;
- ::STARPU_DATA_ARRAY followed by an array of data handles and its number of elements;
- ::STARPU_DATA_MODE_ARRAY followed by an array of struct starpu_data_descr, i.e data handles with their associated access modes, and its number of elements;
- STARPU_EXECUTE_ON_WORKER, STARPU_WORKER_ORDER followed by an integer value specifying the worker on which to execute the task (as specified by starpu_task::execute_on_a_specific_worker)
- the specific values STARPU_VALUE, STARPU_CALLBACK, STARPU_CALLBACK_ARG, STARPU_CAL LBACK_WITH_ARG, STARPU_PRIORITY, STARPU_TAG, STARPU_TAG_ONLY, STARPU_FLOPS, ST ARPU_SCHED_CTX, STARPU_CL_ARGS, STARPU_CL_ARGS_NFREE, STARPU_TASK_DEPS_ARR AY, STARPU_TASK_COLOR, STARPU_HANDLES_SEQUENTIAL_CONSISTENCY, STARPU_TASK_S YNCHRONOUS, STARPU_TASK_END_DEP followed by the appropriated objects as defined elsewhere.

When using ::STARPU_DATA_ARRAY, the access mode of the data handles is not defined, it will be taken from the codelet starpu_codelet::modes or starpu_codelet::dyn_modes field. One should use ::STARPU_DATA_MODE_
ARRAY to define the data handles along with the access modes.

Parameters to be passed to the codelet implementation are defined through the type STARPU_VALUE. The function starpu_codelet_unpack_args() must be called within the codelet implementation to retrieve them.

30.13 Task Insert Utility 301

30.13.4.4 starpu_insert_task()

Similar to starpu_task_insert(). Kept to avoid breaking old codes.

30.13.4.5 starpu_task_insert_data_make_room()

Assuming that there are already <code>current_buffer</code> data handles passed to the task, and if *allocated_buffers is not 0, the <code>task->dyn_handles</code> array has size *allocated_buffers, this function makes room for room other data handles, allocating or reallocating <code>task->dyn_handles</code> as necessary and updating <code>allocated-buffers</code> accordingly. One can thus start with allocated_buffers equal to 0 and current_buffer equal to 0, then make room by calling this function, then store handles with <code>STARPU_TASK_SET_HANDLE()</code>, make room again with this function, store yet more handles, etc.

30.13.4.6 starpu_task_insert_data_process_arg()

```
void starpu_task_insert_data_process_arg (
    struct starpu_codelet * cl,
    struct starpu_task * task,
    int * allocated_buffers,
    int * current_buffer,
    int arg_type,
    starpu_data_handle_t handle )
```

Store data handle handle into task task with mode arg_type , updating *allocated_buffers and *current_buffer accordingly.

30.13.4.7 starpu_task_insert_data_process_array_arg()

```
void starpu_task_insert_data_process_array_arg (
    struct starpu_codelet * cl,
    struct starpu_task * task,
    int * allocated_buffers,
    int * current_buffer,
    int nb_handles,
    starpu_data_handle_t * handles )
```

Store nb_handles data handles handles into task task, updating *allocated_buffers and *current_buffer accordingly.

30.13.4.8 starpu_task_insert_data_process_mode_array_arg()

Store nb_descrs data handles described by descrs into task task, updating *allocated_buffers and *current_buffer accordingly.

30.13.4.9 starpu_codelet_pack_args()

Pack arguments of type STARPU_VALUE into a buffer which can be given to a codelet and later unpacked with the function starpu_codelet_unpack_args().

Instead of calling starpu_codelet_pack_args(), one can also call starpu_codelet_pack_arg_init(), then starpu_codelet_pack_arg_finit().

30.13.4.10 starpu_codelet_pack_arg_init()

Initialize struct starpu_codelet_pack_arg before calling starpu_codelet_pack_arg() and starpu_codelet_pack_arg ← fini(). This will simply initialize the content of the structure.

30.13.4.11 starpu_codelet_pack_arg()

Pack one argument into struct starpu_codelet_pack_arg state. That structure has to be initialized before with starpu_codelet_pack_arg_init(), and after all starpu_codelet_pack_arg() calls performed, starpu_codelet_pack_earg_finit() has to be used to get the cl_arg and cl_arg_size to be put in the task.

30.13.4.12 starpu_codelet_pack_arg_fini()

Finish packing data, after calling starpu_codelet_pack_arg_init() once and starpu_codelet_pack_arg() several times.

30.13.4.13 starpu_codelet_unpack_args()

Retrieve the arguments of type STARPU_VALUE associated to a task automatically created using the function starpu task insert(). If any parameter's value is 0, unpacking will stop there and ignore the remaining parameters.

30.13.4.14 starpu_codelet_unpack_args_and_copyleft()

Similar to starpu_codelet_unpack_args(), but if any parameter is 0, copy the part of cl_arg that has not been read in buffer which can then be used in a later call to one of the unpack functions.

30.14 Explicit Dependencies

Typedefs

typedef uint64 t starpu tag t

Functions

- void starpu_task_declare_deps_array (struct starpu_task *task, unsigned ndeps, struct starpu_task *task
 _array[])
- void starpu task declare deps (struct starpu task *task, unsigned ndeps,...)
- void starpu_task_declare_end_deps_array (struct starpu_task *task, unsigned ndeps, struct starpu_task *task_array[])
- void starpu_task_declare_end_deps (struct starpu_task *task, unsigned ndeps,...)
- int starpu_task_get_task_succs (struct starpu_task *task, unsigned ndeps, struct starpu_task *task_array[])
- int starpu_task_get_task_scheduled_succs (struct starpu_task *task, unsigned ndeps, struct starpu_task *task_array[])
- void starpu task end dep add (struct starpu task *t, int nb deps)
- void starpu_task_end_dep_release (struct starpu_task *t)
- void starpu_tag_declare_deps (starpu_tag_t id, unsigned ndeps,...)
- void starpu_tag_declare_deps_array (starpu_tag_t id, unsigned ndeps, starpu_tag_t *array)
- int starpu tag wait (starpu tag t id)
- int starpu_tag_wait_array (unsigned ntags, starpu_tag_t *id)
- void starpu_tag_restart (starpu_tag_t id)
- · void starpu tag remove (starpu tag t id)
- void starpu_tag_notify_from_apps (starpu_tag_t id)
- struct starpu_task * starpu_tag_get_task (starpu_tag_t id)

30.14.1 Detailed Description

30.14.2 Typedef Documentation

```
30.14.2.1 starpu_tag_t
typedef uint64_t starpu_tag_t
```

Define a task logical identifer. It is possible to associate a task with a unique *tag* chosen by the application, and to express dependencies between tasks by the means of those tags. To do so, fill the field starpu_task::tag_id with a tag number (can be arbitrary) and set the field starpu_task::use_tag to 1. If starpu_tag_declare_deps() is called with this tag number, the task will not be started until the tasks which holds the declared dependency tags are completed.

30.14.3 Function Documentation

30.14.3.1 starpu_task_declare_deps_array()

```
void starpu_task_declare_deps_array (
          struct starpu_task * task,
          unsigned ndeps,
          struct starpu_task * task_array[] )
```

Declare task dependencies between a task and an array of tasks of length ndeps. This function must be called prior to the submission of the task, but it may called after the submission or the execution of the tasks in the array, provided the tasks are still valid (i.e. they were not automatically destroyed). Calling this function on a task that was already submitted or with an entry of task_array that is no longer a valid task results in an undefined behaviour. If ndeps is 0, no dependency is added. It is possible to call starpu_task_declare_deps_array() several times on the same task, in this case, the dependencies are added. It is possible to have redundancy in the task dependencies.

30.14.3.2 starpu_task_declare_deps()

Declare task dependencies between a task and an series of ndeps tasks, similarly to starpu_task_declare deps_array(), but the tasks are passed after ndeps, which indicates how many tasks task shall be made to depend on. If ndeps is 0, no dependency is added.

30.14.3.3 starpu_task_declare_end_deps_array()

Declare task end dependencies between a task and an array of tasks of length ndeps. task will appear as terminated not only when task is termination, but also when the tasks of task_array have terminated. This function must be called prior to the termination of the task, but it may called after the submission or the execution of the tasks in the array, provided the tasks are still valid (i.e. they were not automatically destroyed). Calling this function on a task that was already terminated or with an entry of task_array that is no longer a valid task results in an undefined behaviour. If ndeps is 0, no dependency is added. It is possible to call starpu_task_declare—end_deps_array() several times on the same task, in this case, the dependencies are added. It is currently not implemented to have redundancy in the task dependencies.

30.14.3.4 starpu_task_declare_end_deps()

Declare task end dependencies between a task and an series of ndeps tasks, similarly to starpu_task_declare — _end_deps_array(), but the tasks are passed after ndeps, which indicates how many tasks task 's termination shall be made to depend on. If ndeps is 0, no dependency is added.

30.14.3.5 starpu_task_get_task_succs()

Fill task_array with the list of tasks which are direct children of task. ndeps is the size of task_array. This function returns the number of direct children. task_array can be set to NULL if ndeps is 0, which allows to compute the number of children before allocating an array to store them. This function can only be called if task has not completed yet, otherwise the results are undefined. The result may also be outdated if some additional dependency has been added in the meanwhile.

30.14.3.6 starpu_task_get_task_scheduled_succs()

Behave like starpu_task_get_task_succs(), except that it only reports tasks which will go through the scheduler, thus avoiding tasks with not codelet, or with explicit placement.

30.14.3.7 starpu_task_end_dep_add()

```
void starpu_task_end_dep_add (
```

```
struct starpu_task * t,
int nb deps )
```

Add nb_deps end dependencies to the task t. This means the task will not terminate until the required number of calls to the function starpu_task_end_dep_release() has been made.

30.14.3.8 starpu task end dep release()

Unlock 1 end dependency to the task t. This function must be called after starpu task end dep add().

30.14.3.9 starpu_tag_declare_deps()

Specify the dependencies of the task identified by tag id. The first argument specifies the tag which is configured, the second argument gives the number of tag(s) on which id depends. The following arguments are the tags which have to be terminated to unlock the task. This function must be called before the associated task is submitted to StarPU with starpu task submit().

WARNING! Use with caution. Because of the variable arity of starpu_tag_declare_deps(), note that the last arguments must be of type starpu_tag_t: constant values typically need to be explicitly casted. Otherwise, due to integer sizes and argument passing on the stack, the C compiler might consider the tag 0x200000003 instead of 0x2 and 0x3 when calling $starpu_tag_declare_deps(0x1, 2, 0x2, 0x3)$. Using the $starpu_tag_declare_deps_array()$ function avoids this hazard.

30.14.3.10 starpu_tag_declare_deps_array()

Similar to starpu_tag_declare_deps(), except that its does not take a variable number of arguments but an array of tags of size ndeps.

```
// Tag 0x1 depends on tags 0x32 and 0x52
starpu_tag_t tag_array[2] = {0x32, 0x52};
starpu_tag_declare_deps_array((starpu_tag_t)0x1, 2, tag_array);
```

30.14.3.11 starpu_tag_wait()

Block until the task associated to tag id has been executed. This is a blocking call which must therefore not be called within tasks or callbacks, but only from the application directly. It is possible to synchronize with the same tag multiple times, as long as the starpu_tag_remove() function is not called. Note that it is still possible to synchronize with a tag associated to a task for which the strucuture starpu_task; destroy was enabled).

30.14.3.12 starpu_tag_wait_array()

Similar to starpu_tag_wait() except that it blocks until all the ntags tags contained in the array id are terminated.

Clear the *already notified* status of a tag which is not associated with a task. Before that, calling starpu_tag_
notify_from_apps() again will not notify the successors. After that, the next call to starpu_tag_notify_from_apps()
will notify the successors.

Release the resources associated to tag id. It can be called once the corresponding task has been executed and when there is no other tag that depend on this tag anymore.

Explicitly unlock tag id. It may be useful in the case of applications which execute part of their computation outside StarPU tasks (e.g. third-party libraries). It is also provided as a convenient tool for the programmer, for instance to entirely construct the task DAG before actually giving StarPU the opportunity to execute the tasks. When called several times on the same tag, notification will be done only on first call, thus implementing "OR" dependencies, until the tag is restarted using starpu_tag_restart().

30.15 Performance Model

Data Structures

- struct starpu_perfmodel_device
- struct starpu_perfmodel_arch
- · struct starpu_perfmodel_history_entry
- · struct starpu_perfmodel_history_list
- struct starpu_perfmodel_regression_model
- struct starpu_perfmodel_per_arch
- · struct starpu perfmodel

Macros

- #define STARPU NARCH
- #define starpu_per_arch_perfmodel

Typedefs

- typedef double(* starpu_perfmodel_per_arch_cost_function) (struct starpu_task *task, struct starpu_
 perfmodel_arch *arch, unsigned nimpl)
- typedef size_t(* starpu_perfmodel_per_arch_size_base) (struct starpu_task *task, struct starpu_
 perfmodel_arch *arch, unsigned nimpl)
- typedef struct _starpu_perfmodel_state * starpu_perfmodel_state_t

30.15 Performance Model 307

Enumerations

enum starpu_perfmodel_type {
 STARPU_PERFMODEL_INVALID, STARPU_PER_ARCH, STARPU_COMMON, STARPU_HISTORY_B
 ASED,
 STARPU_REGRESSION_BASED, STARPU_NL_REGRESSION_BASED, STARPU_MULTIPLE_REGR
 ESSION_BASED }

Functions

- void starpu_perfmodel_init (struct starpu_perfmodel *model)
- int starpu_perfmodel_load_file (const char *filename, struct starpu_perfmodel *model)
- int starpu_perfmodel_load_symbol (const char *symbol, struct starpu_perfmodel *model)
- int starpu_perfmodel_unload_model (struct starpu_perfmodel *model)
- void starpu perfmodel get model path (const char *symbol, char *path, size t maxlen)
- void starpu perfmodel dump xml (FILE *output, struct starpu perfmodel *model)
- void starpu_perfmodel_free_sampling_directories (void)
- struct starpu perfmodel arch * starpu worker get perf archtype (int workerid, unsigned sched ctx id)
- int starpu perfmodel get narch combs (void)
- int starpu_perfmodel_arch_comb_add (int ndevices, struct starpu_perfmodel_device *devices)
- int starpu_perfmodel_arch_comb_get (int ndevices, struct starpu_perfmodel_device *devices)
- struct starpu_perfmodel_arch * starpu_perfmodel_arch_comb_fetch (int comb)
- struct starpu_perfmodel_per_arch * starpu_perfmodel_get_model_per_arch (struct starpu_perfmodel *model, struct starpu_perfmodel_arch *arch, unsigned impl)
- struct starpu_perfmodel_per_arch * starpu_perfmodel_get_model_per_devices (struct starpu_perfmodel *model, int impl,...)
- int starpu_perfmodel_set_per_devices_cost_function (struct starpu_perfmodel *model, int impl, starpu
 _perfmodel_per_arch_cost_function func,...)
- int starpu_perfmodel_set_per_devices_size_base (struct starpu_perfmodel *model, int impl, starpu_
 perfmodel_per_arch_size_base func,...)
- void starpu_perfmodel_debugfilepath (struct starpu_perfmodel *model, struct starpu_perfmodel_arch *arch, char *path, size_t maxlen, unsigned nimpl)
- char * starpu perfmodel get archtype name (enum starpu worker archtype archtype)
- void starpu_perfmodel_get_arch_name (struct starpu_perfmodel_arch *arch, char *archname, size_ ← t maxlen, unsigned nimpl)
- double starpu_perfmodel_history_based_expected_perf (struct starpu_perfmodel *model, struct starpu_←
 perfmodel_arch *arch, uint32_t footprint)
- · void starpu perfmodel initialize (void)
- int starpu perfmodel list (FILE *output)
- void **starpu_perfmodel_print** (struct starpu_perfmodel *model, struct starpu_perfmodel_arch *arch, unsigned nimpl, char *parameter, uint32_t *footprint, FILE *output)
- int **starpu_perfmodel_print_all** (struct **starpu_perfmodel** *model, char *arch, char *parameter, uint32_t *footprint, FILE *output)
- int starpu perfmodel print estimations (struct starpu perfmodel *model, uint32 t footprint, FILE *output)
- int starpu_perfmodel_list_combs (FILE *output, struct starpu_perfmodel *model)
- void starpu_perfmodel_update_history (struct starpu_perfmodel *model, struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned cpuid, unsigned nimpl, double measured)
- void starpu_perfmodel_directory (FILE *output)
- void starpu_bus_print_bandwidth (FILE *f)
- void starpu_bus_print_affinity (FILE *f)
- void starpu bus print filenames (FILE *f)
- double starpu transfer bandwidth (unsigned src node, unsigned dst node)
- double starpu_transfer_latency (unsigned src_node, unsigned dst_node)
- double starpu_transfer_predict (unsigned src_node, unsigned dst_node, size_t size)

Variables

• struct starpu_perfmodel starpu_perfmodel_nop

30.15.1 Detailed Description

30.15.2 Data Structure Documentation

30.15.2.1 struct starpu_perfmodel_device

todo

Data Fields

| enum starpu_worker_archtype | type | type of the device |
|-----------------------------|--------|--|
| int | devid | identifier of the precise device |
| int | ncores | number of execution in parallel, minus 1 |

30.15.2.2 struct starpu_perfmodel_arch

todo

Data Fields

| int | ndevices | number of the devices for the given arch |
|----------------------------------|----------|--|
| struct starpu_perfmodel_device * | devices | list of the devices for the given arch |

30.15.2.3 struct starpu_perfmodel_history_entry

Data Fields

| double | mean | mean_n = 1/n sum |
|--------------|------------|---------------------------------|
| double | deviation | n dev_n = sum2 - 1/n (sum) 2 |
| double | sum | sum of samples (in μs) |
| double | sum2 | sum of samples^2 |
| unsigned | nsample | number of samples |
| unsigned | nerror | |
| uint32_t | footprint | data footprint |
| size_t | size | in bytes |
| double | flops | Provided by the application |
| double | duration | |
| starpu_tag_t | tag | |
| double * | parameters | |

30.15.2.4 struct starpu_perfmodel_history_list

Data Fields

| struct | | |
|----------------------------------|-------|--|
| starpu_perfmodel_history_list * | next | |
| struct | | |
| starpu_perfmodel_history_entry * | entry | |

30.15 Performance Model 309

30.15.2.5 struct starpu_perfmodel_regression_model

todo

Data Fields

| double | sumlny | sum of In(measured) |
|---------------|-------------|---|
| double | sumlnx | sum of ln(size) |
| double | sumlnx2 | sum of ln(size)^2 |
| unsigned long | minx | minimum size |
| unsigned long | maxx | maximum size |
| double | sumInxIny | sum of ln(size)*In(measured) |
| double | alpha | estimated = alpha * size ^ beta |
| double | beta | estimated = alpha * size ^ beta |
| unsigned | valid | whether the linear regression model is valid (i.e. enough measures) |
| double | а | estimated = a size ^b + c |
| double | b | estimated = a size ^b + c |
| double | С | estimated = a size ^b + c |
| unsigned | nl_valid | whether the non-linear regression model is valid (i.e. enough measures) |
| unsigned | nsample | number of sample values for non-linear regression |
| double * | coeff | list of computed coefficients for multiple linear regression model |
| unsigned | ncoeff | number of coefficients for multiple linear regression model |
| unsigned | multi_valid | whether the multiple linear regression model is valid |
| | | |

30.15.2.6 struct starpu_perfmodel_per_arch

information about the performance model of a given arch.

Data Fields

- starpu_perfmodel_per_arch_cost_function cost_function
- starpu_perfmodel_per_arch_size_base size_base
- char debug_path [256]

Private Attributes

- struct starpu_perfmodel_history_table * history
- struct starpu_perfmodel_history_list * list
- struct starpu_perfmodel_regression_model regression

30.15.2.6.1 Field Documentation

30.15.2.6.1.1 cost_function

```
\verb|starpu_perfmodel_per_arch_cost_function| starpu_perfmodel_per_arch::cost_function|
```

Used by STARPU_PER_ARCH, must point to functions which take a task, the target arch and implementation number (as mere conveniency, since the array is already indexed by these), and must return a task duration estimation in micro-seconds.

30.15.2.6.1.2 size_base

```
starpu_perfmodel_per_arch_size_base starpu_perfmodel_per_arch::size_base
```

Same as in structure starpu_perfmodel, but per-arch, in case it depends on the architecture-specific implementation.

30.15.2.6.1.3 history

struct starpu_perfmodel_history_table* starpu_perfmodel_per_arch::history [private] The history of performance measurements.

30.15.2.6.1.4 list

struct starpu_perfmodel_history_list* starpu_perfmodel_per_arch::list [private]

Used by STARPU_HISTORY_BASED, STARPU_NL_REGRESSION_BASED and STARPU_MULTIPLE_REGR←

ESSION_BASED, records all execution history measures.

30.15.2.6.1.5 regression

struct starpu_perfmodel_regression_model starpu_perfmodel_per_arch::regression [private] Used by STARPU_REGRESSION_BASED, STARPU_NL_REGRESSION_BASED and STARPU_MULTIPLE_R
EGRESSION BASED, contains the estimated factors of the regression.

30.15.2.7 struct starpu_perfmodel

Contain all information about a performance model. At least the type and symbol fields have to be filled when defining a performance model for a codelet. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset, or by letting the compiler implicitly do it in e.g. static storage case. If not provided, other fields have to be zero.

Data Fields

- · enum starpu_perfmodel_type type
- double(* cost_function)(struct starpu_task *, unsigned nimpl)
- double(* arch cost function)(struct starpu task *, struct starpu perfmodel arch *arch, unsigned nimpl)
- size_t(* size_base)(struct starpu_task *, unsigned nimpl)
- uint32_t(* footprint)(struct starpu_task *)
- const char * symbol
- void(* parameters)(struct starpu_task *task, double *parameters)

Private Attributes

- unsigned is_loaded
- · unsigned benchmarking
- unsigned is_init
- const char ** parameters_names
- · unsigned nparameters
- unsigned ** combinations
- unsigned ncombinations
- starpu_perfmodel_state_t state

30.15.2.7.1 Field Documentation

30.15.2.7.1.1 type

enum starpu_perfmodel_type starpu_perfmodel::type

type of performance model

- STARPU_HISTORY_BASED, STARPU_REGRESSION_BASED, STARPU_NL_REGRESSION_BASED
 ∴ No other fields needs to be provided, this is purely history-based.
- STARPU_MULTIPLE_REGRESSION_BASED: Need to provide fields starpu_perfmodel::nparameters (number of different parameters), starpu_perfmodel::ncombinations (number of parameters combinations-tuples) and table starpu_perfmodel::combinations which defines exponents of the equation. Function cl_perf_func also needs to define how to extract parameters from the task.
- STARPU_PER_ARCH: either field starpu_perfmodel::arch_cost_function has to be filled with a function that returns the cost in micro-seconds on the arch given as parameter, or field starpu_perfmodel::per_arch has to be filled with functions which return the cost in micro-seconds.

30.15 Performance Model 311

• STARPU_COMMON: field starpu_perfmodel::cost_function has to be filled with a function that returns the cost in micro-seconds on a CPU, timing on other archs will be determined by multiplying by an arch-specific factor.

```
30.15.2.7.1.2 cost_function
```

```
double(* starpu_perfmodel::cost_function) (struct starpu_task *, unsigned nimpl)
```

Used by STARPU_COMMON. Take a task and implementation number, and must return a task duration estimation in micro-seconds.

30.15.2.7.1.3 arch_cost_function

```
double(* starpu_perfmodel::arch_cost_function) (struct starpu_task *, struct starpu_perfmodel←
_arch *arch, unsigned nimpl)
```

Used by STARPU_COMMON. Take a task, an arch and implementation number, and must return a task duration estimation in micro-seconds on that arch.

30.15.2.7.1.4 size_base

```
size_t(* starpu_perfmodel::size_base) (struct starpu_task *, unsigned nimpl)
```

Used by STARPU_HISTORY_BASED, STARPU_REGRESSION_BASED and STARPU_NL_REGRESSION_B ← ASED. If not NULL, take a task and implementation number, and return the size to be used as index to distinguish histories and as a base for regressions.

30.15.2.7.1.5 footprint

```
uint32_t(* starpu_perfmodel::footprint) (struct starpu_task *)
```

Used by STARPU_HISTORY_BASED. If not NULL, take a task and return the footprint to be used as index to distinguish histories. The default is to use the starpu_task_data_footprint() function.

30.15.2.7.1.6 symbol

```
const char* starpu_perfmodel::symbol
```

symbol name for the performance model, which will be used as file name to store the model. It must be set otherwise the model will be ignored.

30.15.2.7.1.7 is_loaded

```
unsigned starpu_perfmodel::is_loaded [private]
```

Whether the performance model is already loaded from the disk.

30.15.2.7.1.8 parameters_names

```
const char** starpu_perfmodel::parameters_names [private]
```

Names of parameters used for multiple linear regression models (M, N, K)

30.15.2.7.1.9 nparameters

```
unsigned starpu_perfmodel::nparameters [private]
```

Number of parameters used for multiple linear regression models

30.15.2.7.1.10 combinations

```
unsigned** starpu_perfmodel::combinations [private]
```

Table of combinations of parameters (and the exponents) used for multiple linear regression models

30.15.2.7.1.11 ncombinations

```
unsigned starpu_perfmodel::ncombinations [private]
```

Number of combination of parameters used for multiple linear regression models

30.15.3 Enumeration Type Documentation

```
30.15.3.1 starpu_perfmodel_type
```

```
enum starpu_perfmodel_type
```

todo

Enumerator

| STARPU_PER_ARCH | Application-provided per-arch cost model function |
|----------------------------------|---|
| STARPU_COMMON | Application-provided common cost model function, with |
| | per-arch factor |
| STARPU_HISTORY_BASED | Automatic history-based cost model |
| STARPU_REGRESSION_BASED | Automatic linear regression-based cost model (alpha * size ^ beta) |
| STARPU_NL_REGRESSION_BASED | Automatic non-linear regression-based cost model (a $*$ size $^{\wedge}$ b + c) |
| STARPU_MULTIPLE_REGRESSION_BASED | Automatic multiple linear regression-based cost model. Application provides parameters, their combinations and exponents. |

30.15.4 Function Documentation

30.15.4.1 starpu_perfmodel_init()

Initialize the model performance model structure. This is automatically called when e.g. submitting a task using a codelet using this performance model.

30.15.4.2 starpu_perfmodel_load_file()

Load the performance model found in the file named filename. model has to be completely zero, and will be filled with the information stored in the given file.

30.15.4.3 starpu_perfmodel_load_symbol()

Load a given performance model. model has to be completely zero, and will be filled with the information stored in $STARPU_HOME/.starpu$. The function is intended to be used by external tools that want to read the performance model files.

30.15.4.4 starpu_perfmodel_unload_model()

Unload model which has been previously loaded through the function starpu_perfmodel_load_symbol()

30.15.4.5 starpu_perfmodel_get_model_path()

Fills path (supposed to be maxlen long) with the full path to the performance model file for symbol symbol. This path can later on be used for instance with $starpu_perfmodel_load_file()$.

30.15 Performance Model 313

30.15.4.6 starpu_perfmodel_dump_xml()

Dump performance model model to output stream output, in XML format.

30.15.4.7 starpu_perfmodel_free_sampling_directories()

Free internal memory used for sampling directory management. It should only be called by an application which is not calling starpu_shutdown() as this function already calls it. See for example tools/starpu_perfmodel — _display.c.

30.15.4.8 starpu_worker_get_perf_archtype()

Return the architecture type of the worker workerid.

30.15.4.9 starpu_perfmodel_debugfilepath()

```
void starpu_perfmodel_debugfilepath (
          struct starpu_perfmodel * model,
          struct starpu_perfmodel_arch * arch,
          char * path,
          size_t maxlen,
          unsigned nimpl )
```

Return the path to the debugging information for the performance model.

30.15.4.10 starpu_perfmodel_get_arch_name()

Return the architecture name for arch

30.15.4.11 starpu_perfmodel_history_based_expected_perf()

Return the estimated time of a task with the given model and the given footprint.

30.15.4.12 starpu_perfmodel_initialize()

If starpu_init() is not used, starpu_perfmodel_initialize() should be used called calling starpu_perfmodel_* functions.

30.15.4.13 starpu_perfmodel_list()

Print a list of all performance models on output

```
30.15.4.14 starpu_perfmodel_update_history()
```

```
void starpu_perfmodel_update_history (
    struct starpu_perfmodel * model,
    struct starpu_task * task,
    struct starpu_perfmodel_arch * arch,
    unsigned cpuid,
    unsigned nimpl,
    double measured )
```

Feed the performance model model with an explicit measurement measured (in μ s), in addition to measurements done by StarPU itself. This can be useful when the application already has an existing set of measurements done in good conditions, that StarPU could benefit from instead of doing on-line measurements. An example of use can be seen in Performance Model Example.

```
30.15.4.15 starpu_perfmodel_directory()
```

```
void starpu_perfmodel_directory (
     FILE * output )
```

Print the directory name storing performance models on output

```
30.15.4.16 starpu_bus_print_bandwidth()
```

```
void starpu_bus_print_bandwidth ( FILE * f )
```

Print a matrix of bus bandwidths on f.

30.15.4.17 starpu_bus_print_affinity()

Print the affinity devices on f.

30.15.4.18 starpu_bus_print_filenames()

Print on f the name of the files containing the matrix of bus bandwidths, the affinity devices and the latency.

30.15.4.19 starpu_transfer_bandwidth()

```
double starpu_transfer_bandwidth (  \mbox{unsigned } src\_node, \\ \mbox{unsigned } dst\_node \ )
```

Return the bandwidth of data transfer between two memory nodes

30.15.4.20 starpu_transfer_latency()

Return the latency of data transfer between two memory nodes

30.15.4.21 starpu_transfer_predict()

30.16 Profiling 315

Return the estimated time to transfer a given size between two memory nodes.

30.15.5 Variable Documentation

```
30.15.5.1 starpu_perfmodel_nop
```

```
struct starpu_perfmodel starpu_perfmodel_nop
```

Performance model which just always return 1µs.

30.16 Profiling

Data Structures

- · struct starpu profiling task info
- · struct starpu profiling worker info
- · struct starpu_profiling_bus_info

Macros

- #define STARPU PROFILING DISABLE
- #define STARPU PROFILING ENABLE
- · #define STARPU NS PER S
- #define starpu_timespec_cmp(a, b, CMP)

Functions

- void starpu_profiling_init (void)
- void starpu_profiling_set_id (int new_id)
- int starpu_profiling_status_set (int status)
- int starpu_profiling_status_get (void)
- int starpu_profiling_worker_get_info (int workerid, struct starpu_profiling_worker_info *worker_info)
- int starpu_bus_get_count (void)
- int starpu_bus_get_id (int src, int dst)
- int starpu_bus_get_src (int busid)
- int starpu_bus_get_dst (int busid)
- void starpu_bus_set_direct (int busid, int direct)
- int starpu_bus_get_direct (int busid)
- void starpu_bus_set_ngpus (int busid, int ngpus)
- · int starpu bus get ngpus (int busid)
- int starpu bus get profiling info (int busid, struct starpu profiling bus info *bus info)
- static __starpu_inline void starpu_timespec_clear (struct timespec *tsp)
- static __starpu_inline void starpu_timespec_add (struct timespec *a, struct timespec *b, struct timespec *result)
- static __starpu_inline void starpu_timespec_accumulate (struct timespec *result, struct timespec *a)
- static __starpu_inline void starpu_timespec_sub (const struct timespec *a, const struct timespec *b, struct timespec *result)
- double starpu_timing_timespec_delay_us (struct timespec *start, struct timespec *end)
- double starpu_timing_timespec_to_us (struct timespec *ts)
- · void starpu profiling bus helper display summary (void)
- void starpu_profiling_worker_helper_display_summary (void)
- void starpu_data_display_memory_stats ()

30.16.1 Detailed Description

30.16.2 Data Structure Documentation

30.16.2.1 struct starpu_profiling_task_info

Information about the execution of a task. It is accessible from the field starpu_task::profiling_info if profiling was enabled.

Data Fields

| struct timespec | submit_time | Date of task submission (relative to the initialization of StarPU). |
|-----------------|-------------------------|--|
| struct timespec | push_start_time | Time when the task was submitted to the scheduler. |
| struct timespec | push_end_time | Time when the scheduler finished with the task submission. |
| struct timespec | pop_start_time | Time when the scheduler started to be requested for a task, and eventually gave that task. |
| struct timespec | pop_end_time | Time when the scheduler finished providing the task for execution. |
| struct timespec | acquire_data_start_time | Time when the worker started fetching input data. |
| struct timespec | acquire_data_end_time | Time when the worker finished fetching input data. |
| struct timespec | start_time | Date of task execution beginning (relative to the initialization of StarPU). |
| struct timespec | end_time | Date of task execution termination (relative to the initialization of StarPU). |
| struct timespec | release_data_start_time | Time when the worker started releasing data. |
| struct timespec | release_data_end_time | Time when the worker finished releasing data. |
| struct timespec | callback_start_time | Time when the worker started the application callback for the task. |
| struct timespec | callback_end_time | Time when the worker finished the application callback for the task. |
| int | workerid | Identifier of the worker which has executed the task. |
| uint64_t | used_cycles | Number of cycles used by the task, only available in the MoviSim |
| uint64_t | stall_cycles | Number of cycles stalled within the task, only available in the MoviSim |
| double | energy_consumed | Energy consumed by the task, in Joules |
| | | |

30.16.2.2 struct starpu_profiling_worker_info

Profiling information associated to a worker. The timing is provided since the previous call to starpu_profiling_ worker_get_info()

Data Fields

| struct timespec | start_time | Starting date for the reported profiling measurements. |
|-----------------|-----------------|--|
| struct timespec | total_time | Duration of the profiling measurement interval. |
| struct timespec | executing_time | Time spent by the worker to execute tasks during the profiling measurement interval. |
| struct timespec | sleeping_time | Time spent idling by the worker during the profiling measurement interval. |
| int | executed_tasks | Number of tasks executed by the worker during the profiling measurement interval. |
| uint64_t | used_cycles | Number of cycles used by the worker, only available in the MoviSim |
| uint64_t | stall_cycles | Number of cycles stalled within the worker, only available in the MoviSim |
| double | energy_consumed | Energy consumed by the worker, in Joules |

30.16 Profiling 317

Data Fields

30.16.2.3 struct starpu_profiling_bus_info

Data Fields

| struct timespec | start_time | Time of bus profiling startup. |
|---------------------------------|----------------|---|
| struct timespec | total_time | Total time of bus profiling. |
| int long long transferred_bytes | | Number of bytes transferred during profiling. |
| int | transfer_count | Number of transfers during profiling. |

30.16.3 Macro Definition Documentation

30.16.3.1 STARPU_PROFILING_DISABLE

```
#define STARPU_PROFILING_DISABLE
```

Used when calling the function starpu_profiling_status_set() to disable profiling.

30.16.3.2 STARPU_PROFILING_ENABLE

```
#define STARPU_PROFILING_ENABLE
```

Used when calling the function starpu_profiling_status_set() to enable profiling.

30.16.4 Function Documentation

30.16.4.1 starpu_profiling_init()

Reset performance counters and enable profiling if the environment variable STARPU_PROFILING is set to a positive value.

30.16.4.2 starpu_profiling_set_id()

Set the ID used for profiling trace filename. Has to be called before starpu_init().

30.16.4.3 starpu_profiling_status_set()

Set the profiling status. Profiling is activated by passing STARPU_PROFILING_ENABLE in status. Passing STARPU_PROFILING_DISABLE disables profiling. Calling this function resets all profiling measurements. When profiling is enabled, the field starpu_task::profiling_info points to a valid structure starpu_profiling_task_info containing information about the execution of the task. Negative return values indicate an error, otherwise the previous status is returned.

30.16.4.4 starpu_profiling_status_get()

Return the current profiling status or a negative value in case there was an error.

30.16.4.5 starpu_profiling_worker_get_info()

Get the profiling info associated to the worker identified by workerid, and reset the profiling measurements. If the argument worker_info is NULL, only reset the counters associated to worker workerid. Upon successful completion, this function returns 0. Otherwise, a negative value is returned.

30.16.4.6 starpu_bus_get_count()

Return the number of buses in the machine

30.16.4.7 starpu_bus_get_id()

```
int starpu_bus_get_id (
    int src,
    int dst )
```

Return the identifier of the bus between src and dst

30.16.4.8 starpu_bus_get_src()

Return the source point of bus busid

30.16.4.9 starpu_bus_get_dst()

Return the destination point of bus busid

30.16.4.10 starpu_bus_get_profiling_info()

See _starpu_profiling_bus_helper_display_summary in src/profiling/profiling_helpers.c for a usage example. Note that calling starpu_bus_get_profiling_info() resets the counters to zero.

30.16.4.11 starpu_timing_timespec_delay_us()

Return the time elapsed between start and end in microseconds.

30.16.4.12 starpu_timing_timespec_to_us()

Convert the given timespec ts into microseconds

30.16.4.13 starpu_profiling_bus_helper_display_summary()

Display statistics about the bus on stderr. if the environment variable STARPU_BUS_STATS is defined. The function is called automatically by starpu_shutdown().

30.16.4.14 starpu_profiling_worker_helper_display_summary()

Display statistic about the workers on stderr if the environment variable STARPU_WORKER_STATS is defined. The function is called automatically by starpu shutdown().

30.16.4.15 starpu_data_display_memory_stats()

```
void starpu_data_display_memory_stats ( )
```

Display statistics about the current data handles registered within StarPU. StarPU must have been configured with the configure option --enable-memory-stats (see Memory Feedback).

30.17 Theoretical Lower Bound on Execution Time

Compute theoretical upper computation efficiency bound corresponding to some actual execution.

Functions

- · void starpu_bound_start (int deps, int prio)
- · void starpu_bound_stop (void)
- void starpu bound print dot (FILE *output)
- void starpu_bound_compute (double *res, double *integer_res, int integer)
- void starpu_bound_print_lp (FILE *output)
- void starpu bound print mps (FILE *output)
- void starpu_bound_print (FILE *output, int integer)

30.17.1 Detailed Description

Compute theoretical upper computation efficiency bound corresponding to some actual execution.

30.17.2 Function Documentation

30.17.2.1 starpu_bound_start()

Start recording tasks (resets stats). deps tells whether dependencies should be recorded too (this is quite expensive)

30.17.2.2 starpu_bound_stop()

Stop recording tasks

30.17.2.3 starpu_bound_print_dot()

Emit the DAG that was recorded on output.

30.17.2.4 starpu_bound_compute()

Get theoretical upper bound (in ms) (needs glpk support detected by configure script). It returns 0 if some performance models are not calibrated.

30.17.2.5 starpu_bound_print_lp()

Emit the Linear Programming system on output for the recorded tasks, in the lp format

30.17.2.6 starpu_bound_print_mps()

Emit the Linear Programming system on output for the recorded tasks, in the mps format

30.17.2.7 starpu_bound_print()

```
void starpu_bound_print (
     FILE * output,
     int integer )
```

Emit on output the statistics of actual execution vs theoretical upper bound. integer permits to choose between integer solving (which takes a long time but is correct), and relaxed solving (which provides an approximate solution).

30.18 CUDA Extensions

Macros

- #define STARPU CUBLAS REPORT ERROR(status)
- #define STARPU_CUDA_REPORT_ERROR(status)

Functions

- void starpu_cublas_report_error (const char *func, const char *file, int line, int status)
- void starpu_cuda_report_error (const char *func, const char *file, int line, cudaError_t status)
- cudaStream_t starpu_cuda_get_local_stream (void)
- const struct cudaDeviceProp * starpu_cuda_get_device_properties (unsigned workerid)
- int starpu_cuda_copy_async_sync (void *src_ptr, unsigned src_node, void *dst_ptr, unsigned dst_node, size_t ssize, cudaStream_t stream, enum cudaMemcpyKind kind)
- void starpu_cuda_set_device (unsigned devid)
- void starpu_cusparse_init (void)
- void starpu_cusparse_shutdown (void)
- cusparseHandle_t starpu_cusparse_get_local_handle (void)
- void starpu cublas init (void)
- void starpu_cublas_set_stream (void)
- void starpu_cublas_shutdown (void)

30.18 CUDA Extensions 321

30.18.1 Detailed Description

30.18.2 Macro Definition Documentation

30.18.2.1 STARPU_CUBLAS_REPORT_ERROR

Call starpu_cublas_report_error(), passing the current function, file and line position.

30.18.2.2 STARPU_CUDA_REPORT_ERROR

Call starpu_cuda_report_error(), passing the current function, file and line position.

30.18.3 Function Documentation

30.18.3.1 starpu_cusparse_init()

Initialize CUSPARSE on every CUDA device controlled by StarPU. This call blocks until CUSPARSE has been properly initialized on every device.

30.18.3.2 starpu_cublas_init()

Initialize CUBLAS on every CUDA device. The CUBLAS library must be initialized prior to any CUBLAS call. Calling starpu_cublas_init() will initialize CUBLAS on every CUDA device controlled by StarPU. This call blocks until CU \leftarrow BLAS has been properly initialized on every device.

30.18.3.3 starpu_cublas_report_error()

Report a CUBLAS error.

30.18.3.4 starpu_cuda_report_error()

Report a CUDA error.

30.18.3.5 starpu_cuda_get_local_stream()

Return the current worker's CUDA stream. StarPU provides a stream for every CUDA device controlled by Star \leftarrow PU. This function is only provided for convenience so that programmers can easily use asynchronous operations within codelets without having to create a stream by hand. Note that the application is not forced to use the stream provided by starpu_cuda_get_local_stream() and may also create its own streams. Synchronizing with cuda \leftarrow ThreadSynchronize() is allowed, but will reduce the likelihood of having all transfers overlapped.

30.18.3.6 starpu_cuda_get_device_properties()

Return a pointer to device properties for worker workerid (assumed to be a CUDA worker).

30.18.3.7 starpu_cuda_copy_async_sync()

```
int starpu_cuda_copy_async_sync (
          void * src_ptr,
          unsigned src_node,
          void * dst_ptr,
          unsigned dst_node,
          size_t ssize,
          cudaStream_t stream,
          enum cudaMemcpyKind kind )
```

Copy ssize bytes from the pointer src_ptr on src_node to the pointer dst_ptr on dst_node. The function first tries to copy the data asynchronous (unless stream is NULL). If the asynchronous copy fails or if stream is NULL, it copies the data synchronously. The function returns -EAGAIN if the asynchronous launch was successfull. It returns 0 if the synchronous copy was successful, or fails otherwise.

30.18.3.8 starpu_cuda_set_device()

```
void starpu_cuda_set_device (
          unsigned devid )
```

Call cudaSetDevice (devid) or cudaGLSetGLDevice (devid), according to whether devid is among the field starpu_conf::cuda_opengl_interoperability.

30.18.3.9 starpu_cublas_set_stream()

```
void starpu_cublas_set_stream (
```

Set the proper CUBLAS stream for CUBLAS v1. This must be called from the CUDA codelet before calling CUBLAS v1 kernels, so that they are queued on the proper CUDA stream. When using one thread per CUDA worker, this function does not do anything since the CUBLAS stream does not change, and is set once by starpu_cublas_init().

30.18.3.10 starpu_cublas_shutdown()

```
void starpu_cublas_shutdown (
```

Synchronously deinitialize the CUBLAS library on every CUDA device.

30.18.3.11 starpu_cusparse_shutdown()

Synchronously deinitialize the CUSPARSE library on every CUDA device.

30.18.3.12 starpu_cusparse_get_local_handle()

Return the CUSPARSE handle to be used to queue CUSPARSE kernels. It is properly initialized and configured for multistream by starpu_cusparse_init().

30.19 OpenCL Extensions

Data Structures

• struct starpu_opencl_program

Macros

- #define STARPU USE OPENCL
- #define STARPU MAXOPENCLDEVS
- #define STARPU_OPENCL_DATADIR

Writing OpenCL kernels

- void starpu opencl get context (int devid, cl context *context)
- void starpu_opencl_get_device (int devid, cl_device_id *device)
- void starpu_opencl_get_queue (int devid, cl_command_queue *queue)
- void starpu_opencl_get_current_context (cl_context *context)
- void starpu opencl get current queue (cl command queue *queue)
- int starpu_opencl_set_kernel_args (cl_int *err, cl_kernel *kernel,...)

Compiling OpenCL kernels

Source codes for OpenCL kernels can be stored in a file or in a string. StarPU provides functions to build the program executable for each available OpenCL device as a cl_program object. This program executable can then be loaded within a specific queue as explained in the next section. These are only helpers, Applications can also fill a starpu_opencl_program array by hand for more advanced use (e.g. different programs on the different OpenCL devices, for relocation purpose for instance).

- void starpu_opencl_load_program_source (const char *source_file_name, char *located_file_name, char *located_file_name,
- void starpu_opencl_load_program_source_malloc (const char *source_file_name, char **located_file_←
 name, char **located dir name, char **opencl program source)
- int starpu_opencl_compile_opencl_from_file (const char *source_file_name, const char *build_options)
- int starpu_opencl_compile_opencl_from_string (const char *opencl_program_source, const char *file_name, const char *build_options)
- int starpu_opencl_load_binary_opencl (const char *kernel_id, struct starpu_opencl_program *opencl_
 programs)
- int starpu_opencl_load_opencl_from_file (const char *source_file_name, struct starpu_opencl_program *opencl_programs, const char *build_options)
- int starpu_opencl_load_opencl_from_string (const char *opencl_program_source, struct starpu_opencl_
 program *opencl_programs, const char *build_options)
- int starpu_opencl_unload_opencl (struct starpu_opencl_program *opencl_programs)

Loading OpenCL kernels

- int starpu_opencl_load_kernel (cl_kernel *kernel, cl_command_queue *queue, struct starpu_opencl_comprogram *opencl_programs, const char *kernel_name, int devid)
- int starpu_opencl_release_kernel (cl_kernel kernel)

OpenCL Statistics

int starpu_opencl_collect_stats (cl_event event)

OpenCL Utilities

- const char * starpu_opencl_error_string (cl_int status)
- void starpu opencl display error (const char *func, const char *file, int line, const char *msg, cl int status)
- static __starpu_inline void starpu_opencl_report_error (const char *func, const char *file, int line, const char *msg, cl_int status)
- cl_int starpu_opencl_allocate_memory (int devid, cl_mem *addr, size_t size, cl_mem_flags flags)
- cl_int starpu_opencl_copy_ram_to_opencl (void *ptr, unsigned src_node, cl_mem buffer, unsigned dst_node, size_t size, size_t offset, cl_event *event, int *ret)
- cl_int starpu_opencl_copy_opencl_to_ram (cl_mem buffer, unsigned src_node, void *ptr, unsigned dst_node, size_t size, size_t offset, cl_event *event, int *ret)
- cl_int starpu_opencl_copy_opencl_to_opencl (cl_mem src, unsigned src_node, size_t src_offset, cl_mem dst, unsigned dst_node, size_t dst_offset, size_t size, cl_event *event, int *ret)
- cl_int starpu_opencl_copy_async_sync (uintptr_t src, size_t src_offset, unsigned src_node, uintptr_t dst, size_t dst_offset, unsigned dst_node, size_t size, cl_event *event)
- #define STARPU OPENCL DISPLAY ERROR(status)
- #define STARPU OPENCL REPORT ERROR(status)
- #define STARPU_OPENCL_REPORT_ERROR_WITH_MSG(msg, status)

30.19.1 Detailed Description

30.19.2 Data Structure Documentation

30.19.2.1 struct starpu_opencl_program

Store the OpenCL programs as compiled for the different OpenCL devices.

Data Fields

| cl_program | programs[STARPU_MAXOPENCLDEVS] | Store each program for each OpenCL device. |
|------------|--------------------------------|--|
|------------|--------------------------------|--|

30.19.3 Macro Definition Documentation

30.19.3.1 STARPU_USE_OPENCL

#define STARPU_USE_OPENCL

Defined when StarPU has been installed with OpenCL support. It should be used in your code to detect the availability of OpenCL as shown in Full source code for the 'Scaling a Vector' example.

30.19.3.2 STARPU_MAXOPENCLDEVS

#define STARPU_MAXOPENCLDEVS

Define the maximum number of OpenCL devices that are supported by StarPU.

30.19.3.3 STARPU_OPENCL_DATADIR

#define STARPU_OPENCL_DATADIR

Define the directory in which the OpenCL codelets of the applications provided with StarPU have been installed.

30.19.3.4 STARPU_OPENCL_DISPLAY_ERROR

Call the function starpu_opencl_display_error() with the error status, the current function name, current file and line number, and a empty message.

30.19.3.5 STARPU_OPENCL_REPORT_ERROR

Call the function starpu_opencl_report_error() with the error status, the current function name, current file and line number, and a empty message.

30.19.3.6 STARPU OPENCL REPORT ERROR WITH MSG

Call the function starpu_opencl_report_error() with msg and status, the current function name, current file and line number.

30.19.4 Function Documentation

30.19.4.1 starpu_opencl_get_context()

Return the OpenCL context of the device designated by devid in context.

30.19.4.2 starpu_opencl_get_device()

Return the cl_device_id corresponding to devid in device.

30.19.4.3 starpu_opencl_get_queue()

Return the command queue of the device designated by ${\tt devid}$ into ${\tt queue}.$

30.19.4.4 starpu_opencl_get_current_context()

Return the context of the current worker.

30.19.4.5 starpu_opencl_get_current_queue()

Return the computation kernel command queue of the current worker.

30.19.4.6 starpu_opencl_set_kernel_args()

Set the arguments of a given kernel. The list of arguments must be given as ($size_t size_of_the_\leftrightarrow argument$, $cl_mem * pointer_to_the_argument$). The last argument must be 0. Return the number

of arguments that were successfully set. In case of failure, return the id of the argument that could not be set and err is set to the error returned by OpenCL. Otherwise, return the number of arguments that were set. Here an example:

30.19.4.7 starpu_opencl_load_program_source()

Store the contents of the file <code>source_file_name</code> in the buffer <code>opencl_program_source</code>. The file <code>source_file_name</code> can be located in the current directory, or in the directory specified by the environment variable <code>STARPU_OPENCL_PROGRAM_DIR</code>, or in the directory <code>share/starpu/opencl</code> of the installation directory of <code>StarPU</code>, or in the source directory of <code>StarPU</code>. When the file is found, <code>located_file_name</code> is the full name of the file as it has been located on the <code>system</code>, <code>located_dir_name</code> the directory where it has been located. Otherwise, they are both set to the empty string.

30.19.4.8 starpu_opencl_load_program_source_malloc()

Similar to function starpu_opencl_load_program_source() but allocate the buffers located_file_name, located_dir_name and opencl_program_source.

30.19.4.9 starpu_opencl_compile_opencl_from_file()

Compile the OpenCL kernel stored in the file <code>source_file_name</code> with the given options <code>build_options</code> and store the result in the directory <code>\$STARPU_HOME/.starpu/opencl</code> with the same filename as <code>source-file_name</code>. The compilation is done for every OpenCL device, and the filename is suffixed with the vendor id and the device id of the OpenCL device.

30.19.4.10 starpu_opencl_compile_opencl_from_string()

Compile the OpenCL kernel in the string <code>opencl_program_source</code> with the given options <code>build_options</code> and store the result in the directory <code>\$STARPU_HOME/.starpu/opencl</code> with the filename <code>file_name</code>. The compilation is done for every <code>OpenCL</code> device, and the filename is suffixed with the vendor id and the device id of the <code>OpenCL</code> device.

30.19.4.11 starpu_opencl_load_binary_opencl()

Compile the binary OpenCL kernel identified with kernel_id. For every OpenCL device, the binary Open CL kernel will be loaded from the file \$STARPU_HOME/.starpu/opencl/<kernel_id>.<device_ type>.vendor_id_<vendor_id>_device_id_<device_id>.

30.19.4.12 starpu_opencl_load_opencl_from_file()

Compile an OpenCL source code stored in a file.

30.19.4.13 starpu_opencl_load_opencl_from_string()

Compile an OpenCL source code stored in a string.

30.19.4.14 starpu_opencl_unload_opencl()

Unload an OpenCL compiled code.

30.19.4.15 starpu_opencl_load_kernel()

Create a kernel kernel for device devid, on its computation command queue returned in queue, using program opencl_programs and name kernel_name.

30.19.4.16 starpu_opencl_release_kernel()

Release the given kernel, to be called after kernel execution.

30.19.4.17 starpu_opencl_collect_stats()

Collect statistics on a kernel execution. After termination of the kernels, the OpenCL codelet should call this function with the event returned by clEnqueueNDRangeKernel(), to let StarPU collect statistics about the kernel execution (used cycles, consumed energy).

30.19.4.18 starpu_opencl_error_string()

Return the error message in English corresponding to status, an OpenCL error code.

30.19.4.19 starpu_opencl_display_error()

Given a valid error status, print the corresponding error message on stdout, along with the function name func, the filename file, the line number line and the message msg.

30.19.4.20 starpu_opencl_report_error()

Call the function starpu_opencl_display_error() and abort.

30.19.4.21 starpu_opencl_allocate_memory()

Allocate size bytes of memory, stored in addr. flags must be a valid combination of cl_mem_flags values.

30.19.4.22 starpu_opencl_copy_ram_to_opencl()

Copy size bytes from the given ptr on RAM src_node to the given buffer on OpenCL dst_node. offset is the offset, in bytes, in buffer. if event is NULL, the copy is synchronous, i.e the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. This function returns CL_SUCCESS if the copy was successful, or a valid OpenCL error code otherwise. The integer pointed to by ret is set to -EAGAIN if the asynchronous launch was successful, or to 0 if event was NULL.

30.19.4.23 starpu_opencl_copy_opencl_to_ram()

```
cl_event * event,
int * ret )
```

Copy size bytes asynchronously from the given buffer on OpenCL src_node to the given ptr on RAM dst_node. offset is the offset, in bytes, in buffer. if event is NULL, the copy is synchronous, i.e the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. This function returns CL_SUCCESS if the copy was successful, or a valid OpenCL error code otherwise. The integer pointed to by ret is set to -EAGAIN if the asynchronous launch was successful, or to 0 if event was NULL.

30.19.4.24 starpu_opencl_copy_opencl_to_opencl()

Copy size bytes asynchronously from byte offset src_offset of src on OpenCL src_node to byte offset dst_offset of dst on OpenCL dst_node. if event is NULL, the copy is synchronous, i.e. the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. This function returns CL_SUCCESS if the copy was successful, or a valid OpenCL error code otherwise. The integer pointed to by ret is set to -EAGAIN if the asynchronous launch was successful, or to 0 if event was NULL.

30.19.4.25 starpu_opencl_copy_async_sync()

Copy size bytes from byte offset src_offset of src on src_node to byte offset dst_offset of dst on dst_node. if event is NULL, the copy is synchronous, i.e. the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. The function returns -EAGAIN if the asynchronous launch was successfull. It returns 0 if the synchronous copy was successful, or fails otherwise.

30.20 OpenMP Runtime Support

This section describes the interface provided for implementing OpenMP runtimes on top of StarPU.

Data Structures

- · struct starpu_omp_lock_t
- struct starpu_omp_nest_lock_t
- · struct starpu_omp_parallel_region_attr
- struct starpu_omp_task_region_attr

Macros

• #define STARPU OPENMP

#define __STARPU_OMP_NOTHROW

Enumerations

```
    enum starpu_omp_sched_value {
        starpu_omp_sched_undefined, starpu_omp_sched_static, starpu_omp_sched_dynamic, starpu_omp_
        sched_guided,
        starpu_omp_sched_auto, starpu_omp_sched_runtime }
    enum starpu_omp_proc_bind_value {
        starpu_omp_proc_bind_undefined, starpu_omp_proc_bind_false, starpu_omp_proc_bind_true, starpu_
        omp_proc_bind_master,
        starpu_omp_proc_bind_close, starpu_omp_proc_bind_spread }
```

Initialisation

- int starpu omp init (void) STARPU OMP NOTHROW
- void starpu omp shutdown (void) STARPU OMP NOTHROW

Parallel

- void starpu_omp_parallel_region (const struct starpu_omp_parallel_region_attr *attr) __STARPU_OMP_← NOTHROW
- void starpu_omp_master (void(*f)(void *arg), void *arg) __STARPU_OMP_NOTHROW
- int starpu_omp_master_inline (void) __STARPU_OMP_NOTHROW

Synchronization

- void starpu_omp_barrier (void) __STARPU_OMP_NOTHROW
- void starpu omp critical (void(*f)(void *arg), void *arg, const char *name)
 STARPU OMP NOTHROW
- void starpu_omp_critical_inline_begin (const char *name) __STARPU_OMP_NOTHROW
- void starpu omp critical inline end (const char *name)
 STARPU OMP NOTHROW

Worksharing

- void starpu_omp_single (void(*f)(void *arg), void *arg, int nowait) __STARPU_OMP_NOTHROW
- int starpu_omp_single_inline (void) __STARPU_OMP_NOTHROW
- void starpu_omp_single_copyprivate (void(*f)(void *arg, void *data, unsigned long long data_size), void *arg, void *data, unsigned long long data_size) STARPU OMP NOTHROW
- void * starpu omp single copyprivate inline begin (void *data)
 STARPU OMP NOTHROW
- void starpu_omp_single_copyprivate_inline_end (void) __STARPU_OMP_NOTHROW
- int starpu_omp_for_inline_first (unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long *_first_i, unsigned long long *_nb_i) __STARPU_OMP_NOTHROW
- int starpu_omp_for_inline_next (unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long *_first_i, unsigned long long *_nb_i) __STARPU_OMP_NOTHROW
- void starpu_omp_for_alt (void(*f)(unsigned long long _begin_i, unsigned long long _end_i, void *arg), void *arg, unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) __
 STARPU_OMP_NOTHROW
- int starpu_omp_for_inline_first_alt (unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long * begin i, unsigned long long * end i) STARPU OMP NOTHROW
- int starpu_omp_for_inline_next_alt (unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long *_begin_i, unsigned long long *_end_i) __STARPU_OMP_NOTHROW
- void starpu_omp_ordered (void(*f)(void *arg), void *arg) __STARPU_OMP_NOTHROW
- void starpu omp ordered inline begin (void)
 STARPU OMP NOTHROW
- void starpu_omp_ordered_inline_end (void) __STARPU_OMP NOTHROW

- void starpu_omp_sections (unsigned long long nb_sections, void(**section_f)(void *arg), void **section_arg, int nowait)
 STARPU OMP NOTHROW
- void starpu_omp_sections_combined (unsigned long long nb_sections, void(*section_f)(unsigned long long section_num, void *arg), void *section_arg, int nowait) __STARPU_OMP_NOTHROW

Task

- void starpu_omp_task_region (const struct starpu_omp_task_region_attr *attr) __STARPU_OMP_NOTH
 BOW
- void starpu omp taskwait (void) STARPU OMP NOTHROW
- void starpu_omp_taskgroup (void(*f)(void *arg), void *arg) __STARPU_OMP_NOTHROW
- void starpu_omp_taskgroup_inline_begin (void) __STARPU_OMP_NOTHROW
- · void starpu omp taskgroup inline end (void) STARPU OMP NOTHROW
- void starpu_omp_taskloop_inline_begin (struct starpu_omp_task_region_attr *attr) __STARPU_OMP
 —NOTHROW
- void starpu_omp_taskloop_inline_end (const struct starpu_omp_task_region_attr *attr) __STARPU_O
 MP NOTHROW

API

- void starpu omp set num threads (int threads)
 STARPU OMP NOTHROW
- int starpu omp get num threads () STARPU OMP NOTHROW
- int starpu_omp_get_thread_num () __STARPU_OMP_NOTHROW
- int starpu_omp_get_max_threads () __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_procs (void) __STARPU_OMP_NOTHROW
- int starpu_omp_in_parallel (void) __STARPU_OMP_NOTHROW
- void starpu_omp_set_dynamic (int dynamic_threads) __STARPU_OMP_NOTHROW
- int starpu_omp_get_dynamic (void) __STARPU_OMP_NOTHROW
- void starpu_omp_set_nested (int nested) __STARPU_OMP_NOTHROW
- int starpu_omp_get_nested (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_cancellation (void) __STARPU_OMP_NOTHROW
- void starpu_omp_get_schedule (enum starpu_omp_sched_value *kind, int *modifier) __STARPU_OMP_← NOTHROW
- int starpu_omp_get_thread_limit (void) __STARPU_OMP_NOTHROW
- void starpu omp set max active levels (int max levels)
 STARPU OMP NOTHROW
- int starpu_omp_get_max_active_levels (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_level (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_ancestor_thread_num (int level) __STARPU_OMP_NOTHROW
- int starpu_omp_get_team_size (int level) __STARPU_OMP_NOTHROW
- int starpu_omp_get_active_level (void) __STARPU_OMP_NOTHROW
- int starpu_omp_in_final (void) __STARPU_OMP_NOTHROW
- enum starpu_omp_proc_bind_value starpu_omp_get_proc_bind (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_places (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_place_num_procs (int place_num) __STARPU_OMP_NOTHROW
- void **starpu_omp_get_place_proc_ids** (int place_num, int *ids) __STARPU_OMP_NOTHROW
- int starpu_omp_get_place_num (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_partition_num_places (void) __STARPU_OMP_NOTHROW
- void starpu_omp_get_partition_place_nums (int *place_nums) __STARPU_OMP_NOTHROW
- void starpu omp set default device (int device num) STARPU OMP NOTHROW
- int starpu_omp_get_default_device (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_devices (void) __STARPU_OMP_NOTHROW
- int starpu omp get num teams (void) STARPU OMP NOTHROW
- int starpu_omp_get_team_num (void) __STARPU_OMP_NOTHROW

- int starpu_omp_is_initial_device (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_initial_device (void) __STARPU_OMP_NOTHROW
- int starpu omp get max task priority (void) STARPU OMP NOTHROW
- void starpu omp init lock (starpu omp lock t *lock) STARPU OMP NOTHROW
- void starpu_omp_destroy_lock (starpu_omp_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu_omp_set_lock (starpu_omp_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu_omp_unset_lock (starpu_omp_lock_t *lock) __STARPU_OMP_NOTHROW
- int starpu omp test lock (starpu omp lock t *lock) STARPU OMP NOTHROW
- void starpu omp init nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu omp destroy nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu omp set nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu_omp_unset_nest_lock (starpu_omp_nest_lock_t *lock) __STARPU_OMP_NOTHROW
- int starpu_omp_test_nest_lock (starpu_omp_nest_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu_omp_atomic_fallback_inline_begin (void) __STARPU_OMP_NOTHROW
- · void starpu omp atomic fallback inline end (void) STARPU OMP NOTHROW
- double starpu omp get wtime (void)
 STARPU OMP NOTHROW
- double starpu_omp_get_wtick (void) __STARPU_OMP_NOTHROW
- struct starpu arbiter * starpu omp get default arbiter (void) STARPU OMP NOTHROW

30.20.1 Detailed Description

This section describes the interface provided for implementing OpenMP runtimes on top of StarPU.

30.20.2 Data Structure Documentation

30.20.2.1 struct starpu_omp_lock_t

Opaque Simple Lock object (Simple Locks) for inter-task synchronization operations.

See also

```
starpu_omp_init_lock()
starpu_omp_destroy_lock()
starpu_omp_set_lock()
starpu_omp_unset_lock()
starpu_omp_test_lock()
```

Data Fields

```
void * internal opaque pointer for internal use
```

30.20.2.2 struct starpu_omp_nest_lock_t

Opaque Nestable Lock object (Nestable Locks) for inter-task synchronization operations.

```
starpu_omp_init_nest_lock()
starpu_omp_destroy_nest_lock()
starpu_omp_set_nest_lock()
starpu_omp_unset_nest_lock()
starpu_omp_test_nest_lock()
```

Data Fields

| void * | internal | opaque pointer for internal use |
|--------|----------|---------------------------------|
|--------|----------|---------------------------------|

30.20.2.3 struct starpu_omp_parallel_region_attr

Set of attributes used for creating a new parallel region.

See also

starpu_omp_parallel_region()

Data Fields

| struct starpu_codelet | cl | starpu_codelet (Codelet And Tasks) to use for the parallel region implicit tasks. The codelet must provide a CPU implementation function. |
|------------------------|-------------|---|
| starpu_data_handle_t * | handles | Array of zero or more starpu_data_handle_t data handle to be passed to the parallel region implicit tasks. |
| void * | cl_arg | Optional pointer to an inline argument to be passed to the region implicit tasks. |
| size_t | cl_arg_size | Size of the optional inline argument to be passed to the region implicit tasks, or 0 if unused. |
| unsigned | cl_arg_free | Boolean indicating whether the optional inline argument should be automatically freed (true), or not (false). |
| int | if_clause | Boolean indicating whether the if clause of the corresponding pragma omp parallel is true or false. |
| int | num_threads | Integer indicating the requested number of threads in the team of the newly created parallel region, or 0 to let the runtime choose the number of threads alone. This attribute may be ignored by the runtime system if the requested number of threads is higher than the number of threads that the runtime can create. |

30.20.2.4 struct starpu_omp_task_region_attr

Set of attributes used for creating a new task region.

See also

starpu_omp_task_region()

Data Fields

| struct starpu_codelet | cl | starpu_codelet (Codelet And Tasks) to use for the task region explicit task. The codelet must provide a CPU implementation function or an accelerator implementation for offloaded target regions. |
|------------------------|-------------|--|
| starpu_data_handle_t * | handles | Array of zero or more starpu_data_handle_t data handle to be passed to the task region explicit tasks. |
| void * | cl_arg | Optional pointer to an inline argument to be passed to the region implicit tasks. |
| size_t | cl_arg_size | Size of the optional inline argument to be passed to the region implicit tasks, or 0 if unused. |
| unsigned | cl_arg_free | Boolean indicating whether the optional inline argument should be automatically freed (true), or not (false). |

Data Fields

| int | priority | |
|--------------------|------------------|---|
| int | if_clause | Boolean indicating whether the if clause of the corresponding |
| | | pragma omp task is true or false. |
| int | final_clause | Boolean indicating whether the final clause of the |
| | | corresponding pragma omp task is true or false. |
| int | untied_clause | Boolean indicating whether the untied clause of the |
| | | corresponding pragma omp task is true or false. |
| int | mergeable_clause | Boolean indicating whether the mergeable clause of the |
| | | corresponding pragma omp task is true or false. |
| int | is_loop | taskloop attribute |
| int | nogroup_clause | |
| int | collapse | |
| int | num_tasks | |
| unsigned long long | nb_iterations | |
| unsigned long long | grainsize | |
| unsigned long long | begin_i | |
| unsigned long long | end_i | |
| unsigned long long | chunk | |

30.20.3 Macro Definition Documentation

30.20.3.1 STARPU_OPENMP

#define STARPU_OPENMP

This macro is defined when StarPU has been installed with OpenMP Runtime support. It should be used in your code to detect the availability of the runtime support for OpenMP.

30.20.4 Enumeration Type Documentation

30.20.4.1 starpu_omp_sched_value

```
enum starpu_omp_sched_value
```

Set of constants for selecting the for loop iteration scheduling algorithm (Parallel For) as defined by the OpenMP specification.

See also

```
starpu_omp_for()
starpu_omp_for_inline_first()
starpu_omp_for_inline_next()
starpu_omp_for_alt()
starpu_omp_for_inline_first_alt()
starpu_omp_for_inline_next_alt()
```

Enumerator

| starpu_omp_sched_undefined | Undefined iteration scheduling algorithm. |
|----------------------------|---|
| starpu_omp_sched_static | Static iteration scheduling algorithm. |
| starpu_omp_sched_dynamic | Dynamic iteration scheduling algorithm. |

Enumerator

| starpu_omp_sched_guided | Guided iteration scheduling algorithm. |
|--------------------------|---|
| starpu_omp_sched_auto | Automatically choosen iteration scheduling algorithm. |
| starpu_omp_sched_runtime | Choice of iteration scheduling algorithm deferred at runtime . |

30.20.4.2 starpu_omp_proc_bind_value

```
enum starpu_omp_proc_bind_value
```

Set of constants for selecting the processor binding method, as defined in the OpenMP specification.

See also

```
starpu_omp_get_proc_bind()
```

Enumerator

| starpu_omp_proc_bind_undefined | Undefined processor binding method. |
|--------------------------------|--|
| starpu_omp_proc_bind_false | Team threads may be moved between places at any time. |
| starpu_omp_proc_bind_true | Team threads may not be moved between places. |
| starpu_omp_proc_bind_master | Assign every thread in the team to the same place as the master thread. |
| starpu_omp_proc_bind_close | Assign every thread in the team to a place close to the parent thread. |
| starpu_omp_proc_bind_spread | Assign team threads as a sparse distribution over the selected places. |

30.20.5 Function Documentation

30.20.5.1 starpu_omp_init()

Initialize StarPU and its OpenMP Runtime support.

30.20.5.2 starpu_omp_shutdown()

Shutdown StarPU and its OpenMP Runtime support.

30.20.5.3 starpu_omp_parallel_region()

Generate and launch an OpenMP parallel region and return after its completion. attr specifies the attributes for the generated parallel region. If this function is called from inside another, generating, parallel region, the generated parallel region is nested within the generating parallel region.

This function can be used to implement #pragma omp parallel.

30.20.5.4 starpu_omp_master()

Execute a function only on the master thread of the OpenMP parallel region it is called from. When called from a thread that is not the master of the parallel region it is called from, this function does nothing. f is the function to be called. arg is an argument passed to function f.

This function can be used to implement #pragma omp master.

30.20.5.5 starpu_omp_master_inline()

Determine whether the calling thread is the master of the OpenMP parallel region it is called from or not.

This function can be used to implement #pragma omp master without code outlining.

Returns

- ! 0 if called by the region's master thread.
- 0 if not called by the region's master thread.

30.20.5.6 starpu_omp_barrier()

Wait until each participating thread of the innermost OpenMP parallel region has reached the barrier and each explicit OpenMP task bound to this region has completed its execution.

This function can be used to implement #pragma omp barrier.

30.20.5.7 starpu_omp_critical()

Wait until no other thread is executing within the context of the selected critical section, then proceeds to the exclusive execution of a function within the critical section. f is the function to be executed in the critical section. f arg is an argument passed to function f. name is the name of the selected critical section. If f name f is the unique anonymous critical section.

This function can be used to implement #pragma omp critical.

30.20.5.8 starpu_omp_critical_inline_begin()

Wait until execution can proceed exclusively within the context of the selected critical section. name is the name of the selected critical section. If name = NULL, the selected critical section is the unique anonymous critical section

This function together with starpu_omp_critical_inline_end can be used to implement #pragma omp critical without code outlining.

30.20.5.9 starpu_omp_critical_inline_end()

End the exclusive execution within the context of the selected critical section. name is the name of the selected critical section. If name==NULL, the selected critical section is the unique anonymous critical section.

This function together with starpu_omp_critical_inline_begin can be used to implement #pragma omp critical without code outlining.

30.20.5.10 starpu_omp_single()

Ensure that a single participating thread of the innermost OpenMP parallel region executes a function. f is the function to be executed by a single thread. f is an argument passed to function f. f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating whether an implicit barrier is requested after the single section (f is a flag indicating the secti

This function can be used to implement #pragma omp single.

30.20.5.11 starpu_omp_single_inline()

Decide whether the current thread is elected to run the following single section among the participating threads of the innermost OpenMP parallel region.

This function can be used to implement #pragma omp single without code outlining.

Returns

- ! 0 if the calling thread has won the election.
- 0 if the calling thread has lost the election.

30.20.5.12 starpu_omp_single_copyprivate()

```
void starpu_omp_single_copyprivate (
          void(*)(void *arg, void *data, unsigned long long data_size) f,
          void * arg,
          void * data,
          unsigned long long data_size )
```

Execute f on a single task of the current parallel region task, and then broadcast the contents of the memory block pointed by the copyprivate pointer data and of size data_size to the corresponding data pointed memory blocks of all the other participating region tasks. This function can be used to implement #pragma omp single with a copyprivate clause.

See also

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_begin
starpu_omp_single_copyprivate_inline_end
```

30.20.5.13 starpu_omp_single_copyprivate_inline_begin()

```
void* starpu_omp_single_copyprivate_inline_begin (  {\tt void} \ * \ data \ )
```

Elect one task among the tasks of the current parallel region task to execute the following single section, and then broadcast the copyprivate pointer data to all the other participating region tasks. This function can be used to implement #pragma omp single with a copyprivate clause without code outlining.

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_end
```

30.20.5.14 starpu_omp_single_copyprivate_inline_end()

Complete the execution of a single section and return the broadcasted copyprivate pointer for tasks that lost the election and NULL for the task that won the election. This function can be used to implement $pragma \ omp \ single$ with a copyprivate clause without code outlining.

Returns

the copyprivate pointer for tasks that lost the election and therefore did not execute the code of the single section

NULL for the task that won the election and executed the code of the single section.

See also

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_begin
```

30.20.5.15 starpu_omp_for()

Execute a parallel loop together with the other threads participating to the innermost parallel region. f is the function to be executed iteratively. f is an argument passed to function f. f in f iterations is the number of iterations to be performed by the parallel loop. f chunk is the number of consecutive iterations that should be affected to the same thread when scheduling the loop workshares, it follows the semantics of the f modifier argument in OpenMP #pragma omp for specification. f schedule is the scheduling mode according to the OpenMP specification. f ordered is a flag indicating whether the loop region may contain an ordered section (f ordered==10) or not (f ordered==0). f nowait is a flag indicating whether an implicit barrier is requested after the for section (f nowait==0) or not (f nowait==10).

The function f will be called with arguments _first_i, the first iteration to perform, _nb_i, the number of consecutive iterations to perform before returning, arg, the free arg argument.

This function can be used to implement #pragma omp for.

30.20.5.16 starpu_omp_for_inline_first()

```
int starpu_omp_for_inline_first (
          unsigned long long nb_iterations,
          unsigned long long chunk,
          int schedule,
          int ordered,
          unsigned long long * _first_i,
          unsigned long long * _nb_i )
```

Decide whether the current thread should start to execute a parallel loop section. See starpu_omp_for for the argument description.

This function together with starpu_omp_for_inline_next can be used to implement #pragma omp for without code outlining.

Returns

- $!\,0$ if the calling thread participates to the loop region and should execute a first chunk of iterations. In that case, $*_first_i$ will be set to the first iteration of the chunk to perform and $*_nb_i$ will be set to the number of iterations of the chunk to perform.
- 0 if the calling thread does not participate to the loop region because all the available iterations have been affected to the other threads of the parallel region.

See also

```
starpu omp for
```

30.20.5.17 starpu_omp_for_inline_next()

```
int starpu_omp_for_inline_next (
    unsigned long long nb_iterations,
    unsigned long long chunk,
    int schedule,
    int ordered,
    unsigned long long * _first_i,
    unsigned long long * _nb_i )
```

Decide whether the current thread should continue to execute a parallel loop section. See starpu_omp_for for the argument description.

This function together with starpu_omp_for_inline_first can be used to implement #pragma omp for without code outlining.

Returns

 $!\,0$ if the calling thread should execute a next chunk of iterations. In that case, $*_first_i$ will be set to the first iteration of the chunk to perform and $*_nb_i$ will be set to the number of iterations of the chunk to perform.

0 if the calling thread does not participate anymore to the loop region because all the available iterations have been affected to the other threads of the parallel region.

See also

```
starpu_omp_for
```

30.20.5.18 starpu_omp_for_alt()

```
void starpu_omp_for_alt (
          void(*)(unsigned long long _begin_i, unsigned long long _end_i, void *arg) f,
          void * arg,
          unsigned long long nb_iterations,
          unsigned long long chunk,
          int schedule,
          int ordered,
          int nowait )
```

Alternative implementation of a parallel loop. Differ from starpu_omp_for in the expected arguments of the loop function f.

The function f will be called with arguments _begin_i, the first iteration to perform, _end_i, the first iteration not to perform before returning, arg, the free arg argument.

This function can be used to implement #pragma omp for.

```
starpu_omp_for
```

30.20.5.19 starpu_omp_for_inline_first_alt()

```
int starpu_omp_for_inline_first_alt (
        unsigned long long nb_iterations,
        unsigned long long chunk,
        int schedule,
        int ordered,
        unsigned long long * _begin_i,
        unsigned long long * _end_i )
```

Inline version of the alternative implementation of a parallel loop.

This function together with starpu_omp_for_inline_next_alt can be used to implement #pragma omp for without code outlining.

See also

```
starpu_omp_for
starpu_omp_for_alt
starpu_omp_for_inline_first
```

30.20.5.20 starpu_omp_for_inline_next_alt()

```
int starpu_omp_for_inline_next_alt (
    unsigned long long nb_iterations,
    unsigned long long chunk,
    int schedule,
    int ordered,
    unsigned long long * _begin_i,
    unsigned long long * _end_i )
```

Inline version of the alternative implementation of a parallel loop.

This function together with starpu_omp_for_inline_first_alt can be used to implement $\#pragma \ omp \ for without code outlining.$

See also

```
starpu_omp_for
starpu_omp_for_alt
starpu_omp_for_inline_next
```

30.20.5.21 starpu_omp_ordered()

```
void starpu_omp_ordered (
          void(*)(void *arg) f,
          void * arg )
```

Ensure that a function is sequentially executed once for each iteration in order within a parallel loop, by the thread that own the iteration. f is the function to be executed by the thread that own the current iteration. f is an argument passed to function f.

This function can be used to implement #pragma omp ordered.

30.20.5.22 starpu_omp_ordered_inline_begin()

```
void starpu_omp_ordered_inline_begin (
```

Wait until all the iterations of a parallel loop below the iteration owned by the current thread have been executed. This function together with starpu_omp_ordered_inline_end can be used to implement #pragma omp ordered without code code outlining.

30.20.5.23 starpu_omp_ordered_inline_end()

Notify that the ordered section for the current iteration has been completed.

This function together with starpu_omp_ordered_inline_begin can be used to implement #pragma omp ordered without code code outlining.

30.20.5.24 starpu_omp_sections()

```
void starpu_omp_sections (
        unsigned long long nb_sections,
        void(**)(void *arg) section_f,
        void ** section_arg,
        int nowait)
```

Ensure that each function of a given array of functions is executed by one and only one thread. $nb_sections$ is the number of functions in the array $section_f$. $section_f$ is the array of functions to be executed as sections. $section_arg$ is an array of arguments to be passed to the corresponding function. nowait is a flag indicating whether an implicit barrier is requested after the execution of all the sections (nowait==0) or not (nowait==0).

This function can be used to implement #pragma omp sections and #pragma omp section.

30.20.5.25 starpu_omp_sections_combined()

```
void starpu_omp_sections_combined (
          unsigned long long nb_sections,
          void(*)(unsigned long long section_num, void *arg) section_f,
          void * section_arg,
          int nowait)
```

Alternative implementation of sections. Differ from starpu_omp_sections in that all the sections are combined within a single function in this version. section_f is the function implementing the combined sections.

The function section_f will be called with arguments section_num, the section number to be executed, arg, the entry of section_arg corresponding to this section.

This function can be used to implement #pragma omp sections and #pragma omp section.

See also

starpu_omp_sections

30.20.5.26 starpu_omp_task_region()

Generate an explicit child task. The execution of the generated task is asynchronous with respect to the calling code unless specified otherwise. attr specifies the attributes for the generated task region.

This function can be used to implement #pragma omp task.

30.20.5.27 starpu_omp_taskwait()

Wait for the completion of the tasks generated by the current task. This function does not wait for the descendants of the tasks generated by the current task.

This function can be used to implement #pragma omp taskwait.

30.20.5.28 starpu_omp_taskgroup()

Launch a function and wait for the completion of every descendant task generated during the execution of the function.

This function can be used to implement #pragma omp taskgroup.

See also

```
starpu_omp_taskgroup_inline_begin
starpu omp taskgroup inline end
```

30.20.5.29 starpu_omp_taskgroup_inline_begin()

Launch a function and gets ready to wait for the completion of every descendant task generated during the dynamic scope of the taskgroup.

This function can be used to implement #pragma omp taskgroup without code outlining.

See also

```
starpu_omp_taskgroup starpu omp taskgroup inline end
```

30.20.5.30 starpu_omp_taskgroup_inline_end()

Wait for the completion of every descendant task generated during the dynamic scope of the taskgroup.

This function can be used to implement #pragma omp taskgroup without code outlining.

See also

```
starpu_omp_taskgroup
starpu_omp_taskgroup_inline_begin
```

30.20.5.31 starpu_omp_set_num_threads()

Set ICVS nthreads var for the parallel regions to be created with the current region.

Note: The StarPU OpenMP runtime support currently ignores this setting for nested parallel regions.

See also

```
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

30.20.5.32 starpu_omp_get_num_threads()

```
int starpu_omp_get_num_threads ( )
```

Return the number of threads of the current region.

Returns

the number of threads of the current region.

See also

```
starpu_omp_set_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

30.20.5.33 starpu_omp_get_thread_num()

```
int starpu_omp_get_thread_num ( )
```

Return the rank of the current thread among the threads of the current region.

Returns

the rank of the current thread in the current region.

See also

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

30.20.5.34 starpu_omp_get_max_threads()

```
int starpu_omp_get_max_threads ( )
```

Return the maximum number of threads that can be used to create a region from the current region.

Returns

the maximum number of threads that can be used to create a region from the current region.

See also

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_num_procs
```

30.20.5.35 starpu_omp_get_num_procs()

Return the number of StarPU CPU workers.

Returns

the number of StarPU CPU workers.

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
```

Enable (1) or disable (0) dynamically adjusting the number of parallel threads.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

See also

```
starpu_omp_get_dynamic
```

Return the state of dynamic thread number adjustment.

Returns

- ! 0 if dynamic thread number adjustment is enabled.
- 0 otherwise.

See also

```
starpu_omp_set_dynamic
```

```
30.20.5.39 starpu_omp_set_nested()
```

Enable (1) or disable (0) nested parallel regions.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

```
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

```
30.20.5.40 starpu_omp_get_nested()
```

Return whether nested parallel sections are enabled or not.

Returns

- ! 0 if nested parallel sections are enabled.
- 0 otherwise.

See also

```
starpu_omp_set_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

30.20.5.41 starpu_omp_get_cancellation()

```
\begin{tabular}{ll} int starpu\_omp\_get\_cancellation ( \\ void ) \end{tabular}
```

Return the state of the cancel ICVS var.

30.20.5.42 starpu_omp_set_schedule()

Set the default scheduling kind for upcoming loops within the current parallel section. kind is the scheduler kind, modifier complements the scheduler kind with informations such as the chunk size, in accordance with the OpenMP specification.

See also

```
starpu_omp_get_schedule
```

30.20.5.43 starpu_omp_get_schedule()

Return the current selected default loop scheduler.

Returns

the kind and the modifier of the current default loop scheduler.

```
starpu_omp_set_schedule
```

```
30.20.5.44 starpu_omp_get_thread_limit()
```

Return the number of StarPU CPU workers.

Returns

the number of StarPU CPU workers.

```
30.20.5.45 starpu_omp_set_max_active_levels()
```

Set the maximum number of allowed active parallel section levels.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function and assume max_ \leftarrow levels equals 1 instead.

See also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

30.20.5.46 starpu_omp_get_max_active_levels()

Return the current maximum number of allowed active parallel section levels

Returns

the current maximum number of allowed active parallel section levels.

See also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

30.20.5.47 starpu_omp_get_level()

Return the nesting level of the current parallel section.

Returns

the nesting level of the current parallel section.

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_active_level
```

```
30.20.5.48 starpu_omp_get_ancestor_thread_num()
```

Return the number of the ancestor of the current parallel section.

Returns

the number of the ancestor of the current parallel section.

30.20.5.49 starpu_omp_get_team_size()

Return the size of the team of the current parallel section.

Returns

the size of the team of the current parallel section.

30.20.5.50 starpu_omp_get_active_level()

Return the nestinglevel of the current innermost active parallel section.

Returns

the nestinglevel of the current innermost active parallel section.

See also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
```

30.20.5.51 starpu_omp_in_final()

Check whether the current task is final or not.

Returns

```
! 0 if called from a final task.
```

0 otherwise.

30.20.5.52 starpu_omp_get_proc_bind()

Return the proc_bind setting of the current parallel region.

Returns

the proc_bind setting of the current parallel region.

```
30.20.5.53 starpu_omp_set_default_device()
```

Set the number of the device to use as default.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

See also

```
starpu_omp_get_default_device
starpu_omp_is_initial_device
```

30.20.5.54 starpu_omp_get_default_device()

Return the number of the device used as default.

Returns

the number of the device used as default.

See also

```
starpu_omp_set_default_device
starpu_omp_is_initial_device
```

30.20.5.55 starpu_omp_get_num_devices()

Return the number of the devices.

Returns

the number of the devices.

30.20.5.56 starpu_omp_get_num_teams()

Return the number of teams in the current teams region.

Returns

the number of teams in the current teams region.

See also

```
starpu_omp_get_num_teams
```

30.20.5.57 starpu_omp_get_team_num()

Return the team number of the calling thread.

Returns

the team number of the calling thread.

```
See also
```

```
starpu_omp_get_num_teams
```

```
30.20.5.58 starpu_omp_is_initial_device()
```

Check whether the current device is the initial device or not.

```
30.20.5.59 starpu_omp_get_max_task_priority()
```

Return the maximum value that can be specified in the priority clause.

Returns

```
! 0 if called from the host device.
```

0 otherwise.

See also

```
starpu_omp_set_default_device
starpu_omp_get_default_device
```

30.20.5.60 starpu_omp_init_lock()

Initialize an opaque lock object.

See also

```
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

30.20.5.61 starpu_omp_destroy_lock()

Destroy an opaque lock object.

See also

```
starpu_omp_init_lock
starpu_omp_set_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

Lock an opaque lock object. If the lock is already locked, the function will block until it succeeds in exclusively acquiring the lock.

See also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

30.20.5.63 starpu_omp_unset_lock()

Unlock a previously locked lock object. The behaviour of this function is unspecified if it is called on an unlocked lock object.

See also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_test_lock
```

30.20.5.64 starpu_omp_test_lock()

Unblockingly attempt to lock a lock object and return whether it succeeded or not.

Returns

- ! 0 if the function succeeded in acquiring the lock.
- 0 if the lock was already locked.

See also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_unset_lock
```

30.20.5.65 starpu_omp_init_nest_lock()

Initialize an opaque lock object supporting nested locking operations.

See also

```
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

```
30.20.5.66 starpu_omp_destroy_nest_lock()
```

Destroy an opaque lock object supporting nested locking operations.

See also

```
starpu_omp_init_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

30.20.5.67 starpu_omp_set_nest_lock()

Lock an opaque lock object supporting nested locking operations. If the lock is already locked by another task, the function will block until it succeeds in exclusively acquiring the lock. If the lock is already taken by the current task, the function will increase the nested locking level of the lock object.

See also

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

30.20.5.68 starpu_omp_unset_nest_lock()

Unlock a previously locked lock object supporting nested locking operations. If the lock has been locked multiple times in nested fashion, the nested locking level is decreased and the lock remains locked. Otherwise, if the lock has only been locked once, it becomes unlocked. The behaviour of this function is unspecified if it is called on an unlocked lock object. The behaviour of this function is unspecified if it is called from a different task than the one that locked the lock object.

See also

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_test_nest_lock

30.20.5.69 starpu_omp_test_nest_lock()
```

Unblocking attempt to lock an opaque lock object supporting nested locking operations and returns whether it succeeded or not. If the lock is already locked by another task, the function will return without having acquired the lock. If the lock is already taken by the current task, the function will increase the nested locking level of the lock object.

Returns

! 0 if the function succeeded in acquiring the lock.

starpu_omp_nest_lock_t * lock)

0 if the lock was already locked.

int $starpu_omp_test_nest_lock$ (

```
See also
```

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock

30.20.5.70 starpu_omp_atomic_fallback_inline_begin()

void starpu_omp_atomic_fallback_inline_begin (
```

Implement the entry point of a fallback global atomic region. Block until it succeeds in acquiring exclusive access to the global atomic region.

See also

```
starpu omp atomic fallback inline end
```

void)

```
30.20.5.71 starpu_omp_atomic_fallback_inline_end()
```

Implement the exit point of a fallback global atomic region. Release the exclusive access to the global atomic region.

See also

```
starpu_omp_atomic_fallback_inline_begin
```

```
30.20.5.72 starpu_omp_get_wtime()
```

Return the elapsed wallclock time in seconds.

Returns

the elapsed wallclock time in seconds.

See also

```
starpu_omp_get_wtick
```

```
30.20.5.73 starpu_omp_get_wtick()
```

Return the precision of the time used by $starpu_omp_get_wtime()$.

Returns

```
the precision of the time used by starpu_omp_get_wtime().
```

See also

```
starpu_omp_get_wtime
```

30.21 MIC Extensions 353

30.20.5.74 starpu_omp_vector_annotate()

Enable setting additional vector metadata needed by the OpenMP Runtime Support.

handle is vector data handle. slice_base is the base of an array slice, expressed in number of vector elements from the array base.

See also

```
STARPU_VECTOR_GET_SLICE_BASE
```

30.21 MIC Extensions

Macros

- #define STARPU_USE_MIC
- #define STARPU_MAXMICDEVS

Typedefs

typedef void * starpu_mic_func_symbol_t

Functions

- int starpu mic register kernel (starpu mic func symbol t *symbol, const char *func name)
- starpu_mic_kernel_t starpu_mic_get_kernel (starpu_mic_func_symbol_t symbol)

30.21.1 Detailed Description

30.21.2 Macro Definition Documentation

```
30.21.2.1 STARPU_USE_MIC
```

```
#define STARPU_USE_MIC
```

Defined when StarPU has been installed with MIC support. It should be used in your code to detect the availability of MIC.

30.21.2.2 STARPU_MAXMICDEVS

```
#define STARPU_MAXMICDEVS
```

Define the maximum number of MIC devices that are supported by StarPU.

30.21.3 Typedef Documentation

```
30.21.3.1 starpu_mic_func_symbol_t
typedef void* starpu_mic_func_symbol_t
Type for MIC function symbols
```

30.21.4 Function Documentation

30.21.4.1 starpu_mic_register_kernel()

Initiate a lookup on each MIC device to find the address of the function named func_name, store it in the global array kernels and return the index in the array through symbol.

30.21.4.2 starpu_mic_get_kernel()

If successfull, return the pointer to the function defined by symbol on the device linked to the called device. This can for instance be used in a starpu_mic_func_t implementation.

30.22 Miscellaneous Helpers

Macros

- #define STARPU_MIN(a, b)
- #define STARPU_MAX(a, b)
- #define STARPU POISON PTR

Functions

- char * starpu_getenv (const char *str)
- static __starpu_inline int starpu_get_env_number (const char *str)
- static __starpu_inline int starpu_get_env_number_default (const char *str, int defval)
- static __starpu_inline float starpu_get_env_float_default (const char *str, float defval)
- void starpu_execute_on_each_worker (void(*func)(void *), void *arg, uint32_t where)
- void starpu_execute_on_each_worker_ex (void(*func)(void *), void *arg, uint32_t where, const char *name)
- void starpu_execute_on_specific_workers (void(*func)(void *), void *arg, unsigned num_workers, unsigned *workers, const char *name)
- double starpu_timing_now (void)
- int starpu_data_cpy (starpu_data_handle_t dst_handle, starpu_data_handle_t src_handle, int asynchronous, void(*callback_func)(void *), void *callback_arg)

Variables

int _starpu_silent

30.22.1 Detailed Description

30.22.2 Macro Definition Documentation

30.22.2.1 STARPU_MIN

```
#define STARPU_MIN(
a,
b)
```

Return the min of the two parameters.

30.22.2.2 STARPU_MAX

Return the max of the two parameters.

30.22.2.3 STARPU_POISON_PTR

```
#define STARPU_POISON_PTR
```

Define a value which can be used to mark pointers as invalid values.

30.22.3 Function Documentation

30.22.3.1 starpu_get_env_number()

```
static __starpu_inline int starpu_get_env_number ( {\tt const\ char}\ *\ str\ )\ \ [{\tt static}]
```

Return the integer value of the environment variable named str. Return 0 otherwise (the variable does not exist or has a non-integer value).

30.22.3.2 starpu_execute_on_each_worker()

Execute the given function <code>func</code> on a subset of workers. When calling this method, the offloaded function <code>func</code> is executed by every StarPU worker that are eligible to execute the function. The argument <code>arg</code> is passed to the offloaded function. The argument <code>where</code> specifies on which types of processing units the function should be executed. Similarly to the field <code>starpu_codelet::where</code>, it is possible to specify that the function should be executed on every CUDA device and every CPU by passing <code>STARPU_CPU|STARPU_CUDA</code>. This function blocks until <code>func</code> has been executed on every appropriate processing units, and thus may not be called from a callback function for instance.

30.22.3.3 starpu_execute_on_each_worker_ex()

```
void starpu_execute_on_each_worker_ex (
    void(*)(void *) func,
    void * arg,
    uint32_t where,
    const char * name )
```

Same as starpu_execute_on_each_worker(), except that the task name is specified in the argument name.

30.22.3.4 starpu_execute_on_specific_workers()

```
void starpu_execute_on_specific_workers (
    void(*)(void *) func,
    void * arg,
    unsigned num_workers,
    unsigned * workers,
    const char * name )
```

Call func(arg) on every worker in the workers array. num_workers indicates the number of workers in this array. This function is synchronous, but the different workers may execute the function in parallel.

30.22.3.5 starpu_timing_now()

Return the current date in micro-seconds.

30.22.3.6 starpu_data_cpy()

Copy the content of src_handle into dst_handle. The parameter asynchronous indicates whether the function should block or not. In the case of an asynchronous call, it is possible to synchronize with the termination of this operation either by the means of implicit dependencies (if enabled) or by calling starpu_task_wait_for_all(). If callback_func is not NULL, this callback function is executed after the handle has been copied, and it is given the pointer callback_arg as argument.

30.23 FxT Support

Data Structures

- struct starpu_fxt_codelet_event
- struct starpu_fxt_options

Macros

• #define STARPU_FXT_MAX_FILES

Functions

- void starpu_fxt_options_init (struct starpu_fxt_options *options)
- void starpu_fxt_generate_trace (struct starpu_fxt_options *options)
- void starpu_fxt_autostart_profiling (int autostart)
- void starpu_fxt_start_profiling (void)
- void starpu_fxt_stop_profiling (void)
- void starpu_fxt_write_data_trace (char *filename_in)
- void starpu_fxt_trace_user_event (unsigned long code)
- void starpu_fxt_trace_user_event_string (const char *s)

30.23.1 Detailed Description

30.23.2 Data Structure Documentation

30.23.2.1 struct starpu_fxt_codelet_event

Data Fields

| char | symbol[256] | |
|----------|-------------------------|--|
| int | workerid | |
| char | perfmodel_archname[256] | |
| uint32_t | hash | |
| size_t | size | |
| float | time | |

30.23 FxT Support 357

30.23.2.2 struct starpu_fxt_options

Data Fields

| unsigned | per_task_colour | |
|------------------------------------|-------------------------------|--|
| - | • | |
| unsigned | no_events | |
| unsigned | no_counter | |
| unsigned | no_bus | |
| unsigned | no_flops | |
| unsigned | ninputfiles | |
| unsigned | no_smooth | |
| unsigned | no_acquire | |
| unsigned | memory_states | |
| unsigned | internal | |
| unsigned | label_deps | |
| char * | filenames[STARPU_FXT_MAX_FILE | S] |
| char * | out_paje_path | |
| char * | distrib_time_path | |
| char * | activity_path | |
| char * | dag_path | |
| char * | tasks_path | |
| char * | data_path | |
| char * | anim_path | |
| char * | states_path | |
| char * | file_prefix | In case we are going to gather multiple traces (e.g in the case of MPI processes), we may need to prefix the name of the containers. |
| uint64_t | file_offset | In case we are going to gather multiple traces (e.g in the case of MPI processes), we may need to prefix the name of the containers. |
| int | file_rank | In case we are going to gather multiple traces (e.g in the case of MPI processes), we may need to prefix the name of the containers. |
| char | worker_names[STARPU_NMAXWOI | R OLING][256] ameters |
| struct starpu_perfmodel_arch | worker_archtypes[STARPU_NMAXV | ОРИ∕БЕК ₿≱rameters |
| int | nworkers | Output parameters |
| struct starpu_fxt_codelet_event ** | dumped_codelets | In case we want to dump the list of codelets to an external tool |
| long | dumped_codelets_count | In case we want to dump the list of codelets to an external tool |

30.23.3 Function Documentation

30.23.3.1 starpu_fxt_autostart_profiling()

Determine whether profiling should be started by starpu_init(), or only when starpu_fxt_start_profiling() is called. autostart should be 1 to do so, or 0 to prevent it.

30.23.3.2 starpu_fxt_start_profiling()

Start recording the trace. The trace is by default started from starpu_init() call, but can be paused by using starpu—
_fxt_stop_profiling(), in which case starpu_fxt_start_profiling() should be called to resume recording events.

30.23.3.3 starpu_fxt_stop_profiling()

Stop recording the trace. The trace is by default stopped when calling starpu_shutdown(). starpu_fxt_stop_\(\sigma\) profiling() can however be used to stop it earlier. starpu_fxt_start_profiling() can then be called to start recording it again, etc.

30.23.3.4 starpu_fxt_trace_user_event()

```
void starpu_fxt_trace_user_event (
          unsigned long code )
```

Add an event in the execution trace if FxT is enabled.

30.23.3.5 starpu_fxt_trace_user_event_string()

Add a string event in the execution trace if FxT is enabled.

30.24 FFT Support

Functions

- void * starpufft_malloc (size_t n)
- void starpufft_free (void *p)
- starpufft_plan starpufft_plan_dft_1d (int n, int sign, unsigned flags)
- starpufft_plan starpufft_plan_dft_2d (int n, int m, int sign, unsigned flags)
- struct starpu_task * starpufft_start (starpufft_plan p, void *in, void *out)
- struct starpu_task * starpufft_start_handle (starpufft_plan p, starpu_data_handle_t in, starpu_data_handle ← _ t out)
- int starpufft_execute (starpufft_plan p, void *in, void *out)
- int starpufft execute handle (starpufft plan p, starpu data handle t in, starpu data handle t out)
- void starpufft_cleanup (starpufft_plan p)
- void starpufft_destroy_plan (starpufft_plan p)

30.24.1 Detailed Description

30.24.2 Function Documentation

30.24.2.1 starpufft_malloc()

Allocate memory for n bytes. This is preferred over malloc(), since it allocates pinned memory, which allows overlapped transfers.

30.24 FFT Support 359

30.24.2.2 starpufft_free()

```
void * starpufft_free ( void * p )
```

Release memory previously allocated.

30.24.2.3 starpufft_plan_dft_1d()

Initialize a plan for 1D FFT of size n. sign can be STARPUFFT_FORWARD or STARPUFFT_INVERSE. flags must be 0.

30.24.2.4 starpufft_plan_dft_2d()

Initialize a plan for 2D FFT of size (n, m). sign can be STARPUFFT_FORWARD or STARPUFFT_INVERSE. flags must be 0.

30.24.2.5 starpufft_start()

Start an FFT previously planned as p, using in and out as input and output. This only submits the task and does not wait for it. The application should call $starpufft_cleanup()$ to unregister the

30.24.2.6 starpufft_start_handle()

Start an FFT previously planned as p, using data handles in and out as input and output (assumed to be vectors of elements of the expected types). This only submits the task and does not wait for it.

30.24.2.7 starpufft_execute()

Execute an FFT previously planned as p, using in and out as input and output. This submits and waits for the task.

30.24.2.8 starpufft_execute_handle()

Execute an FFT previously planned as p, using data handles in and out as input and output (assumed to be vectors of elements of the expected types). This submits and waits for the task.

30.25 MPI Support

Macros

- #define STARPU USE MPI
- #define STARPU EXECUTE ON NODE
- #define STARPU EXECUTE ON DATA
- #define STARPU_NODE_SELECTION_POLICY

Functions

- int starpu_mpi_pre_submit_hook_register (void(*f)(struct starpu_task *))
- int starpu_mpi_pre_submit_hook_unregister ()

MPI Master Slave

• #define STARPU USE MPI MASTER SLAVE

Initialisation

- int starpu_mpi_init_conf (int *argc, char ***argv, int initialize_mpi, MPI_Comm comm, struct starpu_conf *conf)
- int starpu_mpi_init_comm (int *argc, char ***argv, int initialize_mpi, MPI_Comm comm)
- int starpu mpi init (int *argc, char ***argv, int initialize mpi)
- int starpu_mpi_initialize (void)
- int starpu_mpi_initialize_extended (int *rank, int *world_size)
- int starpu_mpi_shutdown (void)
- void starpu mpi comm amounts retrieve (size t *comm amounts)
- int starpu mpi comm size (MPI Comm comm, int *size)
- int starpu_mpi_comm_rank (MPI_Comm comm, int *rank)
- · int starpu mpi world rank (void)
- int starpu_mpi_world_size (void)
- int starpu_mpi_comm_get_attr (MPI_Comm comm, int keyval, void *attribute_val, int *flag)
- int starpu_mpi_get_communication_tag (void)
- void starpu_mpi_set_communication_tag (int tag)
- #define STARPU MPI TAG UB

Communication

- typedef void * starpu_mpi_req
- typedef int64 t starpu mpi tag t
- typedef void(* starpu_mpi_datatype_allocate_func_t) (starpu_data_handle_t, MPI_Datatype *)
- typedef void(* starpu mpi datatype free func t) (MPI Datatype *)
- int starpu_mpi_isend (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm)

int starpu_mpi_isend_prio (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi
_tag_t data_tag, int prio, MPI_Comm comm)

- int starpu_mpi_irecv (starpu_data_handle_t data_handle, starpu_mpi_req *req, int source, starpu_mpi_
 tag_t data_tag, MPI_Comm comm)
- int starpu_mpi_send (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm)
- int starpu_mpi_send_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, int prio, MPI Comm comm)
- int starpu_mpi_recv (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI_Comm comm, MPI_Status *status)
- int starpu_mpi_isend_detached (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_isend_detached_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data
 —tag, int prio, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_irecv_detached (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_irecv_detached_sequential_consistency (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg, int sequential_consistency)
- int starpu_mpi_issend (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi_tag
 _t data_tag, MPI_Comm comm)
- int starpu_mpi_issend_prio (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi
 _tag_t data_tag, int prio, MPI_Comm comm)
- int starpu_mpi_issend_detached (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_issend_detached_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data
 _tag, int prio, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_wait (starpu_mpi_req *req, MPI_Status *status)
- int starpu_mpi_test (starpu_mpi_req *req, int *flag, MPI_Status *status)
- int starpu_mpi_barrier (MPI_Comm comm)
- int starpu_mpi_wait_for_all (MPI_Comm comm)
- int starpu_mpi_isend_detached_unlock_tag (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag
 —t data_tag, MPI_Comm comm, starpu_tag_t tag)
- int starpu_mpi_isend_detached_unlock_tag_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi
 _tag_t data_tag, int prio, MPI_Comm comm, starpu_tag_t tag)
- int starpu_mpi_irecv_detached_unlock_tag (starpu_data_handle_t data_handle, int source, starpu_mpi_
 tag t data tag, MPI Comm comm, starpu tag t tag)
- int starpu_mpi_isend_array_detached_unlock_tag (unsigned array_size, starpu_data_handle_t *data_←
 handle, int *dest, starpu_mpi_tag_t *data_tag, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_isend_array_detached_unlock_tag_prio (unsigned array_size, starpu_data_handle_t *data ← _handle, int *dest, starpu_mpi_tag_t *data_tag, int *prio, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_irecv_array_detached_unlock_tag (unsigned array_size, starpu_data_handle_t *data_←
 handle, int *source, starpu_mpi_tag_t *data_tag, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_datatype_register (starpu_data_handle_t handle, starpu_mpi_datatype_allocate_func_
 t allocate_datatype_func, starpu_mpi_datatype_free_func_t free_datatype_func)
- int starpu_mpi_datatype_unregister (starpu_data_handle_t handle)

Communication Cache

- int starpu_mpi_cache_is_enabled ()
- int starpu_mpi_cache_set (int enabled)
- void starpu_mpi_cache_flush (MPI_Comm comm, starpu_data_handle_t data_handle)
- void starpu_mpi_cache_flush_all_data (MPI Comm comm)
- int starpu mpi cached receive (starpu data handle t data handle)
- int starpu_mpi_cached_send (starpu_data_handle_t data_handle, int dest)

MPI Insert Task

- void starpu_mpi_data_register_comm (starpu_data_handle_t data_handle, starpu_mpi_tag_t data_tag, int rank, MPI Comm comm)
- void starpu_mpi_data_set_tag (starpu_data_handle_t handle, starpu_mpi_tag_t data_tag)
- void starpu_mpi_data_set_rank_comm (starpu_data_handle_t handle, int rank, MPI_Comm comm)
- int starpu_mpi_data_get_rank (starpu_data_handle_t handle)
- starpu_mpi_tag_t starpu_mpi_data_get_tag (starpu_data_handle_t handle)
- int starpu_mpi_task_insert (MPI_Comm comm, struct starpu_codelet *codelet,...)
- int starpu mpi insert task (MPI Comm comm, struct starpu codelet *codelet,...)
- struct starpu task * starpu mpi task build (MPI Comm comm, struct starpu codelet *codelet,...)
- int starpu_mpi_task_post_build (MPI_Comm comm, struct starpu_codelet *codelet,...)
- void starpu_mpi_get_data_on_node (MPI_Comm comm, starpu_data_handle_t data_handle, int node)
- void starpu_mpi_get_data_on_node_detached (MPI_Comm comm, starpu_data_handle_t data_handle, int node, void(*callback)(void *), void *arg)
- void starpu_mpi_get_data_on_all_nodes_detached (MPI_Comm comm, starpu_data_handle_t data_handle)
- · void starpu mpi data migrate (MPI Comm comm, starpu data handle t handle, int new rank)
- #define STARPU_MPI_PER_NODE
- #define starpu_mpi_data_register(data_handle, data_tag, rank)
- · #define starpu data set tag
- #define starpu_mpi_data_set_rank(handle, rank)
- #define starpu data set rank
- · #define starpu data get rank
- · #define starpu data get tag

Node Selection Policy

- typedef int(* starpu_mpi_select_node_policy_func_t) (int me, int nb_nodes, struct starpu_data_descr *descr, int nb_data)
- int starpu_mpi_node_selection_register_policy (starpu_mpi_select_node_policy_func_t policy_func)
- int starpu mpi node selection unregister policy (int policy)
- int starpu mpi node selection get current policy ()
- int starpu_mpi_node_selection_set_current_policy (int policy)
- #define STARPU MPI NODE SELECTION CURRENT POLICY
- #define STARPU MPI NODE SELECTION MOST R DATA

Collective Operations

- void starpu_mpi_redux_data (MPI_Comm comm, starpu_data_handle_t data_handle)
- · void starpu mpi redux data prio (MPI Comm comm, starpu data handle t data handle, int prio)
- int starpu_mpi_scatter_detached (starpu_data_handle_t *data_handles, int count, int root, MPI_Comm comm, void(*scallback)(void *), void *sarg, void(*rcallback)(void *), void *rarg)
- int starpu_mpi_gather_detached (starpu_data_handle_t *data_handles, int count, int root, MPI_Comm comm, void(*scallback)(void *), void *sarg, void(*rcallback)(void *), void *rarg)

30.25.1 Detailed Description

30.25.2 Macro Definition Documentation

30.25.2.1 STARPU_USE_MPI

#define STARPU USE MPI

Defined when StarPU has been installed with MPI support. It should be used in your code to detect the availability of MPI.

30.25.2.2 STARPU_USE_MPI_MASTER_SLAVE

```
#define STARPU_USE_MPI_MASTER_SLAVE
```

Defined when StarPU has been installed with MPI Master Slave support. It should be used in your code to detect the availability of MPI Master Slave.

30.25.2.3 STARPU_EXECUTE_ON_NODE

```
#define STARPU_EXECUTE_ON_NODE
```

Used when calling starpu_mpi_task_insert(), must be followed by a integer value which specified the node on which to execute the codelet.

30.25.2.4 STARPU EXECUTE ON DATA

```
#define STARPU_EXECUTE_ON_DATA
```

Used when calling starpu_mpi_task_insert(), must be followed by a data handle to specify that the node owning the given data will execute the codelet.

30.25.2.5 STARPU_NODE_SELECTION_POLICY

```
#define STARPU_NODE_SELECTION_POLICY
```

Used when calling starpu_mpi_task_insert(), must be followed by a identifier to a node selection policy. This is needed when several nodes own data in STARPU_W mode.

30.25.2.6 STARPU_MPI_TAG_UB

```
#define STARPU_MPI_TAG_UB
```

When given to the function starpu_mpi_comm_get_attr(), retrieve the value for the upper bound for tag value.

30.25.2.7 STARPU_MPI_PER_NODE

```
#define STARPU_MPI_PER_NODE
```

Can be used as rank when calling starpu_mpi_data_register() and alike, to specify that the data is per-node: each node will have its own value. Tasks writing to such data will be replicated on all nodes (and all parameters then have to be per-node). Tasks not writing to such data will just take the node-local value without any MPI communication.

30.25.2.8 starpu_mpi_data_register

Register to MPI a StarPU data handle with the given tag, rank and the MPI communicator MPI_COMM_WORLD. It also automatically clears the MPI communication cache when unregistering the data.

```
30.25.2.9 starpu_data_set_tag
```

```
#define starpu_data_set_tag
```

Symbol kept for backward compatibility. Call function starpu_mpi_data_set_tag()

30.25.2.10 starpu_mpi_data_set_rank

Register to MPI a StarPU data handle with the given rank and the MPI communicator MPI_COMM_WORLD. No tag will be defined. It also automatically clears the MPI communication cache when unregistering the data.

```
30.25.2.11 starpu_data_set_rank

#define starpu_data_set_rank
Symbol kept for backward compatibility. Call function starpu_mpi_data_set_rank()

30.25.2.12 starpu_data_get_rank

#define starpu_data_get_rank
Symbol kept for backward compatibility. Call function starpu_mpi_data_get_rank()

30.25.2.13 starpu_data_get_tag

#define starpu_data_get_tag

#define starpu_data_get_tag

Symbol kept for backward compatibility. Call function starpu_mpi_data_get_tag()
```

30.25.3 Typedef Documentation

```
30.25.3.1 starpu_mpi_req

typedef void* starpu_mpi_req

Opaque type for communication request

30.25.3.2 starpu_mpi_tag_t

typedef int64_t starpu_mpi_tag_t

Define the type which can be used to set communication tag when exchanging data.
```

30.25.4 Function Documentation

30.25.4.1 starpu_mpi_init_conf()

```
int starpu_mpi_init_conf (
    int * argc,
    char *** argv,
    int initialize_mpi,
    MPI_Comm comm,
    struct starpu_conf * conf )
```

Initialize the StarPU library with the given <code>conf</code>, and initialize the StarPU-MPI library with the given MPI communicator <code>comm.initialize_mpi</code> indicates if MPI should be initialized or not by StarPU. StarPU-MPI takes the opportunity to modify <code>conf</code> to either reserve a core for its MPI thread (by default), or execute MPI calls on the CPU driver 0 between tasks.

30.25.4.2 starpu_mpi_init_comm()

Same as starpu_mpi_init_conf(), except that this does not initialize the StarPU library. The caller thus has to call starpu_init() before this.

30.25.4.3 starpu_mpi_init()

Call starpu_mpi_init_comm() with the MPI communicator MPI_COMM_WORLD.

30.25.4.4 starpu_mpi_initialize()

Deprecated This function has been made deprecated. One should use instead the function starpu_mpi_init(). This function does not call MPI_Init(), it should be called beforehand.

30.25.4.5 starpu_mpi_initialize_extended()

Deprecated This function has been made deprecated. One should use instead the function starpu_mpi_init(). MPI will be initialized by starpumpi by calling MPI_Init_Thread(argc, argv, MPI_THREAD ← _SERIALIZED, ...).

30.25.4.6 starpu_mpi_shutdown()

Clean the starpumpi library. This must be called after calling any starpu_mpi functions and before the call to starpu_shutdown(), if any. MPI_Finalize() will be called if StarPU-MPI has been initialized by starpu_mpi_cinit().

30.25.4.7 starpu_mpi_comm_amounts_retrieve()

Retrieve the current amount of communications from the current node in the array comm_amounts which must have a size greater or equal to the world size. Communications statistics must be enabled (see STARPU_COM
M STATS).

30.25.4.8 starpu_mpi_comm_size()

Return in size the size of the communicator comm

30.25.4.9 starpu_mpi_comm_rank()

Return in rank the rank of the calling process in the communicator comm

```
30.25.4.10 starpu_mpi_world_rank()
```

Return the rank of the calling process in the communicator MPI_COMM_WORLD

30.25.4.11 starpu_mpi_world_size()

Return the size of the communicator MPI_COMM_WORLD

30.25.4.12 starpu_mpi_comm_get_attr()

Retrieve an attribute value by key, similarly to the MPI function MPI_comm_get_attr(), except that the value is a pointer to int64_t instead of int. If an attribute is attached on comm to keyval, then the call returns flag equal to 1, and the attribute value in attribute_val. Otherwise, flag is set to $\0$.

30.25.4.13 starpu_mpi_isend()

Post a standard-mode, non blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm. After the call, the pointer to the request req can be used to test or to wait for the completion of the communication.

30.25.4.14 starpu_mpi_isend_prio()

Similar to starpu mpi isend(), but take a priority prio.

30.25.4.15 starpu_mpi_irecv()

Post a nonblocking receive in data_handle from the node source using the message tag data_tag within the communicator comm. After the call, the pointer to the request req can be used to test or to wait for the completion of the communication.

30.25.4.16 starpu_mpi_send()

Perform a standard-mode, blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm.

30.25.4.17 starpu_mpi_send_prio()

Similar to starpu_mpi_send(), but take a priority prio.

30.25.4.18 starpu_mpi_recv()

Perform a standard-mode, blocking receive in data_handle from the node source using the message tag data_tag within the communicator comm.

30.25.4.19 starpu_mpi_isend_detached()

Post a standard-mode, non blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm. On completion, the callback function is called with the argument arg. Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

30.25.4.20 starpu_mpi_isend_detached_prio()

Similar to starpu_mpi_isend_detached, but take a priority prio.

30.25.4.21 starpu_mpi_irecv_detached()

Post a nonblocking receive in data_handle from the node source using the message tag data_tag within the communicator comm. On completion, the callback function is called with the argument arg. Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

30.25.4.22 starpu_mpi_irecv_detached_sequential_consistency()

Post a nonblocking receive in data_handle from the node source using the message tag data_tag within the communicator comm. On completion, the callback function is called with the argument arg. The parameter sequential_consistency allows to enable or disable the sequential consistency for data handle (sequential consistency will be enabled or disabled based on the value of the parameter sequential_consistency and the value of the sequential consistency defined for data_handle). Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

30.25.4.23 starpu_mpi_issend()

Perform a synchronous-mode, non-blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm.

30.25.4.24 starpu_mpi_issend_prio()

Similar to starpu mpi issend(), but take a priority prio.

30.25.4.25 starpu_mpi_issend_detached()

```
starpu_mpi_tag_t data_tag,
MPI_Comm comm,
void(*)(void *) callback,
void * arg )
```

Perform a synchronous-mode, non-blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm. On completion, the callback function is called with the argument arg. Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

30.25.4.26 starpu_mpi_issend_detached_prio()

Similar to starpu_mpi_issend_detached(), but take a priority prio.

30.25.4.27 starpu_mpi_wait()

Return when the operation identified by request req is complete.

30.25.4.28 starpu_mpi_test()

If the operation identified by req is complete, set flag to 1. The status object is set to contain information on the completed operation.

30.25.4.29 starpu_mpi_barrier()

Block the caller until all group members of the communicator comm have called it.

30.25.4.30 starpu_mpi_wait_for_all()

Wait until all StarPU tasks and communications for the given communicator are completed.

30.25.4.31 starpu_mpi_isend_detached_unlock_tag()

Post a standard-mode, non blocking send of data_handle to the node dest using the message tag data_tag within the communicator comm. On completion, tag is unlocked.

30.25.4.32 starpu_mpi_isend_detached_unlock_tag_prio()

Similar to starpu_mpi_isend_detached_unlock_tag(), but take a priority prio.

30.25.4.33 starpu_mpi_irecv_detached_unlock_tag()

Post a nonblocking receive in data_handle from the node source using the message tag data_tag within the communicator comm. On completion, tag is unlocked.

30.25.4.34 starpu_mpi_isend_array_detached_unlock_tag()

Post array_size standard-mode, non blocking send. Each post sends the n-th data of the array data_handle to the n-th node of the array dest using the n-th message tag of the array data_tag within the n-th communicator of the array comm. On completion of the all the requests, tag is unlocked.

30.25.4.35 starpu_mpi_isend_array_detached_unlock_tag_prio()

Similar to starpu mpi isend array detached unlock tag(), but take a priority prio.

30.25.4.36 starpu_mpi_irecv_array_detached_unlock_tag()

Post array_size nonblocking receive. Each post receives in the n-th data of the array data_handle from the n-th node of the array source using the n-th message tag of the array data_tag within the n-th communicator of the array comm. On completion of the all the requests, tag is unlocked.

30.25.4.37 starpu_mpi_datatype_register()

Register functions to create and free a MPI datatype for the given handle. It is important that the function is called before any communication can take place for a data with the given handle. See Exchanging User Defined Data Interface for an example.

30.25.4.38 starpu_mpi_datatype_unregister()

Unregister the MPI datatype functions stored for the interface of the given handle.

30.25.4.39 starpu_mpi_cache_is_enabled()

```
int starpu_mpi_cache_is_enabled ( )
```

Return 1 if the communication cache is enabled, 0 otherwise

30.25.4.40 starpu_mpi_cache_set()

If enabled is 1, enable the communication cache. Otherwise, clean the cache if it was enabled and disable it.

30.25.4.41 starpu_mpi_cache_flush()

Clear the send and receive communication cache for the data <code>data_handle</code> and invalidate the value. The function has to be called at the same point of task graph submission by all the MPI nodes on which the handle was registered. The function does nothing if the cache mechanism is disabled (see <code>STARPU_MPI_CACHE</code>).

30.25.4.42 starpu_mpi_cache_flush_all_data()

Clear the send and receive communication cache for all data and invalidate their values. The function has to be called at the same point of task graph submission by all the MPI nodes. The function does nothing if the cache mechanism is disabled (see STARPU_MPI_CACHE).

30.25.4.43 starpu_mpi_cached_receive()

Test whether data_handle is cached for reception, i.e. the value was previously received from the owner node, and not flushed since then.

30.25.4.44 starpu_mpi_cached_send()

Test whether data_handle is cached for emission to node dest, i.e. the value was previously sent to dest, and not flushed since then.

30.25.4.45 starpu_mpi_data_register_comm()

Register to MPI a StarPU data handle with the given tag, rank and MPI communicator. It also automatically clears the MPI communication cache when unregistering the data.

30.25.4.46 starpu_mpi_data_set_tag()

Register to MPI a StarPU data handle with the given tag. No rank will be defined. It also automatically clears the MPI communication cache when unregistering the data.

30.25.4.47 starpu_mpi_data_set_rank_comm()

Register to MPI a StarPU data handle with the given rank and given communicator. No tag will be defined. It also automatically clears the MPI communication cache when unregistering the data.

```
30.25.4.48 starpu_mpi_data_get_rank()
```

Return the rank of the given data.

30.25.4.49 starpu_mpi_data_get_tag()

Return the tag of the given data.

30.25.4.50 starpu_mpi_task_insert()

Create and submit a task corresponding to codelet with the following arguments. The argument list must be zero-terminated. The arguments following the codelet are the same types as for the function starpu_task_insert(). Access modes for data can also be set with STARPU_SSEND to specify the data has to be sent using a synchronous and non-blocking mode (see starpu_mpi_issend()). The extra argument STARPU_EXECUTE_ON_NODE followed by an integer allows to specify the MPI node to execute the codelet. It is also possible to specify that the node owning a specific data will execute the codelet, by using STARPU_EXECUTE_ON_DATA followed by a data handle. The internal algorithm is as follows:

- 1. Find out which MPI node is going to execute the codelet.
 - If there is only one node owning data in STARPU_W mode, it will be selected;
 - If there is several nodes owning data in STARPU_W mode, a node will be selected according to a given node selection policy (see STARPU_NODE_SELECTION_POLICY or starpu_mpi_node_selection_← set_current_policy())
 - The argument STARPU EXECUTE ON NODE followed by an integer can be used to specify the node;

• The argument STARPU_EXECUTE_ON_DATA followed by a data handle can be used to specify that the node owing the given data will execute the codelet.

- 2. Send and receive data as requested. Nodes owning data which need to be read by the task are sending them to the MPI node which will execute it. The latter receives them.
- 3. Execute the codelet. This is done by the MPI node selected in the 1st step of the algorithm.
- 4. If several MPI nodes own data to be written to, send written data back to their owners.

The algorithm also includes a communication cache mechanism that allows not to send data twice to the same MPI node, unless the data has been modified. The cache can be disabled (see STARPU MPI CACHE).

30.25.4.51 starpu_mpi_insert_task()

Call starpu mpi task insert(). Symbol kept for backward compatibility.

30.25.4.52 starpu_mpi_task_build()

Create a task corresponding to <code>codelet</code> with the following given arguments. The argument list must be zero-terminated. The function performs the first two steps of the function <code>starpu_mpi_task_insert()</code>, i.e. submitting the MPI communications needed before the execution of the task, and the creation of the task on one node. Only the MPI node selected in the first step of the algorithm will return a valid task structure which can then be submitted, others will return <code>NULL</code>. The function <code>starpu_mpi_task_post_build()</code> MUST be called after that on all nodes, and after the submission of the task on the node which creates it, with the SAME list of arguments.

30.25.4.53 starpu_mpi_task_post_build()

MUST be called after a call to starpu_mpi_task_build(), with the SAME list of arguments. Perform the fourth – last – step of the algorithm described in starpu_mpi_task_insert().

30.25.4.54 starpu_mpi_get_data_on_node()

Transfer data data_handle to MPI node node, sending it from its owner if needed. At least the target node and the owner have to call the function.

30.25.4.55 starpu_mpi_get_data_on_node_detached()

Transfer data data_handle to MPI node node, sending it from its owner if needed. At least the target node and the owner have to call the function. On reception, the callback function is called with the argument arg.

30.25.4.56 starpu_mpi_get_data_on_all_nodes_detached()

Transfer data data_handle to all MPI nodes, sending it from its owner if needed. All nodes have to call the function.

30.25.4.57 starpu_mpi_data_migrate()

Submit migration of the data onto the new_rank MPI node. This means both submitting the transfer of the data to node new_rank if it hasn't been submitted already, and setting the home node of the data to the new node. Further data transfers submitted by starpu_mpi_task_insert() will be done from that new node. This function thus needs to be called on all nodes which have registered the data at the same point of tasks submissions. This also flushes the cache for this data to avoid incoherencies.

30.25.4.58 starpu_mpi_node_selection_register_policy()

Register a new policy which can then be used when there is several nodes owning data in STARPU_W mode. Here an example of function defining a node selection policy. The codelet will be executed on the node owing the first data with a size bigger than 1M, or on the node 0 if no data fits the given size.

30.25.4.59 starpu_mpi_node_selection_unregister_policy()

Unregister a previously registered policy.

30.25.4.60 starpu_mpi_node_selection_get_current_policy()

```
int starpu_mpi_node_selection_get_current_policy ( )
```

Return the current policy used to select the node which will execute the codelet

30.25.4.61 starpu_mpi_node_selection_set_current_policy()

30.25.4.62 starpu_mpi_redux_data()

Perform a reduction on the given data handle. All nodes send the data to its owner node which will perform a reduction.

30.25.4.63 starpu_mpi_redux_data_prio()

Similar to starpu_mpi_redux_data, but take a priority prio.

30.25.4.64 starpu_mpi_scatter_detached()

```
int starpu_mpi_scatter_detached (
    starpu_data_handle_t * data_handles,
    int count,
    int root,
    MPI_Comm comm,
    void(*)(void *) scallback,
    void * sarg,
    void(*)(void *) rcallback,
    void * rarg)
```

Scatter data among processes of the communicator based on the ownership of the data. For each data of the array $data_handles$, the process root sends the data to the process owning this data. Processes receiving data must have valid data handles to receive them. On completion of the collective communication, the scallback function is called with the argument sarg on the process root, the reallback function is called with the argument rarg on any other process.

30.25.4.65 starpu_mpi_gather_detached()

Gather data from the different processes of the communicator onto the process root. Each process owning data handle in the array data_handles will send them to the process root. The process root must have valid data handles to receive the data. On completion of the collective communication, the reallback function is called with the argument rarg on the process root, the scallback function is called with the argument sarg on any other process.

30.26 Task Bundles

Typedefs

typedef struct _starpu_task_bundle * starpu_task_bundle_t

Functions

- void starpu task bundle create (starpu task bundle t *bundle)
- int starpu task bundle insert (starpu task bundle t bundle, struct starpu task *task)
- int starpu task bundle remove (starpu task bundle t bundle, struct starpu task *task)
- void starpu_task_bundle_close (starpu_task_bundle_t bundle)
- double starpu_task_bundle_expected_length (starpu_task_bundle_t bundle, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- double starpu_task_bundle_expected_data_transfer_time (starpu_task_bundle_t bundle, unsigned memory_node)
- double starpu_task_bundle_expected_energy (starpu_task_bundle_t bundle, struct starpu_perfmodel_arch *arch, unsigned nimpl)

30.26.1 Detailed Description

30.26.2 Typedef Documentation

```
30.26.2.1 starpu_task_bundle_t
typedef struct _starpu_task_bundle* starpu_task_bundle_t
```

Opaque structure describing a list of tasks that should be scheduled on the same worker whenever it's possible. It must be considered as a hint given to the scheduler as there is no guarantee that they will be executed on the same worker.

30.26.3 Function Documentation

Factory function creating and initializing bundle, when the call returns, memory needed is allocated and bundle is ready to use.

30.26.3.2 starpu_task_bundle_insert()

Insert task in bundle. Until task is removed from bundle its expected length and data transfer time will be considered along those of the other tasks of bundle. This function must not be called if bundle is already closed and/or task is already submitted. On success, it returns 0. There are two cases of error: if bundle is already closed it returns -EPERM, if task was already submitted it returns -EINVAL.

30.26.3.3 starpu_task_bundle_remove()

30.27 Task Lists 377

Remove task from bundle. Of course task must have been previously inserted in bundle. This function must not be called if bundle is already closed and/or task is already submitted. Doing so would result in undefined behaviour. On success, it returns 0. If bundle is already closed it returns -ENOENT.

30.26.3.4 starpu_task_bundle_close()

Inform the runtime that the user will not modify <code>bundle</code> anymore, it means no more inserting or removing task. Thus the runtime can destroy it when possible.

30.26.3.5 starpu_task_bundle_expected_length()

Return the expected duration of bundle in micro-seconds.

30.26.3.6 starpu_task_bundle_expected_data_transfer_time()

Return the time (in micro-seconds) expected to transfer all data used within bundle.

30.26.3.7 starpu_task_bundle_expected_energy()

Return the expected energy consumption of bundle in J.

30.27 Task Lists

Data Structures

struct starpu_task_list

Functions

- void starpu_task_list_init (struct starpu_task_list *list)
- void starpu_task_list_push_front (struct starpu_task_list *list, struct starpu_task *task)
- void starpu_task_list_push_back (struct starpu_task_list *list, struct starpu_task *task)
- struct starpu_task * starpu_task_list_front (const struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_back (const struct starpu_task_list *list)
- int starpu_task_list_empty (const struct starpu_task_list *list)
- void starpu_task_list_erase (struct starpu_task_list *list, struct starpu_task *task)
- struct starpu_task * starpu_task_list_pop_front (struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_pop_back (struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_begin (const struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_end (const struct starpu_task_list *list STARPU_ATTRIBUTE_UNU

 SED)
- struct starpu_task * starpu_task_list_next (const struct starpu_task *task)
- int starpu_task_list_ismember (const struct starpu_task_list *list, const struct starpu_task *look)
- void starpu_task_list_move (struct starpu_task_list *ldst, struct starpu_task_list *lsrc)

30.27.1 Detailed Description

30.27.2 Data Structure Documentation

30.27.2.1 struct starpu_task_list

Store a double-chained list of tasks

Data Fields

| struct starpu_task * | head | head of the list |
|----------------------|------|------------------|
| struct starpu_task * | tail | tail of the list |

30.27.3 Function Documentation

```
30.27.3.1 starpu_task_list_init()
void starpu_task_list_init (
              struct starpu_task_list * list )
Initialize a list structure
30.27.3.2 starpu_task_list_push_front()
void starpu_task_list_push_front (
              struct starpu_task_list * list,
              struct starpu_task * task )
Push task at the front of list
30.27.3.3 starpu_task_list_push_back()
void starpu_task_list_push_back (
              struct starpu_task_list * list,
              struct starpu_task * task )
Push task at the back of list
30.27.3.4 starpu_task_list_front()
struct starpu_task* starpu_task_list_front (
              const struct starpu_task_list * list )
Get the front of list (without removing it)
30.27.3.5 starpu_task_list_back()
struct starpu_task* starpu_task_list_back (
              const struct starpu_task_list * list )
Get the back of list (without removing it)
30.27.3.6 starpu_task_list_empty()
int starpu_task_list_empty (
              const struct starpu_task_list * list )
Test if list is empty
```

30.28 Parallel Tasks 379

```
30.27.3.7 starpu_task_list_erase()
void starpu_task_list_erase (
              struct starpu_task_list * list,
              struct starpu_task * task )
Remove task from list
30.27.3.8 starpu_task_list_pop_front()
struct starpu_task* starpu_task_list_pop_front (
              struct starpu_task_list * list )
Remove the element at the front of list
30.27.3.9 starpu_task_list_pop_back()
struct starpu_task* starpu_task_list_pop_back (
              struct starpu_task_list * list )
Remove the element at the back of list
30.27.3.10 starpu_task_list_begin()
struct starpu_task* starpu_task_list_begin (
              const struct starpu_task_list * list )
Get the first task of list.
30.27.3.11 starpu_task_list_end()
struct starpu_task* starpu_task_list_end (
              const struct starpu_task_list *list STARPU_ATTRIBUTE_UNUSED )
Get the end of list.
30.27.3.12 starpu_task_list_next()
struct starpu_task* starpu_task_list_next (
              const struct starpu_task * task )
Get the next task of list. This is not erase-safe.
30.27.3.13 starpu_task_list_ismember()
\verb|int starpu_task_list_ismember (|\\
              const struct starpu_task_list * list,
              const struct starpu_task * look )
Test whether the given task look is contained in the list.
```

30.28 Parallel Tasks

Functions

- unsigned starpu_combined_worker_get_count (void)
- unsigned starpu_worker_is_combined_worker (int id)
- int starpu_combined_worker_get_id (void)
- int starpu_combined_worker_get_size (void)
- int starpu_combined_worker_get_rank (void)
- int starpu_combined_worker_assign_workerid (int nworkers, int workerid_array[])
- int starpu combined worker get description (int workerid, int *worker size, int **combined workerid)
- int starpu_combined_worker_can_execute_task (unsigned workerid, struct starpu_task *task, unsigned nimpl)
- void starpu_parallel_task_barrier_init (struct starpu_task *task, int workerid)
- void starpu_parallel_task_barrier_init_n (struct starpu_task *task, int worker_size)

30.28.1 Detailed Description

30.28.2 Function Documentation

30.28.2.1 starpu_combined_worker_get_count()

Return the number of different combined workers.

30.28.2.2 starpu_combined_worker_get_id()

Return the identifier of the current combined worker.

30.28.2.3 starpu_combined_worker_get_size()

Return the size of the current combined worker, i.e. the total number of CPUS running the same task in the case of STARPU_SPMD parallel tasks, or the total number of threads that the task is allowed to start in the case of STARPU FORKJOIN parallel tasks.

30.28.2.4 starpu_combined_worker_get_rank()

Return the rank of the current thread within the combined worker. Can only be used in STARPU_FORKJOIN parallel tasks, to know which part of the task to work on.

30.28.2.5 starpu_combined_worker_assign_workerid()

```
int starpu_combined_worker_assign_workerid (
          int nworkers,
          int workerid_array[])
```

Register a new combined worker and get its identifier

30.28.2.6 starpu_combined_worker_get_description()

Get the description of a combined worker

30.28.2.7 starpu_combined_worker_can_execute_task()

Variant of starpu worker can execute task() compatible with combined workers

30.28.2.8 starpu_parallel_task_barrier_init()

30.29 Running Drivers 381

Initialise the barrier for the parallel task, and dispatch the task between the different workers of the given combined worker.

30.28.2.9 starpu_parallel_task_barrier_init_n()

Initialise the barrier for the parallel task, to be pushed to $worker_size$ workers (without having to explicit a given combined worker).

30.29 Running Drivers

Data Structures

- · struct starpu_driver
- union starpu_driver.id

Functions

- int starpu_driver_run (struct starpu_driver *d)
- void starpu_drivers_request_termination (void)
- int starpu_driver_init (struct starpu_driver *d)
- int starpu_driver_run_once (struct starpu_driver *d)
- int starpu_driver_deinit (struct starpu_driver *d)

30.29.1 Detailed Description

30.29.2 Data Structure Documentation

30.29.2.1 struct starpu_driver

structure for a driver

Data Fields

| enum starpu_worker_archtype | | Type of the driver. Only STARPU_CPU_WORKER, STARPU_CUDA_WORKER and STARPU_OPENCL_WORKER are currently supported. |
|-----------------------------|----|--|
| union starpu_driver | id | Identifier of the driver. |

30.29.2.2 union starpu_driver.id

Identifier of the driver.

Data Fields

| unsigned | cpu_id | |
|--------------|-----------|--|
| unsigned | cuda_id | |
| cl_device_id | opencl_id | |

30.29.3 Function Documentation

30.29.3.1 starpu_driver_run()

Initialize the given driver, run it until it receives a request to terminate, deinitialize it and return 0 on success. Return −EINVAL if starpu_driver::type is not a valid StarPU device type (STARPU_CPU_WORKER, STARPU_CUDA_← WORKER or STARPU OPENCL WORKER).

This is the same as using the following functions: calling starpu_driver_init(), then calling starpu_driver_run_once() in a loop, and finally starpu_driver_deinit().

30.29.3.2 starpu_drivers_request_termination()

Notify all running drivers that they should terminate.

30.29.3.3 starpu_driver_init()

Initialize the given driver. Return 0 on success, -EINVAL if starpu_driver::type is not a valid starpu_worker_← archtype.

30.29.3.4 starpu_driver_run_once()

```
int starpu_driver_run_once (  struct \ starpu\_driver * d )
```

Run the driver once, then return 0 on success, -EINVAL if starpu_driver::type is not a valid starpu_worker_← archtype.

30.29.3.5 starpu_driver_deinit()

Deinitialize the given driver. Return 0 on success, <code>-EINVAL</code> if <code>starpu_driver::type</code> is not a valid <code>starpu_worker_control</code> archtype.

30.30 Expert Mode

Functions

- void starpu_wake_all_blocked_workers (void)
- int starpu_progression_hook_register (unsigned(*func)(void *arg), void *arg)
- void starpu_progression_hook_deregister (int hook_id)
- int starpu_idle_hook_register (unsigned(*func)(void *arg), void *arg)
- void starpu_idle_hook_deregister (int hook_id)

30.30.1 Detailed Description

30.30.2 Function Documentation

30.30.2.1 starpu_wake_all_blocked_workers()

Wake all the workers, so they can inspect data requests and task submissions again.

30.30.2.2 starpu_progression_hook_register()

```
int starpu_progression_hook_register (
          unsigned(*)(void *arg) func,
          void * arg )
```

Register a progression hook, to be called when workers are idle.

30.30.2.3 starpu progression hook deregister()

Unregister a given progression hook.

30.31 Scheduling Contexts

StarPU permits on one hand grouping workers in combined workers in order to execute a parallel task and on the other hand grouping tasks in bundles that will be executed by a single specified worker. In contrast when we group workers in scheduling contexts we submit starpu tasks to them and we schedule them with the policy assigned to the context. Scheduling contexts can be created, deleted and modified dynamically.

Scheduling Contexts Basic API

- void(*)(unsigned) starpu_sched_ctx_get_sched_policy_init (unsigned sched_ctx_id)
- unsigned starpu sched ctx create (int *workerids ctx, int nworkers ctx, const char *sched ctx name,...)
- unsigned starpu_sched_ctx_create_inside_interval (const char *policy_name, const char *sched_ctx_name, int min_ncpus, int max_ncpus, int max_ncpus, unsigned allow_overlap)
- void starpu_sched_ctx_register_close_callback (unsigned sched_ctx_id, void(*close_callback)(unsigned sched_ctx_id, void *args), void *args)
- void starpu_sched_ctx_add_workers (int *workerids_ctx, unsigned nworkers_ctx, unsigned sched_ctx_id)
- void starpu_sched_ctx_remove_workers (int *workerids_ctx, unsigned nworkers_ctx, unsigned sched_ctx
 —id)
- void starpu sched ctx display workers (unsigned sched ctx id, FILE *f)
- void starpu_sched_ctx_delete (unsigned sched_ctx_id)
- void starpu_sched_ctx_set_inheritor (unsigned sched_ctx_id, unsigned inheritor)
- unsigned starpu sched ctx get inheritor (unsigned sched ctx id)
- unsigned starpu sched ctx get hierarchy level (unsigned sched ctx id)
- void starpu_sched_ctx_set_context (unsigned *sched_ctx_id)
- unsigned starpu_sched_ctx_get_context (void)
- void starpu_sched_ctx_stop_task_submission (void)
- void starpu_sched_ctx_finished_submit (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_get_workers_list (unsigned sched_ctx_id, int **workerids)
- unsigned starpu_sched_ctx_get_workers_list_raw (unsigned sched_ctx_id, int **workerids)
- unsigned starpu_sched_ctx_get_nworkers (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_get_nshared_workers (unsigned sched_ctx_id, unsigned sched_ctx_id2)
- unsigned starpu_sched_ctx_contains_worker (int workerid, unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_contains_type_of_worker (enum starpu_worker_archtype arch, unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_worker_get_id (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_get_ctx_for_task (struct starpu_task *task)
- unsigned starpu_sched_ctx_overlapping_ctxs_on_worker (int workerid)
- void * starpu_sched_ctx_get_user_data (unsigned sched_ctx_id)
- void starpu_sched_ctx_set_user_data (unsigned sched_ctx_id, void *user_data)
- void starpu_sched_ctx_set_policy_data (unsigned sched_ctx_id, void *policy_data)
- void * starpu_sched_ctx_get_policy_data (unsigned sched_ctx_id)
- struct starpu_sched_policy * starpu_sched_ctx_get_sched_policy (unsigned sched_ctx_id)
- void * starpu_sched_ctx_exec_parallel_code (void *(*func)(void *), void *param, unsigned sched_ctx_id)

- int starpu_sched_ctx_get_nready_tasks (unsigned sched_ctx_id)
- double starpu sched ctx get nready flops (unsigned sched ctx id)
- void starpu_sched_ctx_list_task_counters_increment (unsigned sched_ctx_id, int workerid)
- void starpu_sched_ctx_list_task_counters_decrement (unsigned sched_ctx_id, int workerid)
- void starpu sched ctx list task counters reset (unsigned sched ctx id, int workerid)
- void starpu_sched_ctx_list_task_counters_increment_all_ctx_locked (struct starpu_task *task, unsigned sched_ctx_id)
- void starpu_sched_ctx_list_task_counters_decrement_all_ctx_locked (struct starpu_task *task, unsigned sched_ctx_id)
- void starpu sched ctx list task counters reset all (struct starpu task *task, unsigned sched ctx id)
- void starpu sched ctx set priority (int *workers, int nworkers, unsigned sched ctx id, unsigned priority)
- unsigned starpu sched ctx get priority (int worker, unsigned sched ctx id)
- void starpu_sched_ctx_get_available_cpuids (unsigned sched_ctx_id, int **cpuids, int *ncpuids)
- · void starpu sched ctx bind current thread to cpuid (unsigned cpuid)
- int starpu_sched_ctx_book_workers_for_task (unsigned sched_ctx_id, int *workerids, int nworkers)
- void starpu_sched_ctx_unbook_workers_for_task (unsigned sched_ctx_id, int master)
- unsigned starpu_sched_ctx_worker_is_master_for_child_ctx (int workerid, unsigned sched_ctx_id)
- unsigned starpu sched ctx master get context (int masterid)
- void starpu sched ctx revert task counters ctx locked (unsigned sched ctx id, double flops)
- void starpu_sched_ctx_move_task_to_ctx_locked (struct starpu_task *task, unsigned sched_ctx, unsigned with_repush)
- int starpu_sched_ctx_get_worker_rank (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_has_starpu_scheduler (unsigned sched_ctx_id, unsigned *awake_workers)
- int starpu_sched_ctx_get_stream_worker (unsigned sub_ctx)
- int starpu sched ctx get nsms (unsigned sched ctx)
- void starpu_sched_ctx_get_sms_interval (int stream_workerid, int *start, int *end)
- #define STARPU SCHED CTX POLICY NAME
- #define STARPU_SCHED_CTX_POLICY_STRUCT
- #define STARPU SCHED CTX POLICY MIN PRIO
- #define STARPU SCHED CTX POLICY MAX PRIO
- #define STARPU_SCHED_CTX_HIERARCHY_LEVEL
- #define STARPU SCHED CTX NESTED
- #define STARPU SCHED CTX AWAKE WORKERS
- #define STARPU_SCHED_CTX_POLICY_INIT
- #define STARPU_SCHED_CTX_USER_DATA
- #define STARPU_SCHED_CTX_CUDA_NSMS
- #define STARPU SCHED CTX SUB CTXS

Scheduling Context Priorities

- int starpu_sched_ctx_get_min_priority (unsigned sched_ctx_id)
- int starpu_sched_ctx_get_max_priority (unsigned sched_ctx_id)
- int starpu_sched_ctx_set_min_priority (unsigned sched_ctx_id, int min_prio)
- int starpu sched ctx set max priority (unsigned sched ctx id, int max prio)
- int **starpu_sched_ctx_min_priority_is_set** (unsigned sched_ctx_id)
- int starpu_sched_ctx_max_priority_is_set (unsigned sched_ctx_id)
- #define STARPU_MIN_PRIO
- #define STARPU MAX PRIO
- #define STARPU DEFAULT PRIO

Scheduling Context Worker Collection

- struct starpu_worker_collection * starpu_sched_ctx_create_worker_collection (unsigned sched_ctx_id, enum starpu_worker_collection_type type) STARPU_ATTRIBUTE_MALLOC
- void starpu sched ctx delete worker collection (unsigned sched ctx id)
- struct starpu_worker_collection * starpu_sched_ctx_get_worker_collection (unsigned sched_ctx_id)

30.31.1 Detailed Description

StarPU permits on one hand grouping workers in combined workers in order to execute a parallel task and on the other hand grouping tasks in bundles that will be executed by a single specified worker. In contrast when we group workers in scheduling contexts we submit starpu tasks to them and we schedule them with the policy assigned to the context. Scheduling contexts can be created, deleted and modified dynamically.

30.31.2 Macro Definition Documentation

30.31.2.1 STARPU_SCHED_CTX_POLICY_NAME

#define STARPU_SCHED_CTX_POLICY_NAME

Used when calling starpu_sched_ctx_create() to specify a name for a scheduling policy

30.31.2.2 STARPU_SCHED_CTX_POLICY_STRUCT

#define STARPU_SCHED_CTX_POLICY_STRUCT

Used when calling starpu sched ctx create() to specify a pointer to a scheduling policy

30.31.2.3 STARPU_SCHED_CTX_POLICY_MIN_PRIO

#define STARPU_SCHED_CTX_POLICY_MIN_PRIO

Used when calling starpu_sched_ctx_create() to specify a minimum scheduler priority value.

30.31.2.4 STARPU_SCHED_CTX_POLICY_MAX_PRIO

#define STARPU_SCHED_CTX_POLICY_MAX_PRIO

Used when calling starpu_sched_ctx_create() to specify a maximum scheduler priority value.

30.31.2.5 STARPU_SCHED_CTX_AWAKE_WORKERS

#define STARPU_SCHED_CTX_AWAKE_WORKERS

Used when calling starpu sched ctx create() to specify ???

30.31.2.6 STARPU_SCHED_CTX_POLICY_INIT

#define STARPU_SCHED_CTX_POLICY_INIT

Used when calling starpu_sched_ctx_create() to specify a function pointer allowing to initialize the scheduling policy.

30.31.2.7 STARPU_SCHED_CTX_USER_DATA

#define STARPU_SCHED_CTX_USER_DATA

Used when calling starpu_sched_ctx_create() to specify a pointer to some user data related to the context being created.

30.31.2.8 STARPU_SCHED_CTX_CUDA_NSMS

#define STARPU_SCHED_CTX_CUDA_NSMS

Used when calling starpu_sched_ctx_create() in order to create a context on the NVIDIA GPU to specify the number of SMs the context should have

30.31.2.9 STARPU_SCHED_CTX_SUB_CTXS

#define STARPU_SCHED_CTX_SUB_CTXS

Used when calling starpu_sched_ctx_create() to specify a list of sub contexts of the current context.

30.31.2.10 STARPU_MIN_PRIO

```
#define STARPU_MIN_PRIO Provided for legacy reasons.
```

30.31.2.11 STARPU MAX PRIO

```
#define STARPU_MAX_PRIO Provided for legacy reasons.
```

30.31.2.12 STARPU DEFAULT PRIO

```
#define STARPU_DEFAULT_PRIO
```

By convention, the default priority level should be 0 so that we can statically allocate tasks with a default priority.

30.31.3 Function Documentation

30.31.3.1 starpu_sched_ctx_create()

```
unsigned starpu_sched_ctx_create (
    int * workerids_ctx,
    int nworkers_ctx,
    const char * sched_ctx_name,
    ... )
```

Create a scheduling context with the given parameters (see below) and assign the workers in workerids_ctx to execute the tasks submitted to it. The return value represents the identifier of the context that has just been created. It will be further used to indicate the context the tasks will be submitted to. The return value should be at most STARPU NMAX SCHED CTXS.

The arguments following the name of the scheduling context can be of the following types:

- STARPU_SCHED_CTX_POLICY_NAME, followed by the name of a predefined scheduling policy. Use an empty string to create the context with the default scheduling policy.
- STARPU_SCHED_CTX_POLICY_STRUCT, followed by a pointer to a custom scheduling policy (struct starpu_sched_policy *)
- STARPU_SCHED_CTX_POLICY_MIN_PRIO, followed by a integer representing the minimum priority value to be defined for the scheduling policy.
- STARPU_SCHED_CTX_POLICY_MAX_PRIO, followed by a integer representing the maximum priority value to be defined for the scheduling policy.
- STARPU_SCHED_CTX_POLICY_INIT, followed by a function pointer (ie. void init_sched(void)) allowing to initialize the scheduling policy.
- STARPU_SCHED_CTX_USER_DATA, followed by a pointer to a custom user data structure, to be retrieved by starpu_sched_ctx_get_user_data().

30.31.3.2 starpu_sched_ctx_create_inside_interval()

Create a context indicating an approximate interval of resources

30.31.3.3 starpu_sched_ctx_register_close_callback()

Execute the callback whenever the last task of the context finished executing, it is called with the parameters sched_ctx and any other parameter needed by the application (packed in args)

30.31.3.4 starpu_sched_ctx_add_workers()

```
void starpu_sched_ctx_add_workers (
    int * workerids_ctx,
    unsigned nworkers_ctx,
    unsigned sched_ctx_id )
```

Add dynamically the workers in workerids_ctx to the context sched_ctx_id. The last argument cannot be greater than STARPU NMAX SCHED CTXS.

30.31.3.5 starpu_sched_ctx_remove_workers()

```
void starpu_sched_ctx_remove_workers (
    int * workerids_ctx,
    unsigned nworkers_ctx,
    unsigned sched_ctx_id )
```

Remove the workers in $workerids_ctx$ from the context $sched_ctx_id$. The last argument cannot be greater than $STARPU_NMAX_SCHED_CTXS$.

30.31.3.6 starpu_sched_ctx_display_workers()

Print on the file f the worker names belonging to the context sched_ctx_id

30.31.3.7 starpu_sched_ctx_delete()

```
void starpu_sched_ctx_delete (
          unsigned sched_ctx_id )
```

Delete scheduling context sched_ctx_id and transfer remaining workers to the inheritor scheduling context.

30.31.3.8 starpu_sched_ctx_set_inheritor()

```
void starpu_sched_ctx_set_inheritor (
          unsigned sched_ctx_id,
          unsigned inheritor )
```

Indicate that the context inheritor will inherit the resources of the context $sched_ctx_id$ when $sched_ctx_id$ will be deleted.

30.31.3.9 starpu_sched_ctx_set_context()

```
void starpu_sched_ctx_set_context (
          unsigned * sched_ctx_id )
```

Set the scheduling context the subsequent tasks will be submitted to

30.31.3.10 starpu_sched_ctx_get_context()

Return the scheduling context the tasks are currently submitted to, or STARPU_NMAX_SCHED_CTXS if no default context has been defined by calling the function starpu_sched_ctx_set_context().

30.31.3.11 starpu_sched_ctx_stop_task_submission()

Stop submitting tasks from the empty context list until the next time the context has time to check the empty context list

30.31.3.12 starpu_sched_ctx_finished_submit()

```
void starpu_sched_ctx_finished_submit (
          unsigned sched_ctx_id )
```

Indicate starpu that the application finished submitting to this context in order to move the workers to the inheritor as soon as possible.

30.31.3.13 starpu_sched_ctx_get_workers_list()

Return the list of workers in the array workerids, the return value is the number of workers. The user should free the workerids table after finishing using it (it is allocated inside the function with the proper size)

30.31.3.14 starpu_sched_ctx_get_workers_list_raw()

Return the list of workers in the array workerids, the return value is the number of workers. This list is provided in raw order, i.e. not sorted by tree or list order, and the user should not free the workerids table. This function is thus much less costly than starpu_sched_ctx_get_workers_list().

30.31.3.15 starpu_sched_ctx_get_nworkers()

Return the number of workers managed by the specified context (Usually needed to verify if it manages any workers or if it should be blocked)

30.31.3.16 starpu_sched_ctx_get_nshared_workers()

Return the number of workers shared by two contexts.

30.31.3.17 starpu_sched_ctx_contains_worker()

Return 1 if the worker belongs to the context and 0 otherwise

30.31.3.18 starpu_sched_ctx_worker_get_id()

Return the workerid if the worker belongs to the context and -1 otherwise. If the thread calling this function is not a worker the function returns -1 as it calls the function starpu_worker_get_id().

30.31.3.19 starpu_sched_ctx_overlapping_ctxs_on_worker()

Check if a worker is shared between several contexts

30.31.3.20 starpu_sched_ctx_get_user_data()

Return the user data pointer associated to the scheduling context.

30.31.3.21 starpu_sched_ctx_set_policy_data()

Allocate the scheduling policy data (private information of the scheduler like queues, variables, additional condition variables) the context

30.31.3.22 starpu_sched_ctx_get_policy_data()

Return the scheduling policy data (private information of the scheduler) of the contexts previously assigned to.

30.31.3.23 starpu_sched_ctx_exec_parallel_code()

Execute any parallel code on the workers of the sched_ctx (workers are blocked)

30.31.3.24 starpu_sched_ctx_worker_is_master_for_child_ctx()

Return the first context (child of sched_ctx_id) where the workerid is master

30.31.3.25 starpu_sched_ctx_master_get_context()

Return the context id of masterid if it master of a context. If not, return STARPU_NMAX_SCHED_CTXS.

30.31.3.26 starpu_sched_ctx_get_min_priority()

Return the current minimum priority level supported by the scheduling policy of the given scheduler context.

30.31.3.27 starpu_sched_ctx_get_max_priority()

Return the current maximum priority level supported by the scheduling policy of the given scheduler context.

30.31.3.28 starpu_sched_ctx_set_min_priority()

Define the minimum task priority level supported by the scheduling policy of the given scheduler context. The default minimum priority level is the same as the default priority level which is 0 by convention. The application may access that value by calling the function starpu_sched_ctx_get_min_priority(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

30.31.3.29 starpu_sched_ctx_set_max_priority()

```
int starpu_sched_ctx_set_max_priority (
          unsigned sched_ctx_id,
          int max_prio )
```

Define the maximum priority level supported by the scheduling policy of the given scheduler context. The default maximum priority level is 1. The application may access that value by calling the starpu_sched_ctx_get_max_priority() function. This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

30.31.3.30 starpu_sched_ctx_create_worker_collection()

Create a worker collection of the type indicated by the last parameter for the context specified through the first parameter.

30.31.3.31 starpu_sched_ctx_delete_worker_collection()

Delete the worker collection of the specified scheduling context

30.31.3.32 starpu_sched_ctx_get_worker_collection()

Return the worker collection managed by the indicated context

30.32 Scheduling Policy

TODO. While StarPU comes with a variety of scheduling policies (see Task Scheduling Policies), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own scheduling policy.

Data Structures

struct starpu_sched_policy

Macros

- #define STARPU_NMAX_SCHED_CTXS
- #define STARPU MAXIMPLEMENTATIONS

Typedefs

• typedef void(* starpu_notify_ready_soon_func) (void *data, struct starpu_task *task, double delay)

Functions

- struct starpu_sched_policy ** starpu_sched_get_predefined_policies ()
- void starpu_worker_get_sched_condition (int workerid, starpu_pthread_mutex_t **sched_mutex, starpu_
 pthread_cond_t **sched_cond)
- unsigned long starpu_task_get_job_id (struct starpu_task *task)
- int starpu_sched_get_min_priority (void)
- int starpu_sched_get_max_priority (void)
- int starpu_sched_set_min_priority (int min_prio)
- int starpu_sched_set_max_priority (int max_prio)
- int starpu worker can execute task (unsigned workerid, struct starpu task *task, unsigned nimpl)
- int starpu_worker_can_execute_task_impl (unsigned workerid, struct starpu_task *task, unsigned *impl_
 mask)
- int starpu_worker_can_execute_task_first_impl (unsigned workerid, struct starpu_task *task, unsigned *nimpl)
- int starpu_push_local_task (int workerid, struct starpu_task *task, int back)
- int starpu_push_task_end (struct starpu_task *task)
- int starpu_get_prefetch_flag (void)
- int starpu prefetch task input on node prio (struct starpu task *task, unsigned node, int prio)
- int starpu prefetch task input on node (struct starpu task *task, unsigned node)
- int starpu_idle_prefetch_task_input_on_node_prio (struct starpu_task *task, unsigned node, int prio)
- int starpu_idle_prefetch_task_input_on_node (struct starpu_task *task, unsigned node)
- int starpu_prefetch_task_input_for_prio (struct starpu_task *task, unsigned worker, int prio)
- int starpu_prefetch_task_input_for (struct starpu_task *task, unsigned worker)
- int starpu_idle_prefetch_task_input_for_prio (struct starpu_task *task, unsigned worker, int prio)
- int starpu_idle_prefetch_task_input_for (struct starpu_task *task, unsigned worker)
- uint32_t starpu_task_footprint (struct starpu_perfmodel *model, struct starpu_task *task, struct starpu_
 perfmodel_arch *arch, unsigned nimpl)
- uint32_t starpu_task_data_footprint (struct starpu_task *task)
- double starpu_task_expected_length (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- double starpu worker get relative speedup (struct starpu perfmodel arch *perf arch)
- double starpu task expected data transfer time (unsigned memory node, struct starpu task *task)
- double starpu_task_expected_data_transfer_time_for (struct starpu_task *task, unsigned worker)
- double starpu_data_expected_transfer_time (starpu_data_handle_t handle, unsigned memory_node, enum starpu_data_access_mode mode)
- double starpu_task_expected_energy (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- double starpu_task_expected_conversion_time (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- void starpu_task_notify_ready_soon_register (starpu_notify_ready_soon_func f, void *data)
- · void starpu sched ctx worker shares tasks lists (int workerid, int sched ctx id)
- void starpu_sched_task_break (struct starpu_task *task)

Worker operations

- int starpu_wake_worker_relax (int workerid)
- int starpu_wake_worker_no_relax (int workerid)
- int starpu_wake_worker_locked (int workerid)
- · int starpu wake worker relax light (int workerid)

30.32.1 Detailed Description

TODO. While StarPU comes with a variety of scheduling policies (see Task Scheduling Policies), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own scheduling policy.

30.32.2 Data Structure Documentation

30.32.2.1 struct starpu_sched_policy

Contain all the methods that implement a scheduling policy. An application may specify which scheduling strategy in the field starpu_conf::sched_policy passed to the function starpu_init().

For each task going through the scheduler, the following methods get called in the given order:

- starpu_sched_policy::submit_hook when the task is submitted
- starpu_sched_policy::push_task when the task becomes ready. The scheduler is here given the task
- starpu_sched_policy::pop_task when the worker is idle. The scheduler here **gives** back the task to the core. It must not access this task any more
- starpu_sched_policy::pre_exec_hook right before the worker actually starts the task computation (after transferring any missing data).
- starpu sched policy::post exec hook right after the worker actually completes the task computation.

For each task not going through the scheduler (because starpu_task::execute_on_a_specific_worker was set), these get called:

- · starpu_sched_policy::submit_hook when the task is submitted
- starpu_sched_policy::push_task_notify when the task becomes ready. This is just a notification, the scheduler does not have to do anything about the task.
- starpu_sched_policy::pre_exec_hook right before the worker actually starts the task computation (after transferring any missing data).
- starpu sched policy::post exec hook right after the worker actually completes the task computation.

Data Fields

- void(* init_sched)(unsigned sched_ctx_id)
- void(* deinit_sched)(unsigned sched_ctx_id)
- int(* push_task)(struct starpu_task *)
- double(* simulate push task)(struct starpu task *)
- void(* push task notify)(struct starpu task *, int workerid, int perf workerid, unsigned sched ctx id)
- struct starpu_task *(* pop_task)(unsigned sched_ctx_id)
- struct starpu_task *(* pop_every_task)(unsigned sched_ctx_id)
- void(* submit hook)(struct starpu task *task)
- void(* pre exec hook)(struct starpu task *, unsigned sched ctx id)
- void(* post_exec_hook)(struct starpu_task *, unsigned sched_ctx_id)
- void(* do_schedule)(unsigned sched_ctx_id)
- void(* add_workers)(unsigned sched_ctx_id, int *workerids, unsigned nworkers)
- void(* remove_workers)(unsigned sched_ctx_id, int *workerids, unsigned nworkers)
- const char * policy_name
- const char * policy_description
- enum starpu_worker_collection_type worker_type

30.32.2.1.1 Field Documentation

```
30.32.2.1.1.1 init_sched
void(* starpu_sched_policy::init_sched) (unsigned sched_ctx_id)
Initialize the scheduling policy, called before any other method.
30.32.2.1.1.2 deinit_sched
void(* starpu_sched_policy::deinit_sched) (unsigned sched_ctx_id)
Cleanup the scheduling policy
```

```
30.32.2.1.1.3 push_task
```

```
int(* starpu_sched_policy::push_task) (struct starpu_task *)
```

Insert a task into the scheduler, called when the task becomes ready for execution. This must call starpu_push_\circ
task_end() once it has effectively pushed the task to a queue (to note the time when this was done in the task), but before releasing mutexes (so that the task hasn't been already taken by a worker).

```
30.32.2.1.1.4 push_task_notify
```

```
\label{eq:condition} void(* starpu\_sched\_policy::push\_task\_notify) \ (struct \ starpu\_task \ *, \ int \ workerid, \ int \ perf\_{\leftarrow} \ workerid, \ unsigned \ sched\_ctx\_id)
```

Notify the scheduler that a task was pushed on a given worker. This method is called when a task that was explicitly assigned to a worker becomes ready and is about to be executed by the worker. This method therefore permits to keep the state of the scheduler coherent even when StarPU bypasses the scheduling strategy.

```
30.32.2.1.1.5 pop_task
```

```
struct starpu_task*(* starpu_sched_policy::pop_task) (unsigned sched_ctx_id)
```

Get a task from the scheduler. If this method returns NULL, the worker will start sleeping. If later on some task are pushed for this worker, starpu_wake_worker() must be called to wake the worker so it can call the pop_task() method again. The mutex associated to the worker is already taken when this method is called. This method may release it (e.g. for scalability reasons when doing work stealing), but it must acquire it again before taking the decision whether to return a task or NULL, so the atomicity of deciding to return NULL and making the worker actually sleep is preserved. Otherwise in simgrid or blocking driver mode the worker might start sleeping while a task has just been pushed for it. If this method is defined as NULL, the worker will only execute tasks from its local queue. In this case, the push_task method should use the starpu_push_local_task method to assign tasks to the different workers.

```
30.32.2.1.1.6 pop_every_task
```

```
struct starpu_task*(* starpu_sched_policy::pop_every_task) (unsigned sched_ctx_id)
```

Remove all available tasks from the scheduler (tasks are chained by the means of the field starpu_task::prev and starpu_task::next). The mutex associated to the worker is already taken when this method is called. This is currently not used and can be discarded.

```
30.32.2.1.1.7 submit hook
```

```
void(* starpu_sched_policy::submit_hook) (struct starpu_task *task)
```

Optional field. This method is called when a task is submitted.

```
30.32.2.1.1.8 pre_exec_hook
```

```
void(* starpu_sched_policy::pre_exec_hook) (struct starpu_task *, unsigned sched_ctx_id)
```

Optional field. This method is called every time a task is starting.

```
30.32.2.1.1.9 post_exec_hook
```

```
void(* starpu_sched_policy::post_exec_hook) (struct starpu_task *, unsigned sched_ctx_id)
```

Optional field. This method is called every time a task has been executed.

```
30.32.2.1.1.10 do_schedule
```

```
void(* starpu_sched_policy::do_schedule) (unsigned sched_ctx_id)
```

Optional field. This method is called when it is a good time to start scheduling tasks. This is notably called when the application calls starpu_task_wait_for_all(") or starpu_do_schedule() explicitly.

```
30.32.2.1.1.11 add_workers
```

```
void(* starpu_sched_policy::add_workers) (unsigned sched_ctx_id, int *workerids, unsigned
nworkers)
```

Initialize scheduling structures corresponding to each worker used by the policy.

```
30.32.2.1.1.12 remove_workers
```

```
void(* starpu_sched_policy::remove_workers) (unsigned sched_ctx_id, int *workerids, unsigned
nworkers)
```

Deinitialize scheduling structures corresponding to each worker used by the policy.

```
30.32.2.1.1.13 policy_name
```

```
const char* starpu_sched_policy::policy_name
```

Optional field. Name of the policy.

```
30.32.2.1.1.14 policy_description
```

```
const char* starpu_sched_policy::policy_description
```

Optional field. Human readable description of the policy.

30.32.3 Macro Definition Documentation

30.32.3.1 STARPU_NMAX_SCHED_CTXS

```
#define STARPU_NMAX_SCHED_CTXS
```

Define the maximum number of scheduling contexts managed by StarPU. The default value can be modified at configure by using the option --enable-max-sched-ctxs.

30.32.3.2 STARPU_MAXIMPLEMENTATIONS

```
#define STARPU MAXIMPLEMENTATIONS
```

Define the maximum number of implementations per architecture. The default value can be modified at configure by using the option --enable-maximplementations.

30.32.4 Function Documentation

30.32.4.1 starpu_sched_get_predefined_policies()

```
struct starpu_sched_policy** starpu_sched_get_predefined_policies ( )
```

Return an NULL-terminated array of all the predefined scheduling policies.

30.32.4.2 starpu_worker_get_sched_condition()

```
void starpu_worker_get_sched_condition (
          int workerid,
          starpu_pthread_mutex_t ** sched_mutex,
          starpu_pthread_cond_t ** sched_cond )
```

When there is no available task for a worker, StarPU blocks this worker on a condition variable. This function specifies which condition variable (and the associated mutex) should be used to block (and to wake up) a worker. Note that multiple workers may use the same condition variable. For instance, in the case of a scheduling strategy with a single task queue, the same condition variable would be used to block and wake up all workers.

30.32.4.3 starpu_sched_get_min_priority()

```
int starpu_sched_get_min_priority (
     void )
```

TODO: check if this is correct Return the current minimum priority level supported by the scheduling policy

30.32.4.4 starpu_sched_get_max_priority()

TODO: check if this is correct Return the current maximum priority level supported by the scheduling policy

30.32.4.5 starpu_sched_set_min_priority()

TODO: check if this is correct Define the minimum task priority level supported by the scheduling policy. The default minimum priority level is the same as the default priority level which is 0 by convention. The application may access

that value by calling the function starpu_sched_get_min_priority(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

30.32.4.6 starpu_sched_set_max_priority()

TODO: check if this is correct Define the maximum priority level supported by the scheduling policy. The default maximum priority level is 1. The application may access that value by calling the function starpu_sched_get_max—priority(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

30.32.4.7 starpu_worker_can_execute_task()

```
int starpu_worker_can_execute_task (
          unsigned workerid,
          struct starpu_task * task,
          unsigned nimpl )
```

Check if the worker specified by workerid can execute the codelet. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute.

30.32.4.8 starpu_worker_can_execute_task_impl()

Check if the worker specified by workerid can execute the codelet and return which implementation numbers can be used. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute. This should be preferred rather than calling starpu_worker_can_execute_task() for each and every implementation. It can also be used with impl_mask == NULL to check for at least one implementation without determining which.

30.32.4.9 starpu_worker_can_execute_task_first_impl()

Check if the worker specified by workerid can execute the codelet and return the first implementation which can be used. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute. This should be preferred rather than calling $starpu_worker_can_execute_task()$ for each and every implementation. It can also be used with $impl_mask == NULL$ to check for at least one implementation without determining which.

30.32.4.10 starpu_push_local_task()

The scheduling policy may put tasks directly into a worker's local queue so that it is not always necessary to create its own queue when the local queue is sufficient. If back is not 0, task is put at the back of the queue where the worker will pop tasks first. Setting back to 0 therefore ensures a FIFO ordering.

30.32.4.11 starpu_push_task_end()

Must be called by a scheduler to notify that the given task has just been pushed.

```
30.32.4.12 starpu_get_prefetch_flag()
int starpu_get_prefetch_flag (
              void )
Whether STARPU_PREFETCH was set
30.32.4.13 starpu_prefetch_task_input_on_node_prio()
int starpu_prefetch_task_input_on_node_prio (
              struct starpu_task * task,
              unsigned node,
              int prio )
Prefetch data for a given p task on a given p node with a given priority
30.32.4.14 starpu_prefetch_task_input_on_node()
int starpu_prefetch_task_input_on_node (
              struct starpu_task * task,
              unsigned node )
Prefetch data for a given p task on a given p node
30.32.4.15 starpu_idle_prefetch_task_input_on_node_prio()
int \ starpu\_idle\_prefetch\_task\_input\_on\_node\_prio \ (
              struct starpu_task * task,
              unsigned node,
              int prio )
Prefetch data for a given p task on a given p node when the bus is idle with a given priority
30.32.4.16 starpu_idle_prefetch_task_input_on_node()
int starpu_idle_prefetch_task_input_on_node (
              struct starpu_task * task,
              unsigned node )
Prefetch data for a given p task on a given p node when the bus is idle
30.32.4.17 starpu_prefetch_task_input_for_prio()
int starpu_prefetch_task_input_for_prio (
              struct starpu_task * task,
              unsigned worker,
              int prio )
Prefetch data for a given p task on a given p worker with a given priority
30.32.4.18 starpu_prefetch_task_input_for()
int starpu_prefetch_task_input_for (
              struct starpu_task * task,
              unsigned worker )
Prefetch data for a given p task on a given p worker
30.32.4.19 starpu_idle_prefetch_task_input_for_prio()
```

```
int starpu_idle_prefetch_task_input_for_prio (
            struct starpu_task * task,
            unsigned worker,
            int prio )
```

Prefetch data for a given p task on a given p worker when the bus is idle with a given priority

30.32.4.20 starpu_idle_prefetch_task_input_for()

Prefetch data for a given p task on a given p worker when the bus is idle

30.32.4.21 starpu_task_footprint()

Return the footprint for a given task, taking into account user-provided perfmodel footprint or size_base functions.

30.32.4.22 starpu_task_data_footprint()

Return the raw footprint for the data of a given task (without taking into account user-provided functions).

30.32.4.23 starpu_task_expected_length()

Return expected task duration in micro-seconds.

30.32.4.24 starpu_worker_get_relative_speedup()

Return an estimated speedup factor relative to CPU speed

30.32.4.25 starpu_task_expected_data_transfer_time()

Return expected data transfer time in micro-seconds for the given memory_node. Prefer using starpu_task_\to expected_data_transfer_time_for() which is more precise.

30.32.4.26 starpu_task_expected_data_transfer_time_for()

Return expected data transfer time in micro-seconds for the given worker.

30.32.4.27 starpu_data_expected_transfer_time()

Predict the transfer time (in micro-seconds) to move handle to a memory node

30.32.4.28 starpu_task_expected_energy()

Return expected energy consumption in J

30.32.4.29 starpu_task_expected_conversion_time()

Return expected conversion time in ms (multiformat interface only)

30.32.4.30 starpu_task_notify_ready_soon_register()

Register a callback to be called when it is determined when a task will be ready an estimated amount of time from now, because its last dependency has just started and we know how long it will take.

30.32.4.31 starpu_sched_ctx_worker_shares_tasks_lists()

The scheduling policies indicates if the worker may pop tasks from the list of other workers or if there is a central list with task for all the workers

30.32.4.32 starpu_wake_worker_relax()

Wake up workerid while temporarily entering the current worker relax state if needed during the waiting process. Return 1 if workerid has been woken up or its state_keep_awake flag has been set to 1, and 0 otherwise (if workerid was not in the STATE_SLEEPING or in the STATE_SCHEDULING).

30.32.4.33 starpu_wake_worker_no_relax()

Must be called to wake up a worker that is sleeping on the cond. Return 0 whenever the worker is not in a sleeping state or has the state keep awake flag on.

30.32.4.34 starpu_wake_worker_locked()

Version of starpu wake worker no relax() which assumes that the sched mutex is locked

30.32.4.35 starpu_wake_worker_relax_light()

Light version of starpu_wake_worker_relax() which, when possible, speculatively set keep_awake on the target worker without waiting for the worker to enter the relax state.

30.33 Tree

This section describes the tree facilities provided by StarPU.

Data Structures

· struct starpu tree

Functions

- void starpu_tree_reset_visited (struct starpu_tree *tree, char *visited)
- void starpu_tree_prepare_children (unsigned arity, struct starpu_tree *father)
- void starpu_tree_insert (struct starpu_tree *tree, int id, int level, int is_pu, int arity, struct starpu_tree *father)
- struct starpu tree * starpu tree get (struct starpu tree *tree, int id)
- struct starpu_tree * starpu_tree_get_neighbour (struct starpu_tree *tree, struct starpu_tree *node, char *visited, char *present)
- void starpu_tree_free (struct starpu_tree *tree)

30.33.1 Detailed Description

This section describes the tree facilities provided by StarPU.

30.33.2 Data Structure Documentation

30.33.2.1 struct starpu_tree

Data Fields

| struct starpu_tree * | nodes | |
|----------------------|--------|--|
| struct starpu_tree * | father | |
| int | arity | |
| int | id | |
| int | level | |
| int | is_pu | |

30.34 Scheduling Context Hypervisor - Building a new resizing policy

Data Structures

- struct sc_hypervisor_policy
- struct sc_hypervisor_resize_ack
- struct types_of_workers
- struct sc_hypervisor_policy_task_pool

Macros

- #define HYPERVISOR_REDIM_SAMPLE
- #define HYPERVISOR_START_REDIM_SAMPLE
- #define SC NOTHING
- #define SC IDLE
- · #define SC_SPEED

Functions

void sc_hypervisor_policy_add_task_to_pool (struct starpu_codelet *cl, unsigned sched_ctx, uint32_t foot-print, struct sc_hypervisor_policy_task_pool **task_pools, size_t data_size)

- void sc_hypervisor_policy_remove_task_from_pool (struct starpu_task *task, uint32_t footprint, struct sc_
 hypervisor_policy_task_pool **task_pools)
- struct sc_hypervisor_policy_task_pool * sc_hypervisor_policy_clone_task_pool (struct sc_hypervisor_
 policy_task_pool *tp)
- void sc_hypervisor_get_tasks_times (int nw, int nt, double times[nw][nt], int *workers, unsigned size_ctxs, struct sc_hypervisor_policy_task_pool *task_pools)
- unsigned sc hypervisor find lowest prio sched ctx (unsigned reg sched ctx, int nworkers to move)
- int * sc_hypervisor_get_idlest_workers (unsigned sched_ctx, int *nworkers, enum starpu_worker_archtype arch)
- int * sc_hypervisor_get_idlest_workers_in_list (int *start, int *workers, int nall_workers, int *nworkers, enum starpu_worker_archtype arch)
- int sc_hypervisor_get_movable_nworkers (struct sc_hypervisor_policy_config *config, unsigned sched_ctx, enum starpu_worker_archtype arch)
- int sc_hypervisor_compute_nworkers_to_move (unsigned req_sched_ctx)
- unsigned sc_hypervisor_policy_resize (unsigned sender_sched_ctx, unsigned receiver_sched_ctx, unsigned force_resize, unsigned now)
- unsigned sc_hypervisor_policy_resize_to_unknown_receiver (unsigned sender_sched_ctx, unsigned now)
- double sc_hypervisor_get_ctx_speed (struct sc_hypervisor_wrapper *sc_w)
- double sc_hypervisor_get_slowest_ctx_exec_time (void)
- double sc hypervisor get fastest ctx exec time (void)
- · double sc hypervisor get speed per worker (struct sc hypervisor wrapper *sc w, unsigned worker)
- double sc_hypervisor_get_ref_speed_per_worker_type (struct sc_hypervisor_wrapper *sc_w, enum starpu_worker_archtype arch)
- double sc_hypervisor_get_avg_speed (enum starpu_worker_archtype arch)
- void sc_hypervisor_check_if_consider_max (struct types_of_workers *tw)
- void sc_hypervisor_group_workers_by_type (struct types_of_workers *tw, int *total_nw)
- enum starpu_worker_archtype sc_hypervisor_get_arch_for_index (unsigned w, struct types_of_workers *tw)
- unsigned sc_hypervisor_get_index_for_arch (enum starpu_worker_archtype arch, struct types_of_workers *tw)
- unsigned sc_hypervisor_criteria_fulfilled (unsigned sched_ctx, int worker)
- unsigned sc_hypervisor_check_idle (unsigned sched_ctx, int worker)
- unsigned sc_hypervisor_check_speed_gap_btw_ctxs (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- unsigned sc_hypervisor_check_speed_gap_btw_ctxs_on_level (int level, int *workers_in, int nworkers_in, unsigned father_sched_ctx_id, unsigned **sched_ctxs, int *nsched_ctxs)
- unsigned sc_hypervisor_get_resize_criteria ()
- struct types_of_workers * sc_hypervisor_get_types_of_workers (int *workers, unsigned nworkers)
- void sc_hypervisor_set_config (unsigned sched_ctx, void *config)
- struct sc_hypervisor_policy_config * sc_hypervisor_get_config (unsigned sched_ctx)
- void sc_hypervisor_ctl (unsigned sched_ctx,...)
- #define SC_HYPERVISOR_MAX_IDLE
- #define SC_HYPERVISOR_MIN_WORKING
- #define SC HYPERVISOR PRIORITY
- #define SC HYPERVISOR MIN WORKERS
- #define SC HYPERVISOR MAX WORKERS
- #define SC HYPERVISOR GRANULARITY
- #define SC HYPERVISOR FIXED WORKERS
- #define SC HYPERVISOR MIN TASKS
- #define SC_HYPERVISOR_NEW_WORKERS_MAX_IDLE
- #define SC_HYPERVISOR_TIME_TO_APPLY
- #define SC HYPERVISOR NULL
- #define SC HYPERVISOR ISPEED W SAMPLE
- #define SC HYPERVISOR ISPEED CTX SAMPLE

- #define SC HYPERVISOR TIME SAMPLE
- #define MAX IDLE TIME
- #define MIN_WORKING_TIME
- struct sc_hypervisor_wrapper * sc_hypervisor_get_wrapper (unsigned sched_ctx)
- unsigned * sc hypervisor get sched ctxs ()
- int sc_hypervisor_get_nsched_ctxs ()
- double sc hypervisor get elapsed flops per sched ctx (struct sc hypervisor wrapper *sc w)
- int sc hypervisor get nworkers ctx (unsigned sched ctx, enum starpu worker archtype arch)
- double sc hypervisor get total elapsed flops per sched ctx (struct sc hypervisor wrapper *sc w)
- double sc_hypervisorsc_hypervisor_get_speed_per_worker_type (struct sc_hypervisor_wrapper *sc_w, enum starpu_worker_archtype arch)
- double sc_hypervisor_get_speed (struct sc_hypervisor_wrapper *sc_w, enum starpu_worker_archtype arch)

30.34.1 Detailed Description

30.34.2 Data Structure Documentation

30.34.2.1 struct sc_hypervisor_policy

Methods to implement a hypervisor resizing policy.

Data Fields

- const char * name
- unsigned custom
- void(* size ctxs)(unsigned *sched ctxs, int nsched ctxs, int *workers, int nworkers)
- void(* resize_ctxs)(unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void(* handle_idle_cycle)(unsigned sched_ctx, int worker)
- void(* handle pushed task)(unsigned sched ctx, int worker)
- void(* handle_poped_task)(unsigned sched_ctx, int worker, struct starpu_task *task, uint32_t footprint)
- void(* handle idle end)(unsigned sched ctx, int worker)
- void(* handle_post_exec_hook)(unsigned sched_ctx, int task_tag)
- void(* handle_submitted_job)(struct starpu_codelet *cl, unsigned sched_ctx, uint32_t footprint, size_t data
 —size)
- void(* end_ctx)(unsigned sched_ctx)
- void(* start_ctx)(unsigned sched_ctx)
- void(* init_worker)(int workerid, unsigned sched_ctx)

30.34.2.1.1 Field Documentation

30.34.2.1.1.1 name

```
const char* sc_hypervisor_policy::name
```

Indicate the name of the policy, if there is not a custom policy, the policy corresponding to this name will be used by the hypervisor

30.34.2.1.1.2 custom

unsigned sc_hypervisor_policy::custom

Indicate whether the policy is custom or not

30.34.2.1.1.3 size_ctxs

void(* sc_hypervisor_policy::size_ctxs) (unsigned *sched_ctxs, int nsched_ctxs, int *workers,
int nworkers)

Distribute workers to contexts even at the begining of the program

30.34.2.1.1.4 resize_ctxs

void(* sc_hypervisor_policy::resize_ctxs) (unsigned *sched_ctxs, int nsched_ctxs, int *workers,
int nworkers)

Require explicit resizing

30.34.2.1.1.5 handle_idle_cycle

void(* sc_hypervisor_policy::handle_idle_cycle) (unsigned sched_ctx, int worker)

Called whenever the indicated worker executes another idle cycle in sched_ctx

30.34.2.1.1.6 handle_pushed_task

void(* sc_hypervisor_policy::handle_pushed_task) (unsigned sched_ctx, int worker)

Called whenever a task is pushed on the worker's queue corresponding to the context sched ctx

30.34.2.1.1.7 handle_poped_task

 $\label{lem:cond} void(* sc_hypervisor_policy::handle_poped_task) \ (unsigned sched_ctx, int worker, struct starpu \leftarrow _task *task, uint32_t footprint)$

Called whenever a task is poped from the worker's queue corresponding to the context sched_ctx

30.34.2.1.1.8 handle_idle_end

void(* sc_hypervisor_policy::handle_idle_end) (unsigned sched_ctx, int worker)

Called whenever a task is executed on the indicated worker and context after a long period of idle time

30.34.2.1.1.9 handle_post_exec_hook

void(* sc_hypervisor_policy::handle_post_exec_hook) (unsigned sched_ctx, int task_tag)

Called whenever a tag task has just been executed. The table of resize requests is provided as well as the tag

30.34.2.1.1.10 handle_submitted_job

 $\label{local_policy} void(* sc_hypervisor_policy::handle_submitted_job) (struct starpu_codelet *cl, unsigned schederictx, uint32_t footprint, size_t data_size)$

the hypervisor takes a decision when a job was submitted in this ctx

30.34.2.1.1.11 end_ctx

void(* sc_hypervisor_policy::end_ctx) (unsigned sched_ctx)

the hypervisor takes a decision when a certain ctx was deleted

30.34.2.1.1.12 start_ctx

void(* sc_hypervisor_policy::start_ctx) (unsigned sched_ctx)

the hypervisor takes a decision when a certain ctx was registerd

30.34.2.1.1.13 init_worker

 $\verb|void(* sc_hypervisor_policy::init_worker)| (int workerid, unsigned sched_ctx)| \\$

the hypervisor initializes values for the workers

30.34.2.2 struct sc_hypervisor_resize_ack

Structure to check if the workers moved to another context are actually taken into account in that context.

Data Fields

| int | receiver_sched_ctx | The context receiving the new workers | | |
|-------|--------------------|---|--|--|
| int * | moved_workers | List of workers required to be moved | | |
| int | nmoved_workers | Number of workers required to be moved | | |
| int * | acked_workers | List of workers that actually got in the receiver ctx. If the value corresponding to a worker is 1, this worker got moved in the new context. | | |

30.34.2.3 struct types_of_workers

Data Fields

| unsigned | ncpus | |
|----------|-------|--|
| unsigned | ncuda | |
| unsigned | nw | |

30.34.2.4 struct sc_hypervisor_policy_task_pool

Task wrapper linked list

Data Fields

| struct starpu_codelet * | cl | Which codelet has been executed |
|----------------------------------|--------------|--|
| uint32_t | footprint | Task footprint key |
| unsigned | sched_ctx_id | Context the task belongs to |
| unsigned long | n | Number of tasks of this kind |
| size_t | data_size | The quantity of data(in bytes) needed by the task to execute |
| struct | | |
| sc_hypervisor_policy_task_pool * | next | Other task kinds |

30.34.3 Macro Definition Documentation

30.34.3.1 SC_HYPERVISOR_MAX_IDLE

#define SC_HYPERVISOR_MAX_IDLE

This macro is used when calling sc_hypervisor_ctl() and must be followed by 3 arguments: an array of int for the workerids to apply the condition, an int to indicate the size of the array, and a double value indicating the maximum idle time allowed for a worker before the resizing process should be triggered

30.34.3.2 SC_HYPERVISOR_PRIORITY

#define SC_HYPERVISOR_PRIORITY

This macro is used when calling sc_hypervisor_ctl() and must be followed by 3 arguments: an array of int for the workerids to apply the condition, an int to indicate the size of the array, and an int value indicating the priority of the workers previously mentioned. The workers with the smallest priority are moved the first.

30.34.3.3 SC_HYPERVISOR_MIN_WORKERS

#define SC_HYPERVISOR_MIN_WORKERS

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument(int) indicating the minimum number of workers a context should have, underneath this limit the context cannot execute.

30.34.3.4 SC_HYPERVISOR_MAX_WORKERS

#define SC_HYPERVISOR_MAX_WORKERS

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument(int) indicating the maximum number of workers a context should have, above this limit the context would not be able to scale

30.34.3.5 SC HYPERVISOR GRANULARITY

#define SC_HYPERVISOR_GRANULARITY

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument(int) indicating the granularity of the resizing process (the number of workers should be moved from the context once it is resized) This parameter is ignore for the Gflops rate based strategy (see Resizing Strategies), the number of workers that have to be moved is calculated by the strategy.

30.34.3.6 SC_HYPERVISOR_FIXED_WORKERS

#define SC_HYPERVISOR_FIXED_WORKERS

This macro is used when calling sc_hypervisor_ctl() and must be followed by 2 arguments: an array of int for the workerids to apply the condition and an int to indicate the size of the array. These workers are not allowed to be moved from the context.

30.34.3.7 SC_HYPERVISOR_MIN_TASKS

```
#define SC_HYPERVISOR_MIN_TASKS
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument (int) that indicated the minimum number of tasks that have to be executed before the context could be resized. This parameter is ignored for the Application Driven strategy (see Resizing Strategies) where the user indicates exactly when the resize should be done.

30.34.3.8 SC_HYPERVISOR_NEW_WORKERS_MAX_IDLE

```
#define SC_HYPERVISOR_NEW_WORKERS_MAX_IDLE
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument, a double value indicating the maximum idle time allowed for workers that have just been moved from other contexts in the current context.

30.34.3.9 SC_HYPERVISOR_TIME_TO_APPLY

```
#define SC_HYPERVISOR_TIME_TO_APPLY
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument (int) indicating the tag an executed task should have such that this configuration should be taken into account.

30.34.3.10 SC_HYPERVISOR_NULL

```
#define SC_HYPERVISOR_NULL
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument

30.34.3.11 SC_HYPERVISOR_ISPEED_W_SAMPLE

```
#define SC_HYPERVISOR_ISPEED_W_SAMPLE
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument, a double, that indicates the number of flops needed to be executed before computing the speed of a worker

30.34.3.12 SC_HYPERVISOR_ISPEED_CTX_SAMPLE

```
#define SC_HYPERVISOR_ISPEED_CTX_SAMPLE
```

This macro is used when calling sc_hypervisor_ctl() and must be followed by 1 argument, a double, that indicates the number of flops needed to be executed before computing the speed of a context

30.34.4 Function Documentation

```
30.34.4.1 sc_hypervisor_get_wrapper()
struct sc_hypervisor_wrapper* sc_hypervisor_get_wrapper (
```

30.34.4.2 sc_hypervisor_get_sched_ctxs()

```
unsigned* sc_hypervisor_get_sched_ctxs ( )
```

Get the list of registered contexts

30.34.4.3 sc_hypervisor_get_nsched_ctxs()

int sc_hypervisor_get_nsched_ctxs ()

Get the number of registered contexts

```
30.34.4.4 sc_hypervisor_get_elapsed_flops_per_sched_ctx()
double sc_hypervisor_get_elapsed_flops_per_sched_ctx (
              struct sc_hypervisor_wrapper * sc_w )
Get the number of flops executed by a context since last resizing (reset to 0 when a resizing is done)
30.34.4.5 sc_hypervisor_policy_add_task_to_pool()
void sc_hypervisor_policy_add_task_to_pool (
              struct starpu_codelet * cl,
              unsigned sched_ctx,
              uint32_t footprint,
              struct sc_hypervisor_policy_task_pool ** task_pools,
              size_t data_size )
add task information to a task wrapper linked list
30.34.4.6 sc_hypervisor_policy_remove_task_from_pool()
void sc_hypervisor_policy_remove_task_from_pool (
              struct starpu_task * task,
              uint32_t footprint,
              struct sc_hypervisor_policy_task_pool ** task_pools )
remove task information from a task wrapper linked list
30.34.4.7 sc_hypervisor_policy_clone_task_pool()
struct sc_hypervisor_policy_task_pool* sc_hypervisor_policy_clone_task_pool (
              struct sc_hypervisor_policy_task_pool * tp )
clone a task wrapper linked list
30.34.4.8 sc_hypervisor_get_tasks_times()
void sc_hypervisor_get_tasks_times (
             int nw,
              int nt,
              double times[nw][nt],
              int * workers,
              unsigned size_ctxs,
              struct sc_hypervisor_policy_task_pool * task_pools )
get the execution time of the submitted tasks out of starpu's calibration files
30.34.4.9 sc_hypervisor_find_lowest_prio_sched_ctx()
unsigned sc_hypervisor_find_lowest_prio_sched_ctx (
              unsigned req_sched_ctx,
              int nworkers_to_move )
find the context with the lowest priority in order to move some workers
30.34.4.10 sc_hypervisor_get_idlest_workers()
int* sc_hypervisor_get_idlest_workers (
              unsigned sched_ctx,
              int * nworkers,
              enum starpu_worker_archtype arch )
find the first most idle workers of a contex
30.34.4.11 sc_hypervisor_get_idlest_workers_in_list()
int* sc_hypervisor_get_idlest_workers_in_list (
              int * start,
```

```
int * workers,
              int nall_workers,
              int * nworkers,
              enum starpu\_worker\_archtype arch )
find the first most idle workers in a list
30.34.4.12 sc_hypervisor_get_movable_nworkers()
int sc_hypervisor_get_movable_nworkers (
              struct sc_hypervisor_policy_config * config,
              unsigned sched_ctx,
              enum starpu_worker_archtype arch )
find workers that can be moved from a context (if the constraints of min, max, etc allow this)
30.34.4.13 sc_hypervisor_compute_nworkers_to_move()
int sc_hypervisor_compute_nworkers_to_move (
              unsigned req_sched_ctx )
compute how many workers should be moved from this context
30.34.4.14 sc_hypervisor_policy_resize()
unsigned sc_hypervisor_policy_resize (
              unsigned sender_sched_ctx,
              unsigned receiver_sched_ctx,
              unsigned force_resize,
              unsigned now )
check the policy's constraints in order to resize
30.34.4.15 sc_hypervisor_policy_resize_to_unknown_receiver()
unsigned sc_hypervisor_policy_resize_to_unknown_receiver (
              unsigned sender_sched_ctx,
              unsigned now )
check the policy's constraints in order to resize and find a context willing the resources
30.34.4.16 sc_hypervisor_get_ctx_speed()
double sc_hypervisor_get_ctx_speed (
              struct sc_hypervisor_wrapper * sc_w )
compute the speed of a context
30.34.4.17 sc_hypervisor_get_slowest_ctx_exec_time()
{\tt double \ sc\_hypervisor\_get\_slowest\_ctx\_exec\_time \ (}
              void )
get the time of execution of the slowest context
30.34.4.18 sc_hypervisor_get_fastest_ctx_exec_time()
double sc_hypervisor_get_fastest_ctx_exec_time (
              void )
get the time of execution of the fastest context
30.34.4.19 sc_hypervisor_get_speed_per_worker()
double sc_hypervisor_get_speed_per_worker (
              struct sc_hypervisor_wrapper * sc_w,
              unsigned worker )
```

compute the speed of a workers in a context

```
30.34.4.20 sc_hypervisor_get_speed_per_worker_type()
double sc_hypervisor_get_speed_per_worker_type (
              struct sc_hypervisor_wrapper * sc_w,
              enum starpu_worker_archtype arch )
compute the speed of a type of worker in a context
30.34.4.21 sc hypervisor get ref speed per worker type()
double sc_hypervisor_get_ref_speed_per_worker_type (
              struct sc_hypervisor_wrapper * sc_w,
              enum starpu_worker_archtype arch )
compute the speed of a type of worker in a context depending on its history
30.34.4.22 sc_hypervisor_get_avg_speed()
double sc_hypervisor_get_avg_speed (
              enum starpu_worker_archtype arch )
compute the average speed of a type of worker in all ctxs from the begining of appl
30.34.4.23 sc_hypervisor_check_if_consider_max()
void sc_hypervisor_check_if_consider_max (
              struct types_of_workers * tw )
verify if we need to consider the max in the lp
30.34.4.24 sc_hypervisor_group_workers_by_type()
void sc_hypervisor_group_workers_by_type (
              struct types_of_workers * tw,
              int * total_nw )
get the list of workers grouped by type
30.34.4.25 sc_hypervisor_get_arch_for_index()
enum starpu_worker_archtype sc_hypervisor_get_arch_for_index (
              unsigned w,
              struct types_of_workers * tw )
get what type of worker corresponds to a certain index of types of workers
30.34.4.26 sc_hypervisor_get_index_for_arch()
unsigned sc_hypervisor_get_index_for_arch (
              enum starpu_worker_archtype arch,
              struct types_of_workers * tw )
get the index of types of workers corresponding to the type of workers indicated
30.34.4.27 sc_hypervisor_criteria_fulfilled()
unsigned sc_hypervisor_criteria_fulfilled (
              unsigned sched_ctx,
              int worker )
check if we trigger resizing or not
30.34.4.28 sc_hypervisor_check_idle()
unsigned sc_hypervisor_check_idle (
              unsigned sched_ctx,
              int worker )
```

check if worker was idle long enough

```
30.34.4.29 sc_hypervisor_check_speed_gap_btw_ctxs()
unsigned sc_hypervisor_check_speed_gap_btw_ctxs (
              unsigned * sched_ctxs,
              int nsched_ctxs,
              int * workers,
              int nworkers )
check if there is a speed gap btw ctxs
30.34.4.30 sc_hypervisor_check_speed_gap_btw_ctxs_on_level()
unsigned sc_hypervisor_check_speed_gap_btw_ctxs_on_level (
              int level,
              int * workers_in,
              int nworkers_in,
              unsigned father_sched_ctx_id,
              unsigned ** sched_ctxs,
              int * nsched_ctxs )
check if there is a speed gap btw ctxs on one level
30.34.4.31 sc_hypervisor_get_resize_criteria()
unsigned sc_hypervisor_get_resize_criteria ( )
check what triggers resizing (idle, speed, etc.
30.34.4.32 sc_hypervisor_get_types_of_workers()
struct types_of_workers* sc_hypervisor_get_types_of_workers (
              int * workers,
              unsigned nworkers )
load information concerning the type of workers into a types_of_workers struct
30.34.4.33 sc_hypervisor_set_config()
void sc_hypervisor_set_config (
              unsigned sched_ctx,
              void * config )
Specify the configuration for a context
30.34.4.34 sc_hypervisor_get_config()
\verb|struct sc_hypervisor_policy_config* sc_hypervisor_get_config (|
              unsigned sched_ctx )
Return the configuration of a context
30.34.4.35 sc_hypervisor_ctl()
void sc_hypervisor_ctl (
              unsigned sched_ctx,
Specify different parameters for the configuration of a context. The list must be zero-terminated
30.34.4.36 sc_hypervisor_get_nworkers_ctx()
int sc_hypervisor_get_nworkers_ctx (
              unsigned sched_ctx,
              \verb"enum starpu_worker_archtype" arch")
```

Get the number of workers of a certain architecture in a context

```
30.34.4.37 sc_hypervisor_get_total_elapsed_flops_per_sched_ctx()
```

Get the number of flops executed by a context since the begining

30.34.4.38 sc_hypervisorsc_hypervisor_get_speed_per_worker_type()

Compute an average value of the cpu/cuda speed

30.34.4.39 sc_hypervisor_get_speed()

Compte the actual speed of all workers of a specific type of worker

30.35 Scheduling Context Hypervisor - Regular usage

Data Structures

· struct sc_hypervisor_policy

Functions

- void * sc hypervisor init (struct sc hypervisor policy *policy)
- void sc hypervisor shutdown (void)
- void sc_hypervisor_register_ctx (unsigned sched_ctx, double total_flops)
- void sc_hypervisor_unregister_ctx (unsigned sched_ctx)
- void sc_hypervisor_post_resize_request (unsigned sched_ctx, int task_tag)
- void sc_hypervisor_resize_ctxs (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void sc hypervisor stop resize (unsigned sched ctx)
- void sc_hypervisor_start_resize (unsigned sched_ctx)
- const char * sc_hypervisor_get_policy ()
- void sc_hypervisor_add_workers_to_sched_ctx (int *workers_to_add, unsigned nworkers_to_add, unsigned sched_ctx)
- void sc_hypervisor_remove_workers_from_sched_ctx (int *workers_to_remove, unsigned nworkers_to_
 remove, unsigned sched_ctx, unsigned now)
- void sc_hypervisor_move_workers (unsigned sender_sched_ctx, unsigned receiver_sched_ctx, int *workers_to_move, unsigned nworkers_to_move, unsigned now)
- void sc_hypervisor_size_ctxs (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- unsigned sc_hypervisor_get_size_req (unsigned **sched_ctxs, int *nsched_ctxs, int **workers, int *nworkers)
- void sc_hypervisor_save_size_req (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void sc_hypervisor_free_size_req (void)
- unsigned sc_hypervisor_can_resize (unsigned sched_ctx)
- void sc_hypervisor_set_type_of_task (struct starpu_codelet *cl, unsigned sched_ctx, uint32_t footprint, size_t data_size)
- void sc hypervisor update diff total flops (unsigned sched ctx, double diff total flops)
- void sc hypervisor update diff elapsed flops (unsigned sched ctx, double diff task flops)
- void sc hypervisor update resize interval (unsigned *sched ctxs, int nsched ctxs, int max nworkers)
- void sc_hypervisor_get_ctxs_on_level (unsigned **sched_ctxs, int *nsched_ctxs, unsigned hierarchy_level, unsigned father_sched_ctx_id)
- unsigned sc_hypervisor_get_nhierarchy_levels (void)

- void sc_hypervisor_get_leaves (unsigned *sched_ctxs, int nsched_ctxs, unsigned *leaves, int *nleaves)
- double sc_hypervisor_get_nready_flops_of_all_sons_of_sched_ctx (unsigned sched_ctx)
- void sc hypervisor print overhead ()
- void sc hypervisor_init_worker (int workerid, unsigned sched_ctx)

Variables

starpu_pthread_mutex_t act_hypervisor_mutex

30.35.1 Detailed Description

There is a single hypervisor that is in charge of resizing contexts and the resizing strategy is chosen at the initialization of the hypervisor. A single resize can be done at a time.

The Scheduling Context Hypervisor Plugin provides a series of performance counters to StarPU. By incrementing them, StarPU can help the hypervisor in the resizing decision making process.

The function sc_hypervisor_init() initializes the hypervisor to use the strategy provided as parameter and creates the performance counters (see starpu_sched_ctx_performance_counters). These performance counters represent actually some callbacks that will be used by the contexts to notify the information needed by the hypervisor.

Scheduling Contexts that have to be resized by the hypervisor must be first registered to the hypervisor using the function sc hypervisor register ctx()

Note: The Hypervisor is actually a worker that takes this role once certain conditions trigger the resizing process (there is no additional thread assigned to the hypervisor).

30.35.2 Data Structure Documentation

30.35.2.1 struct sc_hypervisor_policy

Methods to implement a hypervisor resizing policy.

Data Fields

- const char * name
- unsigned custom
- void(* size_ctxs)(unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void(* resize_ctxs)(unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void(* handle_idle_cycle)(unsigned sched_ctx, int worker)
- void(* handle_pushed_task)(unsigned sched_ctx, int worker)
- void(* handle poped task)(unsigned sched ctx, int worker, struct starpu task *task, uint32 t footprint)
- void(* handle idle end)(unsigned sched ctx, int worker)
- void(* handle_post_exec_hook)(unsigned sched_ctx, int task_tag)
- void(* handle_submitted_job)(struct starpu_codelet *cl, unsigned sched_ctx, uint32_t footprint, size_t data
 size)
- void(* end ctx)(unsigned sched ctx)
- void(* start_ctx)(unsigned sched_ctx)
- void(* init worker)(int workerid, unsigned sched ctx)

30.35.2.1.1 Field Documentation

30.35.2.1.1.1 name

```
const char* sc_hypervisor_policy::name
```

Indicate the name of the policy, if there is not a custom policy, the policy corresponding to this name will be used by the hypervisor

30.35.2.1.1.2 custom

```
unsigned sc_hypervisor_policy::custom
```

Indicate whether the policy is custom or not

```
30.35.2.1.1.3 size_ctxs
 void(* sc_hypervisor_policy::size_ctxs) (unsigned *sched_ctxs, int nsched_ctxs, int *workers,
 int nworkers)
Distribute workers to contexts even at the begining of the program
30.35.2.1.1.4 resize_ctxs
void(* sc_hypervisor_policy::resize_ctxs) (unsigned *sched_ctxs, int nsched_ctxs, int *workers,
 int nworkers)
Require explicit resizing
30.35.2.1.1.5 handle_idle_cycle
void(* sc_hypervisor_policy::handle_idle_cycle) (unsigned sched_ctx, int worker)
Called whenever the indicated worker executes another idle cycle in sched ctx
30.35.2.1.1.6 handle pushed task
void(* sc_hypervisor_policy::handle_pushed_task) (unsigned sched_ctx, int worker)
Called whenever a task is pushed on the worker's queue corresponding to the context sched_ctx
30.35.2.1.1.7 handle_poped_task
\verb|void(* sc_hypervisor_policy::handle_poped_task)| (unsigned sched_ctx, int worker, struct starpu \leftarrow | (unsigned sched_ctx, int worker, starpu \leftarrow | (unsigned sched_ctx, int worker,
  _task *task, uint32_t footprint)
Called whenever a task is poped from the worker's queue corresponding to the context sched_ctx
30.35.2.1.1.8 handle_idle_end
void(* sc_hypervisor_policy::handle_idle_end) (unsigned sched_ctx, int worker)
Called whenever a task is executed on the indicated worker and context after a long period of idle time
30.35.2.1.1.9 handle_post_exec_hook
void(* sc_hypervisor_policy::handle_post_exec_hook) (unsigned sched_ctx, int task_tag)
Called whenever a tag task has just been executed. The table of resize requests is provided as well as the tag
30.35.2.1.1.10 handle_submitted_job
\verb|void(* sc_hypervisor_policy::handle_submitted_job)| (struct \verb|starpu_code| et *cl, unsigned sched| \leftrightarrow one of the starpu_code of the starpu_code
 _ctx, uint32_t footprint, size_t data_size)
the hypervisor takes a decision when a job was submitted in this ctx
30.35.2.1.1.11 end_ctx
 void(* sc_hypervisor_policy::end_ctx) (unsigned sched_ctx)
the hypervisor takes a decision when a certain ctx was deleted
30.35.2.1.1.12 start ctx
 void(* sc_hypervisor_policy::start_ctx) (unsigned sched_ctx)
the hypervisor takes a decision when a certain ctx was registerd
30.35.2.1.1.13 init_worker
void(* sc_hypervisor_policy::init_worker) (int workerid, unsigned sched_ctx)
the hypervisor initializes values for the workers
 30.35.3 Function Documentation
```

30.35.3.2 sc_hypervisor_shutdown()

Shutdown the hypervisor. The hypervisor and all information concerning it is cleaned. There is no synchronization between this function and starpu_shutdown(). Thus, this should be called after starpu_shutdown(), because the performance counters will still need allocated callback functions.

30.35.3.3 sc_hypervisor_register_ctx()

```
void sc_hypervisor_register_ctx (
          unsigned sched_ctx,
          double total_flops)
```

Register the context to the hypervisor, and indicate the number of flops the context will execute (used for Gflops rate based strategy)

30.35.3.4 sc_hypervisor_unregister_ctx()

```
void sc_hypervisor_unregister_ctx (
          unsigned sched_ctx )
```

Unregister a context from the hypervisor, and so exclude the context from the resizing process

30.35.3.5 sc_hypervisor_post_resize_request()

```
void sc_hypervisor_post_resize_request (
          unsigned sched_ctx,
          int task_tag )
```

Require resizing the context sched_ctx whenever a task tagged with the id task_tag finished executing

30.35.3.6 sc_hypervisor_resize_ctxs()

```
void sc_hypervisor_resize_ctxs (
          unsigned * sched_ctxs,
          int nsched_ctxs,
          int * workers,
          int nworkers )
```

Require reconsidering the distribution of ressources over the indicated scheduling contexts, i.e reevaluate the distribution of the resources and eventually resize if needed

30.35.3.7 sc_hypervisor_stop_resize()

```
void sc_hypervisor_stop_resize ( \label{eq:constraint} \text{unsigned } sched\_ctx \ )
```

Do not allow the hypervisor to resize a context.

30.35.3.8 sc_hypervisor_start_resize()

```
void sc_hypervisor_start_resize (
          unsigned sched_ctx )
```

Allow the hypervisor to resize a context if necessary.

30.35.3.9 sc_hypervisor_get_policy()

```
const char* sc_hypervisor_get_policy ( )
```

Return the name of the resizing policy used by the hypervisor

30.35.3.10 sc_hypervisor_add_workers_to_sched_ctx()

```
unsigned nworkers_to_add,
unsigned sched_ctx )
```

Ask the hypervisor to add workers to a sched_ctx

```
30.35.3.11 sc_hypervisor_remove_workers_from_sched_ctx()
```

```
void sc_hypervisor_remove_workers_from_sched_ctx (
    int * workers_to_remove,
    unsigned nworkers_to_remove,
    unsigned sched_ctx,
    unsigned now )
```

Ask the hypervisor to remove workers from a sched ctx

30.35.3.12 sc_hypervisor_move_workers()

```
void sc_hypervisor_move_workers (
          unsigned sender_sched_ctx,
          unsigned receiver_sched_ctx,
          int * workers_to_move,
          unsigned nworkers_to_move,
          unsigned now )
```

Ask the hypervisor to move workers from one context to another

30.35.3.13 sc_hypervisor_size_ctxs()

```
void sc_hypervisor_size_ctxs (
          unsigned * sched_ctxs,
          int nsched_ctxs,
          int * workers,
          int nworkers )
```

Ask the hypervisor to choose a distribution of workers in the required contexts

30.35.3.14 sc_hypervisor_get_size_req()

```
unsigned sc_hypervisor_get_size_req (
          unsigned ** sched_ctxs,
          int * nsched_ctxs,
          int ** workers,
          int * nworkers )
```

Check if there are pending demands of resizing

30.35.3.15 sc_hypervisor_save_size_req()

```
void sc_hypervisor_save_size_req (
          unsigned * sched_ctxs,
          int nsched_ctxs,
          int * workers,
          int nworkers )
```

Save a demand of resizing

30.35.3.16 sc_hypervisor_free_size_req()

Clear the list of pending demands of resizing

30.35.3.17 sc_hypervisor_can_resize()

Check out if a context can be resized

```
30.35.3.18 sc_hypervisor_set_type_of_task()
```

Indicate the types of tasks a context will execute in order to better decide the sizing of ctxs

30.35.3.19 sc_hypervisor_update_diff_total_flops()

Change dynamically the total number of flops of a context, move the deadline of the finishing time of the context

30.35.3.20 sc_hypervisor_update_diff_elapsed_flops()

Change dynamically the number of the elapsed flops in a context, modify the past in order to better compute the speed

30.35.3.21 sc_hypervisor_update_resize_interval()

Update the min and max workers needed by each context

30.35.3.22 sc_hypervisor_get_ctxs_on_level()

```
void sc_hypervisor_get_ctxs_on_level (
    unsigned ** sched_ctxs,
    int * nsched_ctxs,
    unsigned hierarchy_level,
    unsigned father_sched_ctx_id )
```

Return a list of contexts that are on the same level in the hierarchy of contexts

30.35.3.23 sc_hypervisor_get_nhierarchy_levels()

Returns the number of levels of ctxs registered to the hyp

30.35.3.24 sc_hypervisor_get_leaves()

```
void sc_hypervisor_get_leaves (
          unsigned * sched_ctxs,
          int nsched_ctxs,
          unsigned * leaves,
          int * nleaves )
```

Return the leaves ctxs from the list of ctxs

30.35.3.25 sc_hypervisor_get_nready_flops_of_all_sons_of_sched_ctx()

Return the nready flops of all ctxs below in hierarchy of sched_ctx

30.35.4 Variable Documentation

```
30.35.4.1 act_hypervisor_mutex
starpu_pthread_mutex_t act_hypervisor_mutex
synchronise the hypervisor when several workers try to update its information
```

30.36 Scheduling Context Hypervisor - Linear Programming

Functions

- double sc_hypervisor_lp_get_nworkers_per_ctx (int nsched_ctxs, int ntypes_of_workers, double res[nsched
 _ctxs][ntypes_of_workers], int total_nw[ntypes_of_workers], struct types_of_workers *tw, unsigned *in_
 sched_ctxs)
- double sc_hypervisor_lp_get_tmax (int nw, int *workers)
- void sc_hypervisor_lp_round_double_to_int (int ns, int nw, double res[ns][nw], int res_rounded[ns][nw])
- void sc_hypervisor_lp_redistribute_resources_in_ctxs (int ns, int nw, int res_rounded[ns][nw], double res[ns][nw], unsigned *sched_ctxs, struct types_of_workers *tw)
- void sc_hypervisor_lp_distribute_resources_in_ctxs (unsigned *sched_ctxs, int ns, int nw, int res_← rounded[ns][nw], double res[ns][nw], int *workers, int nworkers, struct types_of_workers *tw)
- void sc_hypervisor_lp_distribute_floating_no_resources_in_ctxs (unsigned *sched_ctxs, int ns, int nw, double res[ns][nw], int *workers, int nworkers, struct types_of_workers *tw)
- void sc_hypervisor_lp_place_resources_in_ctx (int ns, int nw, double w_in_s[ns][nw], unsigned *sched_ctxs, int *workers, unsigned do size, struct types of workers *tw)
- void sc hypervisor lp share remaining resources (int ns, unsigned *sched ctxs, int nworkers, int *workers)
- double sc_hypervisor_lp_find_tmax (double t1, double t2)
- unsigned sc_hypervisor_lp_execute_dichotomy (int ns, int nw, double w_in_s[ns][nw], unsigned solve_lp_
 integer, void *specific_data, double tmin, double tmax, double smallest_tmax, double(*lp_estimated_distrib
 _func)(int ns, int nw, double draft_w_in_s[ns][nw], unsigned is_integer, double tmax, void *specifc_data))
- double sc_hypervisor_lp_simulate_distrib_flops (int nsched_ctxs, int ntypes_of_workers, double speed[nsched
 _ctxs][ntypes_of_workers], double flops[nsched_ctxs], double res[nsched_ctxs][ntypes_of_workers], int total_nw[ntypes_of_workers], unsigned sched_ctxs[nsched_ctxs], double vmax)
- double sc_hypervisor_lp_simulate_distrib_tasks (int ns, int nw, int nt, double w_in_s[ns][nw], double tasks[nw][nt], double times[nw][nt], unsigned is_integer, double tmax, unsigned *in_sched_ctxs, struct sc hypervisor policy task pool *tmp task pools)
- double sc_hypervisor_lp_simulate_distrib_flops_on_sample (int ns, int nw, double final_w_in_s[ns][nw], unsigned is_integer, double tmax, double **speed, double flops[ns], double **final_flops_on_w)

30.36.1 Detailed Description

30.36.2 Function Documentation

30.36.2.1 sc_hypervisor_lp_get_nworkers_per_ctx()

```
int total_nw[ntypes_of_workers],
struct types_of_workers * tw,
unsigned * in_sched_ctxs )
```

return tmax, and compute in table res the nr of workers needed by each context st the system ends up in the smallest tma

30.36.2.2 sc_hypervisor_lp_get_tmax()

return tmax of the system

30.36.2.3 sc_hypervisor_lp_round_double_to_int()

```
void sc_hypervisor_lp_round_double_to_int (
          int ns,
          int nw,
          double res[ns][nw],
          int res_rounded[ns][nw])
```

the linear programme determins a rational number of ressources for each ctx, we round them depending on the type of ressource

30.36.2.4 sc_hypervisor_lp_redistribute_resources_in_ctxs()

```
void sc_hypervisor_lp_redistribute_resources_in_ctxs (
    int ns,
    int nw,
    int res_rounded[ns][nw],
    double res[ns][nw],
    unsigned * sched_ctxs,
    struct types_of_workers * tw )
```

redistribute the ressource in contexts by assigning the first x available ressources to each one

30.36.2.5 sc_hypervisor_lp_distribute_resources_in_ctxs()

make the first distribution of ressource in contexts by assigning the first x available ressources to each one

30.36.2.6 sc_hypervisor_lp_distribute_floating_no_resources_in_ctxs()

```
void sc_hypervisor_lp_distribute_floating_no_resources_in_ctxs (
    unsigned * sched_ctxs,
    int ns,
    int nw,
    double res[ns][nw],
    int * workers,
    int nworkers,
    struct types_of_workers * tw )
```

make the first distribution of ressource in contexts by assigning the first x available ressources to each one, share not integer no of workers

```
30.36.2.7 sc_hypervisor_lp_place_resources_in_ctx()
```

```
void sc_hypervisor_lp_place_resources_in_ctx (
    int ns,
    int nw,
    double w_in_s[ns][nw],
    unsigned * sched_ctxs,
    int * workers,
    unsigned do_size,
    struct types_of_workers * tw )
```

place resources in contexts dependig on whether they already have workers or not

30.36.2.8 sc_hypervisor_lp_share_remaining_resources()

```
void sc_hypervisor_lp_share_remaining_resources (
    int ns,
    unsigned * sched_ctxs,
    int nworkers,
    int * workers )
```

not used resources are shared between all contexts

30.36.2.9 sc_hypervisor_lp_find_tmax()

```
double sc_hypervisor_lp_find_tmax ( \label{eq:condition} \mbox{double } t1, \\ \mbox{double } t2 \mbox{ )}
```

dichotomy btw t1 & t2

30.36.2.10 sc_hypervisor_lp_execute_dichotomy()

execute the lp trough dichotomy

30.36.2.11 sc_hypervisor_lp_simulate_distrib_flops()

linear program that returns 1/tmax, and computes in table res the nr of workers needed by each context st the system ends up in the smallest tmax

30.36.2.12 sc_hypervisor_lp_simulate_distrib_tasks()

linear program that simulates a distribution of tasks that minimises the execution time of the tasks in the pool

30.36.2.13 sc_hypervisor_lp_simulate_distrib_flops_on_sample()

linear program that simulates a distribution of flops over the workers on particular sample of the execution of the application such that the entire sample would finish in a minimum amount of time

30.37 Modularized Scheduler Interface

Data Structures

- · struct starpu_sched_component
- · struct starpu sched tree
- struct starpu_sched_component_fifo_data
- struct starpu_sched_component_prio_data
- struct starpu_sched_component_mct_data
- struct starpu_sched_component_perfmodel_select_data
- struct starpu_sched_component_specs

Macros

- #define STARPU_SCHED_COMPONENT_IS_HOMOGENEOUS(component)
- #define STARPU_SCHED_COMPONENT_IS_SINGLE_MEMORY_NODE(component)
- #define STARPU_COMPONENT_MUTEX_LOCK(m)
- #define STARPU_COMPONENT_MUTEX_TRYLOCK(m)
- #define STARPU_COMPONENT_MUTEX_UNLOCK(m)

Enumerations

Functions

• void starpu_initialize_prio_center_policy (unsigned sched_ctx_id)

Scheduling Tree API

- struct starpu_sched_tree * starpu_sched_tree_create (unsigned sched_ctx_id) STARPU_ATTRIBUTE_M
 ALLOC
- void starpu_sched_tree_destroy (struct starpu_sched_tree *tree)
- struct starpu_sched_tree * starpu_sched_tree_get (unsigned sched_ctx_id)
- void starpu_sched_tree_update_workers (struct starpu_sched_tree *t)
- void starpu sched tree update workers in ctx (struct starpu sched tree *t)
- int starpu_sched_tree_push_task (struct starpu_task *task)
- struct starpu task * starpu sched tree pop task (unsigned sched ctx)
- int starpu_sched_component_push_task (struct starpu_sched_component *from, struct starpu_sched_
 component *to, struct starpu_task *task)
- struct starpu_task * starpu_sched_component_pull_task (struct starpu_sched_component *from, struct starpu sched component *to)
- struct starpu_task * starpu_sched_component_pump_to (struct starpu_sched_component *component, struct starpu_sched_component *to, int *success)
- struct starpu_task * starpu_sched_component_pump_downstream (struct starpu_sched_component *component, int *success)
- int starpu_sched_component_send_can_push_to_parents (struct starpu_sched_component *component)
- void starpu sched tree add workers (unsigned sched ctx id. int *workerids, unsigned nworkers)
- void starpu sched tree remove workers (unsigned sched ctx id, int *workerids, unsigned nworkers)
- void starpu_sched_component_connect (struct starpu_sched_component *parent, struct starpu_sched_component *child)

Generic Scheduling Component API

- typedef struct starpu_sched_component *(* starpu_sched_component_create_t) (struct starpu_sched
 _tree *tree, void *data)
- struct starpu_sched_component * starpu_sched_component_create (struct starpu_sched_tree *tree, const char *name) STARPU_ATTRIBUTE_MALLOC
- void starpu sched component destroy (struct starpu sched component *component)
- void starpu_sched_component_destroy_rec (struct starpu_sched_component *component)
- void starpu_sched_component_add_child (struct starpu_sched_component *component, struct starpu
 sched_component *child)
- int starpu_sched_component_can_execute_task (struct starpu_sched_component *component, struct starpu_task *task)
- int STARPU_WARN_UNUSED_RESULT starpu_sched_component_execute_preds (struct starpu_sched
 _component *component, struct starpu_task *task, double *length)
- double starpu_sched_component_transfer_length (struct starpu_sched_component *component, struct starpu_task *task)
- void starpu_sched_component_prefetch_on_node (struct starpu_sched_component *component, struct starpu_task *task)

Worker Component API

- struct starpu sched component * starpu sched component worker get (unsigned sched ctx, int workerid)
- struct starpu_sched_component * starpu_sched_component_worker_new (unsigned sched_ctx, int workerid)
- struct starpu_sched_component * starpu_sched_component_parallel_worker_create (struct starpu_sched
 _tree *tree, unsigned nworkers, unsigned *workers)
- int starpu_sched_component_worker_get_workerid (struct starpu_sched_component *worker_component)
- int starpu sched component is worker (struct starpu sched component *component)
- int starpu sched component is simple worker (struct starpu sched component *component)
- int starpu sched component is combined worker (struct starpu sched component *component)
- void starpu sched component worker pre exec hook (struct starpu task *task, unsigned sched ctx id)
- void starpu_sched_component_worker_post_exec_hook (struct starpu_task *task, unsigned sched_ctx_id)

Flow-control Fifo Component API

- int starpu_sched_component_can_push (struct starpu_sched_component *component, struct starpu_← sched component *to)
- int starpu_sched_component_can_pull (struct starpu_sched_component *component)
- int starpu sched component can pull all (struct starpu sched component *component)
- double starpu_sched_component_estimated_load (struct starpu_sched_component *component)
- · double starpu sched component estimated end min (struct starpu sched component *component)
- double starpu_sched_component_estimated_end_min_add (struct starpu_sched_component *component, double exp_len)
- double starpu sched component estimated end average (struct starpu sched component *component)
- struct starpu_sched_component * starpu_sched_component_fifo_create (struct starpu_sched_tree *tree, struct starpu_sched_component_fifo_data *fifo_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_fifo (struct starpu_sched_component *component)

Flow-control Prio Component API

- struct starpu_sched_component * starpu_sched_component_prio_create (struct starpu_sched_tree *tree, struct starpu_sched_component_prio_data *prio_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_prio (struct starpu_sched_component *component)

Resource-mapping Work-Stealing Component API

- struct starpu_sched_component * starpu_sched_component_work_stealing_create (struct starpu_sched_
 tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_work_stealing (struct starpu_sched_component *component)
- int starpu_sched_tree_work_stealing_push_task (struct starpu_task *task)

Resource-mapping Random Component API

- struct starpu_sched_component * starpu_sched_component_random_create (struct starpu_sched_tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_random (struct starpu_sched_component *)

Resource-mapping Eager Component API

- struct starpu_sched_component * starpu_sched_component_eager_create (struct starpu_sched_tree *tree, void *arg) STARPU ATTRIBUTE MALLOC
- int starpu_sched_component_is_eager (struct starpu_sched_component *)

Resource-mapping Eager-Calibration Component API

- struct starpu_sched_component * starpu_sched_component_eager_calibration_create (struct starpu
 _sched_tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_eager_calibration (struct starpu_sched_component *)

Resource-mapping MCT Component API

- struct starpu_sched_component * starpu_sched_component_mct_create (struct starpu_sched_tree *tree, struct starpu_sched_component_mct_data *mct_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_mct (struct starpu_sched_component *component)

Resource-mapping Heft Component API

- struct starpu_sched_component * starpu_sched_component_heft_create (struct starpu_sched_tree *tree, struct starpu_sched_component_mct_data *mct_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_heft (struct starpu_sched_component *component)

Special-purpose Best Implementation Component API

Special-purpose Perfmodel_Select Component API

- struct starpu_sched_component * starpu_sched_component_perfmodel_select_create (struct starpu
 _sched_tree *tree, struct starpu_sched_component_perfmodel_select_data *perfmodel_select_data) ST
 ARPU ATTRIBUTE MALLOC
- int starpu_sched_component_is_perfmodel_select (struct starpu_sched_component *component)

Recipe Component API

- struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe_create (void) STARPU_ATTRIBUTE_MALLOC
- struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe_
 create_singleton (struct starpu_sched_component *(*create_component)(struct starpu_sched_tree *tree,
 void *arg), void *arg) STARPU ATTRIBUTE MALLOC
- void starpu_sched_component_composed_recipe_add (struct starpu_sched_component_composed_recipe *recipe, struct starpu_sched_component *(*create_component)(struct starpu_sched_tree *tree, void *arg), void *arg)
- void starpu_sched_component_composed_recipe_destroy (struct starpu_sched_component_composed_
 recipe *)
- struct starpu_sched_component * starpu_sched_component_composed_component_create (struct starpu
 _sched_tree *tree, struct starpu_sched_component_composed_recipe *recipe) STARPU_ATTRIBUTE_M
 ALLOC
- struct starpu_sched_tree * starpu_sched_component_make_scheduler (unsigned sched_ctx_id, struct starpu_sched_component_specs s)

Basic API

- void starpu_sched_component_initialize_simple_scheduler (starpu_sched_component_create_t create_
 decision_component, void *data, unsigned flags, unsigned sched_ctx_id)
- #define STARPU_SCHED_SIMPLE_DECIDE_MASK
- #define STARPU SCHED SIMPLE DECIDE WORKERS
- #define STARPU_SCHED_SIMPLE_DECIDE_MEMNODES
- #define STARPU SCHED SIMPLE DECIDE ARCHS
- #define STARPU_SCHED_SIMPLE_PERFMODEL
- #define STARPU_SCHED_SIMPLE_IMPL
- #define STARPU_SCHED_SIMPLE_FIFO_ABOVE
- #define STARPU SCHED SIMPLE FIFO ABOVE PRIO
- #define STARPU_SCHED_SIMPLE_FIFOS_BELOW
- #define STARPU_SCHED_SIMPLE_FIFOS_BELOW_PRIO
- #define STARPU SCHED SIMPLE WS BELOW
- #define STARPU SCHED SIMPLE COMBINED WORKERS

30.37.1 Detailed Description

30.37.2 Data Structure Documentation

30.37.2.1 struct starpu_sched_component

Structure for a scheduler module. A scheduler is a tree-like structure of them, some parts of scheduler can be shared by several contexes to perform some local optimisations, so, for all components, a list of parent is defined by sched_ctx_id. They embed there specialised method in a pseudo object-style, so calls are like component->push_task (component, task)

Data Fields

- struct starpu_sched_tree * tree
- struct starpu bitmap * workers
- struct starpu_bitmap * workers_in_ctx
- void * data
- · char * name
- · unsigned nchildren
- struct starpu_sched_component ** children
- · unsigned nparents
- struct starpu_sched_component ** parents
- void(* add child)(struct starpu sched component *component, struct starpu sched component *child)
- void(* remove child)(struct starpu sched component *component, struct starpu sched component *child)
- void(* add_parent)(struct starpu_sched_component *component, struct starpu_sched_component *parent)
- void(* remove_parent)(struct starpu_sched_component *component, struct starpu_sched_component *parent)
- int(* push_task)(struct starpu_sched_component *, struct starpu_task *)
- struct starpu_task *(* pull_task)(struct starpu_sched_component *from, struct starpu_sched_component *to)
- int(* can_push)(struct starpu_sched_component *from, struct starpu_sched_component *to)
- int(* can pull)(struct starpu sched component *component)
- int(* notify)(struct starpu_sched_component *component, int message_ID, void *arg)
- double(* estimated load)(struct starpu sched component *component)
- double(* estimated end)(struct starpu sched component *component)
- void(* deinit data)(struct starpu sched component *component)
- void(* notify_change_workers)(struct starpu_sched_component *component)
- · int properties
- hwloc_obj_t obj

30.37.2.1.1 Field Documentation

vector of component's children

```
30.37.2.1.1.1 tree
struct starpu_sched_tree* starpu_sched_component::tree
The tree containing the component
30 37 2 1 1 2 workers
struct starpu_bitmap* starpu_sched_component::workers
set of underlying workers
30.37.2.1.1.3 workers_in_ctx
struct starpu_bitmap* starpu_sched_component::workers_in_ctx
subset of starpu sched component::workers that is currently available in the context The push method should take
this value into account, it is set with: component->workers UNION tree->workers UNION component->child[i]-
>workers in ctx iff exist x such as component->children[i]->parents[x] == component
30.37.2.1.1.4 data
void* starpu_sched_component::data
private data
30.37.2.1.1.5 nchildren
unsigned starpu_sched_component::nchildren
number of compoments's children
30.37.2.1.1.6 children
struct starpu_sched_component** starpu_sched_component::children
```

```
30.37.2.1.1.7 nparents
```

unsigned starpu_sched_component::nparents

number of component's parents

30.37.2.1.1.8 parents

struct starpu_sched_component** starpu_sched_component::parents

vector of component's parents

30.37.2.1.1.9 add_child

void(* starpu_sched_component::add_child) (struct starpu_sched_component *component, struct
starpu_sched_component *child)

add a child to component

30.37.2.1.1.10 remove_child

void(* starpu_sched_component::remove_child) (struct starpu_sched_component *component, struct
starpu_sched_component *child)

remove a child from component

30.37.2.1.1.11 push_task

int(* starpu_sched_component::push_task) (struct starpu_sched_component *, struct starpu_task
*)

push a task in the scheduler module. this function is called to push a task on component subtree, this can either perform a recursive call on a child or store the task in the component, then it will be returned by a further pull_task call. the caller must ensure that component is able to execute task. This method must either return 0 if it the task was properly stored or passed over to a child component, or return a value different from 0 if the task could not be consumed (e.g. the queue is full).

30.37.2.1.1.12 pull_task

```
struct starpu_task*(* starpu_sched_component::pull_task) (struct starpu_sched_component *from,
struct starpu_sched_component *to)
```

pop a task from the scheduler module. this function is called by workers to get a task from their parents. this function should first return a locally stored task or perform a recursive call on the parents. the task returned by this function should be executable by the caller

30.37.2.1.1.13 can push

```
int(* starpu_sched_component::can_push) (struct starpu_sched_component *from, struct starpu_
sched_component *to)
```

This function is called by a component which implements a queue, allowing it to signify to its parents that an empty slot is available in its queue. This should return 1 if some tasks could be pushed The basic implementation of this function is a recursive call to its parents, the user has to specify a personally-made function to catch those calls.

30.37.2.1.1.14 can_pull

```
int(* starpu_sched_component::can_pull) (struct starpu_sched_component *component)
```

This function allow a component to wake up a worker. It is currently called by component which implements a queue, to signify to its children that a task have been pushed in its local queue, and is available to be popped by a worker, for example. This should return 1 if some some container or worker could (or will) pull some tasks. The basic implementation of this function is a recursive call to its children, until at least one worker have been woken up.

30.37.2.1.1.15 estimated load

```
double(* starpu_sched_component::estimated_load) (struct starpu_sched_component *component)
```

heuristic to compute load of scheduler module. Basically the number of tasks divided by the sum of relatives speedup of workers available in context. estimated_load(component) = sum(estimated_load(component_children)) + nb_local_tasks / average(relative_speedup(underlying_worker))

30.37.2.1.1.16 estimated_end

```
double(* starpu_sched_component::estimated_end) (struct starpu_sched_component *component) return the time when a worker will enter in starvation. This function is relevant only if the task->predicted member has been set.
```

30.37.2.1.1.17 deinit_data

void(* starpu_sched_component::deinit_data) (struct starpu_sched_component *component)
called by starpu_sched_component_destroy. Should free data allocated during creation

30.37.2.1.1.18 notify_change_workers

void(* starpu_sched_component::notify_change_workers) (struct starpu_sched_component *component)
this function is called for each component when workers are added or removed from a context

30.37.2.1.1.19 obj

hwloc_obj_t starpu_sched_component::obj

the hwloc object associated to scheduler module. points to the part of topology that is binded to this component, eg: a numa node for a ws component that would balance load between underlying sockets

30.37.2.2 struct starpu_sched_tree

The actual scheduler

Data Fields

| struct starpu_sched_component * | root | entry module of the scheduler |
|---------------------------------|--------------|--|
| struct starpu_bitmap * | workers | set of workers available in this context, this value is used to mask workers in modules |
| unsigned | sched_ctx_id | context id of the scheduler |
| starpu_pthread_mutex_t | lock | lock used to protect the scheduler, it is taken in read mode pushing a task and in write mode for adding or removing workers |

30.37.2.3 struct starpu_sched_component_fifo_data

Data Fields

| unsigned | ntasks_threshold | |
|----------|-------------------|--|
| double | exp_len_threshold | |

30.37.2.4 struct starpu_sched_component_prio_data

Data Fields

| unsigned | ntasks_threshold | |
|----------|-------------------|--|
| double | exp_len_threshold | |

30.37.2.5 struct starpu_sched_component_mct_data

Data Fields

| double | alpha | |
|--------|------------|--|
| double | beta | |
| double | _gamma | |
| double | idle_power | |

30.37.2.6 struct starpu_sched_component_perfmodel_select_data

Data Fields

| struct starpu_sched_component * | calibrator_component | |
|---------------------------------|------------------------|--|
| struct starpu_sched_component * | no_perfmodel_component | |
| struct starpu_sched_component * | perfmodel_component | |

30.37.2.7 struct starpu_sched_component_specs

Define how build a scheduler according to topology. Each level (except for hwloc_machine_composed_sched_ component) can be NULL, then the level is just skipped. Bugs everywhere, do not rely on.

Data Fields

- struct starpu_sched_component_composed_recipe * hwloc_machine_composed_sched_component
- struct starpu_sched_component_composed_recipe * hwloc_component_composed_sched_component
- struct starpu_sched_component_composed_recipe * hwloc_socket_composed_sched_component
- struct starpu_sched_component_composed_recipe * hwloc_cache_composed_sched_component
- struct starpu_sched_component_composed_recipe *(* worker_composed_sched_component)(enum starpu_worker_archtype archtype)
- · int mix heterogeneous workers

30.37.2.7.1 Field Documentation

30.37.2.7.1.1 hwloc_machine_composed_sched_component

 $\verb|struct starpu_sched_component_composed_recipe* starpu_sched_component_specs::hwloc_machine_{\leftarrow} composed_sched_component$

the composed component to put on the top of the scheduler this member must not be \mathtt{NULL} as it is the root of the topology

30.37.2.7.1.2 hwloc_component_composed_sched_component

 $struct \ starpu_sched_component_composed_recipe* \ starpu_sched_component_specs::hwloc_component_ \\ \leftarrow composed_sched_component$

the composed component to put for each memory component

30.37.2.7.1.3 hwloc_socket_composed_sched_component

 $\verb|struct| starpu_sched_component_composed_recipe* starpu_sched_component_specs::hwloc_socket_{\leftarrow} composed_sched_component$

the composed component to put for each socket

30.37.2.7.1.4 hwloc_cache_composed_sched_component

 $struct\ starpu_sched_component_composed_recipe*\ starpu_sched_component_specs::hwloc_cache_{\leftarrow}\ composed_sched_component$

the composed component to put for each cache

30.37.2.7.1.5 worker_composed_sched_component

 $struct\ starpu_sched_component_composed_recipe*(*\ starpu_sched_component_specs::worker_composed \hookleftarrow _sched_component)\ (enum\ starpu_worker_archtype\ archtype)$

a function that return a starpu_sched_component_composed_recipe to put on top of a worker of type archtype. NULL is a valid return value, then no component will be added on top

30.37.2.7.1.6 mix_heterogeneous_workers

int starpu_sched_component_specs::mix_heterogeneous_workers

this flag is a dirty hack because of the poor expressivity of this interface. As example, if you want to build a heft component with a fifo component per numa component, and you also have GPUs, if this flag is set, GPUs will share those fifos. If this flag is not set, a new fifo will be built for each of them (if they have the same starpu_perf_arch and the same numa component it will be shared. it indicates if heterogenous workers should be brothers or cousins, as example, if a gpu and a cpu should share or not there numa node

30.37.3 Macro Definition Documentation

30.37.3.1 STARPU_SCHED_COMPONENT_IS_HOMOGENEOUS

indicate if component is homogeneous

30.37.3.2 STARPU_SCHED_COMPONENT_IS_SINGLE_MEMORY_NODE

indicate if all workers have the same memory component

30.37.3.3 STARPU SCHED SIMPLE DECIDE WORKERS

```
#define STARPU_SCHED_SIMPLE_DECIDE_WORKERS
```

Request to create downstream queues per worker, i.e. the scheduling decision-making component will choose exactly which workers tasks should got to.

30.37.3.4 STARPU_SCHED_SIMPLE_DECIDE_MEMNODES

```
#define STARPU_SCHED_SIMPLE_DECIDE_MEMNODES
```

Request to create downstream queues per memory nodes, i.e. the scheduling decision-making component will choose which memory node tasks will go to.

30.37.3.5 STARPU_SCHED_SIMPLE_DECIDE_ARCHS

```
#define STARPU_SCHED_SIMPLE_DECIDE_ARCHS
```

Request to create downstream queues per computation arch, i.e. the scheduling decision-making component will choose whether tasks go to CPUs, or CUDA, or OpenCL, etc.

30.37.3.6 STARPU_SCHED_SIMPLE_PERFMODEL

```
#define STARPU_SCHED_SIMPLE_PERFMODEL
```

Request to add a perfmodel selector above the scheduling decision-making component. That way, only tasks with a calibrated performance model will be given to the component, other tasks will go to an eager branch that will distributed tasks so that their performance models will get calibrated. In other words, this is needed when using a component which needs performance models for tasks.

30.37.3.7 STARPU_SCHED_SIMPLE_IMPL

```
#define STARPU_SCHED_SIMPLE_IMPL
```

Request that a component be added just above workers, that chooses the best task implementation.

30.37.3.8 STARPU_SCHED_SIMPLE_FIFO_ABOVE

```
#define STARPU_SCHED_SIMPLE_FIFO_ABOVE
```

Request to create a fifo above the scheduling decision-making component, otherwise tasks will be pushed directly to the component.

This is useful to store tasks if there is a fifo below which limits the number of tasks to be scheduld in advance. The scheduling decision-making component can also store tasks itself, in which case this flag is not useful.

30.37.3.9 STARPU_SCHED_SIMPLE_FIFO_ABOVE_PRIO

#define STARPU_SCHED_SIMPLE_FIFO_ABOVE_PRIO

Request that the fifo above be sorted by priorities

30.37.3.10 STARPU_SCHED_SIMPLE_FIFOS_BELOW

```
#define STARPU_SCHED_SIMPLE_FIFOS_BELOW
```

Request to create fifos below the scheduling decision-making component, otherwise tasks will be pulled directly from workers.

This is useful to be able to schedule a (tunable) small number of tasks in advance only.

30.37.3.11 STARPU SCHED SIMPLE FIFOS BELOW PRIO

```
#define STARPU_SCHED_SIMPLE_FIFOS_BELOW_PRIO
```

Request that the fifos below be sorted by priorities

30.37.3.12 STARPU_SCHED_SIMPLE_WS_BELOW

```
#define STARPU_SCHED_SIMPLE_WS_BELOW
```

Request that work between workers using the same fifo below be distributed using a work stealing component.

30.37.3.13 STARPU_SCHED_SIMPLE_COMBINED_WORKERS

```
#define STARPU_SCHED_SIMPLE_COMBINED_WORKERS
```

Request to not only choose between simple workers, but also choose between combined workers.

30.37.4 Enumeration Type Documentation

30.37.4.1 starpu_sched_component_properties

```
enum starpu_sched_component_properties
```

flags for starpu_sched_component::properties

Enumerator

| STARPU_SCHED_COMPONENT_HOMOGENEOUS | indicate that all workers have the same starpu_worker_archtype |
|---|--|
| STARPU_SCHED_COMPONENT_SINGLE_MEM↔ ORY_NODE | indicate that all workers have the same memory component |

30.37.5 Function Documentation

30.37.5.1 starpu_sched_tree_create()

30.37.5.2 starpu_sched_tree_destroy()

destroy tree and free all non shared component in it.

30.37.5.3 starpu_sched_tree_update_workers()

recursively set all starpu_sched_component::workers, do not take into account shared parts (except workers).

(e.g. MCT)

```
30.37.5.4 starpu_sched_tree_update_workers_in_ctx()
void starpu_sched_tree_update_workers_in_ctx (
              struct starpu_sched_tree * t )
recursively set all starpu_sched_component::workers_in_ctx, do not take into account shared parts (except workers)
30.37.5.5 starpu_sched_tree_push_task()
int starpu_sched_tree_push_task (
              struct starpu_task * task )
compatibility with starpu_sched_policy interface
30.37.5.6 starpu_sched_tree_pop_task()
struct starpu_task* starpu_sched_tree_pop_task (
              unsigned sched_ctx )
compatibility with starpu sched policy interface
30.37.5.7 starpu_sched_component_push_task()
int starpu_sched_component_push_task (
             struct starpu_sched_component * from,
             struct starpu_sched_component * to,
              struct starpu_task * task )
Push a task to a component. This is a helper for component->push_task (component, task) plus
tracing.
30.37.5.8 starpu_sched_component_pull_task()
struct starpu_task* starpu_sched_component_pull_task (
              struct starpu_sched_component * from,
              struct starpu_sched_component * to )
Pull a task from a component. This is a helper for component->pull_task (component) plus tracing.
30.37.5.9 starpu_sched_tree_add_workers()
void starpu_sched_tree_add_workers (
             unsigned sched_ctx_id,
              int * workerids,
              unsigned nworkers )
compatibility with starpu_sched_policy interface
30.37.5.10 starpu_sched_tree_remove_workers()
void starpu_sched_tree_remove_workers (
             unsigned sched_ctx_id,
             int * workerids,
              unsigned nworkers )
compatibility with starpu sched policy interface
30.37.5.11 starpu_sched_component_connect()
void starpu_sched_component_connect (
             struct starpu_sched_component * parent,
              struct starpu_sched_component * child )
Attach component child to parent parent. Some component may accept only one child, others accept several
```

30.37.5.12 starpu_sched_component_create()

allocate and initialize component field with defaults values: .pop_task make recursive call on father .estimated — load compute relative speedup and tasks in sub tree .estimated_end return the minimum of recursive call on children .add_child is starpu_sched_component_add_child .remove_child is starpu_sched_component_remove_child .notify_change_workers does nothing .deinit_data does nothing

30.37.5.13 starpu_sched_component_destroy()

free data allocated by starpu_sched_component_create and call component->deinit_data(component) set to NULL the member starpu_sched_component::fathers[sched_ctx_id] of all child if its equal to component

30.37.5.14 starpu_sched_component_destroy_rec()

recursively destroy non shared parts of a component 's tree

30.37.5.15 starpu sched component can execute task()

return true iff component can execute task, this function take into account the workers available in the scheduling context

30.37.5.16 starpu_sched_component_execute_preds()

return a non NULL value if component can execute task. write the execution prediction length for the best implementation of the best worker available and write this at length address. this result is more relevant if starpu_sched_component::is_homogeneous is non NULL. if a worker need to be calibrated for an implementation, nan is set to length.

30.37.5.17 starpu_sched_component_transfer_length()

return the average time to transfer task data to underlying component workers.

30.37.5.18 starpu_sched_component_worker_get()

return the struct starpu_sched_component corresponding to workerid. Undefined if workerid is not a valid workerid

```
30.37.5.19 starpu_sched_component_parallel_worker_create()
struct starpu_sched_component* starpu_sched_component_parallel_worker_create (
                            struct starpu_sched_tree * tree,
                            unsigned nworkers,
                            unsigned * workers )
Create a combined worker that pushes tasks in parallel to workers workers (size nworkers).
30.37.5.20 starpu_sched_component_worker_get_workerid()
int starpu_sched_component_worker_get_workerid (
                            struct starpu_sched_component * worker_component )
return \ the \ workerid \ of \ \verb|worker_component|, \ undefined \ if \ starpu\_sched\_component\_is\_worker(worker\_{\hookleftarrow}) \ and \ 
component) == 0
30.37.5.21 starpu_sched_component_is_worker()
int starpu_sched_component_is_worker (
                            struct starpu_sched_component * component )
return true iff component is a worker component
30.37.5.22 starpu_sched_component_is_simple_worker()
int starpu_sched_component_is_simple_worker (
                            struct starpu_sched_component * component )
return true iff component is a simple worker component
30.37.5.23 starpu_sched_component_is_combined_worker()
int starpu_sched_component_is_combined_worker (
                            struct starpu_sched_component * component )
return true iff component is a combined worker component
30.37.5.24 starpu_sched_component_worker_pre_exec_hook()
void starpu_sched_component_worker_pre_exec_hook (
                            struct starpu_task * task,
                            unsigned sched_ctx_id )
compatibility with starpu_sched_policy interface update predictions for workers
30.37.5.25 starpu_sched_component_worker_post_exec_hook()
void starpu_sched_component_worker_post_exec_hook (
                            struct starpu_task * task,
                            unsigned sched_ctx_id )
compatibility with starpu sched policy interface
30.37.5.26 starpu_sched_component_can_push()
int starpu_sched_component_can_push (
                           struct starpu_sched_component * component,
                            struct starpu_sched_component * to )
default function for the can push component method, just call can push of parents until one of them returns non-
zero
30.37.5.27 starpu_sched_component_can_pull()
int starpu_sched_component_can_pull (
                            struct starpu_sched_component * component )
```

default function for the can_pull component method, just call can_pull of children until one of them returns non-zero

30.37.5.28 starpu_sched_component_can_pull_all()

function for the can pull component method, call can pull of all children

30.37.5.29 starpu_sched_component_estimated_load()

default function for the estimated_load component method, just sum up the loads of the children of the component.

30.37.5.30 starpu_sched_component_estimated_end_min()

function that can be used for the estimated_end component method, compute the minimum completion time of the children.

30.37.5.31 starpu_sched_component_estimated_end_min_add()

function that can be used for the estimated_end component method, compute the minimum completion time of the children, and add to it an estimation of how existing queued work, plus the exp_len work, can be completed. This is typically used instead of starpu_sched_component_estimated_end_min when the component contains a queue of tasks, which thus needs to be added to the estimations.

30.37.5.32 starpu sched component estimated end average()

default function for the estimated end component method, compute the average completion time of the children.

30.37.5.33 starpu_sched_component_fifo_create()

Return a struct starpu_sched_component with a fifo. A stable sort is performed according to tasks priorities. A push_task call on this component does not perform recursive calls, underlying components will have to call pop—task to get it. starpu_sched_component::estimated_end function compute the estimated length by dividing the sequential length by the number of underlying workers.

30.37.5.34 starpu_sched_component_is_fifo()

30.37.5.35 starpu_sched_component_work_stealing_create()

return true iff component is a fifo component

return a component that perform a work stealing scheduling. Tasks are pushed in a round robin way. estimated_end return the average of expected length of fifos, starting at the average of the expected_end of his children. When a worker have to steal a task, it steal a task in a round robin way, and get the last pushed task of the higher priority.

```
30.37.5.36 starpu_sched_component_is_work_stealing()
```

return true iff component is a work stealing component

30.37.5.37 starpu_sched_tree_work_stealing_push_task()

undefined if there is no work stealing component in the scheduler. If any, task is pushed in a default way if the caller is the application, and in the caller's fifo if its a worker.

30.37.5.38 starpu_sched_component_random_create()

create a component that perform a random scheduling

30.37.5.39 starpu_sched_component_is_random()

return true iff component is a random component

30.37.5.40 starpu_sched_component_mct_create()

create a component with mct_data paremeters. the mct component doesnt do anything but pushing tasks on no
_perf_model_component and calibrating_component

30.37.5.41 starpu_sched_component_best_implementation_create()

Select the implementation that offer the shortest computation length for the first worker that can execute the task. Or an implementation that need to be calibrated. Also set starpu_task::predicted_documents-transfer for memory component of the first suitable workerid. If starpu_task::predicted_documents-transfer and starpu_sched_component::push method is called <a href="starpu_sched_component::push method::push method::push method::push method::push method::push method::push method

30.37.5.42 starpu sched component composed recipe create()

```
struct\ starpu\_sched\_component\_composed\_recipe*\ starpu\_sched\_component\_composed\_recipe\_create\ ( void\ )
```

return an empty recipe for a composed component, it should not be used without modification

30.37.5.43 starpu_sched_component_composed_recipe_create_singleton()

```
create_component,
             void * arg )
return a recipe to build a composed component with a create_component
30.37.5.44 starpu_sched_component_composed_recipe_add()
void starpu_sched_component_composed_recipe_add (
             struct starpu_sched_component_composed_recipe * recipe,
             struct starpu_sched_component *(*) (struct starpu_sched_tree *tree, void *arg)
create_component,
             void * arg )
add create_component under all previous components in recipe
30.37.5.45 starpu_sched_component_composed_recipe_destroy()
void starpu_sched_component_composed_recipe_destroy (
             \verb|struct starpu_sched_component_composed_recipe * | | | | |
destroy composed_sched_component, this should be done after starpu_sched_component_composed_←
component create was called
30.37.5.46 starpu_sched_component_composed_component_create()
```

create a component that behave as all component of recipe where linked. Except that you cant use starpu_ contain a single create_foo arg_foo pair, create_foo(arg_foo) is returned instead of a composed component

30.37.5.47 starpu_sched_component_make_scheduler()

build a scheduler for sched_ctx_id according to s and the hwloc topology of the machine.

30.37.5.48 starpu_sched_component_initialize_simple_scheduler()

Create a simple modular scheduler tree around a scheduling decision-making component component. The details of what should be built around component is described by flags. The different STARPU_SCHED_SIMPL_D \leftarrow ECIDE_* flags are mutually exclusive. data is passed to the create_decision_component function when creating the decision component.

30.38 Clustering Machine

Macros

- #define STARPU CLUSTER MIN NB
- #define STARPU_CLUSTER_MAX_NB
- #define STARPU CLUSTER NB
- #define STARPU CLUSTER PREFERE MIN
- #define STARPU CLUSTER KEEP HOMOGENEOUS
- #define STARPU_CLUSTER_POLICY_NAME

- #define STARPU_CLUSTER_POLICY_STRUCT
- #define STARPU_CLUSTER_CREATE_FUNC
- #define STARPU CLUSTER CREATE FUNC ARG
- #define STARPU CLUSTER TYPE
- #define STARPU CLUSTER AWAKE WORKERS
- #define STARPU_CLUSTER_PARTITION_ONE
- #define STARPU CLUSTER NEW
- #define STARPU CLUSTER NCORES
- · #define starpu intel openmp mkl prologue

Enumerations

enum starpu_cluster_types { STARPU_CLUSTER_OPENMP, STARPU_CLUSTER_INTEL_OPENMP_M

KL, STARPU_CLUSTER_GNU_OPENMP_MKL }

Functions

- struct starpu_cluster_machine * starpu_cluster_machine (hwloc_obj_type_t cluster_level,...)
- int starpu_uncluster_machine (struct starpu_cluster_machine *clusters)
- int starpu_cluster_print (struct starpu_cluster_machine *clusters)
- void starpu_openmp_prologue (void *)
- void starpu_gnu_openmp_mkl_prologue (void *)

30.38.1 Detailed Description

30.38.2 Enumeration Type Documentation

30.38.2.1 starpu_cluster_types

enum starpu_cluster_types

These represent the default available functions to enforce cluster use by the sub-runtime

Enumerator

| STARPU_CLUSTER_OPENMP | todo |
|---------------------------------|------|
| STARPU_CLUSTER_INTEL_OPENMP_MKL | todo |
| STARPU_CLUSTER_GNU_OPENMP_MKL | todo |

30.39 Interoperability Support

This section describes the interface supplied by StarPU to interoperate with other runtime systems.

Typedefs

- typedef int starpurm_drs_ret_t
- typedef void * starpurm_drs_desc_t
- typedef void * starpurm drs cbs t
- typedef void(* starpurm drs cb t) (void *)
- typedef void * starpurm_block_cond_t
- typedef int(* starpurm_polling_t) (void *)

Enumerations

 enum e_starpurm_drs_ret { starpurm_DRS_SUCCESS, starpurm_DRS_DISABLD, starpurm_DRS_PERM, starpurm_DRS_EINVAL }

Initialisation

- void starpurm_initialize_with_cpuset (hwloc_cpuset_t initially_owned cpuset)
- · void starpurm initialize (void)
- void starpurm_shutdown (void)

Spawn

- void starpurm spawn kernel on cpus (void *data, void(*f)(void *), void *args, hwloc cpuset t cpuset)
- void starpurm_spawn_kernel_on_cpus_callback (void *data, void(*f)(void *), void *args, hwloc_cpuset_
 t cpuset, void(*cb f)(void *), void *cb args)
- void starpurm_spawn_kernel_callback (void *data, void(*f)(void *), void *args, void(*cb_f)(void *), void *cb_args)

DynamicResourceSharing

- starpurm_drs_ret_t starpurm_set_drs_enable (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_set_drs_disable (starpurm_drs_desc_t *spd)
- int starpurm_drs_enabled_p (void)
- starpurm_drs_ret_t starpurm_set_max_parallelism (starpurm_drs_desc_t *spd, int max)
- starpurm drs ret t starpurm assign cpu to starpu (starpurm drs desc t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_assign_cpus_to_starpu (starpurm_drs_desc_t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_assign_cpu_mask_to_starpu (starpurm_drs_desc_t *spd, const hwloc_
 cpuset_t mask)
- starpurm_drs_ret_t starpurm_assign_all_cpus_to_starpu (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_withdraw_cpu_from_starpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm drs ret t starpurm withdraw cpus from starpu (starpurm drs desc t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_withdraw_all_cpus_from_starpu (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_lend (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_lend_cpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_lend_cpus (starpurm_drs_desc_t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_lend_cpu_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm_drs_ret_t starpurm_reclaim (starpurm_drs_desc_t *spd)
- starpurm drs ret t starpurm reclaim cpu (starpurm drs desc t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_reclaim_cpus (starpurm_drs_desc_t *spd, int ncpus)
- starpurm drs ret t starpurm reclaim cpu mask (starpurm drs desc t *spd, const hwloc cpuset t mask)
- starpurm_drs_ret_t starpurm_acquire (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_acquire_cpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_acquire_cpus (starpurm_drs_desc_t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_acquire_cpu_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm_drs_ret_t starpurm_return_all (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_return_cpu (starpurm_drs_desc_t *spd, int cpuid)

Devices

- int starpurm_get_device_type_id (const char *type_str)
- const char * starpurm_get_device_type_name (int type_id)
- int starpurm get nb devices by type (int type id)
- int starpurm_get_device_id (int type_id, int device_rank)
- starpurm_drs_ret_t starpurm_assign_device_to_starpu (starpurm_drs_desc_t *spd, int type_id, int unit_
 rank)
- starpurm_drs_ret_t starpurm_assign_devices_to_starpu (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_assign_device_mask_to_starpu (starpurm_drs_desc_t *spd, const hwloc_
 cpuset t mask)
- starpurm drs ret t starpurm assign all devices to starpu (starpurm drs desc t *spd, int type id)
- starpurm_drs_ret_t starpurm_withdraw_device_from_starpu (starpurm_drs_desc_t *spd, int type_id, int unit rank)
- starpurm_drs_ret_t starpurm_withdraw_devices_from_starpu (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_withdraw_device_mask_from_starpu (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm_drs_ret_t starpurm_withdraw_all_devices_from_starpu (starpurm_drs_desc_t *spd, int type_id)
- starpurm drs ret t starpurm lend device (starpurm drs desc t *spd, int type id, int unit rank)
- starpurm_drs_ret_t starpurm_lend_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_lend_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm_drs_ret_t starpurm_lend_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm_drs_ret_t starpurm_reclaim_device (starpurm_drs_desc_t *spd, int type_id, int unit_rank)
- starpurm_drs_ret_t starpurm_reclaim_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_reclaim_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm drs ret t starpurm reclaim all devices (starpurm drs desc t *spd, int type id)
- starpurm_drs_ret_t starpurm_acquire_device (starpurm_drs_desc_t *spd, int type_id, int unit_rank)
- starpurm_drs_ret_t starpurm_acquire_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_acquire_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm_drs_ret_t starpurm_acquire_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm drs ret t starpurm return all devices (starpurm drs desc t *spd, int type id)
- starpurm drs ret t starpurm return device (starpurm drs desc t *spd, int type id, int unit rank)

CpusetsQueries

- hwloc cpuset t starpurm get device worker cpuset (int type id, int unit rank)
- hwloc cpuset t starpurm get global cpuset (void)
- hwloc_cpuset_t starpurm_get_selected_cpuset (void)
- · hwloc cpuset t starpurm get all cpu workers cpuset (void)
- hwloc cpuset t starpurm get all device workers cpuset (void)
- hwloc_cpuset_t starpurm_get_all_device_workers_cpuset_by_type (int typeid)

30.39.1 Detailed Description

This section describes the interface supplied by StarPU to interoperate with other runtime systems.

30.39.2 Enumeration Type Documentation

30.39.2.1 e_starpurm_drs_ret

enum e_starpurm_drs_ret

StarPU Resource Manager return type.

Enumerator

| starpurm_DRS_SUCCESS | Dynamic resource sharing operation succeeded. |
|----------------------|---|
| starpurm_DRS_DISABLD | Dynamic resource sharing is disabled. |
| starpurm_DRS_PERM | Dynamic resource sharing operation is not authorized or implemented. |
| starpurm_DRS_EINVAL | Dynamic resource sharing operation has been called with one or more invalid |
| | parameters. |

30.39.3 Function Documentation

Initialize StarPU and the StarPU-RM resource management module. The starpu_init() function should not have been called before the call to starpurm_initialize(). The starpurm_initialize() function will take care of this

```
30.39.3.3 starpurm_shutdown()
```

void)

Shutdown StarPU-RM and StarPU. The starpu_shutdown() function should not be called before. The starpurm_\circ
shutdown() function will take care of this.

30.39.3.4 starpurm_spawn_kernel_on_cpus()

Allocate a temporary context spanning the units selected in the cpuset bitmap, set it as the default context for the current thread, and call user function f. Upon the return of user function f, the temporary context is freed and the previous default context for the current thread is restored.

30.39.3.5 starpurm_spawn_kernel_on_cpus_callback()

Spawn a POSIX thread and returns immediately. The thread spawned will allocate a temporary context spanning the units selected in the cpuset bitmap, set it as the default context for the current thread, and call user function f. Upon the return of user function f, the temporary context will be freed and the previous default context for the current thread restored. A user specified callback cb_f will be called just before the termination of the thread.

30.39.3.6 starpurm_set_drs_enable()

```
starpurm_drs_ret_t starpurm_set_drs_enable (
    starpurm_drs_desc_t * spd )
```

Turn-on dynamic resource sharing support.

30.39.3.7 starpurm_set_drs_disable()

Turn-off dynamic resource sharing support.

30.39.3.8 starpurm_drs_enabled_p()

Return the state of the dynamic resource sharing support (=!0 enabled, =0 disabled).

30.39.3.9 starpurm_set_max_parallelism()

Set the maximum number of CPU computing units available for StarPU computations to max. This number cannot exceed the maximum number of StarPU's CPU worker allocated at start-up time.

30.39.3.10 starpurm_assign_cpu_to_starpu()

Extend StarPU's default scheduling context to execute tasks on worker corresponding to logical unit cpuid. If StarPU does not have a worker thread initialized for logical unit cpuid, do nothing.

30.39.3.11 starpurm_assign_cpus_to_starpu()

Extend StarPU's default scheduling context to execute tasks on nepus more workers, up to the number of StarPU worker threads initialized.

30.39.3.12 starpurm_assign_cpu_mask_to_starpu()

Extend StarPU's default scheduling context to execute tasks on the additional logical units selected in mask. Logical units of mask for which no StarPU worker is initialized are silently ignored.

30.39.3.13 starpurm_assign_all_cpus_to_starpu()

Set StarPU's default scheduling context to execute tasks on all available logical units for which a StarPU worker has been initialized.

```
30.39.3.14 starpurm_withdraw_cpu_from_starpu()
```

Shrink StarPU's default scheduling context so as to not execute tasks on worker corresponding to logical unit cpuid. If StarPU does not have a worker thread initialized for logical unit cpuid, do nothing.

30.39.3.15 starpurm_withdraw_cpus_from_starpu()

Shrink StarPU's default scheduling context to execute tasks on ncpus less workers.

30.39.3.16 starpurm_withdraw_cpu_mask_from_starpu()

Shrink StarPU's default scheduling context so as to not execute tasks on the logical units selected in mask. Logical units of mask for which no StarPU worker is initialized are silently ignored.

30.39.3.17 starpurm_withdraw_all_cpus_from_starpu()

Shrink StarPU's default scheduling context so as to remove all logical units.

30.39.3.18 starpurm_lend()

30.39.3.19 starpurm_lend_cpu()

Synonym for starpurm_assign_cpu_to_starpu().

30.39.3.20 starpurm_lend_cpus()

Synonym for starpurm_assign_cpus_to_starpu().

30.39.3.21 starpurm_lend_cpu_mask()

Synonym for starpurm_assign_cpu_mask_to_starpu().

30.39.3.22 starpurm_reclaim()

Synonym for starpurm_withdraw_all_cpus_from_starpu().

```
30.39.3.23 starpurm_reclaim_cpu()
starpurm_drs_ret_t starpurm_reclaim_cpu (
             starpurm_drs_desc_t * spd,
             int cpuid )
Synonym for starpurm_withdraw_cpu_from_starpu().
30.39.3.24 starpurm_reclaim_cpus()
starpurm_drs_ret_t starpurm_reclaim_cpus (
             starpurm_drs_desc_t * spd,
             int ncpus )
Synonym for starpurm_withdraw_cpus_from_starpu().
30.39.3.25 starpurm_reclaim_cpu_mask()
starpurm_drs_ret_t starpurm_reclaim_cpu_mask (
             starpurm_drs_desc_t * spd,
             const hwloc_cpuset_t mask )
Synonym for starpurm_withdraw_cpu_mask_from_starpu().
30.39.3.26 starpurm acquire()
starpurm_drs_ret_t starpurm_acquire (
             starpurm_drs_desc_t * spd )
Synonym for starpurm_withdraw_all_cpus_from_starpu().
30.39.3.27 starpurm_acquire_cpu()
starpurm_drs_ret_t starpurm_acquire_cpu (
             starpurm_drs_desc_t * spd,
             int cpuid )
Synonym for starpurm_withdraw_cpu_from_starpu().
30.39.3.28 starpurm_acquire_cpus()
starpurm_drs_ret_t starpurm_acquire_cpus (
             starpurm_drs_desc_t * spd,
             int ncpus )
Synonym for starpurm_withdraw_cpus_from_starpu().
30.39.3.29 starpurm_acquire_cpu_mask()
starpurm_drs_ret_t starpurm_acquire_cpu_mask (
             starpurm_drs_desc_t * spd,
             const hwloc_cpuset_t mask )
Synonym for starpurm_withdraw_cpu_mask_from_starpu().
30.39.3.30 starpurm_return_all()
starpurm_drs_ret_t starpurm_return_all (
             starpurm_drs_desc_t * spd )
Synonym for starpurm_assign_all_cpus_to_starpu().
```

```
30.39.3.31 starpurm_return_cpu()
```

Synonym for starpurm_assign_cpu_to_starpu().

30.39.3.32 starpurm_get_device_type_id()

Return the device type ID constant associated to the device type name. Valid names for type_str are:

- "cpu": regular CPU unit;
- "opencl": OpenCL device unit;
- "cuda": nVidia CUDA device unit;
- "mic": Intel KNC type device unit.

30.39.3.33 starpurm_get_device_type_name()

Return the device type name associated to the device type ID constant.

30.39.3.34 starpurm_get_nb_devices_by_type()

Return the number of initialized StarPU worker for the device type type_id.

30.39.3.35 starpurm_get_device_id()

Return the unique ID assigned to the device_rank nth device of type type_id.

30.39.3.36 starpurm_assign_device_to_starpu()

Extend StarPU's default scheduling context to use unit_rank nth device of type type_id.

30.39.3.37 starpurm_assign_devices_to_starpu()

Extend StarPU's default scheduling context to use ndevices more devices of type type_id, up to the number of StarPU workers initialized for such device type.

30.39.3.38 starpurm_assign_device_mask_to_starpu()

Extend StarPU's default scheduling context to use additional devices as designated by their corresponding StarPU worker thread(s) CPU-set mask.

30.39.3.39 starpurm_assign_all_devices_to_starpu()

Extend StarPU's default scheduling context to use all devices of type type_id for which it has a worker thread initialized.

30.39.3.40 starpurm withdraw device from starpu()

Shrink StarPU's default scheduling context to not use unit_rank nth device of type type_id.

30.39.3.41 starpurm_withdraw_devices_from_starpu()

Shrink StarPU's default scheduling context to use ndevices less devices of type type_id.

30.39.3.42 starpurm_withdraw_device_mask_from_starpu()

Shrink StarPU's default scheduling context to not use devices designated by their corresponding StarPU worker thread(s) CPU-set mask.

30.39.3.43 starpurm_withdraw_all_devices_from_starpu()

Shrink StarPU's default scheduling context to use no devices of type type_id.

30.39.3.44 starpurm_lend_device()

Synonym for starpurm_assign_device_to_starpu().

30.39.3.45 starpurm_lend_devices()

```
int type_id,
              int ndevices )
Synonym for starpurm_assign_devices_to_starpu().
30.39.3.46 starpurm_lend_device_mask()
starpurm_drs_ret_t starpurm_lend_device_mask (
              starpurm_drs_desc_t * spd,
              const hwloc\_cpuset\_t\ mask )
Synonym for starpurm_assign_device_mask_to_starpu().
30.39.3.47 starpurm_lend_all_devices()
starpurm_drs_ret_t starpurm_lend_all_devices (
              starpurm_drs_desc_t * spd,
              int type_id )
Synonym for starpurm_assign_all_devices_to_starpu().
30.39.3.48 starpurm_reclaim_device()
starpurm_drs_ret_t starpurm_reclaim_device (
              starpurm_drs_desc_t * spd,
              int type_id,
              int unit_rank )
Synonym for starpurm_withdraw_device_from_starpu().
30.39.3.49 starpurm_reclaim_devices()
starpurm\_drs\_ret\_t starpurm\_reclaim\_devices (
             starpurm_drs_desc_t * spd,
              int type_id,
              int ndevices )
Synonym for starpurm_withdraw_devices_from_starpu().
30.39.3.50 starpurm_reclaim_device_mask()
starpurm\_drs\_ret\_t starpurm\_reclaim\_device\_mask (
             starpurm_drs_desc_t * spd,
              const hwloc_cpuset_t mask )
Synonym for starpurm_withdraw_device_mask_from_starpu().
30.39.3.51 starpurm_reclaim_all_devices()
starpurm_drs_ret_t starpurm_reclaim_all_devices (
             starpurm_drs_desc_t * spd,
              int type_id )
Synonym for starpurm_withdraw_all_devices_from_starpu().
30.39.3.52 starpurm_acquire_device()
starpurm_drs_ret_t starpurm_acquire_device (
              starpurm_drs_desc_t * spd,
              int type_id,
              int unit_rank )
Synonym for starpurm_withdraw_device_from_starpu().
```

```
30.39.3.53 starpurm_acquire_devices()
starpurm_drs_ret_t starpurm_acquire_devices (
              starpurm_drs_desc_t * spd,
              int type_id,
              int ndevices )
Synonym for starpurm_withdraw_devices_from_starpu().
30.39.3.54 starpurm_acquire_device_mask()
starpurm_drs_ret_t starpurm_acquire_device_mask (
             starpurm_drs_desc_t * spd,
              const hwloc_cpuset_t mask )
Synonym for starpurm withdraw device mask from starpu().
30.39.3.55 starpurm_acquire_all_devices()
starpurm_drs_ret_t starpurm_acquire_all_devices (
              starpurm_drs_desc_t * spd,
              int type_id )
Synonym for starpurm_withdraw_all_devices_from_starpu().
30.39.3.56 starpurm_return_all_devices()
starpurm_drs_ret_t starpurm_return_all_devices (
             starpurm_drs_desc_t * spd,
              int type_id )
Synonym for starpurm_assign_all_devices_to_starpu().
30.39.3.57 starpurm_return_device()
starpurm_drs_ret_t starpurm_return_device (
             starpurm_drs_desc_t * spd,
              int type_id,
              int unit_rank )
Synonym for starpurm_assign_device_to_starpu().
30.39.3.58 starpurm_get_device_worker_cpuset()
hwloc_cpuset_t starpurm_get_device_worker_cpuset (
              int type_id,
              int unit_rank )
Return the CPU-set of the StarPU worker associated to the unit_rank nth unit of type type_id.
30.39.3.59 starpurm_get_global_cpuset()
\verb|hwloc_cpuset_t starpurm_get_global_cpuset| (
Return the cumulated CPU-set of all StarPU worker threads.
30.39.3.60 starpurm_get_selected_cpuset()
hwloc_cpuset_t starpurm_get_selected_cpuset (
              void )
Return the CPU-set of the StarPU worker threads currently selected in the default StarPU's scheduling context.
30.39.3.61 starpurm_get_all_cpu_workers_cpuset()
hwloc_cpuset_t starpurm_get_all_cpu_workers_cpuset (
              void )
```

Return the cumulated CPU-set of all CPU StarPU worker threads.

```
30.39.3.62 starpurm_get_all_device_workers_cpuset()
```

```
\label{loc_cpuset_t} \mbox{hwloc\_cpuset\_t starpurm\_get\_all\_device\_workers\_cpuset (} \mbox{ void )}
```

Return the cumulated CPU-set of all "non-CPU" StarPU worker threads.

30.39.3.63 starpurm_get_all_device_workers_cpuset_by_type()

Return the cumulated CPU-set of all StarPU worker threads for devices of type typeid.

Chapter 31

File Index

31.1 File List

| He | e is a list of all documented files with brief descriptions: | |
|----|--|-----|
| | sc_hypervisor.h | |
| | sc_hypervisor_config.h | 495 |
| | sc_hypervisor_lp.h | |
| | sc_hypervisor_monitoring.h | |
| | sc_hypervisor_policy.h | |
| | starpu.h | |
| | starpu_bitmap.h | |
| | starpu_bound.h | |
| | starpu_clusters.h | |
| | starpu_config.h | |
| | starpu_cublas.h | |
| | starpu_cuda.h | |
| | starpu_cusparse.h | |
| | starpu_data.h | |
| | starpu_data_filters.h | |
| | starpu_data_interfaces.h | |
| | starpu_deprecated_api.h | |
| | starpu_disk.h | |
| | starpu_driver.h | |
| | starpu_expert.h | |
| | starpu_fxt.h | |
| | starpu_hash.h | |
| | starpu_helper.h | |
| | starpu_mic.h | |
| | starpu_mod.f90 | |
| | starpu_mpi.h | |
| | starpu_mpi_lb.h | |
| | starpu_opencl.h | |
| | starpu_openmp.h | |
| | starpu_perfmodel.h | |
| | starpu_profiling.h | |
| | starpu_rand.h | |
| | starpu_sched_component.h | |
| | starpu_sched_ctx.h | |
| | starpu_sched_ctx_hypervisor.h | |
| | starpu_scheduler.h | |
| | starpu_simgrid_wrap.h | |
| | starpu_sink.h | |
| | starpu_stdlib.h | 481 |
| | | |

448 File Index

| starpu_task_bundle.h | | | | | | | | | | | | | | | | | | | | | 484 |
|------------------------|--|--|--|--|--|--|--|--|--|------|--|--|--|------|--|--|--|--|--|--|-----|
| starpu_task_dep.h . | | | | | | | | | | | | | | | | | | | | | ?? |
| starpu_task_list.h | | | | | | | | | | | | | | | | | | | | | 484 |
| starpu_task_util.h | | | | | | | | | | | | | | | | | | | | | 485 |
| starpu_thread.h | | | | | | | | | | | | | | | | | | | | | 486 |
| starpu_thread_util.h . | | | | | | | | | | | | | | | | | | | | | 489 |
| starpu_tree.h | | | | | | | | | | | | | | | | | | | | | 490 |
| starpu_util.h | | | | | | | | | | | | | | | | | | | | | 490 |
| starpu_worker.h | | | | | | | | | | | | | | | | | | | | | |
| starpufft.h | | | | | | | | | | | | | | | | | | | | | 493 |
| ctarourm b | | | | | | | | | | | | | | | | | | | | | FOR |

Chapter 32

File Documentation

32.1 starpu.h File Reference

```
#include <stdlib.h>
#include <stdint.h>
#include <starpu_config.h>
#include <starpu_opencl.h>
#include <starpu_thread.h>
#include <starpu_thread_util.h>
#include <starpu_util.h>
#include <starpu_data.h>
#include <starpu_helper.h>
#include <starpu_disk.h>
#include <starpu_data_interfaces.h>
#include <starpu_data_filters.h>
#include <starpu_stdlib.h>
#include <starpu_task_bundle.h>
#include <starpu_task_dep.h>
#include <starpu_task.h>
#include <starpu worker.h>
#include <starpu_perfmodel.h>
#include <starpu_task_list.h>
#include <starpu_task_util.h>
#include <starpu scheduler.h>
#include <starpu_sched_ctx.h>
#include <starpu_expert.h>
#include <starpu_rand.h>
#include <starpu_cuda.h>
#include <starpu_cublas.h>
#include <starpu_cusparse.h>
#include <starpu_bound.h>
#include <starpu_hash.h>
#include <starpu_profiling.h>
#include <starpu_fxt.h>
#include <starpu_driver.h>
#include <starpu_tree.h>
#include <starpu_openmp.h>
#include <starpu_simgrid_wrap.h>
#include <starpu_bitmap.h>
#include <starpu_clusters.h>
#include "starpu_deprecated_api.h"
```

450 File Documentation

Data Structures

· struct starpu conf

Macros

• #define STARPU_THREAD_ACTIVE

Functions

- int starpu_conf_init (struct starpu_conf *conf)
- int starpu_init (struct starpu_conf *conf) STARPU_WARN_UNUSED_RESULT
- int starpu_initialize (struct starpu_conf *user_conf, int *argc, char ***argv)
- · int starpu is initialized (void)
- · void starpu wait initialized (void)
- void starpu_shutdown (void)
- void starpu pause (void)
- · void starpu_resume (void)
- unsigned starpu_get_next_bindid (unsigned flags, unsigned *preferred, unsigned npreferred)
- int starpu_bind_thread_on (int cpuid, unsigned flags, const char *name)
- void starpu topology print (FILE *f)
- int starpu_asynchronous_copy_disabled (void)
- · int starpu asynchronous cuda copy disabled (void)
- int starpu_asynchronous_opencl_copy_disabled (void)
- · int starpu asynchronous mic copy disabled (void)
- int starpu_asynchronous_mpi_ms_copy_disabled (void)
- void starpu_display_stats (void)
- void starpu get version (int *major, int *minor, int *release)

32.2 starpu_bitmap.h File Reference

Functions

- struct starpu_bitmap * starpu_bitmap_create (void) STARPU_ATTRIBUTE_MALLOC
- void starpu_bitmap_destroy (struct starpu_bitmap *b)
- void starpu bitmap set (struct starpu bitmap *b, int e)
- void starpu bitmap unset (struct starpu bitmap *b, int e)
- void starpu bitmap unset all (struct starpu bitmap *b)
- int starpu_bitmap_get (struct starpu_bitmap *b, int e)
- void starpu bitmap unset and (struct starpu bitmap *a, struct starpu bitmap *b, struct starpu bitmap *c)
- void starpu_bitmap_or (struct starpu_bitmap *a, struct starpu_bitmap *b)
- int starpu_bitmap_and_get (struct starpu_bitmap *b1, struct starpu_bitmap *b2, int e)
- int starpu_bitmap_cardinal (struct starpu_bitmap *b)
- int starpu bitmap first (struct starpu bitmap *b)
- int starpu_bitmap_last (struct starpu_bitmap *b)
- int starpu_bitmap_next (struct starpu_bitmap *b, int e)
- int starpu_bitmap_has_next (struct starpu_bitmap *b, int e)

32.3 starpu_bound.h File Reference

#include <stdio.h>

Functions

- · void starpu_bound_start (int deps, int prio)
- void starpu_bound_stop (void)
- void starpu_bound_print_dot (FILE *output)
- void starpu bound compute (double *res, double *integer res, int integer)
- void starpu_bound_print_lp (FILE *output)
- void starpu_bound_print_mps (FILE *output)
- · void starpu_bound_print (FILE *output, int integer)

32.4 starpu_clusters.h File Reference

```
#include <starpu_config.h>
#include <hwloc.h>
```

Macros

- #define STARPU_CLUSTER_MIN_NB
- #define STARPU CLUSTER MAX NB
- #define STARPU_CLUSTER_NB
- #define STARPU_CLUSTER_PREFERE_MIN
- #define STARPU_CLUSTER_KEEP_HOMOGENEOUS
- #define STARPU CLUSTER POLICY NAME
- #define STARPU CLUSTER POLICY STRUCT
- #define STARPU_CLUSTER_CREATE_FUNC
- #define STARPU CLUSTER CREATE FUNC ARG
- #define STARPU_CLUSTER_TYPE
- #define STARPU_CLUSTER_AWAKE_WORKERS
- #define STARPU_CLUSTER_PARTITION_ONE
- #define STARPU_CLUSTER_NEW
- #define STARPU_CLUSTER_NCORES
- · #define starpu intel openmp mkl prologue

Enumerations

enum starpu_cluster_types { STARPU_CLUSTER_OPENMP, STARPU_CLUSTER_INTEL_OPENMP_M
 KL, STARPU_CLUSTER_GNU_OPENMP_MKL }

Functions

- struct starpu_cluster_machine * starpu_cluster_machine (hwloc_obj_type_t cluster_level,...)
- int starpu uncluster machine (struct starpu cluster machine *clusters)
- int starpu_cluster_print (struct starpu_cluster_machine *clusters)
- void starpu_openmp_prologue (void *)
- void starpu_gnu_openmp_mkl_prologue (void *)

32.5 starpu_config.h File Reference

#include <sys/types.h>

452 File Documentation

Macros

- #define STARPU MAJOR VERSION
- #define STARPU MINOR VERSION
- #define STARPU RELEASE VERSION
- #define STARPU USE CPU
- #define STARPU_USE_CUDA
- #define STARPU_USE_OPENCL
- #define STARPU USE MIC
- #define STARPU OPENMP
- #define STARPU CLUSTER
- #define STARPU_SIMGRID
- #define STARPU SIMGRID MC
- #define STARPU SIMGRID HAVE XBT BARRIER INIT
- #define STARPU HAVE SIMGRID MSG H
- · #define STARPU HAVE XBT SYNCHRO H
- #define STARPU_HAVE_VALGRIND_H
- #define STARPU HAVE MEMCHECK H
- #define STARPU VALGRIND FULL
- #define STARPU SANITIZE LEAK
- · #define STARPU NON BLOCKING DRIVERS
- #define STARPU_WORKER_CALLBACKS
- #define STARPU_HAVE_ICC
- #define STARPU USE MPI
- · #define STARPU USE MPI MPI
- · #define STARPU USE MPI NMAD
- #define STARPU_ATLAS
- #define STARPU_GOTO
- #define STARPU OPENBLAS
- · #define STARPU MKL
- #define STARPU ARMPL
- #define STARPU SYSTEM BLAS
- #define STARPU_OPENCL_DATADIR
- #define STARPU HAVE MAGMA
- #define STARPU OPENGL RENDER
- #define STARPU_USE_GTK
- #define STARPU_HAVE_X11
- #define STARPU_HAVE_POSIX_MEMALIGN
- #define STARPU_HAVE_MEMALIGN
- #define STARPU_HAVE_MALLOC_H
- #define STARPU_HAVE_SYNC_BOOL_COMPARE_AND_SWAP
- #define STARPU_HAVE_SYNC_VAL_COMPARE_AND_SWAP
- #define STARPU_HAVE_SYNC_FETCH_AND_ADD
- · #define STARPU HAVE SYNC FETCH AND OR
- #define STARPU HAVE SYNC LOCK TEST AND SET
- #define STARPU HAVE SYNC SYNCHRONIZE
- #define STARPU_DEVEL
- #define STARPU MODEL DEBUG
- #define STARPU_NO_ASSERT
- #define STARPU_DEBUG
- #define STARPU_VERBOSE
- #define STARPU GDB PATH
- #define STARPU_HAVE_FFTW
- #define STARPU HAVE FFTWF
- #define STARPU_HAVE_FFTWL

- #define STARPU HAVE CUFFTDOUBLECOMPLEX
- #define STARPU_HAVE_CURAND
- #define STARPU MAXNODES
- #define STARPU NMAXBUFS
- #define STARPU MAXCPUS
- #define STARPU_MAXNUMANODES
- #define STARPU MAXCUDADEVS
- #define STARPU MAXOPENCLDEVS
- #define STARPU_MAXMICDEVS
- #define STARPU NMAXWORKERS
- #define STARPU NMAX SCHED CTXS
- #define STARPU_MAXIMPLEMENTATIONS
- #define STARPU MAXMPKERNELS
- · #define STARPU USE SC HYPERVISOR
- #define STARPU_SC_HYPERVISOR_DEBUG
- #define STARPU_HAVE_GLPK_H
- #define STARPU_HAVE_CUDA_MEMCPY_PEER
- #define STARPU_HAVE_LIBNUMA
- #define STARPU HAVE WINDOWS
- #define STARPU_LINUX_SYS
- #define STARPU_HAVE_SETENV
- #define STARPU_HAVE_UNSETENV
- #define STARPU HAVE UNISTD H
- #define STARPU HAVE HDF5
- #define STARPU_USE_FXT
- #define STARPU_FXT_LOCK_TRACES
- #define __starpu_func__
- #define starpu inline
- #define STARPU QUICK CHECK
- #define STARPU_LONG_CHECK
- #define STARPU_USE_DRAND48
- #define STARPU USE ERAND48 R
- #define STARPU HAVE NEARBYINTF
- #define STARPU_HAVE_RINTF
- #define STARPU_HAVE_HWLOC
- #define STARPU HAVE PTHREAD SPIN LOCK
- #define STARPU_HAVE_PTHREAD_BARRIER
- #define STARPU_HAVE_PTHREAD_SETNAME_NP
- #define STARPU_HAVE_STRUCT_TIMESPEC
- #define STARPU_HAVE_HELGRIND_H
- #define HAVE_MPI_COMM_F2C
- #define STARPU_HAVE_DARWIN
- #define STARPU_HAVE_CXX11
- #define STARPU_HAVE_STRERROR_R
- #define STARPU_HAVE_STATEMENT_EXPRESSIONS
- #define STARPU_PERF_MODEL_DIR

MPI Master Slave

#define STARPU_USE_MPI_MASTER_SLAVE

Typedefs

typedef ssize_t starpu_ssize_t

454 File Documentation

32.6 starpu_cublas.h File Reference

Functions

- void starpu_cublas_init (void)
- void starpu_cublas_set_stream (void)
- · void starpu cublas shutdown (void)

32.7 starpu_cusparse.h File Reference

```
#include <cusparse.h>
```

Functions

- void starpu_cusparse_init (void)
- void starpu_cusparse_shutdown (void)
- cusparseHandle t starpu cusparse get local handle (void)

32.8 starpu_cuda.h File Reference

```
#include <starpu_config.h>
#include <cuda.h>
#include <cuda_runtime.h>
#include <cuda_runtime_api.h>
```

Macros

- #define STARPU CUBLAS REPORT ERROR(status)
- #define STARPU CUDA REPORT ERROR(status)

Functions

- void starpu_cublas_report_error (const char *func, const char *file, int line, int status)
- void starpu_cuda_report_error (const char *func, const char *file, int line, cudaError_t status)
- · cudaStream t starpu cuda get local stream (void)
- const struct cudaDeviceProp * starpu_cuda_get_device_properties (unsigned workerid)
- int starpu_cuda_copy_async_sync (void *src_ptr, unsigned src_node, void *dst_ptr, unsigned dst_node, size_t ssize, cudaStream_t stream, enum cudaMemcpyKind kind)
- void starpu_cuda_set_device (unsigned devid)

32.9 starpu_data.h File Reference

```
#include <starpu.h>
```

Typedefs

- typedef struct starpu data state * starpu data handle t
- typedef struct starpu_arbiter * starpu_arbiter_t

Enumerations

enum starpu_data_access_mode {
 STARPU_NONE, STARPU_R, STARPU_W, STARPU_RW,
 STARPU_SCRATCH, STARPU_REDUX, STARPU_COMMUTE, STARPU_SSEND,
 STARPU_LOCALITY, STARPU_ACCESS_MODE_MAX }

Functions

- void starpu data set name (starpu data handle t handle, const char *name)
- void starpu data set coordinates array (starpu data handle t handle, int dimensions, int dims[])
- void starpu_data_set_coordinates (starpu_data_handle_t handle, unsigned dimensions,...)
- void starpu_data_unregister (starpu_data_handle_t handle)
- void starpu_data_unregister_no_coherency (starpu_data_handle_t handle)
- void starpu_data_unregister_submit (starpu_data_handle_t handle)
- void starpu data invalidate (starpu data handle t handle)
- void starpu_data_invalidate_submit (starpu_data_handle_t handle)
- void starpu_data_advise_as_important (starpu_data_handle_t handle, unsigned is_important)
- starpu arbiter t starpu arbiter create (void) STARPU ATTRIBUTE MALLOC
- void starpu_data_assign_arbiter (starpu_data_handle_t handle, starpu_arbiter_t arbiter)
- void starpu_arbiter_destroy (starpu_arbiter_t arbiter)
- int starpu_data_request_allocation (starpu_data_handle_t handle, unsigned node)
- int starpu data fetch on node (starpu data handle t handle, unsigned node, unsigned async)
- int starpu_data_prefetch_on_node (starpu_data_handle_t handle, unsigned node, unsigned async)
- int **starpu_data_prefetch_on_node_prio** (starpu_data_handle_t handle, unsigned node, unsigned async, int prio)
- int starpu_data_idle_prefetch_on_node (starpu_data_handle_t handle, unsigned node, unsigned async)
- int **starpu_data_idle_prefetch_on_node_prio** (starpu_data_handle_t handle, unsigned node, unsigned async, int prio)
- unsigned starpu_data_is_on_node (starpu_data_handle_t handle, unsigned node)
- · void starpu data wont use (starpu data handle t handle)
- void starpu_data_set_wt_mask (starpu_data_handle_t handle, uint32_t wt_mask)
- void starpu data set ooc flag (starpu data handle t handle, unsigned flag)
- · unsigned starpu data get ooc flag (starpu data handle t handle)
- void starpu_data_query_status (starpu_data_handle_t handle, int memory_node, int *is_allocated, int *is_valid, int *is_requested)
- void starpu_data_set_reduction_methods (starpu_data_handle_t handle, struct starpu_codelet *redux_cl, struct starpu_codelet *init_cl)
- struct starpu data interface ops * starpu data get interface ops (starpu data handle t handle)
- unsigned starpu_data_test_if_allocated_on_node (starpu_data_handle_t handle, unsigned memory_
 node)
- void starpu_memchunk_tidy (unsigned memory_node)
- void starpu_data_set_user_data (starpu_data_handle_t handle, void *user_data)
- void * starpu_data_get_user_data (starpu_data_handle_t handle)

Implicit Data Dependencies

In this section, we describe how StarPU makes it possible to insert implicit task dependencies in order to enforce sequential data consistency. When this data consistency is enabled on a specific data handle, any data access will appear as sequentially consistent from the application. For instance, if the application submits two tasks that access the same piece of data in read-only mode, and then a third task that access it in write mode, dependencies will be added between the two first tasks and the third one. Implicit data dependencies are also inserted in the case of data accesses from the application.

- void starpu_data_set_sequential_consistency_flag (starpu_data_handle_t handle, unsigned flag)
- unsigned starpu_data_get_sequential_consistency_flag (starpu_data_handle_t handle)
- unsigned starpu_data_get_default_sequential_consistency_flag (void)
- void starpu_data_set_default_sequential_consistency_flag (unsigned flag)

Access registered data from the application

- #define STARPU ACQUIRE NO NODE
- #define STARPU ACQUIRE NO NODE LOCK ALL
- #define STARPU_DATA_ACQUIRE_CB(handle, mode, code)
- int starpu_data_acquire (starpu_data_handle_t handle, enum starpu_data_access_mode mode)
- int starpu_data_acquire_on_node (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode)
- int starpu_data_acquire_cb (starpu_data_handle_t handle, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg)
- int starpu_data_acquire_on_node_cb (starpu_data_handle_t handle, int node, enum starpu_data_access
 mode mode, void(*callback)(void *), void *arg)
- int starpu_data_acquire_on_node_cb_sequential_consistency (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency)
- int starpu_data_acquire_on_node_cb_sequential_consistency_quick (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency, int quick)
- int starpu_data_acquire_on_node_cb_sequential_consistency_sync_jobids (starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*callback)(void *), void *arg, int sequential_consistency, int quick, long *pre_sync_jobid, long *post_sync_jobid)
- int starpu data acquire try (starpu data handle t handle, enum starpu data access mode mode)
- int starpu_data_acquire_on_node_try (starpu_data_handle_t handle, int node, enum starpu_data_access

 mode mode)
- void starpu_data_release (starpu_data_handle_t handle)
- void starpu_data_release_on_node (starpu_data_handle_t handle, int node)

32.10 starpu data filters.h File Reference

```
#include <starpu.h>
#include <stdarg.h>
```

Data Structures

· struct starpu_data_filter

Functions

Basic API

- void starpu data partition (starpu data handle t initial handle, struct starpu data filter *f)
- void starpu_data_unpartition (starpu_data_handle_t root_data, unsigned gathering_node)
- starpu data handle t starpu data get child (starpu data handle t handle, unsigned i)
- int starpu_data_get_nb_children (starpu_data_handle_t handle)
- starpu_data_handle_t starpu_data_get_sub_data (starpu_data_handle_t root_data, unsigned depth,...)
- starpu_data_handle_t starpu_data_vget_sub_data (starpu_data_handle_t root_data, unsigned depth, va list pa)
- void starpu_data_map_filters (starpu_data_handle_t root_data, unsigned nfilters,...)
- void starpu_data_vmap_filters (starpu_data_handle_t root_data, unsigned nfilters, va_list pa)

Asynchronous API

- void starpu_data_partition_plan (starpu_data_handle_t initial_handle, struct starpu_data_filter *f, starpu
 __data_handle_t *children)

- void starpu_data_partition_readonly_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children)
- void starpu_data_partition_readwrite_upgrade_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu data handle t *children)
- void starpu_data_unpartition_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_
 data_handle_t *children, int gathering_node)
- void starpu_data_unpartition_submit_r (starpu_data_handle_t initial_handle, int gathering_node)
- void starpu_data_unpartition_readonly_submit (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int gathering_node)
- void starpu_data_partition_clean (starpu_data_handle_t root_data, unsigned nparts, starpu_data_
 handle t *children)
- void starpu_data_partition_submit_sequential_consistency (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int sequential_consistency)
- void starpu_data_unpartition_submit_sequential_consistency (starpu_data_handle_t initial_handle, unsigned nparts, starpu_data_handle_t *children, int gathering_node, int sequential_consistency)
- void starpu_data_partition_not_automatic (starpu_data_handle_t handle)

Predefined BCSR Filter Functions

Predefined partitioning functions for BCSR data. Examples on how to use them are shown in Partitioning Data.

- void starpu_bcsr_filter_canonical_block (void *father_interface, void *child_interface, struct starpu_data
 —
 filter *f, unsigned id, unsigned nparts)

Predefined CSR Filter Functions

Predefined partitioning functions for CSR data. Examples on how to use them are shown in Partitioning Data.

void starpu_csr_filter_vertical_block (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)

Predefined Matrix Filter Functions

Predefined partitioning functions for matrix data. Examples on how to use them are shown in Partitioning Data.

- void starpu_matrix_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data
 — filter *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_vertical_block (void *father_interface, void *child_interface, struct starpu_data
 —filter *f, unsigned id, unsigned nparts)
- void starpu_matrix_filter_vertical_block_shadow (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)

Predefined Vector Filter Functions

Predefined partitioning functions for vector data. Examples on how to use them are shown in Partitioning Data.

- void starpu_vector_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data
 filter *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_list_long (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)
- void starpu_vector_filter_list (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)

Predefined Block Filter Functions

Predefined partitioning functions for block data. Examples on how to use them are shown in Partitioning Data. An example is available in examples/filters/shadow3d.c

- void starpu_block_filter_block (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_block_shadow (void *father_interface, void *child_interface, struct starpu_data
 —filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_vertical_block_shadow (void *father_interface, void *child_interface, struct starpu_data_filter *f, unsigned id, unsigned nparts)
- void starpu_block_filter_depth_block (void *father_interface, void *child_interface, struct starpu_data_filter
 *f, unsigned id, unsigned nparts)
- void starpu_block_filter_depth_block_shadow (void *father_interface, void *child_interface, struct starpu
 __data_filter *f, unsigned id, unsigned nparts)
- void starpu_filter_nparts_compute_chunk_size_and_offset (unsigned n, unsigned nparts, size_t elemsize, unsigned id, unsigned ld, unsigned *chunk_size, size_t *offset)

32.11 starpu_data_interfaces.h File Reference

```
#include <starpu.h>
#include <cuda_runtime.h>
```

Data Structures

- · struct starpu_data_copy_methods
- · struct starpu data interface ops
- · struct starpu_matrix_interface
- struct starpu_coo_interface
- · struct starpu_block_interface
- struct starpu_vector_interface
- · struct starpu variable interface
- · struct starpu_csr_interface
- · struct starpu_bcsr_interface
- struct starpu_multiformat_data_interface_ops
- · struct starpu multiformat interface

Typedefs

typedef cudaStream t starpu cudaStream t

Enumerations

enum starpu_data_interface_id {
 STARPU_UNKNOWN_INTERFACE_ID, STARPU_MATRIX_INTERFACE_ID, STARPU_BLOCK_INTER
 FACE_ID, STARPU_VECTOR_INTERFACE_ID,
 STARPU_CSR_INTERFACE_ID, STARPU_BCSR_INTERFACE_ID, STARPU_VARIABLE_INTERFACE
 _ ID, STARPU_VOID_INTERFACE_ID,
 STARPU_MULTIFORMAT_INTERFACE_ID, STARPU_COO_INTERFACE_ID, STARPU_MAX_INTERF
 ACE_ID }

Functions

Basic API

- void starpu_data_register (starpu_data_handle_t *handleptr, int home_node, void *data_interface, struct starpu data interface ops *ops)
- void starpu_data_ptr_register (starpu_data_handle_t handle, unsigned node)
- void starpu_data_register_same (starpu_data_handle_t *handledst, starpu_data_handle_t handlesrc)
- void * starpu_data_handle_to_pointer (starpu_data_handle_t handle, unsigned node)
- int starpu_data_pointer_is_inside (starpu_data_handle_t handle, unsigned node, void *ptr)
- void * starpu_data_get_local_ptr (starpu_data_handle_t handle)
- void * starpu_data_get_interface_on_node (starpu_data_handle_t handle, unsigned memory_node)
- enum starpu_data_interface_id starpu_data_get_interface_id (starpu_data_handle_t handle)
- int starpu_data_pack (starpu_data_handle_t handle, void **ptr, starpu_ssize_t *count)
- int starpu_data_unpack (starpu_data_handle_t handle, void *ptr, size_t count)
- size_t starpu_data_get_size (starpu_data_handle_t handle)
- size t starpu data get alloc size (starpu data handle t handle)
- starpu_data_handle_t starpu_data_lookup (const void *ptr)
- int starpu data get home node (starpu data handle t handle)
- int starpu data interface get next id (void)
- int starpu_interface_copy (uintptr_t src, size_t src_offset, unsigned src_node, uintptr_t dst, size_t dst_
 offset, unsigned dst node, size t size, void *async data)
- void starpu_interface_start_driver_copy_async (unsigned src_node, unsigned dst_node, double *start)
- void starpu_interface_end_driver_copy_async (unsigned src_node, unsigned dst_node, double start)
- void starpu_interface_data_copy (unsigned src_node, unsigned dst_node, size_t size)
- uintptr t starpu malloc on node flags (unsigned dst node, size t size, int flags)
- uintptr t starpu malloc on node (unsigned dst node, size t size)
- void starpu_free_on_node_flags (unsigned dst_node, uintptr_t addr, size_t size, int flags)
- void starpu_free_on_node (unsigned dst_node, uintptr_t addr, size_t size)
- void starpu_malloc_on_node_set_default_flags (unsigned node, int flags)

Accessing Matrix Data Interfaces

- #define STARPU_MATRIX_GET_PTR(interface)
- #define STARPU MATRIX GET DEV HANDLE(interface)
- #define STARPU_MATRIX_GET_OFFSET(interface)
- #define STARPU MATRIX GET NX(interface)
- #define STARPU_MATRIX_GET_NY(interface)
- #define STARPU_MATRIX_GET_LD(interface)
- #define STARPU_MATRIX_GET_ELEMSIZE(interface)
- #define STARPU MATRIX GET ALLOCSIZE(interface)
- #define STARPU MATRIX SET NX(interface, newnx)
- #define STARPU MATRIX SET NY(interface, newny)
- #define STARPU_MATRIX_SET_LD(interface, newld)
- struct starpu_data_interface_ops starpu_interface_matrix_ops
- void starpu_matrix_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ld, uint32_t nx, uint32_t ny, size_t elemsize)
- void starpu_matrix_data_register_allocsize (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ld, uint32_t nx, uint32_t ny, size_t elemsize, size_t allocsize)
- uint32 t starpu matrix get nx (starpu data handle t handle)
- uint32_t starpu_matrix_get_ny (starpu_data_handle_t handle)
- uint32 t starpu matrix get local ld (starpu data handle t handle)
- uintptr t starpu matrix get local ptr (starpu data handle t handle)
- size_t starpu_matrix_get_elemsize (starpu_data_handle_t handle)
- size_t starpu_matrix_get_allocsize (starpu_data_handle_t handle)

Accessing COO Data Interfaces

- #define STARPU_COO_GET_COLUMNS(interface)
- #define STARPU COO GET COLUMNS DEV HANDLE(interface)
- #define STARPU_COO_GET_ROWS(interface)
- #define STARPU_COO_GET_ROWS_DEV_HANDLE(interface)
- #define STARPU_COO_GET_VALUES(interface)
- #define STARPU_COO_GET_VALUES_DEV_HANDLE(interface)
- #define STARPU COO GET OFFSET
- #define STARPU COO GET NX(interface)
- #define STARPU COO GET NY(interface)
- #define STARPU_COO_GET_NVALUES(interface)
- #define STARPU COO GET ELEMSIZE(interface)
- · struct starpu data interface ops starpu interface coo ops
- void starpu_coo_data_register (starpu_data_handle_t *handleptr, int home_node, uint32_t nx, uint32_t ny, uint32_t n_values, uint32_t *columns, uint32_t *rows, uintptr_t values, size_t elemsize)

Block Data Interface

- #define STARPU_BLOCK_GET_PTR(interface)
- #define STARPU BLOCK GET DEV HANDLE(interface)
- #define STARPU BLOCK GET OFFSET(interface)
- #define STARPU BLOCK GET NX(interface)
- #define STARPU_BLOCK_GET_NY(interface)
- #define STARPU BLOCK GET NZ(interface)
- #define STARPU_BLOCK_GET_LDY(interface)
- #define STARPU BLOCK GET LDZ(interface)
- #define STARPU BLOCK GET ELEMSIZE(interface)
- struct starpu_data_interface_ops starpu_interface_block_ops
- void starpu_block_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t ldy, uint32_t ldz, uint32_t nx, uint32_t nx, uint32_t nz, size_t elemsize)
- void starpu_block_ptr_register (starpu_data_handle_t handle, unsigned node, uintptr_t ptr, uintptr_t dev_←
 handle, size t offset, uint32 t ldy, uint32 t ldz)
- uint32_t starpu_block_get_nx (starpu_data_handle_t handle)
- uint32_t starpu_block_get_ny (starpu_data_handle_t handle)
- uint32_t starpu_block_get_nz (starpu_data_handle_t handle)
- uint32_t starpu_block_get_local_ldy (starpu_data_handle_t handle)
- uint32_t starpu_block_get_local_ldz (starpu_data_handle_t handle)
- uintptr t starpu block get local ptr (starpu data handle t handle)
- size t starpu block get elemsize (starpu data handle t handle)

Vector Data Interface

- #define STARPU_VECTOR_GET_PTR(interface)
- #define STARPU_VECTOR_GET_DEV_HANDLE(interface)
- #define STARPU_VECTOR_GET_OFFSET(interface)
- #define STARPU VECTOR GET NX(interface)
- #define STARPU VECTOR GET ELEMSIZE(interface)
- #define STARPU_VECTOR_GET_ALLOCSIZE(interface)
- #define STARPU_VECTOR_GET_SLICE_BASE(interface)
- #define STARPU_VECTOR_SET_NX(interface, newnx)
- struct starpu_data_interface_ops starpu_interface_vector_ops
- void starpu_vector_data_register (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t nx, size t elemsize)
- void starpu_vector_data_register_allocsize (starpu_data_handle_t *handle, int home_node, uintptr_t ptr, uint32_t nx, size_t elemsize, size_t allocsize)

- uint32_t starpu_vector_get_nx (starpu_data_handle_t handle)
- size t starpu vector get elemsize (starpu data handle t handle)
- size_t starpu_vector_get_allocsize (starpu_data_handle_t handle)
- · uintptr t starpu vector get local ptr (starpu data handle t handle)

Variable Data Interface

- #define STARPU VARIABLE GET PTR(interface)
- #define STARPU_VARIABLE_GET_OFFSET(interface)
- #define STARPU VARIABLE GET ELEMSIZE(interface)
- #define STARPU_VARIABLE_GET_DEV_HANDLE(interface)
- struct starpu_data_interface_ops starpu_interface_variable_ops
- void starpu variable data register (starpu data handle t *handle, int home node, uintptr t ptr, size t size)
- void starpu_variable_ptr_register (starpu_data_handle_t handle, unsigned node, uintptr_t ptr, uintptr_t dev
 —handle, size_t offset)
- size t starpu variable get elemsize (starpu data handle t handle)
- uintptr_t starpu_variable_get_local_ptr (starpu_data_handle_t handle)

Void Data Interface

- struct starpu_data_interface_ops starpu_interface_void_ops
- void starpu_void_data_register (starpu_data_handle_t *handle)

CSR Data Interface

- #define STARPU_CSR_GET_NNZ(interface)
- #define STARPU_CSR_GET_NROW(interface)
- #define STARPU_CSR_GET_NZVAL(interface)
- #define STARPU CSR GET NZVAL DEV HANDLE(interface)
- #define STARPU_CSR_GET_COLIND(interface)
- #define STARPU_CSR_GET_COLIND_DEV_HANDLE(interface)
- #define STARPU_CSR_GET_ROWPTR(interface)
- #define STARPU CSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU_CSR_GET_OFFSET
- #define STARPU CSR GET FIRSTENTRY(interface)
- #define STARPU_CSR_GET_ELEMSIZE(interface)
- struct starpu_data_interface_ops starpu_interface_csr_ops
- void starpu_csr_data_register (starpu_data_handle_t *handle, int home_node, uint32_t nnz, uint32_t nrow, uintptr_t nzval, uint32_t *colind, uint32_t *rowptr, uint32_t firstentry, size_t elemsize)
- uint32_t starpu_csr_get_nnz (starpu_data_handle_t handle)
- uint32_t starpu_csr_get_nrow (starpu_data_handle_t handle)
- uint32_t starpu_csr_get_firstentry (starpu_data_handle_t handle)
- uintptr_t starpu_csr_get_local_nzval (starpu_data_handle_t handle)
- uint32_t * starpu_csr_get_local_colind (starpu_data_handle_t handle)
- uint32_t * starpu_csr_get_local_rowptr (starpu_data_handle_t handle)
- size_t starpu_csr_get_elemsize (starpu_data_handle_t handle)

BCSR Data Interface

- #define STARPU BCSR GET NNZ(interface)
- #define STARPU_BCSR_GET_NZVAL(interface)
- #define STARPU_BCSR_GET_NZVAL_DEV_HANDLE(interface)
- #define STARPU BCSR GET COLIND(interface)
- #define STARPU BCSR GET COLIND DEV HANDLE(interface)
- #define STARPU BCSR GET ROWPTR(interface)
- #define STARPU BCSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU BCSR GET OFFSET
- struct starpu_data_interface_ops starpu_interface_bcsr_ops
- void starpu_bcsr_data_register (starpu_data_handle_t *handle, int home_node, uint32_t nnz, uint32_t nrow, uintptr_t nzval, uint32_t *colind, uint32_t *rowptr, uint32_t firstentry, uint32_t r, uint32_t c, size_t elemsize)
- uint32_t starpu_bcsr_get_nnz (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_nrow (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_firstentry (starpu_data_handle_t handle)
- uintptr_t starpu_bcsr_get_local_nzval (starpu_data_handle_t handle)
- uint32_t * starpu_bcsr_get_local_colind (starpu_data_handle_t handle)
- uint32_t * starpu_bcsr_get_local_rowptr (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_r (starpu_data_handle_t handle)
- uint32_t starpu_bcsr_get_c (starpu_data_handle_t handle)
- size_t starpu_bcsr_get_elemsize (starpu_data_handle_t handle)

Multiformat Data Interface

- #define STARPU MULTIFORMAT GET CPU PTR(interface)
- #define STARPU_MULTIFORMAT_GET_CUDA_PTR(interface)
- #define STARPU MULTIFORMAT GET OPENCL PTR(interface)
- #define STARPU_MULTIFORMAT_GET_MIC_PTR(interface)
- #define STARPU_MULTIFORMAT_GET_NX(interface)
- void starpu_multiformat_data_register (starpu_data_handle_t *handle, int home_node, void *ptr, uint32_t nobjects, struct starpu_multiformat_data_interface_ops *format_ops)

32.12 starpu_deprecated_api.h File Reference

Macros

· #define starpu permodel history based expected perf

32.13 starpu_disk.h File Reference

```
#include <sys/types.h>
#include <starpu_config.h>
```

Data Structures

· struct starpu_disk_ops

Macros

• #define STARPU DISK SIZE MIN

Functions

- void starpu_disk_close (unsigned node, void *obj, size_t size)
- void * starpu_disk_open (unsigned node, void *pos, size_t size)
- int starpu_disk_register (struct starpu_disk_ops *func, void *parameter, starpu_ssize_t size)

Variables

- struct starpu_disk_ops starpu_disk_stdio_ops
- struct starpu_disk_ops starpu_disk_hdf5_ops
- struct starpu_disk_ops starpu_disk_unistd_ops
- · struct starpu disk ops starpu disk unistd o direct ops
- struct starpu_disk_ops starpu_disk_leveldb_ops
- int starpu_disk_swap_node

32.14 starpu_driver.h File Reference

```
#include <starpu_config.h>
#include <starpu_opencl.h>
```

Data Structures

- · struct starpu_driver
- · union starpu_driver.id

Functions

- int starpu_driver_run (struct starpu_driver *d)
- void starpu_drivers_request_termination (void)
- int starpu_driver_init (struct starpu_driver *d)
- int starpu_driver_run_once (struct starpu_driver *d)
- int starpu_driver_deinit (struct starpu_driver *d)

32.15 starpu expert.h File Reference

Functions

- void starpu_wake_all_blocked_workers (void)
- int starpu_progression_hook_register (unsigned(*func)(void *arg), void *arg)
- void starpu_progression_hook_deregister (int hook_id)
- int starpu idle hook register (unsigned(*func)(void *arg), void *arg)
- void starpu_idle_hook_deregister (int hook_id)

32.16 starpu_fxt.h File Reference

```
#include <starpu_perfmodel.h>
```

Data Structures

- · struct starpu_fxt_codelet_event
- struct starpu_fxt_options

Macros

• #define STARPU_FXT_MAX_FILES

Functions

- void starpu_fxt_options_init (struct starpu_fxt_options *options)
- void starpu_fxt_generate_trace (struct starpu_fxt_options *options)
- void starpu_fxt_autostart_profiling (int autostart)
- void starpu_fxt_start_profiling (void)
- void starpu_fxt_stop_profiling (void)
- void starpu_fxt_write_data_trace (char *filename_in)
- void starpu_fxt_trace_user_event (unsigned long code)
- void starpu_fxt_trace_user_event_string (const char *s)

32.17 starpu_hash.h File Reference

```
#include <stdint.h>
#include <stddef.h>
```

Functions

- uint32 t starpu hash crc32c be n (const void *input, size t n, uint32 t inputcrc)
- uint32_t starpu_hash_crc32c_be (uint32_t input, uint32_t inputcrc)
- uint32_t starpu_hash_crc32c_string (const char *str, uint32_t inputcrc)

32.18 starpu_mic.h File Reference

```
#include <starpu_config.h>
```

Typedefs

typedef void * starpu_mic_func_symbol_t

Functions

- int starpu_mic_register_kernel (starpu_mic_func_symbol_t *symbol, const char *func_name)
- starpu_mic_kernel_t starpu_mic_get_kernel (starpu_mic_func_symbol_t symbol)

32.19 starpu_mod.f90 File Reference

Data Types

- · interface starpu mod::starpu conf init
- · interface starpu_mod::starpu_init
- interface starpu_mod::starpu_pause
- interface starpu_mod::starpu_resume
- interface starpu_mod::starpu_shutdown
- interface starpu_mod::starpu_asynchronous_copy_disabled
- interface starpu_mod::starpu_asynchronous_cuda_copy_disabled
- interface starpu_mod::starpu_asynchronous_opencl_copy_disabled
- interface starpu_mod::starpu_asynchronous_mic_copy_disabled

- · interface starpu_mod::starpu_display_stats
- interface starpu_mod::starpu_get_version
- interface starpu_mod::starpu_cpu_worker_get_count
- · interface starpu mod::starpu task wait for all

32.20 starpu_mpi.h File Reference

```
#include <starpu.h>
#include <mpi.h>
#include <stdint.h>
```

Functions

- int starpu_mpi_pre_submit_hook_register (void(*f)(struct starpu_task *))
- int starpu_mpi_pre_submit_hook_unregister ()

Communication Cache

- int starpu mpi cache is enabled ()
- int starpu_mpi_cache_set (int enabled)
- void starpu mpi cache flush (MPI Comm comm, starpu data handle t data handle)
- void starpu_mpi_cache_flush_all_data (MPI_Comm comm)
- int starpu mpi cached receive (starpu data handle t data handle)
- int starpu mpi cached send (starpu data handle t data handle, int dest)

Collective Operations

- void starpu_mpi_redux_data (MPI_Comm comm, starpu_data_handle_t data_handle)
- · void starpu mpi redux data prio (MPI Comm comm, starpu data handle t data handle, int prio)
- int starpu_mpi_scatter_detached (starpu_data_handle_t *data_handles, int count, int root, MPI_Comm comm, void(*scallback)(void *), void *sarg, void(*rcallback)(void *), void *rarg)
- int starpu_mpi_gather_detached (starpu_data_handle_t *data_handles, int count, int root, MPI_Comm comm, void(*scallback)(void *), void *sarg, void(*rcallback)(void *), void *rarg)

Initialisation

- #define STARPU MPI_TAG_UB
- int starpu_mpi_init_conf (int *argc, char ***argv, int initialize_mpi, MPI_Comm comm, struct starpu_conf *conf)
- int starpu_mpi_init_comm (int *argc, char ***argv, int initialize_mpi, MPI_Comm comm)
- int starpu mpi init (int *argc, char ***argv, int initialize mpi)
- int starpu_mpi_initialize (void)
- int starpu_mpi_initialize_extended (int *rank, int *world_size)
- int starpu mpi shutdown (void)
- void starpu_mpi_comm_amounts_retrieve (size_t *comm_amounts)
- int starpu_mpi_comm_size (MPI_Comm comm, int *size)
- int starpu_mpi_comm_rank (MPI_Comm comm, int *rank)
- int starpu_mpi_world_rank (void)
- int starpu_mpi_world_size (void)
- int starpu_mpi_comm_get_attr (MPI_Comm comm, int keyval, void *attribute_val, int *flag)
- int starpu_mpi_get_communication_tag (void)
- void starpu_mpi_set_communication_tag (int tag)

Communication

- typedef void * starpu mpi req
- typedef int64 t starpu mpi tag t
- typedef void(* starpu_mpi_datatype_allocate_func_t) (starpu_data_handle_t, MPI_Datatype *)
- typedef void(* starpu_mpi_datatype_free_func_t) (MPI_Datatype *)
- int starpu_mpi_isend (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi_tag_t data tag, MPI Comm comm)
- int starpu_mpi_isend_prio (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi
 _tag_t data_tag, int prio, MPI_Comm comm)
- int starpu_mpi_irecv (starpu_data_handle_t data_handle, starpu_mpi_req *req, int source, starpu_mpi_\times tag_t data_tag, MPI_Comm comm)
- int starpu_mpi_send (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm)
- int starpu_mpi_send_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, int prio, MPI Comm comm)
- int starpu_mpi_recv (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI_Comm comm, MPI_Status *status)
- int starpu_mpi_isend_detached (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_isend_detached_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data
 tag, int prio, MPI Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_irecv_detached (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_irecv_detached_sequential_consistency (starpu_data_handle_t data_handle, int source, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg, int sequential_consistency)
- int starpu_mpi_issend (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi_tag
 —t data_tag, MPI_Comm comm)
- int starpu_mpi_issend_prio (starpu_data_handle_t data_handle, starpu_mpi_req *req, int dest, starpu_mpi
 _tag_t data_tag, int prio, MPI_Comm comm)
- int starpu_mpi_issend_detached (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data_tag, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_issend_detached_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag_t data
 _tag, int prio, MPI_Comm comm, void(*callback)(void *), void *arg)
- int starpu_mpi_wait (starpu_mpi_req *req, MPI_Status *status)
- int starpu_mpi_test (starpu_mpi_req *req, int *flag, MPI_Status *status)
- int starpu_mpi_barrier (MPI_Comm comm)
- int starpu_mpi_wait_for_all (MPI_Comm comm)
- int starpu_mpi_isend_detached_unlock_tag (starpu_data_handle_t data_handle, int dest, starpu_mpi_tag
 t data_tag, MPI_Comm comm, starpu_tag_t tag)
- int starpu_mpi_isend_detached_unlock_tag_prio (starpu_data_handle_t data_handle, int dest, starpu_mpi
 tag_t data_tag, int prio, MPI_Comm comm, starpu_tag_t tag)
- int starpu_mpi_irecv_detached_unlock_tag (starpu_data_handle_t data_handle, int source, starpu_mpi_
 tag_t data_tag, MPI_Comm comm, starpu_tag_t tag)
- int starpu_mpi_isend_array_detached_unlock_tag (unsigned array_size, starpu_data_handle_t *data_← handle, int *dest, starpu_mpi_tag_t *data_tag, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_isend_array_detached_unlock_tag_prio (unsigned array_size, starpu_data_handle_t *data ←
 _handle, int *dest, starpu_mpi_tag_t *data_tag, int *prio, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_irecv_array_detached_unlock_tag (unsigned array_size, starpu_data_handle_t *data_← handle, int *source, starpu_mpi_tag_t *data_tag, MPI_Comm *comm, starpu_tag_t tag)
- int starpu_mpi_datatype_register (starpu_data_handle_t handle, starpu_mpi_datatype_allocate_func_
 t allocate_datatype_func, starpu_mpi_datatype_free_func_t free_datatype_func)
- int starpu_mpi_datatype_unregister (starpu_data_handle_t handle)

MPI Insert Task

- #define STARPU MPI PER NODE
- #define starpu mpi data register(data handle, data tag, rank)
- #define starpu_data_set_tag
- #define starpu_mpi_data_set_rank(handle, rank)
- #define starpu_data_set_rank
- · #define starpu data get rank
- · #define starpu data get tag
- void starpu_mpi_data_register_comm (starpu_data_handle_t data_handle, starpu_mpi_tag_t data_tag, int rank, MPI Comm comm)
- void starpu mpi data set tag (starpu data handle t handle, starpu mpi tag t data tag)
- void starpu_mpi_data_set_rank_comm (starpu_data_handle_t handle, int rank, MPI_Comm comm)
- int starpu mpi data get rank (starpu data handle t handle)
- starpu mpi tag t starpu mpi data get tag (starpu data handle t handle)
- int starpu mpi task insert (MPI Comm comm, struct starpu codelet *codelet....)
- int starpu_mpi_insert_task (MPI_Comm comm, struct starpu_codelet *codelet,...)
- struct starpu_task * starpu_mpi_task_build (MPI_Comm comm, struct starpu_codelet *codelet,...)
- int starpu_mpi_task_post_build (MPI_Comm comm, struct starpu_codelet *codelet,...)
- void starpu_mpi_get_data_on_node (MPI_Comm comm, starpu_data_handle_t data_handle, int node)
- void starpu_mpi_get_data_on_node_detached (MPI_Comm comm, starpu_data_handle_t data_handle, int node, void(*callback)(void *), void *arg)
- void starpu_mpi_get_data_on_all_nodes_detached (MPI_Comm comm, starpu_data_handle_t data_handle)
- void starpu_mpi_data_migrate (MPI_Comm comm, starpu_data_handle_t handle, int new_rank)

Node Selection Policy

- #define STARPU MPI NODE SELECTION CURRENT POLICY
- · #define STARPU MPI NODE SELECTION MOST R DATA
- typedef int(* starpu_mpi_select_node_policy_func_t) (int me, int nb_nodes, struct starpu_data_descr *descr, int nb_data)
- int starpu_mpi_node_selection_register_policy (starpu_mpi_select_node_policy_func_t policy_func)
- int starpu_mpi_node_selection_unregister_policy (int policy)
- int starpu mpi node selection get current policy ()
- int starpu_mpi_node_selection_set_current_policy (int policy)

32.21 starpu_mpi_lb.h File Reference

```
#include <starpu.h>
```

Data Structures

struct starpu_mpi_lb_conf

Functions

- void starpu mpi lb init (const char *lb policy name, struct starpu mpi lb conf *)
- void starpu_mpi_lb_shutdown ()

32.22 starpu_opencl.h File Reference

```
#include <starpu_config.h>
#include <CL/cl.h>
#include <assert.h>
```

Data Structures

· struct starpu_opencl_program

Macros

#define CL_TARGET_OPENCL_VERSION

Functions

Writing OpenCL kernels

- void starpu_opencl_get_context (int devid, cl_context *context)
- void starpu_opencl_get_device (int devid, cl_device_id *device)
- void starpu_opencl_get_queue (int devid, cl_command_queue *queue)
- void starpu opencl get current context (cl context *context)
- void starpu opencl get current queue (cl command queue *queue)
- int starpu opencl set kernel args (cl int *err, cl kernel *kernel,...)

Compiling OpenCL kernels

Source codes for OpenCL kernels can be stored in a file or in a string. StarPU provides functions to build the program executable for each available OpenCL device as a cl_program object. This program executable can then be loaded within a specific queue as explained in the next section. These are only helpers, Applications can also fill a starpu_opencl_program array by hand for more advanced use (e.g. different programs on the different OpenCL devices, for relocation purpose for instance).

- void starpu_opencl_load_program_source (const char *source_file_name, char *located_file_name, char *located_dir name, char *opencl_program_source)
- void starpu_opencl_load_program_source_malloc (const char *source_file_name, char **located_file_
 name, char **located_dir_name, char **opencl_program_source)
- int starpu_opencl_compile_opencl_from_file (const char *source_file_name, const char *build_options)
- int starpu_opencl_compile_opencl_from_string (const char *opencl_program_source, const char *file_←
 name, const char *build_options)
- int starpu_opencl_load_binary_opencl (const char *kernel_id, struct starpu_opencl_program *opencl_
 programs)
- int starpu_opencl_load_opencl_from_file (const char *source_file_name, struct starpu_opencl_program *opencl_programs, const char *build_options)
- int starpu_opencl_load_opencl_from_string (const char *opencl_program_source, struct starpu_opencl
 _program *opencl_programs, const char *build_options)
- int starpu_opencl_unload_opencl (struct starpu_opencl_program *opencl_programs)

Loading OpenCL kernels

- int starpu_opencl_load_kernel (cl_kernel *kernel, cl_command_queue *queue, struct starpu_opencl_
 program *opencl_programs, const char *kernel_name, int devid)
- int starpu_opencl_release_kernel (cl_kernel kernel)

OpenCL Statistics

int starpu_opencl_collect_stats (cl_event event)

OpenCL Utilities

- #define STARPU OPENCL DISPLAY ERROR(status)
- #define STARPU_OPENCL_REPORT_ERROR(status)
- #define STARPU OPENCL REPORT ERROR WITH MSG(msg, status)
- const char * starpu opencl error string (cl int status)
- void starpu opencl display error (const char *func, const char *file, int line, const char *msg, cl int status)
- static __starpu_inline void starpu_opencl_report_error (const char *func, const char *file, int line, const char *msg, cl_int status)
- cl_int starpu_opencl_allocate_memory (int devid, cl_mem *addr, size_t size, cl_mem_flags flags)

- cl_int starpu_opencl_copy_ram_to_opencl (void *ptr, unsigned src_node, cl_mem buffer, unsigned dst_node, size_t size, size_t offset, cl_event *event, int *ret)
- cl_int starpu_opencl_copy_opencl_to_ram (cl_mem buffer, unsigned src_node, void *ptr, unsigned dst_node, size t size, size t offset, cl event *event, int *ret)
- cl_int starpu_opencl_copy_opencl_to_opencl (cl_mem src, unsigned src_node, size_t src_offset, cl_mem dst, unsigned dst_node, size_t dst_offset, size_t size, cl_event *event, int *ret)
- cl_int starpu_opencl_copy_async_sync (uintptr_t src, size_t src_offset, unsigned src_node, uintptr_t dst, size t dst offset, unsigned dst node, size t size, cl event *event)

32.23 starpu_openmp.h File Reference

```
#include <starpu_config.h>
```

Data Structures

- · struct starpu omp lock t
- · struct starpu omp nest lock t
- · struct starpu_omp_parallel_region_attr
- · struct starpu omp task region attr

Macros

#define STARPU OMP NOTHROW

Enumerations

- enum starpu_omp_sched_value {
 starpu_omp_sched_undefined, starpu_omp_sched_static, starpu_omp_sched_dynamic, starpu_omp_
 sched_guided,
 starpu_omp_sched_auto, starpu_omp_sched_runtime }
- enum starpu_omp_proc_bind_value {
 starpu_omp_proc_bind_undefined, starpu_omp_proc_bind_false, starpu_omp_proc_bind_true, starpu_
 omp_proc_bind_master,
 starpu_omp_proc_bind_close, starpu_omp_proc_bind_spread }

Functions

Initialisation

- int starpu_omp_init (void) __STARPU_OMP_NOTHROW
- void starpu omp shutdown (void) STARPU OMP NOTHROW

Parallel

- void starpu_omp_master (void(*f)(void *arg), void *arg) __STARPU_OMP_NOTHROW
- int starpu_omp_master_inline (void) __STARPU_OMP_NOTHROW

Synchronization

- void starpu_omp_barrier (void) __STARPU_OMP_NOTHROW
- void starpu_omp_critical (void(*f)(void *arg), void *arg, const char *name) __STARPU_OMP_NOTHROW
- void starpu_omp_critical_inline_begin (const char *name) __STARPU_OMP_NOTHROW
- void starpu_omp_critical_inline_end (const char *name) __STARPU_OMP_NOTHROW

Worksharing

- void starpu_omp_single (void(*f)(void *arg), void *arg, int nowait) __STARPU_OMP_NOTHROW
- int starpu omp single inline (void)
 STARPU OMP NOTHROW
- void starpu_omp_single_copyprivate (void(*f)(void *arg, void *data, unsigned long long data_size), void *arg, void *data, unsigned long long data size) STARPU OMP NOTHROW
- void * starpu_omp_single_copyprivate_inline_begin (void *data) __STARPU_OMP_NOTHROW
- void starpu_omp_single_copyprivate_inline_end (void) __STARPU_OMP_NOTHROW
- void starpu_omp_for (void(*f)(unsigned long long _first_i, unsigned long long _nb_i, void *arg), void *arg, unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) __ST← ARPU OMP NOTHROW
- int starpu omp for inline first (unsigned long long nb iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long *_first_i, unsigned long long *_nb_i) __STARPU_OMP_NOTHROW
- · int starpu_omp_for_inline_next (unsigned long long nb_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long * first i, unsigned long long * nb i) STARPU OMP NOTHROW
- void starpu_omp_for_alt (void(*f)(unsigned long long_begin_i, unsigned long long_end_i, void *arg), void *arg, unsigned long long nb iterations, unsigned long long chunk, int schedule, int ordered, int nowait) ← STARPU OMP NOTHROW
- int starpu omp for inline first alt (unsigned long long nb iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long ∗ begin i, unsigned long long ∗ end i) STARPU OMP NOTHR ← OW
- int starpu omp for inline next alt (unsigned long long nb iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long ∗ begin i, unsigned long long ∗ end i) STARPU OMP NOTHR ←
- void starpu omp ordered (void(*f)(void *arg), void *arg)
 STARPU OMP NOTHROW
- void starpu_omp_ordered_inline_begin (void) __STARPU_OMP_NOTHROW
- void starpu_omp_ordered_inline_end (void) __STARPU_OMP_NOTHROW
- void starpu omp sections (unsigned long long nb sections, void(**section f)(void *arg), void **section← _arg, int nowait) __STARPU_OMP_NOTHROW
- void starpu omp sections combined (unsigned long long nb sections, void(*section f)(unsigned long long section num, void *arg), void *section arg, int nowait) STARPU OMP NOTHROW

Task

- void starpu omp task region (const struct starpu omp task region attr *attr)
 STARPU OMP NOT← **HROW**
- void starpu_omp_taskwait (void) __STARPU_OMP_NOTHROW
- void starpu omp taskgroup (void(*f)(void *arg), void *arg)
 STARPU OMP NOTHROW
- void starpu_omp_taskgroup_inline_begin (void) __STARPU_OMP_NOTHROW
 void starpu_omp_taskgroup_inline_end (void) __STARPU_OMP_NOTHROW
- void starpu_omp_taskloop_inline_begin (struct starpu_omp_task_region_attr *attr) __STARPU_OM← P NOTHROW
- void starpu_omp_taskloop_inline_end (const struct starpu_omp_task_region_attr *attr) __STARPU_ OMP NOTHROW

API

- void starpu omp set num threads (int threads)
 STARPU OMP NOTHROW
- int starpu_omp_get_num_threads () __STARPU_OMP_NOTHROW
- int starpu_omp_get_thread_num () __STARPU_OMP_NOTHROW
- int starpu_omp_get_max_threads () __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_procs (void) __STARPU_OMP_NOTHROW
- int starpu_omp_in_parallel (void) __STARPU_OMP_NOTHROW
- void starpu_omp_set_dynamic (int dynamic_threads) __STARPU_OMP_NOTHROW
 int starpu_omp_get_dynamic (void) __STARPU_OMP_NOTHROW
- void starpu omp set nested (int nested)
 STARPU OMP NOTHROW
- int starpu_omp_get_nested (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_cancellation (void) __STARPU_OMP_NOTHROW
- void starpu_omp_set_schedule (enum starpu_omp_sched_value kind, int modifier) __STARPU_OMP_← **NOTHROW**
- void starpu_omp_get_schedule (enum starpu_omp_sched_value *kind, int *modifier) __STARPU_OM P NOTHROW
- int starpu omp get thread limit (void) STARPU OMP NOTHROW
- void starpu_omp_set_max_active_levels (int max_levels) __STARPU_OMP_NOTHROW
- int starpu omp get max active levels (void)
 STARPU OMP NOTHROW

- int starpu_omp_get_level (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_ancestor_thread_num (int level) __STARPU_OMP_NOTHROW
- int starpu_omp_get_team_size (int level) __STARPU_OMP_NOTHROW
- int starpu omp get active level (void) STARPU OMP NOTHROW
- int starpu_omp_in_final (void) __STARPU_OMP_NOTHROW
- enum starpu_omp_proc_bind_value starpu_omp_get_proc_bind (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_places (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_place_num_procs (int place_num) __STARPU_OMP_NOTHROW
- void starpu omp get_place_proc_ids (int place_num, int *ids) __STARPU_OMP_NOTHROW
- int starpu_omp_get_place_num (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_partition_num_places (void) __STARPU_OMP_NOTHROW
- void starpu_omp_get_partition_place_nums (int *place_nums) __STARPU_OMP_NOTHROW
- void starpu_omp_set_default_device (int device_num) __STARPU_OMP_NOTHROW
- int starpu_omp_get_default_device (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_devices (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_num_teams (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_team_num (void) __STARPU_OMP_NOTHROW
- int starpu_omp_is_initial_device (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_initial_device (void) __STARPU_OMP_NOTHROW
- int starpu_omp_get_max_task_priority (void) __STARPU_OMP_NOTHROW
- void starpu_omp_init_lock (starpu_omp_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu_omp_destroy_lock (starpu_omp_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu omp set lock (starpu omp lock t *lock)
 STARPU OMP NOTHROW
- void starpu omp unset lock (starpu omp lock t *lock) STARPU OMP NOTHROW
- int starpu omp test lock (starpu omp lock t *lock) STARPU OMP NOTHROW
- void starpu omp init nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu omp destroy nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu omp set nest lock (starpu omp nest lock t *lock)
 STARPU OMP NOTHROW
- void starpu_omp_unset_nest_lock (starpu_omp_nest_lock_t *lock) __STARPU_OMP_NOTHROW
- int starpu_omp_test_nest_lock (starpu_omp_nest_lock_t *lock) __STARPU_OMP_NOTHROW
- void starpu_omp_atomic_fallback_inline_begin (void) __STARPU_OMP_NOTHROW
- void starpu_omp_atomic_fallback_inline_end (void) __STARPU_OMP_NOTHROW
- double starpu_omp_get_wtime (void) __STARPU_OMP_NOTHROW
- double starpu_omp_get_wtick (void) __STARPU_OMP_NOTHROW
- void starpu_omp_vector_annotate (starpu_data_handle_t handle, uint32_t slice_base) __STARPU_OM
 P_NOTHROW
- struct starpu arbiter * starpu omp get default arbiter (void) STARPU OMP NOTHROW

32.24 starpu_perfmodel.h File Reference

#include <starpu.h>
#include <stdio.h>

Data Structures

- struct starpu perfmodel device
- · struct starpu perfmodel arch
- · struct starpu perfmodel history entry
- · struct starpu perfmodel history list
- · struct starpu perfmodel regression model
- · struct starpu_perfmodel_per_arch
- · struct starpu_perfmodel

Macros

- #define STARPU NARCH
- #define starpu_per_arch_perfmodel

Typedefs

- typedef double(* starpu_perfmodel_per_arch_cost_function) (struct starpu_task *task, struct starpu_
 perfmodel arch *arch, unsigned nimpl)
- typedef size_t(* starpu_perfmodel_per_arch_size_base) (struct starpu_task *task, struct starpu_
 perfmodel_arch *arch, unsigned nimpl)
- typedef struct starpu perfmodel state * starpu perfmodel state t

Enumerations

enum starpu_perfmodel_type {
 STARPU_PERFMODEL_INVALID, STARPU_PER_ARCH, STARPU_COMMON, STARPU_HISTORY_B
 ASED,
 STARPU_REGRESSION_BASED, STARPU_NL_REGRESSION_BASED, STARPU_MULTIPLE_REGR
 ESSION_BASED }

Functions

- void starpu_perfmodel_init (struct starpu_perfmodel *model)
- int starpu perfmodel load file (const char *filename, struct starpu perfmodel *model)
- int starpu_perfmodel_load_symbol (const char *symbol, struct starpu_perfmodel *model)
- int starpu_perfmodel_unload_model (struct starpu_perfmodel *model)
- void starpu perfmodel get model path (const char *symbol, char *path, size t maxlen)
- void starpu perfmodel dump xml (FILE *output, struct starpu perfmodel *model)
- void starpu perfmodel free sampling directories (void)
- struct starpu_perfmodel_arch * starpu_worker_get_perf_archtype (int workerid, unsigned sched_ctx_id)
- int starpu_perfmodel_get_narch_combs (void)
- int starpu perfmodel arch comb add (int ndevices, struct starpu perfmodel device *devices)
- int starpu perfmodel arch comb get (int ndevices, struct starpu perfmodel device *devices)
- struct starpu_perfmodel_arch * starpu_perfmodel_arch_comb_fetch (int comb)
- struct starpu_perfmodel_per_arch * starpu_perfmodel_get_model_per_arch (struct starpu_perfmodel *model, struct starpu_perfmodel_arch *arch, unsigned impl)
- struct starpu_perfmodel_per_arch * starpu_perfmodel_get_model_per_devices (struct starpu_perfmodel *model, int impl,...)
- int starpu_perfmodel_set_per_devices_cost_function (struct starpu_perfmodel *model, int impl, starpu
 _perfmodel_per_arch_cost_function func,...)
- int **starpu_perfmodel_set_per_devices_size_base** (struct **starpu_perfmodel** *model, int impl, starpu_← perfmodel_per_arch_size_base func,...)
- void starpu_perfmodel_debugfilepath (struct starpu_perfmodel *model, struct starpu_perfmodel_arch *arch, char *path, size_t maxlen, unsigned nimpl)
- char * starpu_perfmodel_get_archtype_name (enum starpu_worker_archtype archtype)
- void starpu_perfmodel_get_arch_name (struct starpu_perfmodel_arch *arch, char *archname, size_←
 t maxlen, unsigned nimpl)
- double starpu_perfmodel_history_based_expected_perf (struct starpu_perfmodel *model, struct starpu_
 perfmodel_arch *arch, uint32_t footprint)
- void starpu_perfmodel_initialize (void)
- int starpu perfmodel list (FILE *output)
- void **starpu_perfmodel_print** (struct **starpu_perfmodel** *model, struct **starpu_perfmodel_arch** *arch, unsigned nimpl, char *parameter, uint32_t *footprint, FILE *output)
- int starpu_perfmodel_print_all (struct starpu_perfmodel *model, char *arch, char *parameter, uint32_
 t *footprint, FILE *output)
- int starpu_perfmodel_print_estimations (struct starpu_perfmodel *model, uint32_t footprint, FILE *output)
- int starpu_perfmodel_list_combs (FILE *output, struct starpu_perfmodel *model)
- void starpu_perfmodel_update_history (struct starpu_perfmodel *model, struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned cpuid, unsigned nimpl, double measured)
- void starpu perfmodel directory (FILE *output)
- void starpu_bus_print_bandwidth (FILE *f)

- void starpu_bus_print_affinity (FILE *f)
- void starpu bus print filenames (FILE *f)
- double starpu_transfer_bandwidth (unsigned src_node, unsigned dst_node)
- double starpu transfer latency (unsigned src node, unsigned dst node)
- double starpu_transfer_predict (unsigned src_node, unsigned dst_node, size_t size)

Variables

· struct starpu perfmodel starpu perfmodel nop

32.25 starpu_profiling.h File Reference

```
#include <starpu.h>
#include <errno.h>
#include <time.h>
```

Data Structures

- · struct starpu profiling task info
- · struct starpu profiling worker info
- struct starpu_profiling_bus_info

Macros

- #define STARPU PROFILING DISABLE
- #define STARPU PROFILING ENABLE
- #define STARPU_NS_PER_S
- #define starpu_timespec_cmp(a, b, CMP)

Functions

- · void starpu profiling init (void)
- void starpu_profiling_set_id (int new_id)
- int starpu profiling status set (int status)
- int starpu_profiling_status_get (void)
- int starpu_profiling_worker_get_info (int workerid, struct starpu_profiling_worker_info *worker_info)
- int starpu bus get count (void)
- int starpu bus get id (int src, int dst)
- int starpu_bus_get_src (int busid)
- int starpu_bus_get_dst (int busid)
- · void starpu_bus_set_direct (int busid, int direct)
- int starpu_bus_get_direct (int busid)
- void starpu_bus_set_ngpus (int busid, int ngpus)
- int starpu_bus_get_ngpus (int busid)
- int starpu_bus_get_profiling_info (int busid, struct starpu_profiling_bus_info *bus_info)
- static starpu inline void starpu_timespec_clear (struct timespec *tsp)
- static __starpu_inline void starpu_timespec_add (struct timespec *a, struct timespec *b, struct timespec *result)
- static starpu inline void starpu timespec accumulate (struct timespec *result, struct timespec *a)
- static __starpu_inline void **starpu_timespec_sub** (const struct timespec *a, const struct timespec *b, struct timespec *result)
- double starpu timing timespec delay us (struct timespec *start, struct timespec *end)
- double starpu_timing_timespec_to_us (struct timespec *ts)
- void starpu profiling bus helper display summary (void)
- void starpu_profiling_worker_helper_display_summary (void)
- void starpu_data_display_memory_stats ()

32.26 starpu_rand.h File Reference

```
#include <stdlib.h>
#include <starpu_config.h>
```

Macros

- #define starpu_seed(seed)
- · #define starpu_srand48(seed)
- #define starpu_drand48()
- #define starpu_Irand48()
- #define starpu_erand48(xsubi)
- #define starpu_srand48_r(seed, buffer)
- #define starpu_erand48_r(xsubi, buffer, result)

Typedefs

· typedef int starpu_drand48_data

32.27 starpu_sched_component.h File Reference

```
#include <starpu.h>
#include <hwloc.h>
```

Data Structures

- · struct starpu_sched_component
- struct starpu_sched_tree
- struct starpu_sched_component_fifo_data
- struct starpu_sched_component_prio_data
- struct starpu_sched_component_mct_data
- struct starpu_sched_component_perfmodel_select_data
- struct starpu_sched_component_specs

Macros

- #define STARPU SCHED COMPONENT IS HOMOGENEOUS(component)
- #define STARPU_SCHED_COMPONENT_IS_SINGLE_MEMORY_NODE(component)
- #define STARPU_COMPONENT_MUTEX_LOCK(m)
- #define STARPU_COMPONENT_MUTEX_TRYLOCK(m)
- #define STARPU_COMPONENT_MUTEX_UNLOCK(m)

Enumerations

Functions

void starpu_initialize_prio_center_policy (unsigned sched_ctx_id)

Scheduling Tree API

struct starpu_sched_tree * starpu_sched_tree_create (unsigned sched_ctx_id) STARPU_ATTRIBUTE
 — MALLOC

- void starpu sched tree destroy (struct starpu sched tree *tree)
- struct starpu sched tree * starpu sched tree get (unsigned sched ctx id)
- void starpu_sched_tree_update_workers (struct starpu_sched_tree *t)
- void starpu sched tree update workers in ctx (struct starpu sched tree *t)
- int starpu sched tree push task (struct starpu task *task)
- struct starpu task * starpu sched tree pop task (unsigned sched ctx)
- int starpu_sched_component_push_task (struct starpu_sched_component *from, struct starpu_sched_← component *to, struct starpu_task *task)
- struct starpu_task * starpu_sched_component_pull_task (struct starpu_sched_component *from, struct starpu sched component *to)
- struct starpu_task * starpu_sched_component_pump_to (struct starpu_sched_component *component, struct starpu_sched_component *to, int *success)
- struct starpu_task * starpu_sched_component_pump_downstream (struct starpu_sched_component *component, int *success)
- int starpu_sched_component_send_can_push_to_parents (struct starpu_sched_component *component)
- void starpu_sched_tree_add_workers (unsigned sched_ctx_id, int *workerids, unsigned nworkers)
- void starpu_sched_tree_remove_workers (unsigned sched_ctx_id, int *workerids, unsigned nworkers)
- void starpu_sched_component_connect (struct starpu_sched_component *parent, struct starpu_sched
 _component *child)

Worker Component API

- struct starpu_sched_component * starpu_sched_component_worker_get (unsigned sched_ctx, int workerid)
- struct starpu_sched_component * starpu_sched_component_worker_new (unsigned sched_ctx, int workerid)
- int starpu_sched_component_worker_get_workerid (struct starpu_sched_component *worker_
 component)
- int starpu sched component is worker (struct starpu sched component *component)
- int starpu_sched_component_is_simple_worker (struct starpu_sched_component *component)
- int starpu_sched_component_is_combined_worker (struct starpu_sched_component *component)
- void starpu sched component worker pre exec hook (struct starpu task *task, unsigned sched ctx id)
- void starpu_sched_component_worker_post_exec_hook (struct starpu_task *task, unsigned sched_ctx
 id)

Flow-control Fifo Component API

- int starpu_sched_component_can_push (struct starpu_sched_component *component, struct starpu_← sched_component *to)
- int starpu sched component can pull (struct starpu sched component *component)
- int starpu_sched_component_can_pull_all (struct starpu_sched_component *component)
- double starpu_sched_component_estimated_load (struct starpu_sched_component *component)
- double starpu_sched_component_estimated_end_min (struct starpu_sched_component *component)
- double starpu_sched_component_estimated_end_min_add (struct starpu_sched_component *component, double exp_len)
- double starpu_sched_component_estimated_end_average (struct starpu_sched_component *component)
- struct starpu_sched_component * starpu_sched_component_fifo_create (struct starpu_sched_tree *tree, struct starpu_sched_component_fifo_data *fifo_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_fifo (struct starpu_sched_component *component)

Flow-control Prio Component API

- struct starpu_sched_component * starpu_sched_component_prio_create (struct starpu_sched_tree *tree, struct starpu_sched_component_prio_data *prio_data) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_prio (struct starpu_sched_component *component)

Resource-mapping Work-Stealing Component API

• struct starpu_sched_component * starpu_sched_component_work_stealing_create (struct starpu_ sched_tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC

- int starpu sched component is work stealing (struct starpu sched component *component)
- int starpu sched tree work stealing push task (struct starpu task *task)

Resource-mapping Random Component API

- struct starpu_sched_component * starpu_sched_component_random_create (struct starpu_sched_tree *tree, void *arg) STARPU ATTRIBUTE MALLOC
- int starpu sched component is random (struct starpu sched component *)

Resource-mapping Eager Component API

- struct starpu_sched_component * starpu_sched_component_eager_create (struct starpu_sched_tree *tree, void *arg) STARPU ATTRIBUTE MALLOC
- int starpu_sched_component_is_eager (struct starpu_sched_component *)

Resource-mapping Eager-Calibration Component API

- struct starpu_sched_component * starpu_sched_component_eager_calibration_create (struct starpu_sched_tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_eager_calibration (struct starpu_sched_component *)

Resource-mapping MCT Component API

- struct starpu_sched_component * starpu_sched_component_mct_create (struct starpu_sched_tree *tree, struct starpu sched component mct data *mct data) STARPU ATTRIBUTE MALLOC
- int starpu_sched_component_is_mct (struct starpu_sched_component *component)

Resource-mapping Heft Component API

- struct starpu_sched_component * starpu_sched_component_heft_create (struct starpu_sched_tree *tree, struct starpu_sched_component_mct_data *mct_data) STARPU_ATTRIBUTE_MALLOC
- int starpu sched component is heft (struct starpu sched component *component)

Special-purpose Best Implementation Component API

struct starpu_sched_component * starpu_sched_component_best_implementation_create (struct starpu_sched_tree *tree, void *arg) STARPU_ATTRIBUTE_MALLOC

Special-purpose Perfmodel_Select Component API

- struct starpu_sched_component * starpu_sched_component_perfmodel_select_create (struct starpu_sched_tree *tree, struct starpu_sched_component_perfmodel_select_data *perfmodel_select_data)
 STARPU_ATTRIBUTE_MALLOC
- int starpu_sched_component_is_perfmodel_select (struct starpu_sched_component *component)

Recipe Component API

- struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe_← create (void) STARPU ATTRIBUTE MALLOC
- struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe
 _create_singleton (struct starpu_sched_component *(*create_component)(struct starpu_sched_tree
 *tree, void *arg), void *arg) STARPU_ATTRIBUTE_MALLOC
- void starpu_sched_component_composed_recipe_add (struct starpu_sched_component_composed_
 recipe *recipe, struct starpu_sched_component *(*create_component)(struct starpu_sched_tree *tree, void *arg), void *arg)
- void starpu_sched_component_composed_recipe_destroy (struct starpu_sched_component_composed ← recipe *)
- struct starpu_sched_component * starpu_sched_component_composed_component_create (struct starpu_sched_tree *tree, struct starpu_sched_component_composed_recipe *recipe) STARPU_AT
 TRIBUTE MALLOC
- struct starpu_sched_tree * starpu_sched_component_make_scheduler (unsigned sched_ctx_id, struct starpu_sched_component_specs s)

Generic Scheduling Component API

- typedef struct starpu_sched_component *(* starpu_sched_component_create_t) (struct starpu_sched_
 tree *tree, void *data)
- struct starpu_sched_component * starpu_sched_component_create (struct starpu_sched_tree *tree, const char *name) STARPU_ATTRIBUTE_MALLOC
- void starpu_sched_component_destroy (struct starpu_sched_component *component)
- void starpu_sched_component_destroy_rec (struct starpu_sched_component *component)
- void starpu_sched_component_add_child (struct starpu_sched_component *component, struct starpu
 sched_component *child)
- int starpu_sched_component_can_execute_task (struct starpu_sched_component *component, struct starpu_task *task)
- int STARPU_WARN_UNUSED_RESULT starpu_sched_component_execute_preds (struct starpu_sched
 _component *component, struct starpu_task *task, double *length)
- double starpu_sched_component_transfer_length (struct starpu_sched_component *component, struct starpu task *task)
- void starpu_sched_component_prefetch_on_node (struct starpu_sched_component *component, struct starpu_task *task)

Basic API

- #define STARPU SCHED SIMPLE DECIDE MASK
- #define STARPU_SCHED_SIMPLE_DECIDE_WORKERS
- #define STARPU SCHED SIMPLE DECIDE MEMNODES
- #define STARPU SCHED SIMPLE DECIDE ARCHS
- #define STARPU SCHED SIMPLE PERFMODEL
- #define STARPU SCHED SIMPLE IMPL
- #define STARPU_SCHED_SIMPLE_FIFO_ABOVE
- #define STARPU_SCHED_SIMPLE_FIFO_ABOVE_PRIO
- #define STARPU_SCHED_SIMPLE_FIFOS_BELOW
- #define STARPU SCHED SIMPLE FIFOS BELOW PRIO
- #define STARPU SCHED SIMPLE WS BELOW
- #define STARPU SCHED SIMPLE COMBINED WORKERS
- void starpu_sched_component_initialize_simple_scheduler (starpu_sched_component_create_t create_← decision component, void *data, unsigned flags, unsigned sched ctx id)

32.28 starpu sched ctx.h File Reference

#include <starpu.h>

Functions

Scheduling Context Worker Collection

- struct starpu_worker_collection * starpu_sched_ctx_create_worker_collection (unsigned sched_ctx_id, enum starpu_worker_collection_type type) STARPU_ATTRIBUTE_MALLOC
- void starpu_sched_ctx_delete_worker_collection (unsigned sched_ctx_id)
- struct starpu_worker_collection * starpu_sched_ctx_get_worker_collection (unsigned sched_ctx_id)

Scheduling Contexts Basic API

- #define STARPU_SCHED_CTX_POLICY_NAME
- #define STARPU SCHED CTX POLICY STRUCT
- #define STARPU SCHED CTX POLICY MIN PRIO
- #define STARPU SCHED CTX POLICY MAX PRIO
- #define STARPU_SCHED_CTX_HIERARCHY_LEVEL

- #define STARPU SCHED CTX NESTED
- #define STARPU_SCHED_CTX_AWAKE_WORKERS
- #define STARPU_SCHED_CTX_POLICY_INIT
- #define STARPU SCHED CTX USER DATA
- #define STARPU SCHED CTX CUDA NSMS
- #define STARPU SCHED CTX SUB CTXS
- void(*)(unsigned) starpu_sched_ctx_get_sched_policy_init (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_create (int *workerids_ctx, int nworkers_ctx, const char *sched_ctx_name,...)
- unsigned starpu_sched_ctx_create_inside_interval (const char *policy_name, const char *sched_ctx_name, int min_ncpus, int max_ncpus, int min_ncpus, int max_ncpus, int max_ncpus, unsigned allow_overlap)
- void starpu_sched_ctx_register_close_callback (unsigned sched_ctx_id, void(*close_callback)(unsigned sched_ctx_id, void *args), void *args)
- void starpu sched ctx add workers (int *workerids ctx, unsigned nworkers ctx, unsigned sched ctx id)
- void starpu_sched_ctx_remove_workers (int *workerids_ctx, unsigned nworkers_ctx, unsigned sched_ctx
 id)
- void starpu_sched_ctx_display_workers (unsigned sched_ctx_id, FILE *f)
- void starpu_sched_ctx_delete (unsigned sched_ctx_id)
- void starpu_sched_ctx_set_inheritor (unsigned sched_ctx_id, unsigned inheritor)
- unsigned starpu_sched_ctx_get_inheritor (unsigned sched_ctx_id)
- unsigned starpu sched ctx get hierarchy level (unsigned sched ctx id)
- void starpu_sched_ctx_set_context (unsigned *sched_ctx_id)
- unsigned starpu sched ctx get context (void)
- void starpu_sched_ctx_stop_task_submission (void)
- void starpu sched ctx finished submit (unsigned sched ctx id)
- unsigned starpu sched ctx get workers list (unsigned sched ctx id, int **workerids)
- unsigned starpu_sched_ctx_get_workers_list_raw (unsigned sched_ctx_id, int **workerids)
- unsigned starpu_sched_ctx_get_nworkers (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_get_nshared_workers (unsigned sched_ctx_id, unsigned sched_ctx_id2)
- unsigned starpu_sched_ctx_contains_worker (int workerid, unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_contains_type_of_worker (enum starpu_worker_archtype arch, unsigned sched ctx id)
- unsigned starpu_sched_ctx_worker_get_id (unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_get_ctx_for_task (struct starpu_task *task)
- unsigned starpu_sched_ctx_overlapping_ctxs_on_worker (int workerid)
- void * starpu_sched_ctx_get_user_data (unsigned sched_ctx_id)
- void starpu_sched_ctx_set_user_data (unsigned sched_ctx_id, void *user_data)
- void starpu_sched_ctx_set_policy_data (unsigned sched_ctx_id, void *policy_data)
- void * starpu_sched_ctx_get_policy_data (unsigned sched_ctx_id)
- struct starpu_sched_policy * starpu_sched_ctx_get_sched_policy (unsigned sched_ctx_id)
- void * starpu_sched_ctx_exec_parallel_code (void *(*func)(void *), void *param, unsigned sched_ctx_id)
- int starpu sched ctx get nready tasks (unsigned sched ctx id)
- double starpu sched ctx get nready flops (unsigned sched ctx id)
- void starpu sched ctx list task counters increment (unsigned sched ctx id, int workerid)
- void starpu_sched_ctx_list_task_counters_decrement (unsigned sched_ctx_id, int workerid)
- void starpu_sched_ctx_list_task_counters_reset (unsigned sched_ctx_id, int workerid)
- void starpu_sched_ctx_list_task_counters_increment_all_ctx_locked (struct starpu_task *task, unsigned sched_ctx_id)
- void starpu_sched_ctx_list_task_counters_decrement_all_ctx_locked (struct starpu_task *task, unsigned sched ctx id)
- void starpu_sched_ctx_list_task_counters_reset_all (struct starpu_task *task, unsigned sched_ctx_id)
- void starpu_sched_ctx_set_priority (int *workers, int nworkers, unsigned sched_ctx_id, unsigned priority)
- unsigned starpu sched ctx get priority (int worker, unsigned sched ctx id)
- void **starpu_sched_ctx_get_available_cpuids** (unsigned sched_ctx_id, int **cpuids, int *ncpuids)
- void starpu sched ctx bind current thread to cpuid (unsigned cpuid)
- int starpu_sched_ctx_book_workers_for_task (unsigned sched_ctx_id, int *workerids, int nworkers)

- void starpu_sched_ctx_unbook_workers_for_task (unsigned sched_ctx_id, int master)
- unsigned starpu_sched_ctx_worker_is_master_for_child_ctx (int workerid, unsigned sched_ctx_id)
- unsigned starpu_sched_ctx_master_get_context (int masterid)
- void starpu_sched_ctx_revert_task_counters_ctx_locked (unsigned sched_ctx_id, double flops)
- void starpu_sched_ctx_move_task_to_ctx_locked (struct starpu_task *task, unsigned sched_ctx, unsigned with_repush)
- int starpu_sched_ctx_get_worker_rank (unsigned sched_ctx_id)
- unsigned starpu sched ctx has starpu scheduler (unsigned sched ctx id, unsigned *awake workers)
- int starpu sched ctx get stream worker (unsigned sub ctx)
- int starpu sched ctx get nsms (unsigned sched ctx)
- void starpu sched ctx get sms interval (int stream workerid, int *start, int *end)

Scheduling Context Priorities

- #define STARPU MIN PRIO
- #define STARPU MAX PRIO
- #define STARPU DEFAULT PRIO
- int starpu_sched_ctx_get_min_priority (unsigned sched_ctx_id)
- int starpu sched ctx get max priority (unsigned sched ctx id)
- int starpu_sched_ctx_set_min_priority (unsigned sched_ctx_id, int min_prio)
- int starpu sched ctx set max priority (unsigned sched ctx id, int max prio)
- int starpu sched ctx min priority is set (unsigned sched ctx id)
- int starpu_sched_ctx_max_priority_is_set (unsigned sched_ctx_id)

32.29 starpu_sched_ctx_hypervisor.h File Reference

Data Structures

• struct starpu_sched_ctx_performance_counters

Functions

Scheduling Context Link with Hypervisor

- void starpu sched ctx set perf counters (unsigned sched ctx id, void *perf counters)
- void starpu_sched_ctx_call_pushed_task_cb (int workerid, unsigned sched_ctx_id)
- void starpu_sched_ctx_notify_hypervisor_exists (void)
- unsigned starpu_sched_ctx_check_if_hypervisor_exists (void)
- void **starpu_sched_ctx_update_start_resizing_sample** (unsigned sched_ctx_id, double start_sample)

32.29.1 Function Documentation

32.29.1.1 starpu_sched_ctx_set_perf_counters()

```
void starpu_sched_ctx_set_perf_counters (
          unsigned sched_ctx_id,
          void * perf_counters )
```

Indicate to starpu the pointer to the performance counter

32.29.1.2 starpu_sched_ctx_call_pushed_task_cb()

Callback that lets the scheduling policy tell the hypervisor that a task was pushed on a worker

32.29.1.3 starpu_sched_ctx_notify_hypervisor_exists()

Allow the hypervisor to let starpu know it's initialised

32.29.1.4 starpu_sched_ctx_check_if_hypervisor_exists()

Ask starpu if it is informed if the hypervisor is initialised

32.30 starpu_scheduler.h File Reference

```
#include <starpu.h>
```

Data Structures

· struct starpu_sched_policy

Typedefs

typedef void(* starpu_notify_ready_soon_func) (void *data, struct starpu_task *task, double delay)

Functions

- struct starpu sched policy ** starpu sched get predefined policies ()
- void starpu_worker_get_sched_condition (int workerid, starpu_pthread_mutex_t **sched_mutex, starpu_

 pthread_cond_t **sched_cond)
- unsigned long starpu task get job id (struct starpu task *task)
- int starpu_sched_get_min_priority (void)
- · int starpu sched get max priority (void)
- int starpu_sched_set_min_priority (int min_prio)
- int starpu_sched_set_max_priority (int max_prio)
- int starpu worker can execute task (unsigned workerid, struct starpu task *task, unsigned nimpl)
- int starpu_worker_can_execute_task_impl (unsigned workerid, struct starpu_task *task, unsigned *impl_
 mask)
- int starpu_worker_can_execute_task_first_impl (unsigned workerid, struct starpu_task *task, unsigned *nimpl)
- int starpu_push_local_task (int workerid, struct starpu_task *task, int back)
- int starpu push task end (struct starpu task *task)
- int starpu_get_prefetch_flag (void)
- int starpu_prefetch_task_input_on_node_prio (struct starpu_task *task, unsigned node, int prio)
- int starpu_prefetch_task_input_on_node (struct starpu_task *task, unsigned node)
- int starpu_idle_prefetch_task_input_on_node_prio (struct starpu_task *task, unsigned node, int prio)
- int starpu_idle_prefetch_task_input_on_node (struct starpu_task *task, unsigned node)
- int starpu prefetch task input for prio (struct starpu task *task, unsigned worker, int prio)
- int starpu_prefetch_task_input_for (struct starpu_task *task, unsigned worker)
- int starpu_idle_prefetch_task_input_for_prio (struct starpu_task *task, unsigned worker, int prio)
- int starpu_idle_prefetch_task_input_for (struct starpu_task *task, unsigned worker)
- uint32_t starpu_task_footprint (struct starpu_perfmodel *model, struct starpu_task *task, struct starpu_
 perfmodel arch *arch, unsigned nimpl)
- uint32_t starpu_task_data_footprint (struct starpu_task *task)
- double starpu_task_expected_length (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)

- double starpu_worker_get_relative_speedup (struct starpu_perfmodel_arch *perf_arch)
- double starpu_task_expected_data_transfer_time (unsigned memory_node, struct starpu_task *task)
- double starpu_task_expected_data_transfer_time_for (struct starpu_task *task, unsigned worker)
- double starpu_data_expected_transfer_time (starpu_data_handle_t handle, unsigned memory_node, enum starpu_data_access_mode mode)
- double starpu_task_expected_energy (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- double starpu_task_expected_conversion_time (struct starpu_task *task, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- void starpu task notify ready soon register (starpu notify ready soon func f, void *data)
- void starpu_sched_ctx_worker_shares_tasks_lists (int workerid, int sched_ctx_id)
- void starpu sched task break (struct starpu task *task)

Worker operations

- int starpu wake worker relax (int workerid)
- int starpu wake worker no relax (int workerid)
- int starpu wake worker locked (int workerid)
- · int starpu wake worker relax light (int workerid)

32.31 starpu_simgrid_wrap.h File Reference

#include <starpu_config.h>

Macros

#define main

32.32 starpu_sink.h File Reference

Functions

void starpu_sink_common_worker (int argc, char **argv)

32.33 starpu_stdlib.h File Reference

#include <starpu.h>

Macros

- #define STARPU MALLOC PINNED
- #define STARPU_MALLOC_COUNT
- #define STARPU MALLOC NORECLAIM
- #define STARPU MEMORY WAIT
- #define STARPU_MEMORY_OVERFLOW
- #define STARPU_MALLOC_SIMULATION_FOLDED
- #define starpu_data_malloc_pinned_if_possible
- #define starpu_data_free_pinned_if_possible

Typedefs

- typedef int(* starpu malloc hook) (unsigned dst node, void **A, size t dim, int flags)
- typedef int(* starpu_free_hook) (unsigned dst_node, void *A, size_t dim, int flags)

Functions

- void starpu_malloc_set_align (size_t align)
- int starpu malloc (void **A, size t dim)
- int starpu_free (void *A)
- int starpu_malloc_flags (void **A, size_t dim, int flags)
- int starpu free flags (void *A, size t dim, int flags)
- void starpu_malloc_set_hooks (starpu_malloc_hook malloc_hook, starpu_free_hook free_hook)
- int starpu_memory_pin (void *addr, size_t size)
- int starpu memory unpin (void *addr, size t size)
- starpu_ssize_t starpu_memory_get_total (unsigned node)
- starpu ssize t starpu memory get available (unsigned node)
- starpu ssize t starpu memory get total all nodes (void)
- starpu_ssize_t starpu_memory_get_available_all_nodes (void)
- int starpu_memory_allocate (unsigned node, size_t size, int flags)
- void starpu_memory_deallocate (unsigned node, size_t size)
- void starpu_memory_wait_available (unsigned node, size_t size)
- void starpu sleep (float nb sec)
- void starpu_usleep (float nb_micro_sec)

32.34 starpu_task.h File Reference

```
#include <starpu.h>
#include <errno.h>
#include <assert.h>
#include <cuda.h>
```

Data Structures

- · struct starpu_codelet
- struct starpu data descr
- struct starpu_task

Macros

- #define STARPU NOWHERE
- #define STARPU CPU
- #define STARPU CUDA
- #define STARPU OPENCL
- #define STARPU_MIC
- #define STARPU MPI MS
- #define STARPU CODELET SIMGRID EXECUTE
- #define STARPU_CODELET_SIMGRID_EXECUTE_AND_INJECT
- #define STARPU_CODELET_NOPLANS
- #define STARPU_CUDA_ASYNC
- #define STARPU_OPENCL_ASYNC
- #define STARPU_MAIN_RAM
- #define STARPU_TASK_INVALID
- #define STARPU_MULTIPLE_CPU_IMPLEMENTATIONS
- #define STARPU MULTIPLE CUDA IMPLEMENTATIONS
- #define STARPU MULTIPLE OPENCL IMPLEMENTATIONS
- #define STARPU VARIABLE NBUFFERS
- #define STARPU SPECIFIC NODE LOCAL
- #define STARPU_SPECIFIC_NODE_CPU

- #define STARPU SPECIFIC NODE SLOW
- #define STARPU_SPECIFIC_NODE_FAST
- #define STARPU_TASK_TYPE_NORMAL
- #define STARPU TASK TYPE INTERNAL
- #define STARPU TASK TYPE DATA ACQUIRE
- #define STARPU TASK INITIALIZER
- #define STARPU TASK GET NBUFFERS(task)
- #define STARPU TASK GET HANDLE(task, i)
- #define STARPU_TASK_GET_HANDLES(task)
- #define STARPU TASK SET HANDLE(task, handle, i)
- #define STARPU_CODELET_GET_MODE(codelet, i)
- #define STARPU CODELET SET MODE(codelet, mode, i)
- #define STARPU_TASK_GET_MODE(task, i)
- #define STARPU TASK SET MODE(task, mode, i)
- #define STARPU_CODELET_GET_NODE(codelet, i)
- #define STARPU CODELET SET NODE(codelet, node, i)

Typedefs

- typedef void(* starpu_cpu_func_t) (void **, void *)
- typedef void(* starpu cuda func t) (void **, void *)
- typedef void(* starpu_opencl_func_t) (void **, void *)
- typedef void(* starpu_mic_kernel_t) (void **, void *)
- typedef starpu_mic_kernel_t(* starpu_mic_func_t) (void)
- typedef void(* starpu_mpi_ms_kernel_t) (void **, void *)
- typedef starpu_mpi_ms_kernel_t(* starpu_mpi_ms_func_t) (void)

Enumerations

- enum starpu_codelet_type { STARPU_SEQ, STARPU_SPMD, STARPU_FORKJOIN }
- enum starpu_task_status {

STARPU_TASK_INVALID, STARPU_TASK_INVALID, STARPU_TASK_BLOCKED, STARPU_TASK_RE ↔ ADY,

 $\label{task_running} \textbf{STARPU_TASK_RUNNING}, \textbf{STARPU_TASK_FINISHED}, \textbf{STARPU_TASK_BLOCKED_ON_TAG}, \textbf{STARPU_TASK_BLOCKED_ON_TASK}, \\ \textbf{PU_TASK_BLOCKED_ON_TASK}, \\ \textbf{STARPU_TASK_BLOCKED_ON_TASK}, \\ \textbf{STARPU_TASK_BLOCKED_ON_TASK_BLOCK$

STARPU_TASK_BLOCKED_ON_DATA, STARPU_TASK_STOPPED }

Functions

- void starpu_task_init (struct starpu_task *task)
- void starpu_task_clean (struct starpu_task *task)
- struct starpu task * starpu task create (void) STARPU ATTRIBUTE MALLOC
- void starpu task destroy (struct starpu task *task)
- int starpu task submit (struct starpu task *task) STARPU WARN UNUSED RESULT
- int starpu_task_submit_to_ctx (struct starpu_task *task, unsigned sched_ctx_id)
- int starpu_task_finished (struct starpu_task *task) STARPU_WARN_UNUSED_RESULT
- int starpu_task_wait (struct starpu_task *task) STARPU_WARN_UNUSED_RESULT
- int starpu_task_wait_array (struct starpu_task **tasks, unsigned nb_tasks) STARPU_WARN_UNUSED_

 RESULT
- int starpu_task_wait_for_all (void)
- int starpu_task_wait_for_n_submitted (unsigned n)
- int starpu_task_wait_for_all_in_ctx (unsigned sched_ctx_id)
- int starpu_task_wait_for_n_submitted_in_ctx (unsigned sched_ctx_id, unsigned n)
- int starpu_task_wait_for_no_ready (void)
- int starpu task nready (void)
- int starpu_task_nsubmitted (void)

- void starpu_iteration_push (unsigned long iteration)
- void starpu_iteration_pop (void)
- · void starpu do schedule (void)
- void starpu codelet init (struct starpu codelet *cl)
- void starpu codelet display stats (struct starpu codelet *cl)
- struct starpu task * starpu task get current (void)
- int starpu_task_get_current_data_node (unsigned i)
- const char * starpu_task_get_model_name (struct starpu_task *task)
- const char * starpu task get name (struct starpu task *task)
- struct starpu_task * starpu_task_dup (struct starpu_task *task)
- void starpu task set implementation (struct starpu task *task, unsigned impl)
- unsigned starpu_task_get_implementation (struct starpu_task *task)
- void starpu_create_sync_task (starpu_tag_t sync_tag, unsigned ndeps, starpu_tag_t *deps, void(*callback)(void *), void *callback_arg)

32.35 starpu_task_bundle.h File Reference

Typedefs

typedef struct _starpu_task_bundle * starpu_task_bundle_t

Functions

- void starpu task bundle create (starpu task bundle t *bundle)
- int starpu_task_bundle_insert (starpu_task_bundle_t bundle, struct starpu_task *task)
- int starpu task bundle remove (starpu task bundle t bundle, struct starpu task *task)
- · void starpu task bundle close (starpu task bundle t bundle)
- double starpu_task_bundle_expected_length (starpu_task_bundle_t bundle, struct starpu_perfmodel_arch *arch, unsigned nimpl)
- double starpu_task_bundle_expected_data_transfer_time (starpu_task_bundle_t bundle, unsigned memory_node)
- double starpu_task_bundle_expected_energy (starpu_task_bundle_t bundle, struct starpu_perfmodel_arch *arch, unsigned nimpl)

32.36 starpu_task_list.h File Reference

```
#include <starpu_task.h>
#include <starpu util.h>
```

Data Structures

· struct starpu_task_list

Functions

- void starpu_task_list_init (struct starpu_task_list *list)
- void starpu_task_list_push_front (struct starpu_task_list *list, struct starpu_task *task)
- void starpu_task_list_push_back (struct starpu_task_list *list, struct starpu_task *task)
- struct starpu_task * starpu_task_list_front (const struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_back (const struct starpu_task_list *list)
- int starpu task list empty (const struct starpu task list *list)
- void starpu_task_list_erase (struct starpu_task_list *list, struct starpu_task *task)
- struct starpu task * starpu task list pop front (struct starpu task list *list)
- struct starpu_task * starpu_task_list_pop_back (struct starpu_task_list *list)

- struct starpu_task * starpu_task_list_begin (const struct starpu_task_list *list)
- struct starpu_task * starpu_task_list_next (const struct starpu_task *task)
- int starpu_task_list_ismember (const struct starpu_task_list *list, const struct starpu_task *look)
- void starpu_task_list_move (struct starpu_task_list *ldst, struct starpu_task_list *lsrc)

32.37 starpu_task_util.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <assert.h>
#include <starpu.h>
```

Data Structures

struct starpu_codelet_pack_arg_data

Macros

- #define STARPU_MODE_SHIFT
- #define STARPU VALUE
- #define STARPU_CALLBACK
- #define STARPU CALLBACK WITH ARG
- #define STARPU_CALLBACK_ARG
- #define STARPU PRIORITY
- #define STARPU_EXECUTE_ON_NODE
- #define STARPU_EXECUTE_ON_DATA
- #define STARPU_DATA_ARRAY
- #define STARPU_DATA_MODE_ARRAY
- #define STARPU TAG
- #define STARPU HYPERVISOR TAG
- #define STARPU FLOPS
- #define STARPU_SCHED_CTX
- #define STARPU_PROLOGUE_CALLBACK
- #define STARPU_PROLOGUE_CALLBACK_ARG
- #define STARPU_PROLOGUE_CALLBACK_POP
- #define STARPU_PROLOGUE_CALLBACK_POP_ARG
- #define STARPU EXECUTE ON WORKER
- #define STARPU_EXECUTE_WHERE
- #define STARPU_TAG_ONLY
- #define STARPU_POSSIBLY_PARALLEL
- #define STARPU WORKER ORDER
- #define STARPU NODE SELECTION POLICY
- #define STARPU NAME
- #define STARPU_CL_ARGS
- #define STARPU_CL_ARGS_NFREE
- #define STARPU TASK DEPS ARRAY
- #define STARPU_TASK_COLOR
- #define STARPU HANDLES SEQUENTIAL CONSISTENCY
- #define STARPU TASK SYNCHRONOUS
- #define STARPU_TASK_END_DEPS_ARRAY
- #define STARPU TASK END DEP
- #define STARPU_SHIFTED_MODE_MAX

Functions

- int starpu_task_set (struct starpu_task *task, struct starpu_codelet *cl,...)
- struct starpu task * starpu task build (struct starpu codelet *cl,...)
- int starpu_task_insert (struct starpu_codelet *cl,...)
- int starpu_insert_task (struct starpu_codelet *cl,...)
- void starpu_task_insert_data_make_room (struct starpu_codelet *cl, struct starpu_task *task, int *allocated buffers, int current buffer, int room)
- void starpu_task_insert_data_process_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated buffers, int *current buffer, int arg type, starpu data handle t handle)
- void starpu_task_insert_data_process_array_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated buffers, int *current buffer, int nb handles, starpu data handle t *handles)
- void starpu_task_insert_data_process_mode_array_arg (struct starpu_codelet *cl, struct starpu_task *task, int *allocated_buffers, int *current_buffer, int nb_descrs, struct starpu_data_descr *descrs)
- void starpu codelet pack args (void **arg buffer, size t *arg buffer size,...)
- void starpu codelet pack arg init (struct starpu codelet pack arg data *state)
- void starpu_codelet_pack_arg (struct starpu_codelet_pack_arg_data *state, const void *ptr, size_t ptr_size)
- void starpu_codelet_pack_arg_fini (struct starpu_codelet_pack_arg_data *state, void **cl_arg, size_t *cl
 _arg_size)
- void starpu codelet unpack args (void *cl arg,...)
- void starpu_codelet_unpack_args_and_copyleft (void *cl_arg, void *buffer, size_t buffer_size,...)

32.38 starpu_thread.h File Reference

```
#include <starpu_config.h>
#include <starpu_util.h>
#include <pthread.h>
#include <xbt/synchro_core.h>
#include <msg/msg.h>
#include <stdint.h>
```

Data Structures

- struct starpu_pthread_barrier_t
- struct starpu_pthread_spinlock_t
- struct starpu_pthread_wait_t
- struct starpu_pthread_queue_t

Macros

- #define starpu pthread setname(name)
- #define STARPU_PTHREAD_MUTEX_INITIALIZER
- #define STARPU PTHREAD COND INITIALIZER
- #define STARPU_PTHREAD_BARRIER_SERIAL_THREAD

Typedefs

- typedef msg_process_t starpu_pthread_t
- typedef int starpu_pthread_attr_t
- typedef xbt_mutex_t starpu_pthread_mutex_t
- typedef int starpu_pthread_mutexattr_t
- typedef int starpu_pthread_key_t
- typedef xbt_cond_t starpu_pthread_cond_t
- typedef int starpu pthread condattr t
- typedef xbt_mutex_t starpu_pthread_rwlock_t

- typedef int starpu_pthread_rwlockattr_t
- typedef int starpu_pthread_barrierattr_t
- typedef msg_sem_t starpu_sem_t

Functions

- int starpu_pthread_equal (starpu_pthread_t t1, starpu_pthread_t t2)
- starpu_pthread_t starpu_pthread_self (void)
- int **starpu_pthread_create_on** (char *name, starpu_pthread_t *thread, const starpu_pthread_attr_t *attr, void *(*start_routine)(void *), void *arg, msg_host_t host)
- int starpu_pthread_create (starpu_pthread_t *thread, const starpu_pthread_attr_t *attr, void *(*start_← routine)(void *), void *arg)
- int starpu pthread join (starpu pthread t thread, void **retval)
- int starpu_pthread_exit (void *retval) STARPU_ATTRIBUTE_NORETURN
- int starpu_pthread_attr_init (starpu_pthread_attr_t *attr)
- int starpu pthread attr destroy (starpu pthread attr t *attr)
- int starpu_pthread_attr_setdetachstate (starpu_pthread_attr_t *attr, int detachstate)
- int starpu_pthread_mutex_init (starpu_pthread_mutex_t *mutex, const starpu_pthread_mutexattr_
 t *mutexattr)
- int starpu_pthread_mutex_destroy (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_lock (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_unlock (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_trylock (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutexattr_gettype (const starpu_pthread_mutexattr_t *attr, int *type)
- int starpu pthread mutexattr settype (starpu pthread mutexattr t *attr, int type)
- int starpu_pthread_mutexattr_destroy (starpu_pthread_mutexattr_t *attr)
- int starpu_pthread_mutexattr_init (starpu_pthread_mutexattr_t *attr)
- int starpu_pthread_mutex_lock_sched (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_unlock_sched (starpu_pthread_mutex_t *mutex)
- int starpu_pthread_mutex_trylock_sched (starpu_pthread_mutex_t *mutex)
- void starpu_pthread_mutex_check_sched (starpu_pthread_mutex_t *mutex, char *file, int line)
- int starpu_pthread_key_create (starpu_pthread_key_t *key, void(*destr_function)(void *))
- int starpu_pthread_key_delete (starpu_pthread_key_t key)
- int starpu pthread setspecific (starpu pthread key t key, const void *pointer)
- void * starpu pthread getspecific (starpu pthread key t key)
- int starpu_pthread_cond_init (starpu_pthread_cond_t *cond, starpu_pthread_condattr_t *cond_attr)
- int starpu_pthread_cond_signal (starpu_pthread_cond_t *cond)
- int starpu pthread cond broadcast (starpu pthread cond t *cond)
- int starpu_pthread_cond_wait (starpu_pthread_cond_t *cond, starpu_pthread_mutex_t *mutex)
- int starpu_pthread_cond_timedwait (starpu_pthread_cond_t *cond, starpu_pthread_mutex_t *mutex, const struct timespec *abstime)
- int starpu_pthread_cond_destroy (starpu_pthread_cond_t *cond)
- int starpu_pthread_rwlock_init (starpu_pthread_rwlock_t *rwlock, const starpu_pthread_rwlockattr_t *attr)
- int starpu_pthread_rwlock_destroy (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_rdlock (starpu_pthread_rwlock_t *rwlock)
- int starpu pthread rwlock tryrdlock (starpu pthread rwlock t *rwlock)
- int starpu_pthread_rwlock_wrlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_trywrlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_rwlock_unlock (starpu_pthread_rwlock_t *rwlock)
- int starpu_pthread_barrier_init (starpu_pthread_barrier_t *barrier, const starpu_pthread_barrierattr_t *attr, unsigned count)
- int starpu pthread barrier destroy (starpu pthread barrier t *barrier)
- int starpu_pthread_barrier_wait (starpu_pthread_barrier_t *barrier)
- int starpu_pthread_spin_init (starpu_pthread_spinlock_t *lock, int pshared)
- int starpu_pthread_spin_destroy (starpu_pthread_spinlock_t *lock)

- int starpu_pthread_spin_lock (starpu_pthread_spinlock_t *lock)
- int starpu_pthread_spin_trylock (starpu_pthread_spinlock_t *lock)
- int starpu_pthread_spin_unlock (starpu_pthread_spinlock_t *lock)
- int starpu_pthread_queue_init (starpu_pthread_queue_t *q)
- int starpu_pthread_queue_signal (starpu_pthread_queue_t *q)
- int starpu_pthread_queue_broadcast (starpu_pthread_queue_t *q)
- int starpu_pthread_queue_destroy (starpu_pthread_queue_t *q)
- int starpu_pthread_wait_init (starpu_pthread_wait_t *w)
- int starpu_pthread_queue_register (starpu_pthread_wait_t *w, starpu_pthread_queue_t *q)
- int starpu pthread queue unregister (starpu pthread wait t *w, starpu pthread queue t *q)
- int starpu pthread wait reset (starpu pthread wait t *w)
- int starpu_pthread_wait_wait (starpu_pthread_wait_t *w)
- int starpu_pthread_wait_timedwait (starpu_pthread_wait_t *w, const struct timespec *abstime)
- int starpu_pthread_wait_destroy (starpu_pthread_wait_t *w)
- int starpu_sem_destroy (starpu_sem_t *)
- int starpu_sem_getvalue (starpu_sem_t *, int *)
- int starpu_sem_init (starpu_sem_t *, int, unsigned)
- int starpu_sem_post (starpu_sem_t *)
- int starpu_sem_trywait (starpu_sem_t *)
- int starpu_sem_wait (starpu_sem_t *)

32.38.1 Data Structure Documentation

32.38.1.1 struct starpu_pthread_barrier_t

Data Fields

| starpu_pthread_mutex_t | mutex |
|------------------------|--------------|
| starpu_pthread_cond_t | cond |
| starpu_pthread_cond_t | cond_destroy |
| unsigned | count |
| unsigned | done |
| unsigned | busy |

32.38.1.2 struct starpu_pthread_spinlock_t

Data Fields

| int taken | |
|-----------|--|
|-----------|--|

32.38.1.3 struct starpu_pthread_wait_t

Data Fields

| starpu_pthread_mutex_t | mutex | |
|------------------------|-------|--|
| starpu_pthread_cond_t | cond | |
| unsigned | block | |

32.38.1.4 struct starpu_pthread_queue_t

Data Fields

| starpu_pthread_mutex_t | mutex | |
|------------------------|-------|--|
|------------------------|-------|--|

Data Fields

| starpu_pthread_wait_t ** | queue | |
|--------------------------|------------|--|
| unsigned | allocqueue | |
| unsigned | nqueue | |

32.39 starpu_thread_util.h File Reference

```
#include <starpu_util.h>
#include <starpu_thread.h>
#include <errno.h>
```

Macros

- #define STARPU_PTHREAD_CREATE_ON(name, thread, attr, routine, arg, where)
- #define STARPU_PTHREAD_CREATE(thread, attr, routine, arg)
- #define STARPU_PTHREAD_JOIN(thread, retval)
- #define STARPU_PTHREAD_MUTEX_INIT(mutex, attr)
- #define STARPU PTHREAD MUTEX DESTROY(mutex)
- #define _STARPU_CHECK_NOT_SCHED_MUTEX(mutex, file, line)
- #define STARPU PTHREAD MUTEX LOCK(mutex)
- #define STARPU PTHREAD MUTEX LOCK SCHED(mutex)
- #define STARPU_PTHREAD_MUTEX_TRYLOCK(mutex)
- #define STARPU_PTHREAD_MUTEX_TRYLOCK_SCHED(mutex)
- #define STARPU_PTHREAD_MUTEX_UNLOCK(mutex)
- #define STARPU_PTHREAD_MUTEX_UNLOCK_SCHED(mutex)
- #define STARPU_PTHREAD_KEY_CREATE(key, destr)
- #define STARPU PTHREAD KEY DELETE(key)
- #define STARPU_PTHREAD_SETSPECIFIC(key, ptr)
- #define STARPU_PTHREAD_GETSPECIFIC(key)
- #define STARPU_PTHREAD_RWLOCK_INIT(rwlock, attr)
- #define STARPU_PTHREAD_RWLOCK_RDLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_TRYRDLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_WRLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_TRYWRLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_UNLOCK(rwlock)
- #define STARPU_PTHREAD_RWLOCK_DESTROY(rwlock)
- #define STARPU PTHREAD COND INIT(cond, attr)
- #define STARPU_PTHREAD_COND_DESTROY(cond)
- #define STARPU_PTHREAD_COND_SIGNAL(cond)
- #define STARPU_PTHREAD_COND_BROADCAST(cond)
- #define STARPU PTHREAD COND WAIT(cond, mutex)
- #define STARPU_PTHREAD_COND_TIMEDWAIT(cond, mutex, abstime)
- #define STARPU_PTHREAD_BARRIER_INIT(barrier, attr, count)
- #define STARPU_PTHREAD_BARRIER_DESTROY(barrier)
- #define STARPU_PTHREAD_BARRIER_WAIT(barrier)

Functions

- static STARPU_INLINE int _starpu_pthread_mutex_trylock (starpu_pthread_mutex_t *mutex, char *file, int line)
- static STARPU_INLINE int _starpu_pthread_mutex_trylock_sched (starpu_pthread_mutex_t *mutex, char *file, int line)
- static STARPU_INLINE int _starpu_pthread_rwlock_tryrdlock (starpu_pthread_rwlock_t *rwlock, char *file, int line)
- static STARPU_INLINE int _starpu_pthread_rwlock_trywrlock (starpu_pthread_rwlock_t *rwlock, char *file, int line)
- static STARPU_INLINE int _starpu_pthread_cond_timedwait (starpu_pthread_cond_t *cond, starpu_
 pthread mutex t *mutex, const struct timespec *abstime, char *file, int line)

32.40 starpu_tree.h File Reference

Data Structures

struct starpu tree

Functions

- void **starpu_tree_reset_visited** (struct **starpu_tree** *tree, char *visited)
- void starpu tree prepare children (unsigned arity, struct starpu tree *father)
- void starpu tree insert (struct starpu tree *tree, int id, int level, int is pu, int arity, struct starpu tree *father)
- struct starpu tree * starpu tree get (struct starpu tree *tree, int id)
- struct starpu_tree * starpu_tree_get_neighbour (struct starpu_tree *tree, struct starpu_tree *node, char *visited, char *present)
- void starpu tree free (struct starpu tree *tree)

32.41 starpu util.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <stdint.h>
#include <string.h>
#include <assert.h>
#include <starpu_config.h>
#include <sys/time.h>
```

Macros

- #define STARPU GNUC PREREQ(maj, min)
- #define STARPU_UNLIKELY(expr)
- #define STARPU LIKELY(expr)
- #define STARPU_ATTRIBUTE_UNUSED
- #define STARPU ATTRIBUTE NORETURN
- #define STARPU ATTRIBUTE INTERNAL
- #define STARPU_ATTRIBUTE_MALLOC
- #define STARPU_ATTRIBUTE_WARN_UNUSED_RESULT
- #define STARPU_ATTRIBUTE_PURE
- #define STARPU_ATTRIBUTE_ALIGNED(size)
- #define STARPU_ATTRIBUTE_FORMAT(type, string, first)
- #define STARPU INLINE
- #define STARPU ATTRIBUTE CALLOC SIZE(num, size)
- #define STARPU_ATTRIBUTE_ALLOC_SIZE(size)

- · #define endif
- #define STARPU_WARN_UNUSED_RESULT
- #define STARPU_BACKTRACE_LENGTH
- #define STARPU_DUMP_BACKTRACE()
- #define STARPU_SIMGRID_ASSERT(x)
- #define STARPU ASSERT(x)
- #define STARPU_ASSERT_ACCESSIBLE(ptr)
- #define STARPU_ASSERT_MSG(x, msg, ...)
- #define _starpu_abort()
- #define STARPU ABORT()
- #define STARPU ABORT MSG(msg, ...)
- #define STARPU CHECK RETURN VALUE(err, message, ...)
- #define STARPU_CHECK_RETURN_VALUE_IS(err, value, message, ...)
- #define **STARPU_ATOMIC_SOMETHING**(name, expr)
- #define STARPU_ATOMIC_SOMETHINGL(name, expr)
- #define STARPU RMB()
- #define STARPU WMB()

32.42 starpu worker.h File Reference

```
#include <stdlib.h>
#include <starpu_config.h>
#include <starpu_thread.h>
#include <starpu_task.h>
#include <hwloc.h>
```

Data Structures

- · struct starpu_sched_ctx_iterator
- · struct starpu_worker_collection

Macros

• #define starpu worker get id check()

Enumerations

- enum starpu_node_kind {
 STARPU_UNUSED, STARPU_CPU_RAM, STARPU_CUDA_RAM, STARPU_OPENCL_RAM,
 STARPU_DISK_RAM, STARPU_MIC_RAM, STARPU_MPI_MS_RAM }
- enum starpu_worker_archtype {
 STARPU_CPU_WORKER, STARPU_CUDA_WORKER, STARPU_OPENCL_WORKER, STARPU_MIC_
 WORKER,
 STARPU_MPI_MS_WORKER, STARPU_ANY_WORKER }
- enum starpu worker collection type { STARPU WORKER TREE, STARPU WORKER LIST }

Functions

- unsigned starpu_worker_get_count (void)
- unsigned starpu_cpu_worker_get_count (void)
- unsigned starpu_cuda_worker_get_count (void)
- unsigned starpu_opencl_worker_get_count (void)
- unsigned starpu_mic_worker_get_count (void)
- unsigned starpu_mpi_ms_worker_get_count (void)
- unsigned starpu_mic_device_get_count (void)

492 File Documentation

- int starpu worker get id (void)
- unsigned starpu worker get id check (const char *f, int I)
- int starpu_worker_get_bindid (int workerid)
- void starpu_sched_find_all_worker_combinations (void)
- enum starpu_worker_archtype starpu_worker_get_type (int id)
- int starpu worker get count by type (enum starpu worker archtype type)
- unsigned starpu_worker_get_ids_by_type (enum starpu_worker_archtype type, int *workerids, unsigned maxsize)
- int starpu_worker_get_by_type (enum starpu_worker_archtype type, int num)
- int starpu worker get by devid (enum starpu worker archtype type, int devid)
- void starpu_worker_get_name (int id, char *dst, size_t maxlen)
- void starpu_worker_display_names (FILE *output, enum starpu_worker_archtype type)
- · int starpu worker get devid (int id)
- int starpu worker get mp nodeid (int id)
- struct starpu tree * starpu workers get tree (void)
- unsigned starpu_worker_get_sched_ctx_list (int worker, unsigned **sched_ctx)
- unsigned starpu worker is blocked in parallel (int workerid)
- unsigned starpu_worker_is_slave_somewhere (int workerid)
- char * starpu_worker_get_type_as_string (enum starpu_worker_archtype type)
- int starpu_bindid_get_workerids (int bindid, int **workerids)
- int starpu_worker_get_devids (enum starpu_worker_archtype type, int *devids, int num)
- int starpu_worker_get_stream_workerids (unsigned devid, int *workerids, enum starpu_worker_archtype type)
- unsigned starpu worker get sched ctx id stream (unsigned stream workerid)
- hwloc_cpuset_t starpu_worker_get_hwloc_cpuset (int workerid)
- hwloc_obj_t starpu_worker_get_hwloc_obj (int workerid)
- int starpu memory node get devid (unsigned node)
- unsigned starpu worker get local memory node (void)
- unsigned starpu_worker_get_memory_node (unsigned workerid)
- unsigned starpu_memory_nodes_get_count (void)
- int starpu memory_node_get_name (unsigned node, char *name, size_t size)
- int starpu_memory_nodes_get_numa_count (void)
- int starpu memory nodes numa id to devid (int osid)
- int starpu_memory_nodes_numa_devid_to_id (unsigned id)
- enum starpu_node_kind starpu_node_get_kind (unsigned node)
- unsigned starpu_combined_worker_get_count (void)
- · unsigned starpu worker is combined worker (int id)
- int starpu_combined_worker_get_id (void)
- int starpu_combined_worker_get_size (void)
- int starpu_combined_worker_get_rank (void)
- int starpu combined worker assign workerid (int nworkers, int workerid array[])
- int starpu_combined_worker_get_description (int workerid, int *worker_size, int **combined_workerid)
- int starpu_combined_worker_can_execute_task (unsigned workerid, struct starpu_task *task, unsigned nimpl)
- void starpu parallel task barrier init (struct starpu task *task, int workerid)
- void starpu_parallel_task_barrier_init_n (struct starpu_task *task, int worker_size)

Scheduling operations

- int starpu worker sched op pending (void)
- void starpu worker relax on (void)
- void starpu_worker_relax_off (void)
- int starpu worker get relax state (void)
- void starpu_worker_lock (int workerid)
- int starpu_worker_trylock (int workerid)
- void starpu worker unlock (int workerid)
- void starpu_worker_lock_self (void)
- void starpu_worker_unlock_self (void)
- void starpu_worker_set_going_to_sleep_callback (void(*callback)(unsigned workerid))
- void starpu_worker_set_waking_up_callback (void(*callback)(unsigned workerid))

Variables

- struct starpu_worker_collection worker_list
- · struct starpu worker collection worker tree

32.43 starpufft.h File Reference

Typedefs

- typedef double Complex starpufft complex
- typedef struct starpufft_plan * starpufft_plan
- · typedef float Complex starpufftf_complex
- typedef struct starpufftf plan * starpufftf_plan
- · typedef long double Complex starpufftl complex
- typedef struct starpufftl_plan * starpufftl_plan

Functions

- starpufft_plan_starpufft_plan_dft_1d (int n, int sign, unsigned flags)
- starpufft plan starpufft plan dft 2d (int n, int m, int sign, unsigned flags)
- starpufft_plan starpufft_plan_dft_r2c_1d (int n, unsigned flags)
- starpufft_plan starpufft_plan_dft_c2r_1d (int n, unsigned flags)
- void * starpufft malloc (size t n)
- void starpufft_free (void *p)
- int starpufft_execute (starpufft_plan p, void *in, void *out)
- struct starpu task * starpufft start (starpufft plan p, void *in, void *out)
- int starpufft_execute_handle (starpufft_plan p, starpu_data_handle_t in, starpu_data_handle_t out)
- struct starpu_task * starpufft_start_handle (starpufft_plan p, starpu_data_handle_t in, starpu_data_handle ←
 _t out)
- void starpufft_cleanup (starpufft_plan p)
- void starpufft_destroy_plan (starpufft_plan p)
- void starpufft_startstats (void)
- void starpufft stopstats (void)
- void starpufft_showstats (FILE *out)
- starpufftf_plan starpufftf_plan_dft_1d (int n, int sign, unsigned flags)
- starpufftf_plan_dft_2d (int n, int m, int sign, unsigned flags)
- starpufftf_plan_dft_r2c_1d (int n, unsigned flags)
- starpufftf plan starpufftf plan dft c2r_1d (int n, unsigned flags)
- void * starpufftf_malloc (size_t n)
- void starpufftf_free (void *p)
- int starpufftf_execute (starpufftf_plan p, void *in, void *out)
- struct starpu_task * starpufftf_start (starpufftf_plan p, void *in, void *out)
- int starpufftf_execute_handle (starpufftf_plan p, starpu_data_handle_t in, starpu_data_handle_t out)
- void starpufftf_cleanup (starpufftf_plan p)
- void starpufftf_destroy_plan (starpufftf_plan p)
- · void starpufftf_startstats (void)
- void starpufftf_stopstats (void)
- void starpufftf_showstats (FILE *out)
- starpufftl_plan starpufftl_plan_dft_1d (int n, int sign, unsigned flags)
- starpufftl plan starpufftl plan dft 2d (int n, int m, int sign, unsigned flags)
- starpufftl_plan_dft_r2c_1d (int n, unsigned flags)
- starpufftl_plan_dft_c2r_1d (int n, unsigned flags)
- void * starpufftl_malloc (size_t n)

494 File Documentation

- void starpufftl_free (void *p)
- int starpufftl_execute (starpufftl_plan p, void *in, void *out)
- struct starpu_task * starpufftl_start (starpufftl_plan p, void *in, void *out)
- int starpufftl_execute_handle (starpufftl_plan p, starpu_data_handle_t in, starpu_data_handle_t out)
- void starpufftl_cleanup (starpufftl_plan p)
- void starpufftl_destroy_plan (starpufftl_plan p)
- void starpufftl startstats (void)
- void starpufftl_stopstats (void)
- void starpufftl_showstats (FILE *out)

Variables

int starpufft_last_plan_number

32.44 sc hypervisor.h File Reference

```
#include <starpu.h>
#include <starpu_sched_ctx_hypervisor.h>
#include <sc_hypervisor_config.h>
#include <sc_hypervisor_monitoring.h>
#include <math.h>
```

Data Structures

struct sc_hypervisor_policy

Functions

- void * sc_hypervisor_init (struct sc_hypervisor_policy *policy)
- void sc hypervisor shutdown (void)
- void sc_hypervisor_register_ctx (unsigned sched_ctx, double total_flops)
- void sc hypervisor unregister ctx (unsigned sched ctx)
- void sc_hypervisor_post_resize_request (unsigned sched_ctx, int task_tag)
- void sc_hypervisor_resize_ctxs (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void sc hypervisor stop resize (unsigned sched ctx)
- void sc_hypervisor_start_resize (unsigned sched_ctx)
- const char * sc_hypervisor_get_policy ()
- void sc_hypervisor_add_workers_to_sched_ctx (int *workers_to_add, unsigned nworkers_to_add, unsigned sched ctx)
- void sc_hypervisor_remove_workers_from_sched_ctx (int *workers_to_remove, unsigned nworkers_to_
 remove, unsigned sched_ctx, unsigned now)
- void sc_hypervisor_move_workers (unsigned sender_sched_ctx, unsigned receiver_sched_ctx, int *workers_to_move, unsigned nworkers_to_move, unsigned now)
- void sc hypervisor size ctxs (unsigned *sched ctxs, int nsched ctxs, int *workers, int nworkers)
- unsigned sc_hypervisor_get_size_req (unsigned **sched_ctxs, int *nsched_ctxs, int **workers, int *nworkers)
- void sc_hypervisor_save_size_req (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- void sc_hypervisor_free_size_req (void)
- unsigned sc_hypervisor_can_resize (unsigned sched_ctx)
- void sc_hypervisor_set_type_of_task (struct starpu_codelet *cl, unsigned sched_ctx, uint32_t footprint, size_t data_size)
- void sc_hypervisor_update_diff_total_flops (unsigned sched_ctx, double diff_total_flops)

- void sc_hypervisor_update_diff_elapsed_flops (unsigned sched_ctx, double diff_task_flops)
- void sc_hypervisor_update_resize_interval (unsigned *sched_ctxs, int nsched_ctxs, int max_nworkers)
- void sc_hypervisor_get_ctxs_on_level (unsigned **sched_ctxs, int *nsched_ctxs, unsigned hierarchy_level, unsigned father sched ctx id)
- unsigned sc_hypervisor_get_nhierarchy_levels (void)
- void sc_hypervisor_get_leaves (unsigned *sched_ctxs, int nsched_ctxs, unsigned *leaves, int *nleaves)
- double sc_hypervisor_get_nready_flops_of_all_sons_of_sched_ctx (unsigned sched_ctx)
- void sc hypervisor print overhead ()
- void sc_hypervisor_init_worker (int workerid, unsigned sched_ctx)

Variables

• starpu_pthread_mutex_t act_hypervisor_mutex

32.45 sc_hypervisor_config.h File Reference

#include <sc_hypervisor.h>

Data Structures

- · struct sc_hypervisor_policy_config
- #define SC HYPERVISOR MAX IDLE
- #define SC HYPERVISOR MIN WORKING
- #define SC_HYPERVISOR_PRIORITY
- #define SC HYPERVISOR MIN WORKERS
- #define SC_HYPERVISOR_MAX_WORKERS
- #define SC HYPERVISOR GRANULARITY
- #define SC HYPERVISOR FIXED WORKERS
- #define SC HYPERVISOR MIN TASKS
- #define SC HYPERVISOR NEW WORKERS MAX IDLE
- #define SC_HYPERVISOR_TIME_TO_APPLY
- #define SC HYPERVISOR NULL
- #define SC HYPERVISOR ISPEED W SAMPLE
- #define SC HYPERVISOR ISPEED CTX SAMPLE
- #define SC_HYPERVISOR_TIME_SAMPLE
- #define MAX_IDLE_TIME
- #define MIN_WORKING_TIME
- void sc_hypervisor_set_config (unsigned sched_ctx, void *config)
- struct sc_hypervisor_policy_config * sc_hypervisor_get_config (unsigned sched_ctx)
- void sc_hypervisor_ctl (unsigned sched_ctx,...)

32.45.1 Data Structure Documentation

32.45.1.1 struct sc_hypervisor_policy_config

Methods that implement a hypervisor resizing policy.

Data Fields

| int | min_nworkers | Indicate the minimum number of workers needed by the context |
|-----|--------------|--|
| int | max_nworkers | Indicate the maximum number of workers needed by the context |
| int | granularity | Indicate the workers granularity of the context |

496 File Documentation

Data Fields

| int | priority[STARPU_NMAXWORKERS] | Indicate the priority of each worker to stay in the context the smaller the priority the faster it will be moved to another context |
|--------|-------------------------------------|---|
| double | max_idle[STARPU_NMAXWORKERS] | Indicate the maximum idle time accepted before a resize is triggered above this limit the priority of the worker is reduced |
| double | min_working[STARPU_NMAXWORKERS] | Indicate that underneath this limit the priority of the worker is reduced |
| int | fixed_workers[STARPU_NMAXWORKERS] | Indicate which workers can be moved and which ones are fixed |
| double | new_workers_max_idle | Indicate the maximum idle time accepted before a resize is triggered for the workers that just arrived in the new context |
| double | ispeed_w_sample[STARPU_NMAXWORKERS] | Indicate the sample used to compute the instant speed per worker |
| double | ispeed_ctx_sample | Indicate the sample used to compute the instant speed per ctxs |
| double | time_sample | Indicate the sample used to compute the instant speed per ctx (in seconds) |

32.46 sc_hypervisor_lp.h File Reference

```
#include <sc_hypervisor.h>
#include <starpu_config.h>
#include <glpk.h>
```

Functions

- double sc_hypervisor_lp_get_nworkers_per_ctx (int nsched_ctxs, int ntypes_of_workers, double res[nsched
 _ctxs][ntypes_of_workers], int total_nw[ntypes_of_workers], struct types_of_workers *tw, unsigned *in_←
 sched_ctxs)
- double sc_hypervisor_lp_get_tmax (int nw, int *workers)
- void sc_hypervisor_lp_round_double_to_int (int ns, int nw, double res[ns][nw], int res_rounded[ns][nw])
- void sc_hypervisor_lp_redistribute_resources_in_ctxs (int ns, int nw, int res_rounded[ns][nw], double res[ns][nw], unsigned *sched ctxs, struct types of workers *tw)
- void sc_hypervisor_lp_distribute_resources_in_ctxs (unsigned *sched_ctxs, int ns, int nw, int res_← rounded[ns][nw], double res[ns][nw], int *workers, int nworkers, struct types_of_workers *tw)
- void sc_hypervisor_lp_distribute_floating_no_resources_in_ctxs (unsigned *sched_ctxs, int ns, int nw, double res[ns][nw], int *workers, int nworkers, struct types_of_workers *tw)
- void sc_hypervisor_lp_place_resources_in_ctx (int ns, int nw, double w_in_s[ns][nw], unsigned *sched_ctxs, int *workers, unsigned do size, struct types of workers *tw)
- void sc_hypervisor_lp_share_remaining_resources (int ns, unsigned *sched_ctxs, int nworkers, int *workers)
- double sc_hypervisor_lp_find_tmax (double t1, double t2)
- unsigned sc_hypervisor_lp_execute_dichotomy (int ns, int nw, double w_in_s[ns][nw], unsigned solve_lp_
 integer, void *specific_data, double tmin, double tmax, double smallest_tmax, double(*lp_estimated_distrib←
 _func)(int ns, int nw, double draft_w_in_s[ns][nw], unsigned is_integer, double tmax, void *specifc_data))
- double sc_hypervisor_lp_simulate_distrib_flops (int nsched_ctxs, int ntypes_of_workers, double speed[nsched
 _ctxs][ntypes_of_workers], double flops[nsched_ctxs], double res[nsched_ctxs][ntypes_of_workers], int total_nw[ntypes_of_workers], unsigned sched_ctxs[nsched_ctxs], double vmax)
- double sc_hypervisor_lp_simulate_distrib_tasks (int ns, int nw, int nt, double w_in_s[ns][nw], double tasks[nw][nt], double times[nw][nt], unsigned is_integer, double tmax, unsigned *in_sched_ctxs, struct sc_hypervisor_policy_task_pool *tmp_task_pools)

double sc_hypervisor_lp_simulate_distrib_flops_on_sample (int ns, int nw, double final_w_in_s[ns][nw], unsigned is_integer, double tmax, double **speed, double flops[ns], double **final_flops_on_w)

32.47 sc_hypervisor_monitoring.h File Reference

#include <sc_hypervisor.h>

Data Structures

- · struct sc_hypervisor_resize_ack
- struct sc_hypervisor_wrapper

Functions

- struct sc_hypervisor_wrapper * sc_hypervisor_get_wrapper (unsigned sched_ctx)
- unsigned * sc hypervisor get sched ctxs ()
- int sc hypervisor get nsched ctxs ()
- int sc_hypervisor_get_nworkers_ctx (unsigned sched_ctx, enum starpu_worker_archtype arch)
- double sc_hypervisor_get_elapsed_flops_per_sched_ctx (struct sc_hypervisor_wrapper *sc_w)
- double sc_hypervisor_get_total_elapsed_flops_per_sched_ctx (struct sc_hypervisor_wrapper *sc_w)
- double sc_hypervisorsc_hypervisor_get_speed_per_worker_type (struct sc_hypervisor_wrapper *sc_w, enum starpu_worker_archtype arch)
- double sc_hypervisor_get_speed (struct sc_hypervisor_wrapper *sc_w, enum starpu_worker_archtype arch)

32.47.1 Data Structure Documentation

32.47.1.1 struct sc_hypervisor_wrapper

Wrapper of the contexts available in StarPU which contains all information about a context obtained by incrementing the performance counters. it is attached to a sched_ctx storing monitoring information

Data Fields

| unsigned | sched_ctx | the monitored context |
|-------------------------------|--------------------------------|--------------------------------------|
| struct | | |
| sc_hypervisor_policy_config * | config | The corresponding resize |
| | | configuration |
| double | start_time_w[STARPU_NMAXWORF | ☐R€}tart time of the resizing |
| | | sample of the workers of this |
| | | context |
| double | current_idle_time[STARPU_NMAXW | OTHEERIE]time counter of each |
| | | worker of the context |
| double | idle_time[STARPU_NMAXWORKER | S]The time the workers were idle |
| | | from the last resize |
| double | idle_start_time[STARPU_NMAXWO | I - I |
| | | started being idle |
| double | exec_time[STARPU_NMAXWORKE | RS]ime during which the worker |
| | | executed tasks |
| double | exec_start_time[STARPU_NMAXWC | RKime When the worker started |
| | | executing a task |
| int | worker_to_be_removed[STARPU_N | MAist/ofDworkers]that will leave the |
| | | context (lazy resizing process) |
| int | pushed_tasks[STARPU_NMAXWOF | KND De ber of tasks pushed on each |
| | | worker in this context |

498 File Documentation

Data Fields

| int | poped_tasks[STARPU_NMAXWORK | FNR Robber of tasks named from each |
|---------------------------------|-----------------------------------|---|
| ш | poped_tasks[STATT O_NMAXWOTT | worker in this context |
| double | total_flops | The total number of flops to |
| | | execute by the context |
| double | total_elapsed_flops[STARPU_NMAX | |
| | | each workers of the context |
| double | elapsed_flops[STARPU_NMAXWOR | · · |
| | | last resizing |
| size_t | elapsed_data[STARPU_NMAXWOR | |
| | | execute tasks on each worker in this context |
| int | elapsed_tasks[STARPU_NMAXWOF | |
| | ciapsed_tasks[e1/411 e_i44////vei | worker in this context |
| double | ref_speed[2] | the average speed of the type of |
| | | workers when they belonged to |
| | | this context 0 - cuda 1 - cpu |
| double | submitted_flops | Number of flops submitted to this |
| | | context |
| double | remaining_flops | Number of flops that still have to |
| | | be executed by the workers in this |
| | | context |
| double | start_time | Start time of the resizing sample of |
| double | roal start time | this context First time a task was pushed to |
| double | real_start_time | this context |
| double | hyp_react_start_time | Start time for sample in which the |
| | 7, | hypervisor is not allowed to react |
| | | bc too expensive |
| struct sc_hypervisor_resize_ack | resize_ack | Structure confirming the last resize |
| | | finished and a new one can be |
| | | done. Workers do not leave the |
| | | current context until the receiver |
| | | context does not ack the receive of |
| at a way with ward was to be | | these workers |
| starpu_pthread_mutex_t | mutex | Mutex needed to synchronize the |
| | | acknowledgment of the workers into the receiver context |
| unsigned | total flops available | Boolean indicating if the hypervisor |
| ansigned | total_nopo_avanabio | can use the flops corresponding to |
| | | the entire execution of the context |
| unsigned | to_be_sized | boolean indicating that a context is |
| | | being sized |
| unsigned | compute_idle[STARPU_NMAXWOR | B66pan indicating if we add the |
| | | idle of this worker to the idle of the |
| | | context |
| unsigned | compute_partial_idle[STARPU_NMA | |
| | | entiere idle of this worker to the |
| | | idle of the context or just half |
| unsigned | consider_max | consider the max in the lp |

32.48 sc_hypervisor_policy.h File Reference

#include <sc_hypervisor.h>

Data Structures

- · struct types of workers
- struct sc_hypervisor_policy_task_pool

Macros

- #define HYPERVISOR REDIM SAMPLE
- #define HYPERVISOR START REDIM SAMPLE
- · #define SC NOTHING
- #define SC IDLE
- #define SC_SPEED

Functions

- void sc_hypervisor_policy_add_task_to_pool (struct starpu_codelet *cl, unsigned sched_ctx, uint32_t foot-print, struct sc_hypervisor_policy_task_pool **task_pools, size_t data_size)
- void sc_hypervisor_policy_remove_task_from_pool (struct starpu_task *task, uint32_t footprint, struct sc_
 hypervisor_policy_task_pool **task_pools)
- struct sc_hypervisor_policy_task_pool * sc_hypervisor_policy_clone_task_pool (struct sc_hypervisor_
 policy_task_pool *tp)
- void sc_hypervisor_get_tasks_times (int nw, int nt, double times[nw][nt], int *workers, unsigned size_ctxs, struct sc_hypervisor_policy_task_pool *task_pools)
- unsigned sc_hypervisor_find_lowest_prio_sched_ctx (unsigned req_sched_ctx, int nworkers_to_move)
- int * sc_hypervisor_get_idlest_workers (unsigned sched_ctx, int *nworkers, enum starpu_worker_archtype arch)
- int * sc_hypervisor_get_idlest_workers_in_list (int *start, int *workers, int nall_workers, int *nworkers, enum starpu worker archtype arch)
- int sc_hypervisor_get_movable_nworkers (struct sc_hypervisor_policy_config *config, unsigned sched_ctx, enum starpu_worker_archtype arch)
- int sc_hypervisor_compute_nworkers_to_move (unsigned req_sched_ctx)
- unsigned sc_hypervisor_policy_resize (unsigned sender_sched_ctx, unsigned receiver_sched_ctx, unsigned force_resize, unsigned now)
- unsigned sc_hypervisor_policy_resize_to_unknown_receiver (unsigned sender_sched_ctx, unsigned now)
- double sc_hypervisor_get_ctx_speed (struct sc_hypervisor_wrapper *sc_w)
- double sc_hypervisor_get_slowest_ctx_exec_time (void)
- double sc_hypervisor_get_fastest_ctx_exec_time (void)
- double sc_hypervisor_get_speed_per_worker (struct sc_hypervisor_wrapper *sc_w, unsigned worker)
- double sc_hypervisor_get_ref_speed_per_worker_type (struct sc_hypervisor_wrapper *sc_w, enum starpu worker archtype arch)
- double sc_hypervisor_get_avg_speed (enum starpu_worker_archtype arch)
- void sc_hypervisor_check_if_consider_max (struct types_of_workers *tw)
- void sc_hypervisor_group_workers_by_type (struct types_of_workers *tw, int *total_nw)
- enum starpu_worker_archtype sc_hypervisor_get_arch_for_index (unsigned w, struct types_of_workers *tw)
- unsigned sc_hypervisor_get_index_for_arch (enum starpu_worker_archtype arch, struct types_of_workers *tw)
- unsigned sc hypervisor criteria fulfilled (unsigned sched ctx, int worker)
- unsigned sc_hypervisor_check_idle (unsigned sched_ctx, int worker)

500 File Documentation

- unsigned sc_hypervisor_check_speed_gap_btw_ctxs (unsigned *sched_ctxs, int nsched_ctxs, int *workers, int nworkers)
- unsigned sc_hypervisor_check_speed_gap_btw_ctxs_on_level (int level, int *workers_in, int nworkers_in, unsigned father_sched_ctx_id, unsigned **sched_ctxs, int *nsched_ctxs)
- unsigned sc_hypervisor_get_resize_criteria ()
- struct types_of_workers * sc_hypervisor_get_types_of_workers (int *workers, unsigned nworkers)

32.49 starpurm.h File Reference

```
#include <hwloc.h>
#include <starpurm_config.h>
```

Typedefs

- typedef int starpurm drs ret t
- typedef void * starpurm drs desc t
- typedef void * starpurm drs cbs t
- typedef void(* starpurm_drs_cb_t) (void *)
- typedef void * starpurm block cond t
- typedef int(* starpurm_polling_t) (void *)

Enumerations

 enum e_starpurm_drs_ret { starpurm_DRS_SUCCESS, starpurm_DRS_DISABLD, starpurm_DRS_PERM, starpurm_DRS_EINVAL }

Functions

Initialisation

- void starpurm_initialize_with_cpuset (hwloc_cpuset_t initially_owned_cpuset)
- void starpurm_initialize (void)
- void starpurm_shutdown (void)

Spawn

- void starpurm spawn kernel on cpus (void *data, void(*f)(void *), void *args, hwloc cpuset t cpuset)
- void starpurm_spawn_kernel_on_cpus_callback (void *data, void(*f)(void *), void *args, hwloc_cpuset_t cpuset, void(*cb_f)(void *), void *cb_args)
- void starpurm_spawn_kernel_callback (void *data, void(*f)(void *), void *args, void(*cb_f)(void *), void *cb_ args)

DynamicResourceSharing

- starpurm_drs_ret_t starpurm_set_drs_enable (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_set_drs_disable (starpurm_drs_desc_t *spd)
- int starpurm drs enabled p (void)
- starpurm_drs_ret_t starpurm_set_max_parallelism (starpurm_drs_desc_t *spd, int max)
- starpurm_drs_ret_t starpurm_assign_cpu_to_starpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_assign_cpus_to_starpu (starpurm_drs_desc_t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_assign_cpu_mask_to_starpu (starpurm_drs_desc_t *spd, const hwloc_
 couset t mask)
- starpurm drs ret t starpurm assign all cpus to starpu (starpurm drs desc t *spd)
- starpurm_drs_ret_t starpurm_withdraw_cpu_from_starpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm drs ret t starpurm withdraw cpus from starpu (starpurm drs desc t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_withdraw_cpu_mask_from_starpu (starpurm_drs_desc_t *spd, const hwloc cpuset t mask)
- starpurm_drs_ret_t starpurm_withdraw_all_cpus_from_starpu (starpurm_drs_desc_t *spd)
- starpurm_drs_ret_t starpurm_lend (starpurm_drs_desc_t *spd)

- starpurm_drs_ret_t starpurm_lend_cpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm drs ret t starpurm lend cpus (starpurm drs desc t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_lend_cpu_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm drs ret t starpurm reclaim (starpurm drs desc t *spd)
- starpurm_drs_ret_t starpurm_reclaim_cpu (starpurm_drs_desc_t *spd, int cpuid)
- starpurm_drs_ret_t starpurm_reclaim_cpus (starpurm_drs_desc_t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_reclaim_cpu_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm_drs_ret_t starpurm_acquire (starpurm_drs_desc_t *spd)
- starpurm drs ret t starpurm acquire cpu (starpurm drs desc t *spd, int cpuid)
- starpurm drs ret t starpurm acquire cpus (starpurm drs desc t *spd, int ncpus)
- starpurm_drs_ret_t starpurm_acquire_cpu_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm drs ret t starpurm return all (starpurm drs desc t *spd)
- starpurm_drs_ret_t starpurm_return_cpu (starpurm_drs_desc_t *spd, int cpuid)

Devices

- int starpurm_get_device_type_id (const char *type_str)
- const char * starpurm_get_device_type_name (int type_id)
- int starpurm_get_nb_devices_by_type (int type_id)
- int starpurm_get_device_id (int type_id, int device_rank)
- starpurm_drs_ret_t starpurm_assign_device_to_starpu (starpurm_drs_desc_t *spd, int type_id, int unit
 rank)
- starpurm_drs_ret_t starpurm_assign_devices_to_starpu (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_assign_device_mask_to_starpu (starpurm_drs_desc_t *spd, const hwloc
 cpuset t mask)
- starpurm drs ret t starpurm assign all devices to starpu (starpurm drs desc t *spd, int type id)
- starpurm_drs_ret_t starpurm_withdraw_device_from_starpu (starpurm_drs_desc_t *spd, int type_id, int unit rank)
- starpurm_drs_ret_t starpurm_withdraw_devices_from_starpu (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_withdraw_device_mask_from_starpu (starpurm_drs_desc_t *spd, const hwloc_cpuset_t mask)
- starpurm_drs_ret_t starpurm_withdraw_all_devices_from_starpu (starpurm_drs_desc_t *spd, int type_id)
- starpurm drs ret t starpurm lend device (starpurm drs desc t *spd, int type id, int unit rank)
- starpurm_drs_ret_t starpurm_lend_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_lend_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm_drs_ret_t starpurm_lend_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm_drs_ret_t starpurm_reclaim_device (starpurm_drs_desc_t *spd, int type_id, int unit_rank)
- starpurm_drs_ret_t starpurm_reclaim_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_reclaim_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm_drs_ret_t starpurm_reclaim_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm_drs_ret_t starpurm_acquire_device (starpurm_drs_desc_t *spd, int type_id, int unit_rank)
- starpurm_drs_ret_t starpurm_acquire_devices (starpurm_drs_desc_t *spd, int type_id, int ndevices)
- starpurm_drs_ret_t starpurm_acquire_device_mask (starpurm_drs_desc_t *spd, const hwloc_cpuset_
 t mask)
- starpurm_drs_ret_t starpurm_acquire_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm_drs_ret_t starpurm_return_all_devices (starpurm_drs_desc_t *spd, int type_id)
- starpurm drs ret t starpurm return device (starpurm drs desc t *spd, int type id, int unit rank)

CpusetsQueries

- hwloc_cpuset_t starpurm_get_device_worker_cpuset (int type_id, int unit_rank)
- hwloc_cpuset_t starpurm_get_global_cpuset (void)
- · hwloc cpuset t starpurm get selected cpuset (void)
- hwloc_cpuset_t starpurm_get_all_cpu_workers_cpuset (void)
- hwloc_cpuset_t starpurm_get_all_device_workers_cpuset (void)
- hwloc_cpuset_t starpurm_get_all_device_workers_cpuset_by_type (int typeid)

502 File Documentation

Chapter 33

Deprecated List

Global starpu codelet::cpu func

Optional field which has been made deprecated. One should use instead the field starpu codelet::cpu funcs.

Global starpu codelet::cuda func

Optional field which has been made deprecated. One should use instead the starpu_codelet::cuda_funcs field.

Global starpu_codelet::opencl_func

Optional field which has been made deprecated. One should use instead the starpu_codelet::opencl_funcs field.

Global starpu data free pinned if possible

Equivalent to starpu_free(). This macro is provided to avoid breaking old codes.

Global starpu_data_interface_ops::handle_to_pointer)(starpu_data_handle_t handle, unsigned node)

Use starpu_data_interface_ops::to_pointer instead. Return the current pointer (if any) for the handle on the given node.

Global starpu data malloc pinned if possible

Equivalent to starpu_malloc(). This macro is provided to avoid breaking old codes.

Global starpu_mpi_initialize (void)

This function has been made deprecated. One should use instead the function starpu_mpi_init(). This function does not call MPI_Init(), it should be called beforehand.

Global starpu mpi initialize extended (int *rank, int *world size)

This function has been made deprecated. One should use instead the function starpu_mpi_init(). MPI will be initialized by starpumpi by calling MPI_Init_Thread(argc, argv, MPI_THREAD_SERIALIZED, ...).

Global STARPU MULTIPLE CPU IMPLEMENTATIONS

Setting the field starpu_codelet::cpu_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::cpu_funcs.

Global STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS

Setting the field starpu_codelet::cuda_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::cuda_funcs.

Global STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS

Setting the field starpu_codelet::opencl_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu_codelet::opencl _ funcs.

504 Deprecated List

Part VI

Appendix

Chapter 34

Full Source Code for the 'Scaling a Vector' Example

34.1 Main Application

```
\star This example demonstrates how to use StarPU to scale an array by a factor.
* It shows how to manipulate data with StarPU's data management library.

* 1- how to declare a piece of data to StarPU (starpu_vector_data_register)
 * 2- how to describe which data are accessed by a task (task->handles[0])
 * 3- how a kernel can manipulate the data (buffers[0].vector.ptr)
#include <starpu.h>
#define
           NX
extern void scal_cpu_func(void *buffers[], void *_args);
extern void scal_sse_func(void *buffers[], void *_args);
extern void scal_cuda_func(void *buffers[], void *_args);
extern void scal_opencl_func(void *buffers[], void *_args);
static struct starpu_codelet cl =
    .where = STARPU_CPU | STARPU_CUDA | STARPU_OPENCL,
    /\star CPU implementation of the codelet \star/
    .cpu_funcs = { scal_cpu_func, scal_sse_func },
.cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
#ifdef STARPU_USE_CUDA
    /\star CUDA implementation of the codelet \star/
    .cuda_funcs = { scal_cuda_func },
#endif
#ifdef STARPU_USE_OPENCL
    /* OpenCL implementation of the codelet */
    .opencl_funcs = { scal_opencl_func },
    .nbuffers = 1,
    .modes = { STARPU_RW }
#ifdef STARPU_USE_OPENCL
struct starpu_opencl_program programs;
int main(int argc, char **argv)
    /* We consider a vector of float that is initialized just as any of C
      * data */
    float vector[NX];
    for (i = 0; i < NX; i++)
        vector[i] = 1.0f;
    fprintf(stderr, "BEFORE: First element was f^n, vector[0]);
    /* Initialize StarPU with default configuration */
    starpu_init(NULL);
#ifdef STARPU USE OPENCL
    starpu_opencl_load_opencl_from_file("
      examples/basic_examples/vector_scal_opencl_kernel.cl", &programs, NULL);
    /* Tell StaPU to associate the "vector" vector with the "vector_handle"
     * identifier. When a task needs to access a piece of data, it should
     * refer to the handle that is associated to it.
     * In the case of the "vector" data interface:
     \star - the first argument of the registration method is a pointer to the
```

```
handle that should describe the data
     \star - the second argument is the memory node where the data (ie. "vector")
          resides initially: STARPU_MAIN_RAM stands for an address in main memory, as
          opposed to an adress on a GPU for instance.

the third argument is the adress of the vector in RAM
the fourth argument is the number of elements in the vector

        - the fifth argument is the size of each element.
    starpu_data_handle_t vector_handle;
    starpu_vector_data_register(&vector_handle, STARPU_MAIN_RAM,
      (uintptr_t)vector, NX, sizeof(vector[0]));
    float factor = 3.14;
    /*\ {\tt create}\ {\tt a}\ {\tt synchronous}\ {\tt task:}\ {\tt any}\ {\tt call}\ {\tt to}\ {\tt starpu\_task\_submit}\ {\tt will}\ {\tt block}
      \star until it is terminated \star/
    struct starpu_task *task = starpu_task_create();
    task->synchronous = 1;
    task->cl = &cl;
    /\star the codelet manipulates one buffer in RW mode \star/
    task->handles[0] = vector_handle;
    /* an argument is passed to the codelet, beware that this is a
     \star READ-ONLY buffer and that the codelet may be given a pointer to a
     * COPY of the argument */
    task->cl_arg = &factor;
    task->cl_arg_size = sizeof(factor);
    /* execute the task on any eligible computational ressource */
    starpu_task_submit(task);
    /\star StarPU does not need to manipulate the array anymore so we can stop
      * monitoring it */
    starpu_data_unregister(vector_handle);
#ifdef STARPU_USE_OPENCL
    starpu_opencl_unload_opencl(&programs);
#endif
    /* terminate StarPU, no task can be submitted after */
    starpu shutdown();
    fprintf(stderr, "AFTER First element is f^n, vector[0]);
    return 0:
}
```

34.2 CPU Kernel

```
#include <starpu.h>
/\star This kernel takes a buffer and scales it by a constant factor \star/
void scal_cpu_func(void *buffers[], void *cl_arg)
     unsigned i;
     float *factor = cl_arg;
     \star The "buffers" array matches the task->handles array: for instance
     * task->handles[0] is a handle that corresponds to a data with 
* vector "interface", so that the first entry of the array in the
      * codelet is a pointer to a structure describing such a vector (ie.
      \star struct starpu_vector_interface \star)\,. Here, we therefore manipulate
      \star the buffers[0] element as a vector: nx gives the number of elements
      \star in the array, ptr gives the location of the array (that was possibly \star migrated/replicated), and elemsize gives the size of each elements.
     struct starpu_vector_interface *vector = buffers[0];
     /\star length of the vector \star/
     unsigned n = STARPU_VECTOR_GET_NX(vector);
     /\star get a pointer to the local copy of the vector: note that we have to
     * cast it in (float *) since a vector could contain any type of
      * elements so that the .ptr field is actually a uintptr_t */
     float *val = (float *)STARPU_VECTOR_GET_PTR(vector);
     /* scale the vector */
for (i = 0; i < n; i++)</pre>
         val[i] *= *factor;
}
```

34.3 CUDA Kernel 509

```
void scal_sse_func(void *buffers[], void *cl_arg)
{
    float *vector = (float *) STARPU_VECTOR_GET_PTR(buffers[0]);
    unsigned int n = STARPU_VECTOR_GET_NX(buffers[0]);
    unsigned int n_iterations = n/4;

    __m128 *VECTOR = (__m128*) vector;
    __m128 FACTOR STARPU_ATTRIBUTE_ALIGNED(16);
    float factor = *(float *) cl_arg;
    FACTOR = _mm_setl_ps(factor);

    unsigned int i;
    for (i = 0; i < n_iterations; i++)
        VECTOR[i] = _mm_mul_ps(FACTOR, VECTOR[i]);

    unsigned int remainder = n%4;
    if (remainder != 0)
    {
        unsigned int start = 4 * n_iterations;
        for (i = start; i < start+remainder; ++i)
        {
            vector[i] = factor * vector[i];
        }
    }
}</pre>
```

34.3 CUDA Kernel

```
#include <starpu.h>

static __global__ void vector_mult_cuda(unsigned n, float *val, float factor)
{
    unsigned i = blockIdx.x*blockDim.x + threadIdx.x;
    if (i < n)
        val[i] *= factor;
}

extern "C" void scal_cuda_func(void *buffers[], void *_args)
{
    float *factor = (float *)_args;

    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* local copy of the vector pointer */
    float *val = (float *)STARPU_VECTOR_GET_PTR(buffers[0]);
    unsigned threads_per_block = 64;
    unsigned nblocks = (n + threads_per_block-1) / threads_per_block;

    vector_mult_cuda<<<nblocks, threads_per_block, 0, starpu_cuda_get_local_stream()>>> (n, val, *factor);

    cudaStreamSynchronize(starpu_cuda_get_local_stream());
}
```

34.4 OpenCL Kernel

34.4.1 Invoking the Kernel

```
#include <starpu.h>
extern struct starpu_opencl_program programs;
void scal_opencl_func(void *buffers[], void *_args)
    float *factor = _args;
                                             /* OpenCL specific code */
    int id, devid, err;
    cl_kernel kernel;
                                             /* OpenCL specific code */
    cl_command_queue queue;
                                             /* OpenCL specific code */
    cl_event event;
                                             /* OpenCL specific code */
    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* OpenCL copy of the vector pointer */
cl_mem val = (cl_mem) STARPU_VECTOR_GET_DEV_HANDLE(buffers[0]);
    { /* OpenCL specific code */
         id = starpu_worker_get_id();
         devid = starpu_worker_get_devid(id);
         err = starpu_opencl_load_kernel(&kernel, &queue, &programs,
```

```
"vector_mult_opencl", /* Name of the codelet */
                                                          devid);
            if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
            err = clSetKernelArg(kernel, 0, sizeof(n), &n);
err |= clSetKernelArg(kernel, 1, sizeof(val), &val);
err |= clSetKernelArg(kernel, 2, sizeof(*factor), factor);
if (err) STARPU_OPENCL_REPORT_ERROR(err);
         /* OpenCL specific code */
          size_t global=n;
size_t local;
           cl_device_id device;
          starpu_opencl_get_device(devid, &device);
err = clGetKernelWorkGroupInfo (kernel, device, CL_KERNEL_WORK_GROUP_SIZE, sizeof(local), &local, &
        s);
           if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
           if (local > global) local=global;
           err = clEnqueueNDRangeKernel(queue, kernel, 1, NULL, &global, &local, 0, NULL, &event);
if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR(err);
     { /* OpenCL specific code */
            clFinish(queue);
            starpu_opencl_collect_stats(event);
clReleaseEvent(event);
            starpu_opencl_release_kernel(kernel);
}
```

34.4.2 Source of the Kernel

Chapter 35

The GNU Free Documentation License

Version 1.3, 3 November 2008

Copyright

2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc. http://fsf.org/

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

1. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document *free* in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

2. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

3. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

4. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a

computer-network location from which the general network-using public has access to download using publicstandard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

5. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- (a) Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- (b) List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- (c) State on the Title page the name of the publisher of the Modified Version, as the publisher.
- (d) Preserve all the copyright notices of the Document.
- (e) Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- (f) Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- (g) Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- (h) Include an unaltered copy of this License.
- (i) Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- (j) Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- (k) For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- (I) Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- (m) Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- (n) Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- (o) Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

6. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

7. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

8. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

9. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

10. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

11. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

12. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

35.1 ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (C) *year your name.* Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

with the Invariant Sections being *list their titles*, with the Front-Cover Texts being *list*, and with the Back-Cover Texts being *list*.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

Part VII

Index

Index

```
__configure__--disable-asynchronous-copy, 172
                                                     configure --enable-openmp, 173
 configure --disable-asynchronous-cuda-copy, 172
                                                     configure --enable-perf-debug, 173
 _configure___-disable-asynchronous-mic-copy, 173
                                                     __configure__--enable-quick-check, 171
__configure__--disable-asynchronous-mpi-master-
                                                     __configure__--enable-sc-hypervisor, 174
         slave-copy, 173
                                                     __configure__--enable-simgrid, 174
 configure -- disable-asynchronous-opencl-copy, 172
                                                     configure --enable-simgrid-mc, 175
__configure__--disable-build-doc, 171
                                                     __configure__--enable-spinlock-check, 171
                                                     __configure__--enable-starpufft-examples, 174
 configure --disable-build-examples, 174
 _configure___--disable-build-tests, 174
                                                     __configure__--enable-verbose, 171
 _configure__--disable-cpu, 172
                                                     __configure__--enable-worker-callbacks, 172
 _configure__--disable-cuda, 172
                                                     configure --mic-host, 173
 configure --disable-cuda-memcpy-peer, 172
                                                     configure --with-atlas-dir, 174
 configure -- disable-fortran, 173
                                                     __configure__--with-coi-dir, 173
 configure --disable-glpk, 174
                                                     __configure__--with-cuda-dir, 172
 _configure___--disable-hdf5, 174
                                                     __configure__--with-cuda-include-dir, 172
 _configure___--disable-icc, 171
                                                     __configure__--with-cuda-lib-dir, 172
 configure --disable-mpi, 173
                                                     configure --with-fxt, 174
 configure --disable-opencl, 172
                                                     configure --with-goto-dir, 174
 configure --disable-socl, 173
                                                     configure --with-hdf5-include-dir, 174
 configure --disable-starpufft, 174
                                                     configure --with-hdf5-lib-dir, 174
 _configure__--enable-allocation-cache, 173
                                                     __configure__--with-hwloc, 171
 _configure___--enable-blas-lib, 174
                                                     __configure__--with-mkl-cflags, 174
 _configure___--enable-blocking-drivers, 172
                                                      configure --with-mkl-ldflags, 174
 configure --enable-calibration-heuristic, 175
                                                     configure --with-mpi-master-slave-multiple-thread,
 configure --enable-cluster, 173
  configure --enable-coverage, 171
                                                      configure --with-mpicc, 173
 _configure___--enable-debug, 171
                                                     __configure__--with-opencl-dir, 172
 _configure___--enable-fast, 171
                                                     __configure__--with-opencl-include-dir, 172
 configure --enable-fxt-lock, 173
                                                     configure --with-opencl-lib-dir, 172
 configure --enable-leveldb, 174
                                                     configure --with-perf-model-dir, 174
 _configure___--enable-long-check, 171
                                                      _configure__--with-simgrid-dir, 174
 configure --enable-max-sched-ctxs, 172
                                                     configure --with-simgrid-include-dir, 175
__configure__--enable-maxbuffers, 173
                                                     __configure__--with-simgrid-lib-dir, 175
 _configure__--enable-maxcpus, 172
                                                     __configure__--with-smpirun, 175
 configure --enable-maxcudadev, 172
                                                     configure --without-hwloc, 171
 configure --enable-maximplementations, 172
                                                     env OCL ICD VENDORS, 164
 configure --enable-maxmicthreads, 173
                                                     env SC HYPERVISOR LAZY RESIZE, 169
 configure -- enable-maxnodes, 173
                                                     __env__SC_HYPERVISOR_MAX_SPEED_GAP, 169
 _configure___--enable-maxnumanodes, 172
                                                     __env__SC_HYPERVISOR_POLICY, 169
                                                     __env__SC_HYPERVISOR_SAMPLE_CRITERIA, 169
 _configure___--enable-maxopencldev, 172
 configure --enable-memory-stats, 174
                                                      env SC HYPERVISOR START RESIZE, 169
 configure --enable-model-debug, 173
                                                     env SC HYPERVISOR STOP PRINT, 169
 configure__--enable-mpi-master-slave, 173
                                                      _env__SC_HYPERVISOR_TRIGGER_RESIZE, 169
 configure -- enable-mpi-pedantic-isend, 173
                                                     env SOCL OCL LIB OPENCL, 164
                                                     __env__STARPU_BUS_CALIBRATE, 164
 _configure__--enable-mpi-verbose, 173
 _configure___--enable-new-check, 171
                                                     env STARPU BUS STATS, 167
 configure --enable-nmad, 173
                                                     env STARPU CALIBRATE, 164
 configure --enable-opencl-simulator, 172
                                                     __env__STARPU_CALIBRATE_MINIMUM, 164
                                                     __env__STARPU_CATCH_SIGNALS, 169
__configure__--enable-opengl-render, 173
```

| env STARPU COMM STATS, 164 | envSTARPU_MIC_SINK_PROGRAM_PATH, 163 |
|---|--|
| env STARPU CUDA PIPELINE, 161 | envSTARPU_MINIMUM_AVAILABLE_MEM, 167 |
| envSTARPU_CUDA_THREAD_PER_DEV, 161 | envSTARPU_MINIMUM_CLEAN_BUFFERS, 167 |
| | |
| envSTARPU_CUDA_THREAD_PER_WORKER, 161 | envSTARPU_MIN_PRIO, 164 envSTARPU_MIN_WORKERSIZE, 163 |
| envSTARPU_DIDUSE_BARRIER, 167 | env STARPU MPI CACHE, 164 |
| | |
| envSTARPU_DISABLE_ASYNCHRONOUS_C | envSTARPU_MPI_CACHE_STATS, 164 |
| OPY, 163 | envSTARPU_MPI_COMM, 164 |
| envSTARPU_DISABLE_ASYNCHRONOUS_C | envSTARPU_MPI_DRIVER_CALL_FREQUENCY, |
| UDA_COPY, 163 | 165 |
| envSTARPU_DISABLE_ASYNCHRONOUS_MI ← C_COPY, 163 | envSTARPU_MPI_DRIVER_TASK_FREQUEN ↔ CY, 165 |
| envSTARPU_DISABLE_ASYNCHRONOUS_M | envSTARPU_MPI_FAKE_RANK, 165 |
| PI_MS_COPY, 163 | envSTARPU_MPI_FAKE_SIZE, 165 |
| _envSTARPU_DISABLE_ASYNCHRONOUS_O | envSTARPU_MPI_MASTER_NODE, 162 |
| PENCL COPY, 163 | envSTARPU_MPI_PRIORITIES, 165 |
| envSTARPU_DISABLE_KERNELS, 168 | env STARPU MPI THREAD CPUID, 162 |
| envSTARPU_DISABLE_PINNING, 163 | env STARPU NCPU, 161 |
| envSTARPU_DISK_SWAP, 167 | envSTARPU_NCPUS, 161 |
| envSTARPU_DISK_SWAP_BACKEND, 167 | envSTARPU_NCUDA, 161 |
| envSTARPU_DISK_SWAP_SIZE, 167 | envSTARPU_NMIC, 162 |
| envSTARPU_ENABLE_CUDA_GPU_GPU_DIR← | envSTARPU_NMICTHREADS, 162 |
| ECT, 163 | envSTARPU_NMPIMSTHREADS, 162 |
| envSTARPU_ENABLE_STATS, 167 | |
| envSTARPU_FXT_PREFIX, 166 | _env_STARPU_NMPI_MS, 162 |
| envSTARPU_FXT_TRACE, 166 | _env_STARPU_NOPENCL, 161 |
| | envSTARPU_NWORKER_PER_CUDA, 161 |
| envSTARPU_GENERATE_TRACE, 167 | _env_STARPU_OPENCL_ONLY_ON_CPUS, 162 |
| envSTARPU_GENERATE_TRACE_OPTIONS, 167 | envSTARPU_OPENCL_ON_CPUS, 162 |
| | envSTARPU_OPENCL_PIPELINE, 161 |
| envSTARPU_GLOBAL_ARBITER, 168 | envSTARPU_OPENCL_PROGRAM_DIR, 166 |
| envSTARPU_HISTORY_MAX_ERROR, 168 | envSTARPU_PATH, 165 |
| envSTARPU_HOME, 165 | envSTARPU_PCI_FLAT, 165 |
| envSTARPU_HOSTNAME, 166 | envSTARPU_PERF_MODEL_DIR, 166 |
| envSTARPU_HWLOC_INPUT, 168 | envSTARPU_PERF_MODEL_HOMOGENEOU |
| envSTARPU_IDLE_FILE, 168 | S_CPU, 166 |
| envSTARPU_IDLE_POWER, 164 | envSTARPU_PERF_MODEL_HOMOGENEOU |
| envSTARPU_IDLE_TIME, 168 | S_CUDA, 166 |
| envSTARPU_LIMIT_CPU_MEM, 166 | envSTARPU_PERF_MODEL_HOMOGENEOU |
| envSTARPU_LIMIT_CPU_NUMA_devid_MEM, | S_MIC, 166 |
| 167 | envSTARPU_PERF_MODEL_HOMOGENEOU↔ |
| envSTARPU_LIMIT_CUDA_MEM, 166 | S_MPI_MS, 166 |
| envSTARPU_LIMIT_CUDA_devid_MEM, 166 | envSTARPU_PERF_MODEL_HOMOGENEOU |
| envSTARPU_LIMIT_MAX_SUBMITTED_TASKS, | S_OPENCL, 166 |
| 167 | _env_STARPU_PREFETCH, 164 |
| envSTARPU_LIMIT_MIN_SUBMITTED_TASKS, | envSTARPU_PROFILING, 164 |
| 167 | envSTARPU_RAND_SEED, 168 |
| envSTARPU_LIMIT_OPENCL_MEM, 166 | envSTARPU_RESERVE_NCPU, 161 |
| envSTARPU_LIMIT_OPENCL_devid_MEM, 166 | envSTARPU_SCHED, 164 |
| envSTARPU_LOGFILENAME, 166 | _env_STARPU_SCHED_ALPHA, 164 |
| envSTARPU_MAIN_THREAD_BIND, 162 | _env_STARPU_SCHED_BETA, 164 |
| envSTARPU_MAIN_THREAD_CPUID, 162 | _env_STARPU_SCHED_GAMMA, 164 |
| envSTARPU_MALLOC_SIMULATION_FOLD, 165 | _env_STARPU_SILENT, 166 |
| envSTARPU_MAX_MEMORY_USE, 167 | envSTARPU_SIMGRID_CUDA_MALLOC_COST, |
| envSTARPU_MAX_PRIO, 164 | 165 |
| envSTARPU_MAX_WORKERSIZE, 163 | envSTARPU_SIMGRID_CUDA_QUEUE_COST, |
| envSTARPU_MEMORY_STATS, 167 | 165 |
| envSTARPU_MIC_PROGRAM_PATH, 163 | envSTARPU_SIMGRID_FETCHING_INPUT_C |
| envSTARPU_MIC_SINK_PROGRAM_NAME, 163 | OST, 165 |

| envSTARPU_SIMGRID_QUEUE_MALLOC_CO | bandwidth |
|--|---|
| ST, 165 | starpu_disk_ops, 271 |
| envSTARPU_SIMGRID_SCHED_COST, 165 | Bitmap, 205 |
| envSTARPU_SIMGRID_TASK_SUBMIT_COST, | starpu_bitmap_and_get, 206 |
| 165 | starpu_bitmap_cardinal, 206 |
| envSTARPU_SIMGRID_TRANSFER_COST, 165 | starpu_bitmap_create, 205 |
| envSTARPU_SINGLE_COMBINED_WORKER, | starpu_bitmap_destroy, 205 |
| 163 | starpu_bitmap_first, 207 |
| env STARPU STATS, 168 | starpu_bitmap_get, 206 |
| env STARPU SYNTHESIZE ARITY COMBINE← | starpu_bitmap_yet, 200 starpu_bitmap_has_next, 207 |
| D WORKER, 163 | starpu_bitmap_last, 207 |
| envSTARPU_TARGET_AVAILABLE_MEM, 167 | starpu_bitmap_tast, 207 starpu_bitmap_next, 207 |
| envSTARPU_TARGET_CLEAN_BUFFERS, 167 | . – .– . |
| | starpu_bitmap_or, 206 |
| envSTARPU_TASK_BREAK_ON_EXEC, 168 | starpu_bitmap_set, 206 |
| envSTARPU_TASK_BREAK_ON_POP, 168 | starpu_bitmap_unset, 206 |
| envSTARPU_TASK_BREAK_ON_PUSH, 168 | starpu_bitmap_unset_all, 206 |
| _envSTARPU_TASK_BREAK_ON_SCHED, 168 | starpu_bitmap_unset_and, 206 |
| envSTARPU_TRACE_BUFFER_SIZE, 167 | bundle |
| envSTARPU_USE_NUMA, 168 | starpu_task, 287 |
| envSTARPU_WATCHDOG_CRASH, 168 | bus_calibrate |
| envSTARPU_WATCHDOG_DELAY, 168 | starpu_conf, 185 |
| envSTARPU_WATCHDOG_TIMEOUT, 168 | CUDA Extensions, 320 |
| envSTARPU_WORKERS_CPUID, 162 | STARPU_CUBLAS_REPORT_ERROR, 321 |
| envSTARPU_WORKERS_CUDAID, 162 | STARPU_CUDA_REPORT_ERROR, 321 |
| envSTARPU_WORKERS_MICID, 163 | |
| envSTARPU_WORKERS_NOBIND, 162 | starpu_cublas_init, 321 |
| envSTARPU_WORKERS_OPENCLID, 162 | starpu_cublas_report_error, 321 |
| envSTARPU_WORKER_STATS, 168 | starpu_cublas_set_stream, 322 |
| envSTARPU_WORKER_TREE, 163 | starpu_cublas_shutdown, 322 |
| | starpu_cuda_copy_async_sync, 322 |
| act_hypervisor_mutex | starpu_cuda_get_device_properties, 322 |
| Scheduling Context Hypervisor - Regular usage, | starpu_cuda_get_local_stream, 321 |
| 415 | starpu_cuda_report_error, 321 |
| add | starpu_cuda_set_device, 322 |
| starpu_worker_collection, 210 | starpu_cusparse_get_local_handle, 322 |
| add_child | starpu_cusparse_init, 321 |
| starpu_sched_component, 423 | starpu_cusparse_shutdown, 322 |
| add_workers | calibrate |
| starpu_sched_policy, 393 | starpu_conf, 185 |
| alloc | callback_arg |
| starpu_disk_ops, 272 | starpu_task, 283 |
| alloc_compare | callback_arg_free |
| starpu_data_interface_ops, 236 | starpu_task, 284 |
| alloc_footprint | callback_func |
| starpu_data_interface_ops, 236 | starpu_task, 283 |
| allocate_data_on_node | can_copy |
| starpu_data_interface_ops, 235 | starpu_data_copy_methods, 231 |
| any_to_any | |
| starpu_data_copy_methods, 234 | can_execute |
| arch coat function | starpu_codelet, 277 |
| arch_cost_function | starpu_codelet, 277 |
| starpu_perfmodel, 311 | - |
| | starpu_codelet, 277 |
| starpu_perfmodel, 311 async_full_read | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 async_full_write | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 catch_signals |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 async_full_write starpu_disk_ops, 272 | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 catch_signals starpu_conf, 186 |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 async_full_write starpu_disk_ops, 272 async_read | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 catch_signals starpu_conf, 186 children |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 async_full_write starpu_disk_ops, 272 async_read starpu_disk_ops, 272 | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 catch_signals starpu_conf, 186 children starpu_sched_component, 422 |
| starpu_perfmodel, 311 async_full_read starpu_disk_ops, 272 async_full_write starpu_disk_ops, 272 async_read | starpu_codelet, 277 can_pull starpu_sched_component, 423 can_push starpu_sched_component, 423 catch_signals starpu_conf, 186 children |

| cl_arg | starpu_task_destroy, 293 |
|--|--|
| starpu_task, 283 | starpu_task_dup, 296 |
| cl_arg_free | starpu_task_get_current, 295 |
| starpu_task, 284 | starpu_task_get_current_data_node, 295 |
| cl_arg_size | starpu_task_get_implementation, 296 |
| starpu_task, 283 | starpu_task_get_model_name, 295 |
| close | starpu_task_get_name, 295 |
| starpu_disk_ops, 272 | starpu_task_init, 292 |
| Clustering Machine, 433 | starpu_task_nready, 294 |
| starpu_cluster_types, 434 | starpu_task_nsubmitted, 294 |
| Codelet And Tasks, 274 | starpu_task_set_implementation, 296 |
| STARPU_CODELET_GET_MODE, 290 | starpu_task_status, 292 |
| STARPU_CODELET_GET_NODE, 291 | starpu_task_submit, 293 |
| STARPU_CODELET_NOPLANS, 288 | starpu_task_submit_to_ctx, 293 |
| STARPU_CODELET_SET_MODE, 290 | starpu_task_wait, 293 |
| STARPU_CODELET_SET_NODE, 291 | starpu_task_wait_array, 294 |
| STARPU CODELET SIMGRID EXECUTE AN↔ | starpu_task_wait_for_all, 294 |
| D_INJECT, 288 | starpu_task_wait_for_all_in_ctx, 294 |
| STARPU_CODELET_SIMGRID_EXECUTE, 288 | starpu_task_wait_for_n_submitted, 294 |
| STARPU CPU, 288 | starpu_task_wait_for_n_submitted_in_ctx, 294 |
| STARPU_CUDA_ASYNC, 289 | starpu_task_wait_for_no_ready, 294 |
| STARPU_CUDA, 288 | color |
| STARPU MAIN RAM, 289 | starpu_codelet, 280 |
| STARPU MIC, 288 | starpu_task, 286 |
| STARPU_MPI_MS, 288 | combinations |
| STARPU MULTIPLE CPU IMPLEMENTATIO↔ | starpu_perfmodel, 311 |
| | . — |
| NS, 289 | compare |
| STARPU_MULTIPLE_CUDA_IMPLEMENTATI OND OND | starpu_data_interface_ops, 236 |
| ONS, 289 | copy |
| STARPU_MULTIPLE_OPENCL_IMPLEMENTA↔ | starpu_disk_ops, 272 |
| TIONS, 289 | copy_methods |
| STARPU_NMAXBUFS, 288 | starpu_data_interface_ops, 235 |
| STARPU_NOWHERE, 288 | cost_function |
| STARPU_OPENCL_ASYNC, 289 | starpu_perfmodel, 311 |
| STARPU_OPENCL, 288 | starpu_perfmodel_per_arch, 309 |
| STARPU_SPECIFIC_NODE_LOCAL, 289 | cpu_func |
| STARPU_TASK_GET_HANDLE, 290 | starpu_codelet, 277 |
| STARPU_TASK_GET_MODE, 290 | cpu_funcs |
| STARPU_TASK_GET_NBUFFERS, 290 | starpu_codelet, 278 |
| STARPU_TASK_INITIALIZER, 289 | cpu_funcs_name |
| STARPU_TASK_SET_HANDLE, 290 | starpu_codelet, 279 |
| STARPU_TASK_SET_MODE, 290 | cuda_flags |
| STARPU_VARIABLE_NBUFFERS, 289 | starpu_codelet, 278 |
| starpu_codelet_display_stats, 295 | cuda func |
| starpu codelet init, 295 | starpu codelet, 277 |
| starpu_codelet_type, 292 | cuda_funcs |
| starpu_cpu_func_t, 291 | starpu_codelet, 278 |
| starpu create sync task, 296 | cuda_opengl_interoperability |
| starpu_cuda_func_t, 291 | starpu_conf, 186 |
| starpu_iteration_pop, 295 | cuda to cuda |
| starpu_iteration_push, 295 | starpu_data_copy_methods, 232 |
| starpu_mic_func_t, 291 | cuda_to_cuda_async |
| starpu_mic_kernel_t, 291 | starpu_data_copy_methods, 233 |
| • — — — | |
| starpu_mpi_ms_func_t, 292 | cuda_to_opencl |
| starpu_mpi_ms_kernel_t, 291 | starpu_data_copy_methods, 232 |
| starpu_opencl_func_t, 291 | cuda_to_ram |
| starpu_task_clean, 293 | starpu_data_copy_methods, 232 |
| starpu_task_create, 293 | cuda_to_ram_async |

| | 07100111117011 057 111 010 |
|--------------------------------------|--|
| starpu_data_copy_methods, 233 | STARPU_MATRIX_GET_NY, 240 |
| custom | STARPU_MATRIX_GET_OFFSET, 240 |
| sc_hypervisor_policy, 401, 410 | STARPU_MATRIX_GET_PTR, 240 |
| 4-4- | STARPU_MATRIX_SET_LD, 241 |
| data | STARPU_MATRIX_SET_NX, 241 |
| starpu_sched_component, 422 | STARPU_MATRIX_SET_NY, 241 |
| Data Interfaces, 226 | STARPU_MULTIFORMAT_GET_CPU_PTR, 247 |
| STARPU_BCSR_GET_COLIND_DEV_HANDLE, | STARPU_MULTIFORMAT_GET_CUDA_PTR, |
| 246 | 247 |
| STARPU_BCSR_GET_COLIND, 246 | STARPU_MULTIFORMAT_GET_MIC_PTR, 247 |
| STARPU_BCSR_GET_NNZ, 246 | STARPU_MULTIFORMAT_GET_NX, 247 |
| STARPU_BCSR_GET_NZVAL_DEV_HANDLE, | STARPU_MULTIFORMAT_GET_OPENCL_PTR, |
| 246 | 247 |
| STARPU_BCSR_GET_NZVAL, 246 | STARPU_VARIABLE_GET_DEV_HANDLE, 244 |
| STARPU_BCSR_GET_OFFSET, 247 | STARPU_VARIABLE_GET_ELEMSIZE, 244 |
| STARPU_BCSR_GET_ROWPTR_DEV_HANDLE, | STARPU VARIABLE GET OFFSET, 244 |
| 246 | STARPU_VARIABLE_GET_OFFSET, 244 STARPU_VARIABLE_GET_PTR, 244 |
| STARPU_BCSR_GET_ROWPTR, 246 | : |
| STARPU_BLOCK_GET_DEV_HANDLE, 242 | STARPU_VECTOR_GET_ALLOCSIZE, 244 |
| STARPU_BLOCK_GET_ELEMSIZE, 243 | STARPU_VECTOR_GET_DEV_HANDLE, 243 |
| STARPU_BLOCK_GET_LDY, 243 | STARPU_VECTOR_GET_ELEMSIZE, 244 |
| STARPU BLOCK GET LDZ, 243 | STARPU_VECTOR_GET_NX, 244 |
| STARPU_BLOCK_GET_NX, 243 | STARPU_VECTOR_GET_OFFSET, 244 |
| STARPU BLOCK GET NY, 243 | STARPU_VECTOR_GET_PTR, 243 |
| STARPU BLOCK GET NZ, 243 | STARPU_VECTOR_GET_SLICE_BASE, 244 |
| STARPU_BLOCK_GET_OFFSET, 243 | STARPU_VECTOR_SET_NX, 244 |
| STARPU BLOCK GET PTR, 242 | starpu_bcsr_data_register, 257 |
| STARPU_COO_GET_COLUMNS_DEV_HAND↔ | starpu_bcsr_get_c, 259 |
| LE, 241 | starpu_bcsr_get_elemsize, 259 |
| STARPU_COO_GET_COLUMNS, 241 | starpu_bcsr_get_firstentry, 258 |
| STARPU_COO_GET_ELEMSIZE, 242 | starpu_bcsr_get_local_colind, 258 |
| STARPU_COO_GET_NVALUES, 242 | starpu_bcsr_get_local_nzval, 258 |
| | starpu_bcsr_get_local_rowptr, 259 |
| STARPU_COO_GET_NX, 242 | starpu_bcsr_get_nnz, 258 |
| STARPU_COO_GET_NY, 242 | starpu_bcsr_get_nrow, 258 |
| STARPU_COO_GET_OFFSET, 242 | starpu_bcsr_get_r, 259 |
| STARPU_COO_GET_ROWS_DEV_HANDLE, | starpu block data register, 253 |
| 242 | starpu_block_get_elemsize, 254 |
| STARPU_COO_GET_ROWS, 241 | starpu_block_get_local_ldy, 254 |
| STARPU_COO_GET_VALUES_DEV_HANDLE, | |
| 242 | starpu_block_get_local_ldz, 254 |
| STARPU_COO_GET_VALUES, 242 | starpu_block_get_local_ptr, 254 |
| STARPU_CSR_GET_COLIND_DEV_HANDLE, | starpu_block_get_nx, 253 |
| 245 | starpu_block_get_ny, 254 |
| STARPU_CSR_GET_COLIND, 245 | starpu_block_get_nz, 254 |
| STARPU_CSR_GET_ELEMSIZE, 246 | starpu_block_ptr_register, 253 |
| STARPU_CSR_GET_FIRSTENTRY, 246 | starpu_coo_data_register, 253 |
| STARPU_CSR_GET_NNZ, 245 | starpu_csr_data_register, 256 |
| STARPU_CSR_GET_NROW, 245 | starpu_csr_get_elemsize, 257 |
| STARPU_CSR_GET_NZVAL_DEV_HANDLE, 245 | starpu_csr_get_firstentry, 256 |
| STARPU_CSR_GET_NZVAL, 245 | starpu_csr_get_local_colind, 257 |
| STARPU_CSR_GET_OFFSET, 245 | starpu_csr_get_local_nzval, 257 |
| STARPU_CSR_GET_ROWPTR_DEV_HANDLE, | starpu_csr_get_local_rowptr, 257 |
| 245 | starpu_csr_get_nnz, 256 |
| STARPU_CSR_GET_ROWPTR, 245 | starpu_csr_get_nrow, 256 |
| STARPU MATRIX GET ALLOCSIZE, 241 | starpu_data_get_alloc_size, 249 |
| STARPU MATRIX GET DEV HANDLE, 240 | starpu_data_get_interface_id, 249 |
| STARPU MATRIX GET ELEMSIZE, 241 | starpu_data_get_interface_on_node, 249 |
| STARPU_MATRIX_GET_LD, 241 | starpu_data_get_local_ptr, 249 |
| STARPU_MATRIX_GET_NX, 240 | starpu_data_get_size, 249 |
| | <u></u> |

| starpu_data_handle_to_pointer, 248 | $starpu_data_acquire_on_node_cb_sequential_{\leftarrow}$ |
|--|--|
| starpu_data_interface_get_next_id, 250 | consistency, 222 |
| starpu_data_interface_id, 247 | starpu_data_acquire_on_node_cb_sequential_← |
| starpu_data_lookup, 249 | consistency_sync_jobids, 222 |
| starpu_data_pack, 249 | starpu_data_acquire_on_node_try, 222 |
| starpu_data_pointer_is_inside, 248 | starpu_data_acquire_try, 222 |
| starpu_data_ptr_register, 248 | starpu_data_advise_as_important, 221 |
| starpu_data_register, 248 | starpu_data_assign_arbiter, 223 |
| starpu_data_register_same, 248 | starpu_data_fetch_on_node, 223 |
| starpu_data_unpack, 249 | starpu_data_get_default_sequential_consistency ← |
| starpu_free_on_node, 251 | _flag, 225 |
| starpu_free_on_node_flags, 251 | starpu_data_get_ooc_flag, 225 |
| starpu_hash_crc32c_be, 259 | starpu_data_get_sequential_consistency_flag, 224 |
| starpu_hash_crc32c_be_n, 259 | starpu_data_get_user_data, 226 |
| starpu_hash_crc32c_string, 260 | starpu_data_handle_t, 218 |
| starpu_interface_copy, 250 | starpu_data_idle_prefetch_on_node, 224 |
| starpu_interface_data_copy, 250 | starpu_data_invalidate, 220 |
| starpu_interface_end_driver_copy_async, 250 | starpu_data_invalidate_submit, 220 |
| starpu_interface_start_driver_copy_async, 250 | starpu_data_is_on_node, 224 |
| starpu_malloc_on_node, 251 | starpu_data_prefetch_on_node, 224 |
| starpu_malloc_on_node_flags, 250 | starpu_data_query_status, 225 |
| starpu_malloc_on_node_set_default_flags, 251 | starpu data release, 223 |
| starpu_matrix_data_register, 251 | starpu_data_release, 223 |
| starpu_matrix_data_register_allocsize, 252 | starpu_data_release_on_node, 223 |
| starpu_matrix_get_allocsize, 252 | starpu_data_request_anocation, 223 starpu_data_set_coordinates, 220 |
| starpu_matrix_get_elemsize, 252 | • — — — |
| starpu_matrix_get_local_ld, 252 | starpu_data_set_coordinates_array, 220 |
| starpu_matrix_get_local_ptr, 252 | starpu_data_set_default_sequential_consistency |
| starpu_matrix_get_nx, 252 | _flag, 225 |
| starpu_matrix_get_ny, 252 | starpu_data_set_name, 219 |
| starpu_matrix_ptr_register, 252 | starpu_data_set_ooc_flag, 225 |
| starpu_multiformat_data_register, 259 | starpu_data_set_reduction_methods, 225 |
| starpu variable data register, 255 | starpu_data_set_sequential_consistency_flag, 224 |
| starpu_variable_get_elemsize, 256 | starpu_data_set_user_data, 225 |
| starpu_variable_get_local_ptr, 256 | starpu_data_set_wt_mask, 224 |
| starpu variable ptr register, 256 | starpu_data_unregister, 220 |
| starpu_vector_data_register, 254 | starpu_data_unregister_no_coherency, 220 |
| starpu vector data register allocsize, 254 | starpu_data_unregister_submit, 220 |
| starpu_vector_get_allocsize, 255 | starpu_data_wont_use, 224 |
| starpu_vector_get_elemsize, 255 | Data Partition, 260 |
| starpu_vector_get_local_ptr, 255 | starpu_bcsr_filter_canonical_block, 267 |
| starpu_vector_get_nx, 255 | starpu_bcsr_filter_canonical_block_child_ops, 267 |
| starpu_vector_ptr_register, 255 | starpu_block_filter_block, 269 |
| starpu_void_data_register, 256 | starpu_block_filter_block_shadow, 269 |
| Data Management, 216 | starpu_block_filter_depth_block, 270 |
| STARPU_ACQUIRE_NO_NODE_LOCK_ALL, 218 | starpu_block_filter_depth_block_shadow, 270 |
| STARPU_ACQUIRE_NO_NODE, 218 | starpu_block_filter_vertical_block, 269 |
| STARPU_DATA_ACQUIRE_CB, 218 | starpu_block_filter_vertical_block_shadow, 269 |
| starpu_arbiter_create, 223 | starpu_csr_filter_vertical_block, 267 |
| starpu_arbiter_destroy, 223 | starpu_data_get_child, 263 |
| starpu_arbiter_t, 218 | starpu_data_get_nb_children, 263 |
| starpu_data_access_mode, 219 | starpu_data_get_sub_data, 264 |
| starpu_data_access_mode, 219 starpu_data_acquire, 221 | starpu_data_map_filters, 264 |
| starpu_data_acquire, 221 starpu_data_acquire_cb, 221 | starpu_data_nap_inters, 204 starpu_data_partition, 263 |
| starpu_data_acquire_cb, 221 starpu_data_acquire_cb_sequential_consistency, | starpu_data_partition_clean, 266 |
| 221 | starpu_data_partition_not_automatic, 266 |
| starpu_data_acquire_on_node, 221 | starpu_data_partition_plan, 264 |
| | starpu_data_partition_plan, 264 starpu_data_partition_readonly_submit, 265 |
| starpu_data_acquire_on_node_cb, 221 | starpu_uata_partition_readonly_submit, 265 |

| starpu_data_partition_readwrite_upgrade_submit, | starpu_codelet, 279 |
|---|---|
| 265 | starpu_task, 282 |
| starpu_data_partition_submit, 265 | dyn_nodes |
| starpu_data_partition_submit_sequential_← | starpu_codelet, 279 |
| consistency, 266 | p, |
| starpu_data_unpartition, 263 | e_starpurm_drs_ret |
| | Interoperability Support, 436 |
| starpu_data_unpartition_readonly_submit, 265 | end_ctx |
| starpu_data_unpartition_submit, 265 | |
| starpu_data_unpartition_submit_sequential_← | sc_hypervisor_policy, 402, 411 |
| consistency, 266 | energy_model |
| starpu_data_unpartition_submit_sequential_← | starpu_codelet, 280 |
| consistency_cb, 266 | estimated_end |
| starpu_data_vget_sub_data, 264 | starpu_sched_component, 423 |
| starpu_data_vmap_filters, 264 | estimated_load |
| starpu_filter_nparts_compute_chunk_size_and_ | starpu_sched_component, 423 |
| offset, 270 | execute_on_a_specific_worker |
| | starpu_task, 285 |
| starpu_matrix_filter_block, 267 | Expert Mode, 382 |
| starpu_matrix_filter_block_shadow, 267 | starpu progression hook deregister, 383 |
| starpu_matrix_filter_vertical_block, 267 | , |
| starpu_matrix_filter_vertical_block_shadow, 268 | starpu_progression_hook_register, 382 |
| starpu_vector_filter_block, 268 | starpu_wake_all_blocked_workers, 382 |
| starpu_vector_filter_block_shadow, 268 | Explicit Dependencies, 302 |
| starpu_vector_filter_divide_in_2, 269 | starpu_tag_declare_deps, 305 |
| starpu_vector_filter_list, 268 | starpu_tag_declare_deps_array, 305 |
| starpu_vector_filter_list_long, 268 | starpu_tag_notify_from_apps, 306 |
| deinit | starpu_tag_remove, 306 |
| | starpu_tag_restart, 306 |
| starpu_worker_collection, 210 | starpu_tag_t, 303 |
| deinit_data | starpu_tag_wait, 305 |
| starpu_sched_component, 423 | starpu_tag_wait_array, 305 |
| deinit_sched | starpu_task_declare_deps, 303 |
| starpu_sched_policy, 392 | starpu_task_declare_deps_array, 303 |
| describe | starpu_task_declare_end_deps, 304 |
| starpu_data_interface_ops, 236 | |
| destroy | starpu_task_declare_end_deps_array, 304 |
| starpu_task, 285 | starpu_task_end_dep_add, 304 |
| detach | starpu_task_end_dep_release, 305 |
| starpu task, 285 | starpu_task_get_task_scheduled_succs, 304 |
| disable_asynchronous_copy | starpu_task_get_task_succs, 304 |
| | |
| starpu_conf, 185 | FFT Support, 358 |
| disable_asynchronous_cuda_copy | starpufft_cleanup, 359 |
| starpu_conf, 185 | starpufft_destroy_plan, 360 |
| disable_asynchronous_mic_copy | starpufft_execute, 359 |
| starpu_conf, 185 | starpufft_execute_handle, 359 |
| disable_asynchronous_mpi_ms_copy | starpufft_free, 358 |
| starpu_conf, 186 | starpufft_malloc, 358 |
| disable_asynchronous_opencl_copy | starpufft_plan_dft_1d, 359 |
| starpu_conf, 185 | starpufft_plan_dft_2d, 359 |
| display | starpufft_start, 359 |
| starpu_data_interface_ops, 236 | • — |
| | starpufft_start_handle, 359 |
| do_schedule | filter_arg |
| starpu_sched_policy, 393 | starpu_data_filter, 263 |
| dontcache | filter_arg_ptr |
| starpu_data_interface_ops, 237 | starpu_data_filter, 263 |
| dyn_handles | filter_func |
| starpu_task, 282 | starpu_data_filter, 262 |
| dyn_interfaces | flags |
| starpu_task, 282 | starpu_codelet, 280 |
| dyn_modes | flops |
| - | • |

| starpu_task, 287 footprint | starpu_sched_component_specs, 425 hwloc_socket_composed_sched_component |
|--|--|
| starpu_data_interface_ops, 236 | starpu_sched_component_specs, 425 |
| starpu_perfmodel, 311 | hypervisor_tag |
| free | starpu_task, 286 |
| starpu_disk_ops, 272 | , – |
| free_data_on_node | init |
| starpu_data_interface_ops, 235 | starpu_data_interface_ops, 235 |
| free_request | starpu_worker_collection, 210 |
| starpu_disk_ops, 273 | init_iterator |
| full_read | starpu_worker_collection, 210 |
| starpu_disk_ops, 272 | init_sched |
| full_write | starpu_sched_policy, 392 |
| starpu_disk_ops, 272 | init_worker |
| FxT Support, 356 | sc_hypervisor_policy, 402, 411 |
| starpu_fxt_autostart_profiling, 357 | Initialization and Termination, 182 |
| starpu_fxt_start_profiling, 358 | STARPU_THREAD_ACTIVE, 186 |
| starpu_fxt_stop_profiling, 358 | starpu_asynchronous_copy_disabled, 188 |
| starpu_fxt_trace_user_event, 358 | starpu_asynchronous_cuda_copy_disabled, 188 |
| starpu_fxt_trace_user_event_string, 358 | starpu_asynchronous_mic_copy_disabled, 188 |
| , = = = = = 0, | starpu_asynchronous_mpi_ms_copy_disabled, |
| get_alloc_size | 188 |
| starpu_data_interface_ops, 236 | starpu_asynchronous_opencl_copy_disabled, 188 |
| get_child_ops | starpu_bind_thread_on, 188 |
| starpu_data_filter, 263 | starpu_conf_init, 186 |
| get_nchildren | starpu_get_next_bindid, 187 |
| starpu_data_filter, 262 | starpu_init, 187 |
| get_next | starpu_initialize, 187 |
| starpu_worker_collection, 210 | starpu_is_initialized, 187 |
| get_size | starpu_pause, 187 |
| starpu_data_interface_ops, 236 | starpu_resume, 187 |
| | starpu_shutdown, 187 |
| handle_idle_cycle | starpu_topology_print, 188 |
| sc_hypervisor_policy, 401, 411 | starpu_wait_initialized, 187 |
| handle_idle_end | interface_size |
| sc_hypervisor_policy, 402, 411 | starpu_data_interface_ops, 237 |
| handle_poped_task | interfaceid |
| sc_hypervisor_policy, 402, 411 | starpu_data_interface_ops, 237 |
| handle_post_exec_hook | interfaces |
| sc_hypervisor_policy, 402, 411 | starpu_task, 282 |
| handle_pushed_task | Interoperability Support, 434 |
| sc_hypervisor_policy, 402, 411 | e_starpurm_drs_ret, 436 |
| handle_submitted_job | starpurm_acquire, 440 |
| sc_hypervisor_policy, 402, 411 | starpurm_acquire_all_devices, 444 |
| handle_to_pointer | starpurm_acquire_cpu, 440 |
| starpu_data_interface_ops, 235 | starpurm_acquire_cpu_mask, 440 |
| handles | starpurm_acquire_cpus, 440 |
| starpu_task, 282 | starpurm_acquire_device, 443 |
| handles_sequential_consistency | starpurm_acquire_device_mask, 444 |
| starpu_task, 283 | starpurm_acquire_devices, 443 |
| has_next | starpurm_assign_all_cpus_to_starpu, 438 |
| starpu_worker_collection, 210 | starpurm_assign_all_devices_to_starpu, 442 |
| history | starpurm_assign_cpu_mask_to_starpu, 438 |
| starpu_perfmodel_per_arch, 309 | starpurm_assign_cpu_to_starpu, 438 |
| hwloc_cache_composed_sched_component | starpurm_assign_cpus_to_starpu, 438 |
| starpu_sched_component_specs, 425 | starpurm_assign_device_mask_to_starpu, 441 |
| hwloc_component_composed_sched_component | starpurm_assign_device_to_starpu, 441 |
| starpu_sched_component_specs, 425 | starpurm_assign_devices_to_starpu, 441 |
| hwloc_machine_composed_sched_component | starpurm_drs_enabled_p, 438 |
| | |

| | starpurm_get_all_cpu_workers_cpuset, 444 starpurm_get_all_device_workers_cpuset, 445 starpurm_get_all_device_workers_cpuset_by_ | MPI | starpu_mic_register_kernel, 353 Support, 360 STARPU_EXECUTE_ON_DATA, 363 |
|-------|---|-----|--|
| | type, 445 | | STARPU_EXECUTE_ON_NODE, 363 |
| | starpurm_get_device_id, 441 | | STARPU_MPI_PER_NODE, 363 |
| | starpurm_get_device_type_id, 441 | | STARPU_MPI_TAG_UB, 363 |
| | starpurm_get_device_type_name, 441 | | STARPU_NODE_SELECTION_POLICY, 363 |
| | starpurm_get_device_worker_cpuset, 444 | | STARPU_USE_MPI_MASTER_SLAVE, 362 |
| | starpurm_get_global_cpuset, 444 | | STARPU_USE_MPI, 362 |
| | starpurm_get_nb_devices_by_type, 441 | | starpu_data_get_rank, 364 |
| | starpurm_get_selected_cpuset, 444 | | starpu_data_get_tag, 364 |
| | starpurm_initialize, 437 | | starpu_data_set_rank, 363 |
| | starpurm_initialize_with_cpuset, 437 | | starpu_data_set_tag, 363 |
| | starpurm_lend, 439 | | starpu_mpi_barrier, 369 |
| | starpurm_lend_all_devices, 443 | | starpu_mpi_cache_flush, 371 |
| | starpurm_lend_cpu, 439 | | starpu_mpi_cache_flush_all_data, 371 |
| | starpurm_lend_cpu_mask, 439 | | starpu_mpi_cache_is_enabled, 371 |
| | starpurm_lend_cpus, 439 | | starpu_mpi_cache_set, 371 |
| | starpurm_lend_device, 442 | | starpu_mpi_cached_receive, 371 |
| | starpurm_lend_device_mask, 443 | | starpu_mpi_cached_send, 371 |
| | starpurm_lend_devices, 442 | | starpu_mpi_comm_amounts_retrieve, 365 |
| | starpurm_reclaim, 439 | | starpu_mpi_comm_get_attr, 366 |
| | starpurm_reclaim_all_devices, 443 | | starpu_mpi_comm_rank, 365 |
| | starpurm_reclaim_cpu, 440 | | starpu_mpi_comm_size, 365 |
| | starpurm_reclaim_cpu_mask, 440 | | starpu_mpi_data_get_rank, 372 |
| | starpurm_reclaim_cpus, 440 | | starpu_mpi_data_get_tag, 372 |
| | starpurm_reclaim_device, 443 | | starpu_mpi_data_migrate, 374 |
| | starpurm_reclaim_device_mask, 443 | | starpu_mpi_data_register, 363 |
| | starpurm_reclaim_devices, 443 | | starpu_mpi_data_register_comm, 371 |
| | starpurm_return_all, 440 | | starpu_mpi_data_set_rank, 363 |
| | starpurm_return_all_devices, 444 | | starpu_mpi_data_set_rank_comm, 372 |
| | starpurm_return_cpu, 440 | | starpu_mpi_data_set_tag, 372 |
| | starpurm_return_device, 444 | | starpu_mpi_datatype_register, 370 |
| | starpurm_set_drs_disable, 438 | | starpu_mpi_datatype_unregister, 371 |
| | starpurm_set_drs_enable, 437 | | starpu_mpi_gather_detached, 375 |
| | starpurm_set_max_parallelism, 438 | | starpu_mpi_get_data_on_all_nodes_detached, |
| | starpurm_shutdown, 437 | | 374 |
| | starpurm_spawn_kernel_on_cpus, 437 | | starpu_mpi_get_data_on_node, 373 |
| | starpurm_spawn_kernel_on_cpus_callback, 437 | | starpu_mpi_get_data_on_node_detached, 373 |
| | starpurm_withdraw_all_cpus_from_starpu, 439 | | starpu mpi init, 364 |
| | starpurm_withdraw_all_devices_from_starpu, 442 | | starpu_mpi_init_comm, 364 |
| | starpurm_withdraw_cpu_from_starpu, 438 | | starpu_mpi_init_conf, 364 |
| | starpurm_withdraw_cpu_mask_from_starpu, 439 | | starpu mpi initialize, 365 |
| | starpurm_withdraw_cpus_from_starpu, 439 | | starpu mpi initialize extended, 365 |
| | starpurm_withdraw_device_from_starpu, 442 | | starpu_mpi_insert_task, 373 |
| | starpurm_withdraw_device_mask_from_starpu, | | starpu_mpi_irecv, 366 |
| | 442 | | starpu_mpi_irecv_array_detached_unlock_tag, |
| is lo | starpurm_withdraw_devices_from_starpu, 442 aded | | 370 |
| _ | starpu_perfmodel, 311 | | starpu_mpi_irecv_detached, 367 |
| list | | | starpu_mpi_irecv_detached_sequential_consistency 368 |
| | starpu_perfmodel_per_arch, 310 | | starpu_mpi_irecv_detached_unlock_tag, 370 |
| MIC | Evtansiana 252 | | starpu_mpi_isend, 366 |
| IVIIC | Extensions, 353 | | starpu_mpi_isend_array_detached_unlock_tag, 370 |
| | STARPU_MAXMICDEVS, 353 | | |
| | STARPU_USE_MIC, 353 starpu_mic_func_symbol_t, 353 | | starpu_mpi_isend_array_detached_unlock_tag_ prio 370 |
| | starpu_mic_get_kernel, 354 | | prio, 370 starpu_mpi_isend_detached, 367 |
| | otalpa_iiio_get_keiiiei, 004 | | starpa_mpr_isena_aetaoneu, sor |

| starpu_mpi_isend_detached_prio, 367 | starpu_sched_component_specs, 425 |
|--|--|
| starpu_mpi_isend_detached_unlock_tag, 369 | model |
| starpu_mpi_isend_detached_unlock_tag_prio, 369 | starpu_codelet, 279 |
| starpu_mpi_isend_prio, 366 | modes |
| starpu_mpi_issend, 368 | starpu_codelet, 279 |
| starpu_mpi_issend_detached, 368 | starpu_task, 282 |
| starpu_mpi_issend_detached_prio, 369 | Modularized Scheduler Interface, 418 |
| starpu_mpi_issend_prio, 368 | STARPU_SCHED_COMPONENT_IS_HOMOG↔ |
| starpu_mpi_node_selection_get_current_policy, | ENEOUS, 426 |
| 374 | STARPU_SCHED_COMPONENT_IS_SINGLE_← |
| starpu_mpi_node_selection_register_policy, 374 | MEMORY_NODE, 426 |
| starpu_mpi_node_selection_set_current_policy, | STARPU_SCHED_SIMPLE_COMBINED_WOR← |
| 374 | KERS, 427 |
| starpu_mpi_node_selection_unregister_policy, | STARPU_SCHED_SIMPLE_DECIDE_ARCHS, |
| 374 | 426 |
| starpu_mpi_recv, 367 | STARPU_SCHED_SIMPLE_DECIDE_MEMNO↔ |
| starpu_mpi_redux_data, 375 | DES, 426 |
| starpu_mpi_redux_data_prio, 375 | STARPU_SCHED_SIMPLE_DECIDE_WORKE← |
| starpu_mpi_req, 364 | RS, 426 |
| starpu_mpi_scatter_detached, 375 | STARPU_SCHED_SIMPLE_FIFO_ABOVE_PRIO, |
| starpu_mpi_send, 366 | 426 |
| starpu_mpi_send_prio, 367 | STARPU_SCHED_SIMPLE_FIFO_ABOVE, 426 |
| starpu mpi shutdown, 365 | STARPU_SCHED_SIMPLE_FIFOS_BELOW_P↔ |
| starpu_mpi_tag_t, 364 | RIO, 427 |
| starpu_mpi_task_build, 373 | STARPU_SCHED_SIMPLE_FIFOS_BELOW, 426 |
| starpu_mpi_task_insert, 372 | STARPU SCHED SIMPLE IMPL, 426 |
| starpu_mpi_task_post_build, 373 | STARPU_SCHED_SIMPLE_PERFMODEL, 426 |
| starpu_mpi_test, 369 | STARPU SCHED SIMPLE WS BELOW, 427 |
| starpu_mpi_wait, 369 | starpu_sched_component_best_implementation ← |
| starpu_mpi_wait_for_all, 369 | _create, 432 |
| starpu_mpi_world_rank, 365 | starpu_sched_component_can_execute_task, 429 |
| starpu_mpi_world_size, 366 | starpu_sched_component_can_pull, 430 |
| magic | starpu_sched_component_can_pull_all, 431 |
| starpu_conf, 183 | starpu_sched_component_can_push, 430 |
| starpu_task, 286 | starpu_sched_component_composed_component |
| max_parallelism | create, 433 |
| starpu_codelet, 277 | starpu_sched_component_composed_recipe_add, |
| mf_skip | 433 |
| starpu_task, 285 | starpu_sched_component_composed_recipe_← |
| mic_funcs | create, 432 |
| starpu_codelet, 278 | starpu_sched_component_composed_recipe_← |
| mic_sink_program_path | create_singleton, 432 |
| starpu_conf, 185 | starpu_sched_component_composed_recipe_← |
| • — | destroy, 433 |
| mic_to_ram | |
| starpu_data_copy_methods, 232 | starpu_sched_component_connect, 428 |
| mic_to_ram_async | starpu_sched_component_create, 428 |
| starpu_data_copy_methods, 234 | starpu_sched_component_destroy, 429 |
| Miscellaneous Helpers, 354 | starpu_sched_component_destroy_rec, 429 |
| STARPU_MAX, 354 | starpu_sched_component_estimated_end_← |
| STARPU_MIN, 354 | average, 431 |
| STARPU_POISON_PTR, 355 | starpu_sched_component_estimated_end_min, |
| starpu_data_cpy, 356 | 431 |
| starpu_execute_on_each_worker, 355 | starpu_sched_component_estimated_end_min_~ |
| starpu_execute_on_each_worker_ex, 355 | add, 431 |
| starpu_execute_on_specific_workers, 355 | starpu_sched_component_estimated_load, 431 |
| starpu_get_env_number, 355 | starpu_sched_component_execute_preds, 429 |
| starpu_timing_now, 355 | starpu_sched_component_fifo_create, 431 |
| mix_heterogeneous_workers | starpu_sched_component_initialize_simple_← |

| scheduler, 433 | starpu_task, 282 |
|--|---|
| starpu_sched_component_is_combined_worker, | nchildren |
| 430 | starpu_data_filter, 262 |
| starpu_sched_component_is_fifo, 431 | starpu_sched_component, 422 |
| starpu sched component is random, 432 | ncombinations |
| starpu_sched_component_is_simple_worker, 430 | starpu_perfmodel, 311 |
| starpu_sched_component_is_work_stealing, 432 | ncpus |
| starpu_sched_component_is_worker, 430 | starpu_conf, 183 |
| starpu sched component make scheduler, 433 | ncuda |
| starpu_sched_component_mct_create, 432 | starpu_conf, 183 |
| starpu_sched_component_parallel_worker_create, | next |
| 429 | starpu_task, 287 |
| starpu_sched_component_properties, 427 | nmic |
| starpu_sched_component_pull_task, 428 | starpu_conf, 184 |
| starpu_sched_component_push_task, 428 | • — |
| | nmpi_ms |
| starpu_sched_component_random_create, 432 | starpu_conf, 184 |
| starpu_sched_component_transfer_length, 429 | no_submitorder |
| starpu_sched_component_work_stealing_create, | starpu_task, 285 |
| 431 | nodes |
| starpu_sched_component_worker_get, 429 | starpu_codelet, 279 |
| starpu_sched_component_worker_get_workerid, | nopencl |
| 430 | starpu_conf, 183 |
| starpu_sched_component_worker_post_exec_← | not_launched_drivers |
| hook, 430 | starpu_conf, 186 |
| starpu_sched_component_worker_pre_exec_← | notify_change_workers |
| hook, 430 | starpu_sched_component, 424 |
| starpu_sched_tree_add_workers, 428 | nparameters |
| starpu_sched_tree_create, 427 | starpu_perfmodel, 311 |
| starpu_sched_tree_destroy, 427 | nparents |
| starpu_sched_tree_pop_task, 428 | starpu_sched_component, 422 |
| starpu_sched_tree_push_task, 428 | nworkers |
| starpu_sched_tree_remove_workers, 428 | starpu_worker_collection, 210 |
| starpu_sched_tree_update_workers, 427 | |
| starpu_sched_tree_update_workers_in_ctx, 427 | obj |
| starpu_sched_tree_work_stealing_push_task, 432 | starpu_sched_component, 424 |
| mpi_ms_funcs | omp_task |
| starpu_codelet, 278 | starpu_task, 287 |
| mpi_ms_to_mpi_ms | open |
| starpu_data_copy_methods, 232 | starpu_disk_ops, 272 |
| mpi_ms_to_mpi_ms_async | OpenCL Extensions, 323 |
| starpu_data_copy_methods, 234 | STARPU_MAXOPENCLDEVS, 324 |
| mpi_ms_to_ram | STARPU_OPENCL_DATADIR, 324 |
| starpu_data_copy_methods, 232 | STARPU_OPENCL_DISPLAY_ERROR, 324 |
| mpi_ms_to_ram_async | STARPU_OPENCL_REPORT_ERROR_WITH_ |
| starpu data copy methods, 234 | MSG, 325 |
| otalpa_aata_oopy_mothodo, 20 1 | STARPU_OPENCL_REPORT_ERROR, 324 |
| n_cuda_opengl_interoperability | STARPU_USE_OPENCL, 324 |
| starpu_conf, 186 | starpu_opencl_allocate_memory, 328 |
| n_not_launched_drivers | starpu_opencl_collect_stats, 327 |
| starpu_conf, 186 | starpu_opencl_compile_opencl_from_file, 326 |
| name | starpu_opencl_compile_opencl_from_string, 326 |
| sc_hypervisor_policy, 401, 410 | starpu_opencl_copy_async_sync, 329 |
| starpu_codelet, 280 | starpu_opencl_copy_opencl_to_opencl, 329 |
| starpu_data_interface_ops, 237 | starpu_opencl_copy_opencl_to_ram, 328 |
| starpu_task, 281 | starpu_opencl_copy_ram_to_opencl, 328 |
| nb_termination_call_required | starpu_opencl_display_error, 328 |
| starpu_task, 287 | starpu_opencl_error_string, 327 |
| nbuffers | starpu_opencl_get_context, 325 |
| starpu_codelet, 279 | starpu_opencl_get_current_context, 325 |
| | states _ spansgot_outlott_outlott, oto |

| | starpu_opencl_get_current_queue, 325 | starpu_omp_master_inline, 336 |
|-----|---|---|
| | starpu_opencl_get_device, 325 | starpu_omp_ordered, 340 |
| | starpu_opencl_get_queue, 325 | starpu_omp_ordered_inline_begin, 340 |
| | starpu_opencl_load_binary_opencl, 326 | starpu_omp_ordered_inline_end, 340 |
| | starpu_opencl_load_kernel, 327 | starpu_omp_parallel_region, 335 |
| | starpu_opencl_load_opencl_from_file, 327 | starpu_omp_proc_bind_value, 335 |
| | starpu_opencl_load_opencl_from_string, 327 | starpu_omp_sched_value, 334 |
| | starpu_opencl_load_program_source, 326 | starpu_omp_sections, 341 |
| | starpu_opencl_load_program_source_malloc, 326 | starpu_omp_sections_combined, 341 |
| | starpu_opencl_release_kernel, 327 | starpu_omp_set_default_device, 347 |
| | starpu_opencl_report_error, 328 | starpu_omp_set_dynamic, 344 |
| | starpu openci set kernel args, 325 | starpu_omp_set_lock, 349 |
| | starpu_opencl_unload_opencl, 327 | starpu_omp_set_max_active_levels, 346 |
| One | nMP Runtime Support, 329 | starpu_omp_set_nest_lock, 351 |
| Opo | STARPU_OPENMP, 334 | starpu_omp_set_nested, 344 |
| | starpu_omp_atomic_fallback_inline_begin, 352 | starpu_omp_set_num_threads, 342 |
| | starpu_omp_atomic_fallback_inline_end, 352 | starpu_omp_set_schedule, 345 |
| | starpu_omp_barrier, 336 | starpu_omp_shutdown, 335 |
| | starpu_omp_critical, 336 | starpu_omp_single, 336 |
| | starpu_omp_critical_inline_begin, 336 | starpu_omp_single_copyprivate, 337 |
| | starpu_omp_critical_inline_end, 336 | starpu_omp_single_copyprivate_inline_begin, 337 |
| | starpu_omp_destroy_lock, 349 | |
| | | starpu_omp_single_copyprivate_inline_end, 337 |
| | starpu_omp_destroy_nest_lock, 350 | starpu_omp_single_inline, 337 |
| | starpu_omp_for, 338 | starpu_omp_task_region, 341 |
| | starpu_omp_for_alt, 339 | starpu_omp_taskgroup, 341 |
| | starpu_omp_for_inline_first, 338 | starpu_omp_taskgroup_inline_begin, 342 |
| | starpu_omp_for_inline_first_alt, 339 | starpu_omp_taskgroup_inline_end, 342 |
| | starpu_omp_for_inline_next, 339 | starpu_omp_taskwait, 341 |
| | starpu_omp_for_inline_next_alt, 340 | starpu_omp_test_lock, 350 |
| | starpu_omp_get_active_level, 347 | starpu_omp_test_nest_lock, 351 |
| | starpu_omp_get_ancestor_thread_num, 346 | starpu_omp_unset_lock, 350 |
| | starpu_omp_get_cancellation, 345 | starpu_omp_unset_nest_lock, 351 |
| | starpu_omp_get_default_device, 348 | starpu_omp_vector_annotate, 352 |
| | starpu_omp_get_dynamic, 344 | opencl_flags |
| | starpu_omp_get_level, 346 | starpu_codelet, 278 |
| | starpu_omp_get_max_active_levels, 346 | opencl_func |
| | starpu_omp_get_max_task_priority, 349 | starpu_codelet, 278 |
| | starpu_omp_get_max_threads, 343 | opencl_funcs |
| | starpu_omp_get_nested, 344 | starpu_codelet, 278 |
| | starpu_omp_get_num_devices, 348 | opencl_to_cuda |
| | starpu_omp_get_num_procs, 343 | starpu_data_copy_methods, 232 |
| | starpu_omp_get_num_teams, 348 | opencl_to_opencl |
| | starpu_omp_get_num_threads, 342 | starpu_data_copy_methods, 232 |
| | starpu_omp_get_proc_bind, 347 | opencl_to_opencl_async |
| | starpu_omp_get_schedule, 345 | starpu_data_copy_methods, 233 |
| | starpu_omp_get_team_num, 348 | opencl_to_ram |
| | starpu omp get team size, 347 | starpu_data_copy_methods, 232 |
| | starpu omp get thread limit, 345 | opencl_to_ram_async |
| | starpu_omp_get_thread_num, 343 | starpu_data_copy_methods, 233 |
| | starpu_omp_get_wtick, 352 | Out Of Core, 270 |
| | starpu_omp_get_wtime, 352 | STARPU_DISK_SIZE_MIN, 273 |
| | starpu_omp_in_final, 347 | starpu_disk_close, 273 |
| | starpu_omp_in_parallel, 343 | starpu_disk_hdf5_ops, 274 |
| | starpu_omp_init, 335 | starpu_disk_leveldb_ops, 274 |
| | starpu_omp_init_lock, 349 | starpu_disk_open, 273 |
| | starpu_omp_init_nest_lock, 350 | starpu_disk_register, 273 |
| | starpu_omp_is_initial_device, 349 | starpu_disk_stdio_ops, 274 |
| | starpu_omp_master, 335 | starpu_disk_stato_ops, 274 starpu_disk_swap_node, 274 |
| | otarpa_omp_master, ooo | σιαι ρα_αισικ_σνναρ_πουσ, <u>Ε/</u> Τ |

| starpu_disk_unistd_o_direct_ops, 274 starpu_disk_unistd_ops, 274 | starpu_task, 287 post_exec_hook |
|---|--|
| pack_data | starpu_sched_policy, 393 |
| starpu_data_interface_ops, 237 | pre_exec_hook |
| Parallel Tasks, 379 | starpu_sched_policy, 393 |
| starpu_combined_worker_assign_workerid, 380 | predicted |
| starpu_combined_worker_can_execute_task, 380 | starpu_task, 287 |
| starpu_combined_worker_get_count, 380 | predicted_transfer |
| starpu_combined_worker_get_description, 380 | starpu_task, 287 |
| starpu_combined_worker_get_id, 380 | prev |
| starpu_combined_worker_get_rank, 380 | starpu_task, 287 |
| starpu_combined_worker_get_size, 380 | priority |
| starpu_parallel_task_barrier_init, 380 | starpu_task, 286 |
| starpu_parallel_task_barrier_init_n, 381 | Profiling, 315 |
| parameters_names | STARPU_PROFILING_DISABLE, 317 STARPU_PROFILING_ENABLE, 317 |
| starpu_perfmodel, 311 | |
| parents | starpu_bus_get_count, 318 starpu_bus_get_dst, 318 |
| starpu_sched_component, 423 | starpu_bus_get_id, 318 |
| per_worker_stats | starpu_bus_get_nd, 316 starpu_bus_get_profiling_info, 318 |
| starpu_codelet, 280 | starpu_bus_get_src, 318 |
| Performance Model, 306 | starpu_bus_get_src, 310 starpu_data_display_memory_stats, 319 |
| starpu_bus_print_affinity, 314 | starpu_data_display_memory_stats, 575 starpu_profiling_bus_helper_display_summary, |
| starpu_bus_print_bandwidth, 314 | 318 |
| starpu_bus_print_filenames, 314 | starpu_profiling_init, 317 |
| starpu_perfmodel_debugfilepath, 313 | starpu_profiling_set_id, 317 |
| starpu_perfmodel_directory, 314 | starpu_profiling_status_get, 317 |
| starpu_perfmodel_dump_xml, 312 | starpu_profiling_status_set, 317 |
| starpu_perfmodel_free_sampling_directories, 313 | starpu_profiling_worker_get_info, 318 |
| starpu_perfmodel_get_arch_name, 313 | starpu_profiling_worker_helper_display_summary, |
| starpu_perfmodel_get_model_path, 312 | 319 |
| starpu_perfmodel_history_based_expected_perf, | starpu_timing_timespec_delay_us, 318 |
| 313 | starpu timing timespec to us, 318 |
| starpu_perfmodel_init, 312 | profiling_info |
| starpu_perfmodel_initialize, 313 | starpu_task, 287 |
| starpu_perfmodel_list, 313 | prologue_callback_arg |
| starpu_perfmodel_load_file, 312 | starpu task, 284 |
| starpu_perfmodel_load_symbol, 312 | prologue_callback_arg_free |
| starpu_perfmodel_nop, 315 | starpu_task, 284 |
| starpu_perfmodel_type, 311 | prologue_callback_func |
| starpu_perfmodel_unload_model, 312 | starpu_task, 283 |
| starpu_perfmodel_update_history, 314 | prologue_callback_pop_arg_free |
| starpu_transfer_bandwidth, 314 | starpu_task, 284 |
| starpu_transfer_latency, 314 | pull_task |
| starpu_transfer_predict, 314 | starpu_sched_component, 423 |
| starpu_worker_get_perf_archtype, 313 | push_task |
| plug | starpu_sched_component, 423 |
| starpu_disk_ops, 271 | starpu_sched_policy, 392 |
| pointer_is_inside | push_task_notify |
| starpu_data_interface_ops, 236 | starpu_sched_policy, 393 |
| policy_description | ware to accele |
| starpu_sched_policy, 394 | ram_to_cuda |
| policy_name | starpu_data_copy_methods, 231 |
| starpu_sched_policy, 393 | ram_to_cuda_async |
| pop_every_task starpu_sched_policy, 393 | starpu_data_copy_methods, 233 |
| pop_task | ram_to_mic starpu_data_copy_methods, 231 |
| starpu_sched_policy, 393 | ram_to_mic_async |
| possibly_parallel | starpu_data_copy_methods, 234 |
| possibly_paraller | otatpu_data_oopy_methodo, 204 |

| ram_to_mpi_ms | SC_HYPERVISOR_NEW_WORKERS_MAX_IDLE |
|--|---|
| starpu_data_copy_methods, 232 | Scheduling Context Hypervisor - Building a new re |
| ram_to_mpi_ms_async | sizing policy, 404 |
| starpu_data_copy_methods, 233 | SC_HYPERVISOR_NULL |
| ram_to_opencl | Scheduling Context Hypervisor - Building a new re |
| starpu_data_copy_methods, 231 | sizing policy, 404 |
| ram_to_opencl_async | SC_HYPERVISOR_PRIORITY |
| starpu_data_copy_methods, 233 | |
| | Scheduling Context Hypervisor - Building a new re |
| ram_to_ram | sizing policy, 403 |
| starpu_data_copy_methods, 231 | SC_HYPERVISOR_TIME_TO_APPLY |
| read | Scheduling Context Hypervisor - Building a new re |
| starpu_disk_ops, 272 | sizing policy, 404 |
| regenerate | STARPU_ABORT_MSG |
| starpu_task, 285 | Toolbox, 195 |
| register_data_handle | STARPU_ABORT |
| starpu_data_interface_ops, 235 | Toolbox, 195 |
| regression | STARPU_ACQUIRE_NO_NODE_LOCK_ALL |
| starpu_perfmodel_per_arch, 310 | Data Management, 218 |
| remove | STARPU_ACQUIRE_NO_NODE |
| starpu_worker_collection, 210 | Data Management, 218 |
| remove_child | STARPU_ASSERT_MSG |
| starpu_sched_component, 423 | Toolbox, 194 |
| remove_workers | STARPU_ASSERT |
| starpu_sched_policy, 393 | |
| reserve_ncpus | Toolbox, 194 |
| starpu_conf, 183 | STARPU_ATTRIBUTE_ALIGNED |
| resize_ctxs | Toolbox, 194 |
| sc_hypervisor_policy, 401, 411 | STARPU_ATTRIBUTE_INTERNAL |
| Running Drivers, 381 | Toolbox, 194 |
| | STARPU_ATTRIBUTE_MALLOC |
| starpu_driver_deinit, 382 | Toolbox, 194 |
| starpu_driver_init, 382 | STARPU_ATTRIBUTE_NORETURN |
| starpu_driver_run, 381 | Toolbox, 194 |
| starpu_driver_run_once, 382 | STARPU_ATTRIBUTE_PURE |
| starpu_drivers_request_termination, 382 | Toolbox, 194 |
| SC HYPERVISOR FIXED WORKERS | STARPU ATTRIBUTE UNUSED |
| | Toolbox, 194 |
| Scheduling Context Hypervisor - Building a new re- | STARPU_ATTRIBUTE_WARN_UNUSED_RESULT |
| sizing policy, 403 | Toolbox, 194 |
| SC_HYPERVISOR_GRANULARITY | STARPU_BCSR_GET_COLIND_DEV_HANDLE |
| Scheduling Context Hypervisor - Building a new re- | Data Interfaces, 246 |
| sizing policy, 403 | STARPU_BCSR_GET_COLIND |
| SC_HYPERVISOR_ISPEED_CTX_SAMPLE | |
| Scheduling Context Hypervisor - Building a new re- | Data Interfaces, 246 |
| sizing policy, 404 | STARPU_BCSR_GET_NNZ |
| SC_HYPERVISOR_ISPEED_W_SAMPLE | Data Interfaces, 246 |
| Scheduling Context Hypervisor - Building a new re- | STARPU_BCSR_GET_NZVAL_DEV_HANDLE |
| sizing policy, 404 | Data Interfaces, 246 |
| SC_HYPERVISOR_MAX_IDLE | STARPU_BCSR_GET_NZVAL |
| Scheduling Context Hypervisor - Building a new re- | Data Interfaces, 246 |
| sizing policy, 403 | STARPU_BCSR_GET_OFFSET |
| SC_HYPERVISOR_MAX_WORKERS | Data Interfaces, 247 |
| Scheduling Context Hypervisor - Building a new re- | STARPU_BCSR_GET_ROWPTR_DEV_HANDLE |
| sizing policy, 403 | Data Interfaces, 246 |
| SC_HYPERVISOR_MIN_TASKS | STARPU_BCSR_GET_ROWPTR |
| Scheduling Context Hypervisor - Building a new re- | Data Interfaces, 246 |
| sizing policy, 403 | STARPU_BLOCK_GET_DEV_HANDLE |
| SC_HYPERVISOR_MIN_WORKERS | Data Interfaces, 242 |
| Scheduling Context Hypervisor - Building a new re- | STARPU_BLOCK_GET_ELEMSIZE |
| - · · · · · · · · · · · · · · · · · · · | |
| sizing policy, 403 | Data Interfaces, 243 |

| STARPU_BLOCK_GET_LDY | Data Interfaces, 242 |
|--|---------------------------------------|
| Data Interfaces, 243 | STARPU_COO_GET_ROWS |
| STARPU_BLOCK_GET_LDZ | Data Interfaces, 241 |
| Data Interfaces, 243 | STARPU_COO_GET_VALUES_DEV_HANDLE |
| STARPU_BLOCK_GET_NX | Data Interfaces, 242 |
| Data Interfaces, 243 | STARPU_COO_GET_VALUES |
| STARPU_BLOCK_GET_NY | Data Interfaces, 242 |
| Data Interfaces, 243 | STARPU_CPU |
| STARPU_BLOCK_GET_NZ | Codelet And Tasks, 288 |
| Data Interfaces, 243 | STARPU_CSR_GET_COLIND_DEV_HANDLE |
| STARPU_BLOCK_GET_OFFSET | Data Interfaces, 245 |
| Data Interfaces, 243 | STARPU_CSR_GET_COLIND |
| STARPU_BLOCK_GET_PTR | Data Interfaces, 245 |
| Data Interfaces, 242 | STARPU_CSR_GET_ELEMSIZE |
| STARPU_CALLBACK_ARG | Data Interfaces, 246 |
| Task Insert Utility, 298 | STARPU_CSR_GET_FIRSTENTRY |
| STARPU_CALLBACK_WITH_ARG | Data Interfaces, 246 |
| Task Insert Utility, 298 | STARPU_CSR_GET_NNZ |
| STARPU_CALLBACK | Data Interfaces, 245 |
| Task Insert Utility, 298 | STARPU_CSR_GET_NROW |
| STARPU_CHECK_RETURN_VALUE_IS | Data Interfaces, 245 |
| Toolbox, 195 | STARPU_CSR_GET_NZVAL_DEV_HANDLE |
| STARPU_CHECK_RETURN_VALUE | Data Interfaces, 245 |
| Toolbox, 195 | STARPU_CSR_GET_NZVAL |
| STARPU_CL_ARGS_NFREE | Data Interfaces, 245 |
| Task Insert Utility, 299 | STARPU_CSR_GET_OFFSET |
| STARPU_CL_ARGS | Data Interfaces, 245 |
| Task Insert Utility, 299 | STARPU_CSR_GET_ROWPTR_DEV_HANDLE |
| STARPU_CODELET_GET_MODE | Data Interfaces, 245 |
| Codelet And Tasks, 290 | STARPU_CSR_GET_ROWPTR |
| STARPU_CODELET_GET_NODE | Data Interfaces, 245 |
| Codelet And Tasks, 291 | STARPU_CUBLAS_REPORT_ERROR |
| STARPU_CODELET_NOPLANS | CUDA Extensions, 321 |
| Codelet And Tasks, 288 | STARPU_CUDA_ASYNC |
| STARPU_CODELET_SET_MODE | Codelet And Tasks, 289 |
| Codelet And Tasks, 290 | STARPU_CUDA_REPORT_ERROR |
| STARPU_CODELET_SET_NODE | CUDA Extensions, 321 |
| Codelet And Tasks, 291 | STARPU_CUDA |
| STARPU_CODELET_SIMGRID_EXECUTE_AND_IN← | Codelet And Tasks, 288 |
| JECT | STARPU_DATA_ACQUIRE_CB |
| Codelet And Tasks, 288 | Data Management, 218 |
| STARPU_CODELET_SIMGRID_EXECUTE | STARPU_DEFAULT_PRIO |
| Codelet And Tasks, 288 | Scheduling Contexts, 386 |
| STARPU_COO_GET_COLUMNS_DEV_HANDLE | STARPU_DISK_SIZE_MIN |
| Data Interfaces, 241 | Out Of Core, 273 |
| STARPU_COO_GET_COLUMNS | STARPU_EXECUTE_ON_DATA |
| Data Interfaces, 241 | MPI Support, 363 |
| STARPU_COO_GET_ELEMSIZE | STARPU_EXECUTE_ON_NODE |
| Data Interfaces, 242 | MPI Support, 363 |
| STARPU_COO_GET_NVALUES | STARPU_EXECUTE_ON_WORKER |
| Data Interfaces, 242 | Task Insert Utility, 298 |
| STARPU_COO_GET_NX | STARPU_EXECUTE_WHERE |
| Data Interfaces, 242 | Task Insert Utility, 298 |
| STARPU_COO_GET_NY | STARPU_FLOPS |
| Data Interfaces, 242 | Task Insert Utility, 298 |
| STARPU_COO_GET_OFFSET | STARPU_GNUC_PREREQ |
| Data Interfaces, 242 | Toolbox, 193 |
| STARPU_COO_GET_ROWS_DEV_HANDLE | STARPU_HANDLES_SEQUENTIAL_CONSISTENCY |
| | |

| Task Insert Utility, 299 | Scheduling Contexts, 385 |
|---------------------------------|--|
| STARPU_LIKELY | STARPU_MINOR_VERSION |
| Toolbox, 194 | Versioning, 181 |
| STARPU_MAIN_RAM | STARPU MIC |
| Codelet And Tasks, 289 | Codelet And Tasks, 288 |
| STARPU_MAJOR_VERSION | STARPU MIN |
| Versioning, 181 | Miscellaneous Helpers, 354 |
| STARPU_MALLOC_COUNT | STARPU_MPI_MS |
| Standard Memory Library, 189 | Codelet And Tasks, 288 |
| STARPU_MALLOC_NORECLAIM | STARPU MPI PER NODE |
| Standard Memory Library, 189 | MPI Support, 363 |
| STARPU_MALLOC_PINNED | STARPU_MPI_TAG_UB |
| Standard Memory Library, 189 | MPI Support, 363 |
| STARPU MALLOC SIMULATION FOLDED | STARPU_MULTIFORMAT_GET_CPU_PTR |
| Standard Memory Library, 190 | Data Interfaces, 247 |
| STARPU_MATRIX_GET_ALLOCSIZE | STARPU_MULTIFORMAT_GET_CUDA_PTR |
| Data Interfaces, 241 | Data Interfaces, 247 |
| STARPU MATRIX GET DEV HANDLE | STARPU_MULTIFORMAT_GET_MIC_PTR |
| Data Interfaces, 240 | Data Interfaces, 247 |
| | STARPU_MULTIFORMAT_GET_NX |
| STARPU_MATRIX_GET_ELEMSIZE | |
| Data Interfaces, 241 | Data Interfaces, 247 |
| STARPU_MATRIX_GET_LD | STARPU_MULTIFORMAT_GET_OPENCL_PTR |
| Data Interfaces, 241 | Data Interfaces, 247 |
| STARPU_MATRIX_GET_NX | STARPU_MULTIPLE_CPU_IMPLEMENTATIONS |
| Data Interfaces, 240 | Codelet And Tasks, 289 |
| STARPU_MATRIX_GET_NY | STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS |
| Data Interfaces, 240 | Codelet And Tasks, 289 |
| STARPU_MATRIX_GET_OFFSET | STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS |
| Data Interfaces, 240 | Codelet And Tasks, 289 |
| STARPU_MATRIX_GET_PTR | STARPU_NAME |
| Data Interfaces, 240 | Task Insert Utility, 299 |
| STARPU_MATRIX_SET_LD | STARPU_NMAX_SCHED_CTXS |
| Data Interfaces, 241 | Scheduling Policy, 394 |
| STARPU_MATRIX_SET_NX | STARPU_NMAXBUFS |
| Data Interfaces, 241 | Codelet And Tasks, 288 |
| STARPU_MATRIX_SET_NY | STARPU_NMAXWORKERS |
| Data Interfaces, 241 | Workers' Properties, 210 |
| STARPU_MAX_PRIO | STARPU_NODE_SELECTION_POLICY |
| Scheduling Contexts, 386 | MPI Support, 363 |
| STARPU_MAXCPUS | STARPU_NOWHERE |
| Workers' Properties, 211 | Codelet And Tasks, 288 |
| STARPU_MAXIMPLEMENTATIONS | STARPU_OPENCL_ASYNC |
| Scheduling Policy, 394 | Codelet And Tasks, 289 |
| STARPU_MAXMICDEVS | STARPU_OPENCL_DATADIR |
| MIC Extensions, 353 | OpenCL Extensions, 324 |
| STARPU_MAXNODES | STARPU_OPENCL_DISPLAY_ERROR |
| Workers' Properties, 211 | OpenCL Extensions, 324 |
| STARPU_MAXNUMANODES | STARPU_OPENCL_REPORT_ERROR_WITH_MSG |
| Workers' Properties, 211 | OpenCL Extensions, 325 |
| STARPU_MAXOPENCLDEVS | STARPU_OPENCL_REPORT_ERROR |
| OpenCL Extensions, 324 | OpenCL Extensions, 324 |
| STARPU_MAX | STARPU_OPENCL |
| Miscellaneous Helpers, 354 | Codelet And Tasks, 288 |
| STARPU_MEMORY_OVERFLOW | STARPU_OPENMP |
| Standard Memory Library, 190 | OpenMP Runtime Support, 334 |
| STARPU_MEMORY_WAIT | STARPU_POISON_PTR |
| Standard Memory Library, 190 | Miscellaneous Helpers, 355 |
| STARPU MIN PRIO | STARPU_PRIORITY |

| Task Insert Utility, 298 | Toolbox, 195 |
|-------------------------------------|---|
| STARPU_PROFILING_DISABLE | STARPU_SCHED_COMPONENT_IS_HOMOGENE ← |
| Profiling, 317 | OUS |
| STARPU_PROFILING_ENABLE | Modularized Scheduler Interface, 426 |
| Profiling, 317 | STARPU_SCHED_COMPONENT_IS_SINGLE_ME |
| STARPU_PTHREAD_BARRIER_DESTROY | MORY_NODE |
| Threads, 199 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_BARRIER_INIT | STARPU_SCHED_CTX_AWAKE_WORKERS |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_BARRIER_WAIT | STARPU_SCHED_CTX_CUDA_NSMS |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_COND_BROADCAST | STARPU_SCHED_CTX_POLICY_INIT |
| | Scheduling Contexts, 385 |
| Threads, 199 | |
| STARPU_PTHREAD_COND_DESTROY | STARPU_SCHED_CTX_POLICY_MAX_PRIO |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_COND_INITIALIZER | STARPU_SCHED_CTX_POLICY_MIN_PRIO |
| Threads, 200 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_COND_INIT | STARPU_SCHED_CTX_POLICY_NAME |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_COND_SIGNAL | STARPU_SCHED_CTX_POLICY_STRUCT |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_COND_WAIT | STARPU_SCHED_CTX_SUB_CTXS |
| Threads, 199 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_CREATE_ON | STARPU_SCHED_CTX_USER_DATA |
| Threads, 197 | Scheduling Contexts, 385 |
| STARPU_PTHREAD_CREATE | STARPU_SCHED_CTX |
| Threads, 197 | Task Insert Utility, 298 |
| STARPU_PTHREAD_GETSPECIFIC | STARPU_SCHED_SIMPLE_COMBINED_WORKERS |
| Threads, 198 | Modularized Scheduler Interface, 427 |
| STARPU_PTHREAD_KEY_CREATE | STARPU_SCHED_SIMPLE_DECIDE_ARCHS |
| Threads, 198 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_KEY_DELETE | STARPU_SCHED_SIMPLE_DECIDE_MEMNODES |
| Threads, 198 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_MUTEX_DESTROY | STARPU_SCHED_SIMPLE_DECIDE_WORKERS |
| Threads, 197 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_MUTEX_INITIALIZER | STARPU_SCHED_SIMPLE_FIFO_ABOVE_PRIO |
| Threads, 200 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_MUTEX_INIT | STARPU_SCHED_SIMPLE_FIFO_ABOVE |
| Threads, 197 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_MUTEX_LOCK | STARPU_SCHED_SIMPLE_FIFOS_BELOW_PRIO |
| Threads, 197 | Modularized Scheduler Interface, 427 |
| STARPU_PTHREAD_MUTEX_UNLOCK | STARPU_SCHED_SIMPLE_FIFOS_BELOW |
| Threads, 198 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_RWLOCK_DESTROY | STARPU_SCHED_SIMPLE_IMPL |
| Threads, 199 | Modularized Scheduler Interface, 426 |
| STARPU PTHREAD RWLOCK INIT | STARPU_SCHED_SIMPLE_PERFMODEL |
| Threads, 198 | Modularized Scheduler Interface, 426 |
| STARPU_PTHREAD_RWLOCK_RDLOCK | STARPU SCHED SIMPLE WS BELOW |
| Threads, 198 | Modularized Scheduler Interface, 427 |
| STARPU_PTHREAD_RWLOCK_UNLOCK | STARPU_SPECIFIC_NODE_LOCAL |
| Threads, 198 | Codelet And Tasks, 289 |
| STARPU_PTHREAD_RWLOCK_WRLOCK | STARPU_TAG_ONLY |
| Threads, 198 | Task Insert Utility, 298 |
| STARPU_PTHREAD_SETSPECIFIC | STARPU TASK COLOR |
| Threads, 198 | Task Insert Utility, 299 |
| STARPU_RELEASE_VERSION | STARPU_TASK_DEPS_ARRAY |
| Versioning, 181 | Task Insert Utility, 299 |
| STARPU RMB | STARPU_TASK_END_DEPS_ARRAY |
| - · · · · · · · · · · · · · · · · · | - · · · · · · · · · · · · · · · · · · · |

| Tools Inpart Hillits 200 | Data Interference 244 |
|--|--|
| Task Insert Utility, 299 STARPU_TASK_END_DEP | Data Interfaces, 244 |
| | STARPU_WMB |
| Task Insert Utility, 299 | Toolbox, 195 |
| STARPU_TASK_GET_HANDLE | STARPU_WORKER_ORDER |
| Codelet And Tasks, 290 | Task Insert Utility, 299 |
| STARPU_TASK_GET_MODE | sc_hypervisor.h, 494 |
| Codelet And Tasks, 290 | sc_hypervisor_add_workers_to_sched_ctx |
| STARPU_TASK_GET_NBUFFERS | Scheduling Context Hypervisor - Regular usage, |
| Codelet And Tasks, 290 | 412 |
| STARPU_TASK_INITIALIZER | sc_hypervisor_can_resize |
| Codelet And Tasks, 289 | Scheduling Context Hypervisor - Regular usage, |
| STARPU_TASK_SET_HANDLE | 413 |
| Codelet And Tasks, 290 | sc_hypervisor_check_idle |
| STARPU_TASK_SET_MODE | Scheduling Context Hypervisor - Building a new re- |
| Codelet And Tasks, 290 | sizing policy, 407 |
| STARPU_TASK_SYNCHRONOUS | sc_hypervisor_check_if_consider_max |
| Task Insert Utility, 299 | Scheduling Context Hypervisor - Building a new re- |
| STARPU_TAG | sizing policy, 407 |
| Task Insert Utility, 298 | sc_hypervisor_check_speed_gap_btw_ctxs |
| STARPU_THREAD_ACTIVE | Scheduling Context Hypervisor - Building a new re- |
| Initialization and Termination, 186 | sizing policy, 407 |
| STARPU_UNLIKELY | sc_hypervisor_check_speed_gap_btw_ctxs_on_level |
| Toolbox, 194 | Scheduling Context Hypervisor - Building a new re- |
| STARPU_USE_MIC | sizing policy, 408 |
| MIC Extensions, 353 | sc_hypervisor_compute_nworkers_to_move |
| STARPU_USE_MPI_MASTER_SLAVE | Scheduling Context Hypervisor - Building a new re- |
| MPI Support, 362 | sizing policy, 406 |
| STARPU_USE_MPI | sc_hypervisor_config.h, 495 |
| MPI Support, 362 | sc_hypervisor_criteria_fulfilled |
| STARPU_USE_OPENCL | Scheduling Context Hypervisor - Building a new re- |
| OpenCL Extensions, 324 | sizing policy, 407 |
| STARPU_VALUE | sc_hypervisor_ctl |
| Task Insert Utility, 298 | Scheduling Context Hypervisor - Building a new re- |
| STARPU VARIABLE GET DEV HANDLE | sizing policy, 408 |
| Data Interfaces, 244 | sc_hypervisor_find_lowest_prio_sched_ctx |
| STARPU_VARIABLE_GET_ELEMSIZE | Scheduling Context Hypervisor - Building a new re- |
| Data Interfaces, 244 | sizing policy, 405 |
| STARPU VARIABLE GET OFFSET | sc_hypervisor_free_size_req |
| Data Interfaces, 244 | Scheduling Context Hypervisor - Regular usage, |
| STARPU_VARIABLE_GET_PTR | 413 |
| Data Interfaces, 244 | sc_hypervisor_get_arch_for_index |
| STARPU_VARIABLE_NBUFFERS | Scheduling Context Hypervisor - Building a new re- |
| Codelet And Tasks, 289 | sizing policy, 407 |
| STARPU VECTOR GET ALLOCSIZE | sc_hypervisor_get_avg_speed |
| Data Interfaces, 244 | |
| | Scheduling Context Hypervisor - Building a new re- |
| STARPU_VECTOR_GET_DEV_HANDLE | sizing policy, 407 |
| Data Interfaces, 243 | sc_hypervisor_get_config |
| STARPU_VECTOR_GET_ELEMSIZE | Scheduling Context Hypervisor - Building a new re- |
| Data Interfaces, 244 | sizing policy, 408 |
| STARPU_VECTOR_GET_NX | sc_hypervisor_get_ctx_speed |
| Data Interfaces, 244 | Scheduling Context Hypervisor - Building a new re- |
| STARPU_VECTOR_GET_OFFSET | sizing policy, 406 |
| Data Interfaces, 244 | sc_hypervisor_get_ctxs_on_level |
| STARPU_VECTOR_GET_PTR | Scheduling Context Hypervisor - Regular usage, |
| Data Interfaces, 243 | 414 |
| STARPU_VECTOR_GET_SLICE_BASE | sc_hypervisor_get_elapsed_flops_per_sched_ctx |
| Data Interfaces, 244 | Scheduling Context Hypervisor - Building a new re- |
| STARPU_VECTOR_SET_NX | sizing policy, 404 |

sc_hypervisor_get_fastest_ctx_exec_time Scheduling Context Hypervisor - Building a new resizing policy, 406 sc_hypervisor_get_idlest_workers Scheduling Context Hypervisor - Building a new resizing policy, 405 sc hypervisor get idlest workers in list Scheduling Context Hypervisor - Building a new resizing policy, 405 sc_hypervisor_get_index_for_arch Scheduling Context Hypervisor - Building a new resizing policy, 407 sc_hypervisor_get_leaves Scheduling Context Hypervisor - Regular usage, 414 sc_hypervisor_get_movable_nworkers Scheduling Context Hypervisor - Building a new resizing policy, 406 sc_hypervisor_get_nhierarchy_levels Scheduling Context Hypervisor - Regular usage, $sc_hypervisor_get_nready_flops_of_all_sons_of_{\leftarrow}$ sched_ctx Scheduling Context Hypervisor - Regular usage, 414 sc hypervisor get nsched ctxs Scheduling Context Hypervisor - Building a new resizing policy, 404 sc_hypervisor_get_nworkers_ctx Scheduling Context Hypervisor - Building a new resizing policy, 408 sc_hypervisor_get_policy Scheduling Context Hypervisor - Regular usage, sc_hypervisor_get_ref_speed_per_worker_type Scheduling Context Hypervisor - Building a new resizing policy, 407 sc_hypervisor_get_resize_criteria Scheduling Context Hypervisor - Building a new resizing policy, 408 sc_hypervisor_get_sched_ctxs Scheduling Context Hypervisor - Building a new resizing policy, 404 sc hypervisor get size req Scheduling Context Hypervisor - Regular usage, sc_hypervisor_get_slowest_ctx_exec_time Scheduling Context Hypervisor - Building a new resizing policy, 406 sc_hypervisor_get_speed Scheduling Context Hypervisor - Building a new resizing policy, 409 sc_hypervisor_get_speed_per_worker Scheduling Context Hypervisor - Building a new resizing policy, 406 sc hypervisor get speed per worker type

Scheduling Context Hypervisor - Building a new re-

sc_hypervisor_get_tasks_times Scheduling Context Hypervisor - Building a new resizing policy, 405 sc_hypervisor_get_total_elapsed_flops_per_sched_ctx Scheduling Context Hypervisor - Building a new resizing policy, 408 sc_hypervisor_get_types_of_workers Scheduling Context Hypervisor - Building a new resizing policy, 408 sc_hypervisor_get_wrapper Scheduling Context Hypervisor - Building a new resizing policy, 404 sc_hypervisor_group_workers_by_type Scheduling Context Hypervisor - Building a new resizing policy, 407 sc_hypervisor_init Scheduling Context Hypervisor - Regular usage, 411 sc_hypervisor_lp.h, 496 sc_hypervisor_lp_distribute_floating_no_resources_ in ctxs Scheduling Context Hypervisor - Linear Programming, 416 sc_hypervisor_lp_distribute_resources_in_ctxs Scheduling Context Hypervisor - Linear Programming, 416 sc hypervisor lp execute dichotomy Scheduling Context Hypervisor - Linear Programming, 417 sc_hypervisor_lp_find_tmax Scheduling Context Hypervisor - Linear Programming, 417 sc_hypervisor_lp_get_nworkers_per_ctx Scheduling Context Hypervisor - Linear Programming, 415 sc_hypervisor_lp_get_tmax Scheduling Context Hypervisor - Linear Programming, 416 sc_hypervisor_lp_place_resources_in_ctx Scheduling Context Hypervisor - Linear Programming, 416 sc_hypervisor_lp_redistribute_resources_in_ctxs Scheduling Context Hypervisor - Linear Programmina, 416 sc_hypervisor_lp_round_double_to_int Scheduling Context Hypervisor - Linear Programming, 416 sc_hypervisor_lp_share_remaining_resources Scheduling Context Hypervisor - Linear Programming, 417 sc_hypervisor_lp_simulate_distrib_flops Scheduling Context Hypervisor - Linear Programming, 417 sc_hypervisor_lp_simulate_distrib_flops_on_sample Scheduling Context Hypervisor - Linear Programming, 418

sc_hypervisor_lp_simulate_distrib_tasks

Scheduling Context Hypervisor - Linear Program-

sizing policy, 406

| ming, 417 | 414 |
|--|---|
| sc_hypervisor_monitoring.h, 497 | sc_hypervisor_shutdown |
| sc_hypervisor_move_workers | Scheduling Context Hypervisor - Regular usage, |
| Scheduling Context Hypervisor - Regular usage, | 411 |
| 413 | sc_hypervisor_size_ctxs |
| sc_hypervisor_policy, 401, 410 | Scheduling Context Hypervisor - Regular usage, |
| custom, 401, 410 | 413 |
| end_ctx, 402, 411 | sc_hypervisor_start_resize |
| handle_idle_cycle, 401, 411 | Scheduling Context Hypervisor - Regular usage, |
| handle_idle_end, 402, 411 | 412 |
| handle_poped_task, 402, 411 | sc_hypervisor_stop_resize |
| handle post exec hook, 402, 411 | Scheduling Context Hypervisor - Regular usage, |
| handle_pushed_task, 402, 411 | 412 |
| handle_submitted_job, 402, 411 | sc_hypervisor_unregister_ctx |
| | Scheduling Context Hypervisor - Regular usage, |
| init_worker, 402, 411 | 412 |
| name, 401, 410 | sc_hypervisor_update_diff_elapsed_flops |
| resize_ctxs, 401, 411 | |
| size_ctxs, 401, 410 | Scheduling Context Hypervisor - Regular usage, 414 |
| start_ctx, 402, 411 | |
| sc_hypervisor_policy.h, 499 | sc_hypervisor_update_diff_total_flops |
| sc_hypervisor_policy_add_task_to_pool | Scheduling Context Hypervisor - Regular usage, |
| Scheduling Context Hypervisor - Building a new re- | 414 |
| sizing policy, 405 | sc_hypervisor_update_resize_interval |
| sc_hypervisor_policy_clone_task_pool | Scheduling Context Hypervisor - Regular usage, |
| Scheduling Context Hypervisor - Building a new re- | 414 |
| sizing policy, 405 | sc_hypervisor_wrapper, 497 |
| sc_hypervisor_policy_config, 495 | sc_hypervisorsc_hypervisor_get_speed_per_worker_ |
| sc_hypervisor_policy_remove_task_from_pool | type |
| Scheduling Context Hypervisor - Building a new re- | Scheduling Context Hypervisor - Building a new re- |
| sizing policy, 405 | sizing policy, 409 |
| sc_hypervisor_policy_resize | sched_ctx |
| Scheduling Context Hypervisor - Building a new re- | starpu_task, 286 |
| sizing policy, 406 | sched_data |
| sc_hypervisor_policy_resize_to_unknown_receiver | starpu_task, 287 |
| Scheduling Context Hypervisor - Building a new re- | sched_policy |
| sizing policy, 406 | starpu_conf, 183 |
| sc_hypervisor_policy_task_pool, 403 | sched_policy_name |
| sc_hypervisor_post_resize_request | starpu_conf, 183 |
| Scheduling Context Hypervisor - Regular usage, | scheduled |
| 412 | starpu_task, 285 |
| sc_hypervisor_register_ctx | Scheduling Context Hypervisor - Building a new resizing |
| Scheduling Context Hypervisor - Regular usage, | policy, 399 |
| 412 | SC_HYPERVISOR_FIXED_WORKERS, 403 |
| sc_hypervisor_remove_workers_from_sched_ctx | SC_HYPERVISOR_GRANULARITY, 403 |
| Scheduling Context Hypervisor - Regular usage, | SC_HYPERVISOR_ISPEED_CTX_SAMPLE, 404 |
| 413 | SC_HYPERVISOR_ISPEED_W_SAMPLE, 404 |
| sc_hypervisor_resize_ack, 402 | SC_HYPERVISOR_MAX_IDLE, 403 |
| sc_hypervisor_resize_ctxs | SC_HYPERVISOR_MAX_WORKERS, 403 |
| Scheduling Context Hypervisor - Regular usage, | SC_HYPERVISOR_MIN_TASKS, 403 |
| 412 | SC_HYPERVISOR_MIN_WORKERS, 403 |
| sc_hypervisor_save_size_req | SC_HYPERVISOR_NEW_WORKERS_MAX_ID↔ |
| Scheduling Context Hypervisor - Regular usage, | LE, 404 |
| 413 | SC_HYPERVISOR_NULL, 404 |
| sc_hypervisor_set_config | SC_HYPERVISOR_PRIORITY, 403 |
| Scheduling Context Hypervisor - Building a new re- | SC_HYPERVISOR_TIME_TO_APPLY, 404 |
| sizing policy, 408 | sc_hypervisor_check_idle, 407 |
| sc_hypervisor_set_type_of_task | sc_hypervisor_check_if_consider_max, 407 |
| Scheduling Context Hypervisor - Regular usage, | sc_hypervisor_check_speed_gap_btw_ctxs, 407 |

| sc_hypervisor_check_speed_gap_btw_ctxs_on_← | 417 |
|--|--|
| level, 408 | sc_hypervisor_lp_simulate_distrib_flops, 417 |
| sc_hypervisor_compute_nworkers_to_move, 406 | sc_hypervisor_lp_simulate_distrib_flops_on_← |
| sc_hypervisor_criteria_fulfilled, 407 | sample, 418 |
| sc_hypervisor_ctl, 408 | sc_hypervisor_lp_simulate_distrib_tasks, 417 |
| sc_hypervisor_find_lowest_prio_sched_ctx, 405 | Scheduling Context Hypervisor - Regular usage, 409 |
| sc_hypervisor_get_arch_for_index, 407 | act_hypervisor_mutex, 415 |
| sc_hypervisor_get_avg_speed, 407 | sc_hypervisor_add_workers_to_sched_ctx, 412 |
| sc_hypervisor_get_config, 408 | sc_hypervisor_can_resize, 413 |
| | sc_hypervisor_free_size_req, 413 |
| sc_hypervisor_get_ctx_speed, 406 | |
| sc_hypervisor_get_elapsed_flops_per_sched_ctx, 404 | sc_hypervisor_get_ctxs_on_level, 414 |
| | sc_hypervisor_get_leaves, 414 |
| sc_hypervisor_get_fastest_ctx_exec_time, 406 | sc_hypervisor_get_nhierarchy_levels, 414 |
| sc_hypervisor_get_idlest_workers, 405 | sc_hypervisor_get_nready_flops_of_all_sons_of← |
| sc_hypervisor_get_idlest_workers_in_list, 405 | _sched_ctx, 414 |
| sc_hypervisor_get_index_for_arch, 407 | sc_hypervisor_get_policy, 412 |
| sc_hypervisor_get_movable_nworkers, 406 | sc_hypervisor_get_size_req, 413 |
| sc_hypervisor_get_nsched_ctxs, 404 | sc_hypervisor_init, 411 |
| sc_hypervisor_get_nworkers_ctx, 408 | sc_hypervisor_move_workers, 413 |
| sc_hypervisor_get_ref_speed_per_worker_type, | sc_hypervisor_post_resize_request, 412 |
| 407 | sc_hypervisor_register_ctx, 412 |
| sc_hypervisor_get_resize_criteria, 408 | sc_hypervisor_remove_workers_from_sched_ctx, |
| sc_hypervisor_get_sched_ctxs, 404 | 413 |
| sc_hypervisor_get_slowest_ctx_exec_time, 406 | sc_hypervisor_resize_ctxs, 412 |
| sc_hypervisor_get_speed, 409 | sc_hypervisor_save_size_req, 413 |
| sc_hypervisor_get_speed_per_worker, 406 | sc_hypervisor_set_type_of_task, 414 |
| sc_hypervisor_get_speed_per_worker_type, 406 | sc_hypervisor_shutdown, 411 |
| sc_hypervisor_get_tasks_times, 405 | sc_hypervisor_size_ctxs, 413 |
| sc_hypervisor_get_total_elapsed_flops_per_← | sc_hypervisor_start_resize, 412 |
| sched_ctx, 408 | sc_hypervisor_stop_resize, 412 |
| sc_hypervisor_get_types_of_workers, 408 | sc_hypervisor_unregister_ctx, 412 |
| sc_hypervisor_get_wrapper, 404 | sc_hypervisor_update_diff_elapsed_flops, 414 |
| sc_hypervisor_group_workers_by_type, 407 | sc_hypervisor_update_diff_total_flops, 414 |
| sc_hypervisor_policy_add_task_to_pool, 405 | sc_hypervisor_update_resize_interval, 414 |
| sc_hypervisor_policy_clone_task_pool, 405 | Scheduling Contexts, 383 |
| sc_hypervisor_policy_remove_task_from_pool, | STARPU_DEFAULT_PRIO, 386 |
| 405 | STARPU MAX PRIO, 386 |
| sc_hypervisor_policy_resize, 406 | STARPU_MIN_PRIO, 385 |
| sc_hypervisor_policy_resize_to_unknown_← | STARPU_SCHED_CTX_AWAKE_WORKERS, |
| receiver, 406 | 385 |
| sc_hypervisor_set_config, 408 | STARPU SCHED CTX CUDA NSMS, 385 |
| sc_hypervisor_set_coming, 400 sc hypervisorsc hypervisor get speed per ← | STARPU SCHED CTX POLICY INIT, 385 |
| worker_type, 409 | STARPU_SCHED_CTX_POLICY_MAX_PRIO, |
| Scheduling Context Hypervisor - Linear Programming, | 385 |
| 415 | STARPU SCHED CTX POLICY MIN PRIO, 385 |
| | |
| sc_hypervisor_lp_distribute_floating_no_resources | STARPU_SCHED_CTX_POLICY_STRUCT, 385 |
| _in_ctxs, 416 | |
| sc_hypervisor_lp_distribute_resources_in_ctxs, | STARPU_SCHED_CTX_SUB_CTXS, 385 |
| 416 | STARPU_SCHED_CTX_USER_DATA, 385 |
| sc_hypervisor_lp_execute_dichotomy, 417 | starpu_sched_ctx_add_workers, 387 |
| sc_hypervisor_lp_find_tmax, 417 | starpu_sched_ctx_contains_worker, 388 |
| sc_hypervisor_lp_get_nworkers_per_ctx, 415 | starpu_sched_ctx_create, 386 |
| sc_hypervisor_lp_get_tmax, 416 | starpu_sched_ctx_create_inside_interval, 386 |
| sc_hypervisor_lp_place_resources_in_ctx, 416 | starpu_sched_ctx_create_worker_collection, 390 |
| sc_hypervisor_lp_redistribute_resources_in_ctxs, | starpu_sched_ctx_delete, 387 |
| 416 | starpu_sched_ctx_delete_worker_collection, 390 |
| sc_hypervisor_lp_round_double_to_int, 416 | starpu_sched_ctx_display_workers, 387 |
| sc_hypervisor_lp_share_remaining_resources, | starpu_sched_ctx_exec_parallel_code, 389 |

| | starpu_sched_ctx_finished_submit, 388 | starpu_wake_worker_relax_light, 398 |
|-----|--|--|
| | starpu_sched_ctx_get_context, 387 | starpu_worker_can_execute_task, 395 |
| | starpu_sched_ctx_get_max_priority, 389 | starpu_worker_can_execute_task_first_impl, 395 |
| | starpu_sched_ctx_get_min_priority, 389 | starpu_worker_can_execute_task_impl, 395 |
| | starpu_sched_ctx_get_nshared_workers, 388 | starpu_worker_get_relative_speedup, 397 |
| | starpu_sched_ctx_get_nworkers, 388 | starpu_worker_get_sched_condition, 394 |
| | starpu_sched_ctx_get_policy_data, 389 | sequential_consistency |
| | starpu_sched_ctx_get_user_data, 389 | starpu_task, 284 |
| | starpu_sched_ctx_get_worker_collection, 390 | single_combined_worker |
| | starpu_sched_ctx_get_workers_list, 388 | starpu_conf, 185 |
| | starpu_sched_ctx_get_workers_list_raw, 388 | size_base |
| | starpu_sched_ctx_master_get_context, 389 | starpu_perfmodel, 311 |
| | starpu_sched_ctx_overlapping_ctxs_on_worker, | starpu_perfmodel_per_arch, 309 |
| | 388 | size_ctxs |
| | starpu_sched_ctx_register_close_callback, 386 | sc_hypervisor_policy, 401, 410 |
| | starpu_sched_ctx_remove_workers, 387 | specific_nodes |
| | starpu_sched_ctx_set_context, 387 | starpu_codelet, 279 |
| | starpu_sched_ctx_set_inheritor, 387 | Standard Memory Library, 189 |
| | starpu_sched_ctx_set_max_priority, 390 | STARPU_MALLOC_COUNT, 189 |
| | starpu_sched_ctx_set_min_priority, 389 | STARPU_MALLOC_NORECLAIM, 189 |
| | starpu_sched_ctx_set_policy_data, 389 | STARPU_MALLOC_PINNED, 189 |
| | starpu_sched_ctx_stop_task_submission, 387 | STARPU_MALLOC_SIMULATION_FOLDED, 190 |
| | starpu_sched_ctx_worker_get_id, 388 | STARPU_MEMORY_OVERFLOW, 190 |
| | starpu sched ctx worker is master for child ← | STARPU_MEMORY_WAIT, 190 |
| | ctx, 389 | starpu_data_free_pinned_if_possible, 190 |
| Sch | eduling Policy, 390 | starpu_data_malloc_pinned_if_possible, 190 |
| | STARPU_MAXIMPLEMENTATIONS, 394 | starpu_free, 191 |
| | STARPU_NMAX_SCHED_CTXS, 394 | starpu_free_flags, 191 |
| | starpu_data_expected_transfer_time, 397 | starpu_malloc, 190 |
| | starpu_get_prefetch_flag, 395 | starpu_malloc_flags, 191 |
| | starpu_idle_prefetch_task_input_for, 396 | starpu_malloc_set_align, 190 |
| | starpu_idle_prefetch_task_input_for_prio, 396 | starpu_malloc_set_hooks, 191 |
| | starpu_idle_prefetch_task_input_on_node, 396 | starpu_memory_allocate, 192 |
| | starpu_idle_prefetch_task_input_on_node_prio, | starpu_memory_deallocate, 192 |
| | 396 | starpu_memory_get_available, 192 |
| | starpu_prefetch_task_input_for, 396 | starpu_memory_get_available_all_nodes, 192 |
| | starpu_prefetch_task_input_for_prio, 396 | starpu_memory_get_total, 192 |
| | starpu_prefetch_task_input_on_node, 396 | starpu_memory_get_total_all_nodes, 192 |
| | starpu_prefetch_task_input_on_node_prio, 396 | starpu_memory_pin, 191 |
| | starpu_push_local_task, 395 | starpu_memory_unpin, 191 |
| | starpu_push_task_end, 395 | starpu_memory_wait_available, 192 |
| | starpu_sched_ctx_worker_shares_tasks_lists, 398 | starpu.h, 449 |
| | starpu_sched_get_max_priority, 394 | starpu_arbiter_create |
| | starpu_sched_get_min_priority, 394 | Data Management, 223 |
| | starpu_sched_get_predefined_policies, 394 | starpu_arbiter_destroy |
| | starpu_sched_set_max_priority, 395 | Data Management, 223 |
| | starpu_sched_set_min_priority, 394 | starpu_arbiter_t |
| | starpu_task_data_footprint, 397 | Data Management, 218 |
| | starpu_task_expected_conversion_time, 398 | starpu_asynchronous_copy_disabled |
| | starpu_task_expected_data_transfer_time, 397 | Initialization and Termination, 188 |
| | starpu_task_expected_data_transfer_time_for, 397 | starpu_asynchronous_cuda_copy_disabled |
| | starpu_task_expected_energy, 397 | Initialization and Termination, 188 |
| | starpu_task_expected_length, 397 | starpu_asynchronous_mic_copy_disabled |
| | starpu_task_footprint, 397 | Initialization and Termination, 188 |
| | starpu_task_notify_ready_soon_register, 398 | starpu_asynchronous_mpi_ms_copy_disabled |
| | starpu_wake_worker_locked, 398 | Initialization and Termination, 188 |
| | starpu_wake_worker_no_relax, 398 | starpu_asynchronous_opencl_copy_disabled |
| | starpu_wake_worker_relax, 398 | Initialization and Termination, 188 |
| | | |

| starpu_bcsr_data_register | starpu_block_filter_block |
|--|--|
| Data Interfaces, 257 | Data Partition, 269 |
| starpu_bcsr_filter_canonical_block | starpu_block_filter_block_shadow |
| Data Partition, 267 | Data Partition, 269 |
| starpu_bcsr_filter_canonical_block_child_ops | starpu_block_filter_depth_block |
| Data Partition, 267 | Data Partition, 270 |
| starpu_bcsr_get_c | starpu_block_filter_depth_block_shadow |
| Data Interfaces, 259 | Data Partition, 270 |
| starpu_bcsr_get_elemsize | starpu_block_filter_vertical_block |
| Data Interfaces, 259 | Data Partition, 269 |
| starpu_bcsr_get_firstentry | starpu_block_filter_vertical_block_shadow |
| Data Interfaces, 258 | Data Partition, 269 |
| starpu_bcsr_get_local_colind | starpu_block_get_elemsize |
| Data Interfaces, 258 | Data Interfaces, 254 |
| starpu_bcsr_get_local_nzval | starpu_block_get_local_ldy |
| Data Interfaces, 258 | Data Interfaces, 254 |
| starpu_bcsr_get_local_rowptr | starpu_block_get_local_ldz |
| Data Interfaces, 259 | Data Interfaces, 254 |
| starpu_bcsr_get_nnz | starpu_block_get_local_ptr |
| Data Interfaces, 258 | Data Interfaces, 254 |
| starpu_bcsr_get_nrow | starpu_block_get_nx |
| Data Interfaces, 258 | Data Interfaces, 253 |
| starpu_bcsr_get_r | starpu_block_get_ny |
| Data Interfaces, 259 | Data Interfaces, 254 |
| starpu_bcsr_interface, 239 | starpu_block_get_nz |
| starpu_bind_thread_on | Data Interfaces, 254 |
| Initialization and Termination, 188 | starpu_block_interface, 238 |
| starpu_bitmap.h, 450 | starpu_block_ptr_register |
| starpu_bitmap_and_get | Data Interfaces, 253 |
| Bitmap, 206 | starpu_bound.h, 450 |
| starpu_bitmap_cardinal | starpu_bound_compute |
| Bitmap, 206 | Theoretical Lower Bound on Execution Time, 320 |
| starpu_bitmap_create | starpu_bound_print |
| Bitmap, 205 | Theoretical Lower Bound on Execution Time, 320 |
| starpu_bitmap_destroy | starpu_bound_print_dot |
| Bitmap, 205 | Theoretical Lower Bound on Execution Time, 319 |
| starpu_bitmap_first | starpu_bound_print_lp |
| Bitmap, 207 | Theoretical Lower Bound on Execution Time, 320 |
| starpu_bitmap_get | starpu_bound_print_mps |
| Bitmap, 206 | Theoretical Lower Bound on Execution Time, 320 |
| starpu_bitmap_has_next | starpu_bound_start |
| Bitmap, 207 | Theoretical Lower Bound on Execution Time, 319 |
| starpu_bitmap_last | starpu_bound_stop |
| Bitmap, 207 | Theoretical Lower Bound on Execution Time, 319 |
| starpu_bitmap_next | starpu_bus_get_count |
| Bitmap, 207 | Profiling, 318 |
| starpu_bitmap_or | starpu_bus_get_dst |
| Bitmap, 206 | Profiling, 318 |
| starpu_bitmap_set | starpu_bus_get_id |
| Bitmap, 206 | Profiling, 318 |
| starpu_bitmap_unset | starpu_bus_get_profiling_info |
| Bitmap, 206 | Profiling, 318 |
| • | |
| starpu_bitmap_unset_all | starpu_bus_get_src Profiling, 318 |
| Bitmap, 206 | |
| starpu_bitmap_unset_and | starpu_bus_print_affinity |
| Bitmap, 206 | Performance Model, 314 |
| starpu_block_data_register | starpu_bus_print_bandwidth |
| Data Interfaces, 253 | Performance Model, 314 |

| starpu_bus_print_filenames Performance Model, 314 | starpu_combined_worker_get_description Parallel Tasks, 380 |
|--|--|
| starpu_cluster_types | starpu combined worker get id |
| Clustering Machine, 434 | Parallel Tasks, 380 |
| starpu_clusters.h, 451 | starpu combined worker get rank |
| starpu_codelet, 276 | Parallel Tasks, 380 |
| can_execute, 277 | starpu_combined_worker_get_size |
| color, 280 | Parallel Tasks, 380 |
| cpu_func, 277 | starpu_conf, 182 |
| cpu_funcs, 278 | bus_calibrate, 185 |
| cpu_funcs_name, 279 | calibrate, 185 |
| cuda_flags, 278 | catch_signals, 186 |
| cuda_func, 277 | cuda_opengl_interoperability, 186 |
| cuda_funcs, 278 | disable_asynchronous_copy, 185 |
| dyn_modes, 279 | disable_asynchronous_cuda_copy, 185 |
| dyn_nodes, 279 | disable_asynchronous_mic_copy, 185 |
| energy_model, 280 | disable_asynchronous_mpi_ms_copy, 186 |
| flags, 280 | disable_asynchronous_opencl_copy, 185 |
| max_parallelism, 277 | magic, 183 |
| mic_funcs, 278 | mic_sink_program_path, 185 |
| model, 279 | n_cuda_opengl_interoperability, 186 |
| modes, 279 | n_not_launched_drivers, 186 |
| mpi_ms_funcs, 278 | ncpus, 183 |
| name, 280 | ncuda, 183 |
| nbuffers, 279 | nmic, 184 |
| nodes, 279 | nmpi_ms, 184 |
| opencl_flags, 278 | nopencl, 183 |
| opencl_func, 278 | not_launched_drivers, 186 |
| opencl_funcs, 278 | reserve_ncpus, 183 |
| per_worker_stats, 280 | sched_policy, 183 |
| specific_nodes, 279 | sched_policy_name, 183 |
| type, 277 | single_combined_worker, 185 |
| where, 277 | trace_buffer_size, 186 |
| starpu_codelet_display_stats | use_explicit_workers_bindid, 184 |
| Codelet And Tasks, 295 | use_explicit_workers_cuda_gpuid, 184 |
| starpu_codelet_init | use_explicit_workers_mic_deviceid, 184 |
| Codelet And Tasks, 295 | use_explicit_workers_mpi_ms_deviceid, 184 |
| starpu_codelet_pack_arg | use_explicit_workers_opencl_gpuid, 184 |
| Task Insert Utility, 302 | workers_bindid, 184 |
| starpu_codelet_pack_arg_data, 297 | workers_cuda_gpuid, 184 |
| starpu_codelet_pack_arg_fini | workers_mic_deviceid, 184 |
| Task Insert Utility, 302 | workers_mpi_ms_deviceid, 185 |
| starpu_codelet_pack_arg_init | workers_opencl_gpuid, 184 |
| Task Insert Utility, 302 | starpu_conf_init |
| starpu_codelet_pack_args | Initialization and Termination, 186 |
| Task Insert Utility, 301 | starpu_config.h, 451 |
| starpu_codelet_type | starpu_coo_data_register |
| Codelet And Tasks, 292 | Data Interfaces, 253 |
| starpu_codelet_unpack_args | starpu_coo_interface, 237 |
| Task Insert Utility, 302 | starpu_cpu_func_t |
| starpu_codelet_unpack_args_and_copyleft Task Insert Utility, 302 | Codelet And Tasks, 291 |
| | starpu_cpu_worker_get_count |
| starpu_combined_worker_assign_workerid Parallel Tasks, 380 | Workers' Properties, 212 |
| | starpu_create_sync_task Codelet And Tasks, 296 |
| starpu_combined_worker_can_execute_task Parallel Tasks, 380 | starpu_csr_data_register |
| starpu_combined_worker_get_count | Data Interfaces, 256 |
| Parallel Tasks, 380 | starpu_csr_filter_vertical_block |
| i didiici 143N3, 000 | otal pa_001_111to1_v61 t10a1_0100ft |

| Data Partition, 267 | starpu_data_acquire_on_node_cb |
|---|--|
| starpu_csr_get_elemsize | Data Management, 221 |
| Data Interfaces, 257 | starpu_data_acquire_on_node_cb_sequential_ |
| starpu_csr_get_firstentry | consistency |
| Data Interfaces, 256 | Data Management, 222 |
| starpu_csr_get_local_colind | starpu_data_acquire_on_node_cb_sequential_ |
| Data Interfaces, 257 | consistency_sync_jobids |
| starpu_csr_get_local_nzval | Data Management, 222 |
| Data Interfaces, 257 | starpu_data_acquire_on_node_try |
| starpu_csr_get_local_rowptr | Data Management, 222 |
| Data Interfaces, 257 | starpu_data_acquire_try |
| starpu_csr_get_nnz | Data Management, 222 |
| Data Interfaces, 256 | starpu_data_advise_as_important |
| starpu csr get nrow | Data Management, 221 |
| Data Interfaces, 256 | starpu_data_assign_arbiter |
| starpu_csr_interface, 239 | Data Management, 223 |
| starpu_cublas.h, 454 | starpu_data_copy_methods, 230 |
| starpu_cublas_init | any_to_any, 234 |
| CUDA Extensions, 321 | |
| | can_copy, 231 |
| starpu_cublas_report_error | cuda_to_cuda, 232 |
| CUDA Extensions, 321 | cuda_to_cuda_async, 233 |
| starpu_cublas_set_stream | cuda_to_opencl, 232 |
| CUDA Extensions, 322 | cuda_to_ram, 232 |
| starpu_cublas_shutdown | cuda_to_ram_async, 233 |
| CUDA Extensions, 322 | mic_to_ram, 232 |
| starpu_cuda.h, 454 | mic_to_ram_async, 234 |
| starpu_cuda_copy_async_sync | mpi_ms_to_mpi_ms, 232 |
| CUDA Extensions, 322 | mpi_ms_to_mpi_ms_async, 234 |
| starpu_cuda_func_t | mpi_ms_to_ram, 232 |
| Codelet And Tasks, 291 | mpi_ms_to_ram_async, 234 |
| starpu_cuda_get_device_properties | opencl_to_cuda, 232 |
| CUDA Extensions, 322 | opencl_to_opencl, 232 |
| starpu_cuda_get_local_stream | opencl_to_opencl_async, 233 |
| CUDA Extensions, 321 | opencl_to_ram, 232 |
| starpu_cuda_report_error | opencl_to_ram_async, 233 |
| CUDA Extensions, 321 | ram_to_cuda, 231 |
| starpu_cuda_set_device | ram_to_cuda_async, 233 |
| CUDA Extensions, 322 | ram_to_mic, 231 |
| starpu_cuda_worker_get_count | ram_to_mic_async, 234 |
| Workers' Properties, 212 | ram to mpi ms, 232 |
| starpu_cusparse.h, 454 | ram_to_mpi_ms_async, 233 |
| starpu_cusparse_get_local_handle | ram to opencl, 231 |
| CUDA Extensions, 322 | ram_to_opencl_async, 233 |
| starpu_cusparse_init | ram_to_ram, 231 |
| CUDA Extensions, 321 | starpu_data_cpy |
| starpu_cusparse_shutdown | Miscellaneous Helpers, 356 |
| CUDA Extensions, 322 | starpu_data_descr, 280 |
| | starpu_data_display_memory_stats |
| starpu_data.h, 454 | |
| starpu_data_access_mode | Profiling, 319 |
| Data Management, 219 | starpu_data_expected_transfer_time |
| starpu_data_acquire | Scheduling Policy, 397 |
| Data Management, 221 | starpu_data_fetch_on_node |
| starpu_data_acquire_cb | Data Management, 223 |
| Data Management, 221 | starpu_data_filter, 262 |
| starpu_data_acquire_cb_sequential_consistency | filter_arg, 263 |
| Data Management, 221 | filter_arg_ptr, 263 |
| starpu_data_acquire_on_node | filter_func, 262 |
| Data Management, 221 | get_child_ops, 263 |

| get_nchildren, 262 | interface_size, 237 |
|---|---|
| nchildren, 262 | interfaceid, 237 |
| starpu_data_filters.h, 456 | name, 237 |
| starpu_data_free_pinned_if_possible | pack_data, 237 |
| Standard Memory Library, 190 | pointer_is_inside, 236 |
| starpu_data_get_alloc_size | register_data_handle, 235 |
| Data Interfaces, 249 | to_pointer, 236 |
| starpu_data_get_child | unpack_data, 237 |
| Data Partition, 263 | starpu_data_interfaces.h, 458 |
| starpu_data_get_default_sequential_consistency_flag | starpu_data_invalidate |
| Data Management, 225 | Data Management, 220 |
| starpu_data_get_interface_id | starpu data invalidate submit |
| Data Interfaces, 249 | Data Management, 220 |
| starpu_data_get_interface_on_node | starpu_data_is_on_node |
| Data Interfaces, 249 | Data Management, 224 |
| starpu_data_get_local_ptr | starpu_data_lookup |
| Data Interfaces, 249 | Data Interfaces, 249 |
| starpu_data_get_nb_children | starpu data malloc pinned if possible |
| Data Partition, 263 | Standard Memory Library, 190 |
| starpu_data_get_ooc_flag | starpu_data_map_filters |
| Data Management, 225 | Data Partition, 264 |
| starpu_data_get_rank | starpu_data_pack |
| MPI Support, 364 | Data Interfaces, 249 |
| starpu_data_get_sequential_consistency_flag | starpu_data_partition |
| Data Management, 224 | Data Partition, 263 |
| starpu_data_get_size | starpu_data_partition_clean |
| Data Interfaces, 249 | Data Partition, 266 |
| starpu_data_get_sub_data | starpu_data_partition_not_automatic |
| Data Partition, 264 | Data Partition, 266 |
| starpu_data_get_tag | starpu_data_partition_plan |
| MPI Support, 364 | Data Partition, 264 |
| starpu_data_get_user_data | starpu_data_partition_readonly_submit |
| Data Management, 226 | Data Partition, 265 |
| starpu_data_handle_t | starpu_data_partition_readwrite_upgrade_submit |
| Data Management, 218 | Data Partition, 265 |
| starpu_data_handle_to_pointer | starpu_data_partition_submit |
| Data Interfaces, 248 | Data Partition, 265 |
| starpu_data_idle_prefetch_on_node | starpu_data_partition_submit_sequential_consistency |
| Data Management, 224 | Data Partition, 266 |
| starpu_data_interface_get_next_id | starpu_data_pointer_is_inside |
| Data Interfaces, 250 | Data Interfaces, 248 |
| starpu_data_interface_id | starpu_data_prefetch_on_node |
| Data Interfaces, 247 | Data Management, 224 |
| starpu_data_interface_ops, 234 | starpu_data_ptr_register |
| alloc_compare, 236 | Data Interfaces, 248 |
| alloc_footprint, 236 | starpu_data_query_status |
| allocate_data_on_node, 235 | Data Management, 225 |
| compare, 236 | starpu_data_register |
| copy_methods, 235 | Data Interfaces, 248 |
| describe, 236 | starpu_data_register_same |
| display, 236 | Data Interfaces, 248 |
| dontcache, 237 | starpu_data_release |
| footprint, 236 | Data Management, 223 |
| free_data_on_node, 235 | starpu_data_release_on_node |
| get_alloc_size, 236 | Data Management, 223 |
| get_size, 236 | starpu_data_request_allocation |
| handle_to_pointer, 235 | Data Management, 223 |
| init, 235 | starpu_data_set_coordinates |

| Data Management, 220 | async_full_read, 272 |
|---|--|
| starpu_data_set_coordinates_array | async_full_write, 272 |
| Data Management, 220 | async_read, 272 |
| starpu_data_set_default_sequential_consistency_flag | async_write, 272 |
| Data Management, 225 | bandwidth, 271 |
| starpu_data_set_name | close, 272 |
| Data Management, 219 | copy, 272 |
| starpu_data_set_ooc_flag | free, 272 |
| Data Management, 225 | free_request, 273 |
| starpu_data_set_rank | full read, 272 |
| MPI Support, 363 | full write, 272 |
| starpu_data_set_reduction_methods | open, 272 |
| Data Management, 225 | · |
| | plug, 271 |
| starpu_data_set_sequential_consistency_flag | read, 272 |
| Data Management, 224 | test_request, 273 |
| starpu_data_set_tag | unplug, 271 |
| MPI Support, 363 | wait_request, 273 |
| starpu_data_set_user_data | write, 272 |
| Data Management, 225 | starpu_disk_register |
| starpu_data_set_wt_mask | Out Of Core, 273 |
| Data Management, 224 | starpu_disk_stdio_ops |
| starpu_data_unpack | Out Of Core, 274 |
| Data Interfaces, 249 | starpu_disk_swap_node |
| starpu_data_unpartition | Out Of Core, 274 |
| Data Partition, 263 | starpu_disk_unistd_o_direct_ops |
| starpu_data_unpartition_readonly_submit | Out Of Core, 274 |
| Data Partition, 265 | starpu_disk_unistd_ops |
| starpu_data_unpartition_submit | Out Of Core, 274 |
| Data Partition, 265 | starpu_driver, 381 |
| starpu_data_unpartition_submit_sequential_consistency | starpu_driver.h, 463 |
| Data Partition, 266 | starpu_driver.id, 381 |
| starpu_data_unpartition_submit_sequential_consistency | • |
| | |
| | |
| _cb | Running Drivers, 382 |
| _cb Data Partition, 266 | Running Drivers, 382 starpu_driver_init |
| _cb Data Partition, 266 starpu_data_unregister | Running Drivers, 382 starpu_driver_init Running Drivers, 382 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk_h, 462 starpu_disk_close | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_voget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk_close Out Of Core, 273 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 |
| cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 starpu_disk_leveldb_ops | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 starpu_free_flags |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_voget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 starpu_disk_leveldb_ops Out Of Core, 274 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 starpu_free_flags Standard Memory Library, 191 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk_h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 starpu_disk_leveldb_ops Out Of Core, 274 starpu_disk_open | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 starpu_free_flags Standard Memory Library, 191 starpu_free_on_node |
| cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk.h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 starpu_disk_leveldb_ops Out Of Core, 274 starpu_disk_open Out Of Core, 273 | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 starpu_free_flags Standard Memory Library, 191 starpu_free_on_node Data Interfaces, 251 |
| _cb Data Partition, 266 starpu_data_unregister Data Management, 220 starpu_data_unregister_no_coherency Data Management, 220 starpu_data_unregister_submit Data Management, 220 starpu_data_vget_sub_data Data Partition, 264 starpu_data_vmap_filters Data Partition, 264 starpu_data_wont_use Data Management, 224 starpu_deprecated_api.h, 462 starpu_disk_h, 462 starpu_disk_close Out Of Core, 273 starpu_disk_hdf5_ops Out Of Core, 274 starpu_disk_leveldb_ops Out Of Core, 274 starpu_disk_open | Running Drivers, 382 starpu_driver_init Running Drivers, 382 starpu_driver_run Running Drivers, 381 starpu_driver_run_once Running Drivers, 382 starpu_drivers_request_termination Running Drivers, 382 starpu_execute_on_each_worker Miscellaneous Helpers, 355 starpu_execute_on_each_worker_ex Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_execute_on_specific_workers Miscellaneous Helpers, 355 starpu_expert.h, 463 starpu_filter_nparts_compute_chunk_size_and_offset Data Partition, 270 starpu_free Standard Memory Library, 191 starpu_free_flags Standard Memory Library, 191 starpu_free_on_node |

| starpu_fxt.h, 463 | starpu_malloc_flags |
|--|--|
| starpu_fxt_autostart_profiling | Standard Memory Library, 191 |
| FxT Support, 357 | starpu_malloc_on_node |
| starpu_fxt_codelet_event, 356 | Data Interfaces, 251 |
| starpu_fxt_options, 357 | starpu_malloc_on_node_flags |
| starpu_fxt_start_profiling | Data Interfaces, 250 |
| FxT Support, 358 | starpu_malloc_on_node_set_default_flags |
| starpu_fxt_stop_profiling | Data Interfaces, 251 |
| FxT Support, 358 | starpu_malloc_set_align |
| starpu_fxt_trace_user_event | Standard Memory Library, 190 |
| FxT Support, 358 | starpu_malloc_set_hooks |
| starpu_fxt_trace_user_event_string | Standard Memory Library, 191 |
| FxT Support, 358 | starpu_matrix_data_register |
| starpu_get_env_number | Data Interfaces, 251 |
| Miscellaneous Helpers, 355 | starpu_matrix_data_register_allocsize |
| • | Data Interfaces, 252 |
| starpu_get_next_bindid | |
| Initialization and Termination, 187 | starpu_matrix_filter_block |
| starpu_get_prefetch_flag | Data Partition, 267 |
| Scheduling Policy, 395 | starpu_matrix_filter_block_shadow |
| starpu_get_version | Data Partition, 267 |
| Versioning, 181 | starpu_matrix_filter_vertical_block |
| starpu_hash.h, 464 | Data Partition, 267 |
| starpu_hash_crc32c_be | starpu_matrix_filter_vertical_block_shadow |
| Data Interfaces, 259 | Data Partition, 268 |
| starpu_hash_crc32c_be_n | starpu_matrix_get_allocsize |
| Data Interfaces, 259 | Data Interfaces, 252 |
| starpu_hash_crc32c_string | starpu_matrix_get_elemsize |
| Data Interfaces, 260 | Data Interfaces, 252 |
| starpu_idle_prefetch_task_input_for | starpu_matrix_get_local_ld |
| Scheduling Policy, 396 | Data Interfaces, 252 |
| starpu_idle_prefetch_task_input_for_prio | starpu_matrix_get_local_ptr |
| Scheduling Policy, 396 | Data Interfaces, 252 |
| starpu_idle_prefetch_task_input_on_node | starpu_matrix_get_nx |
| Scheduling Policy, 396 | Data Interfaces, 252 |
| starpu_idle_prefetch_task_input_on_node_prio | starpu_matrix_get_ny |
| Scheduling Policy, 396 | Data Interfaces, 252 |
| starpu_init | starpu_matrix_interface, 237 |
| Initialization and Termination, 187 | starpu_matrix_ptr_register |
| starpu_initialize | Data Interfaces, 252 |
| Initialization and Termination, 187 | starpu memory allocate |
| starpu insert task | Standard Memory Library, 192 |
| Task Insert Utility, 300 | starpu_memory_deallocate |
| starpu interface copy | Standard Memory Library, 192 |
| Data Interfaces, 250 | starpu_memory_get_available |
| starpu_interface_data_copy | Standard Memory Library, 192 |
| Data Interfaces, 250 | starpu_memory_get_available_all_nodes |
| starpu_interface_end_driver_copy_async | Standard Memory Library, 192 |
| Data Interfaces, 250 | starpu_memory_get_total |
| starpu_interface_start_driver_copy_async | Standard Memory Library, 192 |
| Data Interfaces, 250 | |
| | starpu_memory_get_total_all_nodes |
| starpu_is_initialized | Standard Memory Library, 192 |
| Initialization and Termination, 187 | starpu_memory_nodes_numa_devid_to_id |
| starpu_iteration_pop | Workers' Properties, 214 |
| Codelet And Tasks, 295 | starpu_memory_nodes_numa_id_to_devid |
| starpu_iteration_push | Workers' Properties, 214 |
| Codelet And Tasks, 295 | starpu_memory_pin |
| starpu_malloc | Standard Memory Library, 191 |
| Standard Memory Library, 190 | starpu_memory_unpin |

| Standard Memory Library, 191 | starpu_mpi_datatype_register |
|----------------------------------|--|
| starpu_memory_wait_available | MPI Support, 370 |
| Standard Memory Library, 192 | starpu_mpi_datatype_unregister |
| starpu_mic.h, 464 | MPI Support, 371 |
| starpu_mic_device_get_count | starpu_mpi_gather_detached |
| Workers' Properties, 212 | MPI Support, 375 |
| starpu_mic_func_symbol_t | starpu_mpi_get_data_on_all_nodes_detached |
| MIC Extensions, 353 | MPI Support, 374 |
| starpu_mic_func_t | starpu_mpi_get_data_on_node |
| Codelet And Tasks, 291 | MPI Support, 373 |
| starpu mic get kernel | starpu_mpi_get_data_on_node_detached |
| MIC Extensions, 354 | MPI Support, 373 |
| starpu_mic_kernel_t | starpu_mpi_init |
| Codelet And Tasks, 291 | MPI Support, 364 |
| starpu_mic_register_kernel | starpu_mpi_init_comm |
| MIC Extensions, 353 | MPI Support, 364 |
| starpu_mic_worker_get_count | starpu_mpi_init_conf |
| Workers' Properties, 212 | MPI Support, 364 |
| starpu_mod.f90, 464 | starpu mpi initialize |
| starpu_mpi.h, 465 | MPI Support, 365 |
| starpu_mpi_barrier | starpu_mpi_initialize_extended |
| MPI Support, 369 | MPI Support, 365 |
| starpu_mpi_cache_flush | starpu_mpi_insert_task |
| MPI Support, 371 | MPI Support, 373 |
| starpu_mpi_cache_flush_all_data | starpu_mpi_irecv |
| MPI Support, 371 | MPI Support, 366 |
| starpu_mpi_cache_is_enabled | starpu_mpi_irecv_array_detached_unlock_tag |
| MPI Support, 371 | MPI Support, 370 |
| starpu_mpi_cache_set | starpu_mpi_irecv_detached |
| MPI Support, 371 | MPI Support, 367 |
| starpu_mpi_cached_receive | starpu_mpi_irecv_detached_sequential_consistency |
| MPI Support, 371 | MPI Support, 368 |
| starpu_mpi_cached_send | starpu_mpi_irecv_detached_unlock_tag |
| MPI Support, 371 | MPI Support, 370 |
| starpu_mpi_comm_amounts_retrieve | starpu mpi isend |
| MPI Support, 365 | MPI Support, 366 |
| starpu_mpi_comm_get_attr | starpu_mpi_isend_array_detached_unlock_tag |
| MPI Support, 366 | MPI Support, 370 |
| starpu_mpi_comm_rank | starpu_mpi_isend_array_detached_unlock_tag_prio |
| MPI Support, 365 | MPI Support, 370 |
| starpu_mpi_comm_size | starpu_mpi_isend_detached |
| MPI Support, 365 | MPI Support, 367 |
| starpu_mpi_data_get_rank | starpu_mpi_isend_detached_prio |
| MPI Support, 372 | MPI Support, 367 |
| starpu_mpi_data_get_tag | starpu_mpi_isend_detached_unlock_tag |
| MPI Support, 372 | MPI Support, 369 |
| starpu_mpi_data_migrate | starpu_mpi_isend_detached_unlock_tag_prio |
| MPI Support, 374 | MPI Support, 369 |
| starpu_mpi_data_register | starpu_mpi_isend_prio |
| MPI Support, 363 | MPI Support, 366 |
| starpu_mpi_data_register_comm | starpu_mpi_issend |
| MPI Support, 371 | MPI Support, 368 |
| starpu_mpi_data_set_rank | starpu_mpi_issend_detached |
| MPI Support, 363 | MPI Support, 368 |
| starpu_mpi_data_set_rank_comm | starpu_mpi_issend_detached_prio |
| MPI Support, 372 | MPI Support, 369 |
| starpu_mpi_data_set_tag | starpu_mpi_issend_prio |
| MPI Support, 372 | MPI Support, 368 |

| starpu_mpi_lb.h, 467 | OpenMP Runtime Support, 352 |
|--|------------------------------------|
| starpu_mpi_ms_func_t | starpu_omp_barrier |
| Codelet And Tasks, 292 | OpenMP Runtime Support, 336 |
| starpu_mpi_ms_kernel_t | starpu_omp_critical |
| Codelet And Tasks, 291 | OpenMP Runtime Support, 336 |
| starpu_mpi_ms_worker_get_count | starpu_omp_critical_inline_begin |
| Workers' Properties, 212 | OpenMP Runtime Support, 336 |
| starpu_mpi_node_selection_get_current_policy | starpu_omp_critical_inline_end |
| MPI Support, 374 | OpenMP Runtime Support, 336 |
| starpu_mpi_node_selection_register_policy | starpu_omp_destroy_lock |
| MPI Support, 374 | OpenMP Runtime Support, 349 |
| starpu_mpi_node_selection_set_current_policy | starpu omp destroy nest lock |
| MPI Support, 374 | OpenMP Runtime Support, 350 |
| starpu_mpi_node_selection_unregister_policy | starpu_omp_for |
| MPI Support, 374 | OpenMP Runtime Support, 338 |
| starpu_mpi_recv | starpu_omp_for_alt |
| MPI Support, 367 | OpenMP Runtime Support, 339 |
| • • | |
| starpu_mpi_redux_data | starpu_omp_for_inline_first |
| MPI Support, 375 | OpenMP Runtime Support, 338 |
| starpu_mpi_redux_data_prio | starpu_omp_for_inline_first_alt |
| MPI Support, 375 | OpenMP Runtime Support, 339 |
| starpu_mpi_req | starpu_omp_for_inline_next |
| MPI Support, 364 | OpenMP Runtime Support, 339 |
| starpu_mpi_scatter_detached | starpu_omp_for_inline_next_alt |
| MPI Support, 375 | OpenMP Runtime Support, 340 |
| starpu_mpi_send | starpu_omp_get_active_level |
| MPI Support, 366 | OpenMP Runtime Support, 347 |
| starpu_mpi_send_prio | starpu_omp_get_ancestor_thread_num |
| MPI Support, 367 | OpenMP Runtime Support, 346 |
| starpu_mpi_shutdown | starpu_omp_get_cancellation |
| MPI Support, 365 | OpenMP Runtime Support, 345 |
| starpu_mpi_tag_t | starpu_omp_get_default_device |
| MPI Support, 364 | OpenMP Runtime Support, 348 |
| starpu_mpi_task_build | starpu_omp_get_dynamic |
| MPI Support, 373 | OpenMP Runtime Support, 344 |
| starpu_mpi_task_insert | starpu_omp_get_level |
| MPI Support, 372 | OpenMP Runtime Support, 346 |
| starpu_mpi_task_post_build | starpu_omp_get_max_active_levels |
| MPI Support, 373 | OpenMP Runtime Support, 346 |
| starpu_mpi_test | starpu_omp_get_max_task_priority |
| MPI Support, 369 | OpenMP Runtime Support, 349 |
| starpu_mpi_wait | starpu_omp_get_max_threads |
| MPI Support, 369 | OpenMP Runtime Support, 343 |
| starpu_mpi_wait_for_all | starpu_omp_get_nested |
| MPI Support, 369 | OpenMP Runtime Support, 344 |
| • • | starpu_omp_get_num_devices |
| starpu_mpi_world_rank | · - · |
| MPI Support, 365 | OpenMP Runtime Support, 348 |
| starpu_mpi_world_size | starpu_omp_get_num_procs |
| MPI Support, 366 | OpenMP Runtime Support, 343 |
| starpu_multiformat_data_interface_ops, 239 | starpu_omp_get_num_teams |
| starpu_multiformat_data_register | OpenMP Runtime Support, 348 |
| Data Interfaces, 259 | starpu_omp_get_num_threads |
| starpu_multiformat_interface, 240 | OpenMP Runtime Support, 342 |
| starpu_node_get_kind | starpu_omp_get_proc_bind |
| Workers' Properties, 214 | OpenMP Runtime Support, 347 |
| starpu_omp_atomic_fallback_inline_begin | starpu_omp_get_schedule |
| OpenMP Runtime Support, 352 | OpenMP Runtime Support, 345 |
| starpu omp atomic fallback inline end | starpu omp get team num |

| OpenMP Runtime Support, 348 | starpu_omp_set_num_threads |
|--|--|
| starpu_omp_get_team_size | OpenMP Runtime Support, 342 |
| OpenMP Runtime Support, 347 | starpu_omp_set_schedule |
| starpu_omp_get_thread_limit | OpenMP Runtime Support, 345 |
| OpenMP Runtime Support, 345 | starpu_omp_shutdown |
| starpu_omp_get_thread_num | OpenMP Runtime Support, 335 |
| OpenMP Runtime Support, 343 | starpu_omp_single |
| starpu_omp_get_wtick | OpenMP Runtime Support, 336 |
| OpenMP Runtime Support, 352 | starpu_omp_single_copyprivate |
| starpu_omp_get_wtime | OpenMP Runtime Support, 337 |
| OpenMP Runtime Support, 352 | starpu_omp_single_copyprivate_inline_begin |
| starpu_omp_in_final | OpenMP Runtime Support, 337 |
| OpenMP Runtime Support, 347 | starpu_omp_single_copyprivate_inline_end |
| starpu_omp_in_parallel | OpenMP Runtime Support, 337 |
| OpenMP Runtime Support, 343 | starpu_omp_single_inline |
| starpu_omp_init | OpenMP Runtime Support, 337 |
| OpenMP Runtime Support, 335 | starpu_omp_task_region |
| starpu_omp_init_lock | OpenMP Runtime Support, 341 |
| OpenMP Runtime Support, 349 | starpu_omp_task_region_attr, 333 |
| starpu_omp_init_nest_lock | starpu_omp_taskgroup |
| OpenMP Runtime Support, 350 | OpenMP Runtime Support, 341 |
| starpu_omp_is_initial_device | starpu_omp_taskgroup_inline_begin |
| OpenMP Runtime Support, 349 | OpenMP Runtime Support, 342 |
| starpu_omp_lock_t, 332 | starpu_omp_taskgroup_inline_end |
| starpu_omp_master | OpenMP Runtime Support, 342 |
| OpenMP Runtime Support, 335 | starpu_omp_taskwait |
| starpu_omp_master_inline | OpenMP Runtime Support, 341 |
| OpenMP Runtime Support, 336 | starpu_omp_test_lock |
| starpu_omp_nest_lock_t, 332 | OpenMP Runtime Support, 350 |
| starpu_omp_ordered | starpu_omp_test_nest_lock |
| OpenMP Runtime Support, 340 | OpenMP Runtime Support, 351 |
| starpu_omp_ordered_inline_begin OpenMP Runtime Support, 340 | starpu_omp_unset_lock OpenMP Runtime Support, 350 |
| starpu omp ordered inline end | starpu_omp_unset_nest_lock |
| OpenMP Runtime Support, 340 | OpenMP Runtime Support, 351 |
| starpu_omp_parallel_region | starpu omp vector annotate |
| OpenMP Runtime Support, 335 | OpenMP Runtime Support, 352 |
| starpu omp parallel region attr, 333 | Openivii Tiuntime Support, 332 |
| Starpa only parallel region atti, 000 | • |
| starnu omn proc hind value | starpu_opencl.h, 467 |
| starpu_omp_proc_bind_value OpenMP Buntime Support 335 | starpu_opencl.h, 467 starpu_opencl_allocate_memory |
| OpenMP Runtime Support, 335 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic | starpu_opencl.h, 467 starpu_opencl_allocate_memory |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock OpenMP Runtime Support, 349 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 328 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock OpenMP Runtime Support, 349 starpu_omp_set_max_active_levels | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 328 starpu_opencl_copy_ram_to_opencl |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock OpenMP Runtime Support, 349 starpu_omp_set_max_active_levels OpenMP Runtime Support, 346 | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 328 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 328 |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock OpenMP Runtime Support, 349 starpu_omp_set_max_active_levels OpenMP Runtime Support, 346 starpu_omp_set_nest_lock | starpu_opencl.h, 467 starpu_opencl_allocate_memory OpenCL Extensions, 328 starpu_opencl_collect_stats OpenCL Extensions, 327 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 326 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 326 starpu_opencl_copy_async_sync OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 329 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 328 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 328 starpu_opencl_display_error |
| OpenMP Runtime Support, 335 starpu_omp_sched_value OpenMP Runtime Support, 334 starpu_omp_sections OpenMP Runtime Support, 341 starpu_omp_sections_combined OpenMP Runtime Support, 341 starpu_omp_set_default_device OpenMP Runtime Support, 347 starpu_omp_set_dynamic OpenMP Runtime Support, 344 starpu_omp_set_lock OpenMP Runtime Support, 349 starpu_omp_set_max_active_levels OpenMP Runtime Support, 346 starpu_omp_set_nest_lock OpenMP Runtime Support, 351 | starpu_opencl.h, 467 starpu_opencl_allocate_memory |

| starpu_opencl_func_t | starpu_perfmodel_device, 308 |
|--|--|
| Codelet And Tasks, 291 | starpu_perfmodel_directory |
| starpu_opencl_get_context | Performance Model, 314 |
| OpenCL Extensions, 325 | starpu_perfmodel_dump_xml |
| starpu_opencl_get_current_context | Performance Model, 312 |
| OpenCL Extensions, 325 | starpu_perfmodel_free_sampling_directories |
| starpu_opencl_get_current_queue | Performance Model, 313 |
| OpenCL Extensions, 325 | starpu_perfmodel_get_arch_name |
| starpu_opencl_get_device | Performance Model, 313 |
| OpenCL Extensions, 325 | starpu_perfmodel_get_model_path |
| starpu_opencl_get_queue | Performance Model, 312 |
| OpenCL Extensions, 325 | starpu_perfmodel_history_based_expected_perf |
| starpu_opencl_load_binary_opencl | Performance Model, 313 |
| OpenCL Extensions, 326 | starpu_perfmodel_history_entry, 308 |
| starpu_opencl_load_kernel | starpu_perfmodel_history_list, 308 |
| OpenCL Extensions, 327 | starpu_perfmodel_init |
| starpu_opencl_load_opencl_from_file | Performance Model, 312 |
| OpenCL Extensions, 327 | |
| • | starpu_perfmodel_initialize |
| starpu_opencl_load_opencl_from_string | Performance Model, 313 |
| OpenCL Extensions, 327 | starpu_perfmodel_list |
| starpu_opencl_load_program_source | Performance Model, 313 |
| OpenCL Extensions, 326 | starpu_perfmodel_load_file |
| starpu_opencl_load_program_source_malloc | Performance Model, 312 |
| OpenCL Extensions, 326 | starpu_perfmodel_load_symbol |
| starpu_opencl_program, 324 | Performance Model, 312 |
| starpu_opencl_release_kernel | starpu_perfmodel_nop |
| OpenCL Extensions, 327 | Performance Model, 315 |
| starpu_opencl_report_error | starpu_perfmodel_per_arch, 309 |
| OpenCL Extensions, 328 | cost_function, 309 |
| starpu_opencl_set_kernel_args | history, 309 |
| OpenCL Extensions, 325 | list, 310 |
| starpu_opencl_unload_opencl | regression, 310 |
| OpenCL Extensions, 327 | size_base, 309 |
| starpu_opencl_worker_get_count | starpu_perfmodel_regression_model, 309 |
| Workers' Properties, 212 | starpu_perfmodel_type |
| starpu_openmp.h, 469 | Performance Model, 311 |
| starpu_parallel_task_barrier_init | starpu_perfmodel_unload_model |
| Parallel Tasks, 380 | Performance Model, 312 |
| starpu_parallel_task_barrier_init_n | starpu_perfmodel_update_history |
| Parallel Tasks, 381 | Performance Model, 314 |
| starpu pause | starpu_prefetch_task_input_for |
| Initialization and Termination, 187 | Scheduling Policy, 396 |
| starpu_perfmodel, 310 | starpu prefetch task input for prio |
| arch_cost_function, 311 | Scheduling Policy, 396 |
| combinations, 311 | starpu prefetch task input on node |
| cost_function, 311 | Scheduling Policy, 396 |
| footprint, 311 | starpu_prefetch_task_input_on_node_prio |
| is loaded, 311 | Scheduling Policy, 396 |
| ncombinations, 311 | starpu_private |
| nparameters, 311 | starpu_task, 287 |
| parameters_names, 311 | starpu_task, 207 starpu_profiling.h, 473 |
| size_base, 311 | starpu_profiling_bus_helper_display_summary |
| | |
| symbol, 311 | Profiling, 318 |
| type, 310 | starpu_profiling_bus_info, 317 |
| starpu_perfmodel.h, 471 | starpu_profiling_init |
| starpu_perfmodel_arch, 308 | Profiling, 317 |
| starpu_perfmodel_debugfilepath | starpu_profiling_set_id |
| Performance Model, 313 | Profiling, 317 |

| starpu_profiling_status_get | Threads, 201 |
|--|---|
| Profiling, 317 | starpu_pthread_mutex_unlock |
| starpu_profiling_status_set | Threads, 201 |
| Profiling, 317 | starpu_pthread_mutexattr_destroy |
| starpu_profiling_task_info, 316 | Threads, 202 |
| starpu_profiling_worker_get_info | starpu_pthread_mutexattr_gettype |
| Profiling, 318 | Threads, 201 |
| starpu_profiling_worker_helper_display_summary | starpu_pthread_mutexattr_init |
| Profiling, 319 | Threads, 202 |
| starpu_profiling_worker_info, 316 | starpu_pthread_mutexattr_settype |
| starpu_progression_hook_deregister | Threads, 201 |
| Expert Mode, 383 | starpu pthread queue t, 488 |
| starpu_progression_hook_register | starpu_pthread_rwlock_destroy |
| Expert Mode, 382 | Threads, 203 |
| starpu_pthread_attr_destroy | starpu_pthread_rwlock_init |
| Threads, 200 | Threads, 203 |
| starpu_pthread_attr_init | starpu_pthread_rwlock_rdlock |
| Threads, 200 | Threads, 203 |
| starpu_pthread_attr_setdetachstate | starpu_pthread_rwlock_tryrdlock |
| Threads, 200 | Threads, 203 |
| starpu_pthread_barrier_destroy | starpu_pthread_rwlock_trywrlock |
| Threads, 204 | Threads, 204 |
| starpu_pthread_barrier_init | starpu_pthread_rwlock_unlock |
| Threads, 204 | Threads, 204 |
| starpu_pthread_barrier_t, 488 | starpu_pthread_rwlock_wrlock |
| starpu_pthread_barrier_wait | Threads, 203 |
| Threads, 204 | starpu_pthread_setspecific |
| starpu_pthread_cond_broadcast | Threads, 202 |
| Threads, 202 | starpu_pthread_spin_destroy |
| starpu_pthread_cond_destroy | Threads, 204 |
| Threads, 203 | starpu_pthread_spin_init |
| starpu_pthread_cond_init | Threads, 204 |
| Threads, 202 | starpu_pthread_spin_lock |
| starpu_pthread_cond_signal | Threads, 204 |
| Threads, 202 | starpu_pthread_spin_trylock |
| starpu_pthread_cond_timedwait | Threads, 204 |
| Threads, 203 | starpu_pthread_spin_unlock |
| starpu_pthread_cond_wait | Threads, 205 |
| Threads, 203 | starpu_pthread_spinlock_t, 488 |
| starpu_pthread_create | starpu_pthread_wait_t, 488 |
| Threads, 200 | starpu_push_local_task Scheduling Policy, 395 |
| starpu_pthread_exit Threads, 200 | starpu_push_task_end |
| starpu_pthread_getspecific | Scheduling Policy, 395 |
| Threads, 202 | starpu rand.h, 474 |
| starpu_pthread_join | starpu_rand.n, 474 starpu_resume |
| Threads, 200 | Initialization and Termination, 187 |
| starpu_pthread_key_create | starpu_sched_component, 421 |
| Threads, 202 | add_child, 423 |
| starpu_pthread_key_delete | can_pull, 423 |
| Threads, 202 | can_push, 423 |
| starpu_pthread_mutex_destroy | children, 422 |
| Threads, 201 | data, 422 |
| starpu_pthread_mutex_init | deinit_data, 423 |
| Threads, 201 | estimated_end, 423 |
| starpu_pthread_mutex_lock | estimated_load, 423 |
| Threads, 201 | nchildren, 422 |
| starpu_pthread_mutex_trylock | notify_change_workers, 424 |
| | 3 _ / |

| 1 400 | M |
|--|---|
| nparents, 422 | Modularized Scheduler Interface, 431 |
| obj, 424 | starpu_sched_component_is_random |
| parents, 423 | Modularized Scheduler Interface, 432 |
| pull_task, 423 | starpu_sched_component_is_simple_worker |
| push_task, 423 | Modularized Scheduler Interface, 430 |
| remove_child, 423 | starpu_sched_component_is_work_stealing |
| tree, 422 | Modularized Scheduler Interface, 432 |
| workers, 422 | starpu_sched_component_is_worker |
| workers_in_ctx, 422 | Modularized Scheduler Interface, 430 |
| starpu sched component.h, 474 | starpu_sched_component_make_scheduler |
| starpu_sched_component_best_implementation_create | Modularized Scheduler Interface, 433 |
| Modularized Scheduler Interface, 432 | starpu sched component mct create |
| | . – – . – – |
| starpu_sched_component_can_execute_task | Modularized Scheduler Interface, 432 |
| Modularized Scheduler Interface, 429 | starpu_sched_component_mct_data, 424 |
| starpu_sched_component_can_pull | starpu_sched_component_parallel_worker_create |
| Modularized Scheduler Interface, 430 | Modularized Scheduler Interface, 429 |
| starpu_sched_component_can_pull_all | starpu_sched_component_perfmodel_select_data, 424 |
| Modularized Scheduler Interface, 431 | starpu_sched_component_prio_data, 424 |
| starpu_sched_component_can_push | starpu_sched_component_properties |
| Modularized Scheduler Interface, 430 | Modularized Scheduler Interface, 427 |
| starpu_sched_component_composed_component_ | starpu_sched_component_pull_task |
| create | Modularized Scheduler Interface, 428 |
| Modularized Scheduler Interface, 433 | starpu sched component push task |
| starpu sched component composed recipe add | Modularized Scheduler Interface, 428 |
| Modularized Scheduler Interface, 433 | starpu_sched_component_random_create |
| | |
| starpu_sched_component_composed_recipe_create | Modularized Scheduler Interface, 432 |
| Modularized Scheduler Interface, 432 | starpu_sched_component_specs, 425 |
| starpu_sched_component_composed_recipe_create ← | hwloc_cache_composed_sched_component, 425 |
| _singleton | hwloc_component_composed_sched_component, |
| Modularized Scheduler Interface, 432 | 425 |
| starpu_sched_component_composed_recipe_destroy | hwloc_machine_composed_sched_component, |
| Modularized Scheduler Interface, 433 | 425 |
| starpu_sched_component_connect | hwloc_socket_composed_sched_component, 425 |
| Modularized Scheduler Interface, 428 | mix_heterogeneous_workers, 425 |
| starpu sched component create | worker_composed_sched_component, 425 |
| Modularized Scheduler Interface, 428 | starpu_sched_component_transfer_length |
| starpu_sched_component_destroy | Modularized Scheduler Interface, 429 |
| Modularized Scheduler Interface, 429 | starpu_sched_component_work_stealing_create |
| starpu_sched_component_destroy_rec | Modularized Scheduler Interface, 431 |
| Modularized Scheduler Interface, 429 | starpu_sched_component_worker_get |
| | |
| starpu_sched_component_estimated_end_average | Modularized Scheduler Interface, 429 |
| Modularized Scheduler Interface, 431 | starpu_sched_component_worker_get_workerid |
| starpu_sched_component_estimated_end_min | Modularized Scheduler Interface, 430 |
| Modularized Scheduler Interface, 431 | starpu_sched_component_worker_post_exec_hook |
| starpu_sched_component_estimated_end_min_add | Modularized Scheduler Interface, 430 |
| Modularized Scheduler Interface, 431 | starpu_sched_component_worker_pre_exec_hook |
| starpu_sched_component_estimated_load | Modularized Scheduler Interface, 430 |
| Modularized Scheduler Interface, 431 | starpu_sched_ctx.h, 477 |
| starpu_sched_component_execute_preds | starpu_sched_ctx_add_workers |
| Modularized Scheduler Interface, 429 | Scheduling Contexts, 387 |
| starpu_sched_component_fifo_create | starpu_sched_ctx_call_pushed_task_cb |
| Modularized Scheduler Interface, 431 | starpu_sched_ctx_hypervisor.h, 479 |
| starpu_sched_component_fifo_data, 424 | starpu_sched_ctx_check_if_hypervisor_exists |
| | |
| starpu_sched_component_initialize_simple_scheduler | starpu_sched_ctx_hypervisor.h, 480 |
| Modularized Scheduler Interface, 433 | starpu_sched_ctx_contains_worker |
| starpu_sched_component_is_combined_worker | Scheduling Contexts, 388 |
| Modularized Scheduler Interface, 430 | |
| starpu_sched_component_is_fifo | starpu_sched_ctx_create Scheduling Contexts, 386 |

| starpu_sched_ctx_create_inside_interval | starpu_sched_ctx_set_perf_counters |
|--|---|
| Scheduling Contexts, 386 | starpu_sched_ctx_hypervisor.h, 479 |
| starpu_sched_ctx_create_worker_collection | starpu_sched_ctx_set_policy_data |
| Scheduling Contexts, 390 | Scheduling Contexts, 389 |
| starpu_sched_ctx_delete | starpu_sched_ctx_stop_task_submission |
| Scheduling Contexts, 387 | Scheduling Contexts, 387 |
| starpu_sched_ctx_delete_worker_collection | starpu_sched_ctx_worker_get_id |
| Scheduling Contexts, 390 | Scheduling Contexts, 388 |
| starpu_sched_ctx_display_workers | starpu_sched_ctx_worker_is_master_for_child_ctx |
| Scheduling Contexts, 387 | Scheduling Contexts, 389 |
| starpu_sched_ctx_exec_parallel_code | starpu_sched_ctx_worker_shares_tasks_lists |
| Scheduling Contexts, 389 | Scheduling Policy, 398 |
| starpu_sched_ctx_finished_submit | starpu_sched_get_max_priority |
| Scheduling Contexts, 388 | Scheduling Policy, 394 |
| starpu_sched_ctx_get_context | starpu_sched_get_min_priority |
| Scheduling Contexts, 387 | Scheduling Policy, 394 |
| starpu_sched_ctx_get_max_priority | starpu_sched_get_predefined_policies |
| Scheduling Contexts, 389 | Scheduling Policy, 394 |
| starpu_sched_ctx_get_min_priority | starpu_sched_policy, 392 |
| Scheduling Contexts, 389 | add_workers, 393 |
| starpu_sched_ctx_get_nshared_workers | deinit_sched, 392 |
| Scheduling Contexts, 388 | do_schedule, 393 |
| starpu_sched_ctx_get_nworkers | init_sched, 392 |
| Scheduling Contexts, 388 | policy_description, 394 |
| starpu_sched_ctx_get_policy_data | policy_name, 393 |
| Scheduling Contexts, 389 | pop_every_task, 393 |
| starpu_sched_ctx_get_user_data | pop_task, 393 |
| Scheduling Contexts, 389 | post_exec_hook, 393 |
| starpu_sched_ctx_get_worker_collection | pre_exec_hook, 393 |
| Scheduling Contexts, 390 | push_task, 392 |
| starpu_sched_ctx_get_workers_list | push_task_notify, 393 |
| Scheduling Contexts, 388 | remove_workers, 393 |
| starpu_sched_ctx_get_workers_list_raw | submit_hook, 393 |
| Scheduling Contexts, 388 | starpu_sched_set_max_priority |
| starpu_sched_ctx_hypervisor.h, 479 | Scheduling Policy, 395 |
| starpu_sched_ctx_call_pushed_task_cb, 479 | starpu_sched_set_min_priority |
| starpu_sched_ctx_check_if_hypervisor_exists, 480 | Scheduling Policy, 394 |
| starpu_sched_ctx_notify_hypervisor_exists, 479 | starpu_sched_tree, 424 |
| starpu_sched_ctx_set_perf_counters, 479 | starpu_sched_tree_add_workers |
| starpu_sched_ctx_iterator, 209 | Modularized Scheduler Interface, 428 |
| starpu_sched_ctx_master_get_context | starpu_sched_tree_create |
| Scheduling Contexts, 389 | Modularized Scheduler Interface, 427 |
| starpu_sched_ctx_notify_hypervisor_exists | starpu_sched_tree_destroy |
| starpu_sched_ctx_hypervisor.h, 479 | Modularized Scheduler Interface, 427 |
| starpu_sched_ctx_overlapping_ctxs_on_worker | starpu_sched_tree_pop_task |
| Scheduling Contexts, 388 | Modularized Scheduler Interface, 428 |
| starpu_sched_ctx_register_close_callback | starpu_sched_tree_push_task |
| Scheduling Contexts, 386 | Modularized Scheduler Interface, 428 |
| starpu_sched_ctx_remove_workers | starpu_sched_tree_remove_workers |
| Scheduling Contexts, 387 | Modularized Scheduler Interface, 428 |
| starpu_sched_ctx_set_context | starpu_sched_tree_update_workers |
| Scheduling Contexts, 387 | Modularized Scheduler Interface, 427 |
| starpu_sched_ctx_set_inheritor | starpu_sched_tree_update_workers_in_ctx |
| Scheduling Contexts, 387 | Modularized Scheduler Interface, 427 |
| starpu_sched_ctx_set_max_priority | starpu_sched_tree_work_stealing_push_task |
| Scheduling Contexts, 390 | Modularized Scheduler Interface, 432 |
| starpu_sched_ctx_set_min_priority | starpu_scheduler.h, 480 |
| Scheduling Contexts, 389 | starpu_shutdown |

| Initialization and Termination, 187 | prologue_callback_arg, 284 |
|-------------------------------------|---|
| starpu_simgrid_wrap.h, 481 | prologue_callback_arg_free, 284 |
| | prologue_caliback_arg_free, 264 prologue_caliback_func, 283 |
| starpu_sink.h, 481 | |
| starpu_sleep Threads, 205 | prologue_callback_pop_arg_free, 284 |
| • | regenerate, 285 |
| starpu_stdlib.h, 481 | sched_ctx, 286 |
| starpu_tag_declare_deps | sched_data, 287 |
| Explicit Dependencies, 305 | scheduled, 285 |
| starpu_tag_declare_deps_array | sequential_consistency, 284 |
| Explicit Dependencies, 305 | starpu_private, 287 |
| starpu_tag_notify_from_apps | status, 286 |
| Explicit Dependencies, 306 | synchronous, 284 |
| starpu_tag_remove | tag_id, 284 |
| Explicit Dependencies, 306 | type, 286 |
| starpu_tag_restart | use_tag, 284 |
| Explicit Dependencies, 306 | where, 282 |
| starpu_tag_t | workerid, 285 |
| Explicit Dependencies, 303 | workerids, 286 |
| starpu_tag_wait | workerids_len, 286 |
| Explicit Dependencies, 305 | workerorder, 285 |
| starpu_tag_wait_array | starpu_task.h, 482 |
| Explicit Dependencies, 305 | starpu_task_build |
| starpu_task, 280 | Task Insert Utility, 300 |
| bundle, 287 | starpu task bundle.h, 484 |
| callback_arg, 283 | starpu_task_bundle_close |
| callback_arg_free, 284 | Task Bundles, 377 |
| callback func, 283 | starpu_task_bundle_create |
| cl, 282 | Task Bundles, 376 |
| cl_arg, 283 | starpu_task_bundle_expected_data_transfer_time |
| cl_arg_free, 284 | Task Bundles, 377 |
| cl_arg_size, 283 | starpu_task_bundle_expected_energy |
| color, 286 | Task Bundles, 377 |
| destroy, 285 | starpu_task_bundle_expected_length |
| detach, 285 | Task Bundles, 377 |
| dyn handles, 282 | starpu_task_bundle_insert |
| dyn_interfaces, 282 | Task Bundles, 376 |
| dyn modes, 282 | starpu task bundle remove |
| execute on a specific worker, 285 | Task Bundles, 376 |
| flops, 287 | starpu_task_bundle_t |
| handles, 282 | Task Bundles, 376 |
| handles sequential consistency, 283 | starpu_task_clean |
| hypervisor tag, 286 | • – – |
| | Codelet And Tasks, 293 |
| interfaces, 282 | starpu_task_create |
| magic, 286 | Codelet And Tasks, 293 |
| mf_skip, 285 | starpu_task_data_footprint |
| modes, 282 | Scheduling Policy, 397 |
| name, 281 | starpu_task_declare_deps |
| nb_termination_call_required, 287 | Explicit Dependencies, 303 |
| nbuffers, 282 | starpu_task_declare_deps_array |
| next, 287 | Explicit Dependencies, 303 |
| no_submitorder, 285 | starpu_task_declare_end_deps |
| omp_task, 287 | Explicit Dependencies, 304 |
| possibly_parallel, 287 | starpu_task_declare_end_deps_array |
| predicted, 287 | Explicit Dependencies, 304 |
| predicted_transfer, 287 | starpu_task_destroy |
| prev, 287 | Codelet And Tasks, 293 |
| priority, 286 | starpu_task_dup |
| profiling_info, 287 | Codelet And Tasks, 296 |

| starpu_task_end_dep_add | starpu_task_list_ismember |
|--|---|
| | · — — — |
| Explicit Dependencies, 304 | Task Lists, 379 |
| starpu_task_end_dep_release | starpu_task_list_next |
| Explicit Dependencies, 305 | Task Lists, 379 |
| starpu_task_expected_conversion_time | starpu_task_list_pop_back |
| Scheduling Policy, 398 | Task Lists, 379 |
| starpu_task_expected_data_transfer_time | starpu_task_list_pop_front |
| Scheduling Policy, 397 | Task Lists, 379 |
| starpu_task_expected_data_transfer_time_for | starpu_task_list_push_back |
| Scheduling Policy, 397 | Task Lists, 378 |
| starpu_task_expected_energy | starpu task list push front |
| Scheduling Policy, 397 | Task Lists, 378 |
| starpu_task_expected_length | starpu_task_notify_ready_soon_register |
| Scheduling Policy, 397 | Scheduling Policy, 398 |
| starpu_task_footprint | starpu_task_nready |
| Scheduling Policy, 397 | Codelet And Tasks, 294 |
| starpu_task_get_current | starpu_task_nsubmitted |
| • | |
| Codelet And Tasks, 295 | Codelet And Tasks, 294 |
| starpu_task_get_current_data_node | starpu_task_set |
| Codelet And Tasks, 295 | Task Insert Utility, 300 |
| starpu_task_get_implementation | starpu_task_set_implementation |
| Codelet And Tasks, 296 | Codelet And Tasks, 296 |
| starpu_task_get_model_name | starpu_task_status |
| Codelet And Tasks, 295 | Codelet And Tasks, 292 |
| starpu_task_get_name | starpu_task_submit |
| Codelet And Tasks, 295 | Codelet And Tasks, 293 |
| starpu_task_get_task_scheduled_succs | starpu_task_submit_to_ctx |
| Explicit Dependencies, 304 | Codelet And Tasks, 293 |
| starpu_task_get_task_succs | starpu_task_util.h, 485 |
| Explicit Dependencies, 304 | starpu_task_wait |
| starpu_task_init | Codelet And Tasks, 293 |
| Codelet And Tasks, 292 | starpu_task_wait_array |
| | |
| starpu_task_insert | Codelet And Tasks, 294 |
| Task Insert Utility, 300 | starpu_task_wait_for_all |
| starpu_task_insert_data_make_room | Codelet And Tasks, 294 |
| Task Insert Utility, 301 | starpu_task_wait_for_all_in_ctx |
| starpu_task_insert_data_process_arg | Codelet And Tasks, 294 |
| Task Insert Utility, 301 | starpu_task_wait_for_n_submitted |
| starpu_task_insert_data_process_array_arg | Codelet And Tasks, 294 |
| Task Insert Utility, 301 | starpu_task_wait_for_n_submitted_in_ctx |
| starpu_task_insert_data_process_mode_array_arg | Codelet And Tasks, 294 |
| Task Insert Utility, 301 | starpu_task_wait_for_no_ready |
| starpu_task_list, 378 | Codelet And Tasks, 294 |
| starpu task list.h, 484 | starpu thread.h, 486 |
| starpu_task_list_back | starpu_thread_util.h, 489 |
| Task Lists, 378 | starpu_timing_now |
| starpu_task_list_begin | Miscellaneous Helpers, 355 |
| Task Lists, 379 | starpu_timing_timespec_delay_us |
| | |
| starpu_task_list_empty | Profiling, 318 |
| Task Lists, 378 | starpu_timing_timespec_to_us |
| starpu_task_list_end | Profiling, 318 |
| Task Lists, 379 | starpu_topology_print |
| starpu_task_list_erase | Initialization and Termination, 188 |
| Task Lists, 378 | starpu_transfer_bandwidth |
| starpu_task_list_front | Performance Model, 314 |
| Task Lists, 378 | starpu_transfer_latency |
| starpu_task_list_init | Performance Model, 314 |
| Task Lists, 378 | starpu_transfer_predict |

| Performance Model, 314 | Scheduling Policy, 395 |
|---|-------------------------------------|
| starpu_tree, 399 | starpu_worker_can_execute_task_impl |
| starpu_tree.h, 490 | Scheduling Policy, 395 |
| starpu_util.h, 490 | starpu_worker_collection, 209 |
| starpu_variable_data_register | add, 210 |
| Data Interfaces, 255 | deinit, 210 |
| starpu_variable_get_elemsize | get_next, 210 |
| Data Interfaces, 256 | has_next, 210 |
| starpu_variable_get_local_ptr | init, 210 |
| Data Interfaces, 256 | init_iterator, 210 |
| starpu_variable_interface, 238 | nworkers, 210 |
| starpu_variable_ptr_register | remove, 210 |
| Data Interfaces, 256 | |
| | type, 210 |
| starpu_vector_data_register | workerids, 210 |
| Data Interfaces, 254 | starpu_worker_collection_type |
| starpu_vector_data_register_allocsize | Workers' Properties, 211 |
| Data Interfaces, 254 | starpu_worker_display_names |
| starpu_vector_filter_block | Workers' Properties, 213 |
| Data Partition, 268 | starpu_worker_get_by_devid |
| starpu_vector_filter_block_shadow | Workers' Properties, 213 |
| Data Partition, 268 | starpu_worker_get_by_type |
| starpu_vector_filter_divide_in_2 | Workers' Properties, 213 |
| Data Partition, 269 | starpu_worker_get_count |
| starpu_vector_filter_list | Workers' Properties, 212 |
| Data Partition, 268 | starpu_worker_get_count_by_type |
| starpu_vector_filter_list_long | Workers' Properties, 213 |
| Data Partition, 268 | starpu_worker_get_devid |
| starpu_vector_get_allocsize | Workers' Properties, 214 |
| Data Interfaces, 255 | starpu_worker_get_hwloc_cpuset |
| starpu_vector_get_elemsize | Workers' Properties, 214 |
| Data Interfaces, 255 | starpu_worker_get_hwloc_obj |
| starpu_vector_get_local_ptr | Workers' Properties, 214 |
| | • |
| Data Interfaces, 255 | starpu_worker_get_id |
| starpu_vector_get_nx | Workers' Properties, 212 |
| Data Interfaces, 255 | starpu_worker_get_id_check |
| starpu_vector_interface, 238 | Workers' Properties, 210 |
| starpu_vector_ptr_register | starpu_worker_get_ids_by_type |
| Data Interfaces, 255 | Workers' Properties, 213 |
| starpu_void_data_register | starpu_worker_get_local_memory_node |
| Data Interfaces, 256 | Workers' Properties, 214 |
| starpu_wait_initialized | starpu_worker_get_memory_node |
| Initialization and Termination, 187 | Workers' Properties, 214 |
| starpu_wake_all_blocked_workers | starpu_worker_get_name |
| Expert Mode, 382 | Workers' Properties, 213 |
| starpu_wake_worker_locked | starpu_worker_get_perf_archtype |
| Scheduling Policy, 398 | Performance Model, 313 |
| starpu wake worker no relax | starpu_worker_get_relative_speedup |
| Scheduling Policy, 398 | Scheduling Policy, 397 |
| starpu_wake_worker_relax | starpu_worker_get_relax_state |
| Scheduling Policy, 398 | Workers' Properties, 215 |
| starpu_wake_worker_relax_light | starpu_worker_get_sched_condition |
| Scheduling Policy, 398 | Scheduling Policy, 394 |
| starpu_worker.h, 491 | starpu_worker_get_type |
| | |
| starpu_worker_archtype | Workers' Properties, 212 |
| Workers' Properties, 211 | starpu_worker_get_type_as_string |
| starpu_worker_can_execute_task | Workers' Properties, 214 |
| Scheduling Policy, 395 | starpu_worker_lock |
| starpu_worker_can_execute_task_first_impl | Workers' Properties, 215 |

| starpu_worker_lock_self | starpurm_assign_all_devices_to_starpu |
|---|---|
| Workers' Properties, 216 | Interoperability Support, 442 |
| starpu_worker_relax_off | starpurm_assign_cpu_mask_to_starpu |
| Workers' Properties, 215 | Interoperability Support, 438 |
| starpu_worker_relax_on | starpurm_assign_cpu_to_starpu |
| Workers' Properties, 215 | Interoperability Support, 438 |
| starpu_worker_sched_op_pending | starpurm_assign_cpus_to_starpu |
| Workers' Properties, 215 | Interoperability Support, 438 |
| starpu_worker_set_going_to_sleep_callback | starpurm_assign_device_mask_to_starpu |
| Workers' Properties, 216 | Interoperability Support, 441 |
| starpu_worker_set_waking_up_callback | starpurm_assign_device_to_starpu |
| Workers' Properties, 216 | Interoperability Support, 441 |
| starpu_worker_trylock | starpurm_assign_devices_to_starpu |
| Workers' Properties, 215 | Interoperability Support, 441 |
| starpu_worker_unlock | starpurm_drs_enabled_p |
| Workers' Properties, 215 | Interoperability Support, 438 |
| starpu_worker_unlock_self | starpurm_get_all_cpu_workers_cpuset |
| Workers' Properties, 216 | Interoperability Support, 444 |
| starpufft.h, 493 | starpurm_get_all_device_workers_cpuset |
| starpufft_cleanup | Interoperability Support, 445 |
| FFT Support, 359 | starpurm_get_all_device_workers_cpuset_by_type |
| starpufft_destroy_plan | Interoperability Support, 445 |
| FFT Support, 360 | starpurm_get_device_id |
| starpufft_execute | Interoperability Support, 441 |
| FFT Support, 359 | starpurm_get_device_type_id |
| starpufft_execute_handle | Interoperability Support, 441 |
| FFT Support, 359 | starpurm_get_device_type_name |
| starpufft_free | Interoperability Support, 441 |
| FFT Support, 358 | starpurm_get_device_worker_cpuset |
| starpufft_malloc | Interoperability Support, 444 |
| FFT Support, 358 | starpurm_get_global_cpuset |
| starpufft_plan_dft_1d | Interoperability Support, 444 |
| FFT Support, 359 | starpurm_get_nb_devices_by_type |
| starpufft plan dft 2d | Interoperability Support, 441 |
| FFT Support, 359 | starpurm_get_selected_cpuset |
| starpufft start | Interoperability Support, 444 |
| • — | |
| FFT Support, 359 starpufft_start_handle | starpurm_initialize Interoperability Support, 437 |
| FFT Support, 359 | starpurm initialize with cpuset |
| starpurm.h, 500 | . – – . |
| • | Interoperability Support, 437 |
| starpurm_acquire | starpurm_lend |
| Interoperability Support, 440 | Interoperability Support, 439 |
| starpurm_acquire_all_devices | starpurm_lend_all_devices |
| Interoperability Support, 444 | Interoperability Support, 443 |
| starpurm_acquire_cpu | starpurm_lend_cpu |
| Interoperability Support, 440 | Interoperability Support, 439 |
| starpurm_acquire_cpu_mask | starpurm_lend_cpu_mask |
| Interoperability Support, 440 | Interoperability Support, 439 |
| starpurm_acquire_cpus | starpurm_lend_cpus |
| Interoperability Support, 440 | Interoperability Support, 439 |
| starpurm_acquire_device | starpurm_lend_device |
| Interoperability Support, 443 | Interoperability Support, 442 |
| starpurm_acquire_device_mask | starpurm_lend_device_mask |
| Interoperability Support, 444 | Interoperability Support, 443 |
| starpurm_acquire_devices | starpurm_lend_devices |
| Interoperability Support, 443 | Interoperability Support, 442 |
| starpurm_assign_all_cpus_to_starpu | starpurm_reclaim |
| Interoperability Support, 438 | Interoperability Support, 439 |

| starpurm_reclaim_all_devices | synchronous |
|---|---|
| Interoperability Support, 443 | starpu_task, 284 |
| starpurm_reclaim_cpu | |
| Interoperability Support, 440 | tag_id |
| starpurm_reclaim_cpu_mask | starpu_task, 284 |
| Interoperability Support, 440 | Task Bundles, 376 |
| starpurm_reclaim_cpus | starpu_task_bundle_close, 377 |
| Interoperability Support, 440 | starpu_task_bundle_create, 376 |
| starpurm_reclaim_device | starpu_task_bundle_expected_data_transfer_time, |
| Interoperability Support, 443 | 377 |
| starpurm_reclaim_device_mask | starpu_task_bundle_expected_energy, 377 |
| Interoperability Support, 443 | starpu_task_bundle_expected_length, 377 |
| starpurm_reclaim_devices | starpu_task_bundle_insert, 376 |
| Interoperability Support, 443 | starpu_task_bundle_remove, 376 |
| starpurm_return_all | starpu_task_bundle_t, 376 |
| Interoperability Support, 440 | Task Insert Utility, 296 |
| starpurm_return_all_devices | STARPU_CALLBACK_ARG, 298 |
| Interoperability Support, 444 | STARPU_CALLBACK_WITH_ARG, 298 |
| starpurm return cpu | STARPU_CALLBACK, 298 |
| Interoperability Support, 440 | STARPU_CL_ARGS_NFREE, 299 |
| starpurm_return_device | STARPU_CL_ARGS, 299 |
| Interoperability Support, 444 | STARPU_EXECUTE_ON_WORKER, 298 |
| starpurm set drs disable | STARPU_EXECUTE_WHERE, 298 |
| . – – – | STARPU_FLOPS, 298 |
| Interoperability Support, 438 | STARPU_HANDLES_SEQUENTIAL_CONSIST← |
| starpurm_set_drs_enable | ENCY, 299 |
| Interoperability Support, 437 | STARPU_NAME, 299 |
| starpurm_set_max_parallelism | STARPU_PRIORITY, 298 |
| Interoperability Support, 438 | STARPU_SCHED_CTX, 298 |
| starpurm_shutdown | STARPU_TAG_ONLY, 298 |
| Interoperability Support, 437 | STARPU_TASK_COLOR, 299 |
| starpurm_spawn_kernel_on_cpus | STARPU_TASK_DEPS_ARRAY, 299 |
| Interoperability Support, 437 | STARPU_TASK_END_DEPS_ARRAY, 299 |
| starpurm_spawn_kernel_on_cpus_callback | STARPU_TASK_END_DEP, 299 |
| Interoperability Support, 437 | STARPU_TASK_SYNCHRONOUS, 299 |
| starpurm_withdraw_all_cpus_from_starpu | STARPU_TAG, 298 |
| Interoperability Support, 439 | STARPU VALUE, 298 |
| starpurm_withdraw_all_devices_from_starpu | STARPU_WORKER_ORDER, 299 |
| Interoperability Support, 442 | starpu_codelet_pack_arg, 302 |
| starpurm_withdraw_cpu_from_starpu | starpu_codelet_pack_arg_fini, 302 |
| Interoperability Support, 438 | starpu codelet pack arg init, 302 |
| starpurm_withdraw_cpu_mask_from_starpu | starpu_codelet_pack_args, 301 |
| Interoperability Support, 439 | starpu_codelet_unpack_args, 302 |
| starpurm_withdraw_cpus_from_starpu | starpu_codelet_unpack_args_and_copyleft, 302 |
| Interoperability Support, 439 | starpu_insert_task, 300 |
| starpurm_withdraw_device_from_starpu | starpu_task_build, 300 |
| Interoperability Support, 442 | starpu_task_insert, 300 |
| starpurm withdraw device mask from starpu | starpu_task_insert_data_make_room, 301 |
| Interoperability Support, 442 | starpu_task_insert_data_process_arg, 301 |
| starpurm_withdraw_devices_from_starpu | starpu_task_insert_data_process_array_arg, 301 |
| Interoperability Support, 442 | starpu_task_insert_data_process_mode_array_ \leftarray |
| start_ctx | arg, 301 |
| sc_hypervisor_policy, 402, 411 | |
| | starpu_task_set, 300 |
| status | Task Lists, 377 |
| starpu_task, 286 | starpu_task_list_back, 378 |
| submit_hook | starpu_task_list_begin, 379 |
| starpu_sched_policy, 393 | starpu_task_list_empty, 378 |
| symbol | starpu_task_list_end, 379 |
| starpu_perfmodel, 311 | starpu_task_list_erase, 378 |

| starpu_task_list_front, 378 | starpu_pthread_getspecific, 202 |
|--|---------------------------------------|
| starpu_task_list_init, 378 | starpu_pthread_join, 200 |
| starpu_task_list_ismember, 379 | starpu_pthread_key_create, 202 |
| starpu_task_list_next, 379 | starpu_pthread_key_delete, 202 |
| starpu_task_list_pop_back, 379 | starpu_pthread_mutex_destroy, 201 |
| starpu_task_list_pop_front, 379 | starpu_pthread_mutex_init, 201 |
| starpu_task_list_push_back, 378 | starpu_pthread_mutex_lock, 201 |
| starpu_task_list_push_front, 378 | starpu_pthread_mutex_trylock, 201 |
| test_request | starpu_pthread_mutex_unlock, 201 |
| starpu_disk_ops, 273 | starpu_pthread_mutexattr_destroy, 202 |
| Theoretical Lower Bound on Execution Time, 319 | starpu_pthread_mutexattr_gettype, 201 |
| starpu_bound_compute, 320 | starpu_pthread_mutexattr_init, 202 |
| starpu_bound_print, 320 | starpu_pthread_mutexattr_settype, 201 |
| starpu_bound_print_dot, 319 | starpu_pthread_rwlock_destroy, 203 |
| starpu_bound_print_lp, 320 | starpu_pthread_rwlock_init, 203 |
| starpu_bound_print_mps, 320 | starpu_pthread_rwlock_rdlock, 203 |
| starpu_bound_start, 319 | starpu_pthread_rwlock_tryrdlock, 203 |
| starpu_bound_stop, 319 | starpu_pthread_rwlock_trywrlock, 204 |
| Threads, 195 | starpu_pthread_rwlock_unlock, 204 |
| STARPU PTHREAD BARRIER DESTROY, 199 | starpu_pthread_rwlock_wrlock, 203 |
| STARPU PTHREAD BARRIER INIT, 199 | starpu_pthread_setspecific, 202 |
| STARPU PTHREAD BARRIER WAIT, 199 | starpu_pthread_spin_destroy, 204 |
| STARPU_PTHREAD_COND_BROADCAST, 199 | starpu_pthread_spin_init, 204 |
| STARPU_PTHREAD_COND_DESTROY, 199 | starpu pthread spin lock, 204 |
| STARPU_PTHREAD_COND_INITIALIZER, 200 | starpu_pthread_spin_trylock, 204 |
| STARPU_PTHREAD_COND_INIT, 199 | starpu_pthread_spin_unlock, 205 |
| STARPU PTHREAD COND SIGNAL, 199 | starpu_sleep, 205 |
| STARPU_PTHREAD_COND_WAIT, 199 | to_pointer |
| STARPU_PTHREAD_CREATE_ON, 197 | starpu_data_interface_ops, 236 |
| STARPU_PTHREAD_CREATE, 197 | Toolbox, 193 |
| STARPU PTHREAD GETSPECIFIC, 198 | STARPU_ABORT_MSG, 195 |
| STARPU_PTHREAD_KEY_CREATE, 198 | STARPU_ABORT, 195 |
| STARPU_PTHREAD_KEY_DELETE, 198 | STARPU_ASSERT_MSG, 194 |
| STARPU_PTHREAD_MUTEX_DESTROY, 197 | STARPU ASSERT, 194 |
| STARPU_PTHREAD_MUTEX_INITIALIZER, 200 | STARPU_ATTRIBUTE_ALIGNED, 194 |
| STARPU_PTHREAD_MUTEX_INIT, 197 | STARPU_ATTRIBUTE_INTERNAL, 194 |
| STARPU PTHREAD MUTEX LOCK, 197 | STARPU ATTRIBUTE MALLOC, 194 |
| STARPU PTHREAD MUTEX UNLOCK, 198 | STARPU ATTRIBUTE NORETURN, 194 |
| STARPU_PTHREAD_RWLOCK_DESTROY, 199 | STARPU_ATTRIBUTE_PURE, 194 |
| STARPU_PTHREAD_RWLOCK_INIT, 198 | STARPU ATTRIBUTE UNUSED, 194 |
| STARPU PTHREAD RWLOCK RDLOCK, 198 | STARPU_ATTRIBUTE_WARN_UNUSED_RES↔ |
| STARPU_PTHREAD_RWLOCK_UNLOCK, 198 | ULT, 194 |
| STARPU PTHREAD RWLOCK WRLOCK, 198 | STARPU_CHECK_RETURN_VALUE_IS, 195 |
| STARPU PTHREAD SETSPECIFIC, 198 | STARPU CHECK RETURN VALUE, 195 |
| starpu_pthread_attr_destroy, 200 | STARPU GNUC PREREQ, 193 |
| starpu_pthread_attr_init, 200 | STARPU_LIKELY, 194 |
| starpu_pthread_attr_setdetachstate, 200 | STARPU RMB, 195 |
| starpu pthread barrier destroy, 204 | STARPU UNLIKELY, 194 |
| starpu_pthread_barrier_init, 204 | STARPU_WMB, 195 |
| starpu_pthread_barrier_wait, 204 | trace_buffer_size |
| starpu_pthread_cond_broadcast, 202 | starpu_conf, 186 |
| starpu_pthread_cond_destroy, 203 | Tree, 399 |
| starpu_pthread_cond_init, 202 | tree |
| | |
| starpu_pthread_cond_signal, 202 | starpu_sched_component, 422 |
| starpu_pthread_cond_timedwait, 203 | type |
| starpu_pthread_cond_wait, 203 | starpu_codelet, 277 |
| starpu_pthread_create, 200 | starpu_perfmodel, 310 |
| starpu_pthread_exit, 200 | starpu_task, 286 |

| starpu_worker_collection, 210 | STARPU_MAXNUMANODES, 211 |
|--------------------------------------|--|
| types_of_workers, 402 | STARPU_NMAXWORKERS, 210 |
| | starpu_cpu_worker_get_count, 212 |
| unpack_data | starpu_cuda_worker_get_count, 212 |
| starpu_data_interface_ops, 237 | starpu_memory_nodes_numa_devid_to_id, 214 |
| unplug | starpu_memory_nodes_numa_id_to_devid, 214 |
| starpu_disk_ops, 271 | starpu_mic_device_get_count, 212 |
| use_explicit_workers_bindid | starpu_mic_worker_get_count, 212 |
| starpu_conf, 184 | starpu_mpi_ms_worker_get_count, 212 |
| use_explicit_workers_cuda_gpuid | starpu_node_get_kind, 214 |
| starpu_conf, 184 | starpu_opencl_worker_get_count, 212 |
| use_explicit_workers_mic_deviceid | starpu_worker_archtype, 211 |
| starpu_conf, 184 | starpu_worker_collection_type, 211 |
| use_explicit_workers_mpi_ms_deviceid | starpu_worker_display_names, 213 |
| starpu_conf, 184 | starpu_worker_get_by_devid, 213 |
| use_explicit_workers_opencl_gpuid | starpu_worker_get_by_type, 213 |
| starpu_conf, 184 | starpu_worker_get_count, 212 |
| use_tag | starpu_worker_get_count_by_type, 213 |
| starpu_task, 284 | starpu_worker_get_devid, 214 |
| | starpu_worker_get_hwloc_cpuset, 214 |
| Versioning, 181 | starpu_worker_get_hwloc_obj, 214 |
| STARPU_MAJOR_VERSION, 181 | starpu_worker_get_id, 212 |
| STARPU_MINOR_VERSION, 181 | starpu_worker_get_id_check, 210 |
| STARPU_RELEASE_VERSION, 181 | starpu_worker_get_ids_by_type, 213 |
| starpu_get_version, 181 | starpu_worker_get_local_memory_node, 214 |
| | starpu_worker_get_memory_node, 214 |
| wait_request | starpu_worker_get_name, 213 |
| starpu_disk_ops, 273 | starpu_worker_get_relax_state, 215 |
| where | starpu_worker_get_type, 212 |
| starpu_codelet, 277 | starpu_worker_get_type_as_string, 214 |
| starpu_task, 282 | starpu_worker_lock, 215 |
| worker_composed_sched_component | starpu_worker_lock_self, 216 |
| starpu_sched_component_specs, 425 | starpu_worker_relax_off, 215 |
| workerid | starpu_worker_relax_on, 215 |
| starpu_task, 285 | starpu_worker_sched_op_pending, 215 |
| workerids | starpu_worker_set_going_to_sleep_callback, 216 |
| starpu_task, 286 | starpu_worker_set_waking_up_callback, 216 |
| starpu_worker_collection, 210 | starpu_worker_trylock, 215 |
| workerids_len | starpu_worker_unlock, 215 |
| starpu_task, 286 | starpu_worker_unlock_self, 216 |
| workerorder | write |
| starpu_task, 285 | starpu_disk_ops, 272 |
| workers | starpu_disk_ops, 272 |
| starpu_sched_component, 422 | |
| workers_bindid | |
| starpu_conf, 184 | |
| workers cuda gpuid | |
| starpu conf, 184 | |
| workers_in_ctx | |
| starpu_sched_component, 422 | |
| workers_mic_deviceid | |
| starpu_conf, 184 | |
| workers_mpi_ms_deviceid | |
| starpu_conf, 185 | |
| • — | |
| workers_opencl_gpuid | |
| starpu_conf, 184 | |
| Workers' Properties, 207 | |
| STARPU_MAXCPUS, 211 | |
| STARPU_MAXNODES, 211 | |