# Radiator Policy Server Okta configuration guide

## Important notice

Before proceeding with this configuration guide, you must first complete the Okta application creation process. This includes creating an app and policies, configuring API and generating client secrets.

Please refer to the Okta application creation for Radiator Policy Server authentication before continuing.

## Example configuration setup

The Radiator installation includes an Okta example configuration that demonstrates authentication with Okta. To copy the example configuration as the working configuration, run these commands in your terminal:

```
# Navigate to the Radiator configuration directory
cd /var/lib/radiator/

# Copy all Okta example files to your working configuration
cp -R /opt/radiator/server/doc/example-configurations/okta-ad/* .
```

Please note that the copied configuration contains placeholder values that must be replaced with your actual Okta application information (covered in the following sections).

## Updating the example configuration

After completing the 'Okta application creation for Radiator Policy Server authentication' guide, you will need to modify the example configuration from the first step to match your specific Okta application details. This can be done from the GUI by selecting **Okta details** on the left side panel and filling in the fields (see below).



Alternatively use command line (CLI). Start by opening `/var/lib/radiator/25_pipeline-okta-credentials.radconf`:

```
sudo vi /var/lib/radiator/25_pipeline-okta-credentials.radconf
```

In `25_pipeline-okta-credentials.radconf`, locate the pipeline block named "SET_TENANT_INFORMATION" which looks something like this:

```
aaa {
    @pipeline "SET_TENANT_INFORMATION" {
        modify vars.aaa.oauth2.okta-domain = "https://OKTA DOMAIN";
        modify vars.aaa.oauth2.issuer-uri = "https://OKTA
DOMAIN/oauth2/AUTHORIZATION SERVER IDENTIFIER/v1/token";
        modify vars.aaa.oauth2.authz-server = "AUTHORIZATION SERVER
IDENTIFIER";
        modify vars.aaa.oauth2.client = "CLIENT ID";
        modify vars.aaa.oauth2.secret = "CLIENT SECRET";
    }
}
```

Update the following values either in the GUI or in CLI:




1. In GUI replace `OKTA DOMAIN` and in CLI in vars.aaa.oauth2.okta-domain and vars.aaa.oauth2.issuer-uri, replace `OKTA DOMAIN` with the Okta domain. The Okta domain is shown in the Okta console username dropdown menu:




2. In GUI replace `AUTHORIZATION SERVER IDENTIFIER` and in CLI in vars.aaa.oauth2.issuer-uri and vars.aaa.oauth2.authz-server, replace `AUTHORIZATION SERVER IDENTIFIER` with the Okta Authorization server identifier visible in the Issuer URI. For default Authorization Servers this is 'default':




3. In GUI replace `CLIENT ID` and in CLI in vars.aaa.oauth2.client replace `CLIENT ID` with the Client ID of your Okta application. The Client ID is shown on the Applications General tab

4. In GUI replace `CLIENT SECRET` and in CLI in vars.aaa.oauth2.secret replace `CLIENT SECRET` with the secret. The secret is shown on the Applications General tab:




5. Save the configuration file by pressing **Save** on the GUI or using your editor's Save on the CLI.

When doing changes on the GUI, new configuration is automatically taken into use. On the CLI, restart Radiator Policy Server:

```
sudo systemctl restart radiator-server
```

## Testing

You can test the Okta authentication using the Radiator test client on the CLI with this command:

```
/opt/radiator/server/bin/radiator-client --auth-port 1812 --acct-port 1813
--secret mysecret --user <user@okta-domain.com> --password <password>
```

**Note:** Replace `mysecret` with your configured RADIUS client secret, and use actual Okta user credentials.

## UI

This configuration example has Radiator 10 GUI activated:

- Management UI is open to all IP addresses, protected by username and password or API key, configured in `/var/lib/radiator/management/` directory

- Use https://YOUR-IP-ADDRESS:8443/ to access
- Default username: *admin* and password: *ChangeThisPassword!*