

Level 3 Step 2 Hard – Pratical

4

a. Rename the computer to gsr-dc.

```
$ sudo hostnamectl set-hostname gsr-dc
```

b.

Determine the subnet, gateway and dns server settings provided by your hypervisor to the newly installed VM and set a static IP address for it

Static IP:

```
$ sudo nano /etc/network/interfaces
```

```
auto ens33
iface ens33 inet static
    address 192.168.220.129
    netmask 255.255.255.0
    gateway 192.168.220.2
```

```
$ sudo systemctl restart networking
```

c.

Installing samba and windbind (samba and windbind package)

```
$ sudo apt-get install samba
$ sudo apt-get install winbind
```

d.

Disable and stop the standalone smbd service and unmask/enable the samba-ad-dc service.

```
$ sudo systemctl stop smbd nmbd winbind
$ sudo systemctl disable smbd
$ sudo systemctl unmask samba-ad-dc.service
$ sudo systemctl enable samba-ad-dc.service
```

e.

The installation of Samba will create a smb.conf file that must be discarded prior to running the Provisioning Tool in Interactive mode, or else it will fail.

Change smb.conf to other name

```
$ sudo mv smb.conf smb.conf.old
```

Samba AC-DC non-interactively with the following settings:

```
$sudo samba-tool domain provision --use-rfc2307 --interactive
```

Realm: gsr.ipb.local
Domain: gsr
Server Role: dc
Dns Backend: SAMBA_INTERNAL
DNS forwarder IP: 192.168.220.2

f.

Start the samba-ad-dc service

```
$ sudo systemctl enable samba-ad-dc.service  
$ sudo systemctl start samba-ad-dc.service  
$ sudo systemctl status samba-ad-dc.service
```

7

a) Configure static IP -> /etc/network/interfaces

```
auto ens33  
iface ens33 inet static  
    address 192.168.220.140  
    netmask 255.255.255.0  
    gateway 192.168.220.2
```

b)

```
$ sudo mkdir /home/gsr  
$ sudo chmod 775 /home/gsr
```

c)

```
$ sudo apt-get update  
$ sudo apt-get install nfs-kernel-server
```

Modify /etc/exports, add follow line:

```
/home/gsr 192.168.220.129(rw,sync,no_subtree_check)
```

Export the shared directory

```
$ sudo exportfs -a
```

Restart the nfs service

```
$ sudo service nfs-kernel-server restart
```

8.

a)

Create a mount point (directory) for the NFS sever's shared folder

```
$ sudo mkdir /mnt/gsr
```

In gsr-dc, install the NFS client, by running the following command in Terminal:

```
$ sudo apt-get update
```

```
$ sudo apt-get install nfs-common
```

Mount the server's shared directory on the gsr-dc

```
$ sudo mount 192.168.220.140:/home/gsr /mnt/backup
```

Edit fstab file, from /etc/fstab, adding the line:

```
192.168.220.140:/home/gsr /mnt/gsr nfs rw 0 0
```

Gsr-dc, in the mounted /mnt/gsr directory:

```
rafaelswr@gsr-dc:/mnt/gsr$ ls
response.txt  teste.txt
rafaelswr@gsr-dc:/mnt/gsr$
```

B)

In the *smb.conf* file (/etc/samba/smb.conf) add:

```
[gsr]
```


```
Comment = GSR share
```

```
path = /mnt/gsr
```

```
read-only = yes
```


```
browsable = yes
```

In the windows machine :



C)

User GSR\39041:



List all records samba internal dns

Sudo samba-tool dns query gsr-dc gsr.ipb.local @ ALL -UAdministrator%Rafael.1999.1.

Delete row:

Sudo samba-tool dns delete gsr-dc gsr.ipb.local gsr-ws-01 A 192.168.220.138 -UAdministrator%Rafael.1999.1.

Add row:

Sudo samba-tool dns add gsr-dc gsr.ipb.local store A 192.168.220.145 -UAdministrator%Rafael.1999