ZCL CRM TASK TRANSFER REP Release 740 System CDA Class: ZCL CRM TASK TRANSFER REP Status: Active Inh. from: ZCL_ES_ALV_OM Attributes Description: Task transfer ALV report Instantiation: Public Final Not released Fixed pt.arithmetic Category: General Object Type Package: ZPCABAP Original lang.: EN Created by: P000597 Created on: 21.02.2015 Attributes Public attributes Attrib. Cat Description Ref. Type Init. value C LOG OBJECT Const Application log: Object name (Application code) TYPE BALOBJ D 'ZLO CRM AUDIT CASES' Private attribute Attrib. Cat Description Ref. Type Init. value FROM_CASE Inst BOR case TYPE REF TO ZCL_CRM_BOR_CASE TO CASE Inst BOR case TYPE REF TO ZCL_CRM_BOR_CASE BOL CORE Stat. BOL Core TYPE REF TO CL CRM BOL CORE DATA Stat. TYPE REF TO DATA

```
Stat. Message Log - Handler TYPE REF TO
       LOGGER
CL_S_AUT_BAL_LOG
       Methods
       Public methods
       CLASS CONSTRUCTOR
       Description: CLASS_CONSTRUCTOR
       Static method
         METHOD class_constructor.
           bol core = cl_crm_bol_core=>get_instance().
           bol_core->start_up( iv_appl_name
                                                      = 'CRM CMG'
                               iv display mode support = abap true ).
           logger = cl s aut bal log=>create( im_object = c_log_object
) .
         ENDMETHOD.
       09.03.2015
                                       18:21:01
1
       ZCL CRM TASK TRANSFER REP Release 740
                                                                System
CDA
       SET CASES
       Description: Sets the "from" and "to" cases.
       Instance mthd
       Importing parameter
         P_FROM TYPE RSOBJS_NODE_ID (From Case external ID)
         P TO TYPE RSOBJS NODE_ID (To Case external ID)
       Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         method SET CASES.
           DATA lx error TYPE REF TO cx bapi error.
           from case = NEW zcl crm bor case().
           to_case = NEW zcl_crm_bor_case().
           TRY .
```

```
from_case->set_instance_by_id( p_from ).
                to_case->set_instance_by_id( p_to ).
              CATCH cx_bapi_error INTO lx_error.
               RAISE EXCEPTION lx error.
             ENDTRY.
           endmethod.
         Private methods
         GET DATA
         Description: Fills in the data table.
         Instance mthd
         CHANGING parameter
           PT DATA TYPE CRMT CMG RECORD TAB (CRM Case Management: Case
Record Entries)
         Exceptions
           CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
           METHOD get data.
             DATA: lo case
                                  TYPE REF TO cl_crm_bol_entity,
                    lv_cguid TYPE crmt_genil_object_guid,
lo_tasks TYPE REF TO if_bol_bo_col,
lo_task TYPE REF TO if_bol_bo_property_access,
lx_error TYPE REF TO cx_crm_genil_model_error,
                    lo iterator TYPE REF TO if bol bo col iterator,
                    lt_return TYPE bapiret2_t, lw_return TYPE bapiret2.
              FIELD-SYMBOLS < lw cmg record> TYPE crmt cmg record.
              TRY.
                  lv cguid = me->from case->av objid.
                  lo case = bol_core->get_root_entity( iv_object_name =
'CmgCase'
                                                             iv object guid =
lv cguid ).
                  lo tasks ?= lo case->get related entities(
                                                     iv relation_name =
'CmgRecordRel' ).
                CATCH cx_crm_genil_model_error INTO lx_error.
                  lw_return-id = '00'.
lw_return-type = 'E'.
lw_return-number = 368.
         09.03.2015
                                             18:21:01
2
         ZCL_CRM_TASK_TRANSFER_REP Release 740
                                                                          System
CDA
```

```
lw_return-message_v1 = lx_error->get_text().
                lw_return-message = lx_error->get_text().
                APPEND lw_return TO lt return.
                RAISE EXCEPTION TYPE cx bapi error
                  EXPORTING
                    status = lt return.
            ENDTRY.
            lo iterator = lo tasks->get iterator().
            lo_task = lo_tasks->get_first().
CREATE DATA lrf_data TYPE crmt_cmg_record.
            ASSIGN lrf data->* TO <lw cmg record>.
            WHILE lo task IS BOUND.
              lo task->get properties( IMPORTING
                                         es attributes = <lw cmg record>
) .
              IF <lw_cmg_record>-bor_type = 'BUS2000125'.
                APPEND < Iw cmg record > TO pt data.
              lo task = lo iterator->get next().
              CLEAR < lw cmg record>.
            ENDWHILE.
          ENDMETHOD.
        TRANSFER TASKS
        Description: Transfers tasks from the source to the target cases.
        Instance mthd
          METHOD transfer tasks.
            DATA: lo selections TYPE REF TO cl salv selections,
                  lo from case TYPE REF TO if scmg case api,
                  lo to case TYPE REF TO if scmg case api,
                  lt seletion TYPE
                                            salv t row,
                  lw row
                                TYPE
                                            crmt cmg record,
                  lt_sp_poid
lw_sp_poid
lv_guid_16
lv_guid_32
                                            srm list poid,
                                 TYPE
                                TYPE
                                            srmpoid,
                                 TYPE
                                           crmt_object_guid,
                                 TYPE
                                            scmg_case_guid,
                  lt_return
                                 TYPE
                                           bapiret2 t,
                  lt messages TYPE
                                             scmg t attr return value,
                  lv fail
                                 TYPE
                                             abap bool.
            FIELD-SYMBOLS: index> TYPE
                                                             int4,
                           <lt data> TYPE STANDARD TABLE.
            lo selections = alv->get selections().
            lt_seletion = lo_selections->get_selected_rows().
            IF lt seletion IS INITIAL.
              MESSAGE 'Please, select at least one task.'(M03) TYPE 'I'.
              RETURN.
            ENDIF.
            " Getting an API case instance for the From Case
            lv guid 16 = from case->av objid.
            lv guid 32 = cl crm isu guid=>convert 16 to 32( lv guid 16).
            cl_scmg_case_api=>if_scmg_case_api~open_case(
              EXPORTING
                im_case_guid = lv_guid 32
                im enqueue
                                = abap true
```

```
09.03.2015
                                       18:21:01
3
       ZCL CRM TASK TRANSFER REP Release 740
                                                                System
CDA
               im_update_task = abap_true
             RECEIVING
               re case
                          = lo_from_case
             EXCEPTIONS
                                            = 1
               failed
               enqueue failed
                                            = 2
               invalid guid
               cx srm gsp back
               no authority
               illegal_case_type
                                            = 6
                                            = 7
               OTHERS
                                                        ) .
           IF sy-subrc <> 0.
             m add syst msg.
             MESSAGE 'It is not possible to change the source
case.'(M01)
                TYPE 'E'.
           ENDIF.
           " Getting an API case instance for the To Case
           lv_guid_16 = to_case->av_objid.
           lv guid 32 = cl crm isu guid=>convert 16 to 32( lv guid 16 ).
           cl_scmg_case_api=>if_scmg_case_api~open_case(
             EXPORTING
               im_case_guid = lv_guid_32
im_enqueue = abap_true
               im_update_task = abap_true
             RECEIVING
               re case
                          = lo to case
             EXCEPTIONS
               failed
                                            = 2
               enqueue failed
                                            = 3
               invalid_guid
               cx_srm_gsp_back
no_authority
                                            = 5
               illegal_case_type
                                            = 6
               OTHERS
                                            = 7
                                                       ) .
           IF sy-subrc <> 0.
             lo from case->dequeue().
             m add syst msg.
             MESSAGE 'It is not possible to change the target
case.'(M02)
                TYPE 'E'.
           ENDIF.
           ASSIGN data->* TO <lt data>.
           LOOP AT lt seletion ASSIGNING .
             READ TABLE < lt data > INTO lw row INDEX  .
             IF sy-subrc = 0.
```

CLEAR lt_sp_poid.

```
"im anchor = 'CA'
        im_sp_poid = lt_sp_poid
        im_sps_id = 'CRM_ACTIVITY TASK'
        "im id
                 = lw_row-model_id
      EXCEPTIONS
        failed
        invalid_parameters = 2
                             = 3
        OTHERS
    IF sy-subrc <> 0.
      m_add_syst_msg.
      lv_fail = abap_true.
      EXIT.
    ENDIF.
    " Adding tasks to the Target Case
    lo to case->element insert(
      EXPORTING
        im anchor = 'CA'
        im_sp_poid = lt_sp_poid
        im_sps_id = 'CRM_ACTIVITY TASK'
      EXCEPTIONS
        failed
                           = 1
        not_enqueued = 2
        invalid_parameters = 3
                           = 4
        OTHERS
                                                 ) .
    IF sy-subrc <> 0.
      m_add_syst_msg.
      \overline{lv}_{fail} = abap_{true}.
      EXIT.
    ENDIF.
 ENDIF.
ENDLOOP.
IF lv fail = abap_false.
```

lo_from_case->save(

```
IMPORTING
                 ex_messages = lt_messages
               EXCEPTIONS
                 failed
                               = 1
                               = 2
                 OTHERS
                                            ) .
             IF sy-subrc <> 0.
               m_add_syst_msg.
             ENDIF.
             CLEAR lt_messages.
             lo to case->save(
               IMPORTING
                 ex_messages = lt_messages
               EXCEPTIONS
                                = 1
                 failed
                 OTHERS
                               = 2
                                            ) .
             IF sy-subrc <> 0.
               m_add_syst_msg.
             ENDIF.
             COMMIT WORK AND WAIT.
             LOOP AT lt seletion ASSIGNING .
               DELETE < lt data > INDEX  .
       09.03.2015
                                       18:21:01
       ZCL_CRM_TASK_TRANSFER_REP
                                    Release 740
                                                                System
CDA
             ENDLOOP.
           ELSE.
             ROLLBACK WORK.
             logger->show( im title = text-m02 ).
           lo_from_case->close_case().
           lo_to_case->close_case().
           alv->refresh().
         ENDMETHOD.
       Redefined Methods
       ON USER COMMAND
         method ON_USER_COMMAND.
           IF e_salv_function = 'TRANSFER'.
             me->transfer tasks().
           ENDIF.
           IF e salv function = 'HISTORY'.
             logger->show( im_title = 'Processing messages'(T02) ).
           ENDIF.
```

```
endmethod.
       PROCESS_FUNCTIONS
         METHOD process functions.
           DATA: lo functions TYPE REF TO CL SALV FUNCTIONS,
                ls tooltip TYPE string.
           alv->set screen status ( pfstatus = 'ZCRMR006 ST GUI'
                                 report = me->repid
                                 set functions = alv->c functions all
) .
         ENDMETHOD.
       PROCESS TOP OF LIST
         METHOD process_top_of_list.
           lo grid 1 TYPE REF TO cl salv form layout grid,
                lo flow TYPE REF TO cl_salv_form_layout_flow,
                lo_label TYPE REF TO cl_salv_form_label,
                lo text TYPE REF TO cl salv form text,
                lv value TYPE swc value,
                                    string.
                ls text TYPE
           lo grid = NEW cl salv form layout grid().
           IF me->title IS NOT INITIAL.
             lo grid->create header information(
              row = 1
              column = 1
              text = me->title
              tooltip = me->title ).
           ENDIF.
       *... in the cell [2,1] create a grid
           lo_grid_1 = lo_grid->create_grid(
                        row = 2
                        column = 1).
       09.03.2015
                                     18:21:01
       ZCL_CRM_TASK_TRANSFER_REP Release 740
                                                            System
CDA
       *... in the cell [1,1] of the second grid create a label
           lo_flow = lo_grid_1->create_flow(
                 = 2
            row
            column = 1).
           lo label = lo flow->create label(
             text = 'Source Case:'(t01)
             tooltip = text-t01).
```

```
TRY .
        lv value = from case->get plain attribute( 'EXT KEY' ).
      CATCH cx_bapi_error.
        "Ignore
    ENDTRY.
    SHIFT lv value LEFT DELETING LEADING '0'.
    lo text = lo flow->create text(
      text = lv value
      tooltip = lv_value ).
    lo label = lo flow->create label(
      \overline{\text{text}} = \overline{\text{Target Case: }}(\text{t03})
      tooltip = text-t03).
    TRY .
        lv value = to case->get plain attribute( 'EXT KEY' ).
      CATCH cx bapi error.
        "Ignore
    ENDTRY.
    SHIFT lv value LEFT DELETING LEADING '0'.
    lo text = lo flow->create text(
      \overline{t}ext = \overline{l}v_value
      tooltip = lv_value ).
    alv->set top of list( lo grid ).
  ENDMETHOD.
PUBLISH ALV
  METHOD publish alv.
    DATA: lx error TYPE REF TO cx bapi error,
          lw return TYPE bapiret2.
    TRY .
        me->get data( CHANGING pt data = itab ).
      CATCH cx bapi error INTO lx error.
        LOOP AT lx error->status INTO lw return.
          m add bapi msg.
        ENDLOOP.
        READ TABLE lx error->status INTO lw return
         WITH KEY type = 'E'.
        IF sy-subrc = 0.
          MESSAGE
               ID lw return-id
             TYPE lw return-type
           NUMBER lw return-number
             WITH lw return-message_v1
                   lw return-message v2
                   lw_return-message v3
                   lw_return-message_v4.
        ENDIF.
```

```
09.03.2015
7
```

```
ZCL_CRM_TASK_TRANSFER_REP Release 740 System CDA
```

```
ENDTRY.
           GET REFERENCE OF itab INTO DATA.
            TRY.
                cl salv table=>factory(
                  EXPORTING
                   list display = abap false
                  IMPORTING
                    r salv table = alv
                  CHANGING
                   t table
                                = itab ).
              CATCH cx_salv_msg INTO alv_msg.
                MESSAGE alv msg TYPE 'I'.
               EXIT.
           ENDTRY.
           me->process functions().
           me->set columns().
           me->process layout( i variant ).
           me->register events().
           me->process_report_headers().
           alv->display( ).
         ENDMETHOD.
        REGISTER EVENTS
         METHOD register events.
           DATA: lo events TYPE REF TO cl salv events table.
            lo events = alv->get event().
            SET HANDLER me->on user command FOR lo events.
         ENDMETHOD.
        SET COLUMNS
         method SET_COLUMNS.
           data lo selections TYPE REF TO CL SALV SELECTIONS.
           CALL METHOD SUPER->SET COLUMNS.
            lo selections = alv->get selections().
            lo selections->set selection mode(
if salv c selection mode=>multiple ).
         endmethod.
       Local Types
        \star"* use this source file for any type of declarations (class
        *"* definitions, interfaces or type declarations) you need for
        *"* components in the private section
        Local class definitions
        *"* use this source file for the definition and implementation of
        *"* local helper classes, interface definitions and type
        *"* declarations
       Macros
        *"* use this source file for any macro definitions you need
```

"" in the implementation part of the class

```
09.03.2015 18:21:01

8

ZCL_CRM_TASK_TRANSFER_REP Release 740 System

CDA
```

```
DEFINE m_add_bapi_msg.
  logger->add_entry( im_msgid = lw_return-id
                     im msgtype = lw return-type
                      im_msgno = lw_return-number
                     im_msgv1 = lw_return-message v1
                     im_msgv2 = lw_return-message_v2
im_msgv3 = lw_return-message_v3
                      im msgv4 = lw return-message v4 ).
END-OF-DEFINITION.
DEFINE m add syst msg.
  logger->add_entry( im_msgid = sy-msgid
                      im msgtype = sy-msgty
                      im msgno = sy-msgno
                      im msgv1 = sy-msgv1
                      im msgv2 = sy-msgv2
                      im msgv3 = sy-msgv3
                               = sy-msgv4).
                      im msgv4
END-OF-DEFINITION.
```

6

```
09.03.2015
                                        18:21:01
        ZCL_CRM_TASK_TRANSFER_REP Release 740
                                                                  System
CDA
        Overview
       Attributes
1
       Attributes
          Public attributes
1
          Private attribute
       Methods
1
          Public methods
1
          CLASS_CONSTRUCTOR
1
           SET_CASES
1
          Private methods
2
           GET_DATA
2
           TRANSFER_TASKS
3
          Redefined Methods
```

6
6
7
8
8
Local Types
8
Local class definitions
8
Macros

09.03.2015

10

03.2015 18:21:01