

Field	Description
ID	A unique ID number for the configured rule
Takers	The source Taker(s) You may select one or multiple Takers from the list or type a pattern manually by ticking the Pattern tick-box Note: You may use wildcards (*) for all and negations (!) for exclusion when typing a pattern
Taker Execution Models	This is source TEM, meaning all the trades executed with this TEM shall be executed to the Slave/Target account. Note: You may use wildcards (*) for all and negations (!) for exclusion when typing a pattern
Liquidity Models	Specific Liquidity Model(s) assigned to the TEM. You may select one or multiple LM(s) from the list or type a pattern manually by ticking the Pattern tick-box. Note: You may use wildcards (*) for all and negations (!) for exclusion when typing a pattern
Securities	If you specify any Security here, then only those symbols [under this security] are entitled to be executed from the Master account to the Slave/Target account.
Groups	You may select one or multiple MT4/MT5 Groups by typing in the name of the Group(s). If particular Groups are selected, only Logins belonging to these Groups will have their trades executed to the target account. Note: You may use wildcards (*) for all and negations (!) for exclusion when typing a pattern
Symbols	If you specify any Symbol here, then only those symbols are entitled to be executed from the Master account to the Slave/Target account. Note: By default, all Symbols are selected. You may select particular ones if you wish to restrict the rule to particular Symbols
Side	Default Value: * [meaning all] However, broker can further change the settings to either Buy or Sell trades to be executed from the Master to Slave account.
Master Login	Select a particular MT4/MT5 Login whose trades will be used for execution. Note: This is a very specific rule whereby the copy will be applicable to the selected Login only. Note: It is important to ensure that the Login already satisfies the other criteria [meaning it is targeting the source TEM]. Otherwise, the copy rule would not work
Target Taker	Select one Target Taker of type MT4 or MT5. This could be the same Taker or even a different Taker within the same Centroid Bridge. Note: If no Target Taker is selected, the Centroid Bridge will use the same Taker source for target as well
Target Taker Execution Model	Select the Target Taker Execution Model, this will define where the target or slave trades will be executed. Note: If no Target TEM is selected please note it will use the Source TEM as Target TEM, and all the trades will follow the master TEM for execution.
Target Login	Specify an MT4/MT5 Login into which the copied trades will be booked. This is an optional field that helps keep track of all copied trades pertaining to a particular rule in one single coverage account
Ratio	A component to decide the direction and trade volume to be executed from the master to the slave account. • Positive: executes trades in the same direction [If 1, then same volume, if 2 it will start multiplying but in same direction] • Negative: copies trades in the opposite direction (reverse copy) [If 1, then same volume, if 2 it will start multiplying but in reverse direction]
Copy Mode	Specifies which flow to copy: • All: copies all trades, A and B Book

	- A: copies A Book trades only - B: copies B Book trades only
Priority	This parameter applies in the event of having overlapping configurations. You can proceed to set the priority to adjust the rules, On a scale 1-10, rule with priority 10 will be considered first.
Symbol Format	Specifies in what Symbol format the trade will be booked in the Target Login, if Target Login is selected. You may choose one of the two available formats below and even add a string or suffix that will be added to the end of the Symbol. #ts#: Taker Symbols are used when the Master and the Slave account both the accounts have access to the <u>same set of symbols</u> on the Trading platform i.e. MT4/MT5. Example: Master is placing a trade with EURUSD@ the same EURUSD@ is available on the Slave account on the MT4/MT5. #us#: Universal Symbols are used when the Master and the Slave account both the accounts have access to a <u>different set of symbols</u> on the Trading platform i.e. MT4/MT5. Example: Master is placing a trade with EURUSD@ but this symbol is not available for the slave account on the Trading platform i.e. MT4/MT5 in this case you will proceed to do the below configuration: #ts# Taker Symbol Symbol Format name, #us# Symbol name #us# @ Note: It is important to ensure that the Target Login has access to the specified Taker Format in the MT4/MT5 Server. Otherwise, trade will not be booked
Delay(ms) / Max Waiting	The delay in ms after which the slave or hedge trade will be triggered after the execution of the Master trade.
Send Execution	The Slave or Hedge Trade will be copied or covered to the Target Login after execution.
Always STP	The Slave or Hedge Trade will be sent to the Maker regardless of the TEM B-Book percentage.
Better Points	The extra points added or deducted on the Master trade's executed price for the Slave or Hedge trade to execute at a better price. In other words, the take-profit points at which the slave trade must be triggered for execution.
Worse Points	The extra points added or deducted to the Master trade's price to prevent it from executing at a worse price. In other words, the stop-loss points at which the slave trade must be triggered to avoid further losses.
Description	A short description for reference purposes
Enable	Indicates whether the Trade Copier rule is enabled or disabled - If ticked, the Trade Copier rule is enabled upon creation - If unticked, the Trade Copier rule is disabled upon creation, hence no trades will be copied via this rule

Notes:

- Delay, Better Points, and Worse Points can be combined in a single rule. The trigger point will be whichever condition is met first.
- Better and Worse Points cannot be configured with a Negative Ratio
- The triggered Slave or Hedge trade awaiting execution will be displayed under Monitoring > Hedge Trade Order.

Configure Hedge Trade Rule [🔗](#)

To configure or modify an existing Hedge Trade Rule


1. Select the desired Hedge Trade Rule
2. Configure the desired fields
3. Click the “**Save**” button on top to deploy the changes

Hedge Trade Rules									
Save Revert All									
12 ↑	Takers	Taker Execution...	Liquidity Mod...	Securities	Groups	Symbols	Side	Master Login	Target Taker
7	%	*	%	%	%	EURUSD	%	0 Centroid_MT5	Centroid_hem
									5000
									1

Delete a Hedge Trade Rule [↗](#)


To delete a Hedge Trade Rule

1. Click the “Delete” icon next to the desired Hedge Trade Rule



ID ↑	Exec...	Target Login	Ratio	Copy Mode	Priority	Symbol Format	Delay(ms) / Ma...	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7			5000	1 ALL	1	#ts#	300000	☒	☐		5	5	☒	

2. To confirm deletion, type the ID of the Hedge Trade Rule in the field.
3. Click on the “Delete” button to confirm deletion.




Delete?

To confirm deletion, type "7" in the field.

Exporting a Hedge Trade Rule [↗](#)

1. Filter the desired Hedge Trade Rule(s) using the available filters.
2. Click “Export” and select “Export to Excel” or “Export to CSV”




ID ↑	Takers	Taker Execution...	Liquidity Mod...	Securities	Groups	Symbols	Side	Master Login	Target Taker	Target Taker Exe...	Target Login	
7	%	%	%	%	%	EURUSD	%		0 Centroid_MTS	Centroid_fem		Export to Excel Export to CSV

Case Studies: [↗](#)

Case 1. Configuring the Better Points Only [↗](#)

In this case, only the better points are configured with a value of 5.




ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable
7	1 ALL	1	#ts#	0	☐	☒	5	0		☒

Outcome: The Slave/Hedge trade of BUY side will be triggered for execution once the Market Price reaches 1.00005 following the execution of the Master trade at 1.00010.

Case 2. Configuring the Worse Points Only [↗](#)

In this case, only the Worse Points are configured with a value of 5.



ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable
7	1 ALL	1	#ts#	0	☐	☒	0	5		☒

Outcome: The Slave/Hedge trade of BUY side will be triggered for execution once the Market Price reaches 1.00020 following the execution of the Master trade at 1.00015.

Case 3. Configuring the Delay/Max Waiting Only [↗](#)

In this case, only the Delay(ms) / Max Waiting is configured with a value of 5000 ms.

Hedge Trade Rules											
ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7	1 ALL	1	#ts#	5000	☒	☐		0	0	☒	

Outcome: The Slave/Hedge trade will be triggered for execution after a delay of 5000ms following the execution of the Master trade.

Case 4. Configuring the Better Points and Delay [↗](#)

In this case, Better Points and Delay are configured.

Hedge Trade Rules											
ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7	1 ALL	1	#ts#	6000	☒	☐	5	0		☒	

Outcome: There are two possible outcomes in this situation, the slave trade will be triggered for execution if the better points are reached first; otherwise, it will be triggered after the delay.

Case 5. Configuring the Worse Points and Delay [↗](#)

In this case, Worse Points and Delay are configured.

Hedge Trade Rules											
ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7	1 ALL	1	#ts#	6000	☒	☐	0	5		☒	

Outcome: There are two possible outcomes in this situation, the slave trade will be triggered for execution if the worse points are reached first; otherwise, it will be triggered after the delay.

Case 6. Configuring the Worse Points and Better Points [↗](#)

In this case, Worse Points and Better Points are configured.

Hedge Trade Rules											
ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7	1 ALL	1	#ts#	0	☒	☐	5	5		☒	

Outcome: There are two possible outcomes in this situation, the slave trade will be triggered for execution if the worse points are reached first; otherwise, it will be triggered once the better points are met.

Case 7. Configuring the Worse Points, Better Points and Delay [↗](#)

In this case, Worse Points, Better Points and Delay are configured,

Hedge Trade Rules											
ID ↑	Copy Mode	Priority	Symbol Format	Delay(ms) / Max Waiting	Send Exe...	Always ...	Better Points	Worse Points	Description	Enable	
7	1 ALL	1	#ts#	6000	☒	☐	5	5		☒	


Outcome: There are three possible outcomes:

1. If the worse points are reached first, the slave trade will trigger for execution.
2. Else if the better points are reached first, the slave trade will trigger for execution.
3. Else, if neither of the above conditions are met, the slave trade will trigger for execution after the Delay.

The trigger point will be whichever condition is met first.

Trading

The Trading Module allows configuration, usage, and viewing of Market Watch, Trading Platform, and Push Ticks. Upon clicking the “Trading” button on the left-hand side menu, it expands to show the different components underneath which are explained in greater detail hereunder.



Market Watch

Overview [🔗](#)

The Market Watch allows Brokers to view prices coming through the different Taker Feeds defined in the Centroid Bridge including the full depth of the market. This also allows Brokers to test price connectivity with Makers and the Taker Feed when a new Maker is added or upon adding a new instrument with a Maker.


Within this module, you have the capability to:

- **Add or Remove Symbol from List:** Include or exclude symbols from the list.
- **View Prices with Full Market Depth:** Observe prices in panels with extensive market depth and adjustable based on Taker Feed and Maker level.
- **View Prices as List with TOB:** Explore prices presented as a list with the Top of Book (TOB) highlighted.

Adding a Symbol to the List [🔗](#)

To add a Symbol to the Market Watch list

1. Click the dropdown button **“Toggle here to add/remove Symbol”**.
2. Fill it in with the relevant information. You may refer to the field descriptions hereafter.
3. Click the **“Add / Remove Symbol”** button to submit the changes.




Field	Description
Taker Feed	Select a Taker Feed from the list of available Taker Feeds. You can also add multiple Taker Feeds.
Symbol	Select one or multiple Symbols pertaining to the selected Taker Feed for which you want to see the price.

Deleting a Symbol from the List [🔗](#)

To delete a Symbol from the list


1. Click the dropdown button **“Toggle here to add/remove Symbol”**.

2. In the Symbol textfield, search and choose your desired Symbol. Once you hover your mouse to the selected symbol, you may click the “x” button next to it if you wish to remove it from the list. Alternatively, you can simplify the deletion by clicking the “x” button on the top right side of the panel.
3. Click the “Add / Remove Symbol” button to submit the changes.



Panel View [🔗](#)

In the panel, you can view the price of each Symbol separately. Selected Symbols will appear in a separate panel on which all the pricing-related information is shown.



- Symbol name with configured suffix from Taker Feed
- Bid and Ask indicator with green upward arrow for an increase and red downward arrow for a decrease
- TOB quantity or available liquidity on the Bid and Ask side
- TOB Bid price and TOB Ask price
- Spread at TOB in decimals (e.g., 000002 for a 2 pip spread)
- Time of the last received price
- Full depth of available liquidity sizes on the Bid and Ask side (below TOB)
- Full depth of available liquidity prices on the Bid and Ask side (below TOB)

List View [🔗](#)

In the panel, you can view the TOB price of each Symbol along with other relevant information.

Market Watch

Toggle here to add / remove Symbol

Taker Feed: Plain_Feed

Symbol: Plain_Feed@EURUSD, Plain_Feed@XAUUSD, Plain_Feed@BTCUSD

Ticket: List

Symbol	Bid Price	Ask Price	Spread	Spread Points	Bid Volume	Ask Volume	Bid Maker	Ask Maker	Last Updated	LTP Price	LTP Volume
Plain_Feed@EURUSD	1.09466	1.09468	0.00002	2	2008	2008	LIQUIDITY_PROVIDER_1	LIQUIDITY_PROVIDER_1	21-11-2023 09:16:04	NaN	0
Plain_Feed@XAUUSD	1,986,690	1,986,770	0.080	80	2M	2M	LIQUIDITY_PROVIDER_1	LIQUIDITY_PROVIDER_1	21-11-2023 09:16:04	NaN	0
Plain_Feed@BTCUSD	37,370.00	37,409.00	39.00	3,900	40	40	LIQUIDITY_PROVIDER_1	LIQUIDITY_PROVIDER_1	21-11-2023 09:16:04	NaN	0

Field	Description
Symbol	The selected Taker Feed Symbol(s).
Bid Price	The Bid Price at the top of the book (TOB).
Ask Price	The Ask Price at the top of the book (TOB).
Spread	The Spread at the top of the book (TOB) expressed in decimal form. For instance, a spread of 0.00005 on a 5-digit EURUSD symbol corresponds to 0.5 pips and 5 points.
Spread Points	The spread at the top of the book (TOB) expressed in points. For instance, a spread points of 2 corresponds to 0.00002 on a 5-digit EURUSD symbol.
Bid Volume	The Bid liquidity currently available at the top of the book (TOB).
Ask Volume	The Ask liquidity currently available at the top of the book (TOB).
Bid Maker	The Maker streaming the Bid liquidity.
Ask Maker	The Maker streaming the Ask liquidity.
Last Updated	The timestamp indicating when the price was last updated.
LTP Price	The Last Traded Price.
LTP Volume	The Last Traded Price Volume.

FAQ [🔗](#)

- ✓ What could be the reason why a particular symbol is not pricing on the Taker Feed level?

To troubleshoot, follow these steps:

1. Ensure the Taker Feed is enabled.
2. Check if you have assigned a working Liquidity Model.
3. Check if the assigned Maker is sending prices for that particular Symbol to the Centroid Bridge. You can check this by navigating to Monitoring -> Maker Status, as detailed in the manual.

Trading Platform

Overview [↗](#)

The Trading Platform provides Brokers with direct access to the market to trade directly with their Liquidity Providers (Makers). Through the Trading Panel, Brokers have access to the liquidity book allowing them to see the full depth of the market across all Symbols. Brokers can trade using different order types as well as execution modes such as Market, Limit, Stop, IOC, FOK, and so on.

The Trading Platform component consists of a Trading Panel, Order Logs, Positions, and Account Balance.


Trading Panel [↗](#)

Similar to Market Watch, the Trading Panel displays full pricing information about the Symbol. Additionally, through this panel, Brokers can place different types of orders using different execution methods. One symbol panel can be used at a time.

Adding a Symbol [↗](#)

To add a Symbol to trade on

1. Click the dropdown button “**Toggle here to add/remove Symbol**”.
2. Fill it in with the relevant information. You may refer to the field descriptions hereafter.
3. Click the “**Add / Remove Symbol**” button to submit the changes.



Field	Description
Risk Account / Taker Execution Model	You may choose a Risk Account with its dedicated Taker Feed and Taker Execution Model to trade on or an individual Taker Execution Model. Note: If a Risk Account is chosen, then any order will be subject to all configurations within the Risk Account and will affect the Risk Account balance and positions.
Risk Account	Choose a particular Risk Account from the dropdown list. Note: If Taker Execution Model is initially selected above, this field will be greyed out.
Taker	The Taker to trade on.
Taker Execution Model	The Taker Execution Model within the chosen Taker to trade on.

Taker Feed	The Taker Feed within the chosen Taker to show prices on the Trading Panel.
Symbol	The Symbol to trade on. Note: Only one Symbol can be chosen at a time.
One Click Trading	Defines whether the One Click Trading setting is enabled or disabled. • Enable: Order is placed once the trade button is clicked. • Disable: Order requires an additional confirmation prior to sending it through.
TOB Price	Sends the Top of the Book Price as target price for Orders of types Limit or Stop which require Request Price. • Enable: Sends the TOB Price as a Request Price for Orders of types Limit or Stop. • Disable: User needs to manually input the Request Price for Orders of types Limit or Stop.

Note: To add another Symbol to trade on, you just need to repeat the same process above and replace the current Symbol with the new one in the Symbol field.

Once a Symbol has been added, Brokers can click on the “**Sell**” or “**Buy**” buttons from the Symbol panel to send “**Sell**” or “**Buy**” orders.

Field	Description
Symbol	Symbol to trade on as configured in Taker Feeds.
Maker Liquidity	Price information of the Symbol as explained in Market Watch component.
Ord Type	Order Type which specifies the type of order being sent: • Market: Order is executed at the current Market Price. • Limit: Order is executed at the requested or better price. If price is worse than the requested price, then order will get rejected. • Stop: Order is executed at requested or worse price.
Volume	Quantity the order size in notional volume.

Price	Defines the desired price. For Market orders, no price is sent along with the order request. Order always gets executed at the market price. As for Limit and Stop orders, you can specify the desired price.
Validity	Specifies the execution mode: • IOC: Allows partial filling of an order in case the requested quantity cannot be fully filled. • FOK: Does not allow partial filling. If the order cannot be entirely filled, it will get rejected.
Deviation	Defines the deviation away from the price. This is only applicable for Orders of types Limit and Stop and specifies the deviation in pips that is acceptable if the price improves or worsens for Orders of types Limit and Stop respectively. Example: If a buy Order of Limit type is sent at 1.13850 with a deviation of 1.0, the Order can still be filled if the price worsens by up to 1 pip (10 points) so it can be executed at a worse price up to 1.13840. Any price above 1.13840 is acceptable whereas if price drops below 1.13840, the order will be rejected.
Ext Order ID	An MT4/MT5 order number linked to the order.
Ext Client Login	An MT4/MT5 login number linked to the order.
Ext Client Group	An MT4/MT5 Group linked to the order.
Sell	Button sends a SELL order.
Buy	Button sends a BUY order.

Note: It is important to ensure that the Taker Feed is showing prices and the Trading Account (Taker Execution Model) are assigned to the same Liquidity Models and Markup Models to ensure that you are trading with the correct prices being displayed, hence getting price updates from the same Makers (LP).

Order Logs [🔗](#)

The Order Logs panel is an Order blotter that shows each Order executed through the Trading Platform at different stages of the execution.

Within this module, you have the capability to:

- **Filter and Look Up Orders:** Search orders by different criteria.
- **Navigate to Previous Page:** Move to the previous page by clicking the "Previous" button.
- **Navigate to Next Page:** Move to the next page by clicking the "Next" button.
- **Navigate to Desired Page:** Go to a specific page by entering the page number into the textbox.

	• Partially Filled Orders: Fill Volume less than Volume. • Rejected Orders: 0 Volume as no Volume was executed. The actual filled Volume could be equal or less than the requested Volume above.
Price	The Requested Price specified in the Order request, if any. This is only relevant to Limit and Stop Orders.
Avg Price	The Weighted Average Price in case the Order was split into multiple legs.
Time in Force	The execution mode: IOC or FOK .
Deviation	Defines the deviation between the Requested Price and the Filled Price if any. This is only relevant to Limit and Stop Orders.
Text	A message pertaining to the executed order in the event of execution or rejection. In cases of rejection, this message may provide insights into the reasons behind the rejection.

Positions [🔗](#)

The Positions tab displays the current net open positions in real-time for the selected Risk Account or Taker Execution Model. Brokers can have overview into all Risk Accounts or Taker Execution Models which allows to track the current exposure and net open positions on a per Symbol basis.

One Risk Account/Taker Execution Model only can be selected at a time.

Field	Description
Symbol	The Symbol with open positions
Taker Execution Model	The name of the Taker Execution Model where the Order is originated from Note: This is only relevant if a Taker Execution Model is selected. Otherwise, if a Risk Account is selected, the field will show an empty value
Taker	The name of the Taker where the Order is originated from Note: This is only relevant if a Taker Execution Model is selected. Otherwise, if a Risk Account is selected, the field will show an empty value

Liquidity Model	The Liquidity Model assigned to the Risk Account/Taker Execution Model which specifies the Maker(s) Orders are executed with
Net Volume	The Net Open Positions in notional value. • If the Account is Short on the Symbol, the Net Volume will show a negative value and will be highlighted in Red • If the Account is Long on the Symbol, the Net Volume will show a positive value and will be highlighted in Blue
ANet Volume	The Net Open Positions of the STP Orders
BNet Volume	The Net Open Positions of the internalized (B-Book) Orders
Avg Price	The Weighted Average Price of all Orders that form the Position
AAvg Price	The Weighted Average Price of all Orders that make up the STP Positions
BAvg Price	The Weighted Average Price of all Orders that make up the B Book Positions
Last Time	The Last Time the price hence the Position were updated
Close Price	The current Market Price of the Symbol
PL	The floating (unrealized) P/L of the Symbol based on the Open Positions
Margin	The current Utilized or Blocked Margin of the Symbol's Open Positions
Swaps	The accumulated Swap charges that have been charged on Open Positions. Note: These charges represent the unrealized charges that have not been deducted from the Account Balance yet. When an Order offsets (partially or totally) the Open Position, the corresponding value will be deducted (proportionally or fully) from the Account Balance and will appear in the Account Statement
Commission	The accumulated Commission charges that have been charged upon opening the Position. Note: These charges represent the unrealized charges that have not been deducted from the Account Balance yet. When an Order offsets (partially or totally) the Open Position, the corresponding value will be deducted (proportionally or fully) from the Account Balance and will appear in the Account Statement

Account Balance [🔗](#)

Account Balance is only relevant if Risk Account is selected and shows all balance, P/L and margin information pertaining to the Risk Account.

If Taker Execution Model is selected, this tab will display empty values.

Field	Description
Name	The Name of the Risk Account
Margin Blocked	The blocked or utilized margin of the Risk Account based on the open positions
Balance	The current Balance in USD of the Risk Account
Available Withdraw	The amount in USD available for withdrawal. It is equivalent to the Free Margin of the Risk Account and is calculated as follows: Available Withdraw = Equity – Margin Blocked - Credit
Equity	The current Equity in USD of the Risk Account Equity = Balance + PL

PL	The PL of the floating positions which is equal to the sum of floating PL of all Symbols
Margin Level	The Margin Percentage Level of the Risk Account which specifies the level at which no more Orders are allowed or Account gets liquidated. Margin Level = $\text{Equity} / \text{Margin Blocked} \times 100$
Commission	The accumulated Commission charges that have been charged on the Risk Account. Note: These charges represent the unrealized charges that have not been deducted from the Account Balance yet. When an Order offsets (partially or totally) the Open Position, the corresponding value will be deducted (proportionally or fully) from the Account Balance and will appear in the Account Statement
Swaps	The accumulated Commission charges that have been charged on the Risk Account. Note: These charges represent the unrealized charges that have not been deducted from the Account Balance yet. When an Order offsets (partially or totally) the Open Position, the corresponding value will be deducted (proportionally or fully) from the Account Balance and will appear in the Account Statement
Notional	The Notional Volume of all Open Positions translated into USD (Risk Account Currency)
Credit	The amount of Credit given to the Risk Account, if any
Trading State	The Trading State of the Risk Account. • STOPPED OUT: Risk Account is flat or negative which could be due to stop out or Account is out of balance • MARGIN CALL: Risk Account is on Margin Call when the Margin Level hits or drops below the percentage defined in Warn Level set for the Account • NEUTRAL: Risk Account is funded

Push Ticks

Overview [🔗](#)


The Push Ticks component allows pushing prices manually as a Maker into Taker Feeds in the event of stale prices.

This functionality has several uses and is mainly used for B Book execution, allowing to settle B Book Positions at a certain close price such as Risk Account Adjustment, Position Adjustments, and Expired Future Symbol.

Symbol Selection [🔗](#)

To select the Symbol into which the ticks will be pushed

1. Click the dropdown button **“Toggle here to add/remove Symbol”**.
2. Fill it in with the relevant information. You may refer to the field descriptions hereafter.
3. Click the **“Add / Remove Symbol”** button to submit the changes.



Field	Description
Makers	Select a Maker into which the Orders will be executed.
Taker Feed	Select a Taker Feed into which the ticks will be pushed.
Symbol	Select a Symbol into which the ticks will be pushed. By doing this, you are pushing ticks to that specific symbol only.

Push Ticks Manually [🔗](#)

To push the ticks manually

Once you have selected the desired parameter, you will be presented with a panel pertaining to the selected Symbol through which you can push the ticks manually.

1. Fill in the Bid and Ask volumes and prices as highlighted below. You may refer to the field descriptions hereafter.
2. Click the **“Submit”** button to push the tick.

Push Ticks

Liquidity_Provider

▼

Plain_Feed

▼

EURUSD

▼

Add / Remove Symbol

EURUSD

Qty
0

Bid
0.00⁰

Ask
0.00⁰

Qty
0

Spread 0.00000

LTP Price
0.00000

Points 0

LTP Volume
0

Time -

0.0	-	0.00000	0	0.00000	-	0.0
0.0	-	0.00000	0	0.00000	-	0.0
0.0	-	0.00000	0	0.00000	-	0.0
0.0	-	0.00000	0	0.00000	-	0.0
0.0	-	0.00000	0	0.00000	-	0.0

Symbol
EURUSD

Bid
0.0

Ask
0.0

LTP Price
0.0

Makers
ACG_DEMO

Bid Volume
0

Ask Volume
0


LTP Volume
0

SUBMIT

Field	Description
Symbol	The selected Symbol.
Makers	The selected Maker.
Bid	The Bid Price to be pushed.
Ask	The Ask Price to be pushed.
LTP Price	The Last Traded Price to be pushed.
Bid Volume	The Bid Volume to be pushed along with the Bid Price which defines the available liquidity for order execution.
Ask Volume	The Ask Volume to be pushed along with the Ask Price which defines the available liquidity for order execution.
LTP Volume	The Last Traded Price Volume to be pushed along with the LTP Price which defines the available liquidity for order execution.

Monitoring

The Monitoring module of the Centroid Bridge provides a real-time monitoring tool for Takers and Makers connectivity allowing users to check connections at all times and troubleshoot any Taker/Maker connectivity issue. Real-time and Historical logs and alerts are also available in this module. Upon clicking the “Monitoring” button on the left-hand side menu, it expands to show the different components underneath which are explained in greater detail hereunder.



Logs

Overview [↗](#)

The Logs feature lets you check detailed records of the Centroid Bridge. These logs hold important information for investigating connectivity, pricing, and trading problems, as well as updates to configurations and other relevant details. You can see current logs in real time, while past logs are compressed and saved in the Centroid Bridge at regular intervals.


Log Types [↗](#)

Log type	Description
Makers	Maker logs encompass all the trading and pricing details between your Centroid Bridge and the corresponding Maker.
Takers	Taker logs encompass all the trading and pricing details between your Centroid Bridge and the corresponding Taker.
Feeder	The Feeder contains all the ticks forwarded to your taker, providing real-time ticks specifically tailored for MT4/MT5 takers only.
Trade Statement	If you have Risk Accounts set up in your Centroid Bridge, a statement is generated and stored here at the end of each day. This statement includes all the transactions conducted throughout the day along with additional details.
Downloads	In addition to the Online Manual, you can conveniently find the most recent versions for both GW and Feeder in the download section.
System	The system log compiles all the details of activities carried out at the bridge level. This includes recording any changes made to any component on the bridge.


In-Depth Explanation of All Log Types [↗](#)

1. Makers [↗](#)

Where to Find the Makers Log: Path → Monitoring → Logs → Makers → Two folders available “marketdata” for pricing “trading” for trading logs respectively.



How to Download/Read the Logs: To ensure you download the accurate log file, review the timestamp for each file, where the time is formatted as YY/MM/DD Hours/Minutes/Seconds. For reading the downloaded logs, you can utilize [FIX Parser](#). Follow these steps: Download the log file, locate the specific order or logline, and copy-paste it into the provided link.




What Are the Logs About: The Maker logs provide valuable insights into whether you are receiving prices from a specific maker. They also offer information on the reasons for rejection, providing clarity on whether your trade was successful, partially filled, or rejected. In the case of rejection, the logs specify the reasons behind the rejection, enhancing your understanding of the trading process.

Note: Centroid Bridge stores "Pricing or Market Data" internally for a maximum period of 7 days.


2. Takers [🔗](#)

Where to Find the Takers Log: Path → Monitoring → Logs → Takers → Two separate folders available “MD_Taker_Name” for pricing and “TD_Taker_Name” for trading logs respectively.

Note: For Taker type MT4/MT5 Centroid bridge does not store the ticks in the “marketdata” folder.



How to Download/Read the Logs: To ensure you download the accurate log file, review the timestamp for each file, where the time is formatted as YY/MM/DD Hours/Minutes/Seconds. For reading the downloaded logs, you can utilize [FIX Parser](#). Follow these steps: Download the log file, locate the specific order or logline, and copy-paste it into the provided link.




What Are the Logs About: As mentioned earlier, pricing data is not stored for MT4/MT5 taker types. However, through FIX connections, both Pricing and Trading logs are available. The Trading log is particularly useful for verifying the orders received by the bridge from your Taker. It provides details on whether the order was filled, rejected, or partially filled at the bridge level, and any corresponding out messages sent back to your Taker.

Note: For taker connection type “DropCopy” there will be only one folder available as “Trading” Given that it exclusively encompasses a trading session, the naming convention follows the format DC_TakerName.

3. Feeder [🔗](#)


Where to Find the Feeder Log: Path → Monitoring → Logs → Feeder, This log file is specifically designated for your Taker types MT4 and MT5. If enabled on the backend, it will commence storing pricing data for MT4/5 takers. In the presence of both taker types (MT4 and MT5), the log file consolidates pricing data, and you can distinguish them by entering your Taker Name after downloading the file.

Note: To enable this functionality, it must be activated at the configuration level of your Centroid Bridge. This process can be facilitated from the support side.




4. Trade Statements [🔗](#)

Where to Find the Statement: Path → Monitoring → Logs → Trade Statements




What Is the Statement About: Trade Statements are automatically generated daily and saved as HTML files at the close of each trading day, provided you have Risk Accounts within your Centroid Bridge. To view a statement, you need to download it to your local machine and then open it as an HTML file. The Trade Statement adheres to the naming convention: YY/MM/DD_RiskAccountName.html.



5. System [🔗](#)

Where to Find the System Logs: Path → Monitoring → Logs → System



What Are the Logs About: The System Log encompasses all changes made at the bridge level, recording any addition or modification to its components. In addition to these changes, it also keeps a record of all trades, regardless of whether they belong to the A book or B book. You have the option to download the system logs, and you can read them using a simple text editor like Notepad.

System logs can be categorized into different types, classified as follows:

- [I] → Info
- [W] → Warning
- [E] → Error
- [D] → Debug
- [T] → Trace

Note: The System Log is typically stored as one log file for an entire day.

Centroid
BRIDGE

Search...

Ctrl+k

Operations

Risk Accounts

Risk Users

Trade Copier

Giveup Rule

Filtration Pool

Action Scheduler

Risk Management

Trading

Monitoring

Logs

Logs

makers

takers

feeder

trade statements

downloads

system

system.log

20231207_122600_system.log

20231207_122500_system.log

20231207_121000_system.log

20231207_000000_system.log

20231206_000000_system.zip

20231205_135200_system.zip

20231205_132300_system.zip

20231205_000000_system.zip

Maker Status

Overview [↗](#)

The Maker Status component provides real-time health into the connectivity with Makers to ensure that Maker Sessions are connected at all times in addition to providing statistical data about the connection in addition to prices and execution for each Maker on a per Symbols basis.

Maker Status [↗](#)

The Maker Status monitoring tool provides real-time visibility over the different sessions i.e. Feeding and Trading of different Makers to determine whether the session is connected or not. It also provides statistical data in terms of exchange from and into the Centroid Bridge.

Makers	Status	STime	Logged In	Received Count	Sent Count
Liquidity Provider 2 - Feeding	ENABLED	WITHIN TIME	CONNECTED	1,779,764	1,279
Liquidity Provider 2 - Trading	ENABLED	WITHIN TIME	CONNECTED	3,190	3,190

Field	Description
Maker	The Maker's name can be configured either as a single session encompassing both Feeding and Trading, or as two separate sessions—Feeding and Trading—depending on the specifications of the Maker.
Status	Indicates the status of the connection: • Enabled: If the Maker is enabled from the Maker section. • Disabled: If the Maker is disabled from the Maker section.
STime	Indicates whether the connection is within the defined time session: • Within Time: If the connection falls within the specified time session. • Outside Time: If the connection extends beyond the defined time session. For instance, if the Time Session is set from Monday to Friday, Saturday would be categorized as Outside Time.
Logged in	Specifies the session's connection status: • Connected: If there is an established connection between the Maker and the Centroid Bridge. • Disconnected: If there is no established connection between the Maker and the Centroid Bridge.
Received Count	The count of messages received by the Centroid Bridge from the Maker.
Sent Count	The count of messages sent by the Centroid Bridge to the Maker.

Maker Symbol Status [🔗](#)

The Maker Symbol status is a very useful real-time tool that allows checking of statistical data with each Maker on a per Symbol basis. Data are related to prices obtained from the Makers in addition to Orders that are routed to the Makers.

You need to select a combination of at least one Maker and Symbol for the report to be generated.

The report is reset every five minutes where the Centroid Bridge starts counting all over again until the next reset.

Within this module, you have the capability to:

- **Filter:** Click on the four lines next to the Maker and select the desired Maker.
- **Select/Tick Security or Symbol:** Choose a Security or Symbol by selecting or ticking the desired ones.
- **Export Report (Excel/CSV):** Save the report by exporting it to an Excel or CSV file.

Makers	Status	STime	Logged In	Received Count	Sent Count
Liquidity Provider 2 - Feeding	ENABLED	WITHIN TIME	CONNECTED	1,787,433	3,286
Liquidity Provider 2 - Trading	ENABLED	WITHIN TIME	CONNECTED	3,197	

Makers	Symbol	Sub ID	Subscribed	Ticks Count	Avg Spread	Avg Spread in Points	Spread Ticks Count	Delayed Ticks Count	Skipped Ticks Count	Consumed Ticks Count	Orders Count	Long Orders
Liquidity Provider 2	EURUSD	EURUSD	☐	0	0	0	0	0	0	0	0	0
Liquidity Provider 2	XAUUSD	XAUUSD	☐	704	0.662	662	704	0	0	704	0	0

Field	Description
Maker	The name of the Maker.
Symbol	The name of the Symbol under a specific security.
Sub ID	The Symbol's market data subscription ID that is sent to the Maker upon subscription.
Subscribed	Indicates whether we are subscribed to the Symbol with the Maker or not. • If ticked, it means we are subscribed to the Symbol. • If un-ticked, it means we are not subscribed to the Symbol.
Ticks Count	The number of Ticks or prices updates received for that Symbol during the 5-minute time interval. Note: If Ticks says "0" that means the respective Maker is not pricing.
Avg Spread	The Average Spread of the Symbol in decimal.
Avg Spread in Points	The Average Spread of the Symbol in points.
Spread Ticks Count	The number of Ticks or prices updates received for that Symbol based on which the average spread was calculated during the current time interval.
Delayed Ticks Count	The number of Ticks or prices updated that were delayed.
Orders Count	The total number of Orders executed with the Maker during the time interval irrespective of the Order Size. In other words, if executed Order is counted as 1 no matter what the Volume is.
Long Orders	The total number of Long Orders executed with the Maker during the time interval irrespective of the Order Size.
Short Orders	The total number of Short Orders executed with the Maker during the time interval irrespective of the Order Size.
Avg Fill Time	The Average Fill Time in microseconds of all Orders that were executed during the current time interval.

Avg Travel Time	The Average Time in microseconds it takes the Order to travel from the Centroid Bridge to the Maker.
Rejected Count	The number of rejected Orders.
Partial Fills Count	The number of Orders that resulted in partial fills.
Fully Fills Count	The number of Orders that were fully filled.
Total Till Volume	The total notional Volume executed with the Maker during the 5 minute time interval.
Average Slippage	The Average Slippage in decimals of all executed Orders.
Average Slippage Points	The Average Slippage in points of all executed Orders.

Taker Status

Overview [🔗](#)

The Taker Status component offers a live health assessment of all Pricing and Trading connections across all Takers. It serves as a valuable tool for diagnosing and resolving connectivity issues between Takers and the Centroid Bridge.

The Taker Status is categorized into three sections:

- Trading Status
- Depth Feeding Status
- Feeder Status



Session Type	Taker Type	Connection Status
Trading Status	FIX & MT5, MT4	Trading Connection Status
Depth Feeding Status	FIX Clients only	Pricing Connection Status
Feeder Status	MT5 and MT4 Clients only	Pricing Connection Status

Field	Description
Taker	The name of the Taker which could be set up as one session combining both Feeding and Trading or two separate sessions for each, Feeding and Trading.
Status	Shows the Status of the connection. • Enabled: If Taker is enabled from Taker section. • Disabled: If Taker is disabled from Taker section.
STime	Indicates whether the connection is within the defined time session. • Within Time: If the connection is within the defined time session. • Outside Time: If the connection is outside the defined time session. Example: If Time Session is from Monday to Friday, then Saturday would show Outside Time.
Logged in	Indicates whether the session is connected or not. • Connected: If there is an established connection between the Taker and the Centroid Bridge.

	Disconnected: If there is no established connection between the Taker and the Centroid Bridge.
Received Count	The number of messages received by the Centroid Bridge from the Taker.
Sent Count	The number of messages sent by the Centroid Bridge to the Taker.

Feeder Status [🔗](#)


The Feeder Status component oversees the status and health of feeders associated with Takers of MT4, MT5, or Centroid types, presenting relevant statistics in real time. Moreover, it enables users to inspect all the symbols to which Takers are subscribed on a per Taker basis.


Field	Description
Taker	The name of the Taker
IP	The IP of the Server on which the feeder/ platform (MT4 or MT4) is installed
Last Ping	The last Date and Time the Feeder was pinged successfully
Received Count	The number of messages received in the Centroid Bridge from the Taker which mainly consist of subscription to Symbols
Sent Count	The number of messages sent by the Centroid Bridge to the Taker mainly the ticks pertaining to the quotes streamed into the Taker via Taker Feeds
Subscription List	Allows to check all the Symbols the Taker is subscribed to, by clicking the button next to the desired Taker

Subscription List Check [🔗](#)

To review the list of symbols to which Takers are subscribed:

1. Click on the "Subscription List" next to the desired Taker.
2. In the pop-up window displaying the list of all subscriptions, enter one or multiple values (comma-separated) into the search box. You can input either the full symbol name or a part of it. The symbols matching the criteria will be highlighted in yellow.





Alerts

Overview [↗](#)


The Alerts feature enables users to review issues or incidents that occurred on the Centroid Bridge within a specified time frame. These issues are categorized into three levels, indicating the severity of the incidents.

To access Alerts, click on the alert icon located at the top of the page, as illustrated below:

Request Alert Report [↗](#)

To request an Alert Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. Click **"View Results"** to execute the report or **"Export to CSV or Excel"** file.





Field	Description
Start Date	The Start Date of your desired time interval.
End Date	The End Date of your desired time interval.
Urgency	This indicates the severity of the Alert as explained below: • Critical: Critical Alert such as a major error that occurred in the Centroid Bridge. • Event: Warning about a misconfiguration that could lead to errors. • Information: General information in the Centroid Bridge such as session Login.

Display Alert Report [↗](#)

Once the Alert Report has been generated, you can do the following


1. **Filter** by different columns to look up a particular **"Alert"**
2. Click the **"Export"** button to export the list of Alerts to an **"Excel file"** or a **"CSV file"**



Field	Description
Urgency	This indicates the severity of the Alert as explained below: • Critical: Critical Alert such as a major error that occurred in the Centroid Bridge. • Event: Warning about a misconfiguration that could lead to errors. • Information: General information in the Centroid Bridge such as session login.
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge.
Headline	An informative log message explaining the nature of the Alert.
Time	The Date and Time at which the Alert occurred.

Exporting the Alerts [↗](#)

Click **“Export”** and select **“Export to Excel”** or **“Export to CSV”**



Telegram: How to configure alerts

Overview [↗](#)

A lot of companies started utilizing telegram as one of their main channels to monitor systems and receive notifications or alerts. Within the telegram messaging platform, a bot tool can be created to enable automated interactions with users via text commands. The Telegram Bot API facilitates bot delivering messages which Centroid Solutions integrated into our Centroid Bridge. This integration empowers real-time alerting for critical events, enhancing responsiveness and communication for bridge broker administrators.

Main Requirements [↗](#)


1. Dedicated Telegram Bot
2. Bot Token ID
3. User ID

Important notes:

1. Only 1 telegram bot is required per company
2. Company users must subscribe to the telegram bot that you created
3. Company users are required to retrieve their personal User ID number
4. Company users are required to configure their profile with the token and their User ID


Creating a Telegram bot and retrieving Token ID [↗](#)

1. Download and install Telegram then register for an account
2. To create a bot, search for [@BotFather](#)
3. Click on Start then type **/newbot**
4. Give your bot a unique company name and create a unique username (e.g., Centroid Bridge FXBroker with username CBFXBroker_Bot)
5. Upon confirmation that the bot has been created, retrieve the **token ID**
6. Save the "token ID" for later configuration




Warning: The above bot name is only an example. Please do not copy it to avoid having the same bot name with other Brokers or Centroid Clients.

A quick guide on how to create a bot




Retrieving your User ID

1. Download and Install Telegram then register for an account
2. Search for @userinfobot
3. Click Start then retrieve your UserID number
4. Save the "User ID" for later configuration



Subscribing to your Company's Telegram Bot [🔗](#)

1. Download and Install Telegram then register for an account
2. Search for the **name or username** of the bot that your company created for the Bridge alerts
3. Click Start to subscribe and receive alerts




Configuring Telegram Bridge Alerts [🔗](#)

1. Login to bridge
2. On the left lower pane, click on Account
3. Within the account, click on "Update your profile"
4. Go to "Telegram Notification"
5. Add the Bot Token ID & User ID following the below format

Example only:

7110000034:AAGg4No0000Q2sJKnx9s5_ifRc00000Nfk;920000052



Slack: How to configure Alerts

Overview [↗](#)

Slack is a cloud-based communication and collaboration platform designed for teams to streamline messaging, share files, and integrate with various productivity tools including custom applications for automation. Within the Slack application, a bot app can be created to enable automated interactions with users via text commands. The Slack Bot API facilitates bot delivering messages which Centroid Solutions integrated into our Centroid Bridge. This integration empowers real-time alerting for critical events, enhancing responsiveness and communication for bridge broker administrators.

Main Requirements [↗](#)

1. Dedicated Slack App for Bot
2. Bot OAuth Token
3. Channel ID

Important notes:

1. Only 1 Slack app bot is needed per company
2. For the public channel, any users within the company can join the channel
3. For the private channel, the administrator must add their employees to the channel

Creating a Dedicated Slack App (bot) and retrieving Bot OAuth Token [↗](#)

1. Download and install Slack then register for an account
2. Go to <https://api.slack.com/apps>
3. Click on "Create an App"
4. Select "From an app manifest"
5. Select your workspace
6. Select "YAML" then clear the script
7. Add the below Script


YAML

```
display_information:
  name: Centroid Bridge
features:
  bot_user:
    display_name: Centroid Bridge
    always_online: false
oauth_config:
  scopes:
    bot:
      - chat:write
      - chat:write.public
settings:
  org_deploy_enabled: false
  socket_mode_enabled: false
  token_rotation_enabled: false
```

8. Click "Next" then "Create"
9. Click "OAuth & Permissions"

10. Click on "Install to Workspace" then "Allow"
11. Click on "Copy" to copy the Bot User OAuth Token
12. Save the "Bot User OAuth Token" for later configuration


A quick guide on how to create a Slack App (bot) [🔗](#)



Creating a Channel and Retrieving Channel ID [🔗](#)

1. Go to Slack Application
2. On the lower left pane, click on the plus + icon
3. Select Channel
4. Name the channel
5. You can select the visibility and privacy of the channel
 - Public - anyone in your workspace can join the channel
 - Private - Only specific of invited people can join the channel (please refer below for additional steps)
6. Click on the channel name to access its information
7. Scroll down and copy the "Channel ID"
8. Save the "Channel ID" for later Configuration


A quick guide on how to create a public channel [🔗](#)



Channels with “Private” visibility settings [🔗](#)

1. Bot App is required to join or be added to the channel
2. Click on the channel name
3. Click on “Integrations” then “Add an App”
4. Search for the “Centroid Bridge” app then “Install”

A quick guide on how to create and configure a private channel [🔗](#)



Configuring Slack Bridge Alerts [🔗](#)

1. Login to bridge
2. On the left lower pane, click on Account
3. Within the account, click on "Update your profile"
4. Go to "Slack Notification"
5. Add the Bot User OAuth Token & Channel ID following the below format

Example only:

xoxb-6676000001859-6600000004022-bd7Gx0000000Y0NYj7w8uV7r;C06L000007B


Slack Notification

xoxb-6676000001859-6600000004022-bd7Gx0000000Y0NYj7w8uV7r;C06L000007B

Margin Level Alerts

Overview [🔗](#)


The Margin Level Alerts module facilitates users in examining margin level movements or incidents that transpired on the designated Risk Account within the Centroid Bridge during a specified time interval. These alerts activate when the margin of the designated risk account falls below the predefined Warn Level in the Account Group > Risk Account settings.



Request Margin Level Alerts Report [🔗](#)

To request a Margin Level Alerts Report

1. Click on the "Toggle here to search" button.
2. Complete the Wizard as detailed below.
3. Click "View Results" to execute the report or "Export to CSV or Excel" file.



Field	Description
Start Date	The Start Date of your desired time interval.
End Date	The End Date of your desired time interval.
Risk Account	Select the specific Risk Account

Display Margin Level Alerts Report [🔗](#)

Once the Margin Level Alerts Report has been generated, you can see the following

MARGIN LEVEL ALERTS				
Toggle here to search				
Total Records: 2				
Risk Account	Margin Level	Warn Level	Warn Level Config	Time
Risk Account-1	0.73	<80	80,90,100	11-10-2023 21:40:14
Risk Account-2	0.73	<80	80,90,100	06-09-2023 09:11:31

Field	Description
Risk Account	This column identifies the particular Risk Account referenced.
Margin Level	Within this column, you will find the margin level corresponding to the specific risk account at the time of the incident.
Warn Level	This column serves to specify the Warn level at which the Alert was triggered for the particular risk account.
Warn Level Config	Imprinted within this column is the configured Warn Level at the Risk Account level.
Time	This column precisely notes the occurrence time of the incident.

Exporting the Margin Level Alerts

Click on “Export to CSV” or “Export to Excel” to export the report

MARGIN LEVEL ALERTS				
Toggle here to search				
Total Records: 2				
Risk Account	Margin Level	Warn Level	Warn Level Config	Time
Risk Account-1	0.73	<80	80,90,100	11-10-2023 21:40:14
Risk Account-2	0.73	<80	80,90,100	06-09-2023 09:11:31

Dividends Completed Jobs



Page is under
construction



Reports

Centroid provides over 25 detailed reports, empowering clients to efficiently track their market exposure. Stay informed and make informed decisions with our comprehensive reporting tools.

Positions

Overview [🔗](#)

The Positions report offers an up-to-the-minute summary of the aggregate open positions within one or more Risk Accounts, Taker Execution Models, or a combination thereof. The report presents positions on a per-Account and per-Symbol basis.


This report allows Brokers to effortlessly monitor all net open positions and employ filtering options to examine those associated with a specific Risk Account or Taker Execution Model.

Request a Position Report [🔗](#)

To request a Position Report:

1. Click on the "**Toggle here to search**" button.
2. Complete the **Wizard** as detailed below.
3. Click on the "**Search**" button to execute the report.

Note: Use the Reset button to clear the pre-defined filters




Field	Description
Symbol	Select one or multiple Symbols
Taker	Select one of multiple Takers
Type	The Type of Account • Taker Execution Model: To check the Open Positions of one or multiple Taker Execution Models and/or Makers • Risk Account: To Check the Open Positions of a Risk Account which may contain one or multiple Taker/Taker Execution Models • All Models: A combination of both Risk Accounts and Taker Execution Models and/or Makers
Taker Execution Model	Select one or multiple Risk Accounts, Taker Execution Models, Makers or a combination of all, depending on the Type selected in the previous field

Note: If the above fields are left empty, all values pertaining to the above fields will be included in the search

Display Position Report [🔗](#)


After generating the Position Report, you can perform the following actions

The Positions Report is displayed on a per Risk Account/Taker Execution Model and Symbol basis.



Within the Position Report, you have the capability to:

1. Click the "Columns" button to add and display additional columns related to Positions, which are initially hidden.
2. Apply various arithmetic and logical conditions to filter columns.
3. Export the Maker Positions Report to identify any disparities between actual Trades and Net Positions on the Maker's side, potentially resulting from a Centroid Bridge crash or unplanned restart.
4. Verify discrepancies between Trades and Net Open Positions on the Maker's side.
5. Export the Taker Positions Report to examine any inconsistencies between actual Trades and Net Positions on the Taker's side, possibly stemming from a Centroid Bridge crash or unplanned restart.
6. Verify discrepancies between Trades and Net Open Positions on the Taker's side.
7. Export the list of Open Positions to an Excel or CSV file.
8. Click the arrow button to view the list of Orders comprising the Positions. This feature is relevant to Risk Accounts only.
9. Click the "Refresh" or the right arrow button to update the Positions and access real-time information.



Field	Description
Pos ID	The ID number of the Position
Symbol	The Symbol that has the open position
Taker Execution Model	The Taker Execution Model that has the open position. Note: All B Book orders that were not processed by any Makers will display B_BOOK in this column
Taker	The Taker under which the Taker Execution Model is set up.

Risk Account	The name of the Risk Account that holds the open position Note: This column would appear only if requested Type is Risk Account. If Type is Taker Execution Model or All Models, this column would display an empty value
Account Type	The type of Account that holds the open position • Client: If position belongs to a client, Taker/Risk Account • Provider: If the position belongs to a Maker or B Book
Liquidity Model	The Liquidity Model assigned to the Trading Account which specifies the Maker(s) the open position is held with
Net Volume	The Net Open Positions in notional value. • Short Symbols show a negative value and are highlighted in Red • Long Symbols show a positive value and are highlighted in Blue
ANet Volume	The Net Open Positions of all STP trades in notional value
BNet Volume	The Net Open Positions of all B Book trades in notional value
Avg Price	The Weighted Average Price of all deals that form the position
AAvg Price	The Weighted Average Price of STP Position
BAvg Price	The Weighted Average Price of B Book Position
Last Time	The Last Time the real-time data of the Position were updated
Close Price	The current Market Price
PL	The current floating (unrealized) P/L which is the difference between Close Price and Avg Price multiplied by Net Volume
Margin	The current Blocked Margin of the Position
Swaps	This is relevant to Position pertaining to a Risk Account and shows accumulated Swap charges that have been charged on Open Positions
Commission	This is relevant to Position pertaining to a Risk Account and shows commission charges that have been charged on Open Positions
Base Exposure	The Notional Volume in Base Currency
Quote Exposure	The Notional Volume in Quote Currency
Base Cur Exposure	This Base Volume converted into Risk Account Currency Note: For Positions that do not correspond to a Risk Account, it will show exactly the same value as Base Exposure
Quote Cur Exposure	The Quote Volume converted into Risk Account Currency Note: For Positions that do not correspond to a Risk Account, it will show exactly the same value as Quote Exposure
BBase Exposure	The Notional Volume in Base Currency of the B Book Positions

BQuote Exposure	The Notional Volume in Quote Currency of the B Book Positions
BBase Cur Exposure	This Base Volume of the B Book Positions converted into Risk Account Currency Note: For Positions that do not correspond to a Risk Account, it will show exactly the same value as BBase Exposure
BQuote Cur Exposure	The Quote Volume of the B Book Positions converted into Risk Account Currency Note: For Positions that do not correspond to a Risk Account, it will show exactly the same value as BQuote Exposure
Markup	The Markup in decimal, if any, that was applied to the Open Positions
Margin Conv Rate	The Margin Conversion rate from Base Currency into USD
PL Conv Rate	The Profit Conversion rate from Quote currency into USD
Actions	Allows to check the Orders that make up the Position, in the event of having an aggregated position, and perform closing actions and adjustments for accounting purposes Note: This is only relevant to Positions pertaining to Risk Accounts

As indicated in the preceding step, you have the option to expand the Position further to inspect the various Orders beneath that constitute the Position.

POSITIONS

Toggle here to search

Total Records: 6

0.04%310.00%

≡⌵⌶⌷

Pos ID	Symbol	Taker Symbol	Taker Execution Model	Taker	Taker Feed	Risk Account	Account Type	Liquidity Model	Net Volume	A Net Volume	B Net Volume	Avg Price	A Avg Price	B Avg Price	Last Time	Close Price	PL	Margin	Notional	Swaps	Commission	Actions
947	GBPJPY		Centroid_L	Centroid2_			CLIENT	CS24UAT_	11,000	0	11,000	183.886	0	183.886	05-07-2023 00:40:00.0792...	183.854	-5.44	139.94	13,993.65	0	0	
949	APPLE		Centroid_L	Centroid2_			CLIENT	CS24UAT_	6.21	0	6.21	191.67	0	191.67	05-07-2023 00:39:11.0664...	191.68	0.08	15.74	1,573.61	0	0	
946	EURUSD		Centroid_L	Centroid2_			CLIENT	CS24UAT_	211,000	0	211,000	1.0896	0	1.0896	05-07-2023 00:39:10.9060...	1.0897	15.11	13,187.31	1,318,730...	0	0	
953	> GBPJPY	GBPJPY	Centroid_L	Centroid2_	plain_feed	Cen_Demo	CLIENT	CS24UAT_	11,000	0	0	183.874	0	0	05-07-2023 00:40:07.5152...	183.855	-15.71	165.38	16,537.82	0	0	
952	▼ EURUSD	EURUSD	Centroid_L	Centroid2_	plain_feed	Cen_Demo	CLIENT	CS24UAT_	278,000	0	0	1.08995	0	0	05-07-2023 00:39:17.8503...	1.08906	140.58	13,916.78	1,391,678.1	0	0	

Seq ID	Cen Ord ID	Price	Volume	Time	Actions
18473	487352		1,08859	11000	
18475	487356		1,08882	1000 05-07-2023 00:32:56.901333	
18476	487357		1,08882	10000 05-07-2023 00:33:02.807202	
18477	487358		1,08879	10000 05-07-2023 00:33:25.199158	
18478	487359		1,08879	10000 05-07-2023 00:33:26.939012	
18479	487360		1,08879	10000 05-07-2023 00:33:28.796156	
18480	487361		1,08879	15000 05-07-2023 00:33:41.085604	

951	> APPLE	APPLE	Centroid_L	Centroid2_	plain_feed	Cen_Demo	CLIENT	CS24UAT_	13.29	0	0	191.65	0	0	05-07-2023 00:39:17.8212...	191.69	6.59	25.34	2,533.61	0	0	
-----	---------	-------	------------	------------	------------	----------	--------	----------	-------	---	---	--------	---	---	-----------------------------	--------	------	-------	----------	---	---	--

Field	Description
Seq ID	A sequential ID number of the Order
Cen Ord ID	The Centroid Bridge Order ID of the Order
Price	The Price at which the Order was opened
Volume	The Notional Volume in Base Currency of the Order. The Volume decreases when another Order of opposite side is placed using the FIFO mode
Time	The Date and Time at which the Order was opened
Actions	Allows to close an Order to decrease the overall Position. This does not send the Order to processing. It merely closes it on the Centroid Bridge for Accounting purposes

Position Upload [🔗](#)

The functionality to upload positions is provided for **Risk Account** and the **Taker Execution Model (TEM)**.


- **Risk Account:**

The **Risk Account Position Upload** feature can be utilized when you want to **increase or decrease** the exposure or volume.

- **TEM:**

The **TEM Position Upload** feature can be utilized to **replace** the existing values with new ones.


For more detailed information, please refer to the following pages within the Positions section:



Exporting the Positions Report [🔗](#)

To Export the Position Report

Click on “Export to CSV” or “Export to Excel” to export the report




Risk Account Position Upload

Overview [🔗](#)


In this module, you will learn how to upload positions using the Upload Feature for Risk Accounts. Also when uploading positions, it is strongly recommended to use the correct template to prevent errors.

Guide to Uploading Positions in Risk Accounts [🔗](#)

1. Select the Risk Account Template from the drop-down list.
2. Click the Download icon to obtain the template.



3. Complete the Excel file using the field descriptions below.
4. Upload the completed file to the Bridge.



Field	Possible Values	Description
Symbol	<i>EURUSD</i>	The name of the Symbol as defined under Symbols
Taker Symbol	<i>EURUSD.a ma</i>	The name of Taker Symbol which is allocated for the particular Taker
Taker Execution Model	<i>TEM-1</i>	The name of the Taker Execution Model where the exposure needs to be adjusted & is linked to the specific Risk Account
Taker	<i>Centroid_M T5</i>	The name of the Taker for which the exposure needs to be adjusted & is linked to the specific Risk Account
Taker Feed	<i>Test_Feed</i>	The name of the Taker Feed linked to this Risk Account
Risk Account		The name of the Risk Account for which the exposure needs to be adjusted
Liquidity Model	<i>Liquidity_M odel</i>	The Liquidity Model linked to the Execution Model
Net Volume	<i>10,000</i>	The Net Open Positions must be the sum of ANet and BNet Volumes
ANet Volume	<i>5,000</i>	The volumes to be adjusted (added/deducted) for the A Book Positions.
BNet Volume	<i>5,000</i>	The volumes to be adjusted (added/deducted) for the B Book Positions.

Avg Price	1.08644	The Weighted Average Price of all deals that form the position
AAvg Price	1.08114	The Weighted Average Price of A Book Position
BAvg Price	1.08644	The Weighted Average Price of B Book Position
Close Price	1.07094	The expected close price for this position. Note: The close price will be overridden by the current market price. This field will be useful during market close hours to provide an estimated P&L.

Notes:

- To increase exposure or volume: Enter the amount to be Added in the Excel sheet.
- To decrease exposure or volume: Enter the amount to be Deducted using a negative value.

 Please exercise caution, as changes made after the upload cannot be undone.


TEM Position Upload

Overview [🔗](#)

In this module, you will learn how to upload positions using the Upload Feature for Taker Execution Model. Also when uploading positions, it is strongly recommended to use the correct template to prevent errors.


Guide to Uploading Positions in TEM [🔗](#)

1. Select the Taker Execution Model Template from the drop-down list.
2. Click the Download icon to obtain the template.



3. Complete the Excel file using the field descriptions below.

Upload the completed file to the Bridge.



Field	Possible Values	Description
Symbol	<i>EURUSD</i>	The name of the Symbol as defined under Symbols
Taker Execution Model	<i>TEM-1</i>	The name of the Taker Execution Model where the exposure needs to be adjusted
Taker	<i>Centroid_M T5</i>	The name of the Taker for which the exposure needs to be adjusted
Liquidity Model	<i>Liquidity_Model</i>	The Liquidity Model linked to the Execution Model
Net Volume	<i>10,000</i>	The Net Open Positions must be the sum of ANet and BNet Volumes
ANet Volume	<i>5000</i>	The volumes to be adjusted (added/deducted) for the A Book Positions.
BNet Volume	<i>5000</i>	The volumes to be adjusted (added/deducted) for the B Book Positions.
Avg Price	<i>1.08644</i>	The Weighted Average Price of all deals that form the position
AAvg Price	<i>1.08114</i>	The Weighted Average Price of A Book Position
BAvg Price	<i>1.08644</i>	The Weighted Average Price of B Book Position

Close Price	1.07094	The expected close price for this position. Note: <i>The close price will be overridden by the current market price. This field will be useful during market close hours to provide an estimated P&L.</i>
-------------	---------	--

Notes:

- The uploaded file will overwrite all existing values for the TEM

 Please exercise caution, as changes made after the upload cannot be undone.

Orders

Overview [↗](#)

The Orders Report offers a summary of an order blotter, presenting a comprehensive view of all individual orders placed through the Centroid Bridge, originating from various Takers like: MT4, MT5, FIX, and others.

Much like the Trading section, the Orders Report features two distinct views: Broker and Trader.

You have visibility over all Orders originating from different Takers connected to the Centroid Bridge. Brokers can search and retrieve Orders using different search and filtration criteria.

Request Order Report [↗](#)

To request an Order Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge
TEM	Taker Execution Model(s) through which the Order was executed

Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any
Grid Columns	Columns or data fields that will be available in the report Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display Order Report [🔗](#)

After generating the Orders Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot shows the 'Orders Report' interface. On the left, there are search filters for Start Date, End Date, Ext Client Login, Ext Order ID, Ext Client Group, and Ext Order ID. Below these are buttons for 'View Results', 'Reset', 'Export to CSV', and 'Export to Excel'. In the center, there are sections for 'Symbol' (listing various currency pairs like AUD200, D30, etc.), 'Taker' (set to 'Centroid_MT4'), and 'Risk Account'. Below these are 'Grid Columns' and 'TEM' (set to 'TEM-1'). At the bottom, there is a table titled 'ORDERS Total Records: 2' with columns: Client Ord Id, Cen Ord Id, Recv Time, Taker, Symbol, Side, Volume, Price, Fill Volume, Notional, Avg Price, and Fill State. The table contains two rows of data.

Client Ord Id	Cen Ord Id	Recv Time	Taker	Symbol	Side	Volume	Price	Fill Volume	Notional	Avg Price	Fill State
CE929215002NU86...	517085	21-11-2023 12:05:58.723...	Centroid_MT4	EURUSD	BUY	1,000	1,000	0	1,000	1,094.38	1,09438 FILLED
CE929215002NU86...	517083	21-11-2023 12:03:23.096...	Centroid_MT4	EURUSD	BUY	1,000	1,000	0	1,000	1,094.27	1,09427 FILLED

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Name of the MT4/MT5 Group from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will show an empty value
Ext Order ID	Ticket number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Recv Time	The Time at which the Order was received and processed in the Centroid Bridge
Taker	The Taker that initiated the Order
Taker Execution Model	The Trading Execution Model used for executing the order
Symbol	The universal symbol in the bridge

Taker Symbol	The traded Symbol on Taker's end
Liquidity Model	The Liquidity Model used for execution
Side	The side of the Order; Buy or Sell
Ord Type	The type of the Order; Market, Limit or Stop
Volume	The requested Volume of the Order
Price	Requested or Desired Price, in case of Limit or Stop Orders. For Market Orders, it will be 0 as the Order is executed at the Market Price
Fill Volume	The actual filled Volume of the Order. - Fully Filled Orders have Full Volume equal to Volume - Partially Filled Orders have Fill Volume less than Volume - Rejected Orders have 0 Volume as no Volume was executed
Notional Volume	The Notional Volume of the filled order in USD
Avg Price	The Weighted Average Price in case the Order was split into multiple legs
Fill State	The State of the Order: - Filled: Indicates a full fill of the Order - Partial: Indicates a partial fill of the Order - Rejected: Indicates an Order rejection
Slippage	The Slippage in decimal value which results due to price difference between request price and filled price. Slippage is the difference between the fill price and the requested price
Ext Markup	This is relevant to MT4/MT5 Takers and consists of the Markup at the level of MT4/MT5 group in decimal points
B%	The B Book percentage of the Order
A Vol	The requested A Book volume
B Vol	The requested B Book volume
A Fill	The filled A Book Volume
B Fill	The filled B Book Volume
Sender	The Taker through which the Order was initiated
Exec Time (ms.mic)	Order Execution Time in milliseconds and microseconds

Exporting the Order Report [↗](#)

To Export the Order Report

Click on **“Export to CSV”** or **“Export to Excel”** to export the report

Centroid
BRIDGE

Search...

Ctrl+k

Reports

Positions

Orders

Maker Orders

Giveup Orders

Toggle here to search

Start Date

20-11-2023 00:00:00

End Date

24-11-2023 23:59:59

Ext Client Group

comma separated for multiple values

View Results

Reset

Export to CSV

Export to Excel

Ext Client Login

comma separated for multiple values

Ext Order ID

comma separated for multiple values

Cen Ord Id

comma separated for multiple values

Grid Columns

Client Ord Id

Cen Ord Id

Recv Time

Taker

Symbol

Side

Volume

Price

Fill Volume

Notional

Symbol

Taker

TEM

Risk Account

257

Maker Orders

Overview [↗](#)

The Maker Orders Report offers a comprehensive view of all STP Orders sent to the Maker(s), encompassing relevant execution details. Additionally, it includes orders that have been internalized within the Centroid Bridge as **"B Book"**

Request Maker Report [↗](#)

To request a Maker Order Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4/MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any

Maker	Select one or multiple Makers you wish to check Orders with
Grid Columns	Columns or data fields that will be available in the report

Display Maker Report [🔗](#)

After generating the Maker Orders Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot displays the Centroid Bridge application interface. On the left is a navigation menu with options like Search, Filtration Pool, Action Scheduler, Risk Management, Trading, Monitoring, Reports, Positions, Orders, Maker Orders (selected), and Giveup Orders. The main area is titled 'Toggle here to search' and contains various filters: Start Date (21-11-2023 00:00:00), End Date (21-11-2023 23:59:59), Ext Client Login, Ext Order ID, Ext Client Group, and Grid Columns (Cen Client OrdId, Maker, Price, Avg Price, Raw Avg Price, Volume). There are buttons for 'View Results', 'Export to CSV', and 'Export to Excel'. Below the filters, a table titled 'MAKER ORDERS Total Records: 3' shows order details. The table has columns: Cen, Maker, Price, Avg Price, Raw Avg Price, Volume, Fill Volume, Notional, Fill State, Client Ord..., Cen Ord Id, Recv Time, Taker, Symbol, Side, Volume, Price, Fill Volume, Avg Price, and Fill St... (dropdown). The data rows show orders for 'B_BOOK' and 'Liquidity Provider' with various prices and volumes.

Maker Order Details [🔗](#)

Field	Description
Cen Client Ord ID	The Leg ID of the Order which shows the Order and Leg number in the format OrderID_LegID
Maker	The Maker responsible for processing the order: • If the order is STP, the displayed name of the Maker will be as configured in the Maker • If the order is B Book, "B_BOOK" will be displayed
Price	The raw price advertised by the maker during the time of execution.
Avg Price	The price after including the markup on top of the raw price.
Raw Avg Price	The raw price at which the Maker filled the Order.
Volume	The requested Volume of the Order
Fill Volume	The actual filled Volume which could be equal or less than the requested Volume above
Notional	The Notional Volume of the filled order in USD
Filled State	The State of the Order: • Filled: Indicates a full fill of the Order • Partial: Indicates a partial fill of the Order • Rejected: Indicates an Order rejection


Order Details [↗](#)

Field	Description
Client Ord ID	Client Order ID received in the Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Bridge
Recv Time	The time at which the Order was received in the Bridge
Taker	The taker that initiated the Order
Symbol	The traded Symbol
Side	The side of the Order; Buy or Sell
Volume	The requested Volume of the Order
Price	Requested or Desired Price, in case of Limit or Stop Orders. For Market Orders, it will be 0 as the Order is executed at the Market Price
Fill Volume	The actual filled Volume of the Order. - Fully Filled Orders have Full Volume equal to Volume - Partially Filled Orders have Fill Volume less than Volume - Rejected Orders have 0 Volume as no Volume was executed
Avg Price	The Weighted Average Price in case the Order was split into multiple legs
Filled State	The State of the Order: - Filled: Indicates a full fill of the Order - Partial: Indicates a partial fill of the Order - Rejected: Indicates an Order rejection

Exporting the Maker Order Report [↗](#)

To Export the Maker Order Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report



Giveup Orders

Overview [↗](#)

The Giveup Orders Report offers a summary of all giveup orders recorded on MT4 or MT5 giveup accounts specified in the Giveup Rule module.

Request Giveup Orders Report [↗](#)

To request a Giveup Orders Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4/MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
TEM	Taker Execution Model(s) through which the Order was executed
Grid Columns	Columns or data fields that will be available in the report

Risk Account	Risk Account through which the Order was executed, if any
--------------	---

Display Giveup Orders Report [🔗](#)

After generating the Giveup Orders Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge of the Giveup Order
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge of the Giveup Order
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Group name of the MT4/MT5 Login from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will display an empty value
Ext Order ID	Ticket Number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Send Time	The Time at which the Oder was sent to the Maker
Maker	The Maker that processed the Order • If Order is STP, the name of the Maker would be displayed as configured in Maker Sessions • If Order is B Book, B_BOOK will be displayed
TEM	The Taker Execution Model through which the Order was processed
Symbol	The traded Symbol
Liquidity Model	The Liquidity Model used for execution
Side	The side of the Order; Buy or Sell
Ord Type	The type of the Order; Market, Limit or Stop
Volume	The requested Volume of the Order
Fill Volume	The actual filled Volume of the Order. • Fully Filled Orders have Full Volume equal to Volume • Partially Filled Order have Fill Volume less than Volume • Rejected Orders have 0 Volume as no Volume was executed
Notional	The Notional Volume of the filled order in USD
Avg Price	The Weighted Average Price in case the Order was split into multiple legs

Slippage	The Slippage in decimal value which results due to price difference between request price and filled price. Slippage is the difference between the fill price and the requested price
State	The State of the Order: • Filled: Indicates a full fill of the Order • Partial: Indicates a partial fill of the Order • Rejected: Indicates an Order rejection

Exporting the Giveup Order Report [↗](#)

To Export the Giveup Order Report

Click on “Export to CSV” or “Export to Excel” to export the report

The screenshot displays the Centroid Bridge application interface for the 'Giveup Orders' report. The left sidebar shows the navigation menu with 'Giveup Orders' selected. The main panel features a search bar and various filters for refining the report data, including Start Date, End Date, and client/order identifiers. At the bottom of the filter section, there are four buttons: 'View Results', 'Reset', 'Export to CSV', and 'Export to Excel'. The 'Export to CSV' button is highlighted with a red rectangular box. Below the filters, the interface shows two tabs: 'Giveup Order Details' and 'Source Order Details', each with a table of columns for data export.

Legs

Overview [🔗](#)

The Leg Report offers a detailed overview of each order, outlining the execution process and providing relevant execution details. The relationship between an order and its legs is one-to-many, as a single order may be divided into multiple legs when the order is filled in more than one attempt.

The report is divided into Leg Details and Order Details, each containing relevant fields.

Request Leg Report [🔗](#)

To request a Leg Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4/MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform

Risk Account	Risk Account through which the Order was executed, if any
Maker	Select one or multiple Makers you wish to check Orders with
Grid Columns	Columns or data fields that will be available in the report

Display Leg Report [🔗](#)

After generating the Leg Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot displays the Centroid Bridge application interface. On the left is a sidebar with navigation options: Reports, Positions, Orders, Maker Orders, Group Orders, and Legs. The main area is titled 'Toggle here to search' and contains various filter fields. A red arrow points to the 'View Results' button. Below the filters, a 'Grid Columns' dropdown menu is open, showing a list of available columns. The 'Legs' section at the bottom shows a table of 5 records. The table has columns for Cen Client OrdId, Maker, Volume, Fill Volume, Notional, Fill Price, Price, Raw Fill Price, Cen Ord Id, Recv Time, Symbol, Side, Volume, Price, Fill Volume, Avg Price, and Fill Status. The table is filtered to show 5 records.

Leg Details

Field	Description
Cen Client OrdId	The ID of the Leg. For instance, an Order split into three legs will have Leg IDs of 0, 1 and 2
Maker	The name of the Maker the Leg got it executed with • If A Book: The name of the LP that processed the Order will be displayed as configured in the Centroid Bridge • If B Book: B_BOOK will be displayed
Maker B	This is relevant to B Book Orders only and discloses the Maker that provided the quote at the time the B Book Order was executed
Time	The Date and Time at which the Leg was executed
Side	The side of the Order; Buy or Sell
Volume	The requested Leg Volume
Fill Volume	The actual filled Leg Volume which could be equal or less than the requested Volume above
Notional	The Notional Volume of the filled Leg in USD
Maker Symbol	The name of the Symbol on the Maker's side

Maker OrderID	The assigned ID of the Order returned by the Maker
Maker Cat	The Maker Category or Type
Maker ExecID	The Execution ID of the Leg assigned by the Maker
Fill Price	The fill Price the Leg got executed at including Markup
Markup	Defined Markup in decimal on top of the Price, if any
Raw Fill Price	The fill Price the Leg got executed at excluding Markup
Exec Time (ms.mic)	Order Execution Time in milliseconds and microseconds

Order Details

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Group name of the MT4/MT5 Login from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will display an empty value
Ext Order ID	Ticket Number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
TEM	The Taker Execution Model through which the Order was processed
Symbol	The traded Symbol
Liquidity Model	The Liquidity Model used for execution
Side	The side of the Order; Buy or Sell
Ord Type	The type of the Order; Market, Limit or Stop
Volume	The requested Volume of the Order
Fill Volume	The actual filled Volume of the Order. - Fully Filled Orders have Full Volume equal to Volume - Partially Filled Orders have Fill Volume less than Volume - Rejected Orders have 0 Volume as no Volume was executed
Notional	The Notional Volume of the filled order in USD
Avg Price	The Weighted Average Price in case the Order was split into multiple legs
Slippage	The Slippage in decimal value which results due to price difference between request price and filled price. Slippage is the difference between the fill price and the requested price
State	The State of the Order:

- Filled: Indicates a full fill of the Order
- Partial: Indicates a partial fill of the Order
- Rejected: Indicates an Order rejection

Exporting the Legs Report [🔗](#)

To Export the Legs Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report

The screenshot shows the Centroid Bridge application interface. On the left is a sidebar with navigation options: Reports, Positions, Orders, Maker Orders, Giveup Orders, and Legs. The main area is titled 'Toggle here to search' and contains various filters and controls. The 'Start Date' is set to '24-11-2023 00:00:00' and the 'End Date' is '24-11-2023 23:59:59'. Below these are fields for 'Ext Client Login', 'Ext Order ID', 'Ext Client Group', and 'Cen Ord Id', all with placeholder text 'comma separated for multiple values'. There are also fields for 'Symbol', 'Taker', 'Maker', 'TEM', and 'Risk Account'. At the bottom left of the main area, there are three buttons: 'View Results', 'Reset', and 'Export to CSV' (highlighted with a red box). Below these is another button 'Export to Excel' (also highlighted with a red box). A 'Grid Columns' dropdown menu is open, showing options: 'Cen Client OrdId', 'Maker', 'Volume', 'Fill Volume', 'National', 'Fill Price', and 'Price'. The status bar at the bottom left indicates 'LEGS Total Records: 0'.

Detailed Leg Report

Overview [↗](#)

A Detailed Leg Report provides a brief analysis of slippage at the Maker, Broker, and Client levels, along with profitability (resulting from markups) on a per-leg basis.

Request Detailed Leg Report [↗](#)

To request a Detailed Leg Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4 Group number for Takers of type MT4/MT5
Ext Client Login	MT4 Login number for Takers of type MT4/MT5
Ext Order ID	MT4 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
TEM	Taker Execution Model(s) through which the Order was executed
Risk Account	Risk Account through which the Order was executed, if any

Maker	Select one or multiple Makers from the list. For B Book Orders, they will be under B_BOOK Maker
Grid Columns	Columns or data fields that will be available in the report

Display Detailed Leg Report [🔗](#)

The [Detailed](#) Leg Report is divided into two sections, Leg Details and Order Details. When Order is split into multiple Legs, different Legs will be shown on one side whereas on the other side the same Order will be shown multiple times depending on the number of Legs it was split into.

Once the [Detailed](#) Leg Report has been generated, you can do the following:

1. Sort columns by ascending or descending order
2. Filter columns using a variety of arithmetic and logical conditions
3. Navigate through pages by accessing first, last, previous and next pages
4. Fit the entire report into the page
5. Auto size columns based on the column data

Leg Details

Field	Description
Cen Client OrdId	The ID of the Leg. For instance, an Order split into three legs will have Leg IDs of 0, 1 and 2
Maker	The Maker Leg got executed with or that provided the quote for B Book Orders
Send Time	The Time at which the Leg was sent to the Maker
Fill Volume	The filled Volume of the Leg
Notional	The Notional Volume of the Leg in USD
Maker Symbol	The Symbol name on Maker's side
Maker OrderID	The assigned ID of the Order returned by the Maker

Order Details

Field	Description
Client Ord Id	Client Order ID received in the Centroid Bridge
Cen Ord Id	Centroid unique Order ID recorded in the Centroid Bridge
Recv Time	The Time at which the Oder was received and processed in the Centroid Bridge
Taker	The Taker that initiated the Order
TEM	The Trading Execution Model within the Taker from where the Order was placed
Symbol	The traded Symbol

Ord Type	The type of the Order; Market, Limit or Stop
Side	The side of the Order; Buy or Sell
Fill Volume	The filled Volume of the Order
Avg Price	The VWAP Fill Price reported back to Client after the Order has been filled

Fills

Overview [🔗](#)


The Fills Report presents a detailed overview into each Legs in terms of how the Order got executed along with the relevant execution details. The relationship between Order and Leg is one to many as a single Order can be split into multiple Legs in the event in filling the Order in more than one attempt. The report is split into Leg Details and Order Details which relevant fields for each.

Request Fill Report [🔗](#)

To request a Fill Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters



Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4/MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform

Risk Account	Risk Account through which the Order was executed, if any
Maker	Select one or multiple Makers you wish to check Orders with
Maker B	This is relevant to B Book Orders only where you can check the Makers who provided the quote at the time the B Book Order was executed
Grid Columns	Columns or data fields that will be available in the report

Display Fill Report [↗](#)

After generating the Fills Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

Leg Details

Field	Description
Cen Client OrdId	The ID of the Leg. For instance, an Order split into three legs will have Leg IDs of 0, 1 and 2
Maker	The name of the Maker the Leg got it executed with • If A Book: The name of the LP that processed the Order will be displayed as configured in the bridge • If B Book: B_BOOK will be displayed
Maker B	This is relevant to B Book Orders only and discloses the Maker that provided the quote at the time the B Book Order was executed
Time	The Date and Time at which the Leg was executed
Side	The side of the Order; Buy or Sell
Volume	The requested Leg Volume
Fill Volume	The actual filled Leg Volume which could be equal or less than the requested Volume above
Notional	The Notional Volume of the filled Leg in USD

Maker Symbol	The name of the Symbol on the Maker's side
Maker OrderID	The assigned ID of the Order returned by the Maker
Maker Cat	The Maker Category or Type
Maker ExecID	The Execution ID of the Leg assigned by the Maker
Fill Price	The fill Price the Leg got executed at including Markup
Markup	Defined Markup in decimal on top of the Price, if any
Raw Fill Price	The fill Price the Leg got executed at excluding Markup
Exec Time (ms.mic)	Order Execution Time in milliseconds and microseconds

Order Details


Field	Description
Client Ord ID	Client Order ID received in the bridge
Cen Ord ID	Centroid unique Order ID recorded in the bridge
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Group name of the MT4/MT5 Login from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will display an empty value
Ext Order ID	Ticket Number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
TEM	The Taker Execution Model through which the Order was processed
Symbol	The traded Symbol
Liquidity Model	The Liquidity Model used for execution
Side	The side of the Order; Buy or Sell
Ord Type	The type of the Order; Market, Limit or Stop
Volume	The requested Volume of the Order
Fill Volume	The effective filled Volume of the Order. Fully Filled: Orders exhibit a Full Volume equivalent to the specified Volume. Partially Filled: Orders have a Fill Volume that is less than the specified Volume. Rejected: Orders show 0 Volume since no Volume was executed.
Notional	The Notional Volume of the filled order in USD
Avg Price	The Weighted Average Price in case the Order was split into multiple legs

Slippage	The Slippage in decimal value which results due to price difference between request price and filled price. Slippage is the difference between the fill price and the requested price
State	The status of the Order: Filled: Denotes complete fulfillment of the Order Partial: Denotes a partial fulfillment of the Order Rejected: Denotes rejection of the Order

Exporting the Fills Report [↗](#)

To Export the Fills Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report



MT4 Reports

Overview [↗](#)

The MT4 Report enables users to review all MT4 Orders generated by any MT4 Taker within the Centroid Bridge. It provides a comprehensive display of these orders as they appear in MT4, along with pertinent execution details.

Request MT4 Report [↗](#)

To request an MT4 Report:

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any

Grid	Columns or data fields that will be available in the report
Columns	Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display MT4 Report [↗](#)

After generating the MT4 Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot shows the MT4 Reports interface. At the top, there are search filters for Start Date, End Date, Ext Client Group, Ext Client Login, Ext Order ID, Cen Ord Id, Symbol, Taker, and Risk Account. Below these are buttons for 'View Results', 'Reset', 'Export to CSV', and 'Export to Excel'. A 'Grid Columns' dialog box is open, showing a list of columns: Client Ord Id, Cen Ord Id, Ext Client Login, Ext Client Group, Ext Order ID, Open Time, Taker, Taker Execution Model, and Symbol. Below the dialog, a table of MT4 Reports is displayed with columns: Client, Cen, Ext Client, Ext Order, Open Time, Taker, Taker Ex., Symbol, Taker Sp., Side, Ord Type, Time in F., Volume, Fill Volume, Open Price, Close Vol., Close Price, Close Time, State, and Exec Tim. The table contains one row of data.

Client	Cen	Ext Client	Ext Order	Open Time	Taker	Taker Ex.	Symbol	Taker Sp.	Side	Ord Type	Time in F.	Volume	Fill Volume	Open Price	Close Vol.	Close Price	Close Time	State	Exec Tim.	
205949148...	517129	212121	Real/Support	5589169	22-11-2023 ...	Centroid_MT4	TEM-2	EURUSD	EURUSD	BUY	MARKET	IOC	1000	1000	1.09006	1000	1.09	22-11-2023 ...	FILLED	10:55:19


Field	Description
Client Ord ID	The Client (Taker) Order ID
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	The Login number of the MT4 Account
Ext Client Group	The name of the MT4 Group
Ext Order ID	MT4 ticket number
Open Time	The Time at which the MT4 Order was opened
Taker	The name of the MT4 Taker that initiated the Order
Taker Execution Model	The name of the TEM through which the Order was routed
Symbol	The traded Symbol
Taker Symbol	The Symbol name on the Taker's side
Side	The side of the Order; Buy or Sell
Ord Type	The category of the executed Order, whether it is Market or Limit.
Time in Force	The Fill Policy of the Order: FOK (Fill or Kill): This signifies that the Order can be entirely filled at the specified volume or canceled if full execution is not immediately possible.

	IOC (Immediate or Cancel): In this case, the Order can be partially filled with the maximum available liquidity in the market, and any remaining volume will be canceled.
Volume	The specified MT4 Volume is calculated based on the notional value, where Volume equals the product of MT4 lots and the Symbol Contract Size. Volume = MT4 Lots x Symbol Contract Size
Fill Volume	The volume that has been successfully executed and remains open for the MT4 Order.
Open Price	The Open Price of the MT4 Order
Close Volume	The Close Volume of the MT4 Order
Close Price	The Close Price of the MT4 Order
Close Time	The Time at which the MT4 Order was closed
Slippage	The Slippage in decimal which is the difference between the fill price and the requested price
State	The effective filled Volume of the Order. Fully Filled: Orders exhibit a Full Volume equivalent to the specified Volume. Partially Filled: Orders have a Fill Volume that is less than the specified Volume. Rejected: Orders show 0 Volume since no Volume was executed.
Exec Time (ms.mic)	Order Execution Time in milliseconds and microseconds

Exporting the MT4 Reports [🔗](#)

To Export the MT4 Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report



MT5 Reports

Overview [↗](#)

The MT5 Report enables users to review all MT5 Orders generated by any MT5 Taker within the Centroid Bridge. It provides a comprehensive display of these orders as they appear in MT5, along with all pertinent execution details.

Request MT5 Report [↗](#)

To request an MT5 Report:

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click "View Results" to execute the report or directly "Export to CSV or Excel" file.

Note: Use the Reset button to clear the pre-defined filters


Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any
Grid Columns	Columns or data fields that will be available in the report Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display MT5 Report [↗](#)

After generating the MT5 Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.




Field	Description
Client Ord ID	The Client (Taker) Order ID
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	The Login number of the MT5 Account
Ext Client Group	The name of the MT5 Group
Ext Order ID	MT5 Order ID Number
Open Time	The Time at which the MT5 Order was opened
Taker	The name of the MT5 Taker that initiated the Order
Taker Execution Model	The name of the TEM through which the Order was routed
Symbol	The traded Symbol
Taker Symbol	The name of the Symbol on the Taker's side.
Side	The side of the Order; Buy or Sell
Ord Type	The category of the executed Order, whether it is Market or Limit.
Time in Force	The Fill Policy of the Order: FOK (Fill or Kill): This signifies that the Order can be entirely filled at the specified volume or canceled if full execution is not immediately possible.

	IOC (Immediate or Cancel): In this case, the Order can be partially filled with the maximum available liquidity in the market, and any remaining volume will be canceled.
Volume	The specified MT5 Volume is calculated based on the notional value, where Volume equals the product of MT4 lots and the Symbol Contract Size. Volume = MT5 Lots x Symbol Contract Size
Fill Volume	The Filled Open Volume of the MT5 Order
Open Price	The Open Price of the MT5 Order
Close Volume	The Close Volume of the MT5 Order
Close Price	The Close Price of the MT5 Order
Close Time	The Time at which the MT5 Order was closed
Slippage	The slippage, represented in decimal form, indicates the variance between the fill price and the requested price.
State	The effective filled Volume of the Order. Fully Filled: Orders exhibit a Full Volume equivalent to the specified Volume. Partially Filled: Orders have a Fill Volume that is less than the specified Volume. Rejected: Orders show 0 Volume since no Volume was executed.
Exec Time (ms.mic)	Order Execution Time in milliseconds and microseconds

Exporting the MT5 Reports [↗](#)

To Export the MT5 Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report



Risk Account Statement

Overview [🔗](#)


The Risk Account Statement offers Brokers and Traders (Risk Users) a comprehensive view of Risk Accounts, allowing them to review both Trade and Account information. Moreover, the Risk Account Statement is categorized into three tabs, providing access to historical reports, statements, as well as real-time trade and account details.

Request Risk Account Statement [🔗](#)

To request a Risk Account Statement

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button
4. **Export** the statement to HTML

Note: Use the Reset button to clear the pre-defined filters




Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Risk Account	Choose a specific Risk Account from the array of Risk Accounts configured in the Centroid Bridge.

Display Risk Account Statement [🔗](#)

After generating the Risk Account Statement, you can perform the following actions

The Risk Account Statement is divided into three components: **Closed Transactions**, **Positions** and **Account Balance**



The Closed Transactions Report, positioned at the top, displays all balance transactions impacting the Risk Account Balance. This includes transactions like Deposits, Withdrawals, Realized Profit/Loss, Swaps, Commissions, and more.

Risk Account Statement

Toggle here to search

Start Date

01-10-2023 00:00:00

End Date

22-11-2023 23:59:59

Risk Account

Risk Account-1

Search

Cancel

CLOSED TRANSACTIONS

Total Records: 72

Ticket	Open Time	Volume	Notional	Amt	Type	Symbol	Cur	Open P...	Open Cmn Order	Close Time	Close P...	Close Cmn Order	Comment
37158	16-11-2023 13:15:11	2,000	1,084,44	0.20	PL	EURUSD	USD	1.08444	515894	16-11-2023 13:16:43	515897	1.0844400000000000	1.0844200000
35392	09-11-2023 13:16:05	1,000	1,068,96	0.19	PL	EURUSD	USD	1.06896	512058	09-11-2023 13:16:07	512059	1.0689600000000000	1.0688500000
35293	02-11-2023 16:05:37	1,000	1,062,04	0.19	PL	EURUSD	USD	1.06204	511459	03-11-2023 16:28:14	396338	1.07357	511475
35292	02-11-2023 16:05:23	1,000	1,062,04	0.19	PL	EURUSD	USD	1.06204	511458	03-11-2023 16:28:14	396338	1.07357	511475
35291	02-11-2023 16:04:24	1,000	1,062,32	0.19	PL	EURUSD	USD	1.06232	511456	03-11-2023 16:28:14	396338	1.07357	511475
35290	24-10-2023 09:20:52	2,000	2,128,58	0.30	PL	EURUSD	USD	1.06425	509793	03-11-2023 16:28:14	396338	1.07357	511475
35289	24-10-2023 09:20:52	2,000	2,128,58	0.30	PL	EURUSD	USD	1.06419	509792	03-11-2023 16:28:14	396338	1.07357	511475
35288	24-10-2023 09:20:47	1,000	1,064,34	0.29	PL	EURUSD	USD	1.06434	509791	03-11-2023 16:28:14	396338	1.07357	511475
35287	24-10-2023 09:20:47	1,000	1,064,25	0.30	PL	EURUSD	USD	1.06425	509790	03-11-2023 16:28:14	396338	1.07357	511475

Field	Description
Ticket	The unique ID of the balance transactions
Open Time	The Date and Time at which the balance transaction request was sent to the Centroid Bridge
Volume	This is relevant only if the balance transaction is a PL in FIFO mode where the closed Volume is shown. In case it corresponds to another type of balance transaction not related to trading such as Deposit or Withdrawal the value would be 0
Amt	The amount in USD deposited into or deducted from the Risk Account.
Type	The category of the balance transaction is identified by the following types: • PL [Profit & Loss]: Represents a closed order in FIFO mode. • Commission: Signifies the commission deducted from the Risk Account. • Swaps: Denotes swaps applied to the Risk Account. • Deposit: Indicates a transaction involving a deposit into the Risk Account. • Withdraw: Represents a withdrawal from the Risk Account. • Credit: Refers to a credit transaction, either in or out. • Other: Encompasses other types of in/out balance operations that may be conducted for balance adjustment purposes.
Symbol	The Symbol involved in the event of a balance transaction representing a closed trade. Otherwise, the field will display an empty value.
Cur	Currency of the Risk Account, USD
Open Price	The Open Price of the Order being closed, if Balance Transaction is a PL. For other Balance Transactions, this column will show 0
Open Cen Order	The Order ID of the Open Position if Balance Transaction is a PL resulting from a partial or full closing of a Position. For other Balance Transactions, this column will show an empty value
Close Time	The Close Time of the Position if Balance Transaction is a PL resulting from partial or full Position closure. For other Balance Transactions, this column will show an empty value
Close Price	The Close Price of the Order being closed, if the balance transaction is a PL. Otherwise, this column will show 0

Closed Cen Order	The Order ID for closing a Position is indicated in the case of a PL, Commission, or Swaps balance transaction. For other balance transactions, this column will display 0.
Transaction Time	The Time at which the amount resulting from Balance Transaction was added or deducted from the Account
Comment	The Comment field is either automatically generated or manually entered: • Manual: For non-trade-related transactions like Deposits, Withdrawals, Credits, and Adjustments, it will exhibit the value manually input by the user into the Comment field during the execution of account balance operations. • Automatic: For trade-related transactions such as realized PL, commissions, and Swaps, the comment is automatically populated, revealing the open and closed price of the Order. This is particularly applicable when closing two Orders against each other.
Total Commissions	The aggregate of all incurred Commissions within the specified time frame.
Total Swaps	The cumulative total of all accrued/paid Swaps within the designated time period.
Total Realized PL	The cumulative total of all Realized Profit and Loss (PL) arising from Trades throughout the chosen time period.
Total Deposits	The total accumulation of all Deposits executed in the Account within the specified time frame.
Total Withdrawal	The aggregate of all Withdrawals subtracted from the Account within the specified time frame.
Total Credit	The cumulative amount of Net Credits (in or out) within the specified time interval.

Open Positions [🔗](#)

The Open Positions tab displays the comprehensive view of all net open positions within the Risk Account, consolidated on a per-Symbol basis.

Pos ID	Symbol	Risk Account	Liquidity M...	Net Volume	A/Net Volume	B/Net Volume	Avg Price	A/Avg Price	B/Avg Price	Last Time	Close Price	PL	Margin	Notional	Swaps	Commission
1499	EURUSD	Risk Account-1	Liquidity Model	2000	0	2000	1.0664	0	1.0664	22-11-2023 12:06:36.780482	1.06993	7.06	21.728	2,172.8	0	0
1500	XAUUSD	Risk Account-1	Liquidity Model	1	0	1	1,997.62	0	1,997.62	22-11-2023 12:06:37.126412	2,003.6	5.98	19.9762	1,997.62	0	0

Total Records: 2

Total Unrealized Commissions: 0 Total Unrealized Swaps: 0 Total Unrealized PL: 13.04 Total Notional: 4,170.42

Field	Description
Pos ID	The ID number of the Position
Symbol	The Open Position Symbol
Risk Account	The name of the selected Risk Account

Liquidity Model	The Liquidity Model assigned to the Risk Account which defines the pool of Makers
Net Volume	The Notional Volume of the Position in USD
ANet Volume	The Notional Volume of the STP Position in USD
BNet Volume	The Notional Volume of the B Book Position in USD
Avg Price	The Weighted Average Price of the orders comprising the position.
AAvg Price	The Weighted Average Price of the STP orders forming the position.
BAvg Price	The Weighted Average Price of the B-Book orders forming the position.
Last Time	The Last Time the real-time data of the Position were updated
Close Price	The current market price of the symbol.
PL	The floating Profit/Loss of the symbol determined by the open positions.
Margin	The existing Utilized or Blocked Margin associated with the open positions of the symbol. This reflects the margin amount currently allocated or reserved for the symbol's open positions.
Swaps	The cumulative unrealized Swap charges applied to the open positions. This represents the total accrued swap fees on the currently active positions.
Commissions	The commissions incurred upon the initiation of the positions. This refers to the total commission charges associated with the opening of the positions.
Total Unrealized Swaps	The total of all unrealized swaps associated with open positions across all symbols. This includes the collective amount of swap charges that have accrued but not yet been realized for open positions.
Total Unrealized PL	The overall unrealized Profit/Loss (PL) of the Risk Account. This encompasses the total unrealized financial gain or loss across all open positions within the account.

Account Balance [🔗](#)

The Account Balance tab provides live updates on key Account Balance details for the Risk Account, including information on Balance, Equity, Margin, floating Profit/Loss (PL), and more.

Risk Account Statement

Toggle here to search

Start Date

01-10-2023 00:00:00

End Date

22-11-2023 23:59:59

Risk Account

Risk Account-1

Search

Reset

CLOSED TRANSACTIONS

OPEN POSITIONS

ACCOUNT BALANCE

Total Records: 1

Name	Blocked Margin	Balance	Available to Withdraw	Equity	PL	Margin Level	Commission	Swaps	Notional	Credit	Trading State
Risk Account-1	0000	0000	0000	0000	+/-	0000	0	0	0	0000	0 NEUTRAL

Field	Description
Name	The Name of the selected Risk Account
Margin Blocked	The utilized Margin amount in the Account Currency (USD). This represents the extent of Margin that has been employed in USD within the account.
Balance	The accessible balance within the Risk Account. This denotes the remaining funds that are available for trading or withdrawal after considering existing positions and any reserved margin.
Available to Withdraw	The available withdrawal amount, equivalent to the Free Margin, is calculated as follows: $\text{Available Withdraw} = \text{Equity} - \text{Margin Blocked} - \text{Credit}$ This represents the amount that can be withdrawn, factoring in the current Equity, blocked margin, and credit in the Risk Account.
Equity	The Equity of the Risk Account signifies the total current value of the account, encompassing both the open positions and available balance
PL	The floating Profit/Loss (PL) of the Risk Account represents the unrealized gains or losses associated with open positions.
Margin Level	The Margin Level Percentage for the Risk Account is calculated as follows: $\text{Margin Level} = \text{Equity} / \text{Margin Blocked} \times 100$ This percentage indicates the relationship between the account's Equity and the blocked Margin, serving as a crucial measure of risk exposure and available margin for trading.
Commission	The total unrealized Commission charged in USD on all Open Positions Note: These Commissions remain unrealized (only affect Equity) until the Position or part of the Position is closed, and then it will affect the Balance based on the closed Volume
Swaps	The total unrealized Swaps charged in USD on the Risk Account on a per Symbol basis for keeping positions overnight, if any. Note: These Swaps remain unrealized (only affect Equity) until the Position or part of the Position is closed, and then it will affect the Balance based on the closed Volume
Notional	The aggregated USD exposure of the Risk Account in Notional Volume represents the total financial commitment of the account across all positions.
Credit	The available credit extended to the Risk Account in USD, if applicable. This signifies the amount of credit that the account is currently eligible to utilize.
Trading State	The Trading State of the Risk Account is as follows: • STOPPED OUT: The Risk Account is either flat or negative, possibly resulting from a stop-out or an imbalance in the account. • MARGIN CALL: The Risk Account is under a Margin Call when the Margin Level reaches or falls below the percentage specified in the Warn Level set for the Account. • NEUTRAL: The Risk Account is adequately funded and in a neutral state.

Exporting the Risk Account Statement [🔗](#)

To Export the Risk Account Statement

Click on “**Export to HTML**” to export the statement

Risk Account Statement

Toggle here to search

Start Date

01-11-2023 00:00:00

End Date

29-11-2023 23:59:59

Risk Account

Risk Account-1

Search

Reset

CLOSED TRANSACTIONS

OPEN POSITIONS

ACCOUNT BALANCE

Total Records: 0

Name	Blocked Margin	Balance	Available to Withdraw	Equity	PL	Margin Level	Commission	Swaps	Notional	Credit	Trading State
------	----------------	---------	-----------------------	--------	----	--------------	------------	-------	----------	--------	---------------

286

Trade Transactions

Overview [↗](#)


The Trade Transaction Report serves as a comprehensive account statement, enabling Brokers to review a detailed history of all balance transactions impacting the Risk Account Balance.

This report provides valuable insights into the various financial activities that have influenced the overall balance of the account.

Request Trade Transaction [↗](#)

To request a Trade Transaction Report:

1. Complete the **Wizard** as detailed below.
2. Click the “**Search**” button



Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Risk Account	Choose a specific Risk Account from the array of Risk Accounts configured in the Centroid Bridge.

Display Trade Transaction [↗](#)

After generating the Trade Transaction, you can perform the following actions

Upon requesting the Trade Transaction, you gain visibility into a range of Balance Transactions that occurred, influencing the Risk Account throughout the chosen time interval. This feature allows you to examine and understand the diverse financial activities impacting the account during the specified duration.

Ticket	Open Time	Volume	National	Amnt	Type	Symbol	Cur	Open Price	Open Cmn Order	Close Time	Close Price	Close Cmn Order	Comment
35405	11-11-2023 05:39:05.627364	100000	111444	-117	PL	PNCUSD	USD	1.11444	512175	11-11-2023 05:39:06.347879	1.11327	512176	1.11444000000#1.1132700000
35403	11-11-2023 05:38:31.043374	100000	111444	-117	PL	PNCUSD	USD	1.11444	512173	11-11-2023 05:38:33.736732	1.11327	512174	1.11444000000#1.1132700000
35401	11-11-2023 05:34:27.624648	100000	111456	-135	PL	PNCUSD	USD	1.11456	512171	11-11-2023 05:36:44.210608	1.11321	512172	1.11456000000#1.1132100000
35101	27-10-2023 11:22:44.010300	3882000	4398228.36	-49.7738	COMMISSION	EURUSD	USD	1.07076	1141	27-10-2023 11:22:44.010300	1.07076	1141	1.07076000000#1.0707600000

Field	Description
Ticket	The unique ID of the balance transactions
Open Time	The Date and Time at which the balance transaction request was sent to the Centroid Bridge
Volume	This information is applicable specifically to balance transactions involving PL in FIFO mode, where the closed Volume is displayed. If the transaction corresponds to another type, unrelated to trading, such as Deposit or


	Withdrawal, the value will be 0.
Amt	The USD amount either deposited into or deducted from the Risk Account. This value reflects the financial impact of transactions involving deposits or withdrawals in USD.
Type	The category of the balance transaction is identified by the following types: • PL [Profit & Loss]: Represents a closed order in FIFO mode. • Commission: Signifies the commission deducted from the Risk Account. • Swaps: Denotes swaps applied to the Risk Account. • Deposit: Indicates a transaction involving a deposit into the Risk Account. • Withdraw: Represents a withdrawal from the Risk Account. • Credit: Refers to a credit transaction, either in or out. • Other: Encompasses other types of in/out balance operations that may be conducted for balance adjustment purposes.
Symbol	The Symbol involved in the event of a balance transaction representing a closed trade. Otherwise, the field will display an empty value.
Cur	Currency of the Risk Account, USD
Open Price	The Open Price of the Order being closed, if Balance Transaction is a PL. For other Balance Transactions, this column will show 0
Open Cen Order	The Order ID of the Open Position if Balance Transaction is a PL resulting from a partial or full closing of a Position. For other Balance Transactions, this column will show an empty value
Close Time	The Close Time column indicates the closing time of the position if the balance transaction is a Profit/Loss (PL) resulting from partial or full position closure. For other balance transactions, this column will display an empty value.
Close Price	The Close Price column indicates the closing price of the order if the balance transaction is a Profit/Loss (PL). Otherwise, this column will display a value of 0.
Closed Cen Order	The Order ID for closing a position is displayed if the balance transaction corresponds to a Profit/Loss (PL), Commission, or Swaps. For other balance transactions, this column will indicate 0. This differentiation helps identify the specific order involved in the closure process for relevant transactions and highlights instances where the column remains inactive for other types of balance transactions.
Transaction Time	The timestamp indicating when the amount resulting from the balance transaction was added or deducted from the account.
Comment	The Comment field is either automatically generated or manually entered: • Manual: For non-trade-related transactions like Deposits, Withdrawals, Credits, and Adjustments, it will exhibit the value manually input by the user into the Comment field during the execution of account balance operations. • Automatic: For trade-related transactions such as realized PL, commissions, and Swaps, the comment is automatically populated, revealing the open and closed price of the Order. This is particularly applicable when closing two Orders against each other.
Total Commissions	The aggregate of all incurred Commissions within the specified time frame.
Total Swaps	The cumulative total of all accrued/paid Swaps within the designated time period.
Total Realized PL	The cumulative total of all Realized Profit and Loss (PL) arising from Trades throughout the chosen time period.

Total Deposits	The total accumulation of all Deposits executed in the Account within the specified time frame.
Total Withdrawal	The aggregate of all Withdrawals subtracted from the Account within the specified time frame.
Total Credit	The cumulative amount of Net Credits (in or out) within the specified time interval.

Exporting the Trade Transactions Report [🔗](#)

To Export the Trade Transaction Report

Click **“Export”** and select **“Export to Excel”** or **“Export to CSV”**



BBook Profitability Report

Overview [🔗](#)

The BBook Profitability Report offers a comprehensive examination of orders within the Aggregator, whether partially or fully directed to the B Book. It provides a detailed breakdown of how B Book legs are executed, simulating an authentic STP setup. Moreover, the report enables brokers to contrast the execution on MT4/MT5 platforms with that on the Centroid Aggregator.

Beyond mere numerical data, this report serves as a valuable tool for brokers to assess the financial impact of price improvement. By comparing Centroid Aggregator execution to retaining orders in MT4/MT5, brokers can gauge whether they would achieve better or lesser returns. This analytical approach helps brokers identify scenarios where price improvement proves advantageous for them or their clients, facilitating more informed decision-making.

Note: Brokers have the capability to fine-tune the allocation of price improvement in favor of the client through the Gain Percentage field within the Taker Execution Model, specified on a per Symbol basis. For instance, configuring the Gain Percentage to 100 allows the broker to retain the entire price improvement when it favors the client, without passing on any percentage. Conversely, a Gain Percentage setting of 0 ensures that the client receives the complete benefit of the price improvement.

Request BBook Profitability Report [🔗](#)

To request a BBook Profitability Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4/MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5

Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
TEM	Taker Execution Model(s) through which the Order was executed
Risk Account	Risk Account through which the Order was executed, if any
Ext Bid/Ask	Indicates whether we are comparing the Filled Price to the Price that was initiated from the Taker (MT4 or MT5) or not. - If ticked, Aggregator calculates the Slippage based on the difference between Fill Price and Price initiated by Taker - If unticked, Aggregator calculates the Slippage based on the difference between Fill Price and the Price initiated by the Aggregator based on the first scan of the Liquidity Book when the Order was received
Grid Columns	Columns or data fields that will be available in the report

Display BBook Profitability Report [↗](#)

After generating the BBook Profitability Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

Toggle here to search

Start Date: 23-11-2023 15:03:04

End Date: 23-11-2023 23:59:59

Ext Client Group: comma separated for multiple values

View Results Reset Export to CSV Export to Excel

Ext Client Login: comma separated for multiple values

Ext Order ID: comma separated for multiple values

Cen Ord Id: comma separated for multiple values

Ext Bid/Ask: ☒ Ext Bid/Ask

Grid Columns: Price Improvement (USD) CS Cost (USD) Price Improvement Net of CS Cost (USD)

For more filters you can utilize the Grid Columns

BBOOK PROFITABILITY COMPARISON Total Records: 2

Cen Ord Id	Taker	TEM	Symbol	Side	Fill Volume	BFill Volume	BFill Price	Avg Price	MT Fill Price	Ext Price	Notional B	Price Improvement (USD)	CS Cost (USD)	Price Improvement Net of CS Cost (USD)
5	Centroid_MT4	TEM-1	EURUSD	BUY	1,000,000	1,000,000	1.09044	1.09044	1.09044	1.09045	1,090,440	-10	-1,090,440	-11,090,440
3	Centroid_MT4	TEM-2	EURUSD	BUY	1,000,000	1,000,000	1.09044	1.09044	1.09044	1.09045	1,090,440	-10	-1,090,440	-11,090,440

BBook Profitability Details [↗](#)

Field	Description
Cen Ord ID	Centroid unique Order ID recorded in the Aggregator
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Order ID	Order ID number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0

Recv Time	The Time at which the Oder was received in the Aggregator
Taker Execution Model	The Taker Execution Model through which the Order was processed
Symbol	The traded Symbol
Party Symbol	The Party Symbol as defined in the corresponding Maker Session
Side	The side of the Order; Buy or Sell
Ord Type	The category of the executed Order, whether it is Market or Limit.
Volume	The requested Volume of the Order
Fill Volume	The total Filled Volume in Base Currency
BFill Volume	The B Book Filled Volume of the Order is determined as follows: • If the Order is 100% B Book, BFill Volume is equivalent to the Fill Volume. • If the Order is partially B Booked, this value represents the percentage of the Order that has been directed to the B Book.
BFill Price	The Aggregator's execution price for the B Book Order.
Exit Price	The price at which the client's Order would have been executed in the front-end platform (MT4/MT5) without utilizing the Centroid B Book (Depth of Market).
Notional B	The notional value of the B Book-filled Order in USD.
Price Improvement (USD)	The Price Improvement in USD is calculated as the difference between the Exit Price and BFill Price, multiplied by the Volume. • If the result is positive, it indicates a profit for the Broker. • If the result is negative, it signifies a loss for the Broker and a profit for the Client.
CS Cost (USD)	The cost of executing the Order through Centroid Aggregator in USD.
Price Improvement Net of CS Cost (USD)	The net Profit/Loss attributable to Price Improvement, considering the CS Cost resulting from executing the trade via the Centroid Aggregator, is calculated as follows: Price Improvement Net=Price Improvement USD–CS Cost USD This metric reflects the overall financial impact of price improvement, accounting for the associated cost incurred through the Centroid Aggregator.

Exporting the BBook Profitability Report [🔗](#)

To Export the BBook Profitability Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report

Taker Notional

Overview [🔗](#)

The Taker Notional Report presents a consolidated view of traded USD Volume, organized by individual Takers and Taker Execution Models. This report facilitates an examination of the total Volume generated by each Taker, along with insights into Taker Execution Models representing specific Accounts within a Taker.

Request Taker Notional Report [🔗](#)

To request a Taker Notional Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"Search"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: If Symbol, Taker and/or Taker Execution Model are left empty, the report assumes that all Symbols, Takers and Taker Execution Models are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols. Note: If multiple Symbols are selected, the value shown will be the aggregated total value, not on a per Symbol basis
Taker	Select one or multiple Takers
Taker Execution Model	Select one or multiple Taker Execution Models Note: If multiple Taker Execution Models are selected, the total values shown will be the aggregated values for Each Taker Execution Model within a Taker

Display Taker Notional Report [🔗](#)

After generating the Taker Notional Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.

5. Automatically adjust column sizes based on the data within each column.

TAKER NOTIONAL

Toggle here to search

Start Date

21-11-2023 00:00:00

End Date

22-11-2023 23:59:59

Symbol

TEM

TEM-1TEM-2

Taker

Centroid_M4

Search

Reset

Risk Account

Total Records: 2

Taker	TEM	Symbol	Fill Volume	BFill Vol...	AFill Vol...	Long Fill ...	BLong Fill...	ALong FL...	Short Fill...	BShort FL...	AShort F...	Notional	Notional B	Notional A	Long No...	BLong N...	ALong N...	Short No...	BShort N...	AShort ...
Centroid_M4	TEM-1	EURUSD	4,000	0	4,000	3,000	0	3,000	1,000	0	1,000	4,377.53	0	4,377.53	3,283.1	0	3,283.1	1,094.43	0	1,094.43
Centroid_M4	TEM-2	EURUSD	1,000	1,000	0	1,000	1,000	0	0	0	0	1,094.42	1,094.42	0	1,094.42	1,094.42	0	0	0	0

Note: To check the report corresponding to particular Symbols, you should run multiple reports corresponding to each Symbol, in which the desired Symbol is selected solely in the Symbol field.

Field	Description
Taker	The Taker to which the Volume corresponds
Taker Execution Model	The Taker Execution Model to which the Volume corresponds Note: If one Taker Execution Model is assigned to two different Takers, the same Taker Execution Model will be displayed twice, one time under each Taker
Total Fill Volume	The cumulative total of all filled orders.
Total Notional (USD)	The aggregate notional volume in USD.
Total Notional (USD) Readable Format	The total notional volume in USD is displayed in a condensed format: "K" represents 1000. "M" represents 1 Million (1,000,000). "B" represents 1 Billion (1,000,000,000).

Exporting the Taker Notional Report [🔗](#)

To Export the Taker Notional Report

Click on **"Export to CSV"** or **"Export to Excel"** to export the report

Centroid BRIDGE

Search...

Risk Account Statement
Risk Account Reports
Trade Transactions
BBlock Profitability Compar...

TAKER NOTIONAL
Toggle here to search

Start Date: 24-11-2023 00:00:00 End Date: 24-11-2023 23:59:59
Symbol: TEM: TEM-1, TEM-2 Taker: Centroid_M4

Search Reset

Total Records: 0

Taker	TEM	Symbol	Fill Volume	BFill Vol...	AFill Vol...	Long Fill ...	BLong Fill...	ALong FL...	Short Fill...	BShort FL...	AShort F...	Notional	Notional B	Notional A	Long No...	BLong N...	ALong N...	Short No...	BShort N...	AShort ...
-------	-----	--------	-------------	--------------	--------------	---------------	---------------	-------------	---------------	--------------	-------------	----------	------------	------------	------------	------------	------------	-------------	-------------	------------

Export to CSV Export to Excel

Maker Notional Report

Overview [🔗](#)


The Maker Notional Report provides a consolidated view of traded USD Volume categorized by individual Makers. This report is designed to assess the total Volume directed to each Maker over a specified time interval.

Request Maker Notional Report [🔗](#)

To request a Maker Notional Report

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click "**Search**" to execute the report or directly "**Export to CSV or Excel**" file.

Note: Use the Reset button to clear the pre-defined filters



Note: If Symbol and Maker are left empty, the report assumes that all Symbols and Maker are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols Note: If multiple Symbols are selected, the value shown will be the aggregated total value, not on a per Symbol basis
Maker	Select one or multiple Makers to check the routed Volume

Display Maker Notional Report [🔗](#)

After generating the Maker Notional Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

MAKER NOTIONAL
Toggle here to search

Start Date: 21-11-2023 00:00:00 | End Date: 22-11-2023 23:59:59 | Symbol: | TEM: TEM-1, TEM-2 | Maker: Liquidity Provider

Search | Reset

Risk Account:

Total Records: 2

Maker	TEM	Symbol	Fill Volume	Long Fill Volume	Short Fill Volume	Notional	Long Notional	Short Notional
Liquidity Provider	TEM-1	EURUSD	4,000	4,000	0	4,377.53	4,377.53	0
B_BOOK	TEM-2	EURUSD	1,000	1,000	0	1,094.42	1,094.42	0

Export to CSV | Export to Excel

Note: To check the report corresponding to particular Symbols, you should run multiple reports corresponding to each Symbol, in which the desired Symbol is selected solely in the Symbol field.

Field	Description
Maker	The Maker to which the Volume corresponds
Taker Execution Model	The Taker Execution Model to which the Volume corresponds Note: If one Taker Execution Model is assigned to two different Takers, the same Taker Execution Model will be displayed twice, one time under each Taker
Total Fill Volume	The cumulative total of all filled orders.
Total Notional (USD)	The aggregate notional volume in USD.
Total Notional (USD) Readable Format	The total notional volume in USD is displayed in a condensed format: "K" represents 1000. "M" represents 1 Million (1,000,000). "B" represents 1 Billion (1,000,000,000).

Exporting the Maker Notional Report [🔗](#)

To Export the Maker Notional Report

Click on **“Export to CSV”** or **“Export to Excel”** to export the report

Centroid BRIDGE

Search... | Ctrl+K

Risk Account Reports | Trade Transactions | EBook Profitability Compari... | Taker Notional | **Maker Notional**

MAKER NOTIONAL
Toggle here to search

Start Date: 24-11-2023 00:00:00 | End Date: 24-11-2023 23:59:59 | Symbol: | TEM: | Maker:

Search | Reset

Risk Account:

Total Records: 0

Maker	TEM	Symbol	Fill Volume	Long Fill Volume	Short Fill Volume	Notional	Long Notional	Short Notional
-------	-----	--------	-------------	------------------	-------------------	----------	---------------	----------------

Export to CSV | Export to Excel

Maker Notional Chart

Overview [↗](#)


The Maker Notional Chart features a visual Pie Chart illustrating the distribution of Notional Volume in USD among various Makers and the B Book. The Total Volume is presented individually for each Maker. This visual representation provides an insightful overview of trading volumes associated with different Makers.

Request Maker Notional Chart [↗](#)

To request a Maker Notional Chart Report

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters




Note: If Symbol and Maker are left empty, the report assumes that all Symbols and Makers are selected

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols Note: If multiple Symbols are selected, the value shown will be the aggregated total value, not on a per Symbol basis
Maker	Select one or multiple Makers to check the exposure with. Note: Maker B Book represents the B Book exposure of the flow that has been internalized and not routed to any Maker Note: If multiple Makers are selected, it will show the segregated values for each Maker

Display Maker Notional Chart [↗](#)

After generating the Maker Notional Chart, you can perform the following actions


Upon generating the Maker Notional Chart, you can examine the total USD Volume associated with each Maker and the B Book (if the B Book Maker is selected).



Exporting the Maker Notional Chart [↗](#)

To Export the Maker Notional Chart

You can download the charts in various formats by clicking the button in the "Top Right Corner" and choosing the "Preferred Format"



Note: The M next to the value represents million whereas the B represents billion (equivalent to 1 yard = 1000 M)

Maker Symbol Chart

Overview [↗](#)

The Maker Symbol Chart is a graphical representation in the form of a Bar Chart. It illustrates the Notional Volume in USD for various Makers and the B Book, organized on a per-Symbol basis.

Request Maker Symbol Chart [↗](#)

To request a Maker Symbol Chart Report

- 1. Click on the "Toggle here to search" button.
- 2. Complete the Wizard as detailed below.
- 3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters


Note: If Symbol and Maker are left empty, the report assumes that all Symbols and Makers are selected

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols
Maker	Choose one or multiple Makers to assess the exposure. Note: Maker B_Book signifies the B Book exposure of the flow that has been internalized and not routed to any specific Maker. Note: If multiple Makers are selected, the chart will present segregated values for each Maker.

Display Maker Symbol Chart [↗](#)

After generating the Maker Symbol Chart, you can perform the following actions


Upon generating the Maker Symbol Chart, you can examine the total USD Volume associated with each Maker and the B Book (if the B Book Maker is selected).



Exporting the Maker Symbol Chart [↗](#)

To Export the Maker Symbol Chart

You can download the charts in various formats by clicking the button in the “**Top Right Corner** and choosing the “**Preferred Format**”



Maker Symbol Status

Overview [🔗](#)

The Maker Symbol Status report offers a comprehensive look into various statistical data associated with pricing and trading with the Maker, organized on a per-Symbol basis. The Centroid Bridge captures a snapshot every 5 minutes, consolidating the information into records with all relevant statistics for each Symbol during the specified interval.


This report serves as a valuable tool for assessing the performance of each Maker in terms of pricing and execution. It plays a crucial role in aiding Brokers in the decision-making process regarding Maker selection.

Request Maker Symbol Status Report [🔗](#)

To request a Maker Symbol Status Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters



Note: In the above fields, if Maker and Symbol are left empty, this implies that all values are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Maker	Select one or multiple Makers from the list of Makers configured in the Centroid Bridge
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge

Display Maker Symbol Status Report [🔗](#)

After generating the Maker Symbol Status, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

Toggle here to search

Start Date: 21-11-2023 23:52:25

End Date: 21-11-2023 23:59:59

View Results

Grid Columns:

Makers:

Symbol:

For more Filters you can utilize the Grid Columns

MAKER SYMBOL STATUS Total Records: 4

Makers	Symbol	Time	Subscribed	Ticks Count	Avg Spread	Avg Spread in Points	Spread Ticks Count	Orders Count	Long Orders	Short Orders	Total Volume
Liquidity Provider 1	XAUUSD	21-11-2023 23:57:25.004	YES		261	0.03	3	261	0	0	0
Liquidity Provider 1	EURUSD	21-11-2023 23:57:25.004	YES		59	0.00004	4	59	0	0	0
Liquidity Provider 1	XAUUSD	21-11-2023 23:52:25.002	YES		228	0.03	3	228	0	0	0
Liquidity Provider 1	EURUSD	21-11-2023 23:52:25.002	YES		56	0.00004	4	56	0	0	0


Field	Description
Maker	The name of the Maker
Symbol	The name of the Symbol
Sub ID	The Symbol's market data subscription ID that is sent to the Maker upon subscription
Time	The timestamp indicating when the snapshot was captured and the record was generated.
Subscribed	Specifies whether we are currently subscribed to the Symbol with the Maker. • If YES, it signifies that we are subscribed to the Symbol. • If NO, it indicates that we are not subscribed to the Symbol.
Ticks Count	The count of ticks or price updates received for the Symbol within the 5-minute time interval.
Avg Spread	The average spread of the Symbol, represented in decimal format.
Avg Spread in Points	The average spread of the Symbol, expressed in points.
Spread Ticks Count	The count of ticks or price updates received for the Symbol, which served as the basis for calculating the average spread during the current time interval.
Delayed Ticks Count	The count of ticks or price updates that experienced delays.
Orders Count	The total count of orders executed with the Maker during the specified time interval, regardless of the order size. Each executed order is treated as a single occurrence, irrespective of the volume involved.
Long Orders	The overall count of Long Orders executed with the Maker during the specified time interval, regardless of the order size. Each executed Long Order is considered as one occurrence, irrespective of the volume involved.
Short Orders	The total count of Short Orders executed with the Maker during the specified time interval, regardless of the order size. Each executed Short Order is considered as one occurrence, regardless of the volume involved.
Avg Fill Time	The average fill time, measured in microseconds, for all orders executed during the current time interval.
Avg Travel Time	The average travel time, measured in microseconds, for an order to journey from the Centroid Bridge to the Maker.
Rejected Count	The count of rejected orders.
Partial Fills Count	The count of orders that experienced partial fills.
Fully Fills Count	The count of orders that were completely filled.
Total Till Volume	The aggregate notional volume executed with the Maker within the 5-minute time interval.

Average Slippage	The average slippage, expressed in decimals, for all executed orders.
Average Slippage Points	The average slippage, measured in points, for all executed orders.

Exporting the Maker Symbol Status Report [↗](#)

To Export the Maker Symbol Status Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report



Maker Symbol Spread History Chart

Overview [🔗](#)


The Maker Symbol Spread History Chart enables the examination of historical spreads received from all Makers. The Centroid Bridge records data at 5-minute intervals, calculating the average spread based on all ticks received during each interval. This chart provides insights into the historical spread patterns contributed by different Makers.

Request Maker Symbol Spread History Chart [🔗](#)

To request a Symbol Notional Chart Report

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters



Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Maker	Select one or multiple Makers from the list of Makers configured in the Centroid Bridge
Symbol	Select one Symbol at a time from the available list of Symbols Note: Only one Symbol can be selected at a time

Display Maker Symbol Spread History Chart [🔗](#)

After generating the Maker Symbol Spread History Chart, you can perform the following actions

After generating the Maker Symbol Spread History Chart, you can observe the average spreads in points for the selected Symbol provided by the chosen Makers. The spreads are presented in various chart types within 5-minute intervals.



Exporting the Maker Notional Chart [↗](#)

To Export the Maker Notional Chart

You can download the charts in various formats by clicking the button in the “**Top Right Corner** and choosing the “**Preferred Format**”



Maker Rejection

Overview [↗](#)

The Maker Rejection Report enables the examination of all orders that have been rejected by Makers on a per Leg basis. In instances of Immediate or Cancel (IOC) execution, it is possible to have both accepted and rejected Legs within the same Order.

Request Maker Rejection Report [↗](#)

To request a Maker Rejection Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters


Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols
Maker	The Maker that rejected/declined the Leg.

Display Maker Rejection Report [↗](#)

Once the Maker Rejection Report has been generated, you can do the following:

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.



Field	Description
Cen Client OrdId	The Leg ID of the Order which shows the Order and Leg number in the format OrderID_LegID Note: An Order can be split into N Legs. The ID would look like Order_Leg1, Order_Leg2...LegN
Client Ord Id	Client Order ID received in the Centroid Bridge
Cen Ord Id	Centroid unique Order ID recorded in the Centroid Bridge which could be split into multiple Legs shown as different Cen Client OrdId
Maker	The Maker that rejected/declined the Leg
Symbol	The Symbol that was traded in the rejected Order
Send Time	The timestamp indicating when the rejected Order was transmitted to the Maker.
Maker Recv Time Sec	The timestamp indicating when the Order was received by the Maker.
Price	The requested price of the Order.
Volume	The requested volume of the Order.
Side	The direction of the Order: Buy or Sell.
Ord Type	The classification of the Order: Market, Limit, or Stop.
Time in Force	The Fill Policy of the Order is defined as follows: - FOK: Fill or Kill, indicating that the Order can be fully filled in the requested volume. - IOC: Immediate or Cancel, indicating that the Order can be partially filled with the maximum available liquidity in the market, and any remaining volume will be canceled.
Scale Size	The Scale Size of the Order, as specified in the Maker Session Symbol Settings.

Exporting the Maker Rejection Report [🔗](#)

To Export the Maker Rejection Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report

Controid
BRIDGE

Search... Ctrl+k

Taker Notional

Maker Notional

Maker Notional Chart

Maker Symbol Chart

Maker Symbol Status

Maker Symbol Spread Histo...

Maker Rejection

Toggle here to search

Start Date
24-11-2023 00:00:00

End Date
24-11-2023 23:59:59

Symbol

Maker

View Results

Reset

Export to CSV

Export to Excel

Grid Columns

Cen Client OrdId

Client Ord Id

Cen Ord Id

Maker

Symbol

Send Time

Maker Recv Time Sec

Price

MAKER REJECTION

Total Records: 0

Cen Client OrdId	Client Ord Id	Cen Ord Id	Maker	Symbol	Send Time	Maker Recv Time ...	Price	Volume	Side	Ord Type	Time in Force	Scale Size	Maker Symbol	Maker OrderID
------------------	---------------	------------	-------	--------	-----------	---------------------	-------	--------	------	----------	---------------	------------	--------------	---------------

Slippage Report

Overview [↗](#)

The Slippage Report facilitates the identification of slippage on orders, arising from the variance between the requested price and the actual filled price on an individual order basis. Slippage may favor the client when positive (indicating a better fill) or favor the broker when negative (indicating a worse fill).

Request Slippage Report [↗](#)

Request Slippage Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, except for Start and End Dates, implies that all values are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge
TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any

Grid	Columns or data fields that will be available in the report
Columns	Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display Slippage Report [↗](#)

After generating the Slippage Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot shows the Slippage Report interface. At the top, there are search filters for Start Date, End Date, Ext Client Group, Ext Client Login, Ext Order ID, Cen Ord Id, Symbol, Taker, and Risk Account. Below these are buttons for View Results, Reset, Export to CSV, and Export to Excel. A red arrow points to the View Results button. In the center, there is a 'Grid Columns' dialog box with a list of columns: Client Ord Id, Cen Ord Id, Recv Time, Taker, TEM, Symbol, Side, Ord Type, Fill Volume, and Avg Price. Below the dialog, a red box highlights the text 'For more filters you can utilize the Grid Columns'. At the bottom, the report table is displayed with columns: Client, Cen Or..., Recv Time, Taker, TEM, Symbol, Side, Ord Type, Fill Vol..., Avg Price, Notional, Expecte..., Filled P..., Slippage, Slippag..., Expecte..., Filled P..., Slippage, Slippag..., Expecte..., Filled P..., Slippage, Slippag... The table shows three rows of data.

Client	Cen Or...	Recv Time	Taker	TEM	Symbol	Side	Ord Type	Fill Vol...	Avg Price	Notional	Expecte...	Filled P...	Slippage	Slippag...	Expecte...	Filled P...	Slippage	Slippag...	Expecte...	Filled P...	Slippage	Slippag...
397	100	22-11-2023	Centroid...	TEM-1	EURCAD	BUY	MARKET	1,000	1.49654	1,090.81	0	0	0	0	1.49653	1.49654	-0.00001	-0.00728888	1.49673	1.49654	0.00019	0.13848871
396	99	22-11-2023	Centroid...	TEM-2	EURCAD	BUY	MARKET	2,000	1.49655	2,181.66	0	0	0	0	1.49657	1.49655	0.00002	0.02915586	1.49677	1.49655	0.00022	0.32071444
395	98	22-11-2023	Centroid...	TEM-1	EURCAD	SELL	MARKET	3,000	1.49648	3,272.37	0	0	0	0	1.49649	1.49648	-0.00001	-0.02186711	1.49629	1.49648	0.00019	0.41547518

Primary Details

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Recv Time	The timestamp indicating when the Order was received and processed in the Centroid Bridge.
Taker	The Taker that initiated the Order
TEM	The trading execution model within the Taker from which the Order originated.
Symbol	The Symbol that was traded.
Taker Symbol	The Symbol that was traded on the Taker's end.
Side	The direction of the Order: Buy or Sell.
Ord Type	The classification of the Order: Market, Limit, Stop, etc.
Fill Volume	The volume that has been filled for the Order.
Notional	The notional volume of the Order, expressed in USD.
Avg Price	The VWAP (Volume Weighted Average Price) fill price communicated to the client after the Order has been successfully filled.

Limit Order Slippage

Field	Description
Expected Price	The specified price sent with the Limit Order.
Fill Price	The actual fill price achieved by the broker, which is either equal to or better than the expected price.
Slippage	The slippage, expressed in decimal format, is the difference between the requested price and the actual fill price. It is either 0 or a positive number.
Slippage USD	The slippage, converted into USD, is either 0 or a positive value since there is no worse fill in the case of a Limit Order.

Order Slippage Broker

Field	Description
Expected Price	The price at which the Centroid Bridge processed the Order request.
Fill Price	The actual price at which the broker's Order is filled.
Slippage	The slippage, in decimal form, represents the difference between the requested price and the actual fill price.
Slippage USD	The slippage, when converted into USD • Positive slippage indicates the Order was filled at a better price. • Negative slippage indicates the Order was filled at a worse price. • A slippage of 0 means the Order was filled without any slippage.

Client Order Slippage Ext

Field	Description
Expected Price	The request price from a client's perspective is equivalent to the available price on the client's platforms at the time the Order was placed. This encompasses all markups, including those from Centroid and MT4/MT5.
Fill Price	The actual fill price reported back to the client includes all markups, such as those from Centroid and MT4/MT5.
Slippage	The slippage, expressed in decimal form for the client, is the difference between the client's requested price and the actual fill price.
Slippage USD	The slippage, when converted into USD, is interpreted as follows: • Positive slippage indicates the Order was filled at a better price. • Negative slippage indicates the Order was filled at a worse price. • A slippage of 0 means the Order was filled without any slippage.

Exporting the Slippage Report [↗](#)

To Export the Slippage Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report

Centroid
BRIDGE

Search... Ctrl+k

Taker Notional

Maker Notional

Maker Notional Chart

Maker Symbol Chart

Maker Symbol Status

Maker Symbol Spread Histo...

Maker Rejection

Slippage Report

Toggle here to search

Start Date
24-11-2023 00:00:00

End Date
24-11-2023 23:59:59

Ext Client Group
comma separated for multiple values

View Results

Reset

Export to CSV

Export to Excel

Ext Client Login
comma separated for multiple values

Ext Order ID
comma separated for multiple values

Cen Ord Id
comma separated for multiple values

Grid Columns

Client Ord IdCen Ord IdRecv Time
TakerTEMSymbolSide
Ord TypeFill VolumeAvg Price

Symbol

TEM

Taker

Risk Account

SLIPPAGE REPORT Total Records: 0

Primary										Limit Order Slippage				Order Slippage Broker				Client Order Slippage Ext				
Client...	Cen Or...	Recv Time	Taker	TEM	Symbol	Side	Ord Type	Fill Vol...	Avg Price	Notional	Expec...	Filled P...	Slippage	Slippag...	Expec...	Filled P...	Slippage	Slippag...	Expec...	Filled P...	Slippage	Slippag...

Slippage Leg Report

Overview [↗](#)

The Slippage Report enables the assessment of slippage on orders, considering the variance between the requested price and the actual filled price on a per Leg basis. Slippage can be advantageous for the client if positive, indicating a better fill, or disadvantageous if negative, favoring the broker. Additionally, the Slippage Leg feature allows tracking of slippages the client experiences from the Maker on a per Leg basis, particularly relevant when an order is executed in multiple Legs.

Request Slippage Leg Report [↗](#)

To request a Slippage Leg Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, except for Start and End Dates, implies that all values are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Ext Client Group	MT4 / MT5 Group number for Takers of type MT4/MT5
Ext Client Login	MT4 / MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4 / MT5 Order ID Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
TEM	Taker Execution Model through which the Order was executed
Risk Account	Risk Account through which the Order was executed, if any

Maker	Select one or multiple Makers from the list. For B Book Orders, they will be under B_BOOK Maker
Grid Columns	Columns or data fields that will be available in the report

Display Slippage Leg Report [🔗](#)

After generating the Slippage Leg Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

Leg Details

Field	Description
Cen Client OrdId	The ID of the Leg. For instance, an Order split into three legs will have Leg IDs of 0, 1 and 2
Maker	The Maker Leg that was either executed or provided the quote for B Book Orders.
Send Time	The timestamp indicating when the Leg was transmitted to the Maker.
Fill Volume	The volume that has been filled for the Leg.
Notional	The notional volume of the Leg, expressed in USD.
Raw Fill Price	The raw price at which the Leg was filled with the Maker, excluding all markups.
Fill Price	The fill price of the Leg, which includes the Centroid Bridge markup.
Price	The request price of the Leg, originating from the Centroid Bridge to the Maker.
Maker Symbol	The symbol name on the Maker's side.

Maker Slippage Leg

Field	Description
-------	-------------

Expected Price	The requested price of the Leg.
Fill Price	The actual fill price of the Leg.
Slippage	The slippage, expressed in decimal form, is the difference between the requested price and the actual fill price for the Leg.
Slippage USD	The slippage, when converted into USD, reflects the monetary difference between the requested price and the actual fill price for the Leg. The slippage, when converted into USD - Positive slippage indicates the Order was filled at a better price. - Negative slippage indicates the Order was filled at a worse price. - A slippage of 0 means the Order was filled without any slippage.


Order Details

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Recv Time	The timestamp indicating when the Order was received and processed in the Centroid Bridge.
Taker	The Taker responsible for initiating the Order.
TEM	The trading execution model within the Taker from which the Order was placed.
Symbol	The Symbol that was traded.
Taker Symbol	The Symbol that was traded on the Taker's end.
Side	The direction of the Order: Buy or Sell.
Fill Volume	The volume that has been filled for the Order.
Notional	The notional volume of the Order, expressed in USD.
Avg Price	The VWAP (Volume Weighted Average Price) fill price reported back to the client after the Order has been filled.

Exporting the Slippage Leg Report [↗](#)

To Export the Slippage Leg Report

Click on “Export to CSV” or “Export to Excel” to export the report



Net Per Login

Overview [🔗](#)

The Per Net Login Report provides a detailed summary of the overall Net Open Positions, encompassing both A-Book and B-Book Net Open Positions. This report aggregates the Net Open Positions on a per Symbol basis, delivering valuable insights into trading activities for enhanced analysis and understanding.


When searching for Takers like MT4 and MT5, the report also furnishes external information in the form of Client Login details. This additional feature enhances the comprehensiveness of the report by including pertinent data related to client logins associated with platforms such as MT4 and MT5.

Request Net Per Login Report [🔗](#)

To request a Net Per Login Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters



Note: In the above fields, any field that is left empty implies that all values are included in the selection

Field	Description
Ext Client Login	The Login number of the MT4/MT5 Account. You may enter multiple comma separated Logins
Party Symbol	Party Symbol is the Symbol name on the Taker's side, as set up in the Taker Feeds. You may select one or multiple Party Symbols from the list
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge
Hide Zero Net	Choose whether to display the Logins with no Open Positions or not. • If ticked, the generated report will hide all rows with zero net open positions • If un-ticked, the generated report will still display the rows showing logins with zero net open positions

Display Net Per Login Report [🔗](#)

After generating the Net Per Login Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

NET PER LOGIN

Toggle here to search

Ext Client Login: 3033

Party Symbol: [Empty]

Symbol: [Empty]

Taker: [Empty]

TEM: [Empty]

Hide Zero ANet: ☒ Hide Zero BNet: ☒ Hide Giveup: ☒ Hide DropCopy: ☒ Group By Taker: ☐ Group By TEM: ☐

Total Records: 4

Ext Client Login	Party Symbol	Symbol	Net	Net Buy	Net Sell	ANet	ANet Buy	ANet Sell	BNet	BNet Buy	BNet Sell
3033	EURUSDama	EURUSD	-603,000	1,236,000	1,839,000	1,000	28,000	27,000	-604,000	1,208,000	1,812,000

Field	Description
Ext Client Login	Login number of the MT4/MT5 Taker
Party Symbol	The Symbol name on the Taker's side
Ext Client Login	The Symbol name as configured in Symbols
Net	The Total Net Open Position in Notional Volume denominated in the Base Currency consolidates both buy and sell positions, effectively offsetting each other. It's important to note that a negative value signifies a short net open position (sell), whereas a positive value indicates a long net open position (buy).
Net Buy	The Buy Net Open Position signifies the combined Notional Volume in the Base Currency for all buy positions. This metric is specifically designed to highlight the volume of open positions where clients have adopted a long (buy) position in the market. It provides a targeted insight into the overall volume associated with clients taking a bullish stance.
Net Sell	The Sell Net Open Position relates to the total Notional Volume in the Base Currency attributed to all sell positions. This metric exclusively portrays the volume of open positions wherein clients have assumed a short (sell) position in the market. It offers a focused perspective on the overall volume associated with clients adopting a bearish stance.
ANet	The Comprehensive Net Open Position of A-Book Orders, denominated in Notional Volume in the Base Currency, amalgamates both buy and sell A-Book positions, efficiently balancing each other out. It's crucial to recognize that a negative value indicates a short net open position (sell), while a positive value signifies a long net open position (buy). This metric offers an all-encompassing perspective on the overall A-Book exposure, presenting insights into volume and directional bias.
ANet Buy	The Buy Net Open Position for A-Book Orders, measured in Notional Volume in the Base Currency, represents the aggregated volume of all buy positions within the A-Book. This metric specifically focuses on the cumulative volume associated with clients taking a long (buy) position in the market within the A-Book segment.
ANet Sell	The Sell Net Open Position for A-Book Orders, quantified in Notional Volume in the Base Currency, signifies the combined volume of all sell positions within the A-Book. This metric exclusively reflects the aggregated volume of open positions where clients have opted for a short (sell) stance in the market within the A-Book segment.
BNet	The Total Net Open Position of B-Book Orders, expressed in Notional Volume in the Base Currency, consolidates both buy and sell B-Book positions, effectively offsetting each other. It's important to note that a negative value signifies a

	short net open position (sell), while a positive value indicates a long net open position (buy). This metric provides a comprehensive overview of the overall B-Book exposure in terms of volume and directional bias.
BNet Buy	The Buy Net Open Position for A-Book Orders, measured in Notional Volume in the Base Currency, represents the cumulative volume of all buy positions within the A-Book. This metric specifically focuses on the combined volume associated with clients taking a long (buy) position in the market within the A-Book segment.
BNet Sell	The Sell Net Open Position for B-Book Orders, quantified in Notional Volume in the Base Currency, signifies the aggregated volume of all sell positions within the B-Book. This metric exclusively reflects the combined volume of open positions where clients have chosen a short (sell) stance in the market within the B-Book segment.

Exporting the Net Per Login Report [🔗](#)

To Export the Net Per Login Report

Click on “**Export to CSV**” or “**Export to Excel**” to export the report

The screenshot shows the 'NET PER LOGIN' report interface in the Centroid Bridge application. The interface is dark-themed and includes a sidebar on the left with various report categories. The main content area features search filters for 'Ext Client Login', 'Party Symbol', 'Symbol', 'Taker', and 'TEM'. Below these filters are checkboxes for 'Hide Zero ANet', 'Hide Zero BNet', 'Hide Giveup', and 'Hide DropCopy', as well as 'Group By Taker' and 'Group By TEM'. At the bottom of the interface, there are two buttons: 'Export to CSV' and 'Export to Excel', which are highlighted with a red box.

Symbol Notional Chart

Overview [🔗](#)

The Symbol Notional Chart is a graphical representation in the form of a bar chart, visually illustrating the Notional Volume in USD traded throughout the entirety of the Centroid Bridge.

Request Symbol Notional Chart [🔗](#)

To request a Symbol Notional Chart Report

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters

The screenshot shows the Centroid Bridge web application interface. On the left is a sidebar with a search bar and a list of navigation items. The main panel is titled 'Symbol Notional Chart'. At the top of the main panel, there is a section titled 'Toggle here to search' which contains three input fields: 'Start Date' (with a pre-filled date '22-11-2023 00:00:00'), 'End Date' (with a pre-filled date '22-11-2023 23:59:59'), and 'Symbol'. Below these fields are 'Search' and 'Reset' buttons. Red arrows in the image point to the 'Toggle here to search' text, the Start Date and End Date input fields, and the Symbol input field.


Note: If Symbol is left empty, the report assumes that all Symbols are selected

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols Note: If multiple Symbols are selected, the report will shows the Total Volume for each of the selected Symbols

Display Symbol Notional Chart [🔗](#)

After generating the Symbol Notional Chart, you can perform the following actions

1. The Symbol Notional Chart visually represents Notional Volume in USD traded across the entire Centroid Bridge.
2. Once generated, this chart enables you to analyze the total USD Volume for each selected Symbol using Bar Charts.
3. The displayed dates vary depending on the chosen time interval, with shorter intervals presenting more days on the chart.
4. For instance, a 2-month time interval displays weekly results instead of daily, whereas a 2-week interval includes figures for all days within that timeframe.




Field	Description
Symbol	The traded Symbol to check the Volume for
Total Fill Volume	The cumulative total of all filled orders.
Total Notional (USD)	The aggregate notional volume in USD.
Total Notional (USD) Readable Format	The total notional volume in USD is displayed in a condensed format: • "K" represents 1000. • "M" represents 1 Million (1,000,000). • "B" represents 1 Billion (1,000,000,000).

Exporting the Symbol Notional Chart [↗](#)

To Export the Symbol Notional Chart

You can download the charts in various formats by clicking the button in the **"Top Right Corner"** and choosing the **"Preferred Format"**



Symbol Detail Chart

Overview [🔗](#)


The Symbol Detail Chart offers a visual representation of the Daily Notional Volume in USD traded for a specific Symbol within a user-selected time interval. This chart provides a granular view, allowing users to explore in-depth details and observe the evolution of Volume throughout a chosen day.

Request Symbol Detail Chart [🔗](#)

To request a Symbol Detail Chart

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters




Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols Note: If multiple Symbols are selected, the report will shows the Total Volume for each of the selected Symbols

Display Symbol Detail Chart [🔗](#)

After generating the Symbol Detail Chart, you can perform the following actions


Upon generating the Symbol Detail Chart, users can access the total traded USD Volume for the selected Symbol. Furthermore, users have the capability to delve deeper into specific days and times, gaining insights into how the Volume has changed over the designated period.



Exporting the Symbol Detail Chart [↗](#)

To Export the Symbol Detail Chart

You can download the charts in various formats by clicking the button in the “**Top Right Corner**” and choosing the “**Preferred Format**”



Symbol Notional

Overview [↗](#)


The Symbol Notional Report is a visual representation that displays the Total Volume traded across the entire Centroid Bridge. This report aggregates the data on a per Symbol basis, offering a comprehensive overview of trading activity for individual symbols within the given time frame.

Request Symbol Notional Report [↗](#)

To request a Symbol Notional Report

1. Click on the "Toggle here to search" button.
2. Complete the **Wizard** as detailed below.
3. Click the "Search" button

Note: Use the Reset button to clear the pre-defined filters



Note: If Symbol is left empty, the report assumes that all Symbols are included in the selection

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval
Symbol	Select one or multiple Symbols from the list of Symbols Note: If multiple Symbols are selected, the report will shows the Total Volume for each of the selected Symbols

Display Symbol Notional Report [↗](#)

After generating the Symbol Notional Report, you can perform the following actions

Upon generating the Symbol Notional Report, users have the capability to view the aggregated Volume, providing a detailed breakdown for each Symbol individually. This feature allows for a granular examination of trading activity at the level of each specific symbol within the report.

SYMBOL NOTIONAL
Toggle here to search

Start Date: 01-11-2023 00:00:00 End Date: 22-11-2023 23:59:59

Symbol: EURUSD BTCUSD APPLE XAUUSD

Search Reset

Total Records: 4

Symbol	Fill Volume	BFill Volume	AFill Volume	Long Fill V...	BLong Fill ...	Along Fill ...	Short Fill V...	BShort Fill...	AShort Fill...	Notional	Notional B	Notional A	Long Notl...	BLong Not...	Along No...	Short Notl...	BShort No...	AShort No...
XAUUSD	44,726	42,126	2,600	30,997	29,697	1,300	13,729	12,429	1,300	68,589,218.12	83,420,961.12	5,168,257	61,373,098.42	58,768,595.42	2,584,503	27,216,119.7	24,632,365.7	2,583,754
EURUSD	140,792,654.14	139,394,154.14	1,398,500	72,432,023.03	71,728,023.03	704,000	68,340,631.11	67,666,131.11	694,500	152,533,914.9	150,934,839.69	1,599,075.21	78,676,411.43	77,817,229	858,182.43	73,852,503.47	73,117,610.69	738,892.78
APPLE	0.2	0.2	0	0.2	0.2	0	0	0	0	13.08	13.08	0	13.08	13.08	0	0	0	0
BTCUSD	2	2	0	0	0	0	0	2	2	0	72,878	72,878	0	0	0	0	72,878	72,878

Field	Description
Symbol	The traded Symbol to check the Volume for
Total Fill Volume	The cumulative total of all filled orders.
Total Notional (USD)	The aggregate notional volume in USD.
Total Notional (USD) Readable Format	The total notional volume in USD is displayed in a condensed format: "K" represents 1000. "M" represents 1 Million (1,000,000). "B" represents 1 Billion (1,000,000,000).

Exporting the Symbol Notional Report [↗](#)

To Export the Slippage Report

Click on "Export to CSV" or "Export to Excel" to export the report

Centroid BRIDGE

Search... Ctrl+F

Taken Notional
Maker Notional
Maker Notional Chart
Maker Symbol Chart
Maker Symbol Status
Maker Symbol Spread Histo...
Maker Rejection
Slippage Report
Slippage Log Report
Net Per Login
Symbol Notional Chart
Symbol Detail Chart
Symbol Notional

SYMBOL NOTIONAL
Toggle here to search

Start Date: 27-11-2023 00:00:00 End Date: 27-11-2023 23:59:59

Search Reset

Symbol

Total Records: 0

Symbol	Fill Volume	BFill Volume	AFill Volume	Long Fill V...	BLong Fill ...	Along Fill ...	Short Fill V...	BShort Fill...	AShort Fill...	Notional	Notional B	Notional A	Long Notl...	BLong Not...	Along No...	Short Notl...	BShort No...	AShort No...
--------	-------------	--------------	--------------	----------------	----------------	----------------	-----------------	----------------	----------------	----------	------------	------------	--------------	--------------	-------------	---------------	--------------	--------------

No Rows To Show

Markup Report

Overview [🔗](#)

The Markup Report functions as a pivotal tool for profitability analysis, granting brokers the ability to discern the financial impact of markups on a per-order basis. By offering detailed insights into the relationship between markups and financial performance, this report enables brokers to precisely evaluate how markups influence the profitability of each individual order.

Request Markup Report [🔗](#)

To request a Markup Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge

TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any
Grid Columns	Columns or data fields that will be available in the report Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display Markup Report [🔗](#)

After generating the Markup Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The screenshot displays the Markup Report interface. On the left, there are filter fields for Start Date (22-11-2023 00:00:00), End Date (22-11-2023 23:59:59), Ext Client Group, Ext Client Login, Ext Order ID, and Cen Ord ID. Below these are buttons for View Results, Reset, Export to CSV, and Export to Excel. A red arrow points to the 'Export to CSV' button. In the center, there is a 'Grid Columns' dropdown menu with options: Markup Centroid (USD), Markup MT (USD), Total Markup (USD), Markup WL (USD), Cen Ord ID, Taker, and Ext Client Login. Below this, a note states: 'For more filters you can utilize the Grid Columns'. On the right, there are fields for Symbol, Taker, and Risk Account. At the bottom, a table titled 'MARKUP REPORT Total Records: 3' shows three rows of data. The table has columns: Cen Ord ID, Recv Time, Taker, TEM, Symbol, Side, Fill Volume, Notional, Fill Price Br..., Fill Price Cl..., Ext Avg Price, Markup Centroid, Markup MT, Markup Centroid (USD), Markup MT (USD), Total Markup (USD), and Markup WL (USD). The data rows are for orders 14, 13, and 12, all originating from Centroid_MT4.


Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Name of the MT4/MT5 Group from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will show an empty value
Ext Order ID	Ticket number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Recv Time	The Time at which the Oder was received and processed in the Centroid Bridge
Taker	The Taker that initiated the Order
TEM	The Trading Execution Model within the Taker from where the Order was placed
Symbol	The traded Symbol

Side	The side of the Order; Buy or Sell
Fill Volume	The filled Volume of the Order
Notional	The Notional Volume in USD
Fill Price Broker	The raw Fill Price of the Broker with the Maker (or B Book) excluding any markup
Fill Price Client	The Fill Price reported back to Client which includes the markup, if any, defined in Markup Model
Markup	The Markup in decimal which is the difference between Broker Fill Price and Client Fill Price
Markup USD	The Markup converted into USD representing the Broker's profitability on the Order
Markup WL (%)	WL Markup in USD as per the defined WL Bid % and WL Ask %, if any, in Markup Model

Exporting the Markup Report [↗](#)

To Export the Markup Report

Click on “Export to CSV” or “Export to Excel” to export the report



Markup Leg Report

Overview [🔗](#)

The Markup Leg Report is a profitability analysis tool designed for brokers to assess the profitability attributed to markups on a Per-Leg basis. In the context of orders sent to the Maker, execution occurs on a per Leg basis, with an order comprising multiple Legs. This report provides detailed insights into how markups impact profitability at the individual Leg level within multipart orders.

Request Markup Leg Report [🔗](#)

To request a Markup Leg Report

1. Click on the **"Toggle here to search"** button.
2. Complete the **Wizard** as detailed below.
3. **Pre-set** the columns necessary for the report in the Grid Columns.
4. Click **"View Results"** to execute the report or directly **"Export to CSV or Excel"** file.

Note: Use the Reset button to clear the pre-defined filters

The screenshot shows the Centroid Bridge Markup Leg Report Wizard. The interface is divided into a sidebar on the left with navigation links, a top search bar, and a main form area. The form area contains several input fields for search criteria: Start Date, End Date, Ext Client Group, Ext Client Login, Ext Order ID, Cen Ord Id, Symbol, Taker, Maker, TEM, and Risk Account. There are also buttons for 'View Results', 'Reset', 'Export to CSV', and 'Export to Excel'. A 'Grid Columns' section allows users to select columns for the report. The bottom of the screen displays a table header for the report results, with columns for various fields like Cen CL, Maker, Time, FIB Vol, Notis, FIB PL, FIB PL, Markup, Marku, Marku, Maker, Maker, Client, Cen O, Ext CL, Ext CL, Ext CL, Symbol, Side, FIB Vol, FIB PL, FIB PL, Ext As, Marku, Marku.

Note: In the above fields, any field that is left empty, apart from dates, implies that all values are included in the search

Field	Description
Start Date	The Start Date of your desired search interval
End Date	The End Date of your desired search interval.
Ext Client Group	Name of MT4/MT5 Group for Takers of type MT4/MT5
Ext Client Login	MT4/MT5 Login number for Takers of type MT4/MT5
Ext Order ID	MT4/MT5 Ticket Number for Takers of type MT4/MT5
Cen Ord Id	Centroid Order ID
Symbol	Select one or multiple Symbols from the list of Symbols available in the Centroid Bridge

TEM	Taker Execution Model(s) through which the Order was executed
Taker	The Taker(s) configured in the Centroid Bridge such as FIX, MT4, MT5 and Centroid's Trading Platform
Risk Account	Risk Account through which the Order was executed, if any
Grid Columns	Columns or data fields that will be available in the report Note: To determine the reason and comments for rejections, ensure you include both filters when running the report.

Display Markup Leg Report [🔗](#)

After generating the Markup Leg Report, you can perform the following actions

1. Arrange columns in ascending or descending order.
2. Apply filters to columns using various arithmetic and logical conditions.
3. Navigate through pages using options for first, last, previous, and next pages.
4. Optimize the report layout to fit the entire content on the page.
5. Automatically adjust column sizes based on the data within each column.

The Markup Leg Report is divided into two sections, Leg Details and Order Details. When Order is split into multiple Legs, different Legs will be shown on one side whereas on the other side the same Order will be shown multiple times depending on the number of Legs it was split into.

MARKUP LEG REPORT Total Records: 31																								
Leg Details												Order Details												
Order ID	Maker	Time	Fill Volume	Notional	Fill Price Broker	Fill Price Client	Markup	Markup (USD)	Markup WL (USD)	Maker Symbol	Maker OrderID	Client Ord Id	Cen Ord Id	Ext Client Login	Ext Client Group	Ext Order ID	Symbol	Side	Fill Volume	Fill Price Broker	Fill Price Client	Ext Avg Price	Markup Centroid	Markup MT
89_1	B_BOOK	10-07-2023...	153,000	167,680.35	1.09593	1.09595	0.00002	3.06	0			569884889	488089	3036	realSupport...	4936966	EURUSD	BUY	153,000	1.09593	1.09595	1.09595	0.00002	
88_1	B_BOOK	10-07-2023...	923,000	1,011,460.32	1.09596	1.09594	0.00002	18.46	0			569883903	488088	3036	realSupport...	4936965	EURUSD	SELL	923,000	1.09596	1.09594	1.09594	0.00002	
87_1	B_BOOK	10-07-2023...	323,000	354,001.54	1.09596	1.09598	0.00002	6.46	0			569883854	488087	3036	realSupport...	4936964	EURUSD	BUY	323,000	1.09596	1.09598	1.09598	0.00002	
86_1	B_BOOK	10-07-2023...	323,000	353,956.32	1.09596	1.09594	0.00002	6.46	0			569883529	488086	3036	realSupport...	4936963	EURUSD	SELL	323,000	1.09596	1.09594	1.09594	0.00002	
85_1	B_BOOK	10-07-2023...	619,000	678,424	1.09598	1.096	0.00002	12.38	0			569883104	488085	3036	realSupport...	4936962	EURUSD	BUY	619,000	1.09598	1.096	1.096	0.00002	
84_1	B_BOOK	10-07-2023...	186,000	203,857.86	1.09599	1.09601	0.00002	3.72	0			569882783	488084	3036	realSupport...	4936961	EURUSD	BUY	186,000	1.09599	1.09601	1.09601	0.00002	
83_1	B_BOOK	10-07-2023...	86,000	94,246.54	1.09591	1.09589	0.00002	1.72	0			569882188	488083	3036	realSupport...	4936960	EURUSD	SELL	86,000	1.09591	1.09589	1.09589	0.00002	
82_1	B_BOOK	10-07-2023...	51,000	55,880	1.09598	1.096	0.00002	1.02	0			569882229	488082	3036	realSupport...	4936959	EURUSD	BUY	51,000	1.09598	1.096	1.096	0.00002	

Order Details

Field	Description
Client Ord ID	Client Order ID received in the Centroid Bridge
Cen Ord ID	Centroid unique Order ID recorded in the Centroid Bridge
Ext Client Login	Login number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Ext Client Group	Name of the MT4/MT5 Group from which the order was generated, if the order is originated from a Taker of type MT4 or MT5. Otherwise, the field will show an empty value
Ext Order ID	Ticket number of the MT4/MT5 Taker if the order is originated from a Taker of type MT4 or MT5. Otherwise, value will be 0
Recv Time	The Time at which the Order was received and processed in the Centroid Bridge
Taker	The Taker that initiated the Order
TEM	The Trading Execution Model used for executing the order
Symbol	The universal symbol in the bridge

Taker Symbol	The traded Symbol on Taker's end
Side	The side of the Order; Buy or Sell
Fill Volume	The actual filled Volume of the Order. - Fully Filled Orders have Full Volume equal to Volume - Partially Filled Orders have Fill Volume less than Volume - Rejected Orders have 0 Volume as no Volume was executed
Notional	The Notional Volume of the filled order in USD
Fill Price Broker	The raw Fill Price of the Broker with the Maker (or B Book) excluding any markup
Fill Price Client	The Fill Price reported back to Client which includes the markup, if any, defined in Markup Model
Total Markup	The total Markup of the Order in decimal which is the difference between Broker Fill Price and Client Fill Price
Markup USD	The total Markup of the Order converted into USD representing the Broker's profitability on the Order
Markup WL (%)	WL Markup in USD as per the defined WL Bid % and WL Ask %, if any, in Markup Model


Leg Details

Field	Description
Cen Client OrdId	The ID of the Leg. For instance, an Order split into three legs will have Leg IDs of 0, 1 and 2
Maker	The Maker Leg got executed with. - For A Book: The name of the Maker will be displayed - For B Book: B_BOOK will be displayed
Fill Volume	The filled Volume of the Leg
Notional	The Notional Volume of the Leg in USD
Fill Price Broker	The raw Fill Price of the Broker with the Maker (or B Book) excluding any markup
Fill Price Client	The Fill Price reported back to Client which includes the markup, if any, defined in Markup Model
Markup	The Markup of the Leg in decimal which is the difference between Broker Fill Price and Client Fill Price. For Orders split into multiple Legs, it represents the proportion of the Order executed in the Leg
Markup USD	The Markup converted into USD representing the Broker's profitability on the Leg. For Orders split into multiple Legs, it represents the proportion of the Order executed in the Leg
Markup WL (%)	WL Markup in USD as per the defined WL Bid % and WL Ask %, if any, in Markup Model. For Orders split into multiple Legs, it represents the proportion of the Order executed in the Leg

Exporting the Markup Leg Report [↗](#)

To Export the Markup Leg Report

Click on “Export to CSV” or “Export to Excel” to export the report



Login Spread (Client)



Page is under
construction



Login Spread (Cover)



Page is under
construction



API Documentations

Welcome to the Documentation section of Centroid Bridge APIs! Here, you can access comprehensive documentation for our various APIs, including Dropcopy FIX API, Taker FIX API, and Maker FIX API. We are committed to keeping you informed with the latest updates, and this documentation will be regularly updated to ensure you have access to the most current information. Stay tuned for new updates and enhancements to our APIs. If you have any questions or need further assistance, feel free to reach out to our support team at support@centroidsol.com.

Centroid Database Specification

Centroid Solution is offering Centroid Bridge TradesDB and ConfigDB replicas via Postgres as one solution using our own DB replicator.

Requirements for setup: [🔗](#)

1. Reporting Server for Database (to be hosted by Centroid)
2. Source IP of servers that will connect to the database

How to Request: [🔗](#)

1. Submit an email request to support@centroidsol.com with the subject of "DB Server"
2. With your request, clearly state that you would like to get access to your trades/config DB and include the source IP
3. Centroid Support will provide additional information including the cost of the solution

DB Credentials: [🔗](#)

The information below will be provided by Centroid Support when the DB server is ready

1. DB host/IP
2. DB Port
3. DB Name
4. DB Username
5. DB Password

Centroid Dropcopy API

Centroid FIX 4.4 DropCopy API Specification v1.1 [↗](#)

Changelogs [↗](#)

Date	Version	Changes
08-02-2021	1.1	Enhanced Execution Report – Added available external information
13-08-2021	1.0	Enhanced Execution Report

Messages [↗](#)

As defined in the FIX protocol, the Centroid FIX server uses two different data levels: Session and Application. The Session level handles the delivery of data and the Application level defines the business-related data content. The following session and application messages are supported by the Centroid FIX Engine:

- Standard messages [↗](#)

1. Standard header
2. Standard trailer

- Session messages [↗](#)

1. Heartbeat (Client Centroid)
2. Test Request (Client Centroid)
3. Logon (Client Centroid)
4. Logout (Client Centroid)
5. Resend Request (Client Centroid)
6. Reject (Client Centroid)
7. Business Reject (Client Centroid)
8. Sequence Reset (Client Centroid)

- Application messages [↗](#)

- Trading Session [↗](#)

1. Execution Report (Client Centroid)

Important notes [↗](#)

- All time formats in the system are UTC.
- Session timings are to be communicated with the Broker.
- IP address white-listing is required to obtain the connection to live server.
- Timestamp precision is 3 or more (microseconds or milliseconds).
- Trading Session is to reset sequence number on logon.
- Giveup rule is required to be set up by centroid client.

- For customized tags mentioned in the Execution report, Centroid support team can enable it upon request

Standard Messages [↗](#)

- Standard Header [↗](#)

A standard set of fields to form the header of the FIX message.

Tag	Field name	Required	Description
8	BeginString	Y	Identifies beginning of new message and protocol version (always first field in message)
9	BodyLength	Y	Message length (in bytes) forward to the Checksum field (always second field in message)
35	MsgType	Y	Defines message type (always 3rd tag in message)
49	SenderCompID	Y	Assigned value used to identify the client sending messages (will be provided by Centroid)
56	TargetCompID	Y	Assigned value used to identify receiving party (will be provided by Centroid)
34	MsgSeqNum	Y	Integer message sequence number
50	SenderSubID	N	Optional. Assigned value used to identify specific message originator (desk trader etc.) (will be provided by Centroid if necessary)
52	SendingTime	Y	Message transmission time in UTC/GMT

- Standard Trailer [↗](#)

A standard set of fields to form the trailer of the FIX message.

Tag	Field name	Required	Description
10	Checksum	Y	Three-digit character representing the checksum value of the message

Session Messages (Admin Messages) [↗](#)

- Heartbeat (MsgType=0) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=0
112	TestReqID	N	Required when the heartbeat is the result of a Test Request message
	Standard Trailer	Y	

- Test Request (MsgType=1) [↗](#)

It is intended to test the connectivity and responsiveness of the other party.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=1
112	TestReqID	Y	A unique identifier for this test message
	Standard Trailer	Y	

- Logon (MsgType=A) [↗](#)

Handshake logon initiated by the client and confirmed by Centroid.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=A
98	EncryptMethod	Y	Use of Encryption set to 0
108	HeartBtInt	Y	Heart beat interval in seconds
141	ResetSeqNumFlag	N	Indicates both sides of a FIX session should reset sequence numbers
553	Username	Y	Username
554	Password	Y	Password
	Standard Trailer	Y	

- Logout (MsgType=5) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=5
58	Text	Y	Reason for logout
	Standard Trailer	Y	

- Resend Request (MsgType=2) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=2

7	BeginSeqNo	Y	
16	EndSeqNo	Y	
	Standard Trailer	Y	

- Reject (MsgType=3) [🔗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=3
45	RefSeqNum	Y	MsgSeqNum of rejected message
371	RefTagID	N	The tag number of the FIX field being referenced
372	RefMsgType	N	The MsgType of the FIX message being referenced
373	SessionRejectReason	N	Code to identify reason for a session-level
	Standard Trailer	Y	

- Business Reject (MsgType=j) [🔗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=j
45	RefSeqNum	N	MsgSeqNum (34) of rejected message.
371	RefTagID	Y	The tag number of the FIX field being referenced.
372	RefMsgType	Y	Message Type being referenced.
380	BusinessRejectReason	Y	Code to identify reason for a Business Message Reject (j) message.
58	Text	Y	Where possible, message to explain the rejection reason
	Standard Trailer	Y	

- Sequence Reset (MsgType=4) [🔗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=4
123	GapFillFlag	N	Gap fill flag to determine the need to fill the gap of sequence or not.
36	NewSeqNo	Y	The new sequence number requested
	Standard Trailer	Y	

- Execution Report (MsgType=8) [🔗](#)

Order Execution Report

- C - Conditionally required
- Y - Required
- N - Not required

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=8
1	Account	N	Name of the trading account
11	ClOrdID	Y	Must be unique identifier sent by the client. Used for response
17	ExecID	Y	Unique identifier of execution message assigned by Centroid Gateway
150	ExecType	Y	The execution report type. [2 = Filled]
55	Symbol	Y	Symbol name
54	Side	Y	Side of order [1 = Buy] [2 = Sell]
38	OrderQty	Y	Order Quantity
40	OrdType	Y	[1 = Market], [2 = Limit], [3 = Stop]
32	LastQty	C	Fill Quantity
59	TimeInForce	Y	TimeInForce [1 = GTC], [3 = IOC], [4 = FOK]
37	OrderID	Y	Centroid Gateway order ID
39	OrdStatus	Y	Current order state. [1 = Partially filled] [2 = Filled]
31	LastPx	C	Price of this fill.
151	LeavesQty	C	Remaining quantity open for execution
14	CumQty	C	Cumulative quantity executed
6	AvgPx	C	Average price of executed quantity
44	Price	N	Price of the Limit order
58	Text	Y	Free format text string
60	TransactTime	Y	Time of the transaction
90001	Login	N	External Login/Account from MT4/MT5
90002	Group	N	External Group from MT4/MT5
90003	Order	N	External OrderID/Ticket number
90006	Position ID	N	External Position number from MT4/MT5
90010	B Filled	N	BBook Filled Volume
90011	External Markup	N	External added Markup from the Taker
132	Bid Price	N	External Bid

133	Offer Price	N	External Ask
	Standard Trailer	Y	

Examples of FIX Messages [↗](#)

Notes: the example messages below are client views on how the messages are expected to be received when sent by the dropcopy.

Execution Report (MsgType=8) [↗](#)

- Fully Filled: [↗](#)

```
20210810-21:44:27.038873000 [in] : 8=FIX.4.4 | 9=290 | 35=8 | 34=909 | 49=CENTROID_SOL | 52=20210810-21:44:27.036905 |
56=DC_Centroid | 1=test_tem | 6=1.17218000 | 11=4797_1-12 | 14=1000.00000000 | 17=507114-12 | 31=1.17218000 |
32=1000.00000000 | 37=507114-12 | 38=1000.00000000 | 39=2 | 40=1 | 54=2 | 55=EURUSD | 58=N/A | 59=3 | 60=20210810-21:44:27 |
150=2 | 151=0.00000000 | 10=041 |
```

- Fully Filled through multiple Partial Fills: [↗](#)

```
20210810-22:49:19.866761000 [in] : 8=FIX.4.4 | 9=303 | 35=8 | 34=1043 | 49=CENTROID_SOL | 52=20210810-22:49:19.865676 |
56=DC_Centroid | 1=test_tem | 6=1.17213000 | 11=4801_1-12 | 14=20000000.00000000 | 17=507118-12 | 31=1.17213000 |
32=20000000.00000000 | 37=507118-12 | 38=20000000.00000000 | 39=2 | 40=1 | 54=2 | 55=EURUSD | 58=N/A | 59=3 | 60=20210810-
22:49:19 | 150=2 | 151=0.00000000 | 10=154 |
```

- Partially Filled [↗](#)

```
20210810-22:49:16.693604000 [in] : 8=FIX.4.4 | 9=308 | 35=8 | 34=1042 | 49=CENTROID_SOL | 52=20210810-22:49:16.692405 |
56=DC_Centroid | 1=test_tem | 6=1.17213000 | 11=4800_1-12 | 14=24750000.00000000 | 17=507117-12 | 31=1.17213000 |
32=24750000.00000000 | 37=507117-12 | 38=25000000.00000000 | 39=1 | 40=1 | 54=2 | 55=EURUSD | 58=N/A | 59=3 | 60=20210810-
22:49:16 | 150=2 | 151=250000.00000000 | 10=164 |
```

- With Customized Tags [↗](#)

```
20220208-08:45:16.155807000 [in] : 8=FIX.4.4 | 9=411 | 35=8 | 34=16 | 49=CENTROID_SOL | 52=20220208-08:45:16.151684 |
56=DC_Centroid_DropCopy | 1=test_tem | 6=1.14029000 | 11=32867651006464-12 | 14=1000.00000000 | 17=3566625-12 |
31=1.14029000 | 32=1000.00000000 | 37=3566625-12 | 38=1000.00000000 | 39=2 | 40=1 | 54=2 | 55=EURUSD | 58=Execution | 59=4 |
60=20220208-08:45:16 | 132=1.14023000 | 133=1.14035000 | 150=2 | 151=0.00000000 | 90001=1014 | 90002=realtestla-book |
90003=2970554 | 90006=2970553 | 90011=-0.00006000 | 10=122 |
```

Logon (MsgType=A) [↗](#)

```
20210720-14:31:59.705542000 [in] : 8=FIX.4.4 | 9=128 | 35=A | 34=1 | 49=DC_Centroid | 52=20210720-14:31:59.703 |
56=CENTROID_SOL | 98=0 | 108=30 | 141=Y | 553=Username | 554=Password | 10=140 |
```

```
20210720-14:31:59.707057000 [out] : 8=FIX.4.4 | 9=96 | 35=A | 34=1 | 49=CENTROID_SOL | 52=20210720-14:31:59.707021 |
56=DC_Centroid | 98=0 | 108=30 | 141=Y | 10=026 |
```

Logout (MsgType=A) [↗](#)

```
20210720-14:32:40.749544000 [in] : 8=FIX.4.4 | 9=87 | 35=5 | 34=3 | 49=DC_Centroid | 52=20210720-14:32:40.747 |
56=CENTROID_SOL | 58=disabled | 10=021 |
```

20210720-14:32:40.750004000 [out] : 8=FIX.4.4 | 9=78 | 35=5 | 34=3 | 49=CENTROID_SOL | 52=20210720-14:32:40.749980 | 56=DC_Centroid | 10=213 |

Heartbeat (MsgType=0) [↗](#)

20210720-14:32:29.734267000 [out] : 8=FIX.4.4 | 9=78 | 35=0 | 34=2 | 49=CENTROID_SOL | 52=20210720-14:32:29.734216 | 56=DC_Centroid | 10=200 |

20210720-14:32:29.742891000 [in] : 8=FIX.4.4 | 9=75 | 35=0 | 34=2 | 49=DC_Centroid | 52=20210720-14:32:29.735 | 56=CENTROID_SOL | 10=045 |

Business Reject (MsgType=j) [↗](#)

20210720-14:40:35.990273000 [in] : 8=FIX.4.4 | 9=122 | 35=j | 34=2 | 49=CENTROID_SOL | 52=20210720-14:40:35.989175 | 56=DC_Centroid | 45=2 | 58=Invalid Session | 371=35 | 372=D | 380=11 | 10=029 |

Reject (MsgType=3) [↗](#)

20210720-14:40:35.990389000 [out] : 8=FIX.4.4 | 9=141 | 35=3 | 34=3 | 49=DC_Centroid | 52=20210720-14:40:35.990 | 56=CENTROID_SOL | 45=2 | 58=Tag not defined for this message type | 371=371 | 372=j | 373=2 | 10=069 |

Centroid Maker FIX API

Centroid FIX 4.4 Maker API Specification v1.0.0 [↗](#)

Changelogs [↗](#)

Date	Version	Changes
25-04-2023	1.0.0	Document Creation

Messages [↗](#)

As defined in the FIX protocol, the Centroid FIX server is using two different data levels: Session and Application. The Session level handles the delivery of data and the Application level defines the business-related data content. The following session and application messages are supported by the Centroid FIX Engine

- Standard messages [↗](#)

1. Standard header
2. Standard trailer

- Session messages [↗](#)

1. Heartbeat (Centroid Bridge)
2. Test Request (Centroid Bridge)
3. Logon (Centroid Bridge)
4. Logout (Centroid Bridge)
5. Resend Request (Centroid Bridge)
6. Reject (Maker)
7. Business Reject (Maker)
8. Sequence Reset (Centroid Bridge)

- Application messages [↗](#)

- Market Data Session [↗](#)

1. Market Data Request (Centroid Bridge)
2. Market Data Request Reject (Maker)
3. Market Data Snapshot Full Refresh (Maker)

- Trading Session [↗](#)

1. New Order Single (Centroid Bridge)
2. Order Cancel Request (Centroid Bridge)
3. Order Cancel Replace Request (Centroid Bridge)
4. Order Cancel Reject (Maker)
5. Order Status Request (Centroid Bridge)

6. Execution Report (Maker)

Important notes [↗](#)

- All time formats in the system are UTC.
- Session timings are to be communicated with the Broker.
- IP address white-listing might be required to obtain the connection.
- Timestamp precision is 3 or more (microseconds or milliseconds).
- Trading session is not to reset sequence number on logon.
- Market data session is to reset sequence number on logon.

Standard Messages [↗](#)

- Standard Header [↗](#)

A standard set of fields to form the header of the FIX message.

Tag	Field name	Required	Description
8	BeginString	Y	Identifies beginning of new message and protocol version (always first field in message)
9	BodyLength	Y	Message length (in bytes) forward to the CheckSum field (always second field in message)
35	MsgType	Y	Defines message type (always 3rd tag in message)
49	SenderCompID	Y	Assigned value used to identify the sending messages (will be provided by the Maker)
56	TargetCompID	Y	Assigned value used to identify receiving party (will be provided by the Maker)
34	MsgSeqNum	Y	Integer message sequence number
50	SenderSubID	N	Optional. Assigned value used to identify specific message originator (desk trader etc.) (will be provided by the Maker if necessary)
52	SendingTime	Y	Message transmission time in UTC/GMT

- Standard Trailer [↗](#)

A standard set of fields to form the trailer of the FIX message.

Tag	Field name	Required	Description
10	Checksum	Y	Three digit character representing the checksum value of the message

Session Messages (Admin Messages) [↗](#)

- Heartbeat (MsgType=0) [↗](#)

To be sent/received on a predefined interval basis as mentioned in the Logon message (A). Otherwise, 30 seconds be default.

Tag	Field name	Required	Description
-----	------------	----------	-------------

	Standard Header	Y	MsgType=0
112	TestReqID	N	Required when the heartbeat is the result of a Test Request message
	Standard Trailer	Y	

- Test Request (MsgType=1) [🔗](#)

For the purpose of testing the connectivity and responsiveness of the other party.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=1
112	TestReqID	Y	A unique identifier for this test message
	Standard Trailer	Y	

- Logon (MsgType=A) [🔗](#)

Handshake logon initiated by the Centroid Bridge and confirmed by Maker.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=A
98	EncryptMethod	Y	Use of Encryption set to 0
108	HeartBtInt	Y	Heartbeat interval in seconds
141	ResetSeqNumFlag	N	Indicates both sides of a FIX session should reset sequence numbers
553	Username	Y	Username
554	Password	Y	Password
	Standard Trailer	Y	

- Logout (MsgType=5) [🔗](#)

Handshake logout initiated by the Centroid Bridge/Maker and confirmed by the other party.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=5
58	Text	N	Reason for logout

	Standard Trailer	Y	
--	------------------	---	--

- Resend Request (MsgType=2) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=2
7	BeginSeqNo	Y	
16	EndSeqNo	Y	
	Standard Trailer	Y	

- Reject (MsgType=3) [↗](#)

Session Level reject message.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=3
45	RefSeqNum	Y	MsgSeqNum of rejected message
371	RefTagID	N	The tag number of the FIX field being referenced
372	RefMsgType	N	The MsgType of the FIX message being referenced
373	SessionRejectReason	N	Code to identify reason for a session-level
	Standard Trailer	Y	

- Business Reject (MsgType=j) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=j
45	RefSeqNum	N	MsgSeqNum (34) of rejected message.
371	RefTagID	Y	The tag number of the FIX field being referenced.
372	RefMsgType	Y	Message Type being referenced.
380	BusinessRejectReason	Y	Code to identify reason for a Business Message Reject (j) message.
58	Text	Y	Where possible, message to explain reason for rejection.

	Standard Trailer	Y	
--	------------------	---	--

- Sequence Reset (MsgType=4) [🔗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=4
123	GapFillFlag	N	Gap fill flag to determine the need to fill the gap of sequence or no.
36	NewSeqNo	Y	The new sequence number requested
	Standard Trailer	Y	

Market Data Session Messages [🔗](#)

- Market Data Request (MsgType=V) [🔗](#)

Sent by Centroid Bridge to the Maker to subscribe to a stream of market data pricing. This is to be sent a message per symbol.

Tag	Field name	Required	Description
	Standard header	Y	MsgType=V
262	MDReqID	Y	Unique request id.
263	SubscriptionRequestType	Y	[1 = Snapshot plus updates (subscribe)] [2 = Disable previous snapshot plus update request (unsubscribe)]
264	MarketDepth	Y	Specifies the number of layers requested [Should be > 0].
7533	StreamReference	N	Specifies the stream. Only needed if the Centroid Bridge is configured for more than one streams.
267	NoMDEntryTypes	Y	required but not functional currently
269	MDEntryType	Y	[0: Bid] [1: Ask] required but not functional currently
146	NoRelatedSym	Y	Always set to 1
55	Symbol	Y	Name of the symbol
	Standard Trailer	Y	

- Market Data Request Reject (MsgType=Y) [🔗](#)

A reject response to an invalid market data request (V)

Tag	Field name	Required	Description
-----	------------	----------	-------------

	Standard Header	Y	MsgType=Y
262	MDReqID	Y	ID of the market data request
58	Text	N	Reason for market data request being rejected
	Standard Trailer	Y	

- Market Data Snapshot Full Refresh (MsgType=W) [↗](#)

Symbol-wise, a full refresh of the full depth of the book is to be sent by the Maker to the Centroid Bridge in real-time manner as a response to the subscription request.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=W
262	MDReqID	Y	Refers to the MDReqID of the request
55	Symbol	Y	Symbol to trade on
268	NoMDEntries	Y	Number of entries following
269	MDEntryType	Y	[0: Bid] [1: Ask]
270	MDEntryPx	N	Price of the Market Data Entry.
271	MDEntrySize	N	Quantity or volume represented by the Market Data Entry.
273	MDEntryTime	N	Market Data Entry Time
	Standard Trailer	Y	

Trading Session Messages [↗](#)

- New Order Single (MsgType=D) [↗](#)

Sent by Centroid Bridge to the Maker to request for a trade.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=D
11	ClOrdID	Y	Must be unique identifier sent by the Centroid Bridge. Used for response. Allowed characters A-Z, a-z, ., -, _
1	Account	Y	Account name as provided by the Maker
55	Symbol	Y	Symbol to trade on
54	Side	Y	Side of order: [1 = Buy] [2 = Sell]

38	OrderQty	Y	Order Quantity
40	OrdType	Y	Type of order: [1 = Market] [2=Limit] [3=Stop]
59	TimeInForce	Y	GTC, IOC, FOK (Time in force execution may vary depending on the execution settings on the broker's interface)
44	Price	C	Required when OrdType"40" =2 (Limit). Otherwise, ignored.
60	TransactTime	Y	Timestamp of order request
78	NoAllocs	N	number of allocation accounts if using trades allocation
79	AllocAccount	C	TEM to allocate trade under – mandatory if using tag 78
80	AllocQty	C	quantity to be allocated – mandatory if using tag 78
661	AllocAcctIDSour ce	C	Allocation: [0=A Alloc] [1=B Alloc] (Default is 0) - Optional
90000	TTL	N	Time to live (milliseconds)
90001	Login	N	External trader's login can be passed here
90002	Group	N	External trader's Group
90003	Ticket	N	External Order Ticket number
90008	Deviation	N	Should be decimal number
90009	Contract Size	N	External Contract size for instrument. e.g for EURUSD 100000
132	Bid	N	External trader's Bid Price
133	Ask	N	External trader's Ask Price
	Standard Trailer	Y	

- Order Cancel Request (MsgType=F) [🔗](#)

Available if (MsgType=D, Tag"40"=2, Tag"59"=1"GTC") is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=F
11	ClOrdID	Y	Must be unique identifier sent by the Centroid Bridge. Used for response
1	Account	Y	Target account name as provided by the Maker
41	OrigClOrdID	Y	The ClOrdID of the order to be cancelled
54	Side	Y	Side of order:[1 = Buy] [2 = Sell]
60	TransactTime	Y	Timestamp of the cancel request

	Standard Trailer	Y	
--	------------------	---	--

- Order Cancel Replace Request (MsgType=G) [↗](#)

Available if (MsgType=D, Tag"40"=2, Tag"59"=1"GTC") is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=G
11	ClOrdID	Y	Must be unique identifier sent by the Centroid Bridge. Used for response
1	Account	Y	Target account name as provided by the Maker
41	OrigClOrdID	Y	The ClOrdID of the order to be replaced
54	Side	N	Side of order:[1 = Buy] [2 = Sell]
38	OrderQty	N	Order Quantity
40	OrdType	N	Type of order: [1 = Market] [2=Limit] [3=Stop]
59	TimeInForce	N	GTC, IOC, FOK
44	Price	N	Required when OrdType"40" =2 (Limit). Otherwise, ignored.
60	TransactTime	Y	Timestamp of the cancel request
	Standard Trailer	Y	

- Order Cancel Reject (MsgType=9) [↗](#)

Available if (MsgType=F) is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=9
37	OrderID	Y	Maker Order ID. Can be N/A or NONE indicating no order found.
11	ClOrdID	Y	Order Cancel Request (F) ClOrdID.
39	OrdStatus	Y	The Order Status of the order being cancelled.
41	OrigClOrdID	Y	The ClOrdID of the order to be cancelled.
102	CxlRejReason	Y	Reason of rejecting the Order Cancel Request.
434	CxlRejResponse To	Y	Order Cancel Request (F) message.
60	TransactTime	Y	Timestamp of reject response.

	Standard Trailer	Y	
--	------------------	---	--

- Order Status Request (MsgType=H) [↗](#)

To be sent by Centroid to request for the status of a trade

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=H
37	OrderID	C	Maker Order ID.
11	ClOrdID	Y	The ClOrdID of the order to be requested.
1	Account	Y	The Target account initiated the requested order.
	Standard Trailer	Y	

- Execution Report (MsgType=8) [↗](#)

A response to New Order Single Message (D).

Order Execution Report

- C - Conditionally required
- Y - Required
- N - Not required

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=8
11	ClOrdID	Y	Unique identifier sent by the Centroid Bridge. Used for response
17	ExecID	Y	Unique identifier of execution message assigned by the Maker
150	ExecType	Y	The execution report type. [0 = New] [1 = Partially Filled] [2 = Filled] [4 = Canceled] [8 = Rejected]
55	Symbol	Y	Symbol name
54	Side	Y	Side of order [1= Buy] [2= Sell]
38	OrderQty	Y	Order Quantity
40	OrdType	Y	[1= Market], [2= Limit], [3= Stop]
32	LastQty	C	Fill Quantity
59	TimeInForce	Y	TimeInForce
37	OrderID	Y	Maker order ID

39	OrdStatus	Y	Current order state. [0 = New] [1 = Partially filled] [2 = Filled] [4 = Canceled] [8 = Rejected]
41	OrigClOrdID	C	The ClOrdID of the order to be cancelled.
31	LastPx	C	Price of this fill.
151	LeavesQty	C	Remaining quantity open for execution
14	CumQty	C	Cumulative quantity executed
6	AvgPx	C	Average price of executed quantity
44	Price	N	Price of the Limit order
58	Text	Y	Free format text string
60	TransactTime	Y	Time of the transaction
	Standard Trailer	Y	

Examples of FIX Messages [↗](#)

Market Data Request (V) [↗](#)

20230424-13:56:40.788831000 : 8=FIX.4.4|9=140|35=V|34=2934|49=CENTROID_SOL|52=20230424-13:56:40.788|56=TestMaker|146=1|55=EURUSD|262=EURUSD|263=1|264=5|265=0|267=2|269=0|269=1|10=139|

Market Data Request Reject (Y) [↗](#)

20230424-13:56:40.788831000: 8=FIX.4.4|9=134|35=Y|34=5|49=TestMaker|52=20230424-13:56:40.822|56=CENTROID_SOL|58=Failed to Unsubscribe Symbol: EURUSD|262=USplain_feed2||EURUSD|10=037|

Market Data Snapshot Full Refresh (W) [↗](#)

20230425-11:22:17.090340000: 8=FIX.4.4|9=717|35=W|34=8292277|49=TestMaker|52=20230425-11:22:17.082073|56=CENTROID_SOL|55=EURUSD|262=EURUSD|268=10|269=0|270=1.1021500000|271=23230000.0000000000|273=11:22:17|269=1|270=1.1023200000|271=38267000.0000000000|273=11:22:17|269=0|270=1.1021300000|271=60138000.0000000000|273=11:22:17|269=1|270=1.1023400000|271=82791000.0000000000|273=11:22:17|269=0|270=1.1021000000|271=227976000.0000000000|273=11:22:17|269=1|270=1.1023700000|271=229370000.0000000000|273=11:22:17|269=0|270=1.1020800000|271=437803000.0000000000|273=11:22:17|269=1|270=1.1023900000|271=408756000.0000000000|273=11:22:17|269=0|270=1.1020300000|271=748278000.0000000000|273=11:22:17|269=1|270=1.1024400000|271=601038000.0000000000|273=11:22:17|10=100|

New Order Single (D) [↗](#)

20230425-10:14:38.668706000 8=FIX.4.4|9=197|35=D|34=6988|49=CENTROID_SOL|52=20230425-10:14:38.668|56=TestMaker|1=Test_tem|11=437033_1|15=EUR|21=1|38=1000|40=2|44=1.10309|54=1|55=EURUSD|59=3|60=20230425-10:14:38.667|90008=5|10=153|

New Order Single (D) with Trades Allocation [↗](#)

20230425-10:14:38.668706000 8=FIX.4.4|9=197|35=D|34=6988|49=CENTROID_SOL|52=20230425-10:14:38.668|56=TestMaker|1=Test_tem|11=437033_1|15=EUR|21=1|38=1000|40=2|44=1.10309|54=1|55=EURUSD|59=3|60=20230425-

10:14:38.667|90008=5|78=1|79=tem_alloc_1|80=1000|10=108|

Execution Report (8) [🔗](#)

20230425-10:17:01.148752000: 8=FIX.4.4|9=323|35=8|34=6995|49=TestMaker|52=20230425-
10:17:01.145224|56=CENTROID_SOL|1=Test_tem|6=0.0000000000|11=437035_1|14=0.0000000000|17=239950|31=0.0000000000|32=
0.0000000000|37=239950|38=10000.0000000000|39=0|40=2|44=1.1030200000|54=1|55=EURUSD|58=New
Request|59=3|60=20230425-10:17:01|150=0|151=10000.0000000000|10=046|

Logon (A) [🔗](#)

20230425-11:34:14.269361000: 8=FIX.4.4|9=126|35=A|34=1|49=CENTROID_SOL|52=20230425-
11:34:14.268|56=TestMaker|98=0|108=30|141=Y|553=Username|554=Password|10=032|

20230425-11:34:14.325168000: 8=FIX.4.4|9=95|35=A|34=1|49=TestMaker|52=20230425-
11:34:14.281412|56=CENTROID_SOL|98=0|108=30|141=Y|10=246|

Heartbeat (0) [🔗](#)

20230425-11:32:01.259575000: 8=FIX.4.4|9=77|35=0|34=7143|49=CENTROID_SOL|52=20230425-11:32:01.259|56=TestMaker|10=165|

Centroid Taker FIX API

Centroid FIX 4.4 Trading API Specification v0.16.8 [↗](#)

Changelogs [↗](#)

Date	Version	Changes
30-10-2024	v0.16.9	Added Optional tags under New Order: Security and Direction
24-01-2023	v0.16.8	Added Order Cancel Replace Request Details/ Enabled GTC Limit & Stop
14-10-2022	v0.16.7	OrigClOrdID tag 41 is now available in the FIX Execution report when requesting Limit Order Cancel/Replace
23-05-2022	v0.16.6	Added trades allocation tags 78, 79, 80, and 661 in new order with example
25-08-2020	v0.16.5	MDEntryType tag269 added to MarketDataRequest message (V) as required NoMDEntry tag267 added to MarketDataRequest message (V) as required Validation on ClOrdID tag11 added in NewOrderSingle message (D)

Messages [↗](#)

As defined in the FIX protocol, the Centroid FIX server is using two different data levels: Session and Application. The Session level handles the delivery of data and the Application level defines the business-related data content. The following session and application messages are supported by the Centroid FIX Engine

Standard messages [↗](#)

1. Standard header
2. Standard trailer

Session messages [↗](#)

1. Heartbeat (Client Centroid)
2. Test Request (Client Centroid)
3. Logon (Client Centroid)
4. Logout (Client Centroid)
5. Resend Request (Client Centroid)
6. Reject (Client Centroid)
7. Business Reject (Client Centroid)
8. Sequence Reset (Client Centroid)

Application messages [↗](#)

- Market Data Session [↗](#)

1. Market Data Request (Client)
2. Market Data Request Reject (Centroid)

3. Market Data Snapshot Full Refresh (Centroid)

- Trading Session [↗](#)

1. New Order Single (Client)
2. Order Cancel Request (Client)
3. Order Cancel Replace Request (Client)
4. Order Cancel Reject (Centroid)
5. Order Status Request (Client)
6. Execution Report (Client)

Important notes [↗](#)

- All time formats in the system are UTC.
- Session timings are to be communicated with the Broker.
- IP address white-listing might be required to obtain the connection.
- Timestamp precision is 3 or more (microseconds or milliseconds).
- Trading session is not to reset sequence number on logon.
- Market data session is to reset sequence number on logon.

Standard Messages [↗](#)

- Standard Header [↗](#)

A standard set of fields to form the header of the FIX message.

Tag	Field name	Required	Description
8	BeginString	Y	Identifies beginning of new message and protocol version (always first field in message)
9	BodyLength	Y	Message length (in bytes) forward to the CheckSum field (always second field in message)
35	MsgType	Y	Defines message type (always 3rd tag in message)
49	SenderCompID	Y	Assigned value used to identify the client sending messages (will be provided by Centroid)
56	TargetCompID	Y	Assigned value used to identify receiving party (will be provided by Centroid)
34	MsgSeqNum	Y	Integer message sequence number
50	SenderSubID	N	Optional. Assigned value used to identify specific message originator (desk trader etc.) (will be provided by Centroid if necessary)
52	SendingTime	Y	Message transmission time in UTC/GMT

- Standard Trailer [↗](#)

A standard set of fields to form the trailer of the FIX message.

Tag	Field name	Required	Description
-----	------------	----------	-------------

10	Checksum	Y	Three digit character representing the checksum value of the message
----	----------	---	--

Session Messages (Admin Messages) [↗](#)

- Heartbeat (MsgType=0) [↗](#)

To be sent/received on a predefined interval basis as mentioned in the Logon message (A). Otherwise, 30 seconds be default.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=0
112	TestReqID	N	Required when the heartbeat is the result of a Test Request message
	Standard Trailer	Y	

- Test Request (MsgType=1) [↗](#)

For the purpose of testing the connectivity and responsiveness of the other party.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=1
112	TestReqID	Y	A unique identifier for this test message
	Standard Trailer	Y	

- Logon (MsgType=A) [↗](#)

Handshake logon initiated by the client and confirmed by Centroid.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=A
98	EncryptMethod	Y	Use of Encryption set to 0
108	HeartBtInt	Y	Heartbeat interval in seconds
141	ResetSeqNumFlag	N	Indicates both sides of a FIX session should reset sequence numbers
553	Username	Y	Username
554	Password	Y	Password
	Standard Trailer	Y	

- Logout (MsgType=5) [↗](#)

Handshake logout initiated by the Centroid/Client and confirmed by the other party.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=5
58	Text	N	Reason for logout
	Standard Trailer	Y	

- Resend Request (MsgType=2) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=2
7	BeginSeqNo	Y	
16	EndSeqNo	Y	
	Standard Trailer	Y	

- Reject (MsgType=3) [↗](#)

Session Level reject message.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=3
45	RefSeqNum	Y	MsgSeqNum of rejected message
371	RefTagID	N	The tag number of the FIX field being referenced
372	RefMsgType	N	The MsgType of the FIX message being referenced
373	SessionRejectReason	N	Code to identify reason for a session-level
	Standard Trailer	Y	

- Business Reject (MsgType=j) [↗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=j

45	RefSeqNum	N	MsgSeqNum (34) of rejected message.
371	RefTagID	Y	The tag number of the FIX field being referenced.
372	RefMsgType	Y	Message Type being referenced.
380	BusinessReject Reason	Y	Code to identify reason for a Business Message Reject (j) message.
58	Text	Y	Where possible, message to explain reason for rejection.
	Standard Trailer	Y	

- Sequence Reset (MsgType=4) [🔗](#)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=4
123	GapFillFlag	N	Gap fill flag to determine the need to fill the gap of sequence or no.
36	NewSeqNo	Y	The new sequence number requested
	Standard Trailer	Y	

Market Data Session Messages [🔗](#)

- Market Data Request (MsgType=V) [🔗](#)

Sent by the client to subscribe to a stream of market data pricing. This is to be sent a message per symbol.

Tag	Field name	Required	Description
	Standard header	Y	MsgType=V
262	MDReqID	Y	Unique request id.
263	SubscriptionRequestType	Y	[1 = Snapshot plus updates (subscribe)] [2 = Disable previous snapshot plus update request (unsubscribe)]
264	MarketDepth	N	Specifies the number of layers requested [Should be > 0].
7533	StreamReference	N	Specifies the stream. Only needed if a client is configured for more than one streams.
267	NoMDEntryTypes	Y	required but not functional currently
269	MDEntryType	Y	[0: Bid] [1: Ask] required but not functional currently
146	NoRelatedSym	Y	Always set to 1
55	Symbol	Y	Name of the symbol

	Standard Trailer	Y	
--	------------------	---	--

- Market Data Request Reject (MsgType=Y) [↗](#)

A reject response to an invalid market data request (V)

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=Y
262	MDReqID	Y	ID of the market data request
58	Text	N	Reason for market data request being rejected
	Standard Trailer	Y	

- Market Data Snapshot Full Refresh (MsgType=W) [↗](#)

Symbol-wise, a full refresh of the full depth of the book is to be sent by Centroid aggregator in real-time manner as a response to the subscription request.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=W
262	MDReqID	Y	Refers to the MDReqID of the request
55	Symbol	Y	Symbol to trade on
268	NoMDEntries	Y	Number of entries following
269	MDEntryType	Y	[0: Bid] [1: Ask]
270	MDEntryPx	N	Price of the Market Data Entry.
271	MDEntrySize	N	Quantity or volume represented by the Market Data Entry.
273	MDEntryTime	N	Market Data Entry Time
	Standard Trailer	Y	

Trading Session Messages [↗](#)

- New Order Single (MsgType=D) [↗](#)

Sent by the client to request for a trade.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=D

11	ClOrdID	Y	Must be unique identifier sent by the client. Used for response. Allowed characters A-Z, a-z, ., -, _
1	Account	Y	Account name as provided by Centroid
55	Symbol	Y	Symbol to trade on
54	Side	Y	Side of order: [1 = Buy] [2 = Sell]
38	OrderQty	Y	Order Quantity
40	OrdType	Y	Type of order: [1 = Market] [2=Limit] [3=Stop]
59	TimeInForce	Y	GTC, IOC, FOK (Time in force execution may vary depending on the execution settings on the broker's interface)
44	Price	C	Required when OrdType"40" =2 (Limit). Otherwise, ignored.
60	TransactTime	Y	Timestamp of order request
78	NoAllocs	N	number of allocation accounts if using trades allocation
79	AllocAccount	C	TEM to allocate trade under – mandatory if using tag 78
80	AllocQty	C	quantity to be allocated – mandatory if using tag 78
661	AllocAcctIDSource	C	Allocation: [0=A Alloc] [1=B Alloc] (Default is 0) - Optional
90000	TTL	N	Time to live (milliseconds)
90001	Login	N	External trader's login can be passed here
90002	Group	N	External trader's Group
90003	Ticket	N	External Order Ticket number
90008	Deviation	N	Should be decimal number
90009	Contract Size	N	External Contract size for instrument. e.g for EURUSD 100000
90013	Platform Security	N	Securities Folder Name
90014	Direction	N	Direction of the order: [1 = In] [2 = Out] Including this tag specifies the direction of trades as either 'IN' or 'OUT' for the respective order.
132	Bid	N	External trader's Bid Price
133	Ask	N	External trader's Ask Price
	Standard Trailer	Y	

- Order Cancel Request (MsgType=F) [🔗](#)

Available if (MsgType=D, Tag"40"=2, Tag"59"=1"GTC") is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=F
11	ClOrdID	Y	Must be unique identifier sent by the client. Used for response
1	Account	Y	Account name as provided by Centroid
41	OrigClOrdID	Y	The ClOrdID of the order to be cancelled
54	Side	Y	Side of order:[1 = Buy] [2 = Sell]
60	TransactTime	Y	Timestamp of the cancel request
	Standard Trailer	Y	

- Order Cancel Replace Request (MsgType=G) [↗](#)

Available if (MsgType=D, Tag"40"=2, Tag"59"=1"GTC") is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=G
11	ClOrdID	Y	Must be unique identifier sent by the client. Used for response
1	Account	Y	Account name as provided by Centroid
41	OrigClOrdID	Y	The ClOrdID of the order to be replaced
54	Side	N	Side of order:[1 = Buy] [2 = Sell]
38	OrderQty	N	Order Quantity
40	OrdType	N	Type of order: [1 = Market] [2=Limit] [3=Stop]
59	TimeInForce	N	GTC, IOC, FOK
44	Price	N	Required when OrdType"40" =2 (Limit). Otherwise, ignored.
60	TransactTime	Y	Timestamp of the cancel request
	Standard Trailer	Y	

- Order Cancel Reject (MsgType=9) [↗](#)

Available if (MsgType=F) is available.

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=9

37	OrderID	Y	Centroid Order ID. Can be N/A or NONE indicating no order found.
11	ClOrdID	Y	Order Cancel Request (F) ClOrdID.
39	OrdStatus	Y	The Order Status of the order being cancelled.
41	OrigClOrdID	Y	The ClOrdID of the order to be cancelled.
102	CxlRejReason	Y	Reason of rejecting the Order Cancel Request.
434	CxlRejResponse To	Y	Order Cancel Request (F) message.
60	TransactTime	Y	Timestamp of reject response.
	Standard Trailer	Y	

- Order Status Request (MsgType=H) [↗](#)

To be sent by the client to request for the status of a trade

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=H
37	OrderID	C	Centroid Order ID.
11	ClOrdID	Y	The ClOrdID of the order to be requested.
1	Account	Y	The account initiated the requested order.
	Standard Trailer	Y	

- Execution Report (MsgType=8) [↗](#)

A response to New Order Single Message (D).

Order Execution Report

- C - Conditionally required
- Y - Required
- N - Not required

Tag	Field name	Required	Description
	Standard Header	Y	MsgType=8
11	ClOrdID	Y	Must be unique identifier sent by the client. Used for response
17	ExecID	Y	Unique identifier of execution message assigned by Centroid Gateway
150	ExecType	Y	The execution report type. [0 = New] [1 = Partially Filled] [2 = Filled] [4 = Canceled] [8 = Rejected]

55	Symbol	Y	Symbol name
54	Side	Y	Side of order [1= Buy] [2= Sell]
38	OrderQty	Y	Order Quantity
40	OrdType	Y	[1= Market], [2= Limit], [3= Stop]
32	LastQty	C	Fill Quantity
59	TimeInForce	Y	TimeInForce
37	OrderID	Y	Centroid Gateway order ID
39	OrdStatus	Y	Current order state. [0 = New] [1 = Partially filled] [2 = Filled] [4 = Canceled] [8 = Rejected]
41	OrigClOrdID	C	The ClOrdID of the order to be cancelled.
31	LastPx	C	Price of this fill.
151	LeavesQty	C	Remaining quantity open for execution
14	CumQty	C	Cumulative quantity executed
6	AvgPx	C	Average price of executed quantity
44	Price	N	Price of the Limit order
58	Text	Y	Free format text string
60	TransactTime	Y	Time of the transaction
	Standard Trailer	Y	

Examples of FIX Messages [↗](#)

Market Data Request (V) [↗](#)

20170321-11:51:32.201632000 : 8=FIX.4.4|9=151|35=V|34=8|49=TraderSender|52=20170321-11:51:32.201|56=CENTROID_SOL|146=1|55=EURUSD|262=US1pip_feed||EURUSD|263=2|264=0|267=2|269=0|269=1|10=210|

Market Data Request Reject (Y) [↗](#)

20170321-11:51:24.201729000 : 8=FIX.4.4|9=134|35=Y|34=5|49=CENTROID_SOL|52=20170321-11:51:24.201850|56=TraderSender|58=Failed to Unsubscribe Symbol: EURUSD|262=USplain_feed2||EURUSD|10=037|

Market Data Snapshot Full Refresh (W) [↗](#)

20170321-11:51:33.083494000 : 8=FIX.4.4|9=183|35=W|34=6|49=CENTROID_SOL|52=20170321-11:51:33.083245|56=TraderSender|55=EURUSD_1|262=1|268=2|269=0|270=1.13882|271=1000000|273=11:51:33|269=1|270=1.13904|271=4000000|90007=1pip_feed|10=082|

20170321-11:55:43.514924000 : 8=FIX.4.4|9=182|35=W|34=16|49=CENTROID_SOL|52=20170321-11:55:43.514831|56=TraderSender|55=EURUSD_1|262=1|268=2|269=0|270=1.13908|271=986000|273=11:55:43|269=1|270=1.1393|271=2502000|10=069|

New Order Single (D) [🔗](#)

20170321-11:51:40.225951000 : 8=FIX.4.4|9=186|35=D|34=10|49=TraderSender|52=20170321-11:51:40.225|56=CENTROID_SOL|1=MT5_Plain|11=BI9NLJ5674FDPRD79NGG|38=1000|40=1|54=1|55=EURUSD_1|59=3|60=20170321-11:51:40.222|132=1.13882|133=1.13904|10=108|

New Order Single (D) with Trades Allocation [🔗](#)

20220320-14:31:41.33651000 : 8=FIX.4.4|9=186|35=D|34=10|49=TraderSender|52=20220320-14:31:41.336|56=CENTROID_SOL|1=tem_plain|11=DO9NLJ5674ASGJHASFHF|38=1000|40=1|54=1|55=EURUSD_1|59=3|60=20220320-14:31:41.330|78=1|79=tem_alloc_1|80=1000|10=108|

New Order Single (D) with Custom Tags [🔗](#)

20170321-11:51:40.225951000 : 8=FIX.4.4|9=186|35=D|34=10|49=TraderSender|52=20170321-11:51:40.225|56=CENTROID_SOL|1=tem_Plain|11=BI9NLJ5674FDPRD79NGG|38=1000|40=1|54=1|55=EURUSD_1|59=3|60=20170321-11:51:40.222|132=1.13882|133=1.13904|90001=101112|90002=real\group\Standard|90003=7863455|90013=Forex|90014=1|10=108|

Execution Report (8) [🔗](#)

20170321-11:51:40.228926000 : 8=FIX.4.4|9=277|35=8|34=8|49=CENTROID_SOL|52=20170321-11:51:40.228846|56=TraderSender|1=MT5_Plain|6=0|11=BI9NLJ5674FDPRD79NGG|14=0|17=000120170321000000000000|31=0|32=0|37=000120170321000000000000|38=1000|39=0|40=1|54=1|55=EURUSD_1|58=N/A|59=3|60=20170321-11:51:40|150=0|151=1000|9999=CenSystem|10=213|

Logon (A) [🔗](#)

20170321-11:54:01.992036000 : 8=FIX.4.4|9=117|35=A|34=1|49=TraderSender|52=20170321-11:54:01.991|56=CENTROID_SOL|98=0|108=30|141=Y|553=Username|554=Password|10=063|


20170321-11:54:01.992804000 : 8=FIX.4.4|9=86|35=A|34=1|49=CENTROID_SOL|52=20170321-11:54:01.992734|56=TraderSender|98=0|108=30|141=Y|10=076|

Heartbeat (0) [🔗](#)

20170321-11:55:47.725747000 : 8=FIX.4.4|9=65|35=0|34=4|49=TraderSender|52=20170321-11:55:47.725|56=CENTROID_SOL|10=092|

MT4 Repository

Welcome to the section for setting up your Bridge and Feeder for MT4. Here, you'll find concise guides and the latest installer for a seamless setup experience.



MT4 Centroid Installers

MT4 Bridge Installer		
Version	Installer	Status
238	 Centroid_MT4_Bridge_v238.zip	Latest Version
237	 Centroid_MT4_Bridge_v237.zip	Recent Version
236	 Centroid_MT4_Bridge_v236.zip	Old Version

MT4 Feeder Installer		
Version	Installer	Status
101	 Centroid_MT4_Feeder_v101.zip	Latest Version

MT4 Bridge Operations		
Version	Installer	Status
103	 Centroid_MT4_Operations_v103.zip	Latest Version

MT4 Centroid Feeder Manual

Essential Setup Information [🔗](#)


Before initiating the setup for the Centroid MT4 Feeder, you'll need to provide the following information to whitelist your IPs:

1. Provide the IP or DNS of all MT4 Live Servers where the MT4 Feeder will be installed
2. Provide the IP or DNS of all MT4 Live Backup Servers

Installation of MT4 Feeder [🔗](#)

Configuration Steps for Centroid MT4 Feeder

1. **Remote Server Access:** Remotely access the server hosting the MT4 Server using tools such as RDP or any other remote access method
2. **Stop MT4 Server:** Stop the MT4 Server through Windows Services by stopping the corresponding service named "MetaTrader 4 Server"
3. **File and Configuration Transfer:** Place the Centroid MT4 Feeder .feed File in the 'datafeed' Directory of Your MT4 Server Installation. The Path Typically Resides at D:\MetaTrader4Server\datafeed.
4. **Restart MT4 Server:** Initiate the MT4 Server once again through Windows Services by launching the relevant service named "MetaTrader 4 Server"
5. **Consistent Configuration on Backup Server:** Repeat the aforementioned steps on your MT4 Backup Server for ensuring consistent configuration



Configuration [🔗](#)

To set up the Centroid MT4 Feeder, follow these simple instructions:

1. Log in to MT4 Administrator and navigate to Data Feeds.
2. Add a new Data Feed.
3. Configure the newly added Data Feed with the following details:
 - **Name:** Enter the name of the configured feeder.
 - **Type:** Select "Quotes" from the dropdown list.
 - **File:** Locate the feeder file uploaded to the feeder folder on the MT4 Server, ensuring it matches the exact name.
 - **Server:** Provide the DNS and Port details given by Centroid.
 - **Login:** Enter the trading login ID provided by Centroid.
 - **Password:** Input the trading password provided by Centroid.
 - **Keywords:** This optional field allows you to specify certain Symbols to be quoted via the Data Feed or excluded. Use "*" for wildcard or "!" for negation.

Data Feed

Data Feed provides receiving quotes and news. Choose an appropriate source, data type, then enter authorization data.

☒ Enable

Name: Centroid UniFeeder Quotes

File: centroid_unifeeder.feed Description

Server: xxx.xxx.xxx.7:xxxx(Port) Journal

Login: Username Password: •

Keywords: Language: Any language

Timeouts

Idle timeout: 120 seconds, reconnect after 5 seconds

Sleep for: 60 seconds after 5 attempts

OK Cancel

Config - Centroid_MT4

Feeding Trading Both Feeder

Key	Value
Username	Username
Password	6
IP access	
Host	xxx.xxx.xxx.7:xxxx(Port)

Updating the Feeder [🔗](#)

When upgrading the Centroid MT4 Feeder to a newer version, adhere to the following steps, ensuring the new folder supersedes the old one for simplicity:

1. **Access the Server:** Remotely access the server where the MT4 Server is installed, using RDP or any other tool.
2. **Backup the Old Version:** Create a backup by copying the existing Centroid feeder to another folder. This backup ensures you can easily revert the update if needed.
3. **Stop MT4 Server:** Stop the MetaTrader 4 Server from Windows Services by stopping the relevant service, "MetaTrader 4 Server."
4. **Replace the File:** Override the existing feeder by copying the new Centroid Feeder .feed file into the "datafeed" folder of your MT4 Server installation.
5. **Restart MT4 Server:** Start the MetaTrader 4 Server from Windows Services by initiating the relevant service, "MetaTrader 4 Server."
6. **Version Monitor:** In the MT4 Administrator, monitor the disabled feeder's version under status. Once the correct version is loaded successfully, enable the Feeder.
7. **Enable the Centroid Feeder:** Re-enable the Feeder from the MT4 Administrator.

MT4 Centroid Bridge Manual

Essential Setup Information [🔗](#)


Before initiating the setup for the Centroid MT4 Bridge plugin, you'll need to provide the following information to whitelist your IPs:

1. Provide the IP or DNS of all MT4 Live Servers where the MT4 Bridge Plugin will be installed
2. Provide the IP or DNS of all MT4 Live Backup Servers

Installation of the MT4 Bridge Plugin [🔗](#)

To set up the Centroid MT4 Bridge Plugin, simply follow the below instructions:

1. **Remote Server Access:** Remotely access the server hosting the MT4 Server using tools such as RDP or any other remote access method
2. **Stop MT4 Services:** Stop the MT4 Server through Windows Services by stopping the corresponding service named "MetaTrader 4 Server"
3. **File and Configuration Transfer:** Transfer the .dll file and the configuration folder for the bridge to the "plugins" directory within your MT4 Server. The directory path is typically similar to D:\MetaTrader4Server\plugins
4. **Restart MT4 Server:** Initiate the MT4 Server once again through Windows Services by launching the relevant service named "MetaTrader 4 Server"
5. **Configuration on Backup Server:** Repeat the aforementioned steps on your MT4 Backup Server




Important Note: Restart Required After Initial Installation and Configuration


Please be advised that a restart of the MT4 Server is essential after the initial installation and configuration of the Centroid MT4 Bridge Plugin. This step ensures proper activation and integration of the plugin into the MT4 Server environment. Kindly follow the outlined instructions in the documentation to seamlessly complete the setup process.

Configuration [🔗](#)

Required Configuration Parameters for Establishing MT4 Server and Centroid Bridge Connection:



Obtain the credentials from the bridge Takers -> Config



Updating the MT4 Bridge Plugin [↗](#)

When upgrading the Centroid MT4 Bridge Plugin to a newer version, adhere to the following steps, ensuring the new folder supersedes the old one:

The below process ensures a seamless transition, with the only exception being the temporary cessation of the MT4 Server during the .dll file replacement. The subsequent steps outline the update procedure for better clarity:


1. **Remote Server Access:** Remotely log in to the server hosting the MT4 Server using tools like RDP or any other suitable method

2. **Create a Backup:** As a precautionary measure, copy the existing Centroid MT4 Bridge plugin and its folder to another directory This backup ensures the ability to revert the update if necessary
3. **Stop MT4 Server:** Halt the MT4 Server through Windows Services by stopping the relevant service, "MetaTrader 4 Server"
4. **Replace Plugin Files:** Copy the new Centroid MT4 Bridge Plugin .dll and its folder into the "plugins" directory within your MT4 Server installation This action effectively replaces the existing plugin files
5. **Restart MT4 Server:** Restart the MT4 Server through Windows Services by initiating the relevant service, "MetaTrader 4 Server"
6. **Apply Update to Backup Server:** Repeat the same update steps on your MT4 Backup Server for consistency across your environment

By adhering to these instructions, the process of updating the Centroid MT4 Bridge Plugin is streamlined, ensuring a smooth transition to the latest version while maintaining the integrity of your trading infrastructure

Setting up the MT4 Bridge Plugin [🔗](#)

To Set-up the Centroid Bridge Plugin in your MT4, please follow the steps outlined below:



Details available in the Centroid UI "Taker -> Config"

Let's categorize the parameters into two groups:

General Parameters [🔗](#)

Required Configuration Parameters for Establishing MT4 Server and Centroid Bridge Connection:

Name	Value	Explanation
User	Taker_Name (Centroid_MT4)	Description: Specifies the username associated with the FIX session Configuration: Enter the designated username for authentication
Password	b#4592A	Description: Denotes the password corresponding to the FIX session Configuration: Input the specific password required for authentication
Sender	TD_Taker_Name (TD_Centroid_MT4)	Description: Represents the Sender Comp ID of the FIX session (TD_Username)

		Configuration: Provide the Sender Comp ID associated with the FIX session
Host	Bridge IP/DNS	Description: Specifies the IP address or DNS of the Centroid Bridge Configuration: Input the accurate IP address or DNS information for the Bridge
Port	1245, 1523, 100011	Description: Denotes the target port for the FIX session Configuration: Specify the target port number required for connecting to the FIX session

- Define the "Execution Rules / Routing Rules"

The routing rules determine how trades from various MT4 Groups, Logins, Groups of Symbols, or Symbols are directed to specific accounts or Taker Execution Models (TEM) on the Centroid Bridge

Explanation:

sec = group of symbols (Example: Forex\Major)

sy = symbols

g = groups

ac = accounts / logins

tem = Taker Execution Model on the "Centroid Bridge"

1. No Filters

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.x.x.x.x.x.x.9
Port	12542
AccCfg.1	sec="*;g="*;tem=Test_TEM

Add Delete

OK Cancel

Parameter	Value	Description
AccCfg.1	sec="*;g="*;tem=Test_TEM	This rule defines all the securities and all the groups will target one Taker Execution Model "TEM" ie Test_TEM

2. Group Filter

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.x.9
Port	12542
AccCfg.1	sec=*;g=ABC\USD;tem=TEM-1

Add Delete

OK Cancel

Parameter	Value	Description
AccCfg.1	sec=*;g=ABC\USD;tem=TEM-1	This rule defines all the securities from a specific group ie "ABC/USD" will target to TEM → TEM-1
AccCfg.2	sec=*;g=ABC\USD,TestonlyIA-1,TestonlyIB-2;tem=TEM-1	This rule defines Multiple Groups Targeting one TEM → TEM-1
AccCfg.3	sec=*;g=Testonly*;tem=5points_TEM	This rule defines All the Groups under Testonly\ Targeting one TEM → 5points_TEM

3. Symbol and Group Filter

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.x.9
Port	12542
AccCfg.1	sy=EURUSD.test;g=NYZ\USD;tem=TEM-2

Add Delete

OK Cancel

Parameter	Value	Description
AccCfg.1	sy=EURUSDtest;g=NYZ\USD;tem=TEM-2	This rule defines only symbol "EURUSDtest" from the group "NYZ\USD" will target to TEM → TEM-2
AccCfg.2	sy=EURUSDtest,GBPUSDtest;g=NYZ\USD;tem=TEM-2	This rule defines Multiple Symbols from the group "NYZ\USD" will target to TEM → TEM-2

AccCfg.3	sy=EUR*;g=NYZUSD,Testonly\A1;tem=TEM-2	This rule defines All EUR symbols from specific two groups will target TEM → TEM-2
----------	--	--

4. Account Filter

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.x.x.9
Port	12542
AccCfg.1	sy=*;ac=100012;tem=Plain_TEM

Add Delete OK Cancel

Parameter	Value	Description
AccCfg.1	sy=*;ac=100012;tem=Plain_TEM	This rule defines all the symbols available in the login 100012 will target to TEM → Plain_TEM
AccCfg.2	sy=*;ac=100012,100015,102256;tem=Plain_TEM	This rule defines Multiple Accounts/Logins Targeting one TEM → Plain_TEM

Note: It is recommended to place the Account Rules on top followed by the Group Rules. In the MT4 plugin, it is not feasible to rearrange rules by moving them from the top to the bottom or vice versa using drag & drop. To accomplish this, one must update the configuration number (AccCfg) and the plugin will automatically adjust the rule's positioning.

An example is provided below:

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.x.x.9
Port	12542
AccCfg.1	sec=*;g=ABC(USD;tem=TEM-1
AccCfg.2	sy=*;ac=100012;tem=Plain_TEM

Add Delete OK Cancel

Group Rule

Account Rule

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup
 ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.x00.x.x.x00.9
Port	12542
AccCfg.2	sec="";g=ABC\USD;tem=TEM-1
AccCfg.1	sy="";ac=100012;tem=Plain_TEM

Change Config Number and Click Ok

Rules in the Centroid MT4 Bridge Plugin are sorted by the numerical values following "AccCfg." The order matters, as the plugin processes orders based on the first matching rule

Additional Parameters [🔗](#)

Configure these parameters to utilize the add-on features provided by the "Centroid Bridge"

1. STP Configurations Guide

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup
 ☐ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
Sender	TD_Taker_Name
Host	x.x00.x.x.x00.9
Port	12542
FullStpSecurities	Crypto
FullStpSymbols	XAUUSD
FullStpGroups	Testonly*
FullStpLogins	101215


Name / Parameter 🔗	Value	Explanation
FullStpSecurities	FX,Crypto	This feature designates a set of securities for which trades will be sent to the Bridge as 100% STP, regardless of the percentage defined in the Bridge under TEM Please note that routing to the Bridge adheres to established rules, but trades for symbols within the specified securities will be executed as 100% STP
FullStpSymbols	XAUUSD	This setting identifies a list of symbols for which trades will be directed to the Bridge as 100% STP, regardless of the percentage specified in the Bridge under TEM Please be aware that routing to the Bridge continues to adhere to defined rules, but trades for the specified symbols will be executed as 100% STP

FullStpGroups	NYZUSD,Testonly*	This configuration designates a set of MT4 groups, ensuring that trades from these groups are sent to the Bridge as 100% STP, regardless of the percentage specified in the Bridge under TEM It's important to note that while routing to the Bridge adheres to predefined rules, trades associated with logins under the specified groups will be executed as 100% STP
FullStpLogins	1012,10156	This configuration defines a list of MT4 logins, ensuring that trades from these logins are directed to the Bridge as 100% STP, regardless of the percentage specified in the Bridge under TEM It's important to note that while routing to the Bridge continues to adhere to established rules, trades corresponding to the specified logins will be executed as 100% STP

Note: Adding Multiple Symbols, Securities, Groups, and Logins

You can include multiple symbols, securities, groups, and logins in the respective parameter by using commas (",")

2. BBook Configurations Guide



Name / Parameter	Value	Explanation
FullBBSecurities	Forex/Major	This configuration allows you to specify a list of securities for which trades will be directed to the Bridge as 100% B-Book, irrespective of the percentage set in the Bridge under TEM While routing to the Bridge continues to follow predefined rules, trades associated with the specified symbols will be executed exclusively as 100% B-Book
FullBBSymbols	EURUSD,GBPUSD	This setting lets you choose certain symbols, ensuring that all their trades are consistently processed as 100% B-Book in the Bridge Even though regular routing rules to the Bridge remain in place, the specified symbols will be handled exclusively as 100% B-Book
FullBBGroups	Testonly\B-7	This configuration allows you to designate specific MT4 groups, ensuring that all trades from these groups are consistently processed as 100% B-Book in the Bridge

		While the regular routing rules to the Bridge apply, trades associated with logins under the specified groups will be executed exclusively as 100% B-Book
FullIBBLLogins	558941	This setting enables the selection of specific MT4 logins, ensuring that all trades from these logins are consistently processed as 100% B-Book in the Bridge While the regular routing rules to the Bridge apply, trades corresponding to the specified logins will be executed exclusively as 100% B-Book

Note: Adding Multiple Symbols, Securities, Groups, and Logins

You can include multiple symbols, securities, groups, and logins in the respective parameter by using commas (",")

3. Exclusion Configurations in the Plugin

Plugin: Centroid Bridge 1.00

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☒ Enable plugin profiling
☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xox.x.x.xox.9
Port	12542
IgnoreGroups	Testonly\A-10
IgnoreLogins	559920

Add Delete OK Cancel

Name / Parameter	Value	Explanation
IgnoreGroups	Testonly\A-10	Specify groups here, and the Centroid MT4 Bridge plugin will completely disregard their trades
IgnoreLogins	559920,558974	Specify logins here, and the Centroid MT4 Bridge plugin will completely disregard their trades

Note: Adding Multiple Groups and Logins

You can include multiple groups and logins in the respective parameter by using commas (",")

4. Trade Distinction through Configuration Comments

Plugin: Centroid Bridge light 2.38

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☒ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.xx.9
Port	12542
CommentOrder	cenid;sl;tp;so;giveup;

Add Delete OK Cancel

Name / Parameter	Value	Explanation
CommentOrder	cenid ;sl;tp;so;giveup;	The Centroid order ID will be included to orders initiated by a manager or pending limit orders.
CommentOrder	cenid; sl ;tp;so;giveup;	A "[sl] comment" will be attached to orders with activated stop loss.
CommentOrder	cenid;sl; tp ;so;giveup;	A "[tp] comment" will be appended to orders with activated take profit.
CommentOrder	cenid;sl;tp; so ;giveup;	A "[so] comment" will be appended to the account when Stop Out is Triggered.
CommentOrder	cenid;sl;tp;so; giveup ;	Centroid giveup order ID will be assigned to orders originating from Centroid giveup.

5. Managing Trade Frequency with 'PendingOrderLockTimeout'

Plugin: Centroid Bridge light 2.38

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☒ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.xx.9
Port	12542
PendingOrderLockTimeout	5

Add Delete OK Cancel

Name / Parameter	Value	Explanation
PendingOrderLockTimeout	5	This parameter enables you to regulate the initiation of limit/pending trades, aligning them with the prevailing prices in MT4. This level of customization empowers you to finely adjust trade frequency according to your preferences and market dynamics.

Note: When working with the "PendingOrderLockTimeout" configuration, it's important to understand the default, minimum, and maximum values:

- **Default Duration:** The default duration is set at 15 seconds.
- **Minimum Duration:** You can adjust the duration to a minimum of 3 seconds. If the configured value falls below 3 seconds, it will automatically revert to the default value of 15 seconds.
- **Maximum Duration:** The maximum duration can be set up to 60 seconds. If the configured value exceeds 60 seconds, it will automatically reset to the default value of 15 seconds.

6. Filtering Trades: Utilizing 'IgnoreManagers' Configuration

Plugin: Centroid Bridge light 2.38

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☒ Enable plugin profiling

☐ Configurable by managers

Parameters:

Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.xx.9
Port	12542
IgnoreManagers	10012

Add Delete

OK Cancel

Name / Parameter	Value	Explanation
IgnoreManagers	10012	Implementing the configuration parameter "IgnoreManagers" allows you to specify that any trades originating from a particular manager login, such as "10012," should be disregarded by the bridge. This configuration provides a precise method for selectively excluding trades from specific manager logins based on your requirements

7. Enhanced Order Configuration: Utilizing 'EnLimitClosePx'

Plugin: Centroid Bridge light 2.38

The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Load at server startup ☒ Enable plugin profiling

☐ Configurable by managers

Parameters:


Name	Value
User	Taker_Name
Password	b@#4589#
Sender	TD_Taker_Name
Host	x.xxx.x.x.xx.9
Port	12542
EnLimitClosePx	Y

Add Delete

OK Cancel

Name / Parameter	Value	Explanation
EnLimitClosePx	Y	EnLimitClosePx (Enable Limit Close Price): • Y (Yes - Default): Activate pending orders with the default spread and a negative profit. • N (No): Activate pending orders with zero spread and zero profit. In other words, when "Y" is chosen, pending orders will be triggered with the default spread and a negative profit. On the other hand, selecting "N" will activate pending orders with no spread (zero spread) and no profit.


8. Configuration to Force Price for Trading Accounts



Parameter	Value	Explanation
ForceManagerPx	Y: Yes (Manager can Force Prices) Not specified (Manager cannot Force Prices)	Enabling the "ForceManagerPx" parameter by setting it to 'Y' grants authority to Managers to force prices against the current market price on behalf of the trading account. Note: Enabling this config will impact all the Managers, i.e. All the Managers within the MT4 Admin can force prices.

MT5 Repository

Welcome to the section for setting up your Gateway and Feeder for MT5. Here, you'll find concise guides and the latest installer for a seamless setup experience.



MT5 Centroid Installers

MT5 Gateway Installer		
Version	Installer	Status
137	 Centroid_MT5_Gateway_v137.zip	Old Version
134	Centroid_MT5_Gateway_v134	No longer available
133	Centroid_MT5_Gateway_v133	No longer available

MT5 Top Of Book (TOB) Feeder Installer		
Version	Installer	Status
110	 Centroid_MT5_TOB_Feeder_v110.zip	Latest Version
109	 Centroid_MT5_TOB_Feeder_v109.zip	Old Version
108	Centroid_MT5_Feeder_v108	No longer available
107	Centroid_MT5_Feeder_v107	No longer available

MT5 Depth Of Market (DOM) Feeder Installer		
Version	Installer	Status
115	 Centroid_MT5_DOM_Feeder_v115.zip	Latest Version

MT5 Centroid TOB Feeder Manual

Essential Setup Information [🔗](#)


Before initiating the setup for the Centroid MT5 Feeder, you'll need to provide the following information to whitelist your IPs:

1. Provide the IP of all MT5 Live Servers where the MT5 Feeder will be installed.
2. Supply the IP of all MT5 Live Backup Servers.

Installation [🔗](#)

To configure the Centroid MT5 Feeder, follow the instructions below:

1. Remotely log in to the server where the MT5 Server is installed using RDP or another tool.
2. Copy the Centroid MT5 Datafeed folder into the "Feeder" directory of your MT5 History Server installation. ***"The path will resemble D or C:\MetaTrader 5 Platform\History\Datafeed."***




Note:

1. The installation process does not necessitate stopping the MT5 Service.
2. The Centroid MT5 Feeder will be automatically duplicated to the MT5 Backup Server.


Configuration [🔗](#)

To set up the Centroid MT5 Feeder:

1. Log into MT5 Administrator and navigate to Datafeed.
2. Add a new Datafeed.
3. Customize the newly added Feeder as follows:
 - **Name:** Specify the configured Feeder's name.
 - **Module:** Locate the Feeder file within the uploaded folder.
 - **Select:** Choose "Quotes" from the dropdown.
 - **Trading Server:** Provide the DNS and Port details given by Centroid.
 - **Trading Login:** Enter the trading login ID provided by Centroid.
 - **Password:** Input the trading password provided by Centroid.



Note: Make certain that all the Symbols intended for pricing by the Centroid Feeder are appropriately listed in the Symbols tabs, respectively.



Enhancing the Feeder [🔗](#)

When upgrading the Centroid MT5 TOB Feeder to a newer version, adhere to the following steps, ensuring the new folder supersedes the old one for simplicity:

To enhance the Centroid TOB MT5 Feeder, proceed with the following instructions:

1. **Access the Server:** Remotely access the server where the MT5 History Server is installed, using RDP or any other tool.
2. **Backup the Old Version:** Create a backup by copying the existing Centroid TOB Feeder to another folder, ensuring the ability to revert the update if needed.

i How to Backup:

Please ensure that the existing Centroid TOB Feeder is copied to a location outside the DataFeed folder (e.g., Desktop or any other preferred directory). This will prevent the backup file from appearing in the drop-down menu in MT5.

3. **Disable the Centroid Feeder:** Before replacing the file, it is recommended to disable the "Centroid TOB Feeder" from the MT5 Administrator.
4. **Replace the File:** Replace the existing Centroid TOB Feeder .exe file in the "Datafeed" folder of your MT5 History Server installation with the new one, maintaining the exact name.
5. **Version Monitor:** In the MT5 Administrator, monitor the disabled feeder's version under status. Once the correct version is loaded successfully, enable the Feeder.

6. **Enable the Centroid Feeder:** Re-enable the Feeder using the MT5 Administrator.

Pricing during the Weekend [🔗](#)

Do you offer CRYPTO? Are you expecting Prices during the Weekend? [🔗](#)



If you offer Crypto prices during the weekend, ensure the weekend pricing session is enabled on both SYMBOL and PLATFORM Levels on the MT4/MT5 side. [🔗](#)

Do this only if you are expecting Prices for Crypto During the WEEKEND. [🔗](#)

Symbol: AMA\BTCUSD.ama

Common Currency Quotes Trade Execution Margin Margin Rates Swaps **Sessions**

The setting up of trade and quotation sessions of the symbol by days. During the quotation session it is possible to view the price dynamics but trading is prohibited.

Day	Quotes	Trade
Sunday	00:00-24:00	00:00-24:00
Monday	00:00-24:00	00:00-24:00
Tuesday	00:00-24:00	00:00-24:00
Wednesday	00:00-24:00	00:00-24:00
Thursday	00:00-24:00	00:00-24:00
Friday	00:00-24:00	00:00-24:00
Saturday	00:00-24:00	00:00-24:00

☐ Use time limits From: 1970.01.01 00:00 To: 1970.01.01 00:00

OK Cancel Help

Security **Time** Holidays Groups (569) Clients & Accounts Orders & Deals Gateways Data Feeds Plugins

Day settings

Sunday	00:00-24:00
Monday	00:00-24:00
Tuesday	00:00-24:00
Wednesday	00:00-24:00
Thursday	00:00-24:00
Friday	00:00-24:00
Saturday	00:00-24:00



Scenario 1: If you Don't offer Crypto prices during the weekend, from any plugin apart from Centroid, then ensure the weekend pricing session is disabled on the SYMBOL

and PLATFORM Level at the MT4/MT5 side. [↗](#)

Scenario 2: If any other bridge/plugin is pricing for Crypto and Centroid Feeder is trying to connect, it is better to remove those symbols from the Centroid Feeder. [↗](#)

Do this only in the case of Scenario 1: [↗](#)

Symbol: AMA\BTCUSD.ama

Common Currency Quotes Trade Execution Margin Margin Rates Swaps **Sessions**

 The setting up of trade and quotation sessions of the symbol by days. During the quotation session it is possible to view the price dynamics but trading is prohibited.

Day	Quotes	Trade
 Sunday		
 Monday	00:00-24:00	00:00-24:00
 Tuesday	00:00-24:00	00:00-24:00
 Wednesday	00:00-24:00	00:00-24:00
 Thursday	00:00-24:00	00:00-24:00
 Friday	00:00-24:00	00:00-24:00
 Saturday		

Edit

☐ Use time limits From: 1970.01.01 00:00 To: 1970.01.01 00:00

OK Cancel Help

- Security
- Time**
- Holidays
- Groups (569)
- Clients & Accounts
- Orders & Deals
- Gateways
- Data Feeds
- Plugins

Day settings	
 Sunday	
 Monday	00:00-24:00
 Tuesday	00:00-24:00
 Wednesday	00:00-24:00
 Thursday	00:00-24:00
 Friday	00:00-24:00
 Saturday	

MT5 Centroid DOM Feeder Manual

Essential Setup Information [🔗](#)

Before initiating the setup for the Centroid MT5 DOM Feeder, you'll need to provide the following information to whitelist your IPs:


1. Provide the IP of all MT5 Live Servers where the MT5 Feeder will be installed.
2. Supply the IP of all MT5 Live Backup Servers.

Installation [🔗](#)

i The new plugin can be installed as either a Data Feed or a Gateway. It is recommended that this feeder be installed under datafeed. If there's a requirement to install it as a Gateway, please contact our support team via Skype/Slack or email.

To configure the Centroid MT5 DOM Feeder, follow the instructions below:

1. Remotely log in to the server where the MT5 Server is installed using RDP or another tool.
2. Copy the Centroid MT5 Datafeed folder into the "Feeder" directory of your MT5 History Server installation. ***"The path will resemble D or C:\MetaTrader 5 Platform\History\Datafeed."***





Note:

1. The installation process does not necessitate stopping the MT5 Service.
2. The Centroid MT5 Feeder will be automatically duplicated to the MT5 Backup Server.

Configuration [🔗](#)


To set up the Centroid MT5 DOM Feeder:

1. Log into MT5 Administrator and navigate to Datafeed.
2. Add a new Datafeed.
3. Customize the newly added Feeder as follows:
 - **Name:** Specify the configured Feeder's name.
 - **Module:** Locate the Feeder file within the uploaded folder.
 - **Select:** Choose "Quotes" from the dropdown.
 - **Trading Server:** Provide the DNS and Port details given by Centroid.
 - **Trading Login:** Enter the trading login ID provided by Centroid.
 - **Password:** Input the trading password provided by Centroid.
 - **Parameters:** Sender and Input the TargetComplID provided by Centroid.



⚠ If the **Sender** is not added in the parameters, the DOM Feeder will not be able to establish a connection with the bridge.

Note: Make certain that all the Symbols intended for pricing by the Centroid Feeder are appropriately listed in the Symbols tabs, respectively.



Enhancing the Feeder [🔗](#)

When upgrading the Centroid MT5 DOM Feeder to a newer version, adhere to the following steps, ensuring the new folder supersedes the old one for simplicity:

To enhance the Centroid DOM MT5 Feeder, proceed with the following instructions:

1. **Access the Server:** Remotely access the server where the MT5 History Server is installed, using RDP or any other tool.
2. **Backup the Old Version:** Create a backup by copying the existing Centroid DOM Feeder to another folder, ensuring the ability to revert the update if needed.

i How to Backup:

Please ensure that the existing Centroid DOM Feeder is copied to a location outside the DataFeed folder (e.g., Desktop or any other preferred directory). This will prevent the backup file from appearing in the drop-down menu in MT5.

3. **Disable the Centroid Feeder:** Before replacing the file, it is recommended to disable the "Centroid DOM Feeder" from the MT5 Administrator.
4. **Replace the File:** Replace the existing Centroid DOM Feeder .exe file in the "Datafeed" folder of your MT5 History Server installation with the new one, maintaining the exact name.
5. **Version Monitor:** In the MT5 Administrator, monitor the disabled feeder's version under status. Once the correct version is loaded successfully, enable the Feeder.
6. **Enable the Centroid Feeder:** Re-enable the Feeder using the MT5 Administrator.

i The DOM Feeder will remain **connected**, as the continuous heartbeat exchange ensures an active connection, even if the **prices are not streamed** from your bridge to MT5.

MT5 Centroid Gateway Manual

Essential Setup Information [🔗](#)


Before initiating the setup for the Centroid MT5 Gateway, you'll need to provide the following information to whitelist your IPs:

1. Provide the IP or DNS of all MT5 Live Servers where the MT5 Gateway will be installed.
2. Supply the IP or DNS of all MT5 Live Backup Servers.

Installation [🔗](#)

To configure the Centroid MT5 Gateway, follow the instructions below:

1. Remotely log in to the server where the MT5 Server is installed using RDP or another tool.
2. Copy the Centroid MT5 Gateway folder into the "Gateway" directory of your MT5 History Server installation. ***"The path will resemble D or C:\MetaTrader 5 Platform\History\Gateway."***



Note:

1. The installation process does not necessitate stopping the MT5 Service.
2. The Centroid MT5 Gateway will be automatically duplicated to the MT5 Backup Server.

Configuration [🔗](#)

To set up the Centroid MT5 Gateway:

1. Log into MT5 Administrator and navigate to Gateways.
2. Add a new Gateway.
3. Customize the newly added Gateway as follows:
 - **Name:** Specify the configured Gateway's name.
 - **Module:** Locate the Gateway file within the uploaded folder.
 - **Select:** Choose "Trade Only" from the dropdown.
 - **Trading Server:** Provide the DNS and Port details given by Centroid.
 - **Trading Login:** Enter the trading login ID provided by Centroid.
 - **Password:** Input the trading password provided by Centroid.

Gateway

Common Groups Symbols Translations Parameters Timeouts Monitoring

This is Centroid FIX Gateway for MetaTrader 5.

☒ Enable

Name: Centroid Gateway ID: 47

Module: Centroid Gateway (CentroidGatewayTest5) Trade only

Trading server: xxx.xxx.xxx.7(Host):Port

Trading login: Username Password:

[Show additional network settings](#)

Details available in the Centroid UI "Taker -> Config"


OK Cancel Help

Config - Centroid_Testing_5

Feeding Trading Both Feeder

Key	Value
ResetOnLogon	N
IPList	
DisableLog	N
EndDay	Friday
BeginString	FIX.4.4
Enabled	Y
StartTime	00:00:00
Password	Ab12Ovbz
ResetOnDisconnect	N
StartDay	Friday
SSLProtocol	all
EndTime	00:00:00
ResetOnLogout	N
Username	Centroid_Taker
Host	xxx.xxx.xxx.7:xxxx

Note: Make certain that all the Groups and Symbols intended for processing by the Gateway are appropriately listed in the Groups and Symbols tabs, respectively.



Updating the Gateway [🔗](#)


When upgrading the Centroid MT5 Gateway to a newer version, adhere to the following steps, ensuring the new folder supersedes the old one for simplicity:

To enhance the Centroid MT5 Gateway, proceed with the following instructions:

1. **Access the Server:** Remotely access the server where the MT5 Server is installed, using RDP or any other tool.
2. **Backup the Old Version:** Safeguard your current Centroid MT5 Gateway folder by copying it into a separate folder. This backup facilitates a seamless reversion to the previous version if necessary.
3. **Disable the Centroid Gateway:** Before replacing the file, it is recommended to disable the "Centroid Gateway" from the MT5 Administrator.
4. **Replace the File:** Overwrite the existing Centroid MT5 Gateway folder in the MT5 History Installation with the new one.
5. **Enable the Centroid Gateway:** Re-enable the Gateway using the MT5 Administrator.

Setting up the "Centroid Gateway" [🔗](#)

To Set-Up the Centroid Gateway in your MT5, please follow the steps outlined below:



Let's categorize the parameters into two groups:

General Parameters [🔗](#)

- Facilitating the connection of your "Centroid Gateway" (MT5) to the "Centroid Bridge" (Bridge).

Parameter	Value	Description
Sender	Example: TD_Username	This is available in the 'Centroid Bridge' Taker -> Config -> SenderCompID. Please note: The format is supposed to be TD_Username.
Account	Example: TEM-1, Test_TEM, Plain_TEM	This Account will represent that, you wish to target this Account while executing your trades, this is available in the "Centroid Bridge" under Taker -> Taker Execution Model (TEM) and this will be further used while establishing the "Execution Rules".

- Define the **"Execution Rules."**

The routing rules determine how trades from various MT5 Groups, Logins, Groups of Symbols, or Symbols are directed to specific accounts or Taker Execution Models (TEM) on the Centroid Bridge.

Explanation:

sec = group of symbols (Example: Forex\Major)

sy = symbols

g = groups

ac = accounts / logins

tem = Taker Execution Model on the "Centroid Bridge"

dir = direction of the order (close/open)

1. No Filters

The screenshot shows the 'Parameters' tab in the Gateway window. The 'Parameter' column has 'Sender' and 'AccCfg.1'. The 'Value' column has 'TD_Centroid_Testing_5' and 'sec=*;g=*;tem=Test_TEM'. Red arrows point to the 'AccCfg.1' parameter and its value.

Parameter	Value
Sender	TD_Centroid_Testing_5
AccCfg.1	sec=*;g=*;tem=Test_TEM

Parameter	Value	Description
AccCfg.1	sec=*;g=*;tem=Test_TEM	This rule defines all the securities and all the groups will target one Taker Execution Model "TEM" i.e. Test_TEM

2. Group Filter

The screenshot shows the 'Parameters' tab in the Gateway window. The 'Parameter' column has 'Sender' and 'AccCfg.1'. The 'Value' column has 'TD_Centroid_Testing_5' and 'sec=*;g=ABC\USD;tem=TEM-1'. Red arrows point to the 'AccCfg.1' parameter and its value.

Parameter	Value
Sender	TD_Centroid_Testing_5
AccCfg.1	sec=*;g=ABC\USD;tem=TEM-1

Parameter	Value	Description
AccCfg.1	sec=*;g=ABC\USD;tem=TEM-1	This rule defines all the securities from a specific group i.e. "ABC/USD" will target to TEM → TEM-1
AccCfg.2	sec=*;g=ABC\USD,Testonly\A-1,Testonly\B-2;tem=TEM-1	This rule defines Multiple Groups Targeting one TEM
AccCfg.3	sec=*;g=Testonly*;tem=5points_TEM	This rule defines All the Groups under Testonly\ Targeting one TEM

3. Symbol and Group Filter

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
Sender	TD_Centroid_Testing_5
AccCfg.1	sy=EURUSD.test;g=NYZ\USD;tem=TEM-2

Parameter	Value	Description
AccCfg.1	sy=EURUSD.test;g=NYZ\USD;tem=TEM-2	This rule defines only symbol "EURUSD.test" from the group "NYZ\USD" will target to TEM → TEM-2
AccCfg.2	sy=EURUSD.test,GBPUSD.test;g=NYZ\USD;tem=TEM-2	This rule defines Multiple Symbols from the group "NYZ\USD" will target to TEM → TEM-2
AccCfg.3	sy=EUR*;g=NYZ\USD,Testonly\A1;tem=TEM-2	This rule defines All EUR symbols from specific two groups will target TEM → TEM-2

4. Account Filter

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.


Up Down

Parameter	Value
Sender	TD_Centroid_Testing_5
AccCfg.1	sy=*;ac=100012;tem=Plain_TEM

Parameter	Value	Description
AccCfg.1	sy=*;ac=100012;tem=Plain_TEM	This rule defines all the symbols available in the account 100012 will target to TEM → Plain_TEM
		Note: Account rules should always be placed at the Top of all the Group rules, as the "Gateway" follows Top-Down Approach.

AccCfg.2	sy=*;ac=100012,100015,102256;tem=Plain_TEM	This rule defines Multiple Accounts/Logins Targeting one TEM
AccCfg.3	ac=501265,511456;tem=TEM-2	This rule defines Multiple Accounts/Logins Targeting one TEM

5. Entry Direction Filter



Parameter	Value	Description
AccCfg.1	sec=*;g=real/fx-1;tem=Plain_TEM;dir=in	This rule defines all the symbols available in the group real/fx-1 from any account with deal entry as IN or opening orders will be directed to Plain_TEM
AccCfg.2	sec=*;g=real/fx-1;tem=Slip_TEM;dir=out	This rule defines all the symbols available in the group real/fx-1 from any account with deal entry as OUT or closing orders will be directed to Slip_TEM

Additional Parameters [🔗](#)

Configure these parameters to utilize the add-on features provided by the "Centroid Bridge."

1. EnGiveUp

Configuration Guide →

Assign the configured "Centroid Gateway" to the "Slave Account" to establish a seamless connection.

Account: 3034, Test Account, USD, 1:500, Netting

Overview Personal **Account** Limits Profile Subscriptions Security

Group: real\Support\AMA\Netting

Color: ☐ None Leverage: 1 : 500

Bank account: Agent account:

☒ Enable this account
☒ Enable password change
☒ Enable one-time password
☐ Change password at next login

Trade accounts:

Gateway ID	Account	
47, Centroid Test 5	3034	Same Account Number

Centroid Gateway

Add Edit Delete

New Client... Update Cancel Help

2. EnTradeCopy

Configuration Guide →

1. Add a parameter in the "Centroid Gateway" for optimal settings.

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
ab Sender	TD_TakerName
ab EnTradeCopy	Y

Parameter	Value	Explanation
EnTradeCopy	Y	The Parameter is enabled and it allows to send copy trades to the "Slave Account"
EnTradeCopy	N	The Parameter is disabled

2. Assign the configured "Centroid Gateway" to the "Slave Account" to establish a seamless connection.

Account: 3034, Test Account, USD, 1:500, Netting

Overview Personal **Account** Limits Profile Subscriptions Security

Group: real\Support\AMA\Netting

Color: ☐ None Leverage: 1 : 500

Bank account: Agent account:

☒ Enable this account
☒ Enable password change
☒ Enable one-time password
☐ Change password at next login

Trade accounts:

Gateway ID	Account	
47, Centroid Test 5	3034	Same Account Number

Centroid Gateway

Add Edit Delete

New Client... Update Cancel Help

3. EnReturnFillPolicy

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
ab Sender	TD_Centroid_Testing_5
ab EnReturnFillPolicy	Y

Parameter	Value	Explanation
EnReturnFillPolicy	Y	This parameter is pertinent to pending orders in MT5. When enabled, it permits MT5 to resend the remaining volume in case of full or partial order cancellation.
EnReturnFillPolicy	N	The Parameter is disabled, and the pending order will be cancelled.

4. Configuration of Limit Orders

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
ab Sender	TD_Centroid_Testing_5
ab AccCfg.1	sec=*;g=Testonly\A-1;tem=TEM-1;lmt=Y
ab AccCfg.2	sec=*;g=Testonly\A-2;tem=TEM-1;stp=Y
ab AccCfg.3	sec=*;g=Testonly\B-1;tem=TEM-1;sl=Y
ab AccCfg.4	sec=*;g=Testonly\B-2;tem=TEM-1;tp=Y

Parameter	Value	Explanation
lmt	Y: Yes (Send as a Limit Order) Not specified (Send as a Market Order)	Enabling the " lmt " parameter by setting it to "Y" facilitates the transmission of pending orders, specifically Sell Limit and Buy Limit types, to the Bridge as Limit orders upon activation. Ordinarily, these order types are sent as Market orders by default. Sample Rule: sec=*;g=Testonly\A-1;tem=TEM-1; lmt=Y
stp	Y: Yes (Send as a Limit Order) Not specified (Send as a Market Order)	Enabling the "stp" parameter by setting it to "Y" enables the transmission of pending orders, specifically Sell Stop and Buy Stop types, to the Aggregator as Limit orders upon activation. Ordinarily, these order types are sent as Market orders by default. Sample Rule: sec=*;g=Testonly\A-1;tem=TEM-1; stp=Y
sl	Y: Yes (Send as a Limit Order) Not specified (Send as a Market Order)	Enabling the "sl" parameter by setting it to "Y" enables the transmission of Stop Loss triggered orders to the Aggregator as Limit orders upon activation. Ordinarily, these order types are sent as Market orders by default. Sample Rule: sec=*;g=Testonly\B-1;tem=TEM-1; sl=Y
tp	Y: Yes (Send as a Limit Order) Not specified (Send as a Market Order)	Enabling the "tp" parameter by setting it to "Y" enables the transmission of Take Profit triggered orders to the Aggregator as Limit orders upon activation. Ordinarily, these order types are sent as Market orders by default. Sample Rule: sec=*;g=Testonly\B-2;tem=TEM-1; tp=Y

5. Limit Order Deviation Configuration

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
ab Sender	TD_Centroid_Testing_5
ab AccCfg.1	sec=*;g=Testonly\A-1;tem=TEM-1;lmt=Y;dev=10
ab AccCfg.2	sec=*;g=Testonly\A-1;tem=TEM-1;stp=Y;dev=5
ab AccCfg.3	sec=*;g=Testonly\A-1;tem=TEM-1;sl=Y;dev=7
ab AccCfg.4	sec=*;g=Testonly\A-1;tem=TEM-1;tp=Y;dev=3

Parameter	Value	Explanation
dev	10, 5, 7, 3 (In Points)	Enabling the "dev" parameter by setting it to the desired value (in points), hence allowing for the acceptance of deviation concerning Limit Orders. Deviation is consistently measured in points. It's essential to note that for deviation to function, your limit configurations must be in place; deviation operates in conjunction with Limit orders and cannot function independently.

6. Configuration to Force Price for Trading Accounts when a trade placed by a Manager

Gateway

Common Groups Symbols Translations **Parameters** Timeouts Monitoring

Please specify parameters of the gateway. These parameters are specific for each type of gateway. They allow using additional settings that were not available in the "Common" tab.

Up Down

Parameter	Value
ab Sender	TD_Centroid_Testing_5
ab ForceManagerPx	Y
ab ListForceManagerPx	Manager Number

Parameter	Value	Explanation
ForceManagerPx	Y: Yes (Manager can Force Prices) Not specified (Manager cannot Force Prices)	Enabling the "ForceManagerPx" parameter by setting it to 'Y' grants authority to managers listed in "ListForceManagerPx" to force prices against the current market price for the trading accounts.
ListForceManagerPx	1012, 1013, 1015	The authority to force prices is exclusive to the manager number specified in the "ListForceManagerPx" parameter.

Two Factor Authentication (2FA)



Overview [↗](#)


2-Factor Authentication (2FA) is a security method that adds an extra layer of protection to accounts. It requires users to provide a second form of identification, like a mobile-generated code, in addition to their password. This dual authentication enhances security and helps prevent unauthorized access as it requires both something known (password) and something possessed (mobile device) for account verification.

Before You Begin [↗](#)


1. Authenticator app on your mobile.

Enabling 2FA: Step-by-Step Instructions [↗](#)

1. Access your bridge account
2. Navigate to your profile
3. Click on Two-factor authentication



4. Open the authenticator app on your mobile device



5. Scan the code displayed on the bridge using the app

Two-factor authentication

Register a one-time password authenticator

Use a one-time password authenticator on your mobile device or computer to enable two-factor authentication (2FA).



Can't scan the code?

To add the entry manually, provide the following details to the application on your phone.

Account: Centroid Bridge:Centroid_Support

Key:

Current password

Required


Enter verification code

Required

Submit

6. After scanning, you will promptly receive a code on your Authenticator app.
7. Input your current password and the received code
8. Confirm by selecting the submit button

Voila! We are done. Now, your profile is secured with Two-Factor Authentication.

A screenshot of a web application interface for two-factor authentication. At the top, the title "Sign In - Two factor authenticator" is displayed. Below it is the Centroid BRIDGE logo. A message states: "Enter the code from your two-factor authenticator app. If you've lost your device, click on disable two-factor authenticator." There is a text input field labeled "Verify Code" with a "Required" status below it. A link "Reset two-factor authenticator" with a right-pointing chevron is located below the input field. At the bottom, there is a large blue button labeled "Sign In".

Sign In - Two factor authenticator

**Centroid
BRIDGE**

Enter the code from your two-factor authenticator app. If you've lost your device, click on disable two-factor authenticator.

Verify Code
Required


[Reset two-factor authenticator](#) >

Sign In

Disabling the Two-Factor Authentication (2FA) [🔗](#)

To disable the 2FA

1. Log in to your bridge account.
2. Navigate to your profile.
3. Click on the "Two-factor authentication" option.
4. Enter your current password.
5. Select the "Disable Two-factor authentication" option.

A screenshot of a web application interface for disabling two-factor authentication. The title "Two-factor authentication" is at the top. Below it, the text "Disable two-factor authentication" and "Use this section to disable your one-time password authenticator." are shown. There is a text input field labeled "Current password" with a "Required" status below it. A red arrow points to this field. At the bottom right, there is a red button labeled "Disable two-factor authentication". Another red arrow points to this button.

Two-factor authentication

Disable two-factor authentication
Use this section to disable your one-time password authenticator.

Current password
Required

Disable two-factor authentication

Reset the Two-Factor Authentication (2FA) [🔗](#)

To reset the 2FA

1. Log in to your bridge account.
2. Click on "Reset two-factor authenticator."

Sign In - Two factor authenticator

 Centroid
BRIDGE

Enter the code from your two-factor authenticator app. If you've lost your device, click on disable two-factor authenticator.

Verify Code
Required

[Reset two-factor authenticator](#) >

Sign In

3. Enter the code sent to your email.

✓ An email has been sent with a verification code

 Centroid
BRIDGE

Use this section to reset your one-time password authenticator.

Email Verification Code
Required

[Resend Email Code 05:00](#) >

Reset two-factor authenticator

You should now be able to log in to the bridge. If you wish to enhance account security, please set up the new Two-Factor Authentication (2FA) by following the same steps mentioned above.


How To Restart Centroid Bridge

Overview [↗](#)

This page will help you restart your Centroid Bridge.



You can follow the Step-by-step process below to restart your Centroid Bridge.

1. Go to your Account which can be located on the lower left part of your bridge:



2. Click on your Account and it will open the Account Settings and you should be able to see the Restart button.

3. Click on the Restart Button and enter the reason why you want to Restart your Centroid Bridge.



Impact of the Bridge Restart [↗](#)

- This will result in a brief downtime which will lead to the disconnection of all the MT Gateway/Feeder and FIX connections
- Downtime will also result in a price halt and trade rejection

Schedule of the Bridge Restart [↗](#)

- We highly suggest scheduling the bridge restart during the following windows:
 - EOD or FX Market Rollover
 - Weekend
 - Whenever you find it convenient for your operation

Actions that require to perform a Bridge Restart [↗](#)

- Adding a new Maker
- Adding a new Taker
- Enabling a new Taker
- Symbol Volume Digits Changes
- Various Config changes
 - Native system configuration (done by the support team)
 - Maker Connection config changes
 - Taker Connection config changes

- ✓ It is also recommended to perform post-checks after a Centroid Bridge Restart, to make sure everything is connected and working as expected.