


Clink on Insert row and add VLAN ID and subnet of Managemnt network, Livemigration Network & Storge network.






Click finesh to create Logical Network




Please go to jobs and verify status of the task.




4.4 Creating Logical Switch in SCVMM


Select Logical Switch option from the Fabric




Follow Create Logical Switch Wizard
Enter Switch name and short Discription and Uplink Mode set ad Embedded Team.
Create will be fourth option then click on down arrow




Set Minunumum bandwidth mode as Weight







Click on Add to add virtual port.




Click on Browse to select port Classification.




Select Host Managemnt and click ok.





Click on browse under port profile to select port.
(Click OK not Create Port Classification)





Add Virtual Port
Specify the port profile and map it to port classification
VMM includes built in virtual network adapter port profiles and built in port classifications. For each switch
Select a virtual network adapter port profile
Select a virtual network adapter port profile
Name
Description
Cluster
A port profile that specifies the rec...
Default
A port profile that indicates default...
Guest Dynamic IP
A port profile that is suitable for V...
High Bandwidth Adapter
A port profile that is suitable for V...
Host management
A port profile that specifies the rec...
iScsi
A port profile that specifies the rec...
Live migration
A port profile that specifies the rec...
Medium Bandwidth Adapter
A port profile that is suitable for V...
Network load balancer NIC Profile
A port profile that specifies the rec...
SR-IOV Profile
A port profile that specifies the rec...
Create...
Clear selection
OK
Cancel
Getting Star
General
Settings
Extensions
Virtual Port
Uplinks
Summary
Browse...
Add...
Edit...
Remove
Cancel
OK
Cancel


Select a Port Profile Classification
Select a Port Profile Classification
Name
Description
SR-IOV
Port classification to be used for virtual machines t...
Network load balancing
Port classification to be used for virtual machines t...
Guest Dynamic IP
Port classification to be used for virtual machines t...
Live migration workload
Port classification to be used for host live migratio...
Medium bandwidth
Port classification to be used for virtual machines t...
Host Cluster Workload
Port classification for host cluster workloads.
Low bandwidth
Port classification to be used for virtual machines t...
High bandwidth
Port classification to be used for virtual machines t...
iSCSI workload
Port classification for host iSCSI workloads.
Create Port Classification...
OK
Cancel
Getting Star
General
Settings
Extensions
Virtual Port
Uplinks
Summary
Add...
Edit...
Remove
Cancel


Add Virtual Port
Specify the port profile and map it to port classification
VMM includes built in virtual network adapter port profiles and built in port classifications. For each switch
Select a virtual network adapter port profile
Select a virtual network adapter port profile
Name
Description
Cluster
A port profile that specifies the rec...
Default
A port profile that indicates default...
Guest Dynamic IP
A port profile that is suitable for V...
High Bandwidth Adapter
A port profile that is suitable for V...
Host management
A port profile that specifies the rec...
iScsi
A port profile that specifies the rec...
Live migration
A port profile that specifies the rec...
Medium Bandwidth Adapter
A port profile that is suitable for V...
Network load balancer NIC Profile
A port profile that specifies the rec...
SR-IOV Profile
A port profile that specifies the rec...
Create...
Clear selection
OK
Cancel
Getting Star
General
Settings
Extensions
Virtual Port
Uplinks
Summary
Browse...
Add...
Edit...
Remove
Cancel
OK
Cancel



Add Virtual Port
Specify the port profile and map it to port classification
VMM includes built in virtual network adapter port profiles and built in port classifications. For each switch extension associated to the logical switch, one port profile may be selected. Additionally, a Hyper-V virtual network adapter port profile may be associated to the virtual port.
Choose or Define a Port Classification
Port classification:
iSCSI workload
Browse...
Choose or Define a Port Profile that needs to be mapped to the classification
Port profile:
iScsi
Browse...
Getting Star
General
Settings
Extensions
Virtual Port
Uplinks
Summary
Add...
Edit...
Remove
Cancel
OK
Cancel

Set Host Management post profile as default







Click on Add and select New Uplink port Profile to create new




Enter Uplink Name and short discription and select network site.




Check summary and click finesh to create New Logical Switch.




Moniter tasks from jobs.




Once switch created clink on propertes to add add network adaptors







Select Uplinks and click on New virtual network adaptor.




(Uncheck Available for Placement and Used by Management options for all unused Network adapters)


Enter Network adaptor name like Managemnt/ Storage/ Live Migration
and select aparoperate VM Network and enable VLAN.
(If VM Network not available please refer **4.5 Creating VM Network in SCVMM** from this document to create).






For Managemnet adapter ensure to enable use for host managemnt and inherit connection settings.





LS-SGP-S01 Properties
General
Settings
Extensions
Virtual Port
Uplinks
Add
New virtual network adapter
Remove
SGP01-PP-Uplink
SwitchIndependent
MGMT
SGP-MGMT-VLAN...
Storage
SGP-Storage-VLA...
Name:
Storage
Connectivity
VM Network:
SGP-Storage-VLAN-1700
Browse...
VM Subnet:
SGP-Storage-VLAN-1700_0
Enable VLAN
VLAN ID:
1700
This virtual network adapter will be used for host management
Inherit connection settings from host network adapter
IP address configuration
DHCP
Static
IPv4 pool:
Not Applicable
IPv6 pool:
Not Applicable
Port Classification:
iSCSI workload
View Script
OK
Cancel



LS-SGP-S01 Properties
General
Settings
Extensions
Virtual Port
Uplinks
Add
New virtual network adapter
Remove
SGP01-PP-Uplink
SwitchIndependent
MGMT
SGP-MGMT-VLAN...
Storage
SGP-Storage-VLA...
LiveMigration
SGP-LM-VLAN-1740
Name:
LiveMigration
Connectivity
VM Network:
SGP-LM-VLAN-1740
Browse...
VM Subnet:
SGP-LM-VLAN-1740_0
Enable VLAN
VLAN ID:
1740
This virtual network adapter will be used for host management
Inherit connection settings from host network adapter
IP address configuration
DHCP
Static
IPv4 pool:
Not Applicable
IPv6 pool:
Not Applicable
Port Classification:
Live migration workload
View Script
OK
Cancel

4.5 Creating VM Network in SCVMM


Select VMs and Serveses from the left side menu.




Select VM Network from the left side menu.




Click on Create VM Network from the top menu.





Follow Create VM Network Wizard
Enter VM Network name and short Discription and select Logical network from the dropdown.







Select specify a VLAN and select network site & VLAN Subnet





Verify the summary and click finesh to create.
(Its about adding second & third VLANS)







4.6 Adding cluster/Host to SCVMM

(Applies for both Cluster hosts & applicable for Standalone hosts)


1. Open SCVMM under VM's and services select appropriate folder to add host.
2. Right click on the folder and select add Hyper-V Hosts and Clusters.





Follow add resource Wizard steps.



Use VMMADMIN account as run as account.
(Before this please add VMMADMIN account in the host level)


Add Resource Wizard
Credentials
Resource Location
Credentials
Discovery Scope
Target Resources
Host Settings
Summary
Select a Run As Account
Select a Run As account
vmm
Name
Description
User Role
vmmadmin(RunAsAcco...
RunAsAccount
Administrator
Create Run As Account
OK
Cancel
Browse...
Previous
Next
Cancel



Add Resource Wizard
Discovery Scope
Resource Location
Credentials
Discovery Scope
Target Resources
Host Settings
Summary
Specify the search scope for virtual machine host candidates
Search for computers by whole or partial names, FQDNs, and IP addresses. Alternatively, you may generate an Active Directory query to discover the desired computers.
Specify Windows Server computers by names
Specify an Active Directory query to search for Windows Server computers
Enter the computer names of the hosts or host candidates that you want VMM to manage. Each computer name must be on a separate line.
Computer names:
wcoshv02
Skip AD verification
Examples: server1
server1.contoso.com
10.0.1.1
2a01:110:1e:3:f8ffcfe44:23
Previous
Next
Cancel




4.7 Configuring the Network adapters for new Hyper-V Host

1. Pushing Network Configuration from SCVMM.


Select propertes of the host you want to push the network configuration




Select Hardware and go to network adapters.




Select Network adapters where the network cable got plugged and assigned IP.




Enable Availability for Placement option & Used by management for both adaptors.





Select Virtual switches and add New Virtual Switch.




Enter logical switch name and select logical switch and select physical adaptors.





wsgphv01.sgp.is.keysight.com Properties
General
Status
Hardware
Host Access
Virtual Machine Paths
Reserves
Storage
Virtual Switches
Migration Settings
Placement Paths
Servicing Windows
Host Guardian Service
Enhanced Session
New Virtual Switch
New Virtual Network Adapter
Delete
LS-SGP-S01
Logical Switch
Logical switch: LS-SGP-S01
LBFO Team switches are deprecated for Azure Stack HCI and Windows Server 2022 and above versions. They will not be available for selection in the drop down.
The logical switch supports teaming which means if you connect more than one physical adapter they will work together as a single uplink.
Physical adapters:
Adapter
Uplink Port Pr
SLOT 1 Port 1 - Broadco
SGP01-PP-Up
SLOT 1 Port 2 - Broadco
SGP01-PP-Up
Add
Remove
The teaming mode supported by this switch requires all physical adapters to use the same uplink port profile.
The following virtual network adapters will be created:
Name
VM Network
VM Subnet
VLAN ID
MGMT
SGP-MGMT-\
SGP-MGMT-\
1760
Storage
SGP-Storage-
SGP-Storage-
1700
LiveMigration
SGP-LM-VLAI
SGP-LM-VLAI
1740
View Script
OK
Cancel


wsgphv01.sgp.is.keysight.com Properties
General
Status
Hardware
Host Access
Virtual Machine Paths
Reserves
Storage
Virtual Switches
Migration Settings
Placement Paths
Servicing Windows
Host Guardian Service
Enhanced Session
New Virtual Switch
New Virtual Network Adapter
Delete
LS-SGP-S01
Logical Switch
Logical switch: LS-SGP-S01
LBFO Team switches are deprecated for Azure Stack HCI and Windows Server 2022 and above versions. They will not be available for selection in the drop down.
The logical switch supports teaming which means if you connect more than one physical adapter they will work together as a single uplink.
Virtual Machine Manager
While Virtual Machine Manager is applying the changes, the host may temporarily lose network connectivity. This may have an adverse effect on other network operations in progress.
Do you want to continue?
Yes
No
Add
Remove
VLAN ID
MGMT
SGP-MGMT-\
SGP-MGMT-\
1760
Storage
SGP-Storage-
SGP-Storage-
1700
LiveMigration
SGP-LM-VLAI
SGP-LM-VLAI
1740
View Script
OK
Cancel




Login to host and verify Virtual Adapter status.





Assign IPs to Live Migration and Storage Adaptors.


4.8 Configure ISCSI Initiator

1. Open ISCSI Initiator and collect Initiator name.
2. Share Initiator name to storage team to map LUN.
   a. 

3. Follow the screenshots below for reference to map LUN.


iSCSI Initiator Properties
Targets
Discovery
Favorite Targets
Volumes and Devices
RADIUS
Configuration
Target portals
The system will look for Targets on following portals:
Refresh
Address
Port
Adapter
IP address
10.176.33.3
3260
Default
Default
To add a target portal, click Discover Portal.
Discover Portal...
To remove a target portal, select the address above and then click Remove.
Remove
iSNS servers
The system is registered on the following iSNS servers:
Refresh
Name
To add an iSNS server, click Add Server.
Add Server...
To remove an iSNS server, select the server above and then click Remove.
Remove
OK
Cancel
Apply


iSCSI Initiator Properties
Discover Target Portal
Enter the IP address or DNS name and port number of the portal you want to add.
To change the default settings of the discovery of the target portal, click the Advanced button.
IP address or DNS name:
Port: (Default is 3260.)
10.176.33.40
3260
Advanced...
OK
Cancel
Remove
iSNS servers
The system is registered on the following iSNS servers:
Refresh
Name
To add an iSNS server, click Add Server.
Add Server...
To remove an iSNS server, select the server above and then click Remove.
Remove
OK
Cancel
Apply


Advanced Settings
General
IPsec
Connect using
Local adapter:
Microsoft iSCSI Initiator
Initiator IP:
10.5.28.49
Target portal IP:
CRC / Checksum
Data digest
Header digest
Enable CHAP log on
CHAP Log on information
CHAP helps ensure connection security by providing authentication between a target and an initiator.
To use, specify the same name and CHAP secret that was configured on the target for this initiator. The name will default to the Initiator Name of the system unless another name is specified.
Name:
iqn.1991-05.com.microsoft:wbbnhv02.bbn.is.keysight.com
Target secret:
Perform mutual authentication
To use mutual CHAP, either specify an initiator secret on the Configuration page or use RADIUS.
Use RADIUS to generate user authentication credentials
Use RADIUS to authenticate target credentials
OK
Cancel
Apply
iSCSI Initiator Properties
Advanced Settings
General
IPsec
Connect using
Local adapter:
Microsoft iSCSI Initiator
Initiator IP:
10.176.36.245
Target portal IP:
CRC / Checksum
Data digest
Header digest
Enable CHAP log on
CHAP Log on information
CHAP helps ensure connection security by providing authentication between a target and an initiator.
To use, specify the same name and CHAP secret that was configured on the target for this initiator. The name will default to the Initiator Name of the system unless another name is specified.
Name:
iqn.1991-05.com.microsoft:wcoshv02.cos.is.keysight.com
Target secret:
Perform mutual authentication
To use mutual CHAP, either specify an initiator secret on the Configuration page or use RADIUS.
Use RADIUS to generate user authentication credentials
Use RADIUS to authenticate target credentials
OK
Cancel
Apply