

Ravan Muradzada

Task 1

- 1) In my network at home, private ips do not start with `172`, they are just `192.168`. So before starting the process, I want to redesign network settings for me:

I will try to switch to:

Static IP: 192.168.88.11

Netmask: 255.255.255.0

Default Gateway: 192.168.88.1

Primary DNS Server: 8.8.8.8

DNS Search Path: example.com

Hostname stays the same as `server.example.com`.

Changing a hostname is very easy and I prefer to do it with the command of:

`hostnamectl set-hostname <HOSTNAME_NAME>.`

If we run `hostname` command, we can see our current hostname.


```
[root@rhel9 ~ #] hostnamectl set-hostname serverX.example.com
[root@rhel9 ~ #] bash
[root@serverX ~ #] hostname
serverX.example.com
```

I created a new virtual adapter to set the other settings. To create a new virtual adapter, we go to VMWare Workstation Pro and right click to our virtual machine and click Settings. Then we added New Network Adapter. When we restart the virtual machine, it will be available. To see all available adapters with their configuration, we use `ip a` command:

```
[root@serverX ~ #] ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: ens160: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:ea brd ff:ff:ff:ff:ff:ff
    altname enp3s0
    inet 192.168.88.129/24 brd 192.168.88.255 scope global dynamic noprefixroute ens160
        valid_lft 1414sec preferred_lft 1414sec
    inet6 fe80::20c:29ff:fe2e:eaea/64 scope link noprefixroute
        valid_lft forever preferred_lft forever
3: ens224: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:f4 brd ff:ff:ff:ff:ff:ff
    altname enp19s0
    inet 192.168.88.137/24 brd 192.168.88.255 scope global dynamic noprefixroute ens224
        valid_lft 1415sec preferred_lft 1415sec
    inet6 fe80::b55b:a14c:c48f:8f87/64 scope link noprefixroute
        valid_lft forever preferred_lft forever
```

Here, `ens224` is our new adapter and it has default private ip which is given by DHCP.
Now we will change it.

We write `nmtui` command and select `Edit Connection`. I can see that:



Here, `Wired Connection` is our new adapter. We need to select it and click `Edit` button.

Now in the opening page, I have changed or added some settings:

Edit Connection

Profile name

Device

= ETHERNET <Show>

= 802.1X SECURITY <Show>

= IPv4 CONFIGURATION <Manual> <Hide>

Addresses <Remove>

<Add...>

Gateway

DNS servers <Remove>

<Add...>

Search domains <Remove>

<Add...>

Routing (No custom routes) <Edit...>

☐ Never use this network for default route

☐ Ignore automatically obtained routes

☐ Ignore automatically obtained DNS parameters

☐ Require IPv4 addressing for this connection

= IPv6 CONFIGURATION <Disabled> <Show>

☒ Automatically connect

☒ Available to all users

<Cancel> <OK>

What did I change here?

- First, I updated device name to `ens224` from `Wired Connection`.
- I changed IPv4 Config from Automatic to Manual (to disable DHCP).
- I have given this address: `192.168.88.11/24`.
- I have given this gateway: `192.168.88.1`.
- I have given this DNS server: `8.8.8.8`.
- I have given this search domain: `example.com`
- I have disabled IPv6, because I do not want to see when I run `ip a`.

Now I need to click Ok. Then I deactivate and then reactivate the adapter.

Now, when I run `ip a`, I will see:

```
[root@serverX ~ #] ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: ens160: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:ea brd ff:ff:ff:ff:ff:ff
    altname enp3s0
    inet 192.168.88.129/24 brd 192.168.88.255 scope global dynamic noprefixroute ens160
        valid_lft 1769sec preferred_lft 1769sec
3: ens224: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:f4 brd ff:ff:ff:ff:ff:ff
    altname enp19s0
    inet 192.168.88.11/24 brd 192.168.88.255 scope global noprefixroute ens224
        valid_lft forever preferred_lft forever
```

As you can see, the private ip for `ens224` has changed properly!

We can see gateway has changed too:

```
[root@serverX ~ #] ip route
default via 192.168.88.1 dev ens224 proto static metric 101
```

For DNS:

```
[root@serverX ~ #] cat /etc/resolv.conf
# Generated by NetworkManager
search example.com localdomain
nameserver 8.8.8.8
nameserver 192.168.88.2
```

Task 2

- 1) We go to VMWare Workstation Pro and right click the VM and select Settings.
Here we add a new network adapter. Then select Bridged.
- 2) We need to type `ip a` command to see all adapters and their config info:

```
[root@rhel-9 ~ #] ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: ens160: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:ea brd ff:ff:ff:ff:ff:ff
    altname enp3s0
    inet 192.168.88.129/24 brd 192.168.88.255 scope global dynamic noprefixroute ens160
        valid_lft 1787sec preferred_lft 1787sec
4: ens224: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:f4 brd ff:ff:ff:ff:ff:ff
    altname enp19s0
    inet 192.168.88.11/24 brd 192.168.88.255 scope global noprefixroute ens224
        valid_lft forever preferred_lft forever
```

Here `ens224` is our new network adapter. It has already a private ip.

If we want to dive into logs, we can use `dmesg | grep -i 'ens224'` command:

```
[root@rhel-9 ~ #] dmesg | grep -i ens224
[ 177.994135] vmxnet3 0000:13:00.0 ens224: renamed from eth0
[ 178.070192] vmxnet3 0000:13:00.0 ens224: intr type 3, mode 0, 3 vectors allocated
[ 178.070782] vmxnet3 0000:13:00.0 ens224: NIC Link is Up 10000 Mbps
[ 5886.799170] vmxnet3 0000:13:00.0 ens224: renamed from eth0
[ 5886.882560] vmxnet3 0000:13:00.0 ens224: intr type 3, mode 0, 3 vectors allocated
[ 5886.883517] vmxnet3 0000:13:00.0 ens224: NIC Link is Up 10000 Mbps
```

- 3) When we run `nmcli device status`, we can see all available virtual network adapters and whether they are connected or disconnected. To connect to a virtual network adapter, we use `nmcli device connect <ADAPTER_NAME>`. To disconnect, we use `nmcli device disconnect <ADAPTER_NAME>`.

```

[root@rhel-9 ~ #] nmcli device status
DEVICE  TYPE      STATE              CONNECTION
ens160  ethernet  connected          ens160
ens224  ethernet  connected          ens224
lo      loopback  connected (externally) lo
[root@rhel-9 ~ #] nmcli device disconnect ens224
Device 'ens224' successfully disconnected.
[root@rhel-9 ~ #] nmcli device status
DEVICE  TYPE      STATE              CONNECTION
ens160  ethernet  connected          ens160
lo      loopback  connected (externally) lo
ens224  ethernet  disconnected         --
[root@rhel-9 ~ #] nmcli device connect ens224
Device 'ens224' successfully activated with '166e0310-97f9-3e5a-963c-0d06880e4af3'.
[root@rhel-9 ~ #] nmcli device status
DEVICE  TYPE      STATE              CONNECTION
ens160  ethernet  connected          ens160
ens224  ethernet  connected          ens224
lo      loopback  connected (externally) lo

```

As you can see, connecting and disconnecting processes have been done successfully. After both I have run `nmcli device status` and everything is ok and our new virtual network adapter is here.

- 4) I prefer to use `nmtui` command. We type `nmtui`, then go `Edit Connection`, select our new adapter (which is ens224) and from right we press `Edit`.

Edit Connection

Profile name **ens224**
Device **ens224 (00:0C:29:2E:EA:F4)**

= ETHERNET <Show>
= 802.1X SECURITY <Show>

= IPv4 CONFIGURATION <Manual> <Hide>
Addresses **192.168.88.12/24** <Remove>
<Add...>
Gateway **192.168.88.1**
DNS servers <Add...>
Search domains <Add...>

Routing (No custom routes) <Edit...>
[] Never use this network for default route
[] Ignore automatically obtained routes
[] Ignore automatically obtained DNS parameters
[] Require IPv4 addressing for this connection

= IPv6 CONFIGURATION <Disabled> <Show>

[X] Automatically connect
[X] Available to all users

<Cancel> <OK>

As you can see, I gave it a new private IP address, gateway IP, DNS server and Search Domain. I disabled IPv6 and make IPv4 manual.

- 5) As you can see above, I tick 'Automatically connect' option. That ensures our adapter connects to network when it reboots.
- 6) As you can see above, my default gateway is '192.168.88.1'. Let's ping it:

```
[root@rhel-9 ~ #] ip a | grep "ens224" #Get private ip of our new adapter
4: ens224: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    inet 192.168.88.12/24 brd 192.168.88.255 scope global noprefixroute ens224
[root@rhel-9 ~ #] ping -I 192.168.88.12 192.168.88.1
PING 192.168.88.1 (192.168.88.1) from 192.168.88.12 : 56(84) bytes of data.
64 bytes from 192.168.88.1: icmp_seq=1 ttl=128 time=0.622 ms
64 bytes from 192.168.88.1: icmp_seq=2 ttl=128 time=0.630 ms
64 bytes from 192.168.88.1: icmp_seq=3 ttl=128 time=0.643 ms
64 bytes from 192.168.88.1: icmp_seq=4 ttl=128 time=0.828 ms

--- 192.168.88.1 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3063ms
rtt min/avg/max/mdev = 0.622/0.680/0.828/0.085 ms
```

I have used `ping -I` command, so here `-I` option forces Linux to send the ping from specified IP. I specified our new adapter's private ip.

As you can see, pinging is successful.

- 7) The file you mention is `/etc/resolv.conf`.

```
[root@rhel-9 ~ #] echo "nameserver 8.8.8.8" >> /etc/resolv.conf
[root@rhel-9 ~ #] cat /etc/resolv.conf
# Generated by NetworkManager
search localdomain 7
nameserver 192.168.88.2
nameserver 8.8.8.8
```

- 8) I have found two main tools to resolve: nslookup and dig.

```
[root@rhel-9 ~ #] nslookup www.box.az
Server:          192.168.88.2
Address:         192.168.88.2#53

Non-authoritative answer:
Name:   www.box.az
Address: 94.20.74.2

[root@rhel-9 ~ #] nslookup box.az
Server:          192.168.88.2
Address:         192.168.88.2#53

Non-authoritative answer:
Name:   box.az
Address: 94.20.74.2
```



```
[root@rhel-9 ~ #] dig www.box.az

; <<>> DiG 9.18.29 <<>> www.box.az
;; global options: +cmd
;; Got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 36548
;; flags: qr rd ra; QUERY: 1, ANSWER: 1, AUTHORITY: 3, ADDITIONAL: 4

;; OPT PSEUDOSECTION:
; EDNS: version: 0, flags:; MBZ: 0x0005, udp: 4096
; COOKIE: c9f61f4c0f7c8eca5b01ca8269b5d1a8701d02c0caaa8339 (good)
;; QUESTION SECTION:
;www.box.az.                IN      A

;; ANSWER SECTION:
www.box.az.                5       IN      A      94.20.74.2

;; AUTHORITY SECTION:
box.az.                    5       IN      NS      ns4.box.az.
box.az.                    5       IN      NS      ns5.box.az.
box.az.                    5       IN      NS      ns3.box.az.

;; ADDITIONAL SECTION:
ns3.box.az.                5       IN      A      94.20.74.3
ns4.box.az.                5       IN      A      217.14.96.34
ns5.box.az.                5       IN      A      194.135.30.47

;; Query time: 5 msec
;; SERVER: 192.168.88.2#53(192.168.88.2) (UDP)
;; WHEN: Sun Mar 15 01:22:48 +04 2026
;; MSG SIZE rcvd: 185
```

```

[root@rhel-9 ~ #] dig box.az

; <<> DiG 9.18.29 <<> box.az
;; global options: +cmd
;; Got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 28059
;; flags: qr rd ra; QUERY: 1, ANSWER: 1, AUTHORITY: 3, ADDITIONAL: 4

;; OPT PSEUDOSECTION:
; EDNS: version: 0, flags:; MBZ: 0x0005, udp: 4096
; COOKIE: 503bb796c2924cbccb09d9c569b5d1aba8a52a86b6528a6a (good)
;; QUESTION SECTION:
;box.az.                                IN      A

;; ANSWER SECTION:
box.az.                                5        IN      A      94.20.74.2

;; AUTHORITY SECTION:
box.az.                                5        IN      NS      ns4.box.az.
box.az.                                5        IN      NS      ns5.box.az.
box.az.                                5        IN      NS      ns3.box.az.

;; ADDITIONAL SECTION:
ns3.box.az.                            5        IN      A      94.20.74.3
ns4.box.az.                            5        IN      A      217.14.96.34
ns5.box.az.                            5        IN      A      194.135.30.47

;; Query time: 4 msec
;; SERVER: 192.168.88.2#53(192.168.88.2) (UDP)
;; WHEN: Sun Mar 15 01:22:51 +04 2026
;; MSG SIZE rcvd: 181

```

- 9) To deactivate or activate an interface, we use `nmcli connection down <NAME>` and `nmcli connection up <NAME>`.

I have opened two ssh terminals, from the first one I deactivate and activate `ens224` interface. I used `journalctl -f` command in the second one to see real time logs.

First terminal:

```
[root@rhel-9 ~ #] nmcli device status | grep "ens224"
ens224 ethernet connected ens224
[root@rhel-9 ~ #] nmcli connection down ens224
Connection 'ens224' successfully deactivated (D-Bus ac
[root@rhel-9 ~ #] nmcli device status | grep "ens224"
ens224 ethernet disconnected --
[root@rhel-9 ~ #] nmcli connection up ens224
Connection successfully activated (D-Bus active path:
[root@rhel-9 ~ #] nmcli device status | grep "ens224"
ens224 ethernet connected ens224
```

Second terminal:

```
Mar 15 01:40:45 rhel-9.7 NetworkManager[936]: <info> [1773524445.4686] device (ens224): state change: deactivating -> disconnected (reason 'user-requested', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2161] agent-manager: agent[21d4969060b9c50,1.113/nmcli-connect/0]: agent registered
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2168] device (ens224): Activation: starting connection 'ens224' (166e0310-97f9-3e5a-963c-0d06880e4af3)
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2169] audit: op="connection-activate" uuid="166e0310-97f9-3e5a-963c-0d06880e4af3" name="ens224" pid=3170 uid=0 result="success"
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2170] device (ens224): state change: disconnected -> prepare (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2172] device (ens224): state change: prepare -> config (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2244] device (ens224): state change: config -> ip-config (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2251] device (ens224): state change: ip-config -> ip-check (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2263] device (ens224): state change: ip-check -> secondaries (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2266] device (ens224): state change: secondaries -> activated (reason 'none', managed-type: 'full')
Mar 15 01:40:47 rhel-9.7 NetworkManager[936]: <info> [1773524447.2272] device (ens224): Activation: successful, device activated.
Mar 15 01:40:57 rhel-9.7 systemd[1]: NetworkManager-dispatcher.service: Deactivated successfully.
```

10)

```
[root@rhel-9 ~ #] ss -tln #Get info about all ports
Netid State Recv-Q Send-Q Local Address:Port Peer Address:Port
udp UNCONN 0 0 127.0.0.1:323 0.0.0.0:*
udp UNCONN 0 0 [::1]:323 [::]:*
tcp LISTEN 0 128 0.0.0.0:22 0.0.0.0:*
tcp LISTEN 0 128 [::]:22 [::]:*
[root@rhel-9 ~ #] ss -tln #Get info about only tcp ports
State Recv-Q Send-Q Local Address:Port Peer Address:Port
LISTEN 0 128 0.0.0.0:22 0.0.0.0:*
LISTEN 0 128 [::]:22 [::]:*
```

11) We need to run this command: `ip route add 8.8.8/32 via <OUR_ROUTE_IP>`.`

```
[root@rhel-9 ~ #] ip route
default via 192.168.88.2 dev ens160 proto dhcp src 192.168.88.129 metric 102
default via 192.168.88.1 dev ens224 proto static metric 103
192.168.88.0/24 dev ens160 proto kernel scope link src 192.168.88.129 metric 102
192.168.88.0/24 dev ens224 proto kernel scope link src 192.168.88.12 metric 103
[root@rhel-9 ~ #] ip route add 8.8.8.8/32 via 192.168.88.1
[root@rhel-9 ~ #] ip route show
default via 192.168.88.2 dev ens160 proto dhcp src 192.168.88.129 metric 102
default via 192.168.88.1 dev ens224 proto static metric 103
8.8.8.8 via 192.168.88.1 dev ens160
192.168.88.0/24 dev ens160 proto kernel scope link src 192.168.88.129 metric 102
192.168.88.0/24 dev ens224 proto kernel scope link src 192.168.88.12 metric 103
```

12)

```
[root@rhel-9 ~ #] ip route show
default via 192.168.88.2 dev ens160 proto dhcp src 192.168.88.129 metric 102
default via 192.168.88.1 dev ens224 proto static metric 103
8.8.8.8 via 192.168.88.1 dev ens160
192.168.88.0/24 dev ens160 proto kernel scope link src 192.168.88.129 metric 102
192.168.88.0/24 dev ens224 proto kernel scope link src 192.168.88.12 metric 103
[root@rhel-9 ~ #] ip route del 8.8.8.8/32 via 192.168.88.1
[root@rhel-9 ~ #] ip route show
default via 192.168.88.2 dev ens160 proto dhcp src 192.168.88.129 metric 102
default via 192.168.88.1 dev ens224 proto static metric 103
192.168.88.0/24 dev ens160 proto kernel scope link src 192.168.88.129 metric 102
192.168.88.0/24 dev ens224 proto kernel scope link src 192.168.88.12 metric 103
```

To show route table we use either ``ip route`` or ``ip route show`` commands.

To delete a route from a route table we use ``ip route del 8.8.8.8/32 via <OUR_ROUTE_IP>``.

13)

- a) To add new interfaces, we need to go VMWare Workstation Pro, right click our VM, select Settings and add new network adapters. We add two new network adapters.
- b) If we want interfaces not to have ip addresses, we need to go nmtui and disable both IPv4 and IPv6 there. Then we deactivate and activate both. Now if we run ``ip a`` command, we will see neither of them has ip.

```
[root@rhel-9 ~ #] ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: ens160: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:ea brd ff:ff:ff:ff:ff:ff
    altname enp3s0
    inet 192.168.88.129/24 brd 192.168.88.255 scope global dynamic noprefixroute ens160
        valid_lft 1758sec preferred_lft 1758sec
3: ens224: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:f4 brd ff:ff:ff:ff:ff:ff
    altname enp19s0
4: ens256: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:0c:29:2e:ea:fe brd ff:ff:ff:ff:ff:ff
    altname enp27s0
```

The last two represent new interfaces and they do not have ip addresses.

c)

- Let's look at all connections in the system:

```
[root@rhel-9 ~ #] nmcli con show
```

NAME	UUID	TYPE	DEVICE
ens160	7aa6b362-5c9e-3e74-9fb8-09de496c8dcc	ethernet	ens160
ens224	166e0310-97f9-3e5a-963c-0d06880e4af3	ethernet	ens224
ens256	981cc0bf-2b66-30b8-a86a-0b8dffe8b244	ethernet	ens256
lo	64ec3caa-b735-4ef9-b0dd-d07c7d902611	loopback	lo

Here `ens224` and `ens256` are our new interfaces.

- Then create a team:

```
[root@rhel-9 ~ #] nmcli connection add type team con-name team0 ifname team0 config '{"runner": {"name": "loadbalance"}}'
Connection 'team0' (f09bd4c9-85fe-43ce-b455-7791151a5344) successfully added.
```

- Then add new interfaces to the team:

```
[root@rhel-9 ~ #] nmcli connection add type team-slave ifname ens224 master team0
Connection 'team-slave-ens224' (2f3392b4-319a-4991-a330-9f8e0db1768d) successfully added.
[root@rhel-9 ~ #] nmcli connection add type team-slave ifname ens256 master team0
Connection 'team-slave-ens256' (686da8f5-f88f-4c3e-ae4a-97f4b6670493) successfully added.
```

- Now let's make both team and team members up:

```
[root@rhel-9 ~ #] nmcli connection up team0
Connection successfully activated (controller waiting for ports) (D-Bus active path: /org/freedesktop/NetworkManager/ActiveConnection/32)
[root@rhel-9 ~ #] nmcli connection up team-slave-ens224
Connection successfully activated (D-Bus active path: /org/freedesktop/NetworkManager/ActiveConnection/33)
[root@rhel-9 ~ #] nmcli connection up team-slave-ens256
Connection successfully activated (D-Bus active path: /org/freedesktop/NetworkManager/ActiveConnection/34)
```

- Now let's check connections again:

```
[root@rhel-9 ~ #] nmcli con show
```

NAME	UUID	TYPE	DEV
ens160	7aa6b362-5c9e-3e74-9fb8-09de496c8dcc	ethernet	ens160
team-slave-ens224	2f3392b4-319a-4991-a330-9f8e0db1768d	ethernet	ens224
team-slave-ens256	686da8f5-f88f-4c3e-ae4a-97f4b6670493	ethernet	ens256
team0	f09bd4c9-85fe-43ce-b455-7791151a5344	team	team0
lo	64ec3caa-b735-4ef9-b0dd-d07c7d902611	loopback	lo
ens224	166e0310-97f9-3e5a-963c-0d06880e4af3	ethernet	--
ens256	981cc0bf-2b66-30b8-a86a-0b8df8e8b244	ethernet	--