# RMdrumachine

## User Manual

16-pad drum machine, sample player and step sequencer for REAPER (JSFX)




### ReNo Mellow

Free plugin collection for REAPER - github.com/renothestraws/reno-mellow

Version 1.7 - written for complete beginners

# Contents

1. Welcome 3

2. Installation 4

3. A tour of the interface 5

4. The pads 7

5. Kits 9

6. Pad settings 10

7. Global settings 11

8. The step sequencer, step by step 12

9. Playing the pads with MIDI 15

10. CV / audio trigger: drive the pads from other tracks 16

11. The 8 outputs: mixing pads on separate tracks 18

12. MIDI output: other instruments and editable MIDI 19

13. Troubleshooting 20

# 1. Welcome

RMdrumachine is a free drum machine that lives inside REAPER. It plays drum sounds ("samples") from 16 **pads**, and it has a built-in **step sequencer** so you can program beats with a few clicks, without a MIDI keyboard. It is inspired by classic machines such as the Roland TR-808 and TR-909, the Linn drum machines and the Akai MPC.

This manual assumes you have never used a drum machine or a step sequencer before. Every step is explained, from installation to advanced routing. You can read it from start to finish, or jump to the chapter you need.

## What you can do with it

- Play 16 drum sounds, each with its own volume, pan, tuning, length and output.
- Program beats on a 16-step grid, with accents, ghost notes, swing and rolls.
- Play the pads from a MIDI keyboard or a MIDI item in REAPER.
- Trigger the pads from real drum recordings ("CV / audio trigger"), for example to add a sample under a recorded kick drum.
- Send the beat as MIDI notes to another instrument, or turn it into an editable MIDI item.
- Use your own sounds: drag a WAV or OGG file onto a pad, and save your own kits.
- Switch between 4 factory kits and 8 patterns (A to H) per project.

## Words used in this manual

| Word | Meaning |
|---|---|
| Sample | A short audio recording, for example one hit of a snare drum. |
| Pad | One of the 16 squares. Each pad holds one sample. |
| Step | One box of the sequencer. 16 steps make one bar of music at the 1/16 grid. |
| Velocity | How hard a note is hit, from 1 (softest) to 127 (hardest). |
| Accent | A louder, punchier hit (velocity 127). |
| Ghost note | A very soft hit (velocity 30), used to add groove. |
| Track / FX | In REAPER, a track holds items; plugins are added to its FX chain. |
| Kit | A set of 16 sounds plus their pad settings. |
| Pattern | One complete beat for all 16 pads. RMdrumachine holds 8 patterns, A to H. |
| Routing | Sending audio or MIDI from one track to another. |

# 2. Installation

## Option A - with ReaPack (recommended)

ReaPack is a free REAPER extension that installs and updates plugins for you. If you do not have it yet, download it from **reapack.com**, copy the file into REAPER's **UserPlugins** folder (menu **Options > Show REAPER resource path in explorer/finder**), and restart REAPER.

1. In REAPER, open **Extensions > ReaPack > Import repositories...**
2. Paste this address and click OK:
   **https://raw.githubusercontent.com/renothestraws/reno-mellow/main/index.xml**
3. Open **Extensions > ReaPack > Browse packages**, type **RMdrumachine** in the search field.
4. Right-click the line, choose **Install**, then click **Apply**.
5. Done. The plugin, its 4 factory kits and the note-name file are installed. Later, **Extensions > ReaPack > Synchronize packages** gets updates.

## Option B - manual installation

1. Download the repository from GitHub (green **Code** button > **Download ZIP**) and unzip it.
2. Open REAPER's resource folder: **Options > Show REAPER resource path in explorer/finder**.
3. Copy **RMdrumachine.jsfx** (folder *Instruments*) into the **Effects** folder.
4. Copy the **RMdrumachine** folder (it contains the kit folders Doves, IWDwS, Vogue and Monday) into the **Data** folder, so you get *Data/RMdrumachine/Doves/01_kick.ogg*, etc.
5. Restart REAPER (or click **FX browser > Scan for new plugins**).

> **Good to know**
>
> If the default sounds are missing (for example if you only copied the .jsfx file), the pads still work: they use built-in synthesized 808/909-style sounds instead.

## First launch

1. Create a new track: **Track > Insert new track** (or Ctrl+T / Cmd+T).
2. Click the green **FX** button of the track. In the FX browser, type **RMdrumachine** and double-click it.
3. The plugin window opens. Click the **KICK** pad: you should hear a kick drum.
4. Press the space bar to start playback: a demo beat plays (kick, snare and hi-hat).
5. Press the space bar again to stop.

> **No sound?**
>
> Check that the track is not muted, that its volume fader is up, and that your audio device is working (REAPER menu **Options > Preferences > Audio > Device**). The sequencer only plays while REAPER is playing.

# 3. A tour of the interface

The window has six areas. Use the **SIZE** buttons at the bottom right (75 / 100 / 125 / 150 %) to make it bigger or smaller.





*The full interface at 125 %.*

| Area | Where | What it does |
|---|---|---|
| Kit | Top | Name of the current kit, LOAD KIT and SAVE KIT buttons. |
| Pads | Left, 4 x 4 grid | Select and play the 16 sounds, load your own samples. |
| Pad editor | Top right | Settings of the selected pad: MIDI note, volume, pan, tune, decay, output, mute, solo, swing. |
| Global settings | Middle right | Tempo mode, grid, swing amount, sequencer and MIDI out switches, CV trigger, master volume, layers, play style. |
| Step sequencer | Bottom | Pattern buttons A-H and the 16 steps of the selected pad. |
| Footer | Very bottom | Hints and window size. |

## Mouse basics

| Action | Result |
|---|---|
| Click and drag up / down on a knob | Turns the knob. |
| Shift + drag | Fine adjustment (slower). |
| Ctrl + click on a knob | Back to the default value. |
| Click a pad | Selects it and plays it. |
| Right-click a pad | Reloads the sound of the current kit. |
| Drag up / down on the MIDI NOTE box | Changes the note of the pad (1 to 100). |
| Shift + click a pattern button | Copies the current pattern there. |
| Shift + right-drag up/down on a step | Splits the step into 1 to 8 sub-steps. |

# 4. The pads




*The 16 pads. Top-left number = pad number, top-right number = MIDI note.*

Each pad shows its number, its MIDI note, its name and the name of the loaded sample (the kit name, for example "Doves", when it is a factory sound). A pad **lights up** when it plays. The selected pad has an **orange frame**. A small **orange dot** means that this pad has steps programmed in the sequencer. Small red / yellow marks show **mute** and **solo**.

| Pad | Name | Note | Pad | Name | Note |
|---|---|---|---|---|---|
| 1 | Kick | 36 | 9 | Ride | 51 |
| 2 | Snare | 38 | 10 | Crash | 49 |
| 3 | Low Tom | 45 | 11 | HH Closed | 42 |
| 4 | Mid Tom | 47 | 12 | HH Open | 46 |
| 5 | Hi Tom | 50 | 13 | Maracas | 70 |
| 6 | Clap | 39 | 14 | Misc (kick layer) | 35 |
| 7 | Perc | 56 | 15 | Misc (snare/clap layer) | 40 |
| 8 | Rim | 37 | 16 | Misc (hi-hat group) | 44 |

These are the default notes. They follow the **General MIDI** drum standard, so most MIDI drum patterns you find will play the right sounds.

## Changing the MIDI note of a pad

Select the pad, then drag the **MIDI NOTE** box of the pad editor up or down (Ctrl + click = back to the default note). Any note from 1 to 100 can be used; several pads can share the same note, they then play together. Notes 101 to 108 are reserved: they switch patterns (chapter 8).

## Loading your own sounds

### From your computer's file browser

1. Open Windows Explorer or the macOS Finder next to REAPER.
2. Find a WAV or OGG file (for example *my_snare.wav*).
3. Drag it with the mouse and drop it **on the pad** you want to replace.
4. The pad name stays the same, but the sample name below it changes (shown in orange).

You can drop **several files at once**: the first goes on the pad under the mouse, the next ones on the following pads.

### From REAPER's Media Explorer

REAPER has its own sound browser, the **Media Explorer**. It lets you **listen** to sounds before you choose them.

1. Open it with **View > Media Explorer** (shortcut Ctrl+Alt+X on Windows, Cmd+Option+X on macOS).
2. Browse to your sample folder on the left. Click a file to hear it.
3. When you like a sound, drag it from the Media Explorer list and drop it on a pad of the RMdrumachine window.
4. Tip: dock the Media Explorer under the plugin window so both are visible at the same time.

> **If dropping from the Media Explorer does nothing**
>
> Some REAPER versions or operating systems do not pass Media Explorer drags to plugin windows. In that case, right-click the file in the Media Explorer, choose **Show in explorer/finder**, and drag it from there.

### Going back to the kit sound

Right-click the pad. The sound of the current factory kit is reloaded. The paths of your samples are saved inside your REAPER project, so they come back when you reopen it - as long as you do not move or rename the files.

# 5. Kits




*The kit name, LOAD KIT and SAVE KIT, at the top of the window.*

A **kit** is a complete set of sounds. RMdrumachine comes with four factory kits; **Doves** is loaded when you insert the plugin.

The four factory kits are **Doves**, **IWDwS**, **Vogue** and **Monday**. Each one fills all 16 pads.

## Loading a kit

1. Click **LOAD KIT**. A menu opens.
2. Choose a factory kit (Doves, IWDwS, Vogue, Monday) or one of your 8 user kits (greyed out while empty).
3. The 16 pads load their new sounds. Your patterns are not changed: you can try the same beat with different kits.

Loading a **factory kit** only changes the sounds. Loading a **user kit** also restores the pad settings it was saved with (volume, pan, tune, decay, output, swing and MIDI note).

## Saving your own kit

1. Load your own samples on the pads (chapter 4) and set the pads as you like.
2. Click **SAVE KIT** and choose one of the 8 slots, **User 1** to **User 8**.
3. The kit name at the top now shows **USER n**. Reload it at any time with LOAD KIT.

> **Where are user kits stored?**
>
> A JSFX plugin cannot write files on your disk, so user kits are stored inside the plugin: they are saved with your project. To use them in every new project, save a REAPER preset of the plugin (**+** button > **Save preset**), or make it the default with **Presets > Save as default**. Samples are stored as file paths: keep your sample files in a fixed folder, for example *Data/RMdrumachine/MyKits/*.

# 6. Pad settings




*The pad editor always shows the selected pad.*

| Control | What it does | Tip |
|---|---|---|
| VOLUME | Level of the pad, from -inf (off) to +6 dB. | Balance your kit here first. |
| PAN | Left / right position in the stereo image. | Spread toms from left to right like a real kit. |
| TUNE | Pitch, from -12 to +12 semitones. | Lower a kick or a tom to make it deeper. |
| DECAY | Length of the sound. FULL = the whole sample. | Shorten a long open hi-hat or a boomy kick. |
| MIDI NOTE | The note that plays the pad (1 to 100). | Drag up / down; Ctrl + click = default. |
| OUTPUT | Sends the pad to outputs 1-2, 3-4, 5-6 or 7-8. | See chapter 11 to mix pads on separate tracks. |
| MUTE | Silences the pad. | |
| SOLO | Plays only the soloed pads. | Useful to work on one sound. |
| SWING | Lets this pad follow the swing setting. | On by default for pads 9, 10, 11, 12, 13 and 16. |

## Automatic behaviours (no setting needed)

- **Hi-hat choke**: pads 11, 12 and 16 cut each other, like a real hi-hat (a closed hi-hat stops a ringing open one).
- **Anti "machine gun"**: on the hi-hats, every hit is slightly different (level, length, pitch, start), like on the classic Linn machines, so fast hi-hat lines sound human.
- **Accents** are punchier (+3 dB on the attack) and very slightly lower in pitch. **Ghost notes** are softer on the attack (-4.5 dB) and very slightly higher.
- **Layers**: pad 14 can play together with the kick, pad 15 with the snare or the clap (see chapter 7).

# 7. Global settings




*Global settings apply to the whole machine.*

| Control | What it does |
|---|---|
| TEMPO: HALF / NORMAL / DOUBLE | Plays the pattern at half speed, normal speed or double speed compared with the project tempo. |
| GRID: 1/16, 1/32, 1/16T | Length of one step: sixteenth notes (normal), thirty-second notes (twice as fast) or sixteenth-note triplets. |
| SEQ ON | Turns the step sequencer on or off. Off = the pads only play from MIDI or CV. |
| MIDI OUT | Sends the sequencer notes as MIDI (chapter 12). |
| SWING | Delays (positive values) or pushes forward (negative values) every second step. Only pads with SWING on are affected. |
| CV THR / CV IN | Audio trigger threshold and on/off switch (chapter 10). |
| MASTER | Overall output level. |
| LAYERS | **14 + KICK**: pad 14 plays every time the kick plays. **15 +**: pad 15 plays with the snare (SNR) or the clap (CLP). |
| PLAY STYLE | **PUSH**, **NORMAL** or **LAID** (laid back): moves the snare, the clap and pad 15 (when it is layered) slightly ahead of or behind the grid (chapter 8). |

**Layers in practice**

Put a long sub-bass "808 boom" on pad 14 and switch on **14 + KICK**: every kick now has a deep tail. Put a clap or a second snare on pad 15 and choose **SNR** for a fatter snare.

# 8. The step sequencer, step by step

## What is a step sequencer?

A step sequencer divides one bar of music into equal boxes called **steps**. You switch a step on, and the sound plays at that moment, again and again, every bar. With the default **1/16 grid**, one bar of 4/4 has **16 steps**: steps 1, 5, 9 and 13 fall exactly on the four beats you would count "1, 2, 3, 4".

Each pad has its **own row of 16 steps**. Only the row of the **selected pad** is shown: click a pad to see and edit its steps. All the rows together form one **pattern**.




*The sequencer of the selected pad. Light grey bands group the steps by beat (4 steps = 1 beat).*

## The three buttons of a step

| Part of the step | Click it to... | Plays at |
|---|---|---|
| Big middle button | Switch the step on (orange) or off. | velocity 100 (normal) |
| Small top button | Make the step an ACCENT (red). | velocity 127, punchier |
| Small bottom button | Make the step a GHOST note (blue). | velocity 30, soft |

A white frame moves along the steps while REAPER plays: it shows where you are in the bar.

## Your first beat

1. Click the **KICK** pad. Click **CLEAR** to start from an empty row. Switch on steps **1, 5, 9 and 13**.
2. Click the **SNARE** pad, click CLEAR, switch on steps **5 and 13**.
3. Click the **HH CLOSED** pad, click CLEAR, switch on every odd step: **1, 3, 5, 7, 9, 11, 13, 15**.
4. Press the space bar. You have a classic "four on the floor" beat.




*Beat 1 - the steps to switch on.*

## Adding feel: accents and ghost notes

Real drummers do not hit every note with the same strength. Try this variation: make the snare on steps 5 and 13 an **accent**, add **ghost** snare notes on steps 8 and 10, and play the hi-hat on every step with a ghost on each even step.




*Beat 2 - accents (A) and ghost notes (g) give the groove its life.*

## Swing

Swing makes straight rhythms "bounce". Turn the **SWING** knob to +15 or +25 % and listen to the hi-hats: every second step is played a little later. Swing only affects the pads whose **SWING** button is on. Negative values push those steps earlier, for a nervous, rushing feel.

## Splitting a step (rolls and flams)

You can cut one step into 2 to 8 smaller sub-steps - perfect for hi-hat rolls, snare rolls before a chorus, or trap-style hi-hats.

1. Hold **Shift** and press the **right mouse button** on a step.
2. Keep the button pressed and move the mouse **up**: every 10 pixels adds one division (up to 8). Move down to remove divisions.
3. Release. The step is now drawn as several thin columns. Only the first one is on.
4. Click each thin column to switch it on or off. The small top and bottom buttons work per sub-step too (accent / ghost).


The step number shows the division, for example **"4 /3"** = step 4 split in 3. Going back down to 1 turns it into a normal step again.

## Play style: push and laid back

Drummers rarely play the snare exactly on the grid. **PUSH** plays the snare, the clap and pad 15 (when layered with them) a little **early**, which sounds urgent and driving. **LAID** (laid back) plays them a little **late**, for a relaxed, heavy groove. **NORMAL** keeps them exactly on the grid.

The shift changes slightly on every hit, between 0 and 20 % of a sixteenth note, so it never sounds mechanical. Split steps are never moved, so your rolls stay tight.

## Patterns A to H




*The pattern buttons, next to the step sequencer title.*

RMdrumachine stores **8 patterns**. Each pattern contains the steps of all 16 pads. Use them for the parts of a song: A = verse, B = chorus, C = fill, and so on.

1. Click a letter (**A** to **H**) to play and edit that pattern.
2. Hold **Shift** and click a letter to **copy** the current pattern there and switch to it - the quickest way to make a variation.
3. To change patterns automatically during a song, put MIDI notes **101** (A) to **108** (H) in a MIDI item on the RMdrumachine track: when the note plays, the pattern changes.

> **Tip**
>
> Place the pattern-change notes exactly on the first beat of a bar, for example a short note 101 at bar 1, 102 at bar 9 and 101 again at bar 17.

## Grid and tempo modes

Use **1/32** for very fast patterns (the 16 steps then last half a bar), and **1/16T** for triplet feels (shuffle, 6/8 grooves). **HALF** and **DOUBLE** play the whole pattern at half or double speed without touching the project tempo - handy for half-time breakdowns.

> **Important**
>
> The sequencer follows REAPER's timeline: it only plays while REAPER is playing (or recording), and it always stays locked to the bars of your project. Step 1 always falls on the first beat of a bar.

# 9. Playing the pads with MIDI

You can play RMdrumachine like any virtual instrument: from a MIDI keyboard, from MIDI drum pads, or from a MIDI item drawn in REAPER's piano roll.

## With a MIDI keyboard or pad controller

1. Make sure your controller is enabled in **Options > Preferences > Audio > MIDI Inputs**.
2. On the RMdrumachine track, click the **record arm** button (red circle).
3. Click the small input selector of the track and choose **Input: MIDI > (your device) > All channels**.
4. Turn on **monitoring** (the speaker icon next to record arm). Now play: the pads respond to notes 35 to 70 (see the table in chapter 4).

## How velocity is used

| Velocity received | Result |
|---|---|
| 120 to 127 | Accent: fixed accent level, punchy attack, slightly lower pitch. |
| 31 to 119 | Normal hit; the harder you play, the louder it is. |
| 1 to 30 | Ghost note: fixed ghost level, softer attack, slightly higher pitch. |

Notes 101 to 108 do not play a pad: they switch patterns A to H. The incoming MIDI is also passed to the plugin's MIDI output, so you can still use it further down the chain.

## Seeing the pad names in REAPER's MIDI editor

The piano roll can show "Kick", "Snare", "HH Closed"... instead of note numbers:


1. Open a MIDI item of the RMdrumachine track in the MIDI editor (double-click it).
2. In the MIDI editor menu, choose **File > Note names > Load note names from file...**
3. Open *Data/RMdrumachine/RMdrumachine_note_names.txt* (inside REAPER's resource folder).
4. Optional: in the MIDI editor, use **View > Mode: named notes** to show only the drum notes.

The file uses the default notes. If you change the note of a pad, edit the file with a text editor: each line is "note number, space, name".

# 10. CV / audio trigger: drive the pads from other tracks

This feature lets **recorded drums** trigger the pads. Example: you recorded a real kick drum, and you want an electronic kick to play exactly with it. RMdrumachine listens to its **audio inputs 1 to 6**; when a hit is detected on input 1, pad 1 plays; on input 2, pad 2 plays, and so on up to pad 6 (Kick, Snare, Low Tom, Mid Tom, Hi Tom, Clap).

The loudness of the hit becomes the velocity: a hit at 0 dBFS gives velocity 127, a hit at -36 dB gives velocity 30, everything in between is proportional. So a very hard hit can become an accent, and a very soft hit a ghost note.




*Each drum track sends its audio to one input channel of the RMdrumachine track.*

## Step 1 - give the RMdrumachine track enough channels

1. Click the **ROUTE** button (or the I/O button) of the RMdrumachine track.
2. At the top, set **Track channels** to **8**.

## Step 2 - send each drum track to the right channel

Do this for the kick track (example):

1. Click the **ROUTE** button of the **kick microphone** track.
2. Under **Sends**, choose **Add new send...** and select the RMdrumachine track.
3. In the new send, set the **Audio** field to send **mono source channel 1** to **destination channel 1** (for the snare: destination 2, low tom: 3, mid tom: 4, hi tom: 5, clap: 6).
4. Leave **MIDI** at "None" for this send.

> **Why mono?**
>
> If you send a stereo pair "1/2 -> 1/2", the kick would arrive on input 1 AND input 2, and also trigger the snare. Always send a mono channel to exactly one destination channel.


## Step 3 - switch on and adjust

1. In RMdrumachine, switch on **CV IN** (it is off by default, so that audio on the track never triggers pads by accident).
2. Play the project. Each hit now triggers its pad.
3. If quiet sounds (bleed from other drums) trigger the pad, turn **CV THR** to the right (higher threshold). If soft hits are missed, turn it to the left.
4. To hear only the electronic sound, do not lower the send (it must stay loud enough to be detected): lower the fader of the original drum track instead.

> **The original audio is not passed through**
>
> RMdrumachine only outputs its own sounds. The audio you send to it is used for detection only, then discarded.

# 11. The 8 outputs: mixing pads on separate tracks

By default every pad goes to outputs 1-2, so the whole kit comes out of the RMdrumachine track. If you want to process the kick, the snare and the cymbals separately (EQ, compression, reverb...), send them to other outputs and pick them up on their own tracks.





*Example: kick on outputs 3-4, snare on 5-6, cymbals on 7-8.*

1. Set the RMdrumachine track to **8 channels** (ROUTE button > Track channels: 8).
2. In the pad editor, choose the **OUTPUT** of each pad: kick = 3-4, snare = 5-6, ride + crash + hi-hats = 7-8.
3. Create a new track named "Kick". Click its **ROUTE** button > **Add new receive...** > choose the RMdrumachine track.
4. In the receive, set Audio to **3/4 -> 1/2**. Do the same for the "Snare" track (5/6 -> 1/2) and the "Cymbals" track (7/8 -> 1/2).
5. On the RMdrumachine track, open ROUTE and set the **parent / master send** to channels **1-2 only**, so outputs 3-8 are not heard twice.

> **Tip**
>
> Use REAPER's track templates to save this setup once and reuse it in every project: select the tracks, then **Track > Save tracks as track template**.

# 12. MIDI output: other instruments and editable MIDI

When **MIDI OUT** is on (default), every step played by the sequencer is also sent as a MIDI note on channel 1: accents with velocity 127, normal steps 100, ghost notes 30, using the pad notes (kick = 36, snare = 38...). Audio-triggered hits are sent too.




## Play another drum instrument with the sequencer

1. On the same track, add your other drum instrument **after** RMdrumachine in the FX chain.
2. It receives the notes and plays along. Mute the RMdrumachine pads (MUTE or MASTER at -inf) if you only want to hear the other instrument.

## Send the MIDI to another track

1. On the RMdrumachine track, click **ROUTE** > **Add new send...** > choose the destination track.
2. In the send, set Audio to **None** and MIDI to **All -> All**.
3. Put an instrument on the destination track: it now plays the RMdrumachine pattern.

## Turn the pattern into a MIDI item

This lets you edit your beat in REAPER's piano roll, or move it to another project.

1. On the RMdrumachine track, create an empty MIDI item as long as the part you want: **Insert > New MIDI item**, then drag its right edge.
2. Select the item.
3. Run the action **Item: Apply track/take FX to items as new take (MIDI output)** (press **?** to open the Actions list and type "MIDI output" to find it).
4. A new take appears in the item with all the notes of the sequencer. Switch off **SEQ ON** afterwards, or the sequencer and the MIDI item will play twice.

# 13. Troubleshooting

| Problem | Solution |
|---|---|
| I hear nothing when I press play. | Check SEQ ON, the track mute and fader, the pad MUTE / SOLO buttons, and the MASTER knob. The sequencer only plays while REAPER is playing. |
| A pad shows "load failed". | The file was moved, renamed, or is not a WAV/OGG file. Drop it again on the pad. |
| The default sounds are synthetic, not the samples. | The kit folders are not in REAPER's Data/RMdrumachine folder. Reinstall with ReaPack or copy the folder manually (chapter 2), then reload the kit with LOAD KIT. |
| Pads play on their own. | CV IN is on and audio reaches inputs 1-6. Switch CV IN off, or check your sends (chapter 10). |
| Outputs 3-8 are silent. | The track has only 2 channels. Set Track channels to 8 in the ROUTE window. |
| The sound distorts. | The outputs have a hidden safety clipper at 0 dBFS. Lower the MASTER or the pad volumes. |
| I hear the beat twice. | A MIDI item and the sequencer are playing the same pattern. Switch SEQ ON off, or remove the MIDI item. |
| The pattern changes on its own. | A MIDI item contains notes 101 to 108, which switch patterns. Remove them or move them. |
| LOAD KIT shows a user kit greyed out. | That slot is empty: save a kit there first with SAVE KIT. |

## Technical facts

- Zero latency. 8 audio outputs, 6 audio inputs (trigger), MIDI in and out.
- Samples: WAV or OGG, mono or stereo, up to about 20 seconds (stereo, 48 kHz) per pad.
- Pad volume, pan, tune and decay can be automated in REAPER; the other settings, the 8 patterns and the 8 user kits are saved with the project.
- Free for any use, including commercial. Part of the ReNo Mellow collection.