


RIP v2 Comandes

Previo

!! Importante > Todo lo que este entre routers es un red

!! Importante > En el PC y Server, puedo usar cualquiera de los gateways de los dos routers



Router 0

(Enllaç Switch 1)

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 172.16.16.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up

Router(config-if)#exit
Router(config)#
```

Copy

Paste

(Enllaç Router 1)

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip address 172.16.17.1 255.255.255.0
Router(config-if)#no shutdown


%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#exit
Router(config)#
```

(RIP v2 Router 0)

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#no auto-summary
Router(config-router)#network 172.16.16.0
Router(config-router)#network 172.16.17.0
Router(config-router)#passive-interface fa0/0
Router(config-router)#exit
Router(config)#
```

Copy


IP PC 0:



The screenshot shows a window titled "PC0" with tabs for Physical, Config, Desktop, Programming, and Attributes. The "Config" tab is active, and the "IP Configuration" section is expanded. The interface is set to "FastEthernet0". The configuration is set to "Static" (selected with a radio button). The IPv4 Address is 172.16.16.10, the Subnet Mask is 255.255.255.0, the Default Gateway is 172.16.16.1, and the DNS Server is 0.0.0.0.

IP Configuration	
Interface: FastEthernet0	
IP Configuration	
☐ DHCP ☒ Static	
IPv4 Address	172.16.16.10
Subnet Mask	255.255.255.0
Default Gateway	172.16.16.1
DNS Server	0.0.0.0

IP PC1:



Router 1

(Enllaç amb Switch 0)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 172.16.19.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
```

(Enllaç Router 0)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip address 172.16.17.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Router(config-if)#exit
Router(config)#
```


(Enllaç amb Server 0)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa1/0
Router(config-if)#ip address 172.16.18.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
```

Copy

Paste

IP Server 0:



The screenshot shows a window titled 'Server0' with tabs for Physical, Config, Services, Desktop, Programming, and Attributes. The 'Desktop' tab is active, and the 'IP Configuration' window is open. It shows the 'Static' radio button selected for IP Configuration. The fields are filled with: IPv4 Address: 172.16.18.2, Subnet Mask: 255.255.255.0, Default Gateway: 172.16.18.1, and DNS Server: 0.0.0.0.

(RIP v2 Router 1)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#no auto-summary
Router(config-router)#network 172.16.18.0
Router(config-router)#network 172.16.19.0
Router(config-router)#network 172.16.17.0
Router(config-router)#passive-interface fa0/0
Router(config-router)#exit
Router(config)#
```

Copy

Paste

(RIP v2 > Borrar interfície passiva antiga i configurar la nova)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router rip
Router(config-router)#no passive-interface fa0/0
Router(config-router)#passive-interface fa1/0
Router(config-router)#exit
Router(config)#
```

Copy


Paste

Ricard Sala Nikitin

Xarxa Interna (Entre R1 i R2)

! Important > Als dispositius els hi puc posar qualsevol dels gateways, ja siguin del router 1 o del router 2, ja que formen part de la mateixa xarxa !


IP PC4:



The screenshot shows the 'PC4' configuration window with the 'Desktop' tab selected. The 'IP Configuration' section is active, showing the 'FastEthernet0' interface. The configuration is set to 'Static' with the following values:

Field	Value
IPv4 Address	172.16.19.10
Subnet Mask	255.255.255.0
Default Gateway	172.16.19.1
DNS Server	0.0.0.0

IP Server 2:



The screenshot shows the 'Server2' configuration window with the 'Desktop' tab selected. The 'IP Configuration' section is active, showing the configuration for the interface. The configuration is set to 'Static' with the following values:

Field	Value
IPv4 Address	172.16.19.15
Subnet Mask	255.255.255.0
Default Gateway	172.16.19.1
DNS Server	0.0.0.0

Router 2

(Enllaç amb switch 0)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 172.16.19.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
```

Copy


Paste

(Enllaç amb Server 2)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa1/0
Router(config-if)#ip address 172.16.20.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
```

Copy

(IP Server 1)



Server1

Physical Config Services Desktop Programming Attributes

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.20.2

Subnet Mask 255.255.255.0

Default Gateway 172.16.20.1

DNS Server 0.0.0.0

(RIP v2 Router 2)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#no auto-summary
Router(config-router)#network 172.16.19.0
Router(config-router)#network 172.16.20.0
Router(config-router)#network 172.16.21.0
Router(config-router)#passive-interface fa0/0
Router(config-router)#exit
Router(config)#
```

Copy

Paste

(RIP v2 > Eliminar interfície antiga i configurar nova)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router rip
Router(config-router)#no passive-interface fa0/0
Router(config-router)#passive-interface fa1/0
Router(config-router)#exit
Router(config)#
```

Copy

(Enllaç Router 3)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip address 172.16.21.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#
```

Router 3:

(Enllaç amb router 2)

```
Router>ena
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip address 172.16.21.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
Router(config-if)#
```

(Enllaç amb router Switch 2)

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 172.16.22.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up


Router(config-if)#
```

(RIP v2 Router 3)

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#no auto-summary
Router(config-router)#network 172.16.21.0
Router(config-router)#network 172.16.22.0
Router(config-router)#passive-interface fa0/0
Router(config-router)#exit
Router(config)#
```

Copy

IP PC2:



The screenshot shows a window titled "PC2" with tabs for Physical, Config, Desktop, Programming, and Attributes. The "Config" tab is active, and the "IP Configuration" section is expanded. The interface "FastEthernet0" is selected. The configuration is set to "Static" with the following values:

Field	Value
IPv4 Address	172.16.22.10
Subnet Mask	255.255.255.0
Default Gateway	172.16.22.1
DNS Server	0.0.0.0

IP PC3:

PC3

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address	172.16.22.11
Subnet Mask	255.255.255.0
Default Gateway	172.16.22.1
DNS Server	0.0.0.0