# Two-Computer Installation Guide

Live Auction Host + Cashier Workstation

**Use this sequence exactly: install both PCs, collect both Machine IDs, activate both PCs, configure the host, then pair the cashier.**

| | |
|---|---|
| Installer | HammerTrackPro-0.7.34-x64-signed.msi |
| Supported setup | Two Windows x64 computers on the same private local network |
| Computer 1 | Live Auction Host - owns the auction database |
| Computer 2 | Cashier Workstation - connects securely to the host |

## Important

Never place or share the HammerTrack database on a network drive. The host keeps the database locally; the cashier communicates with the host through HammerTrack's paired HTTPS connection.

Print this guide in color or grayscale at 100% scale on US Letter paper.

# 1. Before you begin

Gather everything before auction day. Perform the installation while both computers can remain on the same private network.

## You will need

[ ] The HammerTrack Pro 0.7.34 signed MSI installer on a USB drive or other trusted transfer method.

[ ] Administrator permission on both Windows computers.

[ ] One host computer for live-auction operation and one cashier computer.

[ ] Both computers connected to the same trusted private router or LAN.

[ ] A signed .htplicense file that includes the Machine ID of both computers.

## Choose and label the computers

| | |
|---|---|
| LIVE AUCTION HOST | Runs the auction, stores the local database, and must stay powered on while the cashier is working. |
| CASHIER | Looks up current-auction buyers and sellers and records payments through the secure connection to the host. |

**Do not use public Wi-Fi. If possible, connect both PCs by Ethernet to the same router for the most reliable auction-day connection.**

## Record for this installation

| | |
|---|---|
| Auction company | _____ |
| Host PC name | _____ |
| Cashier PC name | _____ |
| Installation date | _____ |

# 2. Install and activate both computers

**1. Install on the host**
Copy HammerTrackPro-0.7.34-x64-signed.msi to the live-auction computer. Double-click it, approve the Windows administrator prompt, and complete the installer.

**2. Install on the cashier**
Repeat the same signed MSI installation on the cashier computer.

**3. Launch HammerTrack Pro**
Use the Desktop or Start Menu shortcut. The installer is locally self-signed. If Windows displays an unknown-publisher warning on a computer that does not trust the local certificate, confirm the MSI came from your trusted HammerTrack provider before continuing.

**4. Collect both Machine IDs**
At the activation screen, select Copy Machine ID on each computer. Label each ID as Host or Cashier and send both IDs to the license issuer.

**5. Receive one license file**
The issuer creates one signed .htplicense file containing both Machine IDs. Keep the file private and unchanged.

**6. Activate both computers**
On each activation screen, import the same .htplicense file. HammerTrack confirms the licensed customer name.

**A license for only one Machine ID will not activate the other PC. If either computer is replaced, request a replacement license containing the complete approved Machine ID list.**

## Activation record

| | |
|---|---|
| Host Machine ID | _____ |
| Cashier Machine ID | _____ |
| License file received | _____ Date: _____ |

# 3. Configure the Live Auction Host

**1. Select the host role**
On first setup, choose Live Auction Host (stores the database), then save the selection. Restart HammerTrack if prompted or if you later change the role.

**2. Allow private-network access**
If Windows Firewall asks, allow HammerTrack on Private networks. Do not enable it for public networks.

**3. Open Network Information**
In HammerTrack, open Network Information. Leave this screen available while setting up the cashier.

**4. Copy the pairing values**
Record the Host address, Alternate IP address, Pairing key, and Certificate fingerprint exactly as displayed. Keep the pairing key private.

**5. Keep the host running**
HammerTrack must remain open on this computer whenever the cashier workstation is being used.

## Host pairing record

| | |
|---|---|
| Host address | _____ |
| Alternate IP address | _____ |
| Pairing key | _____<br>_____ |
| Certificate fingerprint | _____<br>_____ |

**The live-auction host is the only computer that opens the SQLite database. Never copy the live database to a shared, UNC, mapped-network, or cloud-synced folder.**

# 4. Pair the Cashier Workstation

**1. Confirm the host is ready**
The host PC must be running HammerTrack and both computers must be on the same private network.

**2. Select the cashier role**
On the cashier setup screen, choose Cashier Workstation (connects to host).

**3. Enter the secure connection values**
Copy the Host address, Pairing key, and Certificate fingerprint from Network Information on the host. Include the full HTTPS address.

**4. Save and restart**
Save the workstation setup. Restart HammerTrack after changing the workstation role or connection settings.

**5. Verify connection status**
Open the cashier screen and confirm it connects to the host. The cashier retries health checks after a temporary disconnect.

**If the computer-name Host address does not connect, edit cashier setup and use the Alternate IP address shown on the host. Keep the same pairing key and certificate fingerprint.**

## Run a pre-auction cashier test

[ ] On the host, select the correct Current Auction.

[ ] On the cashier, confirm the connected state and current-auction context.

[ ] Look up a test Buyer registered for that auction and confirm the expected purchases and totals.

[ ] Open Add Buyer and Add Seller; confirm existing Buyer Numbers appear for Seller linking.

[ ] Verify an existing Buyer can be registered as a Seller using the same number without creating a duplicate Buyer.

[ ] Use Full Screen or F11 and confirm Escape exits full screen.

[ ] If using license scanning, test a license with the barcode level, close, sharp, and filling most of the dashed guide.

[ ] For a handheld scanner, enable PDF417 and USB HID/keyboard mode. In Use Handheld Scanner, verify the received-character count increases and the bidder fields fill after the scan.

[ ] Do not record a real payment during the connection test unless it is intended and auditable.

## Security note

The cashier pins the host certificate fingerprint and uses the pairing key. Do not bypass certificate or pairing errors; compare the values against the host's Network Information screen.

# 5. Troubleshooting and auction-day checklist

## If the cashier will not connect

| | |
|---|---|
| Disconnected | Confirm HammerTrack is open on the host and both PCs are connected to the same private router/LAN. |
| Host name fails | Use the Alternate IP address from the host's Network Information screen. |
| Not paired | Re-enter the pairing key exactly. Do not add spaces before or after it. |
| Fingerprint error | Re-enter the certificate fingerprint exactly as displayed on the host. Do not ignore a mismatch. |
| Still offline | Confirm Windows classified the network as Private and HammerTrack is allowed through the host firewall on Private networks. |

## If activation fails

| | |
|---|---|
| PC not included | Send the displayed Machine ID to the license issuer and request a replacement license that retains all approved PCs. |
| Invalid file | Import the original .htplicense file without renaming its extension or editing its contents. |
| Expired license | Contact the license issuer for a renewed signed license. |

## Before bidders arrive

[ ] Host PC is connected to power and sleep is disabled for the event.

[ ] Cashier PC is connected and shows a healthy connection.

[ ] Correct Current Auction is selected on the host.

[ ] A recent in-app backup exists in the local Backups folder.

[ ] Network Information is available to the operator but the pairing key is not publicly visible.

[ ] Buyer lookup and same-number Seller linking succeed from the cashier.

**Data location: %ProgramData%\HammerTrackPro. Application upgrades and uninstall preserve the database, backups, logs, settings, and license, but maintain current backups before any upgrade or service work.**

Installation completed by: _____ Date: _____